

Packet Tracer - WLAN Configuration

Addressing Table

Device	Interface	IP Address
Home Wireless Router	Internet	DHCP
	LAN	192.168.6.1/27
RTR-1	G0/0/0.2	192.168.2.1/24
	G0/0/0.5	192.168.5.1/24
	G0/0/0.100	192.168.100.1/24
	G0/0/1	10.6.0.1/24
SW1	VLAN 200	192.168.100.100/24
LAP-1	G0	DHCP
WLC-1	Management	192.168.100.254/24
RADIUS Server	NIC	10.6.0.254/24
Home Admin	NIC	DHCP
Enterprise Admin	NIC	192.168.100.200/24
Web Server	NIC	203.0.113.78/24
DNS Server	NIC	10.100.100.252
Laptop	NIC	DHCP
Tablet PC	Wireless0	DHCP
Smartphone	Wireless0	DHCP
Wireless Host 1	Wireless0	DHCP
Wireless Host 2	Wireless0	DHCP

WLAN Information

WLAN	SSID	Authentication	Username	Password
Home Network	HomeSSID	WPA2-Personal	N/A	Cisco123
WLAN VLAN 2	SSID-2	WPA-2 Personal	N/A	Cisco123
WLAN VLAN 5	SSID-5	WPA-2 Enterprise	userWLAN5	userW5pass

Note: It is not a good practice to reuse passwords as is done in this activity. Passwords have been reused to make it easier to work through the tasks.

Objectives

In this activity, you will configure both a wireless home router and a WLC-based network. You will implement both WPA2-PSK and WPA2-Enterprise security.

- = Configure a home router to provide Wi-Fi connectivity to a variety of devices.
- = Configure WPA2-PSK security on a home router.
- = Configure interfaces on a WLC.
- = Configure WLANs on a WLC.
- = Configure WPA2-PSK security on a WLAN and connect hosts to WLAN.
- = Configure WPA2-Enterprise on a WLAN and connect hosts to the WLAN.
- = Verify connectivity WLAN connectivity.

Background / Scenario

You will apply your WLAN skills and knowledge by configuring a home wireless router and an enterprise WLC. You will implement both WPA2-PSK and WPA2-Enterprise security. Finally, you will connect hosts to each WLAN and verify connectivity.

Instructions

Part 1: Configure a Home Wireless Router.

You are installing a new home wireless router at a friend's house. You will need to change settings on the router to enhance security and meet your friend's requirements.

Step 1: Change DHCP settings.

a. Open the Home Wireless Router GUI and change the router IP and DHCP settings according to the information in the Addressing Table.

b. Permit a maximum of **20** addresses to be issued by the router.

c. Configure the DHCP server to start with IP address **.3** of the LAN network.

d. Configure the internet interface of the router to receive its IP address over DHCP.

Verify the address. What address did it receive?

เมื่อเราเตอร์ทำการร้องขอ IP แบบ DHCP ผ่านพอร์ต Internet สำเร็จ (อาจกด Save Settings อีกครั้งเพื่อให้อ่านค่า) ในช่อง Internet IP Address จะได้รับค่าเป็น **10.6.0.x** (โดยปกติในแล็บนี้จะได้เป็น **10.6.0.2** หรือขึ้นอยู่กับลำดับการแจกของ RTR-1)

e. Configure the static DNS server to the address in the Addressing Table.

The screenshot shows the 'Setup' page of a 'Wireless Tri-Band Home Router'. The top navigation bar includes 'Setup', 'Wireless', 'Security', 'Access Restrictions', 'Applications & Gaming', 'Administration', and 'Status'. The 'Setup' page is divided into 'Internet Setup' and 'Network Setup' sections.

Internet Setup:

- Internet Connection type: Automatic Configuration - DHCP
- Optional Settings (required by some internet service providers):
 - Host Name: []
 - Domain Name: []
 - MTU: [] Size: 1500

Network Setup:

- Router IP:
 - IP Address: 192 . 168 . 6 . 1
 - Subnet Mask: 255.255.255.224
- DHCP Server Settings:
 - DHCP Server: ☒ Enabled ☐ Disabled
 - Start IP Address: 192.168.6. 3
 - Maximum number of Users: 20
 - IP Address Range: 192.168.6. 3 - 22
 - Client Lease Time: 0 minutes (0 means one day)
 - Static DNS 1: 10 . 100 . 100 . 252
 - Static DNS 2: 0 . 0 . 0 . 0
 - Static DNS 3: 0 . 0 . 0 . 0
 - WINS: 0 . 0 . 0 . 0
- ISP Vlan:
 - ☐ Enabled ☒ Disabled
 - Vlan IDs: Internet: [] VoIP: [] IPTV: []
 - Port Vlan:
 - Port 1: Internet
 - Port 2: Internet
 - Port 3: Internet
 - Port 4: Internet
 - 2.4GHz: Internet
 - 5GHz - 1: Internet
 - 5GHz - 2: Internet

Wireless Tri-Band Home Router		HomeRouter-PT-AC
Status	Setup	Wireless
Router		Local Network
Router Information	Firmware Version: v0.9.7 Current Time: Not Available Internet MAC Address: 00E0.F797.9801 Host Name: Domain Name:	
Internet Connection	Connection Type: Automatic Configuration - DHCP Internet IP Address: 10.100.200.2 Subnet Mask: 255.255.255.0 Default Gateway: 10.100.200.1 DNS1: 10.100.100.252 DNS2: DNS3: MTU: 1500 DHCP Lease Time: 1 days 0:0:0 IP Address Release IP Address Renew	

Step 2: Configure the Wireless LAN.

- The network will use the 2.4GHz Wireless LAN interface. Configure the interface with the SSID shown in the Wireless LAN information table.
- Use **channel 6**.
- Be sure that all wireless hosts in the home will be able to see the SSID.

Wireless Tri-Band Home Router		HomeRouter-PT-AC
Wireless	Setup	Wireless
Basic Wireless Settings		Wireless Security
Basic Wireless Settings	Network Mode: Auto Network Name (SSID): HomeSSID SSID Broadcast: ☒ Enabled ☐ Disabled Standard Channel: 6 - 2.437GHz Channel Bandwidth: Auto	

Step 3: Configure security.

a. Configure wireless LAN security. Use WPA2 Personal and the passphrase shown in the Wireless LAN information table. b. Secure the router by changing the default password to the value shown in the Wireless LAN information table.

Physical Config **GUI** Attributes

Firmware Version: v0.9.7

Wireless Setup Wireless Security Access Restrictions Applications & Gaming Administration Status

Basic Wireless Settings Wireless Security Guest Network Wireless MAC Filter Advanced Wireless Settings

Wireless Security

2.4 GHz

Security Mode: WPA2 Personal

Encryption: AES


Passphrase: Cisco123

Key Renewal: 3600 seconds

Help...

Step 4: Connect clients to the network.

a. Open the PC Wireless app on the desktop of the laptop and configure the client to connect to the network. b. Open the Config tab on the Tablet PC and Smartphone and configure the wireless interfaces to connect to the wireless network. c. Verify connectivity. The hosts should be able to ping each other and the web server. They should also be able to reach the web server URL.



Part 2: Configure a WLC Controller Network

Configure the wireless LAN controller with two WLANs. One WLAN will use WPA2-PSK authentication. The other WLAN will use WPA2-Enterprise authentication. You will also configure the WLC to use an SNMP server and configure a DHCP scope that will be used by the wireless management network.

Step 1: Configure VLAN interfaces.

a. From the Enterprise Admin, navigate to the WLC-1 management interface via a web browser. To log into WLC-1, use **admin** as the username and **Cisco123** as the password.

b. Configure an interface for the first WLAN.

Name: **WLAN 2**

VLAN Identifier: **2**

Port Number: **1**

Interface IP Address: **192.168.2.254**

Netmask: **255.255.255.0**

Gateway: **RTR-1 G0/0/0.2 address**

Primary DHCP Server: **Gateway address**

c. Configure an interface for the second WLAN.

Name: **WLAN 5**

VLAN Identifier: **5**

Port Number: **1**

Interface IP Address: **192.168.5.254**

Netmask: **255.255.255.0**

Gateway: **RTR-1 interface G0/0/0.5 address**

Primary DHCP Server: **Gateway address**

Physical Information

Port Number	1
Backup Port	0
Active Port	1
Enable Dynamic AP Management	☐

Interface Address

VLAN Identifier	5
IP Address	192.168.5.254
Netmask	255.255.255.0
Gateway	192.168.5.1

DHCP Information

Primary DHCP Server	192.168.5.1
Secondary DHCP Server	
DHCP Proxy Mode	Global ▼
Enable DHCP Option 82	☐

Step 2: Configure a DHCP scope for the wireless management network.

Configure and enable an internal DHCP scope as follows:

Scope Name: **management**

Pool Start Address: **192.168.100.235**

Pool End Address: **192.168.100.245**

Network: **192.168.100.0**

Netmask: **255.255.255.0**

Default Routers: **192.168.100.1**

Step 3: Configure the WLC with external server addresses.

a. Configure the RADIUS server information as follows:

Sever Index: **1**

Sever Address: **10.6.0.254**

Shared Secret: **RadiusPW**

b. Configure the WLC to send logs information to an SNMP server.

Community Name: **WLAN**

IP Address: **10.6.0.254**

Step 4: Create the WLANs.

a. Create the first WLAN:

Profile Name: **Wireless VLAN 2**

WLAN SSID: **SSID-2**

ID: **2**

Interface: **WLAN 2**

Security: **WPA2-PSK**

Passphrase: **Cisco123**

Under the Advanced tab, go to the FlexConnect section. Enable **FlexConnect Local Switching** and **FlexConnect Local Auth**. b. Create the second WLAN:

Profile Name: **Wireless VLAN 5**

WLAN SSID: **SSID-5**

Interface: **WLAN 5**

ID: **5**

Security: **802.1x - WPA2-Enterprise**

Configure the WLAN to use the RADIUS server for authentication.

Make the **FlexConnect** settings as was done in Step 4a.


Step 5: Configure the hosts to connect to the WLANs.

Use the desktop PC Wireless app to configure the hosts as follows:

- Wireless Host 1 should connect to Wireless VLAN 2.
- Wireless Host 2 should connect to Wireless VLAN 5 using the credentials in the WLAN information table.

Step 6: Test connectivity.

Test connectivity between the wireless hosts and the Web Server by ping and URL.



```
Wireless Host 1
Physical Config Desktop Programming Attributes
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.5.2

Pinging 192.168.5.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.5.2: bytes=32 time=128ms TTL=127
Reply from 192.168.5.2: bytes=32 time=50ms TTL=127
Reply from 192.168.5.2: bytes=32 time=61ms TTL=127


Ping statistics for 192.168.5.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 50ms, Maximum = 128ms, Average = 79ms

C:\>ping 203.0.113.78

Pinging 203.0.113.78 with 32 bytes of data:

Reply from 203.0.113.78: bytes=32 time=57ms TTL=126
Reply from 203.0.113.78: bytes=32 time=77ms TTL=126
Reply from 203.0.113.78: bytes=32 time=38ms TTL=126
Reply from 203.0.113.78: bytes=32 time=22ms TTL=126

Ping statistics for 203.0.113.78:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 22ms, Maximum = 77ms, Average = 48ms
```

Laptop

Physical Config Desktop Programming Attributes

Command Prompt

```
Pinging 203.0.113.78 with 32 bytes of data:

Reply from 203.0.113.78: bytes=32 time=10ms TTL=126
Reply from 203.0.113.78: bytes=32 time=11ms TTL=126
Reply from 203.0.113.78: bytes=32 time=9ms TTL=126
Reply from 203.0.113.78: bytes=32 time=10ms TTL=126

Ping statistics for 203.0.113.78:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 9ms, Maximum = 11ms, Average = 10ms
```

☐ Top



นางสาวสุชานาฏ แก้วมุงคุณ 643020651-7