# **Operating System - Memory Management**

- Memory management is the functionality of an operating system which handles or manages primary memory and moves processes back and forth between main memory and disk during execution.
- Memory management keeps track of each and every memory location, regardless of either it is allocated to some process or it is free.
- It checks how much memory is to be allocated to processes.
- > It decides which process will get memory at what time.
- It tracks whenever some memory gets freed or unallocated and correspondingly it updates the status.

## **Process Address Space**

The process address space is the set of logical addresses that a process references in its code.

For example, when 32-bit addressing is in use, addresses can range from 0 to 0x7fffffff; that is, 2^31 possible numbers, for a total theoretical size of 2 gigabytes.

The operating system takes care of mapping the logical addresses to physical addresses at the time of memory allocation to the program.

There are three types of addresses used in a program before and after memory is allocated -

Virtual and physical addresses are the same in compile-time and load-time address-binding schemes. Virtual and physical addresses differ in execution-time address-binding scheme.

The set of all logical addresses generated by a program is referred to as a **logical address space**. The set of all physical addresses corresponding to these logical addresses is referred to as a **physical address space**.

The runtime mapping from virtual to physical address is done by the memory management unit (MMU) which is a hardware device. MMU uses following mechanism to convert virtual address to physical address.

• The value in the base register is added to every address generated by a user process, which is treated as offset at the time it is sent to memory. For example, if the base register value is 10000,

S.N.	Memory Addresses & Description
1	Symbolic addresses The addresses used in a source code. The variable names, constants, and instruction labels are the basic elements of the symbolic address space.
2	Relative addresses At the time of compilation, a compiler converts symbolic addresses into relative addresses.
3	Physical addresses The loader generates these addresses at the time when a program is loaded into main memory.


then an attempt by the user to use address location 100 will be dynamically reallocated to location 10100.

• The user program deals with virtual addresses; it never sees the real physical addresses.

## **Binding of Instructions and Data to Memory**


Address binding of instructions and data to memory addresses can happen at three different stages.

- 1. **Compile time**: The compile time is the time taken to compile the program or source code. During compilation, if memory location known a priori, then it generates absolute codes
- 2. **Load time**: It is the time taken to link all related program file and load into the main memory. It must generate relocatable code if memory location is not known at compile time.
- 3. **Execution time**: It is the time taken to execute the program in main memory by processor. Binding delayed until run time if the process can be moved during its execution from one memory segment to another. Need hardware support for address maps (e.g., base and limit registers).



# **Logical- Versus Physical-Address Space**

- An address generated by the CPU is commonly referred to as a logical address or a virtual
  address whereas an address seen by the main memory unit is commonly referred to as a physical
  address.
- The set of all logical addresses generated by a program is a **logical-address space whereas** the set of all physical addresses corresponding to these logical addresses is a **physical address space**.
- Logical and physical addresses are the same in compile-time and load-time addressbinding schemes; logical (virtual) and physical addresses differ in execution-time address binding scheme.
- The Memory Management Unit is a hardware device that maps virtual to physical address. In MMU scheme, the value in the relocation register is added to every address generated by a user process at the time it is sent to memory as follows:



## Static vs Dynamic Loading

- The choice between Static or Dynamic Loading is to be made at the time of computer program being developed.
- If you have to load your program statically, then at the time of compilation, the complete programs will be compiled and linked without leaving any external program or module dependency.
- The linker combines the object program with other necessary object modules into an absolute program, which also includes logical addresses.
- If you are writing a Dynamically loaded program, then your compiler will compile the program and for all the modules which you want to include dynamically, only references will be provided and rest of the work will be done at the time of execution.
- At the time of loading, with **static loading**, the absolute program (and data) is loaded into memory in order for execution to start.
- If you are using **dynamic loading**, dynamic routines of the library are stored on a disk in relocatable form and are loaded into memory only when they are needed by the program.


•

## **Static vs Dynamic Linking**

- when static linking is used, the linker combines all other modules needed by a program into a single executable program to avoid any runtime dependency.
- When dynamic linking is used, it is not required to link the actual module or library with the program, rather a reference to the dynamic module is provided at the time of compilation and linking.
- Dynamic Link Libraries (DLL) in Windows and Shared Objects in Unix are good examples of dynamic libraries.

# **Swapping**

- Swapping is a mechanism in which a process can be swapped temporarily out of main memory (or move) to secondary storage (disk) and make that memory available to other processes.
- At some later time, the system swaps back the process from the secondary storage to main memory.
- Though performance is usually affected by swapping process but it helps in running multiple and big processes in parallel and that's the reason Swapping is also known as a technique for memory compaction.



main memory

The total time taken by swapping process includes the time it takes to move the entire process to a secondary disk and then to copy the process back to memory, as well as the time the process takes to regain main memory.

Let us assume that the user process is of size 2048KB and on a standard hard disk where swapping will take place has a data transfer rate around 1 MB per second. The actual transfer of the 1000K process to or from memory will take

2048KB / 1024KB per second

- = 2 seconds
- = 2000 milliseconds

Now considering in and out time, it will take complete 4000 milliseconds plus other overhead where the process competes to regain main memory.

#### MEMORY ALLOCATION

- The main memory must accommodate both the operating system and the various user processes.
- We need to allocate different parts of the main memory in the most efficient way possible.
- The main memory is usually divided into two partitions: one for the resident operating system, and one for the user processes.
- We may place the operating system in either low memory or high memory.
- The major factor affecting this decision is the location of the interrupt vector.
- Since the interrupt vector is often in low memory, programmers usually place the operating system in low memory as well.

There are following two ways to allocate memory for user processes:


- 1. Contiguous memory allocation
- 2. Non contiguous memory allocation

## 1. Contiguous Memory Allocation

- ➤ Here, all the processes are stored in contiguous memory locations.
- To load multiple processes into memory, the Operating System must divide memory into multiple partitions for those processes.

**Hardware Support:** The relocation-register scheme used to protect user processes from each other, and from changing operating system code and data.

Relocation register contains value of smallest physical address of a partition and limit register contains range of that partition. Each logical address must be less than the limit register.



(Hardware support for relocation and limit registers)

According to size of partitions, the multiple partition schemes are divided into two types:

- i. Multiple fixed partition/ multiprogramming with fixed task(MFT)
- ii. Multiple variable partition/ multiprogramming with variable task(MVT)

**i. Multiple fixed partitions**: Main memory is divided into a number of static partitions at system generation time. In this case, any process whose size is less than or equal to the partition size can be loaded into any available partition.

If all partitions are full and no process is in the Ready or Running state, the operating system can swap a process out of any of the partitions and load in another process, so that there is some work for the processor.

Advantages: Simple to implement and little operating system overhead.

**Disadvantage**: \* Inefficient use of memory due to internal fragmentation.

- \* Maximum number of active processes is fixed
- . ii. Multiple variable partitions: With this partitioning, the partitions are of variable length and number. When a process is brought into main memory, it is allocated exactly as much memory as it requires and no more.

Advantages: No internal fragmentation and more efficient use of main memory.

Disadvantages: Inefficient use of processor due to the need for compaction to counter external fragmentation.

## **Partition Selection policy:**

When the multiple memory holes (partitions) are large enough to contain a process, the operating system must use an algorithm to select in which hole the process will be loaded.

The partition selection algorithm are as follows

- : ⇒ First-fit: The OS looks at all sections of free memory. The process is allocated to the first hole found that is big enough size than the size of process. ⇒ Next Fit: The next fit search starts at the last hole allocated and The process is allocated to the next hole found that is big enough size than the size of process.
- ⇒ **Best-fit:** The Best Fit searches the entire list of holes to find the smallest hole that is big enough size than the size of process.
- ⇒ Worst-fit: The Worst Fit searches the entire list of holes to find the largest hole that is big enough size than the size of process.

# **Fragmentation**

- As processes are loaded and removed from memory, the free memory space is broken into little pieces.
- It happens after sometimes that processes cannot be allocated to memory blocks considering their small size and memory blocks remains unused. This problem is known as Fragmentation.

Fragmentation is of two types -


S.N.	Fragmentation & Description
1	<b>External fragmentation</b> Total memory space is enough to satisfy a request or to reside a process in it, but it is not contiguous, so it cannot be used.
2	Internal fragmentation  Memory block assigned to process is bigger. Some portion of memory is left unused, as it cannot be used by another process.

The following diagram shows how fragmentation can cause waste of memory and a compaction technique can be used to create more free memory out of fragmented memory –

Fragmented memory before compaction



#### Memory after compaction



- External fragmentation can be reduced by compaction or shuffle memory contents to place all free memory together in one large block.
- To make compaction feasible, relocation should be dynamic.
- The internal fragmentation can be reduced by effectively assigning the smallest partition but large enough for the process.


# 2. Noncontiguous memory allocation

In noncontiguous memory allocation, it is allowed to store the processes in non contiguous memory locations. There are different techniques used to load processes into memory, as follows:

- 1. Paging
- 2. Segmentation
- 3. Virtual memory paging(Demand paging) etc.

# **Paging**

- > Paging is a memory management technique that allows a non contiguous process to execute.
- In paging technique process address space (logical address space)is broken into blocks of the same size called **pages** (size is power of 2, between 512 bytes and 8192 bytes).
- The size of the process is measured in the number of pages.
- Similarly, main memory is divided into small fixed-sized blocks of (physical) memory called **frames** and the size of a frame is kept the same as that of a page to have optimum utilization of the main memory and to avoid external fragmentation



(Diagram of Paging hardware)

# **Process of Translation from logical to physical addresses**

- Every address generated by the CPU is divided into two parts: a page number (p) and a page offset (d). The page number is used as an index into a page table.
- > The page table contains the base address of each page in physical memory. This base address is combined with the page offset to define the physical memory address that is sent to the memory unit.
- ➤ If the size of logical-address space is 2m and a page size is 2n addressing units (bytes or words), then the high-order (m n) bits of a logical address designate the page number and the n low-order bits designate the page offset.

Thus the logical address is as follows:

page number	page offset
P	d
m-n	n

Where p is an index into the page table and d is the displacement within the page.

# **Example:**

Consider a page size of 4 bytes and a physical memory of 32 bytes (8 pages),

we show how the user's view of memory can be mapped into physical memory.

Logical address 0 is page 0, offset 0. Indexing into the page table, we find that page 0 is in frame 5.


Thus, logical address 0 maps to physical address  $20 = (5 \times 4) + 0$ .

Logical address 3 (page 0, offset 3) maps to physical address  $23 = (5 \times 4) + 3$ .

Logical address 4 is page 1, offset 0; according to the page table, page 1 is mapped to frame 6.

Thus, logical address 4 maps to physical address  $24 = (6 \times 4) + 0$ . Logical address

13 maps to physical address  $9 = (2 \times 4) + 1$ .



## **Hardware Support for Paging:**

- Each operating system has its own methods for storing page tables.
- Most operating systems allocate a page table for each process.
- A pointer to the page table is stored with the other register values (like the instruction counter) in the process control block.
- When the dispatcher is told to start a process, it must reload the user registers and define the correct hardware page table values from the stored user page table.

## **Implementation of Page Table**

Generally, Page table is kept in main memory. The Page Table Base Register (PTBR) points to the page table. And Page-table length register (PRLR) indicates size of the page table.

In this scheme every data/instruction access requires two memory accesses. One for the page table and one for the data/instruction.


The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs).

# **Paging Hardware With TLB**

The TLB is an associative and high-speed memory. Each entry in the TLB consists of two parts: a key (or tag) and a value.

The TLB is used with page tables in the following way.

- The TLB contains only a few of the page-table entries. When a logical address is generated by the CPU, its page number is presented to the TLB.
- If the page number is found (known as a **TLB Hit**), its frame number is immediately available and is used to access memory. It takes only one memory access.
- If the page number is not in the TLB (known as a **TLB** miss), a memory reference to the page table must be made. When the frame number is obtained, we can use it to access memory. It takes two memory accesses.
- In addition, it stores the page number and frame number to the TLB, so that they will be found quickly on the next reference.
- If the TLB is already full of entries, the operating system must select one for replacement by using replacement algorithm.




The percentage of times that a particular page number is found in the TLB is called the **hit ratio**. The effective access time (EAT) is obtained as follows:

## EAT= $HR \times (TLBAT + MAT) + MR \times (TLBAT + 2 \times MAT)$

Where HR: Hit Ratio, TLBAT: TLB access time, MAT: Memory access time, MR: Miss Ratio.

# **Memory protection in Paged Environment:**


- Memory protection in a paged environment is accomplished by protection bits that are associated with each frame. These bits are kept in the page table.
- > One bit can define a page to be read-write or read-only. This protection bit can be checked to verify that no writes are being made to a read-only page. An attempt to write to a read only page causes a hardware trap to the operating system (or memory-protection violation)
- ➤ One more bit is attached to each entry in the page table: a **valid-invalid** bit. When this bit is set to "valid," this value indicates that the associated page is in the process' logical address space, and is a legal (or valid) page. If the bit is set to "invalid," this value indicates that the page is not in the process' logical-address space.
- ➤ Illegal addresses are trapped by using the valid-invalid bit. The operating system sets this bit for each page to allow or disallow accesses to that page.



# **Structure of the Page Table**


There are different structures of page table described as follows:

**1. Hierarchical Page table:** When the number of pages is very high, then the page table takes large amount of memory space. In such cases, we use multilevel paging scheme for reducing size of page table. A simple technique is a two-level page table. Since the page table is paged, the page number is further divided into parts: page number and page offset. Thus, a logical address is as follows:




Where pi is an index into the outer page table, and p2 is the displacement within the page of the outer page table.

**Two-Level Page-Table Scheme:** 




## Address translation scheme for a two-level paging architecture:




# 2. Hashed Page Tables:

- This scheme is applicable for address space larger than 32bits. In this scheme, the virtual page number is hashed into a page table.
- This page table contains a chain of elements hashing to the same location.
- Virtual page numbers are compared in this chain searching for a match. If a match is found, the corresponding physical frame is extracted.



# 3. Inverted Page Table:

- One entry for each real page of memory.
- Entry consists of the virtual address of the page stored in that real memory location, with
- information about the process that owns that page.
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs.



# **Shared Pages Shared code**

One copy of read-only (reentrant) code shared among processes (i.e., text editors,

- compilers, window systems).
- Shared code must appear in same location in the logical address space of all processes.

#### Private code and data

- Each process keeps a separate copy of the code and data.
- The pages for the private code and data can appear anywhere in the logical address space

# Segmentation


- > Segmentation is a memory-management scheme that supports user view of memory.
- > A program is a collection of segments.
- A segment is a logical procedure, function, method, object, local variables, global variables, common block, stack, symbol table, arrays etc.
- > A logical-address space is a collection of segments. Each segment has a name and a length.
- > The user specifies each address by two quantities: a segment name/number and an offset.
- Hence, Logical address consists of a two tuple: <segment-number, offset>

Segment table maps two-dimensional physical addresses and each entry in table has:

**base** – contains the starting physical address where the segments reside in memory.

**limit** – specifies the length of the segment.


**Segment-table base register (STBR)** points to the segment table's location in memory. **Segment-table length register (STLR)** indicates number of segments used by a program. such as: main program,



- The segment number is used as an index into the segment table.
- > The offset d of the logical address must be between 0 and the segment limit.
- ➤ If it is not, we trap to the operating system that logical addressing attempt beyond end of segment.
- If this offset is legal, it is added to the segment base to produce the address in physical memory of the desired byte.


Consider we have five segments numbered from 0 through 4. The segments are stored in physical memory as shown in figure. The segment table has a separate entry for each segment, giving start address in physical memory (or base) and the length of that segment (or limit). For example,

segment 2 is 400 bytes long and begins at location 4300. Thus, a reference to byte 53 of segment 2 is mapped onto location 4300 + 53 = 4353.



## VIRTUAL MEMORY

- Virtual memory is a technique that allows the execution of processes that may not be completely in memory.
- Only part of the program needs to be in memory for execution.
- It means that Logical address space can be much larger than physical address space.
- Virtual memory allows processes to easily share files and address spaces, and it provides an efficient mechanism for process creation.
- Virtual memory is the separation of user logical memory from physical memory.
- This separation allows an extremely large virtual memory to be provided for programmers when only a smaller physical memory is available.
- Virtual memory makes the task of programming much easier, because the programmer no longer needs to worry about the amount of physical memory available.



Virtual memory can be implemented via:

- Demand paging
- Demand segmentation


•

#### **DEMAND PAGING**

- A demand-paging system is similar to a paging system with swapping.
- Generally, Processes reside on secondary memory (which is usually a disk).
- When we want to execute a process, we swap it into memory.
- Rather than swapping the entire process into memory, it swaps the required page.
- This can be done by a lazy swapper.
- A lazy swapper never swaps a page into memory unless that page will be needed.
- A swapper manipulates entire processes, whereas a pager is concerned with the individual pages
  of a process.


## Page transfer Method:

- When a process is to be swapped in, the pager guesses which pages will be used before the process is swapped out again.
- Instead of swapping in a whole process, the pager brings only those necessary pages into memory.
- Thus, it avoids reading into memory pages that will not be used anyway, decreasing the swap time and the amount of physical memory needed.




## Page Table:

- The valid-invalid bit scheme of Page table can be used for indicating which pages are currently in memory.
- When this bit is set to "valid", this value indicates that the associated page is both legal and in memory.
- If the bit is set to "invalid", this value indicates that the page either is not valid or is valid but is currently on the disk.
- > The page-table entry for a page that is brought into memory is set as usual, but the pagetable entry for a page that is not currently in memory is simply marked invalid, or contains the address of the page on disk.



When a page references an invalid page, then it is called **Page Fault**. It means that page is not in main memory. The procedure for handling page fault is as follows:

- 1. We check an internal table for this process, to determine whether the reference was a valid or invalid memory access.
- 2. If the reference was invalid, we terminate the process. If it was valid, but we have not yet brought in that page in to memory.
- 3. We find a free frame (by taking one from the free-frame list).
- 4. We schedule a disk operation to read the desired page into the newly allocated frame.
- 5. When the disk read is complete, we modify the internal table kept with the process and the page table to indicate that the page is now in memory.
- 6. We restart the instruction that was interrupted by the illegal address trap. The process can now access the page as though it had always been in memory



The pages are copied into memory, only when they are required. This mechanism is called **Pure Demand Paging**.

## **Performance of Demand Paging**

Let p be the probability of a page fault (0 ).

Then the **effective access time** is

## Effective access time = (1 - p) x memory access time + p x page fault time


In any case, we are faced with three major components of the page-fault service time:

- 1. Service the page-fault interrupt.
- 2. Read in the page.
- **3.** Restart the process.

#### **PAGE REPLACEMENT**

**The page replacement** is a mechanism that loads a page from disc to memory when a page of memory needs to be allocated. Page replacement can be described as follows:

- 1. Find the location of the desired page on the disk.
- 2. Find a free frame:
- a. If there is a free frame, use it.
- b. If there is no free frame, use a page-replacement algorithm to select a victim frame.
- c. Write the victim page to the disk; change the page and frame tables accordingly.
- 3. Read the desired page into the (newly) free frame; change the page and frame tables.
- 4. Restart the user process.



## **Page Replacement Algorithms**

The page replacement algorithms decide which memory pages to page out (swap out, write to disk) when a page of memory needs to be allocated. We evaluate an algorithm by running it on a particular string of memory references and computing the number of page faults. The string of memory references is called a **reference string**.


The different page replacement algorithms are described as follows:

## 1. First-In-First-Out (FIFO) Algorithm:

- A FIFO replacement algorithm associates with each page the time when that page was brought into memory.
- When a page must be replaced, the oldest page is chosen to swap out.

- We can create a FIFO queue to hold all pages in memory.
- We replace the page at the head of the queue. When a page is brought into memory, we insert it at the tail of the queue.

# Example:




page frames

**Note**: For some page-replacement algorithms, the page fault rate may *increase* as the number of allocated frames increases. This most unexpected result is known as **Belady's anomaly.** 

# 2. Optimal Page Replacement algorithm:


- One result of the discovery of Belady's anomaly was the search for an optimal page replacement algorithm.
- An optimal page-replacement algorithm has the lowest page-fault rate of all algorithms, and will never suffer from Belady's anomaly.
- Such an algorithm does exist, and has been called OPT or MIN.
- It is simply "Replace the page that will not be used for the longest period of time". Use of this page-replacement algorithm guarantees the lowest possible pagefault rate for a fixed number of frames.

# Example:



## 3. LRU Page Replacement algorithm

- If we use the recent past as an approximation of the near future, then we will replace the page that has not been used for the longest period of time.
- This approach is the leastrecently-used (LRU) algorithm.
- LRU replacement associates with each page the time of that page's last use. When a page must be replaced,
- LRU chooses that page that has not been used for the longest period of time.



The major problem is **how** to implement LRU replacement. An LRU page-replacement algorithm may require substantial hardware assistance. The problem is to determine an order for the frames defined by the time of last use. Two implementations are feasible:


#### **Counters:**

- We associate with each page-table entry a time-of-use field, and add to the CPU a logical clock or counter.
- The clock is incremented for every memory reference.
- Whenever a reference to a page is made, the contents of the clock register are copied to the time-of-use field in the page-table entry for that page. We replace the page with the smallest time value.
- This scheme requires a search of the page table to find the LRU page, and a write to memory (to the time-of-use field in the page table) for each memory access.
- The times must also be maintained when page tables are changed (due to CPU scheduling).

#### Stack:

- Another approach to implementing LRU replacement is to keep a stack of page numbers.
- Whenever a page is referenced, it is removed from the stack and put on the top.
- In this way, the top of the stack is always the most recently used page and the bottom is the LRU page.
- Because entries must be removed from the middle of the stack, it is best implemented by a
  doubly linked list, with a head and tail pointer.
- Each update is a little more expensive, but there is no search for a replacement; the tail pointer points to the bottom of the stack, which is the LRU page.
- This approach is particularly appropriate for software or microcode impleme-ntations of LRU replacement.

Example:



## 4. LRU Approximation Page Replacement algorithm

- In this algorithm, Reference bits are associated with each entry in the page table.
- Initially, all bits are cleared (to 0) by the operating system.
- As a user process executes, the bit associated with each page referenced is set (to 1) by the hardware.
- After some time, we can determine which pages have been used and which have not been used by examining the reference bits.

This algorithm can be classified into different categories as follows:

# i. Additional-Reference-Bits Algorithm:

- It can keep an 8-bit(1 byte) for each page in a page table in memory.
- At regular intervals, a timer interrupt transfers control to the operating system.
- The operating system shifts the reference bit for each page into the highorder bit of its 8-bit, shifting the other bits right over 1 bit position, discarding the low-order bit.
- These 8 bits shift registers contain the history of page use for the last eight time periods.
- If we interpret these 8-bits as unsigned integers, the page with the lowest number is the LRU page, and it can be replaced.

# ii. Second-Chance Algorithm:

- The basic algorithm of second-chance replacement is a FIFO replacement algorithm.
- When a page has been selected, we inspect its reference bit. If the value is 0, we proceed to replace this page.
- If the reference bit is set to 1, we give that page a second chance and move on to select the next FIFO page.
- When a page gets a second chance, its reference bit is cleared and its arrival time is reset to the current time.
- Thus, a page that is given a second chance will not be replaced until all other pages are replaced.

## 5. Counting-Based Page Replacement

We could keep a counter of the number of references that have been made to each page, and develop the following two schemes.

- **i. LFU page replacement algorithm:** The **least frequently used** (LFU) **pagereplacement algorithm** requires that the page with the smallest count be replaced. The reason for this selection is that an actively used page should have a large reference count.
- **ii. MFU page-replacement algorithm**: The **most frequently used** (MFU) **page replacement algorithm** is based on the argument that the page with the largest count be replaced.

#### **Allocation of Frames**

When a page fault occurs, there is a free frame available to store new page into a frame. While the page swap is taking place, a replacement can be selected, which is written to the disk as the user process continues to execute. The operating system allocate all its buffer and table space from the free-frame list for new page.

Two major allocation Algorithm/schemes.

## 1. equal allocation

#### 2. proportional allocation

- **1. Equal allocation:** The easiest way to split m frames among n processes is to give everyone an equal share, m/n frames. This scheme is called **equal allocation.**
- **2. proportional allocation:** Here, it allocates available memory to each process according to its size. Let the size of the virtual memory for process pi be si, and define  $S=\Sigma$  Si

Then, if the total number of available frames is m, we allocate ai frames to process pi, where ai is approximately ai = Si/Sxm.

#### **Global Versus Local Allocation**

We can classify page-replacement algorithms into two broad categories:


# global replacement and local replacement.

Global replacement allows a process to select a replacement frame from the set of all frames, even if that frame is currently allocated to some other process; one process can take a frame from another. Local replacement requires that each process select from only its own set of allocated frames.

#### **THRASHING**

The system spends most of its time shuttling pages between main memory and secondary memory due to frequent page faults. This behavior is known as thrashing.

A process is thrashing if it is spending more time paging than executing. This leads to: low CPU utilization and the operating system thinks that it needs to increase the degree of multiprogramming.



degree of multiprogramming