LAB 04 FLAGS & DATA RELATED **OPERATIONS**



STUDENT NAME		ROLL NO	$\overline{ ext{SEC}}$
_		SIGNATURE	E & DATE
MARKS	S AWARDED:		
NATIONAL UNIVERSITY OF CO	OMPUTER AND EME CS), KARACHI	RGING SCIEN	CES

Version: Prepared by: Aamir Ali

1.0

 12^{th} Sep 2022Date:

Lab Session 04: FLAGS & DATA RELATED OPERATIONS

Objectives:

- Observing effect of Arithmetic Instructions on Flag Register
- Direct-offset operands
- OFFSET operator
- PTR operator
- TYPE operator
- LENGTHOF operator
- SIZEOF operator
- Indirect operands
- Indexed operands

Arithmetic Instructions & Flags

Status flags are updated to indicate certain properties of the result. Once a flag is set, it remains in that state until another instruction that affects (update) the flags is executed.

*NOTE: A flag is set when it equals to 1, otherwise it is clear

Z-Zero Flag:

The Zero flag is set when the result of an operation produces zero in the destination operand.

```
mov cx, 1
sub cx, 1
                               : CX=0, ZF=1
mov ax, 0FFFFh
                               ; AX=0, ZF=1;
inc ax
                               ; AX=1, ZF=0;
inc ax
```

C-Carry Flag:

This flag is set, when there is a carry out of MSB in case of addition and borrow in case of subtraction. The Carry flag is set when the result of an operation generates an unsigned value that is out of range (too big or too small for the destination operand).

```
mov al, 0FFh
add al, 1
                                ;CF=1, AL=0
; for trying less than 0
                                ; CF=1, AL=FF
sub al, 1
```

S-Sign Flag:

This flag indicates the sign of the result of an operation. A 0 for positive number and 1 for a negative number.

```
mov al , 15
add al, 97
                                ;observe SIGN Flag
mov al , 15
sub al, 97
                                ;observe SIGN Flag
mov al, 97
add al, 97
                                ;observe SIGN Flag
```

Instructor: Kashan Hussain **National University of Computer & Emerging Sciences,**

Instructor: Kashan

AC-Auxilary Carry Flag:

This flag is set, if there is a carry from the lowest nibble, i.e., bit three during addition, or borrow for the lowest nibble, i.e. bit three, during subtraction.

Suppose we add 1 to 0Fh. The sum (10h) contains a 1 in bit position 4 that was carried out of bit position 3:

```
mov al, 0Fh
add al, 1
                              AC=1
```

P Parity Flag:

The Parity flag (PF) is set when the least significant byte of the destination has an even number of 1 bits. The following ADD and SUB instructions alter the parity of AL:

```
mov al, 10001100b
add al, 000000010b
                           ; AL=10001110, PF =1
sub al, 100000000b
                           ; AL=00001110, PF=0
```

O-Over flow Flag:

The Overflow flag is set when the result of a signed arithmetic operation over-flows or underflows the destination operand. For example, the largest possible integer signed byte value is +127; adding 1 to it causes overflow:

```
mov al., 127
add al, 1
                                  : OF=1
```

Similarly, the smallest possible negative integer byte value is 128. Subtracting 1 from it causes underflow. The destination operand value does not hold a valid arithmetic result, and the Overflow flag is set:

```
mov al, -128
sub al, 1
                                ; OF=1
```

DATA Related Operations

Direct-offset Operands:

You can add a displacement to the name of a variable, creating a direct-offset operand.

Example:

```
.data
arrayB BYTE 10h,20h,30h,40h,50h
arrayW WORD 100h,200h,300h
.code
mov al, arrayB
                             ; AL = 10h
mov al,[arrayB+1]
                             ; AL = 20h
mov ax,arrayW
                             ; AX = 100h
mov ax,[arrayW+2]
                             AX = 200h
```

OFFSET Operator:

The OFFSET operator returns the offset of a data label.

Syntax:

MOV reg32, OFFSET mem ; reg32 points to count

Example:

```
.data
bVal BYTE?
wVal WORD?
dVal DWORD?
dVal2 DWORD?
;If bVal is located at offset 00404000h, we would get:
mov esi, OFFSET bval ; ESI = 00404000
mov esi, OFFSET wVal ; ESI = 00404001
mov esi, OFFSET dVal ; ESI = 00404003
mov esi, OFFSET dVal ; ESI = 00404007
```

PTR Operator:

We can use the PTR operator to override the declared size of an operand. Note PTR must be used in combination with one of the standard assembler data types.

For example: that we would like to move the lower 16 bits of a doubleword variable named myDouble into AX. The assembler will not permit the following move because the operand sizes do not match:

```
.data
myDouble DWORD 12345678h
.code
mov ax, myDouble ; error
```

But the WORD PTR operator makes it possible to move the low-order word (5678h) to AX:

```
mov ax, word ptr myDouble ; AX = 5678H and higher word (1234h) to AX:
mov dx, word ptr myDouble+2 ; DX = 1234H
```

Moving Smaller Values into Larger Destinations

We might want to move two smaller values from memory to a larger destination operand. In the next example, the first word is copied to the lower half of EAX and the second word is copied to the upper half.

The DWORD PTR operator makes this possible:

```
.data
wordList WORD 5678h, 1234h
.code
mov eax, DWORD PTR wordList; EAX = 12345678h
```

TYPE Operator:

Instructor: Kashan Hussain

The TYPE operator returns the size, in bytes, of a single element of a variable.

Syntax:

```
MOV reg16, TYPE mem

Example 1:
    .data
    var1 BYTE ? ; TYPE var1 = 1
```

var2 WORD ? ; TYPE var2 = 2

Instructor: Kashan

```
var3 DWORD? ; TYPE var3 = 4
var4 QWORD? ; TYPE var4 = 8
```

Example 2:

```
.data
var1 BYTE 20h
var2 WORD 1000h
var3 DWORD?
var4 BYTE 10, 20, 30, 40, 50
msg BYTE 'File not found', 0
.code
mov ax, type var1
                                     ; AX = 0001
mov ax, type var2
                                     : AX = 0002
mov ax, type var3
                                     ; AX = 0004
mov ax, type var4
                                     AX = 0001
mov ax, type msg
                                     ; AX = 0001
```

LENGTHOF Operator:

The LENGTHOF operator counts the number of individual elements in a variable that has been defined using DUP.

Syntax:

```
MOV reg16, LENGTHOF mem
```

Example:

```
.data
val1 WORD 1000h
val2 SWORD 10, 20, 30 array WORD 10 DUP(?),0
array2 WORD 5 DUP(3 DUP(0))
message BYTE 'File not found', 0
.code
mov ax, LENGTHOF val1
                                  ; AX = 1
mov ax, LENGTHOF val2
                                  ; AX = 3
mov ax, LENGTHOF array
                                  ; AX = 11
mov ax, LENGTHOF array2
                                  ; AX = 15
mov ax, LENGTHOF message
                                  ; AX = 15
```

SIZEOF Operator:

The SIZEOF operator returns the number of bytes an array takes up. It is similar in effect to multiplying LENGTHOF with TYPE.

Syntax:

```
MOV reg16/32, SIZEOF mem
```

Example:

```
.data
intArray WORD 32 DUP(0)
.code
```



```
mov eax, SIZEOF int Array
                               ; EAX = 64
```

Indirect Operands

In protected mode, an indirect operand can be any 32-bit general-purpose register (EAX, EBX, ECX, EDX, ESI, EDI, EBP, and ESP) surrounded by brackets. The register is assumed to contain the address of some data.

Example:

```
.data
byteVal BYTE 10h
.code
mov esi,OFFSET byteVal
mov al, [esi]; AL = 10h
```

If the destination operand uses indirect addressing, a new value is placed in memory at the location pointed to by the register.

```
mov [esi],bl
```

Using PTR with Indirect Operands

```
inc [esi]
                                           ; error: operand must have size
```

The assembler does not know whether ESI points to a byte, word, doubleword, or some other size. The PTR operator confirms the operand size:

```
inc BYTE PTR [esi]
```

Arrays

Indirect operands are ideal tools for stepping through arrays.

Example:

```
.data
arrayB BYTE 10h,20h,30h
.code
mov esi,OFFSET arrayB
mov al, [esi]; AL = 10h
inc esi
mov al, [esi]; AL = 20h
```

If we use an array of 16-bit integers, we add 2 to ESI to address each subsequent array element.

```
arrayW WORD 1000h,2000h,3000h
.code
mov esi,OFFSET arrayW
mov ax, [esi]; AX = 1000h
add esi.2
mov ax, [esi]; AX = 2000h
```

If we use an array of 32-bit integers, we add 4 to ESI to address each subsequent array element.

Indexed Operands

Instructor: Kashan Hussain

An indexed operand adds a constant to a register to generate an effective address. Any of the 32-bit general-purpose registers may be used as index registers.

Page 5 of 7

```
Syntax:
```

```
constant [ reg32 ] ; reg32 can be any of the 32-bit general registers [ constant + reg32 ]
```

Example:

```
.data
arrayB BYTE 20, 40, 60, 80
.code
mov esi, 1
mov al, arrayB[esi]
inc esi
mov al, arrayB[esi]
mov esi, 3
mov al, [arrayB + esi]
```

Adding Displacements: The second type of indexed addressing combines a register with a constant offset. The index register holds the base address of an array.

```
.data
arrayW WORD 1000h,2000h,3000h
.code
main PROC
mov esi,OFFSET arrayW
mov ax,[esi] ; AX = 1000h
mov bx,[esi+2] ; BX = 2000h
mov cx,[esi+4] ; CX = 3000h
```

Scale Factors in Indexed Operands

Indexed operands must take into account the size of each array element when calculating offsets.

Syntax:

```
constant [ reg32 * TYPE constant]
```

Example:

```
.data
arrayW WORD 1000h, 2000h, 3000h, 4000h
.code
main PROC
mov eax,0
mov ebx,0
mov ecx,0
mov esi, 1
mov ax, arrayW[esi * TYPE arrayW]
mov esi, 2
mov bx, arrayW[esi * TYPE arrayW]
mov esi, 3
mov cx, arrayW[esi * TYPE arrayW]
call DumpRegs
```

Lab Exercise:

- 1. Initialize a double word array consisting of elements 7,4,1,5,2. Sort the given array in ascending order directly with the help of registers. Use direct-offset addressing to access the elements.
- 2. Use following array declarations:

```
arrayB BYTE 10, 20, 30
arrayW WORD 150, 250, 350
arrayD DWORD 600, 1200, 1800
```

Now initialize three double word variables SUM1, SUM2, SUM3 and perform following operations (expressed in pseudo-code here):

```
SUM1 = arrayB[0] + arrayW[0] + arrayD[0]
SUM2 = arrayB[1] + arrayW[1] + arrayD[1]
SUM3 = arrayB[2] + arrayW[2] + arrayD[2]
```

Note: Use PTR or any other required directives/operator.

- 3. Declare a 32-bit signed integer **val1** and initialize it with the 8000h. If **val1** is incremented by 1000h using the ADD instruction, what will be the values of the Carry and Sign flags?
- 4. Initialize two arrays:

Instructor: Kashan Hussain

```
array1 BYTE 10, 20, 30, 40 array2 BYTE DUP(?)
```

Copy elements of array1 into array2 in reverse order.

5. Write down the values of the Carry, Sign, Zero, and Overflow flags after each instruction has executed:

```
mov ax , 7FF0h ;CF=?, SF=?, ZF=?, OF=? add al , 10h ;CF=?, SF=?, ZF=?, OF=? add ah , 1 ;CF=?, SF=?, ZF=?, OF=? add ax , 2 ;CF=?, SF=?, ZF=?, OF=?
```