
## True Strain



### home > deformation & strain > true strain



#### Introduction

True strain is also called natural strain. As will be shown, it arises from the time integration of the rate of deformation tensor, which was introduced on the velocity gradient page. This page will show that true strain is defined as

$$\epsilon_{
m True} = \ln \left( rac{L_F}{L_o} 
ight)$$

for an object undergoing tension and/or compression.

### Rate of Deformation and True Strain

This example will demonstrate the connection between the rate of deformation tensor,  $\mathbf{D}$ , and true strain.



### Comparison to True Strain

Imagine a wire being stretched in tension. At the beginning of a time step, the wire is 0.50 m, and 2 sec later, it is 0.55 m long. So this can be described as

$$x(t) = x \left[ 1 + \left( rac{0.05}{0.50} 
ight) \, \left( rac{t}{2} 
ight) 
ight]$$

This works because at t=0, it reduces to x(t)=x, and at t=2 sec, it gives x(t)=x(0.55/0.50). And yes, the equation is in terms of x, not X.

Between 2 and 4 seconds, the wire is stretched to 0.60 m long.

$$x(t) = x \left[ 1 + \left( rac{0.05}{0.55} 
ight) \, \left( rac{t-2}{2} 
ight) 
ight]$$

And between 4 and 6 seconds, it is stretched to  $0.65\ \mathrm{m}$  long.

$$\frac{\text{Loading [MathJax]/extensions/MathZoom. js}}{x(t) = } x \left[ 1 + \left( \frac{0.05}{0.60} \right) \, \left( \frac{t-4}{2} \right) \right]$$

In order to calculate a velocity gradient, we first need velocities. So take the time derivative of each equation.

$$0 < t < 2: \quad v_x = \left(rac{x}{2}
ight) \left(rac{0.05}{0.50}
ight)$$

$$2 < t < 4: \hspace{0.5cm} v_x = \hspace{0.1cm} \left(rac{x}{2}
ight) \hspace{0.1cm} \left(rac{0.05}{0.55}
ight)$$

$$4 < t < 6: \hspace{0.5cm} v_x = \left(rac{x}{2}
ight) \, \left(rac{0.05}{0.60}
ight)$$

And the velocity gradient during each 2 second time step is

$$0 < t < 2: \hspace{0.5cm} D_{11} = \hspace{0.1cm} \left(rac{1}{2}
ight) \hspace{0.1cm} \left(rac{0.05}{0.50}
ight)$$

$$2 < t < 4: \hspace{0.5cm} D_{11} = \hspace{0.1cm} \left(rac{1}{2}
ight) \hspace{0.1cm} \left(rac{0.05}{0.55}
ight)$$

$$4 < t < 6: \hspace{0.5cm} D_{11} = \hspace{0.1cm} \left(rac{1}{2}
ight) \hspace{0.1cm} \left(rac{0.05}{0.60}
ight)$$

So far, so good, but nothing special. But now numerically integrate  $\int D dt$ .

$$\int D \, dt = \frac{0.05}{0.50} + \frac{0.05}{0.55} + \frac{0.05}{0.60} = 0.274$$

The important point is to recognize the connection to true strain. To see this, note that

$$D \, dt \; = \; \left( rac{\partial v}{\partial x} 
ight) dt \; = \; rac{\partial (v \, dt)}{\partial x} \; = \; rac{\partial u}{\partial x} \; = \; rac{dl}{l}$$

So

$$\epsilon_{\mathrm{True}} \,=\, \int D\,dt \,=\, \int rac{dl}{l} \,=\, \ln\left(rac{L_F}{L_o}
ight) \,=\, \ln\left(rac{0.65}{0.50}
ight) \,=\, 0.262$$

The only reason that the numerical integration gave a slightly different result than  $\epsilon_{\mathrm{True}}$  is because the time steps were relatively large.

This example demonstrates that  $\int D\,dt = \epsilon_{\mathrm{True}}$  and  $D = \dot{\epsilon}_{\mathrm{True}}.$ 

True strain is also called natural strain, although this name does not appear to


### True Strain vs Engineering Strain

True strain does have an attractive property that no other strain definition possesses. That is, its range spans from  $-\infty$  to  $+\infty$ . It is compared to engineering strain in the figure below. Note that the relationship is

$$\epsilon_{\mathrm{True}} = \ln(1 + \epsilon_{\mathrm{Eng}})$$

because

$$1 + \epsilon_{
m Eng} \; = \; 1 + rac{\Delta L}{L_o} \; = \; rac{L_o}{L_o} + rac{\Delta L}{L_o} \; = \; rac{L_F}{L_o}$$



# True Strain and Incompressible Materials


True strain possesses an additional property that is quite attractive when working with incompressible materials. To see this, recall this discussion on volume change on the hydrostatic and deviatoric strain webpage.

Recall that the ratio of initial to final volume is

$$rac{V_F}{V_o} = \left(rac{W_F}{W_o}
ight) \left(rac{D_F}{D_o}
ight) \left(rac{H_F}{H_o}
ight) = 1$$

Now take the natural log of this equation to get

$$\ln \left(rac{W_F}{W_o}
ight) + \ln \left(rac{D_F}{D_o}
ight) + \ln \left(rac{H_F}{H_o}
ight) = 0$$



But each log term is just the true strain. In fact, the sum is the trace of the true strain tensor.

$$\epsilon_1^{\mathrm{True}} + \epsilon_2^{\mathrm{True}} + \epsilon_3^{\mathrm{True}} = 0$$
 (incompressible materials)

Unlike small strains and Green strains, the above relationship applies to true strains even when the strains are finite.

Also, since the sum is zero, the rate of change of the sum will also always be zero for incompressible materials. So

$$\dot{\epsilon}_1^{\,\mathrm{True}} + \dot{\epsilon}_2^{\,\mathrm{True}} + \dot{\epsilon}_3^{\,\mathrm{True}} = 0$$
 (incompressible materials)

But since  $D=\dot{\epsilon}_{True}$ , then the above equation can be written equally well as

$$D_{11} + D_{22} + D_{33} = 0$$
 (incompressible materials)

And furthermore, since each of these equations is the first invariant of its associated strain or rate of deformation tensor, the above identities are not limited to principal orientations and principal strains. They will apply even if shears are present.

### True Strain and Volume Change

More generally, if the material is compressible, then the above relationship becomes

$$\ln \left(rac{V_F}{V_o}
ight) \, = \, \ln \left(rac{W_F}{W_o}
ight) + \ln \left(rac{D_F}{D_o}
ight) + \ln \left(rac{H_F}{H_o}
ight) \, = \, \epsilon_{
m Vol}^{
m True}$$

$$\epsilon_1^{\mathrm{True}} + \epsilon_2^{\mathrm{True}} + \epsilon_3^{\mathrm{True}} = \epsilon_{\mathrm{Vol}}^{\mathrm{True}}$$

except this time, this applies for all strains, not just small ones.

Taking the time derivative again gives

$$\dot{\epsilon}_1^{\mathrm{True}} + \dot{\epsilon}_2^{\mathrm{True}} + \dot{\epsilon}_3^{\mathrm{True}} = \dot{\epsilon}_{\mathrm{Vol}}^{\mathrm{True}}$$

and in terms of the rate of deformation tensor components...

$$D_{11} + D_{22} + D_{33} = \dot{\epsilon}_{
m Vol}^{
m True}$$

Once again, this applies for finite strains, not just infinitesimal ones, and not just in principal orientations.


#### True Strain and Rotations

Things get complicated when the rate of deformation tensor is integrated over time to obtain true strain while rigid body rotations are present. Consider the following example of an object being stretched and rotated simultaneously.



### Tension Example with Rotation

In this example, the square starts out being stretched in the x-direction, but is also being rotated at the same time. It finishes after having rotated  $90^{\circ}$ , while all the time, being stretched in tension.



At t=0, the object is being stretched along the x-axis, and shrinking along the y-axis due to Poisson's effect. The rate of deformation tensor could be

$$\mathbf{D} = egin{bmatrix} 3.0 & 0.0 \ 0.0 & -2.0 \end{bmatrix}$$

And if this takes place for 0.1 sec, then the integration of  $\int \mathbf{D} \, dt$  gives

$$oldsymbol{\epsilon}_{ ext{True}} = egin{bmatrix} 0.3 & 0.0 \ 0.0 & -0.2 \end{bmatrix}$$

At some instant later, the object has rotated  $45\,^\circ$  , and continues to stretch. At this point, because it is at  $45\,^\circ$  , this deformation shows up as shear. So  $\bf D$  could be

$$\mathbf{D} = egin{bmatrix} 0.0 & 1.5 \ 1.5 & 0.0 \end{bmatrix}$$

And if this occurs for another 0.1 sec, then the <u>increment</u> in true strain is

$$\Delta oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.00 & 0.15 \ 0.15 & 0.00 \end{bmatrix}$$

and the total strain is the sum of the two.

$$oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.30 & 0.15 \ 0.15 & -0.20 \end{bmatrix}$$

Then at a later time, the object has rotated  $90^{\circ}\,$  and is still being pulled in tension such that

$$\mathbf{D} = \begin{bmatrix} -1.0 & 0.0 \\ 0.0 & 1.5 \end{bmatrix}$$

So the increment for this step is

$$\Delta oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} -0.10 & 0.00 \ 0.00 & 0.15 \end{bmatrix}$$

Remember that it has been stretched to a longer length now, so dl/l is decreasing because the denominator is increasing.

Adding this to the previous total strain tensor gives

$$oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.20 & 0.15 \ 0.15 & -0.05 \end{bmatrix}$$


The problem here is that the final true strain tensor is just a jumbled mess. It includes shear values, even though the corners remain at  $90^{\circ}$ , and ends with a negative  $D_{22}$  value even though the object was indeed stretching in the ydirection at the end of the process. This exemplifies the near uselessness of  $\int \mathbf{D} \, dt$  when rotations are present.

But there is an alternative! Compute  $\int \mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R} \, dt$  instead. The  $\mathbf{R}^T$  and  $\mathbf{R}$  rotate the deformations back to the initial orientation without altering the levels. This gives a true strain result that is in the initial reference orientation, like a Green strain tensor. The result is a bit of a hybrid because it is based on  $\mathbf{D}$ , which is clearly an Eulerian quantity, but it is in the reference orientation, like a Lagrangian quantity. Granted, it also requires a polar decomposition, which is a little extra work, but it gives a much more easily interpreted strain tensor.



### Tension Example with Rotations Again

This is the exact same example, but the strain state is calculated differently this time.



At t=0, the object is being stretched along the x-axis, and shrinking along the y-axis due to Poisson's effect. The rate of deformation tensor is the same as before.

$$\mathbf{D} = egin{bmatrix} 3.0 & 0.0 \ 0.0 & -2.0 \end{bmatrix}$$

And it takes place for  $0.1~{\rm sec}$ , and  ${\bf R}={\bf 0}$  at this point, so the integration of

 $\int \mathbf{D} dt$  gives

$$oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.3 & 0.0 \ 0.0 & -0.2 \end{bmatrix}$$

After the object has rotated  $45^{\circ}$  ,  $\mathbf{D}$  is now

$$\mathbf{D} = egin{bmatrix} 0.0 & 1.5 \ 1.5 & 0.0 \end{bmatrix}$$

But the rotation matrix is

$$\mathbf{R} = \begin{bmatrix} 0.7071 & -0.7071 \\ 0.7071 & 0.7071 \end{bmatrix}$$

So  $\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R}$  gives

$$\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R} = \begin{bmatrix} 1.5 & 0.0 \\ 0.0 & -1.5 \end{bmatrix}$$

Multiplying this by 0.1 sec gives

$$\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R} \, dt = \begin{bmatrix} 0.15 & 0.0 \\ 0.0 & -0.15 \end{bmatrix}$$

And adding this to the first result gives

$$oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.45 & 0.00 \ 0.00 & -0.35 \end{bmatrix}$$

Finally, the object has rotated  $90^{\circ}$  . So  ${\bf D}$  and  ${\bf R}$  are

$$\mathbf{D} = egin{bmatrix} -1.0 & 0.0 \ 0.0 & 1.5 \end{bmatrix} \qquad \qquad \mathbf{R} = egin{bmatrix} 0 & -1 \ 1 & 0 \end{bmatrix}$$

Computing  $\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R}$  gives

$$\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R} \ = \ egin{bmatrix} 1.5 & 0.0 \ 0.0 & -1.0 \end{bmatrix}$$

And multiplying by 0.1 sec gives

$$\mathbf{R}^T \cdot \mathbf{D} \cdot \mathbf{R} \, dt = egin{bmatrix} 0.15 & 0.00 \ 0.00 & -0.10 \end{bmatrix}$$

And finally, adding this to the previous running total gives

$$oldsymbol{\epsilon}_{\mathrm{True}} = egin{bmatrix} 0.60 & 0.00 \ 0.00 & -0.45 \end{bmatrix}$$

This result is much more intuitive. It shows that the object was stretched in its <u>original</u> x-direction and compressed in its <u>original</u> y-direction. And the components correspond to  $\ln(L_F/L_o)$ , so they are still true strain type quantities.



Table of Contents



Material Derivatives