# Package 'proj4'

February 20, 2015

	<b>3</b> ,
Version 1.0-8	
<b>Title</b> A simple interfa	ce to the PROJ.4 cartographic projections
<b>Depends</b> R (>= 2.0.0)	
Author Simon Urban	ek <simon.urbanek@r-project.org></simon.urbanek@r-project.org>
Maintainer Simon U	rbanek <simon.urbanek@r-project.org></simon.urbanek@r-project.org>
transformation of It allows transfo	interface to lat/long projection and datum of the PROJ.4 cartographic projections library. rmation of geographic coordinates from one r datum to another.
SystemRequirements	proj 4.4.6 or higher (http://proj.maptools.org/)
License GPL-2	
URL http://www.rf	orge.net/proj4/
Repository CRAN	
<b>Date/Publication</b> 201	2-08-05 06:07:47
NeedsCompilation y	es
R topics docum	nented:
1 0	
Index	5
project	Projection of coordinates

## Description

Projection of lat/long coordinates or its inverse.

2 project

#### **Usage**

#### **Arguments**

xy input (list, matrix or 2d-array) - see details below.

proj projection definition

inverse if TRUE inverse projection is performed (from a cartographic projection into

lat/long), otherwise projects from lat/long into a cartographic projection.

degrees if TRUE then the lat/long data is assumed to be in degrees, otherwise in radians

silent if set to TRUE, warnings will be suppressed

ellps.default default ellipsoid that will be added if no datum or ellipsoid parameter is specified

in proj. Older versions of PROJ.4 didn't require a datum (and used sphere by default), but 4.5.0 and higher always require a datum or an ellipsoid. Set to NA if no datum should be added to proj (e.g. if you specify an ellipsoid directly).

#### **Details**

The input can be a list of two or more vectors (if the list contains more than two entries, only first two entries are used and a warning is issued), a two-dimensional matrix or array (the number of columns or rows must be exactly two) or a vector of the length 2. If the input is a list then the result will be a list with the entries named x and y, otherwise the result is a matrix with two columns.

When the list form is used, inputs are recycled with a warning when necessary.

proj specifies the target (or source if inverse) projection. The format can be either a single (unnamed) string which contains all parameters: "+proj=lcc +lat\_1=33 +lat\_2=45 +lat\_0=39 +lon\_0=-96" or an unnamed vector of complete individual parameters: c("+proj=lcc","+lat\_1=33","+lat\_2=45","+lat\_0=39","+lor a named vector or list that will be composed into parameters: list(proj="lcc", lat\_1=33, lat\_2=45, lat\_0=39, lor

A list of some commonly used projections can be found at http://www.remotesensing.org/geotiff/proj\_list/

if degrees is TRUE then the latitude and longitude are expected to be in degrees, if FALSE then in radians.

## Value

A two column matrix or list of coordinates. If the input was a list then the output will be a list, otherwise a matrix.

### References

http://www.remotesensing.org/proj/

transform 3

## **Examples**

```
## this is just very simple, because we don't want to depend on
## maps package, so we can't show more useful stuff..
data(state)
s <- project(state.center, "+proj=merc")
plot(s, type='n', asp=1)
text(s,, state.abb)</pre>
```

transform

Transform geographic coordinates from one projection into another

## **Description**

Transformation of geographics coordinates from one projection to another, using PROJ.4 library.

## Usage

```
ptransform(data, src.proj, dst.proj, silent=TRUE)
```

## **Arguments**

data input (list, matrix or 2d-array) - see details below.

src.proj description of the source projection
dst.proj description of the destination projection
silent if set to TRUE, warnings will be suppressed

## **Details**

The data can be a list of vectors (if the list contains more than three entries, only first three entries are used and a warning is issued), a two-dimensional matrix or array (the number of columns or rows must be at most three). If the input is a list then the result will be a list with the entries named x, y and z, otherwise the result is a matrix with three columns.

When the list form is used, inputs are recycled with a warning when necessary. All unspecified coordinates are set to zero.

Note that the project specification *must* include an ellipsoid or a datum. Add ellps='sphere' to obtain the same result as older PROJ.4 versions with no datum specification.

Datum files must be installed in order to be able to perform datum shifts (on Windows they should be located in c:\proj) - see PROJ.4 website for the download of datum files.

A list of some commonly used projections can be found at http://www.remotesensing.org/geotiff/proj\_list/,

#### Value

A matrix with three columns or list with projected coordinates. If the input was a list then the output will be a list, otherwise a matrix.

4 transform

## Author(s)

Simon Urbanek

#### References

```
http://www.remotesensing.org/proj/
```

## **Examples**

## **Index**

```
*Topic spatial
project, 1
transform, 3

project, 1
ptransform (transform), 3

transform, 3
```