N . E . K . O .



Installing your personal AI helper

A step-by-step guide to put N.E.K.O. on a new computer.
No experience with AI or computers needed.

About 30 minutes of your time | 1-3 hours of waiting | One double-click

Neuro Electric Knowledge Operator · runs on your own computer · your data stays with you

BEFORE YOU START

What are we installing?

N.E.K.O. ("Neko") is a helper that lives on your computer. You talk to her like a person - out loud or by typing - and she answers, and she can do things on the computer for you: open programs, play music, read files, set reminders and much more.

She listens

Say her name, then what you want. No buttons needed.

She thinks

An **AI** (a program that understands language) works out what you mean.

She asks first

Anything risky waits for your OK. Nothing leaves the PC without permission.

What you need


	Thing	Why
	A Windows 10 or 11 computer	The computer Neko will live on.
	An NVIDIA graphics card (6 GB or more is best)	The AI runs on it. The office PC's RTX 5060 Ti 16 GB is perfect. Without one she still works, slower.
	About 60 GB of free disk space	Most of it is the AI's "brain" files.
	Internet during the install	To download the AI. Afterwards she also works offline.
	A phone with Telegram (optional)	To chat with her and approve things from anywhere.
	Tailscale (optional, free)	A private connection between your computers and phones.

Words you will see: **AI model** = the brain file Neko thinks with. **Telegram bot** = a chat contact on your phone that is really Neko. **Pairing** = telling Neko which phone is yours.

THE BIG PICTURE

How everything fits together

You can have Neko on more than one computer. Each one is its own Neko with its own memory - but they can help each other.



The laptop (main PC)

The owner's computer. It can borrow the office PC's stronger AI when that PC is on, and it can ask the office Neko to do things there.

The office PC

Gets its own Neko with its own name and memory. Its strong graphics card runs bigger, smarter AI models.

The owner's phone

Approves risky actions on **both** computers, can upgrade Neko. Needs a PIN for the riskiest things.

Everyday phones

For people who use a PC every day: chat, music, reminders, running programs. Anything risky they ask for goes to the owner's phone.

PART A · ON THE MAIN LAPTOP

Get the installer ready

Do this once on the laptop that already has Neko. It prepares a small package to carry to the new PC.

A1

Send the newest version to your private online copy

Tell Neko:

"Neko, publish the update"

She checks everything, asks you to confirm (on the phone it needs your PIN), and sends the newest Neko to your private GitHub storage. New computers download their updates from there.

A2

Make the installer package

Open **PowerShell** (press the Windows key, type *PowerShell*, press Enter) and paste this line:

```
powershell -ExecutionPolicy Bypass -File D:\PROJECT\N.E.K.O\scripts\build-dist.ps1
```

After a few seconds you have the file `D:\NEKO-Data\dist\NEKO-Setup.zip` (less than 1 MB). It contains Neko's program only - **no memories, no passwords, no keys**. The builder refuses to make the package if it finds anything personal.

A3

Copy it to the new computer

Use a USB stick, Google Drive, OneDrive or any way you like.

Tip: You can make a new package any time - it always contains the newest version.

PART B · ON THE NEW COMPUTER


Install with one double-click

B1 Unzip the package

Right-click `NEKO-Setup.zip` → **Extract All** → **Extract**. A folder **NEKO-Setup** appears.

B2 Double-click INSTALL.cmd

A black window opens and checks the computer. It shows what is there and what is missing:



B3 Press Enter to say yes - then wait

It now installs Python, Neko, her voice, her hearing, and the AI models sized for this graphics card. On a normal home connection this takes **1-3 hours**. You can leave the computer alone - it continues by itself. If it stops (for example the internet drops), just double-click INSTALL.cmd again: it continues where it stopped.

Old graphics driver? RTX 50-series cards need NVIDIA driver 572 or newer. If yours is older, the installer offers to open NVIDIA's download page. Install the driver, restart, and run INSTALL.cmd again.

PART B · A FEW QUESTIONS

Tell her who she is


Near the end the installer asks some simple questions. Answer for the person who will use **this** computer:

N.E.K.O. installer - profile

```
[8] Your profile
  Your name (what should the assistant call you?): Rafi
  The assistant's name [Neko]: Nova
  Voice: female or male? [female]: female
  Do you also talk to Nova in Bangla? [y/N]: y
  Control Nova from a phone through Telegram? [y/N]: y
    Paste the bot key (or press Enter to skip): ************
    bot @office_nova_bot is ready
  Add free cloud brains now? [y/N]: n
Start Nova automatically with Windows? [Y/n]: y
```

Making the Telegram bot

When it asks about Telegram, take **your own phone** (the owner's):



1. **Open @BotFather**

   In Telegram, search **@BotFather** - pick the one with the **blue tick**. Tap **Start**.

2. **Send /newbot**

   Give it a name (e.g. *Office Nova*) and a username that ends in **bot**.

3. **Copy the key**

   BotFather replies with a long key. Copy it and paste it into the installer.

> ⚠ **Always a NEW bot.** Never use the laptop's bot - two computers on one bot would steal each other's messages (Neko notices and warns you).

PART B · FIRST START


Meet her and pair the phones


B4 She starts by herself

At the end the installer runs a self-test and asks *Start now?* - say yes. A glowing orb appears. From now on she starts with Windows, hidden, and appears when you say her name.

B5 Pair the OWNER phone first

The orb shows a message like **Pair your phone: send /pair 482913 to @office_nova_bot**. On **your** phone, open that bot and send exactly that. She answers *Paired as the owner!*





B6 Set the approval PIN

Double-click the orb → **Command Center** → **Phone** → **3. Approval PIN**: type 4-8 digits → **Set PIN**. Use a number that isn't your phone's unlock code.

B7 Add the everyday phone

Same page: **Pair an everyday phone**. A new code appears; the person who uses this PC sends **/pair** and that code from their Telegram to the same bot. Their risky requests will come to your phone.

B8 Only you approve

Still on the Phone page, under **Approvals** tick **Only my (owner) phone can approve** and click **Save options**. Now the approval window on this PC can only say *Deny* - risky things need **your** phone.

PART C · OPTIONAL EXTRAS

Connect the computers and phones

These are optional, but they make Neko much more useful. All of them use **Tailscale** - a free app that makes a private, encrypted network just for your own devices.

C1

Install Tailscale everywhere

Get Tailscale from **tailscale.com/download** on the laptop, the office PC and your phones. Sign in with the **same account** on all of them.

C2

Let the laptop use the office PC's AI power

On the office PC, in PowerShell:

```
powershell -ExecutionPolicy Bypass -File D:\NEKO\app\scripts\share-gpu.ps1
```

Now, whenever the office PC is on, the laptop automatically thinks with the office PC's bigger AI.

C3

Link the two Nekos

On the office PC: Command Center → Phone → **Let my other PC connect** and copy the code. On the laptop: Command Center → Phone → **Connect to my other PC** and paste it. Then the laptop can answer:

"what can the office PC do that you can't?" "on the office PC, run Print SOFT"

C4

Phone calls

Command Center → Phone → **Turn on calls** → **Send call link to my phone**. Tap the link on the phone and talk to her like a phone call (earbuds and smart glasses work too).

Safe by design: nothing here opens the computer to the internet. Only devices signed in to **your** Tailscale account can reach it, and each connection also needs its own secret key.

AFTERWARDS

Updates and if something goes wrong

Updates (one click)

When a new version is published, the office Neko says *An update for me is ready*. Click the small Neko icon near the clock → **Install update**. She makes a backup, updates, tests herself, and **goes back automatically** if anything fails. Her memory, phones and keys are never touched.

Troubleshooting

What you see	What to do
The installer stopped with a red message	Read the message, fix it (often: no internet), then double-click **INSTALL.cmd** again. It continues where it stopped.
'Your NVIDIA driver is too old'	Install the newest driver from nvidia.com, restart, run the installer again.
Not enough disk space	Free some space, or run it with smaller models: in PowerShell `.\install.ps1 -Models light` (about 18 GB).
The orb doesn't appear	Double-click the **Nova/Neko** icon on the Desktop. Or restart the PC.
She doesn't hear me	Check the microphone in Windows sound settings; speak after saying her name clearly.
'bot key used by another PC'	Make a NEW bot for this PC in @BotFather and paste its key in Command Center → Phone → 1.
Phone pairing code expired	Command Center → Phone → **Pair my phone** for a fresh code.
Call page says 'Can't reach Neko'	The PC is off/asleep, or Tailscale isn't connected on the phone.

Removing Neko

Delete the folder `D:\NEKO`, the folder `%LOCALAPPDATA%\NEKO` (her memory) and the Desktop shortcut. In @BotFather you can send `/deletebot` to remove the phone bot too.