Writing Custom Signatures for the Cisco Intrusion Prevention System

Contents

Introduction

Signature Development Lifecycle

Research the Vulnerability

Determine Patterns in Malicious Traffic

Develop the Signature

IPS Engine Overview

Regular Expressions

Signature Configuration on Cisco IPS

Cloning a Signature

Test the Signature

Unit Testing

Real Network Traffic Test

False Positives

False Positive Example

False Negatives

False Negative Example

Examples of Real Cisco IPS Signatures

Cisco IPS Signature: Null Byte In HTTP Request (5170/0)

Cisco IPS Signature: phpMyAdmin PHP Code Injection Vulnerability (26040/0)

Custom Signatures to Detect Yahoo! Messenger Activity

Detect Yahoo! Messenger Login

Detect Yahoo! Messenger Send and Receive Message

Snort Comparison

Introduction

Content and Perl-Compatible Regular Expressions vs. Cisco IPS Regular Expressions

Depth/Offset vs. Min/Max Match Offset Length

Examples

Example 1: TCP Streams

Example 2: UDP Packets

Example 3: Distance vs. Minimum Spacing

Example 4: HTTP Header

Example 5: Non-Payload Detection Rule Options

Example 6: Flowbits vs. Meta

Introduction

This paper provides instruction in creating signatures for the Cisco Intrusion Prevention System (IPS).

Signature Development Lifecycle

The signature development lifecycle has the following steps:

- · Research the vulnerability
- · Develop the signature
- · Test the signature

Research the Vulnerability

During the vulnerability research step, the signature developer essentially thinks like a potential attacker and gains the knowledge necessary to exploit the vulnerability. The idea is that understanding the vulnerability will allow the signature developer to protect against attempts to exploit that vulnerability. Ideally, the signature developer will have actual exploits and have knowledge of the full range of attack vectors. Various sources can be used to gather this information. These include the following:

- · Vendor security advisories
- Security forums (such as Bugtraq and Full Disclosure)
- · Reverse engineering vendor patches
- · Tools such as Metasploit

Determine Patterns in Malicious Traffic

After the developer has an understanding of an attack, the information is used to get insight into how malicious traffic looks as it traverses the network. At the end of this step, the developer should have answers to these types of questions:

- What protocols are relevant to the attack?
- · What fields of the relevant protocols are used in attacks?
- · What values are used for these fields when an attack is being launched?

False positives: The developer should determine whether the malicious traffic appears in normal network communication. If it does, there is the potential for the signature to generate an alert that is a *false positive*. A false positive exists if a signature that is written to detect a particular threat generates alerts based on benign traffic.

False negatives: Ideally, a signature will detect all possible attacks that successfully exploit the relevant threat. If the signature does not detect a particular attack, missing the attack is termed a *false negative* for that threat.

Develop the Signature

IPS Engine Overview

Cisco IPS uses signature engines to inspect traffic. A signature engine decodes protocols and exposes elements of those protocols to signature developers through engine parameters. Signature developers can use engine parameters to inspect specific protocol fields to detect malicious traffic. Perhaps the most important signature engine parameters are those that use regular expressions (regexes). This document includes a section that discusses Cisco IPS regular expressions. The guide *Installing and Using Cisco Intrusion Prevention System Device Manager 7.0* provides in-depth documentation of Signature Engines.

The three most-used engines are the String TCP, Atomic IP, and Service HTTP engines. The following sections provide details about these engines and summarize the most important information you will need to get started producing signatures quickly.

String TCP Engine

The String TCP engine allows users to inspect TCP payload. The following table documents other useful engine parameters:

Table 1. Select String TCP Engine Parameters

Parameter	Description
Direction	This parameter can be set to <i>to-service</i> or <i>from-service</i> . If the goal is to inspect traffic that is going to a host that sends the initial SYN when establishing a TCP connection, Direction should be set to <i>from-service</i> . If the goal is to inspect traffic that is coming from the host that receives the initial SYN, the direction should be set to <i>to-service</i> .
Min Match Length	This parameter is used to ensure that the TCP payload that matches a given regex is greater than a given length. Min Match Length measures the length, in bytes, from where a regex starts matching the data to where the match ends.
Exact Match Offset	This parameter is used to specify the exact offset into a TCP stream where a match ends. This is a zero-based offset. In fact, all the offsets are zero based.
Min Match Offset	This parameter is used to specify an offset into the stream that is being inspected. Signatures will generate an alert if the portion of the stream matched by the regex is located after this offset.
Max Match Offset	This parameter is used to specify an offset into the stream being inspected. Signatures will generate an alert if the portion of the steam matched by the regex is located before this offset.

Atomic IP Engine

The Atomic IP engine allows users to inspect the headers and payload of an IP packet. The following table documents useful engine parameters:

Table 2. Select Atomic IP Engine Parameters

Parameter	Description
Specify Layer 4 Protocol	This parameter specifies which Layer 4 protocol to inspect. Options include TCP, UDP, ICMP, and Other.

Specify Payload Inspection	If this parameter is set to yes, users can specify a regex, min match length, min match offset, and max match offset. These parameters function as documented in Table 1.
TCP Flags	See the following section
TCP Mask	See the following section

Atomic IP Engine Parameters: Specify TCP Flag and TCP Mask

You can specify TCP flags and masks in Cisco IPS versions 4.x and 5.x. The formula is as follows:

(packet & mask) == flags

The TCP flags from the packet in question are logically ANDed with the **Mask** parameter and compared against the **TcpFlags** parameter.

In brief, this formula means

- If a flag is not set in the mask, there is no examination for the presence of the flag in the packet.
- If a flag is set in the mask and not in the flags, the flag must not be present in the packet.
- If a flag is set in both the mask and flags, the flag must be present in the packet.

Example: Match All packets with SYN and ACK Flags Set

TcpFlags == SYN|ACK

Mask == SYN|ACK

SYN and ACK are set in the mask and flags because they are required to be set. The signature would fire if any other flags were set in the packet.

Example: Explicitly Match Packets with Just the SYN and ACK Flags Set

TcpFlags == SYN|ACK

Mask == SYN|ACK|RST|URG|PSH|FIN

This mask is necessary to force only the SYN and ACK to be set.

Service HTTP Engine

The Service HTTP engine is used to inspect HTTP headers. It currently does not inspect the content transported over HTTP. The following table documents useful engine parameters:

Table 3. Select Service HTTP Engine Parameters


Parameter	Description
Specify Max URI Field Length, Specify Max Arg Field Length, Specify Max Header Field Length, Specify Max Request Field Length	These parameters are used to apply a length limit to the URI field, Arg field, entire HTTP header, and Request fields. See Figure 1 for a visual representation.
Specify URI Regex, Specify Arg Name Regex, Specify Header Regex, Specify Request Regex	These parameters are used to apply a regular expression to the URI, Arg Name, Header, and Request portion of an HTTP header. See Figure 1 for a visual representation.

Figure 1 shows how the Service HTTP engine parameters are used. Individual arguments are separated by an ampersand (&), whereas the argument name and value are separated by one equal sign (=).

Figure 1. HTTP Engine Parameters

User Input: http://10.20.35.6/twiki/bin/search?userid=100&username=admin

Browser output:



Other Engines

Cisco IPS provides numerous additional engines. Examples include Service DNS, Service SMB Advanced, and Fixed TCP. For a full list of engines, see the <u>Signature Engines</u> section of *Installing and Using Cisco Intrusion Prevention System Device Manager 7.0*.

Choosing the Best Engine

At times, it is obvious which engine should be used. For example, if a signature is being written to detect an exploit that targets a vulnerability in the SMB protocol, it make sense to use the Service SMB Advanced engine. However, sometimes it is possible to use several engines to detect certain threats. Following are some questions that will aid this decision-making process:

Q. Can an engine inspect the type of traffic necessary?

A. If the engine cannot detect the type of traffic in question, it is eliminated from the list of possible engines. For example, if a vulnerability is exploited via UDP, the String TCP engine is irrelevant because it cannot inspect UDP traffic.

Q. Does an engine provide access to a particular protocol's fields via engine parameters?

A. If the engine decodes a particular protocol, it may make it easier for the signature developer to write a particular signature. For example, a signature can be written to detect a pattern in SMB traffic using the String TCP traffic because TCP is often used to transport SMB. However, the SMB Advanced traffic exposes particular portions of the SMB protocol via engine parameters. Thus, it may be easier to use the SMB Advanced engine instead of the String TCP engine.

Regular Expressions

Cisco IPS uses regular expressions to define rules to match malicious or unwanted behavior over the network. All the different engines in Cisco IPS support regular expressions. Here are some basic examples.

Square Brackets

To match the exact word hello, you would use the following string:

hello

Which expression would you use, however, if the first character of this word could be uppercase or lowercase?

[hH]ello

Square brackets allow you to specify different possibilities within a single expression. In this case, [hH]ello basically means hello or Hello. These brackets will match if one single character out of the set specified in the brackets matches the expression.

To match the word *hello* in any form, no matter whether any single letter uses uppercase or lowercase, the regular expression has to be modified. The correct form would be as follows:

[hH][eE][lL][lL][oO]

This expression will match heLLo or HeLIO or hELLO (and so on).

Could you just use the expression [hHeElLILoO]? Because square brackets and their content can represent only a single character, the content of these brackets would match the single letter h, e, l, or o spelled using uppercase or lowercase. Therefore, this expression is not the same as [hH][eE][IL][IL][oO].

The OR Operator

You can also match either of two variants, such as *document* or *file*, with a single expression. This is where the OR operator comes into play. This operator is represented by the single character |, also called a *pipe*. It allows you to match either one possibility or the other. The regular expression in question would look like this: *document|file*.

The NOT Operator

Sometimes you need to specifically exclude one or more characters in a regular expression. Common examples are signatures that may trigger only if a certain character is not found at a certain position or within a certain range. To exclude one or more characters, you can use the circumflex character. As a first example, here is a regular expression for the letter A not followed by the letter B: A[^B].

You can also use this expression to deny more than one letter. If A must not be followed by C or D, here is the expression: A/^CD].

Ranges

How do you write a regular expression for a single letter that is followed by a number that is 0 through 9?

First Try

Because you do not know which letter of the alphabet will be followed by which number, you will have to match all of them. For the sake of convenience, the example will be lowercase. Here is one possibility to accomplish this goal:

[abcdefghijklmnopgrstuvwxyz][0123456789]

This expression will do the job. Two sets of brackets equal two characters, one a lowercase letter, one a number that is 0 through 9. The expression is correct, just not very convenient.

Second Try

Regular expressions allow for the definition of ranges of characters or numbers, which comes in very handy for matching an expression like this one. Instead of [0123456789], the following expression will do the same job: [0-9].

This technique will also work for letters. Here is the alphabet, in short: [a-z].

And here is a regular expression that will match the same two-character string as the one in the first try: [a-z][0-9].

How would you match the letter if it could be uppercase or lowercase? You need to use a single square bracket set to match the lowercase and uppercase alphabet. Here is a modification of the first part of the expression that matches the new requirements: [a-zA-Z].

Grouping Expressions

A preceding example explained the OR operator and how to apply it to match one word or another. But how would you distinguish between parts of words? How would you make sure the regex parser knows which fragments to use with the OR operator? Does abc|def mean abc OR def? Or does it mean ab followed by the letter c OR d followed by ef? What if the requirement was to match a when it is followed by bc OR de, followed in turn by f?

Parentheses can clarify expressions. They allow you to group expressions to clearly define where one expression ends and another starts. This way you can safely and easily differentiate between the different sets:

- (abc)|(def) equals abc OR def
- ab(c|d)ef equals ab followed by the letter c OR d followed by ef
- a((bc)|(de))f equals a followed by bc OR de followed in turn by f

Escaping Characters

So far it was shown that parentheses, square brackets, and the pipe are special characters. But what if you need to match a string that contains one of these characters? There are three possible solutions:

Include the character to match in square brackets: Examples follow:

- []] matches the pipe. The expression abc[]]def matches the string abc|def.
- [[] matches the opening bracket. The expression AA[[]BB matches the string AA[BB.

Escape the character as you would in UNIX by using the backslash character: Examples follow:

- \| matches the pipe. The expression abc\|def matches the string abc|def
- \[matches the opening bracket. The expression AA\[BB matches the string AA[BB.

Use the hexadecimal representation: Every character has a hexadecimal number, commonly referred to as the hex code, that may be used at any time instead of the real character. To notify the regex parser of upcoming hexadecimal representations, place the two-letter combination w before each

hex code. For example, \(\lambda 41 \lambda 42 \lambda 43 \) is the same as \(ABC \).

Counting

Continuation

What if the length of a certain string was unknown? In this example, you know only that the string starts with an A, it is followed by one or more As, and it ends with the letter B. You may try this:

```
AAB | AAAB | AAAAB | ...
```

Not very effective, right? That is why there are two special wildcard operators: the plus (+) and the asterisk (*). The plus operator signifies that one or more of the previous expressions will follow, whereas the asterisk means that zero or more of those expressions will follow. Keep in mind that these operators will not stop matching, so be sure to terminate them by adding a terminal expression (such as the *B* in the following examples). In this case, the following expressions match all the preceding examples in this section, and many more:

- A+B matches at least one A, or many more, followed by B
- AAA*B matches AA followed by zero or more As followed by B

Whereas the expression a^* means zero or more, up to many, occurrences of a, the expression a^* means that there is at least one a, but there could also be more. The expression a^* is equivalent to aa^* .

Regular expressions that end with a plus or asterisk should be set to **fire-once** to ensure that they do not go off for every single matching following character after they have fired the first time.

Potentially Missing Expressions

Sometimes a regular expression could be written to match data sets that differ by a slight margin, if only one part of the expression could be rendered ineffective in certain cases. This problem can be solved by applying the question mark (?) operator. If used in an expression, this operator indicates that the expression right before the question mark might be applied, but it does not have to be.

Here is a simple example. Anton has a sister, Antonia. The only way of writing one expression that properly matches both their names is with the question mark operator because it allows the matching of the last two letters in Antonia's name to be conditional. Here is an example expression:

Anton(ia)?

This expression matches Antonia as well as Anton because the characters in the parentheses do not have to be applied for a match to occur.

Signature Configuration on Cisco IPS

IPS Device Manager Overview

There are multiple options for modifying the signature configuration on the IPS sensor. The easiest method to begin with uses the IPS Device Manager (IDM) utility.

IDM is a Java-based web tool that implements a graphical user interface (GUI) that you can use to configure a Cisco IPS device.

The first step to using IDM is installing the software. Begin the installation by directing a Java-enabled web browser to the Cisco IPS device on port 443:

https://<IP of IPS device>/

You will see a web page that offers to install IDM.

Figure 2. IDM Installation Web Page



Click **Run IDM**. You will see a prompt to perform a Java Web Start installation of the IDM application. For the download to work, ensure that Java Runtime Environment (JRE) is installed. One place to acquire this software is the Sun area of the Oracle website. (http://www.oracle.com/us/sun/).


After Java Web Start runs, IDM will be installed on your computer and a Launcher login screen will appear (see Figure 3). The credentials for this prompt were configured when the IPS device itself was set up.

Figure 3. IDM Launcher Login Screen



After you complete the login process, you will see the IDM interface. Initially the dashboard will be displayed. This dashboard shows statistics about the health and configuration of the IPS device. Click **Configuration** in the top menu bar to move to the IPS device configuration screen.

Figure 4. Configuration Button in the IDM Dashboard




From here, click Policies in the bottom left (as shown in Figure 5), then click All Signatures to navigate to the signature page.

Figure 5. Policies Button in the IPS Device Configuration Screen



The signature view (see Figure 6) allows you to perform a variety of tasks on the existing signature set, including enabling/disabling signatures and adding/deleting signatures. You can also use the **Clone** button to create a copy of an existing signature.

Figure 6. IDM Signature Page



(Click for larger image)

Signature Creation Demonstration

Now that you are familiar with the basics of IDM, you can look at the process of using it to enter a signature onto the IPS sensor itself.

For the sake of this demonstration, you will enter a signature that looks for the regular expression [A-D][A-B][A-C]a+ sent to a server on TCP port 6060. You will also restrict this signature to looking at the first 5,000 bytes of the TCP stream.

To begin entering this signature, click **Add** on the signature page.


Figure 7. Add Button in IDM Signature Page



You will see a dialog box that contains fields for each parameter of the signature. Begin by populating the **Signature Name** and **Alert Notes** fields with the data that should be displayed when the signature fires.


The next step is to select the required engine. You will then see the appropriate fields for the selected engine. For the signature described for this demonstration, choose the String TCP engine (see Figure 8).

Figure 8. Choosing the String TCP Engine in the Add Signature Dialog Box




Now that the fields for the engine are visible, you can populate them with the values for the demonstration signature. Enter the regular expression into the **Regex String** field, and enter the port number in **Service Ports**. Leave **Direction** set to the default (To Service) because the demonstration signature should fire on traffic that is traveling to TCP port 6060. To match the first 5,000 bytes, set **Max Match Offset** to the value 4999, accounting for the fact that this field offsets from zero. Figure 9 shows the completed fields.

Figure 9. Engine Settings in the Add Signature Dialog Box



After you have entered the engine parameters, click **OK**. The dialog box will close, but the signature will not be pushed to the actual sensor until you click **Apply**. After you apply the changes, you will see the following message window, indicating that the signature is being pushed to the sensor.

Figure 10. Applying the Signature to Push It to the Sensor



After the update process has finished, the signature has been applied to the sensor and is now active.

IPS Command-Line Interface

For some cases, it may be faster to use the IPS command-line interface (CLI) instead of launching IDM to create or modify a signature. The CLI also allows you to perform batch processing of a large number of custom signatures, which is not covered in this paper. If you have some knowledge of the Cisco IOS CLI, these processes should not be difficult.

Entering an Individual Signature Using the CLI

Access the IPS CLI by entering the IP address of the IPS device in your SSH client (such as OpenSSH or Putty). Log in as the user cisco.

After you have logged in to the device, enter the following command to put the CLI into configuration mode:

```
ipsdevice# conf t
ipsdevice(config)#
```

Now you can begin to enter the signature. This demonstration will use the same signature described in the IDM example. The signature uses the String TCP engine and looks for the regular expression [A-D][A-B][A-C]a+ traveling to TCP port 6060. The Max Match Offset will be 4999 again.

To begin the process of entering the signature, enter the context of the appropriate signature definition. By default, this context is *sig0*, which is entered with the following command:

```
ipsdevice(config)# service signature-definition sig0
ipsdevice(config-sig)#
```

Next, enter a signature ID for the signature. For this example, use 61101, which is unlikely to be in use. Use the following command to begin editing signature 61101:

```
ipsdevice(config-sig)# signatures 61101 0
```

Now that you are in the context of signature 61101, you need to populate the attributes for this signature, starting with the signature name. The name is in the sig-description context, so enter the **sig-description** command, then enter the **sig-name** command followed by the signature name.

```
ipsdevice(config-sig-sig)# sig-description
ipsdevice(config-sig-sig-sig)# sig-name Test Signature
ipsdevice(config-sig-sig-sig)# exit
```

Next, select the engine for the signature and populate its parameters. In this case, you will use the String TCP engine:

```
ipsdevice(config-sig-sig)# engine string-tcp
```

You can then enter the signature parameters:

```
ipsdevice(config-sig-sig-str)# regex-string [A-D][A-B][A-C]a+
ipsdevice(config-sig-sig-str)# service-ports 6060
ipsdevice(config-sig-sig-str)# specify-exact-match-offset no
ipsdevice(config-sig-sig-str-no)# specify-max-match-offset yes
ipsdevice(config-sig-sig-str-no-yes)# max-match-offset 4999
```

Finally, enter the exit command multiple times to exit each step in the process:

```
ipsdevice(config-sig-sig-str-no-yes)# exit
ipsdevice(config-sig-sig-str-no)# exit
ipsdevice(config-sig-sig-str)# exit
ipsdevice(config-sig-sig)# exit
ipsdevice(config-sig)# exit
ipsdevice(config)# exit
```

The IPS device will prompt you to save the changes. If you reply yes to this prompt, the signature will be updated on the device.

```
Apply Changes?[yes]: yes
Processing config: /
```

Cloning a Signature

Administrators often find the need to modify a signature to meet the needs of a specific network, such as to reduce false positives or false negatives. In such cases, the first approach should be to fine tune signature parameters such as event action filters and override policies. If these tunings are not sufficient, the last action that is available is to modify a signature. By default, signature parameters such as the regular expression cannot be modified. The signature must first be cloned in order to modify such signature parameters. The original signature can be retired or disabled if it is determined that it is no longer required.

How to Clone a Signature


Cloning a signature results in an exact copy of the signature. To clone a signature, go to **Configuration > Policies > Signature Definitions**, select the signature that needs to be cloned, and click the **Clone** button (as shown in Figure 11).

Figure 11. Clone a Signature



You will see a new window with the signature details of the signature that is being cloned (as shown in Figure 12).

Figure 12. Clone Signature Parameters



"Clone" will be appended to the new signature name by default. The signature ID field defaults to the custom signature ID range (greater than 60000). This value can be changed to any unique value within this range. Make changes to the sub sig id if needed. The rest of the signature parameters—including Signature Engine, Regex, Offsets, and all other signature parameters—will be a copy of the signature being cloned. Make changes as necessary and click **OK** to close the dialog box. To push the changes to the sensor, click **Apply**. This will push the new configuration to the sensor.

The following fields cannot be cloned:

- Obsoletes
- · Protected parameters
- · Hidden parameters
- Cisco Security Monitoring, Analysis, and Response System (MARS) category

If a signature that is retired and disabled by default is cloned, the new signature will be enabled and unretired.

Hidden and Protected Signature Parameters

Some of the default signature parameters are hidden and protected. These parameters are not visible through IDM or the IPS CLI. Such signature parameters cannot be modified or cloned. This limitation applies to components of a meta signature as well as components of the Multi String engine.

Test the Signature

Testing validates the signature. Many of the testing steps are performed iteratively with signature development steps. Cisco strongly recommends using **produce-verbose-alert** *event-action* for custom signatures, especially for the testing phase.

For illustrative purposes, this section examines a signature that detects traffic that attempts to contact command-and-control servers for a botnet.

Hosts that are infected with the associated malware create an HTTP header that looks like the following:

```
GET /image.png HTTP/1.0
User-Agent: evil-software/3.2
Accept: */*
Host: example.org
Connection: Keep-Alive
```

Researching this issue revealed that hosts that are infected with the malware send an HTTP GET request to example.org with a User-Agent string of evil-software/3.2. Thus, the (example) signature for detecting this traffic would use the Service HTTP engine and have the request regex set to User-Agent:\\\\x20evil-software\\\\\x2f3\\\\\x2e2. The following example is the complete signature configuration displayed from the IPS CLI. You could also view this information in IDM.

```
IPS-4240# configure terminal
IPS-4240(config)# service signature-definition sig0
IPS-4240(config-sig)# signatures 60023 0
IPS-4240(config-sig-sig)# show settings
  sig-id: 60023
  subsig-id: 0
    alert-severity: high default: medium
    sig-fidelity-rating: 95 default: 75
    promisc-delta: 0 <defaulted>
    sig-description
       sig-name: Botnet command and control traffic default: My Sig
       sig-string-info: User-Agent: evil-software/3.2 default: My Sig Info
       sig-comment: Sig Comment <defaulted>
       alert-traits: 0 <defaulted>
       release: custom <defaulted>
       sig-creation-date: 20000101 <defaulted>
       sig-type: Other <defaulted>
    engine
           _____
         event-action: produce-alert <defaulted>
         de-obfuscate: true <defaulted>
         max-field-sizes
            specify-max-uri-field-length
              no
            specify-max-arg-field-length
              no
              _____
            _____
            specify-max-header-field-length
              _____
            specify-max-request-length
               _____
            ______
         regex
            specify-uri-regex
              no
            specify-arg-name-regex
              nο
```

```
specify-header-regex
            no
            ______
          specify-request-regex
              request-regex: User-Agent:\x20evil-software\x2f3\x2e2
              specify-min-request-match-length
                ______
        service-ports: #WEBPORTS
        swap-attacker-victim: true default: false
       ______
    event-counter
      event-count: 1 <defaulted>
      event-count-key: AxBx default: Axxx
      specify-alert-interval
       no
        ______
      summary-mode
        summarize
          summary-interval: 15 <defaulted>
          summary-key: Axxx <defaulted>
          specify-global-summary-threshold
            ______
      _____
    status
      enabled: true <defaulted>
      retired: false <defaulted>
      obsoletes (min: 0, max: 65535, current: 0)
    vulnerable-os: general-os <defaulted>
    specify-mars-category
      ves
      _____
       mars-category: Info/Misc <defaulted>
      ______
    _____
IPS-4240(config-sig-sig)#
```

Unit Testing

Unit testing entails creating the signature on a sensor and replaying traffic through the sensor to ensure that the signature fires as expected.

Cisco captured traffic from a host infected with the malware in the lab. It is also possible to simulate additional pcap files for testing purposes. For example, you can use **wget** -U "evil-software/3.2" example.org/image.png to send an HTTP request to example.org with the User-Agent string set to

evil-software/3.2. It is often necessary to create traffic samples to test signatures. The following code snippet shows how to generate and capture this traffic.

```
$ tshark -w sample_traffic.pcap host example.org
```

Run wget from a different terminal:

```
$ wget -U "evil-software/3.2" example.org/image.png
```

When the **wget** command execution is complete, TShark will have created a pcap file that contains sample traffic you can use to test the signature. You can use the **tcpreplay** command to replay the test traffic to the IPS device to test the signature:

```
$ tcpreplay -i eth0 sample_traffic.pcap
```

You can check the IPS device to verify that the signature fired:

```
IPS-4240# show events alert
evIdsAlert: eventId=1287597699201549604 severity=high vendor=Cisco
  originator:
   hostId: TPS-4240
   appName: sensorApp
    appInstanceId: 9803
  time: 2010/11/12 22:42:18 2010/11/12 22:42:18 UTC
  signature: description=Botnet command and control traffic id=60023
       created=20000101 type=other version=custom
    subsiqId: 0
    sigDetails: User-Agent: evil-software/3.2
    marsCategory: Info/Misc
  interfaceGroup: vs0
  vlan: 0
  participants:
    attacker:
      addr: locality=OUT 192.0.32.10
      port: 80
    target:
      addr: locality=OUT 64.101.177.162
      port: 51099
      os: idSource=unknown relevance=relevant type=unknown
  actions:
    denyPacketRequestedNotPerformed: true
    denyFlowRequestedNotPerformed: true
  context:
    fromTarget:
000000 47 45 54 20 2F 69 6D 61 67 65 2E 70 6E 67 20 48 GET /image.png H
000010 54 54 50 2F 31 2E 30 0D 0A 55 73 65 72 2D 41 67 TTP/1.0..User-Ag
        65 6E 74 3A 20 65 76 69
                                   6C 2D 73 6F 66 74 77 61
                                                             ent: evil-softwa
000030 72 65 2F 33 2E 32 0D 0A 41 63 63 65 70 74 3A 20 re/3.2..Accept:
000040 2A 2F 2A 0D 0A 48 6F 73 74 3A 20 65 78 61 6D 70 */*..Host: examp
000050 6C 65 2E 6F 72 67 0D 0A 43 6F 6E 6E 65 63 74 69 000060 6F 6E 3A 20 4B 65 65 70 2D 41 6C 69 76 65 0D 0A
                                                              le.org..Connecti
                                                             on: Keep-Alive..
000070 OD 0A
  riskRatingValue: attackRelevanceRating=relevant targetValueRating=medium 100
  threatRatingValue: 100
  interface: ge0 0
  protocol: tcp
```

Unit testing can also involve testing for false positives. A false positive occurs when a signature fires an alert for traffic that is not malicious. To test for false positives, generate traffic samples for known benign traffic. This testing is particularly useful for signatures that detect malicious traffic that closely resembles benign traffic.

Real Network Traffic Test

Before declaring that a signature is ready for production use, it is wise to deploy it to IPS devices that inspect real-world traffic. This test gives signature developers an opportunity to tune signatures if needed and provides an additional layer of false-positive testing.

False Positive

A false positive occurs when legitimate network activity is interpreted and reported as an attack. This happens when network activity meets criteria that were specified to identify an attack. A false positive can be addressed by tuning the sensor configuration by disabling or retiring the signature or developing a higher-fidelity signature when possible.

The original version of Signature 5916-0 detects the URL Handler vulnerability on return web ports with the following regex:

[\x22\x27](([Mm][Aa][li][Ll][Tt][Oo])|([Nn][Nn][Tt][Pp])|([Ss]?

This is intended to detect attacks of the following form:

mailto:%00../../../windows/system32/cmd.exe

The following alert is a false positive that triggers the preceding signature:

```
0000
      43 6c 61 69 6d 20 66 6t
                                 72 6d 73 20 6d 75 73 74
                                                            Claim to rms must
                                    61 72 6b 65 64 20 62
0010
      20 62 65 20 70 6f
                         73 74
                                 6d
                                                             be post marked b
0020
      79 20 44 65 63 65 6d 62
                                 65
                                   72 20 33 30 2c 20 32
                                                             y Decemb er 30, 2
                                 72 65 63 65 69 76 65 64
0030
      30 31 30 20 61 6e 64 20
                                                            010 and received
0040
      20 62 79 0d 20
                      20 20
                                 20 20 20
                                          20 4a 61 6e 75
                            20
                                                             by.
                                                                          Janu
0050
      61 72
            79
               20
                   33
                      30
                         2c
                            20
                                 32
                                    30
                                       31
                                          31
                                             2e
                                                 3c
                                                    62 72
                                                            ary 30,
                                                                      2011. <br
      20 2f
                                                    20 4f
               0d 20
                         20
                            20
                                    20
                                       20
0060
            3e
                      20
                                 20
                                          20
                                             37
                                                 2e
                                                              />.
0070
      72 64 65
               72
                  73
                      20 61
                            72
                                 65
                                    20 6f
                                          72 64 69
                                                   6e 61
                                                            rders ar e ordina
0080
      72 69 6c 79 20 64
                                   76 65 72 65
                         65
                            6c
                                 69
                                                64
                                                   20 77
                                                            rily del ivered w
0090
      69 74 68 69 6e 20 36
                            2d
                                 38 20 77 65 65
                                                6b 73 2e
                                                             ithin 6- 8 weeks.
00a0
      20 50 6c 65 61
                      73 65
                            20
                                 63 61 6c 6c 20 31 2d 38
                                                             Please call 1-8
                     34
00b0
      37
         37
            2d 38 38
                         2d 30
                                 30 34 38 0d 20
                                                20 20 20
                                                            77-884-0 048.
                                                            or e mail <a
href="ma ilto:%20
00c0
      20
         20
            20 20
                   6f
                      72
                         20
                            65
                                 6d
                                    61
                                       69
                                          6c
                                             20
                                                 3c
                                                    61
                                                       20
         72 65 66 3d
                                          6f
                                                   32 30
00d0
                      22
                         6d
                                 69 6c
                                       74
                                             3a 25
      68
                            61
                                                            mitsubis hi@links
00e0
      6d 69 74 73 75 62
                         69
                            73
                                 68 69 40 6c
                                             69 6e 6b
                                                       73
00f0
      75 6e 6c 69 6d 69 74 65
                                 64 2e 63 6f
                                             6d 25 30 30
                                                            unlimite d.com%00
      fd 85 c1 c1 b1 a5 8d 85
                                 d1 a5 bd b8 bd e1 b5 b0
0100
                                                c0 b8
0110
      ed c4 f4 c0 b8 e4 b0 a8
                                 bc a8 ed c4 f4
                                                       e0
                                                       9d
         29 05 8d 8d 95 c1 d0
                                       85 b9 9d d5
                                                   85
                                                            4)......
0120
      34
                                 b5
                                    31
                                    95 b8 ed c4
                                                    c0 b8
0130
      94
         e8 81 95 b8 b5 d5
                            CC
                                 b1
                                                f4
                                                               . . . . . . . . . . . . .
0140
      d4 34 29 05 8d 8d 95 c1
                                 d0 b5 15 b9 8d bd 91 a5
                                                             .4)....
0150
      b9 9c e8 81 9d e9 a5 c0
                                 b1 91 95 99 b1 85 d1 94
```

The fix for the above false positive is to remove the percent sign (%) from the wildcarded character class, which results in a signature with higher fidelity.

The corrected regex follows:

 $[\x22\x27](([Mm][Aa][Ii][LI][Tt][Oo])|([Nn][Nn][Tt][Pp])|([Ss]?$

 $[Nn][Ee][Ww][Ss])|([Tt][Ee][L][Nn][Ee][Tt])|([Ff][li][Rr][Ee][Ff][Oo][Xx][Uu][Rr][Ll])|([Ff][li][Rr][Ee][Ff][Oo][Xx][Hh][Tt][Mm][Ll]))[:][x21\\x23\\x24\\x26\\x28\\x7f]^*[\%]((x30\\x30)|(x2e\\x2e\\x2f))$

Notice the change in the wild card character class from [x21x23-x26x28-x7f] to [x21x23x24x26x28-x7f].

False Negative

A false negative occurs when an attack is not detected. Tuning the sensor configurations will help to decrease the number of false negatives.

False Negative Example

Signature 11020-0 detects BitTorrent client activity. The regex of the initial signature follows:

Because BitComet traffic does not contain 0s after "bittorrent," the signature causes a false negative condition. The following is a modified version of the signature:

^[x13][Bb][li][Tt][Tt][Oo][Rr][Rr][Ee][Nn][Tt][\x20][Pp][Rr][Oo][Tt][Oo][Cc][Oo][Li]

Examples of Real Cisco IPS Signatures

The previous examples explained the techniques for developing a signature for Cisco IPS. A case study of some existing signatures will further extend that understanding.

Cisco IPS Signature: Null Byte In HTTP Request (5170/0)

The first existing signature to examine is 5170/0 (Null Byte In HTTP Request). This signature is designed as a generic method of flagging an HTTP request as possibly malicious. It is based on a vulnerability class rather than a specific vulnerability.

In some web applications, input data will be URI escaped; any characters that take the form %{hex code} will be translated into the equivalent literal

character. For example, the escape code %20 will translate into a literal space character.

A NULL byte injection attack takes advantage of escape code translation. A poorly written web application may not account for the way in which translation changes the NULL byte. In the URI-encoded form, a NULL byte is simply the string %00 and has no effect on the string. However, after an application unescapes the string to its original form, k00, it can be treated by low-level applications as a string termination character.

Signature 5170/0 was created to help mitigate these NULL byte termination attacks. This signature was written using the Service HTTP engine because the signature examines

- to-service traffic to a web server
- The URI

This signature uses the *specify-uri-regex* parameter to supply a regular expression that can be matched against the URI. The regular expression in the signature is 1%00.

The service HTTP engine also has a *de-obfuscate* option. With de-obfuscation turned on, URI-encoded data will be converted back to literal values before the regular expression is matched. However, this option is not turned off for this signature because the original (undecoded) buffer is also tested with the regular expression. This means the signature will also catch double decoding problems.

Cisco IPS Signature: phpMyAdmin PHP Code Injection Vulnerability (26040/0)

The next signature to examine is 26040/0. Rather than being a generic signature to catch a vulnerability class, this signature is more specific to a particular vulnerability: CVE-2009-1151.

This vulnerability is in the phpMyAdmin PHP administration system. After the application is installed, the *setup.php* script remains on the system. This script has permissions that allow anyone to create and execute a PHP script on the web server.

To detect this vulnerability over the network, the signature developer must first isolate the problem to its base elements. This analysis will show that an attacker must execute the script on the web server in the directory /scripts/, and that the name of the script is setup.php.

To detect this behavior, the signature can use the Service HTTP engine and, in the *specify-uri-regex* field, use the regex [Ss][Cc][Rr][Ii][Pp][Tt][Ss][Ss][Ee][Tt][Uu][Pp][.][Pp][.][Pp][.][Pp][.][Pp]. This is exactly what Cisco IPS signature 26040/0 does. However, this behavior by itself would cause the IPS to generate a false-positive alert when this application is set up correctly. Because of this fact, additional criteria are needed to detect this vulnerability.

The code injection vulnerability exists when the application parses the configuration HTTP variable. This information leads to the second criterion. To ensure sure this variable is being inspected, the *specify-arg-name-regex* parameter is used. To make sure the signature catches any particular case, it can use the following regular expression [cC][Oo][Nn][Ff][Ii][Gg][Uu][Rr][Aa][Tt][Ii][Oo][Nn].

However, this new criterion is also not specific enough and would fire on legitimate uses of the setup script. The final step to add to this signature is detection of the actual characters that trigger the vulnerability. The characters that are used in public exploits for this vulnerability are "Host']=" followed by the payload that is to be injected into the configuration file. This input will break out of the data definition in the file and cause the payload to execute.

To trigger on this information, the *specify-arg-value-regex* parameter is used, which ensures that the signature detects injection of the malicious payload into the *CONFIGURATION* variable and nothing else. For this signature, the regular expression \(\frac{\cute{22[Hh][Oo][Ss][Tt]\cute{27\cute{27}\cute{2

The details about this signature show that Cisco IPS engines provide a precise way to stipulate exactly which traffic is to be inspected by the regular expression, which reduces the chance of false positives and provides a more accurate signature base.

Custom Signatures to Detect Yahoo! Messenger Activity

Observation of the network traffic during the login process of a Yahoo! Messenger client indicates that the stream always starts with *YMSG*, followed by 2 bytes for version, followed by 2 random bytes and then 2 bytes for packet length. The subsequent 2 bytes indicate activity. The information from these 2 bytes, along with the service ports, indicates the type of activity.

Detect Yahoo! Messenger Login

The Yahoo! Messenger client speaks to the Yahoo! server from a random high port to port 5050. The Yahoo! Messenger client login has a challenge-response sequence. The connection starts to/from port 5050, and the 2 bytes that indicate this activity are \(\lambda 00\lambda 4c\), which are \(\section \text{everify}\). This is followed by a response with service bytes \(\lambda 00\lambda 57\), which are the service authorization. After successful negotiation, the client sends service bytes \(\lambda 00\lambda \text{v00\lambda v054}\) to port 5050. Use the String TCP engine to detect this activity.

The network packet trace of the login activity is illustrated below:

```
00000036
          59 4d 53 47 00 0c 00 00
                                       00 dc 00 54 5a 55 aa 55 YMSG.... ... TZU.U
                                                     54 3d 61 37 ....6..r =j8,T=a7
           00 00 00 00 36 c0 80 72
00000046
                                        3d 6a 38 2c
                                       6e 6d 3b 4f 3d 66 38 2c ;r=63,w= nm;0=f8,
           3b 72 3d 36 33 2c 77 3d
00000056
                                       69 3b 53 3d 63 36 3b 54 C=86;Q=F i;S=c6;T
00000066
           43 3d 38 36 3b 51 3d 46
           3d 62 38 3b 52 3d 70 32 2c c0 80 39 36 c0 80 6d =b8; R=p2 ,..96..m
00000076
           3d 6a 46 2c 57 3d 67 6a
6a 31 2c 77 3d 70 61 2c
                                       3b 72 3d 6a 61 3b 4b 3d =jF,W=gj ;r=ja;K=
00000086
                                       4c 3d 46 6a 2c 45 3d 61 j1,w=pa, L=Fj,E=a
3d 6c 68 3b 54 3d 39 6d h;L=pB,C =1h;T=9m
00000096
           68 3b 4c 3d 70 42 2c 43
000000A6
                                       64 6c 5f 64 75 6d 62 c0 ,..0..tw dl_dumb.
5f 64 75 6d 62 c0 80 31 .2..twdl _dumb..1
           2c c0 80 30 c0 80 74 77
000000В6
00000006
          80 32 c0 80 74 77 64 6c
          39 32 c0 80 2d 31 c0 80 32 c0 80 31 c0 80 31 c0 92..-1.. 2..1..1.
000000D6
000000E6
          80 74 77 64 6c 5f 64 75
                                       6d 62 c0 80 31 33 35 c0 .twdl_du mb..135.
          80 36 2c 30 2c 30 2c 31
c0 80 33 30 30 c0 80 35
                                       37 35 30 c0 80 31 34 38 .6,0,0,1 750..148
000000F6
00000106
                                        39 c0 80 42 09 33 71 32 ..300..5 9..B.3q2
          34 65 6e 35 30 75 63 6d
                                      72 61 26 62 3d 32 c0 80 4en50ucm ra&b=2..
00000116
```

The following regular expression detects this activity:

[Y][M][S][G][\x00-\xFF]{6}\x00\x54

The preceding regular expression detects ASCII characters Y, M, S, and G followed by any six characters followed by hex \(\cut00\)\(\cut054.\)

The following signature detects this activity:

```
sig-id: 11217
subsig-id: 0
  alert-severity: informational
  sig-fidelity-rating: 85
  promisc-delta: 15
  sig-description
          _____
    sig-name: Yahoo Messenger Logon
    sig-string-info: 00 54
    sig-comment: empty
    alert-traits: 0
    release: S139
    sig-creation-date: 20050127
    sig-type: Anomaly
  engine
    _____
    string-tcp
      event-action: produce-alert
      strip-telnet-options: false
      specify-min-match-length
        no
        _____
      regex-string: [Y][M][S][G][\x00-\xFF]{6}\x00\x54
      service-ports: 5050-5050
      direction: to-service
      specify-exact-match-offset
        no
        ______
          specify-max-match-offset
          ______
            _____
            ______
          specify-min-match-offset
            nο
      swap-attacker-victim: false
  ______
  event-counter
```

```
event-count: 1
  event-count-kev: Axxx
  specify-alert-interval
  summary-mode
     summarize
        summary-interval: 15
        summary-key: Axxx
        specify-global-summary-threshold
           ______
status
  enabled: false
  retired: false
  obsoletes (min: 0, max: 65535, current: 0)
vulnerable-os: general-os
specify-mars-category
     mars-category: Info/UncommonTraffic/Chat
```

Detect Yahoo! Messenger Send and Receive Message

The following illustrates network activity when a send message is initiated by a Yahoo! Messenger client:

```
000001EA 59 4d 53 47 00 0c 00 00 00 5c 00 06 5a 55 aa 56 YMSG....\..ZU.V 000001FA b5 95 d9 b3 31 c0 80 74 77 64 6c 5f 64 75 6d 62 ....1..t wdl_dumb
                                                   6c 79 6d c0 80 31 34 c0 .....wsu lym...14.
0000020A c0 80 35 c0 80 77 73 75
             80 73 65 6e 64 69 6e 67 20 61 20 74 65 73 74 20 .sending a test
0000021A
0000022A
             6d 65 73 73 61 67 65 c0 80 39 37 c0 80 31 c0 80 message. .97..1..
             36 33 c0 80 3b 30 c0 80 36 34 c0 80 30 c0 80 31 63..;0.. 64..0..1 30 30 32 c0 80 31 c0 80 32 30 36 c0 80 30 c0 80 002..1.. 206..0.. 59 4d 53 47 00 0c 00 00 00 62 00 15 00 00 00 00 YMSG.... b..... b5 95 d9 b3 32 31 31 c0 80 4d 73 67 3a 54 6f 74 ....211. Msg:Tot
0000023A
0000024A
0000025A
0000026A
             61 6c 3d 31 09 44 69 73
                                                 70 6c 61 79 3d 31 2c 30 al=1.Dis play=1,0
0000027A
0000028A 2c 30 0a 54 61 62 3a 79 6d 73 67 72 5f 6c 61 75 ,0.Tab:y msgr_lau
0000029A 6e 63 68 63 61 73 74 3d 30 2c 32 36 0a 49 4d 56 nchcast= 0,26.IMV
000002AA 3a 4e 6f 6e 65 3d 31 2c 30 2c 30 2c 30 2c :None=1, 0,0,0,0,000002BA 30 2c 30 0a c0 80 31 30 30 35 c0 80 33 34 35 34 0,0...10 05..3454
```

The stream starts with YMSG followed by six random characters followed by service bytes \(\omega0\)\(\omega0\)\(\omega0.6).

The following regular expression detects this activity: [Y][M][S][G][\x00-\xFF]{6}\x00\x06

The only difference between detecting a *send* message and a *receive* message is the direction of the service ports. Send message traffic is *to-service*, whereas receive message traffic is *from-service*.

The following signature detects Yahoo! Messenger send activity:

```
subsig-id: 0
 alert-severity: informational
 sig-fidelity-rating: 85
 promisc-delta: 15
 sig-description
   sig-name: Yahoo Messenger Send Message
   sig-string-info: 00 06
   sig-comment: empty
   alert-traits: 0
   release: S139
   sig-creation-date: 20050127
   sig-type: Anomaly
      -----
 engine
   string-tcp
          ______
     event-action: produce-alert
     strip-telnet-options: false
     specify-min-match-length
                  _____
       _____
       _____
     regex-string: [Y][M][S][G][\x00-\xFF]{6}\x00\x06
     service-ports: 5050-5050,5101-5101
     direction: to-service
     specify-exact-match-offset
      no
        specify-max-match-offset
          ______
        specify-min-match-offset
          ______
     swap-attacker-victim: false
   ______
 event-counter
   event-count: 1
   event-count-key: Axxx
   specify-alert-interval
              -----
     ______
 _____
 alert-frequency
   ______
   summary-mode
     summarize
      summary-interval: 15
       summary-key: Axxx
       specify-global-summary-threshold
           _____
        _____
        _____
     ______
 _____
```

```
enabled: false
retired: false
obsoletes (min: 0, max: 65535, current: 0)

vulnerable-os: general-os
specify-mars-category

yes

mars-category: Info/UncommonTraffic/Chat
```

Snort Comparison

Introduction

Because of the amount of information available, wide deployment, and open source nature of the Snort community, there has been an ongoing need to convert Snort signatures to be used with Cisco IPS. This section provides an overview of the conversion process.

Users are advised that many of the signatures widely available on the Internet have been developed by administrators who have limited knowledge of IPS signature development. Therefore, these signatures may detect a particular exploit instead of detecting all exploits. They may also consume high resources and need to be continually updated to keep pace with changing exploits. Such signatures should be used with caution.

The following figure is an example of a Snort rule:

Figure 13. Snort Rule Example



A Snort signature consists of the following sections:

Rule actions: The rule action tells Snort what to do when it finds a packet that matches the rule criteria. There are five available actions in Snort: alert, log, pass, activate, and dynamic. In inline mode, additional options such as *drop*, *reject*, and *sdrop* are available.

Protocols: Snort supports the following protocols: TCP, UDP, ICMP, and IP.

Directional operator: The directional operator is used to indicate the direction of the traffic to which the Snort rule applies.

Rule options: The following table illustrates Snort rule options and their equivalent Cisco IPS signature parameters.

Table 4. Rule Options

Snort Rule Option	Equivalent Cisco IPS Signature Parameter	Engine
depth	Specify Max Match Offset	String TCP and Atomic IP
dsize	Specify Payload Length	Atomic IP
flags	TCP Flags and TCP Mask	Atomic IP
http_header	Specify HTTP Header Regex	Service HTTP
http_uri	Specify URI Regex	Service HTTP

icmp_id	Specify ICMP Identifier	Atomic IP
icmp_seq	Specify Sequence	Atomic IP
icode	Specify ICMP Code	Atomic IP
itype	Specify ICMP Type	Atomic IP
logto	Log Victim/Attacker/Pair Packets	All engines
msg	Signature Name	All engines
offset	Specify Min Match Offset	String TCP and Atomic IP
pcre	Specify Regex Inspection	String TCP and Atomic IP

Content and Perl-Compatible Regular Expressions vs. Cisco IPS Regular Expressions

The **content** keyword in Snort is used for text and binary content matching. Binary content matching is enclosed in the pipe (|) character. Perl-compatible regular expressions (PCRE) support regular expression matching. The key difference between binary content matching and PCRE is the ability to specify offsets when using the **content** parameter. Offsets cannot be applied to the PCRE section of a Snort signature. Cisco signatures rely exclusively on regexes for matching ASCII and hex characters, and the signatures use and apply offsets to these matches. Offsets play an important role in reducing false positives. Regular expression support in Cisco IPS signatures is limited to the keywords specified at the following link: http://www.cisco.com/en/US/docs/security/ips/7.0/configuration/guide/idm/idm_signature_engines.html#wp1408334

Depth/Offset vs. Min/Max Match Offset Length

For Cisco IPS, **Min Match Offset** is used to specify the minimum offset into the packet or stream the regular expression must match. **Max Match Offset** is used to specify the maximum offset the regular expression must match. These offsets are very similar to the **offset** and **depth** keywords in Snort, respectively. However, Snort **depth** and **offset** are content modifiers and do not apply to PCRE payload detection matches. The min/max offsets used in Cisco IPS engines apply to regular expression matches also. This makes the process of developing vulnerability-based signatures easier.

Examples

The following examples illustrate the process of converting Snort signatures to Cisco signatures.

Example 1: TCP Streams

The following example illustrates a signature that triggers on established TCP streams.

Snort Signature

The following Snort rule fires on established TCP streams with a destination port of 1024.

alert tcp \$EXTERNAL_NET any -> \$HOME_NET 1024: (msg:"SPYWARE-PUT Screen-Scraper farsighter runtime detection - initial connection"; flow:to_server,established; content:"|00 00 05 00 00 00|"; depth:8; offset:2; nocase; reference:url,www.spywareguide.com/product_show.php?id=587; classtype:successful-recon-limited; sid:5771; rev:3)

Cisco IPS Custom Signature

An equivalent signature that uses Cisco IPS would use the String TCP engine.

Signature Name: Screen-Scraper farsighter runtime detection

Engine: String TCP Service Ports: 1024 Direction: To-Service

Regex:\x00\x00\x05\x00\x00\x00
Specify Min Match Offset:Yes

Min Match Offset:2

Specify Max Match Offset:Yes

Max Match Offset:8

Event Action: Produce Alert

Example 2: UDP Packets

The following example illustrates a signature that triggers on UDP packets.

Snort Signature

In the following example, the connection flow type is not specified in the Snort rule. The global configuration is loaded from the Snort configuration file. The default setting is to track sessions for UDP. Explicitly specifying **stateless** as a flow parameter will cause this signature to be packet based rather than stream based. An equivalent Cisco IPS custom signature, illustrated in the following section, uses the Atomic IP engine.

alert udp \$EXTERNAL_NET any -> \$HOME_NET 15164 (msg:" Keylogger stealthwatcher 2000 runtime detection - agent status monitoring"; content:"|0A 02 08 FE 00|"; depth:10; offset:4; threshold:type limit, track by_src, count 1, seconds 300; metadata:policy security-ips drop; reference:url,www.spywareguide.com/product_show.php? id=879;classtype:successful-recon-limited; sid:6385; rev:2)

Cisco IPS Custom Signature

Signature Name: Keylogger stealthwatcher 2000 runtime detection

Engine: Atomic IP

Specify Layer 4 Protocol: Yes Layer 4 Protocol: UDP Specify Payload detection: Yes Regex String: \x0A\x02\x08\xFE\x00 Specify Min Match Offset: Yes

Min Match Offset: 4

Specify Max Match Offset: Yes

Max Match Offset: 10

Example 3: Distance vs. Minimum Spacing

The **distance** content modifier specifies how far into the packet or stream Snort should start the pattern match relative to the end of the previous pattern match. Similarly, **Minimum Spacing** in the Multi String engine in Cisco IPS specifies the minimum length of spacing between the previous multistring component match. The following examples show how Snort and Cisco IPS use these settings:

Snort Signature

alert tcp \$EXTERNAL_NET any -> \$HOME_NET 15164 (msg:"Test for MultiString"; flow:to_server,established; content:"|0A 0A 0A 0A|"; content:"|0B 0B 0B 0B|"; distance:8; metadata:policy security-ips drop; sid:63851; rev:2)

Cisco IPS Custom Signature

Engine: MultiString Protocol: TCP

Port Selection: Destination

Dest Ports: 15164
Regex Component:
Regex String 1:
\x0A\x0A\x0A\x0A
Regex String 2:
\x0B\x0B\x0B\x0B
Spacing Type: Minimum
Minimum Spacing:8

Example 4: HTTP Header

The following example illustrates signatures that detect attacks based on the HTTP protocol.

Snort Signature

alert tcp any any -> any \$HTTP_PORTS (msg:"Test for HTTP Signature"; flow:to_server,established; content:"ABC"; content: "EFG"; http_client_body;content:"DEF";http_header;content:"JLM";http_uri)

Cisco IPS Custom Signature

Engine:Service HTTP
Service Ports: #WEBPORTS
Specify Request Regex: yes
Request Regex: EFG
Specify Header Regex: Yes
Header Regex: DEF
Specify URI Regex: Yes
URI Regex: JLM

Example 5: Non-Payload Detection Rule Options

The following table identifies Snort non-payload detection rule options.

Table 5. Snort Non-Payload Detection Rule Options

Option	Description
ttl	Checks the IP TTL value
tos	Checks the IP TOS field for a specific value
fragbits	Checks whether fragmentation and reserved bits are set in the IP header
flags	Checks whether specific TCP flag bits are present

Snort Signature

alert tcp any any -> any any (msg"IP Options test";ttl:3;tos:4;fragbits:M;flags:SF,12)

Cisco IPS Custom Signature

Engine: Atomic IP

Fragment Status: Fragmented Specify IP Time-To-Live: Yes

TTL: 3

Specify IP Type-of-Service: IP Type of Service:4

Specify Layer 4 Protocol: Yes

Layer 4 Protocol: TCP TCP Flags: SYN, FIN TCP Mask: SYN, FIN

Example 6: Flowbits vs. Meta

The **flowbit** parameter is used in Snort to track the state of a transport layer protocol stream. Where Snort uses the **flowbit** parameter along with the set and isset options, an equivalent Cisco IPS signature will use the Meta engine. The following examples illustrate this process.

Snort Signature

alert tcp any \$HTTP_PORTS -> any any (msg:" Signature 1"; flow:to_server,established; content:"abc"; flowbits:set,abc_check; flowbits:noalert;)
alert tcp any \$HTTP_PORTS -> any any (msg:" Signature 2"; flow:to_server,established; content:"def"; flowbits:set,def_check; flowbits:noalert;)
alert tcp any \$HTTP_PORTS -> any any (msg:" Signature 3"; flow:to_server,established; flowbits:isset,abc_check; flowbits:isset,def_check;)

Cisco IPS Custom Signature

Component 1:

Engine: String-TCP

Signature Name: Signature 1 alert severity: informational

Sig Fidelity Rating: 60 service ports: #WEBPORTS direction: from service Event Action: none selected

regex: abc

Component 2: Engine: String-TCP

Signature Name: Signature 1 alert severity: informational Sig Fidelity Rating: 60 service ports: #WEBPORTS direction: from service Event Action: none selected

regex: def

Meta Signature: Engine: Meta

Signature Name: Signature 3 event action: produce alert

Component List: Component 1 and Component 2

All Components Required: Yes

Acknowledgments

Martin Zeiser, Software Engineer Neil Archibald, Software Engineer Shiva Persaud, Software Engineer Roopesh Uppala, Software Engineer

This document is part of Cisco Security Intelligence Operations.

This document is provided on an "as is" basis and does not imply any kind of guarantee or warranty, including the warranties of merchantability or fitness for a particular use. Your use of the information on the document or materials linked from the document is at your own risk. Cisco reserves the right to change or update this document at any time.

Back to Top

Cisco Security Intelligence Operations