COBA Version Management REST

Contents

1 Version Read Request

- 1.1 General Entity
- 1.2 Global List
- 1.3 Successful Response
- 1.4 Error Codes

1 Version Read Request

The COBA Version Management REST interface lists the working and released versions for a record or global list.

1.1 General Entity

Retrieves the working and released versions of a general entity record.

HTTP Method

GET

URI

http://<host>:<port>/coba/entity/listVersions/v1/<entityType>/<publicKey>
https://<host>:<port>/coba/entity/listVersions/v1/<entityType>/<publicKey>

Table 1 URI Parameters						
Parameter	Description					
entityType	Name of the entity type.					
publicKey	Public key of the record.					

Example

The following request lists **Released** or **Working** versions of general entity RateType for public key callSetup.

URI

http://<host>:<port>/coba/entity/listVersions/v1/RateType/callSetup

Response 200

Γ

```
{
    "rateType": "callSetup",
    "includedInActualPrice":TRUE,
    "versionNumber": 1463980032027,
"status": "released",
    "description": "Call Setup",
    "uri": "rmref://coba/RateType/callSetup",
    "id": "callSetup",
    "validFor": [
        "startDateTime": "1970-01-01T00:00:00.000+00:00",
        "endDateTime": "9999-12-31T23:59:59.000+00:00"
1
    },
 {
    "rateType": "callSetup",
    "includedInActualPrice":TRUE,
    "versionNumber": 1464673316028,
    "status": "working",
    "description": "Call Setup - Working State",
    "uri": "rmref://coba/RateType/callSetup",
    "id": "callSetup",
    "validFor": [
        "startDateTime": "1970-01-01T00:00:00.000+00:00",
        "endDateTime": "9999-12-31T23:59:59.000+00:00"
]
    }
1
```

1.2 Global List

Retrieves the working and released versions of a global list.

HTTP Method

GET

URI

```
http://<host>:<port>/coba/globalList/listVersions/v1/{globalListSpecification
Name}/{globalListName}
https://<host>:<port>/coba/globalList/listVersions/v1/{globalListSpecificatio
nName}/{globalListName}
```

Table 2 URI Parameters

Parameter

Description

globalListSpecificationName	Name of the global list specification.
globalListName	Name of the global list.

Example

The following request reads if the global list Test4Operator is in Released or Working state.

URI

http://<host>:<port>/coba/globalList/listVersions/v1/Operator/Test4Ope
rator

Response 200

1.3 Successful Response

The read response includes the status code and response in the message body.

Table 3 Response Code and Header				
Field Name	Value	Description		
HTTP Response Code	200 OK	The request served successfully.		
Content-Type	application/json	JSON object returned in the body.		
x-content- typeoptions	nosniff	This option prevents the MIMEsniffing a response other than the declared content-type.		

Response Body

The response body lists the working and released versions of a record or global list.

1.4 Error Codes

The following table lists the possible error codes which may occur when retrieving versions for a global list.

Table	e 4 Gen	eral Enti	tv Version Re	ad Request Error Codes
	Error Code		Response	
404	COBAC 001	Invalid EntityT ype		The error message is displayed if the entity type is invalid. http:// <host>:<port>/coba/listEntityVersion/v1?entityType =abc&publicKey=JP</port></host>
400	COBAR 010	ory field	"status": 400,	The error message is displayed if the entity key is null or empty. http:// <host>:<port>/coba/listEntityVersion/v1?entityType =Country&publicKey=null http://<host>:<port>/coba/listEntityVersion/v1?entityType =Country&publicKey=""</port></host></port></host>

			missing" , "details ": "Mandato ry field EntityKe y is missing" }	
404	COBAR 008	Data not found	<pre>"status" : 404, "code": "COBAR00 8", "message ": "Data not found", "details ": "Data not found")</pre>	The error message is displayed if publick key is invalid. http:// <host>:<port>/coba/listEntityVersion/v1?entityType =Country&publicKey=abc</port></host>

404	COBAR 019	Functio n is not active	<pre>"status" : 404, "code": "COBAR01 9", "message ": "Functio n is not active", "details ": "Functio n is not active" }</pre>	This error message is displayed when function control is not active.
-----	--------------	----------------------------------	--	--

Tab	Table 5 Global List Version Read Request Error Codes					
	Code	rror Message Response		Details		
40 4	COBA R016	Invalid EntityType or	<pre>{ "status": 404,</pre>	The error message is displayed if the global list specification is invalid, null, or empty.		
		GlobalListSp ecification	"code": "COBAC006", "message": "Invalid EntityType or GlobalListSpec ification", "details": "Invalid EntityType or GlobalListSpec ification", }	http:// <host>:<port>/coba/globalList/listVersio ns/v1/OperatorTest/Test4Operator</port></host>		

40	COBA R013	Mandatory field GlobalList Name is missing	<pre>{ "status": 400, "code": "COBAR013", "message": "Mandatory field GlobalList name is missing", "details": "Mandatory field GlobalList name is missing"; </pre>	The error message is displayed if the global list name is null or empty. http:// <host>:<port>/coba/globalList/listVersions/v1/Operator/null</port></host>
40		Data not found	<pre>{ "status": 404, "code": "COBAR008", "message": "Data not found", "details": "Data not found"</pre>	The error message is displayed if the global list name is invalid. http:// <host>:<port>/coba/globalList/listVersio ns/v1/Operator/123</port></host>
40	COBA R019	Function is not active.	<pre>{ "status": 404, "code": "COBAR019", "message": "Function is not active", "details": "Function is not active" }</pre>	This error message is displayed when function control is not active.