INSTALL GUIDE · SELF-HOSTED · v1

# HOODEN

## ON AN INTEL NUC, RUN OVER SSH

From a bare NUC to a private community site your friends can open on their phones: Ubuntu Server, SSH, Docker, Hooden itself, HTTPS, notifications and voice chat. Plus how to keep it running, updated and backed up. There's an Unraid section at the end too.

**HARDWARE**
Intel NUC7i5BNK
(any amd64 PC works)


**SYSTEM**
Ubuntu Server
26.04.1 LTS

**RUNS AS**
Docker container
ghcr.io/svennefenne/hooden

BEFORE YOU START

# 00 WHAT YOU'RE BUILDING

The NUC sits at home without a screen. You set it up once with a keyboard and monitor, and after that you control it from your own computer over SSH. Hooden runs inside Docker, and a small HTTPS front door lets your friends reach it from anywhere.




SSH You manage everything from your own computer: `ssh nuc`

## You need

- [ ] The NUC with RAM and an SSD (8 GB RAM and a 120 GB SSD is plenty)
- [ ] A USB stick of 4 GB or more (it will be wiped)
- [ ] A keyboard and a monitor (HDMI), for the install only
- [ ] A network cable to your router (a server should be wired)
- [ ] Your own computer (Windows, Mac or Linux) to SSH from
- [ ] For HTTPS: a domain name (about €10 a year) and access to your router's settings

## Contents


01 Prepare the NUC
02 Install Ubuntu Server
03 First boot
04 SSH from your computer
05 Install Docker
06 Install Hooden
07 HTTPS
08 Phones and voice
09 Day to day
10 Backups
11 Troubleshooting
12 Unraid
13 Reference


## How to read the commands

Every command box says where to type it: a terminal on the computer you sit at, the NUC after you've connected with `ssh`, or the settings file `/opt/hooden/.env`. Copy the lines one at a time and press `Enter` after each.

YOUR COMPUTER
```
ssh nuc
```

ON THE NUC
```
docker compose ps
```

IN THE .env FILE
```
TZ=Europe/Stockholm
```

SWAP IN YOUR OWN VALUES

The examples use `192.168.1.50` for the NUC's address, `fenne` for your username on the NUC, and `hooden.example.com` for your domain. Replace them with yours everywhere you see them.

KEYBOARD AND MONITOR PLUGGED IN

# 01 PREPARE THE NUC

## STEP 1.1 Make the install stick

1. Download **Ubuntu Server 26.04.1 LTS** from ubuntu.com/download/server. The file is called something like `ubuntu-26.04.1-live-server-amd64.iso`.
2. Write it to the USB stick with **balenaEtcher** (Windows, Mac, Linux) or **Rufus** (Windows). Pick the ISO, pick the stick, and click Flash or Start.

On Linux you can also use `dd`. Check the stick's name with `lsblk` first, because `dd` overwrites whatever disk you give it:

YOUR COMPUTER — Linux · /dev/sdX is the USB stick

```
lsblk
sudo dd if=ubuntu-26.04.1-live-server-amd64.iso of=/dev/sdX bs=4M status=progress conv=fsync
```

## STEP 1.2 Set the NUC to switch itself back on

A server should come back by itself after a power cut. Plug the keyboard, monitor and network cable into the NUC, switch it on, and press F2 straight away to open the BIOS.

1. Go to ‹**Power**› → ‹**Secondary Power Settings**› (on some versions it's under ‹**Advanced**› → ‹**Power**›).
2. Set ‹**After Power Failure**› to **Power On**.
3. Press F10 to save and exit.

> GOOD TO KNOW
>
> Leave Secure Boot as it is; Ubuntu works with it. The menus on the NUC7 are Intel's "Visual BIOS", so the names may differ a little from the ones above.

## STEP 1.3 Start the installer

1. Put the USB stick in and switch the NUC on.
2. Press F10 during start-up to get the boot menu, and pick the USB stick.
3. In the menu that appears, choose ‹**Try or Install Ubuntu Server**›.

ABOUT 15 MINUTES

# 02 INSTALL UBUNTU SERVER

The installer is text-only. Move with the arrow keys and `Tab`, tick boxes with `Space`, and continue with `Enter` on ‹**Done**›. The screens come in roughly this order:

| SCREEN | WHAT TO CHOOSE |
|---|---|
| Language, keyboard | Yours. If it offers an **installer update**, take it. |
| Type of installation | **Ubuntu Server** (not the "minimized" one, which leaves out tools you'll want). |
| Network | The wired connection should already have an address, such as `192.168.1.50/24`. **Write it down.** If it says "disabled", check the cable. |
| Proxy, mirror | Leave as they are. |
| Storage | **Use an entire disk**, pick the NUC's SSD, and keep **Set up this disk as an LVM group** ticked. On the summary, choose ‹**Done**›, then ‹**Continue**› to confirm. This wipes the disk. |
| Profile | Your name, a server name such as `nuc`, a username (lowercase, such as `fenne`) and a good password. You'll use the password for `sudo`. |
| Ubuntu Pro | Skip for now. |
| SSH | **Tick Install OpenSSH server.** This is what lets you control the NUC from your computer. If your SSH key is on GitHub, you can import it here (‹**Import SSH key**› → from GitHub → your GitHub username) and skip step 4.2. |
| Featured server snaps | **Pick nothing**, and especially not `docker`. Part 05 installs Docker's own packages, which work better with Hooden's setup. |
| Installing | Wait until it says ‹**Reboot Now**›, choose it, and pull out the USB stick when it asks. |

DONE WHEN

The NUC restarts into a black screen with a login prompt such as `nuc login:`. Log in with your username and password to check that it works.

STILL AT THE NUC'S KEYBOARD

# 03 FIRST BOOT

## STEP 3.1 Find and fix the NUC's address

This shows the NUC's network address (the number before the `/`):

ON THE NUC — at the keyboard

```
ip -br -4 addr
```

EXAMPLE OUTPUT

```
lo               UNKNOWN        127.0.0.1/8
eno1             UP             192.168.1.50/24
```

Your router hands out addresses and may give the NUC a different one later. To stop that, open your router's settings page, find the list of connected devices (look for `nuc`), and add a **DHCP reservation** (also called a *static lease* or *fixed IP*) for it with the address it has now. Every router names this differently.

## STEP 3.2 Bring Ubuntu up to date

ON THE NUC

```
sudo apt update && sudo apt full-upgrade -y
sudo reboot
```

Ubuntu installs security updates by itself after this (the `unattended-upgrades` service is on by default).

## STEP 3.3 Give the system the whole disk

The installer may give the system only part of the SSD. Check for unused space:

ON THE NUC

```
sudo vgs
```

If the `VFree` column shows more than a few GB, give it to the system, then check that `/` is now the size of the SSD:

ON THE NUC

```
sudo lvextend -r -l +100%FREE /dev/ubuntu-vg/ubuntu-lv
df -h /
```

## STEP 3.4 Optional: reach it by name

After `sudo apt install -y avahi-daemon` on the NUC, `nuc.local` works as well as `192.168.1.50` on most home networks.

> DONE WHEN
>
> You know the NUC's address, it's reserved in the router, and Ubuntu is up to date. From now on the NUC needs no keyboard or monitor; you can unplug them.

BACK AT YOUR OWN COMPUTER

# 04 SSH FROM YOUR COMPUTER

SSH gives you the NUC's command line from your own computer. Windows 10/11 (PowerShell), macOS (Terminal) and Linux all have it built in.

## STEP 4.1 Connect for the first time

YOUR COMPUTER

```
ssh fenne@192.168.1.50
```

The first time, it asks whether you trust the NUC's key. Type `yes`, then your password. To leave the NUC again, type `exit`.

## STEP 4.2 Log in with a key instead of a password

A key is safer than a password and saves typing. Skip this if you imported your key from GitHub during the install. Make a key (press `Enter` for the defaults; a passphrase is optional) and copy it to the NUC:

YOUR COMPUTER — Linux and Mac

```
ssh-keygen -t ed25519
ssh-copy-id fenne@192.168.1.50
```

YOUR COMPUTER — Windows PowerShell

```
ssh-keygen -t ed25519
type $env:USERPROFILE\.ssh\id_ed25519.pub | ssh fenne@192.168.1.50 "mkdir -p ~/.ssh && cat >> ~/.ssh/authorized_keys"
```

## STEP 4.3 A short name: `ssh nuc`

Add this to the file `.ssh/config` in your home folder (create it if it isn't there; on Windows it's `C:\Users\<you>\.ssh\config`):

YOUR COMPUTER — ~/.ssh/config

```
Host nuc
    HostName 192.168.1.50
    User fenne
```

Now `ssh nuc` logs you straight in, and file copies work with the same name, such as `scp nuc:backups/file.tgz .`

STEP 4.4

## Turn off password logins

Once the key works (`ssh nuc` logs in without asking for the NUC password), stop SSH from accepting passwords at all:

ON THE NUC

```
printf 'PasswordAuthentication no\nKbdInteractiveAuthentication no\n' | sudo tee
/etc/ssh/sshd_config.d/10-keys-only.conf
sudo sshd -t && sudo systemctl restart ssh
```

Test it from a **new** terminal window, keeping your current session open in case something went wrong. The first command should still log in; the second should be refused with `Permission denied (publickey)`.

YOUR COMPUTER

```
ssh nuc
ssh -o PubkeyAuthentication=no nuc
```

DON'T OPEN SSH TO THE INTERNET

Never forward port 22 in your router. To manage the NUC when you're away from home, use a private VPN such as **Tailscale** instead: install it on the NUC with `curl -fsSL https://tailscale.com/install.sh | sh` and then `sudo tailscale up`, install it on your laptop too, and `ssh` to the NUC's Tailscale name.

OVER SSH FROM HERE ON

# 05 INSTALL DOCKER

## STEP 5.1 Install Docker Engine and Compose

Docker's own install script sets up its official packages, including `docker compose`, and starts Docker at every boot:

ON THE NUC

```
curl -fsSL https://get.docker.com | sudo sh
```

## STEP 5.2 Use Docker without sudo

ON THE NUC

```
sudo usermod -aG docker $USER
exit
```

Log in again (`ssh nuc`) so the change takes effect, then test it:

ON THE NUC

```
docker run --rm hello-world
docker compose version
```

You should see `Hello from Docker!` and a version number.

## STEP 5.3 Keep container logs from filling the disk

By default Docker keeps container logs forever. This keeps at most 3 × 10 MB per container. Do it now, because it only applies to containers created afterwards:

ON THE NUC

```
printf '{\n  "log-driver": "json-file",\n  "log-opts": { "max-size": "10m", "max-file": "3"
}\n}\n' | sudo tee /etc/docker/daemon.json
sudo systemctl restart docker
```

> ABOUT THE FIREWALL
>
> Ubuntu's firewall (`ufw`) is off by default, which is fine behind a home router. If you turn it on, allow SSH first (`sudo ufw allow OpenSSH`, then `sudo ufw enable`), and for voice (part 08) also `sudo ufw allow 3478` and `sudo ufw allow 49160:49200/udp`. Note that ports Docker publishes (3000, 80, 443) **bypass ufw**. To keep port 3000 off your network, use `HOODEN_PORT=127.0.0.1:3000` as described in part 07.

THE MAIN EVENT

# 06 INSTALL HOODEN

## STEP 6.1 Make a home for it and download the files

Everything lives in `/opt/hooden`: the Compose file that describes the containers, your settings in `.env`, and later the `data` folder.

ON THE NUC

```
sudo mkdir -p /opt/hooden
sudo chown $USER: /opt/hooden
cd /opt/hooden
B=https://raw.githubusercontent.com/svennefenne/hooden/main
curl -fLO $B/docker-compose.yml
curl -fLo .env $B/.env.example
mkdir -p deploy && curl -fLo deploy/Caddyfile $B/deploy/Caddyfile
id
```

The last command shows your user and group numbers, such as `uid=1000(fenne) gid=1000(fenne)`. You need them next.

## STEP 6.2 Fill in the settings

ON THE NUC

```
nano .env
```

For the first start, only these three matter. Set them to your time zone and the numbers `id` showed:

IN THE .env FILE

```
TZ=Europe/Stockholm
PUID=1000
PGID=1000
```

Leave the lines starting with `#` for now; parts 07 and 08 turn them on. Save with `Ctrl`+`O` then `Enter`, and leave nano with `Ctrl`+`X`.

## STEP 6.3 Start it

ON THE NUC — in /opt/hooden

```
docker compose up -d
docker compose logs -f hooden
```

The first start downloads the image (a few hundred MB). When the log shows `[hooden] ready`, press `Ctrl`+`C` to stop watching; Hooden keeps running. `docker compose ps` should then show the container as `Up … (healthy)`.

## STEP 6.4 Create the admin account

1. On your computer, open **http://192.168.1.50:3000** in a browser.

2. A fresh Hooden opens on the setup page. Pick the site's name and create your own account; it becomes the admin.
3. Look around: ‹**Admin**› has the site's settings, members, invites, features and the look.

INVITE YOUR FRIENDS AFTER HTTPS

Hooden is invite-only by default. You make invite links under ‹**Admin**› → ‹**Invites & sign-up**›. Set up HTTPS (part 07) first, so the links use your real address and work on phones.

DONE WHEN

You're logged in to your own Hooden at `http://192.168.1.50:3000`. It starts by itself after a reboot or a power cut.

SO IT WORKS ON PHONES, FROM ANYWHERE

# 07 HTTPS

Phones only allow notifications, the microphone (voice chat) and installing a site as an app on secure **https://** addresses. You need a domain name; then pick one of two ways. Both are already in Hooden's Compose file.

OPTION A · EASIEST

### Cloudflare Tunnel

- No router changes and no open ports
- Works even if your internet provider shares your public IP (CGNAT)
- Your domain must use Cloudflare's (free) DNS
- Traffic goes through Cloudflare

OPTION B · DIRECT

### Caddy

- Traffic goes straight to your home
- Caddy gets and renews the certificate itself
- Needs ports 80 and 443 forwarded in your router
- Doesn't work behind CGNAT

## OPTION A Cloudflare Tunnel

1. Add your domain to a free Cloudflare account and change its nameservers at the registrar to the two Cloudflare gives you (or buy the domain from Cloudflare).
2. In the Cloudflare dashboard, go to ‹**Zero Trust**› → ‹**Networks**› → ‹**Tunnels**› → ‹**Create a tunnel**›. Choose **Cloudflared** and name it `hooden`.
3. On the connector page, choose **Docker**. The command it shows ends in `--token eyJ…`. **Copy only the long token**; don't run the command, because Hooden's Compose file runs the tunnel for you.
4. Next, add a public hostname: subdomain `hooden`, your domain, service type **HTTP**, URL `hooden:3000`. Save. Cloudflare creates the DNS record itself.

Cloudflare moves and renames these menus now and then; a "public hostname" may be called a "published application route". Look for the same ideas.

IN THE .env FILE — remove the # in front of these lines and fill them in

```
COMPOSE_PROFILES=tunnel
PUBLIC_URL=https://hooden.example.com
CLOUDFLARE_TUNNEL_TOKEN=eyJhIjoi…the whole token…
TRUSTED_IP_HEADER=cf-connecting-ip
HOODEN_PORT=127.0.0.1:3000   # optional: only reachable through the tunnel (and SSH)
```

ON THE NUC — in /opt/hooden

```
docker compose up -d
docker compose logs cloudflared
```

Look for `Registered tunnel connection`, then open **https://hooden.example.com**.

## OPTION B Caddy

1. Find your home's public IP on the NUC with `curl -4 ifconfig.me`. In your domain's DNS, add an **A record** for `hooden.example.com` pointing at it. If your home IP changes now and then, use your router's dynamic DNS feature (or a service such as DuckDNS) and point a CNAME record at that name instead.
2. In your router, forward **TCP 80** and **TCP + UDP 443** to `192.168.1.50`.

IN THE .env FILE

```
COMPOSE_PROFILES=https
HOODEN_DOMAIN=hooden.example.com
PUBLIC_URL=https://hooden.example.com
HOODEN_PORT=127.0.0.1:3000   # optional: only reachable through Caddy (and SSH)
```

ON THE NUC — in /opt/hooden

```
docker compose up -d
docker compose logs -f caddy
```

Wait for `certificate obtained successfully`, press `Ctrl`+`C`, and open **https://hooden.example.com**.

IS YOUR IP SHARED? (CGNAT)

Compare the "WAN" or "internet" address on your router's status page with `curl -4 ifconfig.me`. If they differ, or the router's starts with `100.`, your provider shares your IP, and incoming connections never reach you. Use option A.

CHANGED .ENV? USE UP, NOT RESTART

Settings in `.env` only apply when the containers are re-created, so always run `docker compose up -d` after editing it. `docker compose restart` keeps the old settings.

ONCE HTTPS WORKS

# 08 PHONES AND VOICE

## STEP 8.1 Install Hooden on a phone

| PHONE | HOW |
|---|---|
| **Android**<br>Chrome | Open `https://hooden.example.com` and log in. Menu (⋮) → ‹**Add to home screen**› → ‹**Install**›. |
| **iPhone, iPad**<br>Safari | Open the address in **Safari** and log in. Share button → ‹**Add to Home Screen**›. From then on, **open Hooden from the home-screen icon**: iOS only allows notifications for sites added this way (iOS 16.4 or newer). |

Then turn notifications on when Hooden asks, or in Hooden under ‹**Settings**› → ‹**Notifications**›. There you can also pick what to be notified about and set quiet hours.

## STEP 8.2 Voice chat on mobile data: a TURN server

Voice works out of the box on the same network and through most home routers. Phones on mobile data and strict networks need a relay, called a **TURN** server. Hooden's Compose file includes one (coturn). To set it up:

1. **Router:** forward **UDP + TCP 3478** and **UDP 49160–49200** to `192.168.1.50`.
2. **A name that reaches your home directly.** With Caddy, use the same domain. With a Cloudflare Tunnel, add a DNS record `turn` (type A, your public IP) and set its proxy status to **DNS only** (grey cloud), because TURN can't go through the tunnel.
3. **A password:** make one with `openssl rand -hex 24` on the NUC.

IN THE .env FILE — add turn to the profiles you already have

```
COMPOSE_PROFILES=tunnel,turn
VOICE_TURN_URL=turn:turn.example.com:3478
VOICE_TURN_USER=hooden
VOICE_TURN_PASS=the password you just made
VOICE_TURN_LAN_IP=192.168.1.50
```

ON THE NUC — in /opt/hooden

```
docker compose up -d
docker compose logs coturn | grep -iE "relay address|external-ip|failed"
```

You should see `Relay address to use: 192.168.1.50` and `Whitelisting external-ip private part: 192.168.1.50`. coturn looks up your public IP each time it starts. If the log says `All providers failed`, put your public IP in `VOICE_TURN_PUBLIC_IP=` and run `docker compose up -d` again.

> IF YOUR HOME IP CHANGES
>
> Run `docker compose restart coturn` so it picks up the new address. To test, start a voice chat between someone on Wi-Fi at home and a phone on mobile data.

RUNNING IT OVER SSH

# 09 DAY TO DAY

Connect with `ssh nuc` and go to the Hooden folder with `cd /opt/hooden`. Every command below runs there.

| TO… | RUN |
|---|---|
| See if it's running | `docker compose ps` |
| Watch the log | `docker compose logs -f hooden` (stop watching with `Ctrl`+`C`), or `--tail 100` instead of `-f` for the last lines |
| Update Hooden to the newest version | `docker compose pull && docker compose up -d && docker image prune -f` |
| Apply a change to `.env` | `docker compose up -d` |
| Restart Hooden | `docker compose restart hooden` |
| Stop everything | `docker compose down` (your data stays) |
| Start everything | `docker compose up -d` |
| Check disk space | `df -h /` and `du -sh data` |
| Update Ubuntu | `sudo apt update && sudo apt full-upgrade -y` |
| Restart the NUC | `sudo reboot` (Hooden comes back by itself) |
| Switch the NUC off | `sudo poweroff` |

## A good routine

- **Monthly:** update Ubuntu and Hooden with the two commands above. If the login message says `*** System restart required ***`, run `sudo reboot`.
- **Now and then:** check ‹**Admin**› → ‹**Overview**› in Hooden for activity and disk use, and ‹**Reports**› for anything members flagged.
- **Before big changes:** take a backup (part 10).

> WHERE THINGS ARE
>
> `/opt/hooden/docker-compose.yml` describes the containers; `/opt/hooden/.env` holds your settings; `/opt/hooden/data` holds everything Hooden stores: the database, uploaded pictures and its own backups. Those three are all you need to move Hooden to another machine.

YOUR FRIENDS' POSTS AND PICTURES

# 10 BACKUPS

Everything Hooden stores is in `/opt/hooden/data`. Stop Hooden for the few seconds it takes to pack it up, so the database is copied in a consistent state.

## STEP 10.1 A backup by hand

ON THE NUC — in /opt/hooden

```
mkdir -p ~/backups
docker compose stop hooden
tar czf ~/backups/hooden-$(date +%F).tgz data
docker compose start hooden
```

The quickest alternative: ‹**Admin**› → ‹**System & backup**› in Hooden downloads a consistent copy of the database to your computer without stopping anything. It doesn't include the uploaded pictures.

## STEP 10.2 Every night, by itself

Open your scheduled tasks with `crontab -e` (choose `nano` if it asks) and add this as **one line**. It backs up at 04:30 and keeps two weeks of backups:

ON THE NUC — crontab -e · one line

```
30 4 * * * cd /opt/hooden && docker compose stop hooden && tar czf $HOME/backups/hooden-$(date +\%F).tgz data; docker compose start hooden; find $HOME/backups -name 'hooden-*.tgz' -mtime +14 -delete
```

## STEP 10.3 Keep a copy somewhere else

A backup on the same NUC won't survive a broken SSD. Copy the backups to your computer, or a NAS, now and then:

YOUR COMPUTER

```
scp 'nuc:backups/hooden-*.tgz' .
```

## STEP 10.4 Restore a backup

ON THE NUC — in /opt/hooden

```
docker compose down
mv data data.old
tar xzf ~/backups/hooden-2026-10-23.tgz
docker compose up -d
```

Once everything looks right, delete the old copy with `rm -rf data.old`. On a new machine, follow parts 02–06, then copy `.env` and a backup over and restore it this way.

WHEN SOMETHING'S OFF

# 11 TROUBLESHOOTING

Start with `docker compose ps` and `docker compose logs --tail 100 hooden` in `/opt/hooden`. The log usually says what's wrong.

| WHAT YOU SEE | WHAT TO DO |
|---|---|
| `ssh`: connection refused or timed out | Is the NUC on, and is the address right? (Check `ip -br -4 addr` at the NUC.) If OpenSSH wasn't ticked during the install: `sudo apt install openssh-server` at the NUC's keyboard. |
| `permission denied` … `docker.sock` | Log out and back in after step 5.2, so your user's new Docker group applies. |
| `curl: (23) Failure writing output` | You don't own `/opt/hooden`: `sudo chown $USER: /opt/hooden`. |
| The page at `:3000` doesn't load | `docker compose ps` should say `Up … (healthy)`. With `HOODEN_PORT=127.0.0.1:3000`, port 3000 is only open on the NUC itself, so use your https address, or `ssh -L 3000:localhost:3000 nuc` and `http://localhost:3000`. |
| `port is already allocated` | Another program uses port 3000. Set `HOODEN_PORT=3001` (for example) and run `docker compose up -d`. |
| Cloudflare shows **502 Bad Gateway** | The tunnel's hostname must point at service type HTTP and `hooden:3000` (not `localhost`). Check `docker compose logs cloudflared` and the token in `.env`. |
| Caddy gets no certificate | The A record must point at your public IP, and ports 80 and 443 must be forwarded to the NUC. Check for CGNAT (part 07). `docker compose logs caddy` says which step fails. |
| Invite links or calendar feeds use the wrong address | Set `PUBLIC_URL` in `.env` to your https address and run `docker compose up -d`. |
| No notifications on an iPhone | It needs https, iOS 16.4 or newer, and Hooden opened from the home-screen icon (step 8.1), not from Safari. Then turn notifications on in Hooden's settings. |
| Voice works at home but not on mobile data | Set up TURN (step 8.2). Check the port forwards and the `docker compose logs coturn` lines. |
| Files in `data` belong to the wrong user | Set `PUID` and `PGID` to what `id` shows, then `docker compose up -d`. Hooden fixes the owners as it starts. |
| The disk is filling up | `du -sh data ~/backups`. Remove old backups and unused images with `docker image prune -f`. ‹**Admin**› → ‹**System & backup**› → ‹**Remove pictures nothing uses**› frees space too. |

IF YOU'D RATHER USE YOUR UNRAID SERVER

# 12 UNRAID

Hooden comes with an Unraid template, so there's nothing to install on the command line.

1. In Unraid, go to ‹**Docker**› → ‹**Add Container**›. Under ‹**Template repositories**›, add `https://github.com/svennefenne/hooden` and save.
2. Pick **Hooden** from the template list.
3. Check the values: the port (`3000`), **Appdata** (`/mnt/user/appdata/hooden`) and your time zone. It runs as `99:100` (nobody:users), Unraid's default.
4. Apply, then open `http://<your-unraid>:3000` and create the admin account.

For HTTPS, use what you already run on Unraid: SWAG, Nginx Proxy Manager (turn on *Websockets Support*) or the Cloudflare Tunnel container, pointing at `http://<your-unraid>:3000`. Then fill in **Public URL** in the template. A TURN server for voice can be set in the template's advanced view or in Hooden under ‹**Admin**› → ‹**Notifications & voice**›. The **Appdata Backup** plugin covers the data.

Updates: Unraid shows an update for the container when a new version is out. Apply it from the Docker tab.

AT A GLANCE

# 13 REFERENCE

## Settings in `.env`

| SETTING | WHAT IT DOES |
|---|---|
| `TZ` | Your time zone, such as `Europe/Stockholm` (reminders, birthdays, calendar files) |
| `PUID`, `PGID` | Who owns the files in `data`; what `id` shows |
| `HOODEN_DATA` | Where the data folder is (`./data`) |
| `HOODEN_PORT` | The port on the NUC (`3000`); `127.0.0.1:3000` keeps it off your network |
| `COMPOSE_PROFILES` | The extras to run: `tunnel`, `https`, `turn`, comma-separated |
| `PUBLIC_URL` | Your https address (invite links, calendar feeds, push) |
| `CLOUDFLARE_TUNNEL_TOKEN` | The tunnel's token (option A) |
| `TRUSTED_IP_HEADER` | `cf-connecting-ip` behind a Cloudflare Tunnel, so login protection sees each visitor's own address |
| `HOODEN_DOMAIN` | Your domain, for Caddy (option B) |
| `VOICE_TURN_URL`, `_USER`, `_PASS` | The TURN server for voice chat |
| `VOICE_TURN_LAN_IP` | The NUC's own address on your network |
| `VOICE_TURN_PUBLIC_IP` | Your public IP, only if coturn can't look it up |

## Ports

| PORT | USED BY | OPEN TO |
|---|---|---|
| `22` TCP | SSH | Your home network only. Never forward it in the router. |
| `3000` TCP | Hooden | Your home network, or only the NUC itself (`127.0.0.1:3000`) |
| `80` TCP, `443` TCP + UDP | Caddy | The internet: forward them (option B only) |
| `3478` UDP + TCP, `49160–49200` UDP | coturn | The internet: forward them (voice on mobile data) |

## More

- Source, issues and the newest version of this guide: github.com/svennefenne/hooden
- The Docker image: `ghcr.io/svennefenne/hooden:latest` (built from `main`)