```
2
       *VirtualBox 6.1.44 for Windows hosts 기준
 3
      1)[파일] > [환경설정] > [일반]
 4
         -[기본 머신 폴더]: 미리 탐색기에서 생성한 "Virtual Machines" 폴더 선택
 5
 6
      2)[입력] > [가상 머신] 탭
 7
         -[호스트 키 조합] : F12
 8
 9
      3)[네트워크] > [+] 버튼 클릭
10
         -NAT 네트워크
11
         -"NatNetwork" 선택 > [편집] 버튼 클릭
12
         -[NAT 네트워크 정보] 창에서
            --[네트워크 사용] 체크
--[네트워크 이름] : DockerNetwork
13
14
15
            --[네트워크 CIDR]: 10.0.2.0/24
16
            --[네트워크 옵션] : DHCP 지원만 체크
17
            --[포트 포워딩] 버튼 클릭
18
         -[포트 포워딩 규칙] 창에서
            --IPv4
19
20
            --[+] 버튼 클릭
            --[이름] : docker-ubuntu
21
22
            --[프로토콜] : TCP
23
            --[호스트 IP]: 127.0.0.1
24
            --[호스트 포트] : 105
25
            --[게스트 IP]: 10.0.2.105
26
            --[게스트 포트]: 22
27
            --[확인] 버튼 클릭
28
         -[확인] 버튼 클릭
29
      4)[확장] : [+] 버튼 클릭 후 다운로드 받은 Extension Pack 설치
30
31
32
    2. Ubuntu Server Setting
33
      1)[이름] : docker-ubuntu
34
      2)[종류] : Linux
35
      3)[버전]: Ubuntu (64-bit)
36
      4)[Memory]: 2048 MB
37
      5)[하드 디스크] : 지금 새 가상 하드 디스크 만들기
      6)[하드 디스크 파일 종류] : VDI
38
39
      7)[물리적 하드 드라이브에 저장 : 동적 할당
40
      8)[파일 위치 및 크기] : 50GB
41
      9)[만들기] > [설정] 버튼 클릭
42
      10)[시스템] > [마더보드] > [부팅 순서] : 플로피 체크 해제
43
      11)[[시스템] > [프로세서] : 2
44
       11)[저장소] > [컨트롤러(IDE)] > "비어있음" 선택 -> 다운로드 받은 iso(ubuntu-20.04.2-live-server-amd64.iso)
45
46
47
    3. Ubuntu Sever Installation
      1)Language: English
48
49
      2)Keyboard configuration: Done
50
      3)Network connections: Done
51
      4)Configure proxy: Done
52
      5)Configure Ubuntu archive mirror: Done
53
      6)Guided storage configuration : Custom storage layout 체크
54
         -SWAP: 4.00 GiB
55
         -/boot: 512.00 MiB
56
         -/: 나머지
57
         -Done
58
      7)Confirm destructive action: Are you sure you want to continue? Continue
59
      8)Profile setup
60
         -Your name:
         -Your server's name : ubuntu-server
61
62
         -Pick a username: ubuntu
63
         -Choose a password:
64
         -Confirm your password :
65
      9)SSH Setup: No Check, Done
      10) Featured Server Snaps: No Check, Done
66
67
      11)설치마치면 Reboot Now
68
69
70
    4. Post-Intallation Setting
71
      1)Network Manager Installation
72
         -$ sudo apt update
73
         -$ sudo apt install network-manager
74
         -$ sudo systemctl status NetworkManager
75
76
      2)View Current IP Address
77
         -$ ip a or $ ip addr
78
79
      3)Set Static IP Address
80
         -Oracle VM VirtualBox 관리자창에서
81
         -docker-ubuntu의 설정 > 네트워크 > 다음에 연결됨 : NAT 네트워크 | DockerNetwork로 변경 > 확인
82
83
         -$ Is /etc/netplan
84
            00-installer-config.yaml
```

1

1. VirtualBox Network Setting

```
86
           -$ sudo cp /etc/netplan/00-installer-config.yaml /etc/netplan/00-installer-config.yaml.bak
 87
           -$ sudo nano /etc/netplan/00-installer-config.yaml
 88
             [before]
 89
 90
             network:
 91
                ethernets:
 92
                   enp0s3:
 93
                     dhcp4: true
 94
                version: 2
 95
 96
             [after]
 97
             network:
 98
                renderer: NetworkManager
 99
                ethernets:
100
                   enp0s3:
101
                     dhcp4: no
                     addresses:
102
                     - 10.0.2.105/24
103
104
                     routes:
                      - to: default
105
106
                       via: 10.0.2.1
107
                     nameservers:
                        addresses: [8.8.8.8, 8.8.4.4]
108
109
                version: 2
110
111
           -Save
112
           -Test the new configuration
113
             $ sudo netplan try
114
115
           -Run the new configurations.
116
             $ sudo netplan apply
117
118
           -$ ip addr
           -$ ping -c 4 8.8.8.8
119
120
           -$ sudo apt update
121
122
        4)View Current Hostname
123
           $ hostnamectl
124
125
        5)Change Hostname
126
          $ sudo nano /etc/hostname
127
             ubuntu-server.example.com
128
129
           $ sudo nano /etc/hosts
130
             127.0.0.1 localhost
131
             10.0.2.105 ubuntu-server.example.com
132
133
           $ ping -c 4 ubuntu-server.example.com
134
135
        6)SSH Server Installation
136
          $ sudo apt install openssh-server curl tree
137
138
          $ systemctl status ssh
139
140
          $ export HOST=ubuntu-server
141
142
          $ ssh $USER@$HOST
143
             - Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
144
             - 확인 후 exit
145
146
        7)root 계정 비밀번호 설정(옵션)
147
          $ sudo passwd root
           [sudo] password for {{현재 로그인 계정}} :
148
149
           New password:
150
          Retype new password:
151
          passwd: passsword updated successfully
152
153
          -root 계정으로 전환
154
          $ su -
155
          Password:
156
          root@ubuntu-server:~#
157
158
159
     5. Windows Host OS에서 Ubuntu Guest OS 연결하기
160
        1)PuTTY
161
           -Window > Appearance
162
             --Font settings : Courier New, 16-point
163
           -Window > Colours
164
             --Default Foreground: 0, 0, 0
165
             -- Default Background: 255, 255, 255
166
167
168
           -Session
```

85

```
169
             --Host Name(or IP address): 127.0.0.1
170
             --Port: 105
171
             --Connection type : SSH
172
             --Saved Sessions : docker-ubuntu
173
174
             --Save
175
176
          -Open > 인증서에서 [예(Y)] Click
177
178
        2)XShell
179
          -파일메뉴 > 새로 만들기
180
            --연결
181
               이름: docker-ubuntu
               프로토콜 : SSH
182
183
               호스트: 127.0.0.1
184
               포트 번호: 105
185
             --연결 > 사용자 인증
               사용자 이름 : ubuntu
186
187
               암호:
188
               방법: Password
189
             --확인
190
          -모든 세션 > docker-ubuntu double click
191
192
             -SSH 보안 경고 > 수락 및 저장
193
194
        3)Tabby
195
          -[Settings] > [Profiles & connections] > [New profile] 버튼 클릭
196
          -[SSH connection] 선택
197
          -[Name] : docker-ubuntu
          -[Host]: 127.0.0.1
198
          -[Port] : 105
199
200
          -[Username] : ubuntu
201
          -[Password] : [Set password] 클릭 > 패스워드 입력 > [OK]
202
          -[Save]
203
          -[docker-ubuntu] > ▶ 버튼 클릭
204
          -[Host key verification] > [Accept and remember key] 클릭
205
206
207
     6. Host OS에서 Guest OS 연결 후 작업
208
        1)IP Address 확인
209
          $ ip addr
210
       2)OS 확인하기
211
212
          $ cat /etc/os-release
             PRETTY_NAME="Ubuntu 22.10"
213
             NAME="Ubuntu"
214
215
             VERSION ID="22.10"
            VERSION="22.10 (Kinetic Kudu)"
216
217
             VERSION CODENAME=kinetic
218
            ID=ubuntu
219
             ID LIKE=debian
220
             HOME_URL="https://www.ubuntu.com/"
             SUPPORT_URL="https://help.ubuntu.com/"
221
222
             BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
             PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-policy"
223
224
             UBUNTU_CODENAME=kinetic
225
             LOGO=ubuntu-logo
226
       3)Memory 확인
227
228
          $ free -h
229
230
        4)System Shutdown
231
          $ sudo shutdown now
232
233
     7. Ubuntu Virtual Machine에 Host-Only NIC 설치하기
234
235
        1)docker-ubuntu > [설정] > [네트워크]
236
        2)[어댑터 2] > [네트워크 어댑터 사용하기] 체크
237
        3)[다음에 연결됨] : [호스트 전용 어댑터]
238
        4)[이름]: VirtualBox Host-Only Ethernet Adapter
239
        5)[확인] 클릭
240
        6)Host OS에서 이더넷 어댑터 VirtualBox Host-Only Network 파악하기
241
          -Windows 10 > cmd > ipconfig /all
242
          -VirtualBox Host-Only Ethernet Adapter의 IPv4 확인하기
243
             --예)192.168.56.1
244
245
        7)docker-ubuntu Booting 후, enp0s8 Ip Address 확인하기
          -$ sudo nano /etc/netplan/00-installer-config.yaml
246
247
248
             network:
               renderer: NetworkManager
249
250
               ethernets:
251
                  enp0s3:
252
                     dhcp4: no
```

```
253
                     addresses:
254
                     - 10.0.2.105/24
255
                     routes:
256
                     - to: default
257
                      via: 10.0.2.1
258
                     nameservers:
259
                        addresses: [8.8.8.8, 8.8.4.4]
260
                   enp0s8:
                                          <--- 추가
                                          <---추가
261
                     dhcp4: true
                version: 2
262
263
264
           -Save
265
           -Test the new configuration
266
             $ sudo netplan try
267
           -Run the new configurations.
268
269
             $ sudo netplan apply
270
271
272
           -Restart network-manger service
             $ sudo systemctl restart network-manager
273
          - $ ip address
274
```

- ตุ:192.168.56.101/24

275