```
1. VirtualBox Network Setting
 1
 2
      1)VirtualBox 환경설정 > 네트워크
 3
      2)새 NAT 네트워크 생성 > 네트워크 편집
 4
         -네트워크 이름: DockerNetwork
 5
         -네트워크 CIDR: 10.0.2.0/24
 6
         -네트워크 옵션: DHCP 지원만 체크
 7
         -포트 포워딩
           --IPv4
 8
 9
           --이름: docker-ubuntu
           --호스트 IP: 127.0.0.1
10
           --호스트 포트: 105
11
           --게스트 IP: 10.0.2.105
12
13
           --게스트 포트 : 22
14
15
16
    2. Ubuntu Server Setting
17
      1)이름: docker-ubuntu
18
      2)종류: Linux
19
      3)버전: Ubuntu (64-bit)
      4) Memory: 2048 MB
20
      5)하드 디스크: 지금 새 가상 하드 디스크 만들기
21
22
      6)하드 디스크 파일 종류: VDI
23
      7)물리적 하드 드라이브에 저장 : 동적 할당
24
      8) 파일 위치 및 크기: 50GB
25
      9)만들기 > 설정
26
      10)시스템: 플로피 체크 해제, 프로세서: 2
27
      11)저장소: 컨트롤러(IDE) -> 다운로드 받은 iso(ubuntu-20.04.2-live-server-amd64.iso)
28
29
    3. Ubuntu Sever Installation
30
31
      1)Language: English
32
      2) Keyboard configuration: Done
      3) Network connections: Done
33
34
      4)Configure proxy: Done
35
      5) Configure Ubuntu archive mirror: Done
      6) Guided storage configuration: Done
36
37
      7) Storage configuration: Done
38
      8) Confirm destructive action: Are you sure you want to continue? Continue
39
      9)Profile setup
         -Your name:
40
41
         -Your server's name:
42
         -Pick a username: docker-ubuntu
43
         -Choose a password:
44
         -Confirm your password :
      10)SSH Setup: No Check, Done
45
46
      11) Featured Server Snaps: No Check, Done
47
      12)설치마치면 Reboot Now
48
49
50
   4. Post-Intallation Setting
51
      1)Network Manager Installation
52
         -$ sudo apt update
         -$ sudo apt install network-manager
53
54
         -$ sudo systemctl status network-manager
55
56
      2) View Current IP Address
57
         -$ ip a or $ ip addr
58
59
      3)Set Static IP Address
60
         -Oracle VM VirtualBox 관리자창에서
```

```
61
          -docker-ubuntu의 설정 > 네트워크 > 다음에 연결됨: NAT 네트워크 | DockerNetwork로 변경
           > 확인
 62
 63
          -$ ls /etc/netplan
 64
             00-installer-config.yaml
 65
 66
          -$ sudo cp /etc/netplan/00-installer-config.yaml
          /etc/netplan/00-installer-config.yaml.bak
          -$ sudo nano /etc/netplan/00-installer-config.yaml
 67
 68
 69
             [before]
             network:
 70
 71
                ethernets:
 72
                  enp0s3:
 73
                     dhcp4: true
 74
                version: 2
 75
 76
             [after]
 77
             network:
 78
                renderer: NetworkManager
 79
                ethernets:
 80
                  enp0s3:
 81
                     dhcp4: no
 82
                     addresses:
 83
                     - 10.0.2.105/24
 84
                     gateway4: 10.0.2.1
 85
                     nameservers:
 86
                        addresses: [8.8.8.8, 8.8.4.4]
 87
                version: 2
 88
 89
          -Save
 90
          -Test the new configuration
             $ sudo netplan try
 91
 92
 93
          -Run the new configurations.
 94
             $ sudo netplan apply
 95
 96
          -$ ip addr
          -$ ping -c 4 8.8.8.8
 97
 98
          -$ sudo apt update
 99
100
        4) View Current Hostname
          $ hostnamectl
101
102
103
        5)Change Hostname
          $ sudo nano /etc/hostname
104
105
             docker-ubuntu.example.com
106
107
          $ sudo nano /etc/hosts
108
             127.0.0.1 localhost
             10.0.2.105 docker-ubuntu.example.com
109
110
111
          $ ping docker-ubuntu.example.com
112
113
        6)SSH Server Installation
114
          $ sudo apt install openssh-server curl tree
115
116
          $ systemctl status sshd
```

117118

\$ ssh \$USER@\$HOST

```
119
            - Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
            - 확인 후 exit
120
121
122
       7)root 계정 비밀번호 설정
123
          $ sudo passwd root
          [sudo] password for {{현재 로그인 계정}}:
124
125
          New password:
126
          Retype new password:
127
          passwd: passsword updated successfully
128
129
          -root 계정으로 전환
130
          $ su -
131
          Password:
          root@docker-ubuntu:~#
132
133
134
135
     5. Windows Host OS에서 Ubuntu Guest OS 연결하기
136
       1)PuTTY
137
          -Window > Appearance
138
            --Font settings : Courier New, 16-point
139
          -Window > Colours
140
            --Default Foreground: 0, 0, 0
141
142
            -- Default Background : 255, 255 ,255
143
144
          -Session
145
            --Host Name(or IP address): 127.0.0.1
146
            --Port: 105
            -- Connection type: SSH
147
            --Saved Sessions : docker-ubuntu
148
149
150
            --Save
151
          -Open > 인증서에서 [예(Y)] Click
152
153
154
       2)XShell
155
          -파일메뉴 > 새로 만들기
156
            --연결
157
               이름: docker-ubuntu
158
               프로토콜: SSH
159
               호스트: 127.0.0.1
               포트 번호: 105
160
161
            --연결 > 사용자 인증
162
               사용자 이름: instructor
163
               암호:
164
               방법: Password
165
            --확인
166
167
          -모든 세션 > docker-ubuntu double click
168
            -SSH 보안 경고 > 수락 및 저장
169
170
171
    6. Host OS에서 Guest OS 연결 후 작업
172
       1)IP Address 확인
173
          $ ip addr
174
175
       2)OS 확인하기
176
          $ cat /etc/os-release
177
            NAME="Ubuntu"
178
            VERSION="20.04.2 LTS (Focal Fossa)"
```

```
179
            ID=ubuntu
180
            ID_LIKE=debian
            PRETTY_NAME="Ubuntu 20.04.2 LTS"
181
            VERSION ID="20.04"
182
183
            HOME_URL="https://www.ubuntu.com/"
184
            SUPPORT_URL="https://help.ubuntu.com/"
            BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
185
186
            PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-p
            olicy"
187
            VERSION CODENAME=focal
188
            UBUNTU_CODENAME=focal
189
190
       3)Memory 확인
          $ free -h
191
192
193
194
     7. Ubuntu Virtual Machine에 Host-Only NIC 설치하기
195
       1)docker-ubuntu > 설정 > 네트워크
196
       2)어댑터2
197
       3)다음에 연결됨 : 호스트 전용 어댑터
       4)이름: VirtualBox Host-Only Ethernet Adapter
198
       5)확인 클릭
199
200
       6)Host OS에서 이더넷 어댑터 VirtualBox Host-Only Network 파악하기
          -Windows 10 > cmd > ipconfig /all
201
          -VirtualBox Host-Only Ethernet Adapter의 IPv4 확인하기
202
            --예)192.168.56.1
203
204
       7)docker-ubuntu Booting 후, enp0s8 Ip Address 확인하기
205
206
          - $ ip address
```

207

- 예:192.168.56.101/24