Seminar 3

Little-endian representation of numbers in the memory. Conditional and unconditional jumps.

String operations

Contents

Seminar 3	1
1. Little-endian representation in the memory and non-destructive conversions	1
2. Conditional and unconditional jump instructions	4
3. Working with strings of bytes	6

1. Little-endian representation in the memory and non-destructive conversions

In the computer memory (<u>not on the CPU registers!</u>) numbers represented on more than 1 byte are represented in <u>little-endian format</u> (i.e. the least significant byte of the representation is placed at the smallest memory address).

We also said in the previous seminar that numbers are represented in the memory and on the CPU registers in the unsigned representation or the signed representation. And now we are saying numbers are represented in little-endian format in the memory. So which is it?

Well, every number in assembly is represented on 1, 2, 4 or 8 bytes (depending on the context in which it is declared; if we have this declaration: "a dw 2", then 2 will be represented on 2 bytes). It is first represented in binary using signed or unsigned representation. If the number is represented on more than 1 byte and in the memory (not on the CPU registers), the bytes of the signed or unsigned representation are then placed in the memory in little-endian format.

Example:

a DD 0

. . . .

mov dword [a], 12345

In the above instruction, the number 12345 is positive so it will be represented in the unsigned representation on 4 bytes as 0000 0000 0000 0000 0011 0000 0011 1001. Let's write this binary number in the hexadecimal base (as we know from seminar 1 that a group of 4 bits is a hexadecimal digit): 00003039h. This double word number will then be represented in memory in little-endian representation on 4 bytes as:

The memory addresses: "a", "a+1", "a+2", "a+3" represent the memory addresses of the 4 bytes of variable "a"; each address is the address of 1 byte. The byte from memory address "a" is the least significant byte of the number, the byte from memory address "a+1" is the next least significant byte of the number and so on. We usually use the hexadecimal base when we represent a number in the memory (because there are less digits) and we also know that 4 bits is a hexadecimal digit. The above little-endian representation is:
If we consider the next example:
mov dword [a], -12345
we first represent -12345 in the signed representation as 1111 1111 1111 1110 1111 1100 0111 and we consider this sequence on 32 bits in hexadecimal as FFFFCFC7h so this will be represented in the memory in little-endian format as:
The little-endian representation is important when we want to do "non-destructive conversions" like: refer to the low word of a double word from the memory, refer to the high byte of a word from the memory, etc.
Ex. 1. Write a program that computes the expression: $x:=a*b+c*d$ where all numbers are unsigned and represented on a word.
bits 32
global start
extern exit
import exit msvcrt.dll

```
segment data use32 class=data
        a dw 2
        b dw 5
        c dw 10
        d dw 40
        x dd 0
segment code use32 class=code
start:
        mov ax, [a]
        mul word [b]
                                ; DX:AX := AX * b = 2*5 = 10
        ; we save the doubleword DX:AX into x
        mov word [x], ax
                                ; save AX into the low word of "x" (i.e. the word from the address "x")
                                ; save DX into the high word of "x" (i.e. the word from the address "x+2")
        mov word [x+2], dx
        mov ax, [c]
        mul word [d]
                                        ; DX:AX := AX*d = c*d = 400
        ; add DX:AX to x
        add word [x], ax
                                ; we first add AX to the low word of "x"
                                ; if there is an overflow, the CF (Carry Flag) will be set to 1
                                ; otherwise CF will be set to zero
        adc word [x+2], dx
                                ; add DX to the high word of "x", but add also the CF
        ; call exit(0)
        push dword 0
        call [exit]
```

New instructions:

ADC – Add with Carry

adc dest, source => dest:=dest+source+CF

SBB – Substract with borrow

sbb dest, source => dest:=dest+source+CF

2. Conditional and unconditional jump instructions

Conditional jump instructions are just like the "IF" instruction in a high-level programming language. In assembly language, an "IF" is composed of 2 instructions: the compare instruction and the conditional jump instruction.

The compare instruction:

 \mathbf{cmp} a, b : performs a non-distructive $\mathbf{\mathit{sub}}\ a$, $\mathbf{\mathit{b}}$ (meaning that $\mathbf{\mathit{a}}$ does not change) and sets the flags accordingly

The conditional jump instructions check the value of specific flags and depending on this value, performs a "jump in the program" (i.e. moves the execution to a different part of the program - a part of the program is identified by a label). A conditional jump instruction makes sense and should follow a **cmp** instruction.

Conditional jump instructions that consider the numbers unsigned

jb label : (Jump if below) jumps to label if a<b

ibe label : (Jump if below or equal) jumps to label if a <= b

jnb label : (Jump if not below) jumps to label if a>=b

inbe label : (Jump if not below or equal) jumps to label if a>b

ja label : (Jump if above) jumps to label if a>b

jae label : (Jump if above or equal) jumps to label if a>=b

ina label : (Jump if not above) jumps to label if a <= b

jnae label : (Jump if not above or equal) jumps to label if a < b

The a and b values from above are the a and b operands of the **cmp** instruction that was issued before the conditional jump instruction.

Conditional jump instructions that consider the numbers signed

il label : (Jump if less) jumps to label if a < b

jle label : (Jump if less or equal) jumps to label if a<=b

inl label : (Jump if not less) jumps to label if a>=b

inle label : (Jump if not less or equal) jumps to label if a>b

ig label : (Jump if greater) jumps to label if a>b

ige label : (Jump if greater or equal) jumps to label if a>=b

ing label : (Jump if not greater) jumps to label if a <= b

jnge label : (Jump if not greater or equal) jumps to label if a < b

The a and b values from above are the a and b operands of the **cmp** instruction that was issued before the conditional jump instruction.

Conditional jump instructions that consider one flag

jc label ;Jump if CF=1 (carry flag)

inc label

je label ;Jump if ZF=1 (zero flag)

jz label ;Jump if ZF=1

jne label

jnz label

js label ;Jump if SF = 1 (sign flag)

jns label

jp label ;Jump if PF = 1 (parity flag)

jnp label

```
jo label
                    ;Jump if OF =1 (overflow flag)
jno label
Conditional jump instructions that check the value of CX or ECX
                        ;Jump if CX = 0
Jcxz label
                       ;Jump if ECX = 0
Jecxz label
Unconditional jump instruction
jmp label
             : always jumps to the specified label
Example if-then
if a>1 then
   a++
a db 10
cmp byte [a], 1
jbe noinc ; we need the oposite condition to skip the instructions inside the if clause and jump to label noinc
       inc byte [a]
noinc:
Example: If-else statement in assembly:
If a>1 then
   a++
else
   b++
```

```
In assembly the solution is:

a db 10

b db 20
....

cmp byte [a], 1

jbe incb ; we start with the oposite condition to do the jump

inc byte [a]

jmp overelse ; we skip the instruction in the else, otherwise the exection continues incb:

inc byte [b]

overelse:
```

3. Working with strings of bytes


Memory addresses and offsets

In order to work with strings of bytes/words/dwords we need to know more about memory addresses. So far, we have used expressions like:

```
mov ax, [a]
```

where a is a variable and the instruction above moves a word value from the memory starting at the memory address "a". We have seen so far that a variable name is just a constant address – the address of that variable in the memory. To be more precise, a variable name is a constant offset. A full address specification comes in the form of two numbers: segment_selector: offset. A segment_selector is a 16-bit number and specifies a pointer in a segment descriptor table (GDT – global descriptor table) which defines a memory zone. For today's seminar you don not really need to understand what a memory segment is (you will find more details about memory segments and memory management at the course), just know that a memory segment is a continuous memory zone and its address is already stored in the appropriate segment register (CS, DS, ES or SS) by the

operating system before your program starts and you are not allowed to change it. The **offset** is a 32-bit number which specifies a pointer inside the segment specified by the **segment_selector**. The name of a variable, like I have said before, represents just the offset of that variable (the segment to which this offset refers to is the data segment whose starting address is already placed in the DS register by the operating system). The full format of an offset includes 4 quantities: a base, an index, a scale and a displacement and is presented below in the following figure:



In an offset specification any combination of the above 4 quantities can appear (inside "[]"), including each component individually. The displacement is just a constant number. Below you can find some examples of offset specifications (as the second operand of the instruction):

```
mov ax, [a] ; only displacement

mov ax, [eax] ; only base or index

mov ax, [a+eax+ebx] ; base, index and displacement

mov ax, [eax+eax+a+2]; base, index and displacement

mov ax, [a+4+ebx*2] ; index, scale (i.e. 2) and displacement

mov ax, [eax + ebx*4 + 20]; base, index, scale (i.e. 4) and displacement
```


Ex.2. Being given a string of bytes containing lowercase letters, build a new string of bytes containing the corresponding uppercase letters.

Method 1:

```
bits 32
global start
extern exit
import exit msvcrt.dll
```

```
segment data use32 class=data
    s1 db 'abcdef'
    lenS1 equ $-s1
    s2 times lenS1 db 0
```

; the data segment looks in the memory like this:



; the top row in the above figures represents offsets. For example, in OllyDebugger, the first byte; from the data segment and thus the offset of sI is always 0×00401000 . The offset of variable s2; is equal to the offset of sI plus 6 (i.e. 0×00401006). The bottom grow gregoresents the actual

; values from the memory in base 10 (97 is the ASCII code of 'a', 98 is the ASCII code of 'b', 99; is the ASCII code of 'c' ...). The bytes from string s2 are initialized with zero.

; lenS1 equ \$-s1 defines a constant (equ = constant, no memory space is reserved)

; \$ is the location counter, the current offset in the data segment up to the code line in which it

; appears. So, before the code line $lenS1\ equ\$ \$-s1 , there were 6 bytes generated in the string s1

; so the current offset is \$=s1+6. s1 in the above instruction is just the offset of variable s1, so

; len1 =\$ - s1 = s1+6-s1 = 6 bytes (the length in bytes of string s1).

; s2 times lenS1 db 0 defines a variable s2 which contains lenS1=6 bytes, all initialized with

; the value zero.

segment code use32 class=code

start:

; we solve this problem by considerring in ESI the current index in string s1 and string s2; and we do a loop with lenS1=6 iterations and at each iteration we move the byte s1[ESI]; into s2[ESI], after we change it to an uppercase letter. So, in this loop, ESI will have the ; values: 0, 1, 2, 3, 4, 5.

```
mov esi, 0
     repeat:
         mov al, [s1+esi]; AL <- the byte from the offset s1+esi
         sub al, 'a' -'A' ; obtain the corresponding uppercase letter in AL
         mov [s2+esi], al ; AL -> the byte from the offset s2+esi
         inc esi
                                ; esi:=esi+1; move to the next index in strings s1 and s2
         cmp esi, lenS1
                                ; IF (esi < lenS1) jump to repeat,
         jb repeat
                                ; otherwise continue below
    push dword 0
     call [exit]
Method 2:
bits 32
global start
extern exit
import exit msvcrt.dll
segment data use32 class=data
     s1 db 'abcdef'
     lenS1 equ $-s1
     s2 times lenS1 db 0
```

; this time we solve this problem by considerring in ESI the offset of the current byte from

segment code use32 class=code

start:

```
; string s1 and in EDI the offset of the current byte from string s2. We do a loop with
; lenS1=6 iterations and at each iteration we move the byte from offset ESI into the byte
; from offset EDI, after we change it to an uppercase letter. So, in this loop, ESI will have
; the values: s1+0, s1+1, s1+2, s1+3, s1+4, s1+5 and EDI will have the values: s1+6, s1+7,
; s1+8, s1+9, s1+10, s1+11.
mov esi, s1 ; initialize esi
mov edi, s2 ; initialize edi
mov ecx, lenS1; ecx will store the number of iterations in the loop
repeat:
                        ; AL <- the byte from the offset s1+esi
     mov al, [esi]
      sub al, 'a' -'A'; obtain the corresponding uppercase letter in AL
     mov [edi], al
                         ; AL -> the byte from the offset s2+edi
                ; esi:=esi+1; move to the next byte in strings s1
      inc esi
                     ; edi:=edi+1; move to the next byte in strings s2
      inc edi
      dec ecx
                     ; exc = ecx-1
      cmp ecx, 0; IF (ecx > 0) jump to repeat
                     ; otherwise exit the loop
      jb repeat
push dword 0
call [exit]
```

Instructions for loops

LOOP label

- Continues the loop as long as the value of ECX $\neq 0$
- It is equivalent to these 3 instructions:

; dec ecx ; cmp ecx, 0 ; ja label

LOOPE / LOOPZ

- Continues the loop as long as the value of ECX \neq 0 and ZF = 1

- So the cycle terminating either if ECX = 0 or if ZF = 0.

LOOPNE / LOOPNZ

- Continues the loop as long as the value of ECX \neq 0 and ZF = 0
- So the cycle terminating either if ECX = 0 or if ZF = 1.

Method 3:

```
bits 32
global start
extern exit
import exit msvcrt.dll
segment data use32 class=data
    s1 db 'abcdef'
    lenS1 equ $-s1
    s2 times lenS1 db 0
segment code use32 class=code
start:
    mov esi, s1 ; initialize esi
    mov edi, s2 ; initialize edi
    mov ecx, lenS1; ecx will store the number of iterations in the loop
    jecxz finished
    repeat:
                          ; AL <- the byte from the offset s1+esi
         mov al, [esi]
         sub al, 'a' -'A'
                                  ; obtain the corresponding uppercase letter in AL
                                   ; AL -> the byte from the offset s2+edi
         mov [edi], al
                       ; esi:=esi+1; move to the next byte in strings s1
         inc esi
         inc edi
                       ; edi:=edi+1; move to the next byte in strings s2
         loop repeat
    finished:
    push dword 0
    call [exit]
```

Problem 2:

An array of doublewords S of length 1 is given. Obtain the array D of length 1-1, such that each element of D is the remainder of two consecutive elements of S, i.e. D(i) = S(i) % S(i+1). Use signed interpretation of numbers.

```
bits 32
global start
extern exit
import exit msvcrt.dll
segment data use32 class=data
    s dd 100, 26, 19, 5, 10
    len equ (\$-s)/4
    d times len dd 0
    ; signed interpretation of numbers
; our code starts here
segment code use32 class=code
    start:
        mov esi, s
        mov edi, d
        mov ecx, len-1
        jecxz endloop
        repeta:
            mov eax, [esi]
            cdq ; edx:eax = first elem
            mov ebx, [esi+4] ; second elem
            idiv ebx ; edx=edx:eax%ebx remainder
            mov [edi], edx
            add esi, 4 ; 4 positions because we have array of double words
                       ; doubleword is 4 bytes
            add edi, 4
        loop repeta
        endloop:
                             ; push the parameter for exit onto the stack
        push
                dword 0
        call
                [exit]
                             ; call exit to terminate the program
```

Problem 3:

Compute the sum of odd numbers in an array of words, using unsigned interpretation.

```
bits 32
global start
extern exit
import exit msvcrt.dll
segment data use32 class=data
    s dw 10,11,12,13,14,15
    len equ (\$-s)/2
    ; compute the sum of odd numbers unsigned
    two db 2
segment code use32 class=code
    start:
        mov bx, 0; initialize the sum
        mov esi, s
        mov ecx, len
        jecxz endloop
        sumloop:
           mov ax, [esi]
           div byte [two]; Al=ax/2; AH=Ax%2
           cmp ah, 1 ; check ramained is 1
           jne dontadd ; if it's not 1 don;t add the number
               add bx, [esi] ; if it is one, jump is not taken
           dontadd:
           add esi, 2; increment with 2 because we have array of words
        loop sumloop
        endloop:
        push dword 0
        call [exit]
```