Chapter 3
Transport Layer

A note on the use of these PowerPoint slides:


We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we'd like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

For a revision history, see the slide note for this page.

Thanks and enjoy! JFK/KWR

All material copyright 1996-2023
J.F Kurose and K.W. Ross, All Rights Reserved



Computer Networking: A Top-Down Approach

8th edition
Jim Kurose, Keith Ross
Pearson, 2020

Transport layer: overview

Our goal:

- understand principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- learn about Internet transport layer protocols:
  - UDP: connectionless transport
  - TCP: connection-oriented reliable transport
  - TCP congestion control


Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control




Transport services and protocols

- provide *logical communication* between application processes running on different hosts
- transport protocols actions in end systems:
  - sender: breaks application messages into *segments*, passes to network layer
  - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
  - TCP, UDP




Transport Layer Actions



Sender:

- is passed an application-layer message
- determines segment header fields values
- creates segment
- passes segment to IP

Transport Layer Actions




Receiver:

- receives segment from IP
- checks header values
- extracts application-layer message
- demultiplexes message up to application via socket

Two principal Internet transport protocols

- **TCP:** Transmission Control Protocol
  - reliable, in-order delivery
  - congestion control
  - flow control
  - connection setup
- **UDP:** User Datagram Protocol
  - unreliable, unordered delivery
  - no-frills extension of “best-effort” IP
- services *not* available:
  - delay guarantees
  - bandwidth guarantees



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control




Multiplexing/demultiplexing


multiplexing as sender:

handle data from multiple sockets, add transport header (later used for demultiplexing)


demultiplexing as receiver:


use header info to deliver received segments to correct socket





client
application
NETFLIX
transport
$H_n H_t$ HTTP msg
link
physical
HTTP server
APACHE
HTTP SERVER
HTTP msg
H_t HTTP msg
$H_n H_t$ HTTP msg
link
physical
application
transport
network
link
physical
$H_n H_t$ HTTP msg

Q: how did transport layer know to deliver message to Firefox browser process rather then Netflix process or Skype process?






multiplexing



NETFLIX
application
transport
multiplexing



Multiplexing



de-multiplexing




de-multiplexing



Demultiplexing

How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries one transport-layer segment
  - each segment has source, destination port number
- host uses *IP addresses & port numbers* to direct segment to appropriate socket



TCP/UDP segment format

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control



UDP: User Datagram Protocol

Due to Coronovirus (COVID19) all TCP applications are being converted to UDP to avoid Handshakes.

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
  - lost
  - delivered out-of-order to app
- *connectionless:*
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
  - UDP can blast away as fast as desired!
  - can function in the face of congestion

UDP: User Datagram Protocol

- UDP use:
  - streaming multimedia apps (loss tolerant, rate sensitive)
  - DNS
  - SNMP
  - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
  - add needed reliability at application layer
  - add congestion control at application layer

UDP: User Datagram Protocol [RFC 768]

INTERNET STANDARD

RFC 768

J. Postel
ISI
28 August 1980


User Datagram Protocol

Introduction


This User Datagram Protocol (UDP) is defined to make available a datagram mode of packet-switched computer communication in the environment of an interconnected set of computer networks. This protocol assumes that the Internet Protocol (IP) [1] is used as the underlying protocol.

This protocol provides a procedure for application programs to send messages to other programs with a minimum of protocol mechanism. The protocol is transaction oriented, and delivery and duplicate protection are not guaranteed. Applications requiring ordered reliable delivery of streams of data should use the Transmission Control Protocol (TCP) [2].


Format



UDP: Transport Layer Actions




UDP: Transport Layer Actions



UDP sender actions:

- is passed an application-layer message
- determines UDP segment header fields values
- creates UDP segment
- passes segment to IP


UDP: Transport Layer Actions



UDP receiver actions:


- receives segment from IP
- checks UDP checksum header value
- extracts application-layer message
- demultiplexes message up to application via socket

UDP segment header



UDP checksum

Goal: detect errors (*i.e.*, flipped bits) in transmitted segment



Internet checksum

Goal: detect errors (*i.e.,* flipped bits) in transmitted segment

sender:


- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - not equal - error detected
  - equal - no error detected. *But maybe errors nonetheless?* More later ….

Internet checksum: an example


example: add two 16-bit integers



Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

Internet checksum: weak protection!

example: add two 16-bit integers



Summary: UDP

- "no frills" protocol:
  - segments may be lost, delivered out of order
  - best effort service: "send and hope for the best"
- UDP has its plusses:
  - no setup/handshaking needed (no RTT incurred)
  - can function when network service is compromised
  - helps with reliability (checksum)
- build additional functionality on top of UDP in application layer (e.g., HTTP/3)

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control




Principles of reliable data transfer



reliable service *abstraction*

Principles of reliable data transfer


reliable service *abstraction*



reliable service *implementation*

Principles of reliable data transfer

Complexity of reliable data transfer protocol will depend (strongly) on characteristics of unreliable channel (lose, corrupt, reorder data?)




reliable service *implementation*

Principles of reliable data transfer


Sender, receiver do *not* know the "state" of each other, e.g., was a message received?

- unless communicated via a message



reliable service *implementation*


Reliable data transfer protocol (rdt): interfaces



Reliable data transfer: getting started

We will:


- incrementally develop sender, receiver sides of reliable data transfer protocol (`rdt`)
- consider only unidirectional data transfer
  - but control info will flow in both directions!
- use finite state machines (FSM) to specify sender, receiver




rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - no bit errors
  - no loss of packets
- *separate* FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver reads data from underlying channel







rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
  - checksum (e.g., Internet checksum) to detect bit errors
- *the* question: how to recover from errors?

rdt2.0: channel with bit errors


- underlying channel may flip bits in packet
  - checksum to detect bit errors
- *the* question: how to recover from errors?
  - *acknowledgements (ACKs):* receiver explicitly tells sender that pkt received OK
  - *negative acknowledgements (NAKs):* receiver explicitly tells sender that pkt had errors
  - sender *retransmits* pkt on receipt of NAK

stop and wait


sender sends one packet, then waits for receiver response

rdt2.0: FSM specifications

sender



rdt2.0: FSM specification




Note: "state" of receiver (did the receiver get my message correctly?) isn't known to sender unless somehow communicated from receiver to sender


- that's why we need a protocol!



rdt2.0: operation with no errors



rdt2.0: corrupted packet scenario



rdt2.0 has a fatal flaw!

what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds *sequence number* to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


stop and wait

sender sends one packet, then waits for receiver response

rdt2.1: sender, handling garbled ACK/NAKs



rdt2.1: receiver, handling garbled ACK/NAKs



rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "expected" pkt should have seq # of 0 or 1

receiver:


- must check if received packet is duplicate
  - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can *not* know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - receiver must *explicitly* include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: *retransmit current pkt*

As we will see, TCP uses this approach to be NAK-free

rdt2.2: sender, receiver fragments



rdt3.0: channels with errors *and* loss

New channel assumption: underlying channel can also *lose* packets (data, ACKs)

- checksum, sequence #s, ACKs, retransmissions will be of help … but not quite enough

Q: How do *humans* handle lost sender-to-receiver words in conversation?

rdt3.0: channels with errors *and* loss


Approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but seq #s already handles this!
  - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after "reasonable" amount of time




timeout


rdt3.0 sender




rdt3.0 sender



rdt3.0 in action




(a) no loss




(b) packet loss

rdt3.0 in action



(c) ACK loss



(d) premature timeout/ delayed ACK


Performance of rdt3.0 (stop-and-wait)

- U_{sender}: *utilization* – fraction of time sender busy sending

- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
  - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

rdt3.0: stop-and-wait operation




rdt3.0: stop-and-wait operation

$$U_{sender} = \frac{L / R}{RTT + L / R}$$

$$= \frac{.008}{30.008}$$

$$= 0.00027$$




- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

rdt3.0: pipelined protocols operation


pipelining: sender allows multiple, “in-flight”, yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver



(a) a stop-and-wait protocol in operation

Pipelining: increased utilization




3-packet pipelining increases utilization by a factor of 3!

$$U_{sender} = \frac{3L / R}{RTT + L / R} = \frac{.0024}{30.008} = 0.00081$$

Go-Back-N: sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
  - k-bit seq # in pkt header





- *cumulative ACK:* ACK(*n*): ACKs all packets up to, including seq # *n*
  - on receiving ACK(*n*): move window forward to begin at *n+1*
- timer for oldest in-flight packet
- *timeout(n):* retransmit packet n and all higher seq # packets in window

Go-Back-N: receiver


- ACK-only: always send ACK for correctly-received packet so far, with highest *in-order* seq #
  - may generate duplicate ACKs
  - need only remember `rcv_base`
- on receipt of out-of-order packet:
  - can discard (don't buffer) or buffer: an implementation decision
  - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:






Go-Back-N in action



Selective repeat: the approach

- *pipelining*: *multiple* packets in flight
- *receiver individually ACKs* all correctly received packets
  - buffers packets, as needed, for in-order delivery to upper layer
- sender:
  - maintains (conceptually) a timer for each unACKed pkt
    - timeout: retransmits single unACKed packet associated with timeout
  - maintains (conceptually) "window" over *N* consecutive seq #s
    - limits pipelined, "in flight" packets to be within this window

Selective repeat: sender, receiver windows



(a) sender view of sequence numbers

Selective repeat: sender and receiver

sender

data from above:

- if next available seq # in window, send packet

timeout(*n*):

- resend packet *n*, restart timer

ACK(*n*) in [sendbase,sendbase+N-1]:

- mark packet *n* as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet *n* in [rcvbase, rcvbase+N-1]

- send ACK(*n*)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yet-received packet


packet *n* in [rcvbase-N,rcvbase-1]

- ACK(*n*)

otherwise:

- ignore


Selective Repeat in action




Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3



(a) no problem




(b) oops!

Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: what relationship is needed between sequence # size and window size to avoid problem in scenario (b)?



Chapter 3: roadmap


- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
  - one sender, one receiver
- reliable, in-order *byte steam:*
  - no “message boundaries"
- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- cumulative ACKs
- pipelining:
  - TCP congestion and flow control set window size
- connection-oriented:
  - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

TCP segment structure



TCP sequence numbers, ACKs

Sequence numbers:


- byte stream "number" of first byte in segment's data

Acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments

- *A:* TCP spec doesn't say, - up to implementor



TCP round trip time, timeout

Q: how to set TCP timeout value?

- longer than RTT, but RTT varies!
- *too short:* premature timeout, unnecessary retransmissions
- *too long:* slow reaction to segment loss


Q: how to estimate RTT?

- `SampleRTT`: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- `SampleRTT` will vary, want estimated RTT "smoother"
  - average several *recent* measurements, not just current `SampleRTT`

TCP round trip time, timeout

EstimatedRTT = (1- α)*EstimatedRTT + α*SampleRTT

- exponential weighted moving average (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125



TCP round trip time, timeout

- timeout interval: **EstimatedRTT** plus "safety margin"
  - large variation in **EstimatedRTT**: want a larger safety margin

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```



estimated RTT

"safety margin"

- **DevRTT**: EWMA of **SampleRTT** deviation from **EstimatedRTT**:

```
DevRTT = (1-β)*DevRTT + β*|SampleRTT-EstimatedRTT|
```

(typically, β = 0.25)

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval: **`TimeOutInterval`**


event: timeout

- retransmit segment that caused timeout
- restart timer


event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments

TCP: retransmission scenarios




lost ACK scenario



premature timeout

TCP: retransmission scenarios



TCP fast retransmit


TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

- likely that unACKed segment lost, so don't wait for timeout



Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!




Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- Principles of congestion control
- TCP congestion control



TCP flow control


Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?






receiver protocol stack


TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



flow control: # bytes receiver willing to accept

Application removing data from TCP socket buffers




receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?


flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast



TCP flow control


- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow



TCP receiver-side buffering

TCP flow control


- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow




TCP connection management

before exchanging data, sender/receiver “handshake”:

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)







```
Socket clientSocket =
  newSocket("hostname","port number");
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

Agreeing to establish a connection


2-way handshake:



Q: will 2-way handshake always work in network?

- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side


2-way handshake scenarios



No problem!




2-way handshake scenarios



Problem: half open connection! (no client)

2-way handshake scenarios



Problem: dup data accepted!

TCP 3-way handshake

Client state

```
clientSocket = socket(AF_INET, SOCK_STREAM)
```

LISTEN

```
clientSocket.connect((serverName,serverPort))
```



choose init seq num, x
send TCP SYN msg

SYNSENT

SYNbit=1, Seq=x



choose init seq num, y
send TCP SYNACK
msg, acking SYN

SYNbit=1, Seq=y
ACKbit=1; ACKnum=x+1

received SYNACK(x)
indicates server is live;
send ACK for SYNACK;
this segment may contain
client-to-server data

ESTAB

ACKbit=1, ACKnum=y+1

received ACK(y)
indicates client is live

Server state

```
serverSocket = socket(AF_INET,SOCK_STREAM)
serverSocket.bind(('',serverPort))
serverSocket.listen(1)
connectionSocket, addr = serverSocket.accept()
```

LISTEN

SYN RCVD

ESTAB

A human 3-way handshake protocol



Closing a TCP connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- **Principles of congestion control**
- TCP congestion control
- Evolution of transport-layer functionality



Principles of congestion control

Congestion:

- informally: “too many sources sending too much data too fast for *network* to handle”
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!






congestion control:
too many senders,
sending too fast

flow control: one sender
too fast for one receiver

Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream



Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



TCP congestion control: AIMD


- *approach:* senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase

increase sending rate by 1 maximum segment size every RTT until loss detected

Multiplicative Decrease

cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD – a distributed, asynchronous algorithm – has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

TCP congestion control: details



TCP sending behavior:


- *roughly:* send `cwnd` bytes, wait RTT for ACKS, then send more bytes

$$\text{TCP rate} \approx \frac{\texttt{cwnd}}{\text{RTT}} \text{ bytes/sec}$$

- TCP sender limits transmission: **`LastByteSent- LastByteAcked ≤ cwnd`**
- `cwnd` is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially **`cwnd`** = 1 MSS
  - double **`cwnd`** every RTT
  - done by incrementing **`cwnd`** for every ACK received
- *summary:* initial rate is slow, but ramps up exponentially fast




TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?


A: when **`cwnd`** gets to 1/2 of its value before timeout.

Implementation:

- variable **`ssthresh`**
- on loss event, **`ssthresh`** is set to 1/2 of **`cwnd`** just before loss event




Summary: TCP congestion control




TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
  - W_{max}: sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn't changed much
  - after cutting rate/window in half on loss, initially ramp to to W_{max} *faster*, but then approach W_{max} more *slowly*




TCP CUBIC

- K: point in time when TCP window size will reach W_{max}
  - K itself is tunable
- increase W as a function of the *cube* of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*




TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the *bottleneck link*
- understanding congestion: useful to focus on congested bottleneck link



Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



$$\text{measured throughput} = \frac{\text{\# bytes sent in last RTT interval}}{RTT_{measured}}$$

Delay-based approach:

- RTT_{min} - minimum observed RTT (uncongested path)
- uncongested throughput with congestion window `cwnd` is cwnd/RTT_{min}

if measured throughput "very close" to uncongested throughput
    increase `cwnd` linearly /* since path not congested */
else if measured throughput "far below" uncongested throughout
    decrease `cwnd` linearly /* since path is congested */


Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full… ") while keeping delay low ("…but not fuller")
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google's (internal) backbone network

Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked *by network router* to indicate congestion
  - *policy* to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



TCP fairness


Fairness goal: if *K* TCP sessions share same bottleneck link of bandwidth *R*, each should have average rate of *R/K*



Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

Fairness: must all network apps be “fair”?

Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss
- there is no “Internet police” policing use of congestion control

Fairness, parallel TCP connections

- application can open *multiple* parallel connections between two hosts
- web browsers do this , e.g., link of rate R with 9 existing connections:
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2

Chapter 3: summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

Up next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network-layer chapters:
  - data plane
  - control plane