50.039 – Theory and Practice of Deep Learning

Alex

Week 03: Pytorch basics I

[The following notes are compiled from various sources such as textbooks, lecture materials, Web resources and are shared for academic purposes only, intended for use by students registered for a specific course. In the interest of brevity, every source is not cited. The compiler of these notes gratefully acknowledges all such sources.]

Key content

- pytorch tensors: numpy with GPU transfer option
 - linear algebra similar to numpy
 - torch.einsum for general tensor multiplications with summing
 - data is stored in .data field
- pytorch broadcasting rules
- when one needs to use only data or handle gradients, tensor have .data and .grad.data fields

1 Pytorch tensor basics

https://pytorch.org/tutorials/beginner/blitz/tensor_tutorial.html#sphx-glr-beginner-blitz-tensor-tutorial-py

Tensor mathematically:

- 1-tensor: a linear mapping $v_1 \mapsto L(v_1)$, representable as $L(v_1) = u \cdot v_1$ by a vector $u = (u_i)$
- 2-tensor: a bilinear mapping $v_1, v_2 \mapsto L(v_1, v_2)$, representable as $L(v_1, v_2) = v_1^t A v_2 = \sum_{ij} v_{1,i} v_{2,j} A_{ij}$ by a matrix $A = (A_{ij})$
- 3-tensor: a trilinear mapping $v_1, v_2, v_3 \mapsto L(v_1, v_2, v_3)$, representable as $L(v_1, v_2, v_3) = \sum_{ijk} v_{1,i} v_{2,j} v_{3,k} A_{ijk}$ by a 3-dim array $A = (A_{ij})$
- \bullet n-tensor ... n-linear mapping ... representable by a n-dim array $A=(A_{i_1\cdots i_n})$
- n-tensors \leftrightarrow n-dim arrays

Tensor in pytorch:

placement

a representation of an numpy-array-like structure A_i or $A_{i,j,k}$ or $A_{i,j,k}$ or $A_{i,j,k,l}$ with possibly more than 2 indices with benefits (for storing computed gradients).

init tensor as zeros, ones, constants

```
x= torch.empty((2,3)) %empty tensor
```

A tensor has three important properties:

- its .size() or .shape
- the dtype: its numerical type (most nns use torch.float32)
- device it is placed on (cpu, cuda:0, cuda:1)

```
getting its size: output is a torch.Size() object.
print(x.size())
print(x.shape)
Use list or tuple to get a list/tuple from that.
xs=tuple(x.size())
print(type(xs))
print(xs)
print(xs[0])
get its dtype:
print(x.dtype)
get its device placement
print(x.device)
x.device is a torch.device class
if you need strings, use .__repr__().
Test for equality with
x.device==torch.device('cuda:0')
x.dtype==torch.float %rhs is a torch.dtype object
x.dtype.__repr__() == 'torch.float32'
Important: you can print these anywhere in your execution code. no ugly fixed
graph surprises.
x= torch.zeros((5,1))
y= torch.ones((5))
z= torch.empty((3,2,3))
a= torch.new_full((3,2),42.) # tensor with a value
```

https://pytorch.org/docs/stable/tensors.html-dtypes and tensor types. dtype is the type of one element. tensor type depends on dtype and device

1.2 tensor from numpy

```
a=np.random.normal(5,size=(2,3)).astype('float32')
x=torch.tensor(a) % this copies data
x2=torch.as_tensor(a) % this does NOT COPY data , and does nothing if its a tensor with ri
x3=torch.from_numpy( a) % this does NOT COPY data - when this can be inappropriate? not re
```

1.3 tensor to numpy

t=x.data.numpy() #x.numpy() works only if x has no gradient attached)later(

1.4 change shape: reshape a tensor

```
a.view(...)
x=torch.ones((10))
x=x.view((-1,5))
```

Be careful which element lands where after reshaping!

1.5 change device: move tensor to gpu / cpu device

```
device=torch.device('cuda:0')
xg=x.to(device)
xc=x.to(torch.device('cpu'))
```

1.6 change tensor dtype

```
https://pytorch.org/docs/stable/tensors.html
print your type
print(x.type())
cast tensor
x=x.type(torch.FloatTensor) % pretty common error source in dataloaders
x=x.type_as(a) # a is another tensor
```

1.7 create tensor of same type and device as another tensor

This is useful when one uses torch.nn.DataParallel for multi-GPU computations – then one does not want to instantiate a tensor explicitly on a fixed GPU like cuda:0.

```
b=a.new_ones((3,2))
```

1.8 other useful stuff

res=torch.where(x>5,x,y)

https://pytorch.org/docs/stable/tensors.html

Debugging in pytorch

Most of my own programming errors come from above three properties: try to compute results

- with incompatible shapes.
- from two tensors with incompatible numerical type (integer and float, float32 and double),
- with incompatible devices (one on cpu, other on GPU),

The good news: in pytorch you can print .size() anywhere in the running code, also its dtype and its device placement

debugging advice: RTFM and print the shapes.

2 broadcasting

https://pytorch.org/docs/stable/notes/broadcasting.html

```
a = torch.ones((4))
b = torch.ones((1,4))
torch.add(a,b) \rightarrow (1,4)
a = torch.ones((4))
b = torch.ones((4,1))
torch.add(a,b) \rightarrow (4,4)!!!
a = torch.ones((3))
b = torch.ones((4,1))
torch.add(a,b) \rightarrow (4,3)
a = torch.ones((3))
b = torch.ones((1,4))
torch.add(a,b) \rightarrow ERR
```

• smaller tensor gets filled **from the left** with singleton dimensions until he has same dimensionality as larger tensor, as if .unsqueeze(0) would be applied again and again

$$a = torch.ones((2,5))$$

$$b = torch.ones((5))$$

$$torch.add(a,b) \rightarrow (2,5)$$

$$\rightarrow a = torch.ones((2,5)) \text{ ok as is}$$

$$\rightarrow b = torch.ones((1,5)) \text{ copy 1x until } (2,5)$$

$$a = torch.ones((3))$$

$$b = torch.ones((4,1))$$

$$torch.add(a,b) \rightarrow (4,3)$$

$$\rightarrow a = torch.ones((1,3)) \text{ copy 3x until } (4,3)$$

$$\rightarrow b = torch.ones((4,1)) \text{ copy 2x until } (4,3)$$

• whenever a dimension with size 1 meets a dimension with a size k > 1, then the smaller vector is replicated/copied k - 1 times in this dimension until he reaches in this dimension size k

2.1 linear algebra: sum, inner product, matrix product

 ${\tt torch.mm(a,b)}$ dot product, not broadcasting. a,b must be 1-tensors

$$\begin{split} a.size() &= (d) \\ b.size() &= (d) \\ torch.dot(a,b) &= \sum_{d'} a_{d'}b_{d'} = \sum_{d'} a[d']b[d'] \rightarrow torch.dot(a,b).size() = () \end{split}$$

torch.mm(A,B) matrix multiplication, not broadcasting. A, B must be 2-tensors

$$\begin{split} A.size() &= (i,k) \\ B.size() &= (k,l) \\ torch.mm(A,B)[i,l] &= \sum_{k'} A_{i,k'} B_{k',l} = \sum_{k} A[i,k'] B[k',l] \rightarrow torch.mm(A,B).size() = (i,l) \end{split}$$

torch.bmm(A,B) batched matrix multiplication, not broadcasting. A, B must be 3-tensors. multiplication along last dim of A and second dim of B.

$$\begin{aligned} A.size() &= (b,i,k) \\ B.size() &= (b,k,l) \\ torch.bmm(A,B)[b,i,l] &= \sum_{k'} A_{b,i,k'} B_{b,k',l} = \sum_{k} A[b,i,k'] B[b,k',l] \rightarrow torch.bmm(A,B).size() = (b,i,l) \end{aligned}$$

torch.matmul(A,B) - matrix multiplication with broadcasting - that is only 1 dimension is summed out https://pytorch.org/docs/stable/torch.html# torch.matmul This function is a bit tricky, performs broadcasting of shapes (https://pytorch.org/docs/stable/notes/broadcasting.html), then multiplies along the last dimension of A, and over the second last dimension of B - torch.einsum is more clear here.

Broadcasting warning

You cannot avoid getting to know the broadcasting rules (quiz?).

many simple functions like +, * do broadcasting by default.

torch.tensordot(A,B, dims=(list1,list2)) - general tensor contractions
with broadcasting - that is multiple dimensions can be summed out https:
//pytorch.org/docs/stable/torch.html#torch.tensordot

torch.einsum

a general way to do all kinds of batched and non-batched tensor multiplications: torch.einsum

https://rockt.github.io/2018/04/30/einsum

rule:

left of ->: all tensors separated by , which are to be multiplied and summed.

indices that have same name in multiple tensors, will get multiplied together

right of -> the result tensor with remaining indices. All indices missing right of -> are summed out so that they vanish in the result.

2.2 linear algebra: shapes dont fit?!

torch.squeeze(A,dim=2) - remove singleton dim $(a,b,1,c) \rightarrow (a,b,c)$

torch.unsqueeze(A,dim=1) - insert singleton dim $(a,b,c) \to (a,1,b,c)$ torch.unsqueeze(A,dim=0) - insert singleton dim $(a,b,c) \to (1,a,b,c)$

example: want to compute with mm matrix vector product $(vA)_l = \sum_k v_k A_{k,l}$. v is 1-tensor, so cannot use torch.mm(v,A). So add a singleton dimension in v:

$$torch.mm(v.unsqueeze(0),A) \rightarrow (1,L)$$

$$torch.mm(v.unsqueeze(0),A).squeeze(0) \rightarrow (1,L) \rightarrow (L)$$

torch.transpose(A,dim1,dim2) swaps two dimensions
torch.Tensor.permute(*dims) permutes a set of dimensions rather than just
swapping two