


Chapter 12: I/O Systems





Chapter 12: I/O Systems

- Overview
- I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance





Objectives

- Explore the structure of an operating system's I/O subsystem
- Discuss the principles and complexities of I/O hardware
- Explain the performance aspects of I/O hardware and software





Overview

- I/O management is a major component of operating system design and operation
 - Important aspect of computer operation
 - I/O devices vary greatly
 - Various methods to control them
 - Performance management
 - New types of devices frequent
- Ports, busses, device controllers connect to various devices
- **Device drivers** encapsulate device details
 - Present uniform device-access interface to I/O subsystem





I/O Hardware

- Incredible variety of I/O devices
 - Storage
 - Transmission
 - Human-interface
- Common concepts – signals from I/O devices interface with computer
 - **Port** – connection point for device
 - **Bus - daisy chain** or shared direct access
 - 4 **PCI** bus common in PCs and servers, PCI Express (**PCle**)
 - 4 **expansion bus** connects relatively slow devices
 - 4 **Serial-attached SCSI (SAS)** common disk interface






I/O Hardware (Cont.)

- **Controller (host adapter)** – electronics that operate port, bus, device
 - 4 Sometimes integrated
 - 4 Sometimes separate circuit board (host adapter)
 - 4 Contains processor, microcode, private memory, bus controller, etc.
 - Some talk to per-device controller with bus controller, microcode, memory, etc.





A Typical PC Bus Structure





I/O Hardware (Cont.)

- **Fibre channel (FC)** is complex controller, usually separate circuit board (**host-bus adapter, HBA**) plugging into bus
- I/O instructions control devices
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
 - Data-in register, data-out register, status register, control register
 - Typically 1-4 bytes, or FIFO buffer






I/O Hardware (Cont.)

- Devices have addresses, used by
 - Direct I/O instructions
 - **Memory-mapped I/O**
 - 4 Device data and command registers mapped to processor address space
 - 4 Especially for large address spaces (graphics)





Device I/O Port Locations on PCs (partial)



I/O address range (hexadecimal)	device
000–00F	DMA controller
020–021	interrupt controller
040–043	timer
200–20F	game controller
2F8–2FF	serial port (secondary)
320–32F	hard-disk controller
378–37F	parallel port
3D0–3DF	graphics controller
3F0–3F7	diskette-drive controller
3F8–3FF	serial port (primary)





Polling

- For each byte of I/O
 1. Read busy bit from status register until 0
 2. Host sets read or write bit and if write copies data into data-out register
 3. Host sets command-ready bit
 4. Controller sets busy bit, executes transfer
 5. Controller clears busy bit, error bit, command-ready bit when transfer done
- Step 1 is **busy-wait** cycle to wait for I/O from device
 - Reasonable if device is fast
 - But inefficient if device slow
 - CPU switches to other tasks?
 - 4 But if miss a cycle data overwritten / lost







Interrupts

- Polling can happen in 3 instruction cycles
 - Read status, logical-and to extract status bit, branch if not zero
 - How to be more efficient if non-zero infrequently?
- CPU **Interrupt-request line** triggered by I/O device
 - Checked by processor after each instruction
- **Interrupt handler** receives interrupts
 - **Maskable** to ignore or delay some interrupts
- **Interrupt vector** to dispatch interrupt to correct handler
 - Context switch at start and end
 - Based on priority
 - Some **nonmaskable**
 - Interrupt chaining if more than one device at same interrupt number





Interrupt-Driven I/O Cycle





Interrupts (Cont.)

- Interrupt mechanism also used for **exceptions**
 - Terminate process, crash system due to hardware error
- Page fault executes when memory access error
- System call executes via **trap** to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
 - If operating system designed to handle it
- Used for time-sensitive processing, frequent, must be fast





Latency

- Stressing interrupt management because even single-user systems manage hundreds of interrupts per second and servers hundreds of thousands
- For example, a quiet macOS desktop generated 23,000 interrupts over 10 seconds

SCHEDULER		INTERRUPTS
<hr/>		
total_samples	13	22998
delays < 10 usecs	12	16243
delays < 20 usecs	1	5312
delays < 30 usecs	0	473
delays < 40 usecs	0	590
delays < 50 usecs	0	61
delays < 60 usecs	0	317
delays < 70 usecs	0	2
delays < 80 usecs	0	0
delays < 90 usecs	0	0
delays < 100 usecs	0	0
total < 100 usecs	13	22998





Intel Pentium Processor Event-Vector Table

vector number	description
0	divide error
1	debug exception
2	null interrupt
3	breakpoint
4	INTO-detected overflow
5	bound range exception
6	invalid opcode
7	device not available
8	double fault
9	coprocessor segment overrun (reserved)
10	invalid task state segment
11	segment not present
12	stack fault
13	general protection
14	page fault
15	(Intel reserved, do not use)
16	floating-point error
17	alignment check
18	machine check
19–31	(Intel reserved, do not use)
32–255	maskable interrupts






Direct Memory Access

- Used to avoid **programmed I/O** (one byte at a time) for large data movement
- Requires **DMA** controller
- Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
 - Source and destination addresses
 - Read or write mode
 - Count of bytes
 - Writes location of command block to DMA controller
 - Bus mastering of DMA controller – grabs bus from CPU
- 4 **Cycle stealing** from CPU but still much more efficient
 - When done, interrupts to signal completion
- Version that is aware of virtual addresses can be even more efficient - **DVMA**





Six Step Process to Perform DMA Transfer





Characteristics of I/O Devices

aspect	variation	example
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read-write	CD-ROM graphics controller disk





Characteristics of I/O Devices (Cont.)

- Subtleties of devices handled by device drivers
- Broadly I/O devices can be grouped by the OS into
 - Block I/O
 - Character I/O (Stream)
 - Memory-mapped file access
 - Network sockets
- For direct manipulation of I/O device specific characteristics, usually an escape / back door
 - Unix **ioctl()** call to send arbitrary bits to a device control register and data to device data register
- UNIX and Linux use tuple of “major” and “minor” device numbers to identify type and instance of devices (here major 8 and minors 0-4)

```
o 1 - - /dev/sd*  
brw-rw---- 1 root disk 8, 0 Mar 16 09:18 /dev/sda  
brw-rw---- 1 root disk 8, 1 Mar 16 09:18 /dev/sda1  
brw-rw---- 1 root disk 8, 2 Mar 16 09:18 /dev/sda2  
brw-rw---- 1 root disk 8, 3 Mar 16 09:18 /dev/sda3
```





Block and Character Devices

- Block devices include disk drives
 - Commands include read, write, seek
 - **Raw I/O, direct I/O**, or file-system access
 - Memory-mapped file access possible
 - 4 File mapped to virtual memory and clusters brought via demand paging
 - DMA
- Character devices include keyboards, mice, serial ports
 - Commands include **get()**, **put()**
 - Libraries layered on top allow line editing





Network Devices

- Varying enough from block and character to have own interface
- Linux, Unix, Windows and many others include **socket** interface
 - Separates network protocol from network operation
 - Includes **select()** functionality
- Approaches vary widely (pipes, FIFOs, streams, queues, mailboxes)





Clocks and Timers

- Provide current time, elapsed time, timer
- Normal resolution about 1/60 second
- Some systems provide higher-resolution timers
- **Programmable interval timer** used for timings, periodic interrupts
- **ioctl()** (on UNIX) covers odd aspects of I/O such as clocks and timers







Nonblocking and Asynchronous I/O

- **Blocking** - process suspended until I/O completed
 - Easy to use and understand
 - Insufficient for some needs
- **Nonblocking** - I/O call returns as much as available
 - User interface, data copy (buffered I/O)
 - Implemented via multi-threading
 - Returns quickly with count of bytes read or written
 - `select()` to find if data ready then `read()` or `write()` to transfer
- **Asynchronous** - process runs while I/O executes
 - Difficult to use
 - I/O subsystem signals process when I/O completed





Two I/O Methods





Vectored I/O

- **Vectored I/O** allows one system call to perform multiple I/O operations
 - For example, Unix **readve()** accepts a vector of multiple buffers to read into or write from
 - This scatter-gather method better than multiple individual I/O calls
 - Decreases context switching and system call overhead
 - Some versions provide atomicity
- 4 Avoid for example worry about multiple threads changing data as reads / writes occurring






Kernel I/O Subsystem


- Scheduling
 - Some I/O request ordering via per-device queue
 - Some OSs try fairness
 - Some implement Quality Of Service (i.e. IPQOS)
- **Buffering** - store data in memory while transferring between devices
 - To cope with device speed mismatch
 - To cope with device transfer size mismatch
 - To maintain “copy semantics”
 - **Double buffering** – two copies of the data
 - 4 Kernel and user
 - 4 Varying sizes
 - 4 Full / being processed and not-full / being used
 - 4 Copy-on-write can be used for efficiency in some cases







Device-status Table





Common PC and Data-center I/O devices and Interface Speeds





Kernel I/O Subsystem

- **Caching** - faster device holding copy of data
 - Always just a copy
 - Key to performance
 - Sometimes combined with buffering
- **Spooling** - hold output for a device
 - If device can serve only one request at a time
 - i.e., Printing
- **Device reservation** - provides exclusive access to a device
 - System calls for allocation and de-allocation
 - Watch out for deadlock





Error Handling

- OS can recover from disk read, device unavailable, transient write failures
 - Retry a read or write, for example
 - Some systems more advanced – Solaris FMA, AIX
 - 4 Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports






I/O Protection

- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
 - All I/O instructions defined to be privileged
 - I/O must be performed via system calls
 - 4 Memory-mapped and I/O port memory locations must be protected too





Use of a System Call to Perform I/O






Kernel Data Structures

- Kernel keeps state info for I/O components, including open file tables, network connections, character device state
- Many, many complex data structures to track buffers, memory allocation, “dirty” blocks
- Some use object-oriented methods and message passing to implement I/O
 - Windows uses message passing
 - 4 Message with I/O information passed from user mode into kernel
 - 4 Message modified as it flows through to device driver and back to process
 - 4 Pros / cons?





UNIX I/O Kernel Structure





Power Management

- Not strictly domain of I/O, but much is I/O related
- Computers and devices use electricity, generate heat, frequently require cooling
- OSes can help manage and improve use
 - Cloud computing environments move virtual machines between servers
 - 4 Can end up evacuating whole systems and shutting them down
- Mobile computing has power management as first class OS aspect





Power Management (Cont.)

- For example, Android implements
 - Component-level power management
 - 4 Understands relationship between components
 - 4 Build device tree representing physical device topology
 - 4 System bus -> I/O subsystem -> {flash, USB storage}
 - 4 Device driver tracks state of device, whether in use
 - 4 Unused component – turn it off
 - 4 All devices in tree branch unused – turn off branch





Power Management (Cont.)

- For example, Android implements (Cont.)
 - Wake locks – like other locks but prevent sleep of device when lock is held
 - Power collapse – put a device into very deep sleep
 - 4 Marginal power use
 - 4 Only awake enough to respond to external stimuli (button press, incoming call)
- Modern systems use **advanced configuration and power interface (ACPI)** firmware providing code that runs as routines called by kernel for device discovery, management, error and power management





Kernel I/O Subsystem Summary

- In summary, the I/O subsystem coordinates an extensive collection of services that are available to applications and to other parts of the kernel
 - Management of the name space for files and devices
 - Access control to files and devices
 - Operation control (for example, a modem cannot seek())
 - File-system space allocation
 - Device allocation
 - Buffering, caching, and spooling
 - I/O scheduling
 - Device-status monitoring, error handling, and failure recovery
 - Device-driver configuration and initialization
 - Power management of I/O devices
- The upper levels of the I/O subsystem access devices via the uniform interface provided by the device drivers






Transforming I/O Requests to Hardware Operations

- Consider reading a file from disk for a process:
 - Determine device holding file
 - Translate name to device representation
 - Physically read data from disk into buffer
 - Make data available to requesting process
 - Return control to process





Life Cycle of An I/O Request






STREAMS

- **STREAM** – a full-duplex communication channel between a user-level process and a device in Unix System V and beyond
- A STREAM consists of:
 - STREAM head interfaces with the user process
 - driver end interfaces with the device
 - zero or more STREAM modules between them
- Each module contains a **read queue** and a **write queue**
- Message passing is used to communicate between queues
 - **Flow control** option to indicate available or busy
- Asynchronous internally, synchronous where user process communicates with stream head





The STREAMS Structure






Performance

- I/O a major factor in system performance:
 - Demands CPU to execute device driver, kernel I/O code
 - Context switches due to interrupts
 - Data copying
 - Network traffic especially stressful





Intercomputer Communications






Improving Performance


- Reduce number of context switches
- Reduce data copying
- Reduce interrupts by using large transfers, smart controllers, polling
- Use DMA
- Use smarter hardware devices
- Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads






Device-Functionality Progression





I/O Performance of Storage (and Network Latency)



End of Chapter 12

