Simple layers

Simple Modules are used for various tasks like adapting Tensor methods and providing affine transformations:

- Parameterized Modules:
 - Linear: a linear transformation;
 - SparseLinear: a linear transformation with sparse inputs;
 - Bilinear: a bilinear transformation with sparse inputs;
 - PartialLinear: a linear transformation with sparse inputs with the option of only computing a subset;
 - Add: adds a bias term to the incoming data;
 - CAdd: a component-wise addition to the incoming data;
 - Mul: multiply a single scalar factor to the incoming data;
 - CMul: a component-wise multiplication to the incoming data;
 - Euclidean: the euclidean distance of the input to k mean centers;
 - WeightedEuclidean: similar to Euclidean, but additionally learns a diagonal covariance matrix;
 - Cosine: the cosine similarity of the input to k mean centers;
- Modules that adapt basic Tensor methods:
 - Copy: a copy of the input with type casting;
 - Narrow: a narrow operation over a given dimension;
 - Replicate: repeats input n times along its first dimension;
 - Reshape: a reshape of the inputs;
 - view: a view of the inputs;
 - Contiguous : contiguous of the inputs ;
 - Select: a select over a given dimension;
 - MaskedSelect: a masked select module performs the torch.maskedSelect operation;
 - Index: a index over a given dimension;
 - Squeeze: squeezes the input;
 - Unsqueeze: unsqueeze the input, i.e., insert singleton dimension;
 - Transpose: transposes the input;
- Modules that adapt mathematical Tensor methods:
 - AddConstant: adding a constant;
 - MulConstant: multiplying a constant;
 - Max: a max operation over a given dimension;
 - Min: a min operation over a given dimension;
 - Mean: a mean operation over a given dimension;

- Sum: a sum operation over a given dimension;
- Exp: an element-wise exp operation;
- Log: an element-wise log operation;
- Abs: an element-wise abs operation;
- Power: an element-wise pow operation;
- Square: an element-wise square operation;
- Sqrt: an element-wise sqrt operation;
- Clamp: an element-wise clamp operation;
- Normalize: normalizes the input to have unit L_p norm;
- MM: matrix-matrix multiplication (also supports batches of matrices);

Miscellaneous Modules:

- BatchNormalization: mean/std normalization over the mini-batch inputs (with an optional affine transform);
- PixelShuffle: Rearranges elements in a tensor of shape [C*r, H, W] to a tensor of shape [C, H*r, W*r];
- Identity: forward input as-is to output (useful with ParallelTable);
- Dropout: masks parts of the input using binary samples from a bernoulli distribution;
- SpatialDropout: same as Dropout but for spatial inputs where adjacent pixels are strongly correlated;
- VolumetricDropout: same as Dropout but for volumetric inputs where adjacent voxels are strongly correlated;
- Padding: adds padding to a dimension;
- L1Penalty: adds an L1 penalty to an input (for sparsity);
- GradientReversal: reverses the gradient (to maximize an objective function);
- GPU: decorates a module so that it can be executed on a specific GPU device.
- TemporalDynamicKMaxPooling: selects the k highest values in a sequence. k can be calculated based on sequence length;

Linear

```
module = nn.Linear(inputDimension, outputDimension, [bias = true])
```

Applies a linear transformation to the incoming data, i.e. y = Ax + b. The input tensor given in forward(input) must be either a vector (1D tensor) or matrix (2D tensor). If the input is a matrix, then each row is assumed to be an input sample of given batch. The layer can be used without bias by setting bias = false.

You can create a layer in the following way:

```
module = nn.Linear(10, 5) -- 10 inputs, 5 outputs
```

Usually this would be added to a network of some kind, e.g.:

```
mlp = nn.Sequential()
mlp:add(module)
```

The weights and biases (A and b) can be viewed with:

```
print(module.weight)
print(module.bias)
```

The gradients for these weights can be seen with:

```
print(module.gradWeight)
print(module.gradBias)
```

As usual with nn modules, applying the linear transformation is performed with:

```
x = torch.Tensor(10) -- 10 inputs
y = module:forward(x)
```

SparseLinear

```
module = nn.SparseLinear(inputDimension, outputDimension)
```

Applies a linear transformation to the incoming sparse data, i.e. y = Ax + b. The input tensor given in forward(input) must be a sparse vector represented as 2D tensor of the form torch. Tensor(N, 2) where the pairs represent indices and values.

The SparseLinear layer is useful when the number of input dimensions is very large and the input data is sparse.

You can create a sparse linear layer in the following way:

```
module = nn.SparseLinear(10000, 2) -- 10000 inputs, 2 outputs
```

The sparse linear module may be used as part of a larger network, and apart from the form of the input, SparseLinear operates in exactly the same way as the Linear layer.

A sparse input vector may be created as so...

```
x = torch.Tensor({ {1, 0.1}, {2, 0.3}, {10, 0.3}, {31, 0.2} })

print(x)

1.0000    0.1000
2.0000    0.3000
10.0000    0.3000
31.0000    0.2000
[torch.Tensor of dimension 4x2]
```

The first column contains indices, the second column contains values in a a vector where all other elements are zeros. The indices should not exceed the stated dimensions of the input to the layer (10000 in the example).

Bilinear

```
module = nn.Bilinear(inputDimension1, inputDimension2,
outputDimension, [bias = true])
```

Applies a bilinear transformation to the incoming data, i.e. \forall k: $y_k = x_1 A_k x_2 + b$. The input tensor given in forward(input) is a table containing both inputs x_1 and x_2 , which are tensors of size N x inputDimension1 and N x inputDimension2, respectively. The layer can be trained without biases by setting bias = false.

You can create a layer in the following way:

```
module = nn.Bilinear(10, 5, 3) -- 10 and 5 inputs, 3 outputs
```

Input data for this layer would look as follows:

```
input = {torch.randn(128, 10), torch.randn(128, 5)} -- 128 input
examples
module:forward(input)
```

PartialLinear

```
module = nn.PartialLinear(inputSize, outputSize, [bias = true])
```

PartialLinear is a Linear layer that allows the user to a set a collection of column indices. When the column indices are set, the layer will behave like a Linear layer that only has those columns. Meanwhile, all parameters are preserved, so resetting the PartialLinear layer will result in a module that behaves just like a regular Linear layer.

This module is useful, for instance, when you want to do forward-backward on only a subset of a Linear layer during training but use the full Linear layer at test time.

You can create a layer in the following way:

```
module = nn.PartialLinear(5, 3) -- 5 inputs, 3 outputs
```

Input data for this layer would look as follows:

```
input = torch.randn(128, 5) -- 128 input examples
module:forward(input)
```

One can set the partition of indices to compute using the function setPartition(indices) where indices is a tensor containing the indices to compute.

```
module = nn.PartialLinear(5, 3) -- 5 inputs, 3 outputs
module:setPartition(torch.Tensor({2,4})) -- only compute the 2nd
and 4th indices out of a total of 5 indices
```

One can reset the partition via the resetPartition() function that resets the partition to compute all indices, making it's behaviour equivalent to nn.Linear

Dropout

```
module = nn.Dropout(p)
```

During training, Dropout masks parts of the input using binary samples from a bernoulli distribution.

Each input element has a probability of p of being dropped, i.e having its commensurate output element be zero. This has proven an effective technique for regularization and preventing the co-adaptation of neurons (see Hinton et al. 2012).

Furthermore, the outputs are scaled by a factor of 1/(1-p) during training. This allows the input to be simply forwarded as-is during evaluation.

In this example, we demonstrate how the call to forward samples different outputs to dropout (the zeros) given the same input:

```
module = nn.Dropout()
> x = torch.Tensor\{\{1, 2, 3, 4\}, \{5, 6, 7, 8\}\}
> module: forward(x)
      0
          0
              8
 10
      0 14
              0
[torch.DoubleTensor of dimension 2x4]
> module:forward(x)
  0
      0
              0
          6
 10
              0
[torch.DoubleTensor of dimension 2x4]
```

Backward drops out the gradients at the same location:

```
> module: forward(x)
0 4 0 0
```

```
10 12 0 16
[torch.DoubleTensor of dimension 2x4]

> module:backward(x, x:clone():fill(1))
0 2 0 0
2 2 0 2
[torch.DoubleTensor of dimension 2x4]
```

In both cases the gradOutput and input are scaled by 1/(1-p), which in this case is 2.

During evaluation, Dropout does nothing more than forward the input such that all elements of the input are considered.

```
> module:evaluate()
> module:forward(x)
1 2 3 4
5 6 7 8
[torch.DoubleTensor of dimension 2x4]
```

There is also an option for stochastic evaluation which drops the outputs just like how it is done during training:

```
module_stochastic_evaluation = nn.Dropout(nil, nil, nil, true)
> module_stochastic_evaluation:evaluate()
> module_stochastic_evaluation:forward(x)
    2     4     6     0
    0     12     14     0
[torch.DoubleTensor of dimension 2x4]
```

We can return to training our model by first calling Module:training():

```
> module:training()

> return module:forward(x)
2  4  6  0
0  0  0  16

[torch.DoubleTensor of dimension 2x4]
```

When used, Dropout should normally be applied to the input of parameterized Modules like Linear or SpatialConvolution. A p of 0.5 (the default) is usually okay for hidden layers. Dropout can sometimes be used successfully on the dataset inputs with a p around 0.2. It sometimes works best following Transfer Modules like ReLU. All this depends a great deal on the dataset so its up to the user to try different combinations.

SpatialDropout

```
module = nn.SpatialDropout(p)
```

This version performs the same function as nn.Dropout, however it assumes the 2 right-most dimensions of the input are spatial, performs one Bernoulli trial per output feature when training, and extends this dropout value across the entire feature map.

As described in the paper "Efficient Object Localization Using Convolutional Networks" (http://arxiv.org/abs/1411.4280), if adjacent pixels within feature maps are strongly correlated (as is normally the case in early convolution layers) then iid dropout will not regularize the activations and will otherwise just result in an effective learning rate decrease. In this case, nn.SpatialDropout will help promote independence between feature maps and should be used instead.

nn. Spatial Dropout accepts 3D or 4D inputs. If the input is 3D than a layout of (features x height x width) is assumed and for 4D (batch x features x height x width) is assumed.

VolumetricDropout

```
module = nn.VolumetricDropout(p)
```

This version performs the same function as nn.Dropout, however it assumes the 3 right-most dimensions of the input are spatial, performs one Bernoulli trial per output feature when training, and extends this dropout value across the entire feature map.

As described in the paper "Efficient Object Localization Using Convolutional Networks" (http://arxiv.org/abs/1411.4280), if adjacent voxels within feature maps are strongly correlated (as is normally the case in early convolution layers) then iid dropout will not regularize the activations and will otherwise just result in an effective learning rate decrease. In this case, nn.VolumetricDropout will help promote independence between feature maps and should be used instead.

nn. Volumetric Dropout accepts 4D or 5D inputs. If the input is 4D than a layout of (features x time x height x width) is assumed and for 5D (batch x features x time x height x width) is assumed.

Abs

```
module = Abs()

m = nn.Abs()
ii = torch.linspace(-5, 5)
oo = m:forward(ii)
go = torch.ones(100)
gi = m:backward(ii, go)
gnuplot.plot({'f(x)', ii, oo, '+-'}, {'df/dx', ii, gi, '+-'})
gnuplot.grid(true)
```

Add

```
module = nn.Add(inputDimension, scalar)
```

Applies a bias term to the incoming data, i.e. $yi = x_i + b_i$, or if scalar = true then uses a single bias term, $yi = x_i + b$. So if scalar = true then inputDimension value will be disregarded.

Example:

```
y = torch.Tensor(5)
mlp = nn.Sequential()
mlp:add(nn.Add(5))

function gradUpdate(mlp, x, y, criterion, learningRate)
```

```
local pred = mlp:forward(x)
local err = criterion:forward(pred, y)
local gradCriterion = criterion:backward(pred, y)
mlp:zeroGradParameters()
mlp:backward(x, gradCriterion)
mlp:updateParameters(learningRate)
return err
end

for i = 1, 10000 do
    x = torch.rand(5)
    y:copy(x);
    for i = 1, 5 do y[i] = y[i] + i; end
    err = gradUpdate(mlp, x, y, nn.MSECriterion(), 0.01)
end

print(mlp:get(1).bias)
```

gives the output:

```
1.0000
2.0000
3.0000
4.0000
5.0000
[torch.Tensor of dimension 5]
```

i.e. the network successfully learns the input x has been shifted to produce the output y.

CAdd

```
module = nn.CAdd(size)
```

Applies a component-wise addition to the incoming data, i.e. $y_i = x_i + b_i$. Argument size can be one or many numbers (sizes) or a torch. LongStorage. For example, nn.CAdd(3,4,5) is equivalent to nn.CAdd(torch.LongStorage{3,4,5}). If the size for a particular dimension is 1, the addition will be expanded along the entire axis.

Example:

```
mlp = nn.Sequential()
mlp:add(nn.CAdd(5, 1))
y = torch.Tensor(5, 4)
bf = torch.Tensor(5, 4)
for i = 1, 5 do bf[i] = i; end -- scale input with this
function gradUpdate(mlp, x, y, criterion, learningRate)
   local pred = mlp:forward(x)
   local err = criterion:forward(pred, y)
   local gradCriterion = criterion:backward(pred, y)
   mlp:zeroGradParameters()
   mlp:backward(x, gradCriterion)
   mlp:updateParameters(learningRate)
   return err
end
for i = 1, 10000 do
   x = torch.rand(5, 4)
   y:copy(x)
   y:add(bf)
   err = gradUpdate(mlp, x, y, nn.MSECriterion(), 0.01)
end
print(mlp:get(1).bias)
```

gives the output:

```
1.0000
2.0000
3.0000
4.0000
5.0000
[torch.Tensor of dimension 5x1]
```

i.e. the network successfully learns the input \times has been shifted by those bias factors to produce the output y.

Mul

```
module = nn.Mul()
```

Applies a *single* scaling factor to the incoming data, i.e. $y = w \times x$, where w is a scalar.

Example:

```
y = torch.Tensor(5)
mlp = nn.Sequential()
mlp:add(nn.Mul())
function gradUpdate(mlp, x, y, criterion, learningRate)
   local pred = mlp:forward(x)
   local err = criterion:forward(pred, y)
   local gradCriterion = criterion:backward(pred, y)
   mlp:zeroGradParameters()
   mlp:backward(x, gradCriterion)
   mlp:updateParameters(learningRate)
   return err
end
for i = 1, 10000 do
   x = torch.rand(5)
   y:copy(x)
   y:mul(math.pi)
   err = gradUpdate(mlp, x, y, nn.MSECriterion(), 0.01)
end
print(mlp:get(1).weight)
```

gives the output:

```
3.1416
[torch.Tensor of dimension 1]
```

i.e. the network successfully learns the input x has been scaled by pi.

CMul

```
module = nn.CMul(size)
```

Applies a component-wise multiplication to the incoming data, i.e. $y_i = w_i * x_i$. Argument size can be one or many numbers (sizes) or a torch. LongStorage. For example, nn. CMul(3,4,5) is equivalent to nn. CMul(torch. LongStorage {3,4,5}). If the size for a particular dimension is 1, the multiplication will be expanded along the entire axis.

Example:

```
mlp = nn.Sequential()
mlp:add(nn.CMul(5, 1))
y = torch.Tensor(5, 4)
sc = torch.Tensor(5, 4)
for i = 1, 5 do sc[i] = i; end -- scale input with this
function gradUpdate(mlp, x, y, criterion, learningRate)
   local pred = mlp:forward(x)
   local err = criterion:forward(pred, y)
   local gradCriterion = criterion:backward(pred, y)
   mlp:zeroGradParameters()
   mlp:backward(x, gradCriterion)
   mlp:updateParameters(learningRate)
   return err
end
for i = 1, 10000 do
   x = torch.rand(5, 4)
   y:copy(x)
   y:cmul(sc)
   err = gradUpdate(mlp, x, y, nn.MSECriterion(), 0.01)
end
print(mlp:get(1).weight)
```

gives the output:

```
1.0000
2.0000
3.0000
4.0000
```

```
5.0000
[torch.Tensor of dimension 5x1]
```

i.e. the network successfully learns the input \times has been scaled by those scaling factors to produce the output y.

Max

```
module = nn.Max(dimension, nInputDim)
```

Applies a max operation over dimension dimension.

Hence, if an nxpxq Tensor was given as input, and dimension = 2 then an nxq matrix would be output.

When nInputDim is provided, inputs larger than that value will be considered batches where the actual dimension to apply the max operation will be dimension dimension + 1.

Min

```
module = nn.Min(dimension, nInputDim)
```

Applies a min operation over dimension dimension.

Hence, if an nxpxq Tensor was given as input, and dimension = 2 then an nxq matrix would be output.

When nInputDim is provided, inputs larger than that value will be considered batches where the actual dimension to apply the min operation will be dimension dimension + 1.

Mean

```
module = nn.Mean(dimension, nInputDim)
```

Applies a mean operation over dimension dimension.

Hence, if an nxpxq Tensor was given as input, and dimension = 2 then an nxq matrix would be output.

When nInputDim is provided, inputs larger than that value will be considered batches where the actual dimension to apply the sum operation will be dimension dimension + 1. This module is based on nn.Sum.

Sum

```
module = nn.Sum(dimension, nInputDim, sizeAverage)
```

Applies a sum operation over dimension dimension.

Hence, if an nxpxq Tensor was given as input, and dimension = 2 then an nxq matrix would be output.

When nInputDim is provided, inputs larger than that value will be considered batches where the actual dimension to apply the sum operation will be dimension dimension + 1. Negative indexing is allowed by providing a negative value to nInputDim.

When sizeAverage is provided, the sum is divided by the size of the input in this dimension. This is equivalent to the mean operation performed by the nn.Mean module.

Euclidean

```
module = nn.Euclidean(inputSize,outputSize)
```

Outputs the Euclidean distance of the input to outputSize centers, i.e. this layer has the weights w_j , for j = 1,..., outputSize, where w_j are vectors of dimension inputSize.

The distance y_j between center j and input x is formulated as $y_j = || w_j - x ||$.

WeightedEuclidean

```
module = nn.WeightedEuclidean(inputSize,outputSize)
```

This module is similar to Euclidean, but additionally learns a separate diagonal covariance matrix across the features of the input space *for each center*.

In other words, for each of the outputSize centers w_j , there is a diagonal covariance matrices c_j , for j=1,..., outputSize, where c_j are stored as vectors of size inputSize.

The distance y_j between center j and input x is formulated as $y_j = || c_j * (w_j - x) ||$.

Cosine

```
module = nn.Cosine(inputSize,outputSize)
```

Outputs the cosine similarity of the input to outputSize centers, i.e. this layer has the weights w_j , for j = 1,..., outputSize, where w_j are vectors of dimension inputSize.

The distance y_j between center j and input x is formulated as $y_j = (x \cdot w_j) / (||w_j|| * || x ||)$.

Identity

```
module = nn.Identity()
```

Creates a module that returns whatever is input to it as output.

This is useful when combined with the module ParallelTable in case you do not wish to do anything to one of the input Tensors.

Example:

```
mlp = nn.Identity()
print(mlp:forward(torch.ones(5, 2)))
```

gives the output:

```
1  1
1  1
1  1
1  1
1  1
1  1
[torch.Tensor of dimension 5x2]
```

Here is a more useful example, where one can implement a network which also computes a Criterion using this module:

```
pred_mlp = nn.Sequential() -- A network that makes predictions
given x.
pred_mlp:add(nn.Linear(5, 4))
pred_mlp:add(nn.Linear(4, 3))
xy_mlp = nn.ParallelTable() -- A network for predictions and for
keeping the
criterion
xy_mlp:add(nn.Identity()) -- by forwarding both x and y through
the network.
and y.
mlp:add(xy_mlp)
               -- It feeds x and y to parallel
networks;
cr = nn.MSECriterion()
cr_wrap = nn.CriterionTable(cr)
mlp:add(cr_wrap)
                       -- and then applies the criterion.
for i = 1, 100 do
                       -- Do a few training iterations
  x = torch.ones(5)
                       -- Make input features.
  y = torch.Tensor(3)
  y:copy(x:narrow(1,1,3)) -- Make output label.
  err = mlp:forward{x,y}
                       -- Forward both input and output.
                       -- Print error from criterion.
  print(err)
  mlp:zeroGradParameters() -- Do backprop...
  mlp:backward({x, y})
  mlp:updateParameters(0.05)
```

Copy

```
module = nn.Copy(inputType, outputType, [forceCopy, dontCast])
```

This layer copies the input to output with type casting from inputType to outputType. Unless forceCopy is true, when the first two arguments are the same, the input isn't copied, only transferred as the output.

The default forceCopy is false.

When dontCast is true, a call to nn.Copy:type(type) will not cast the module's output and gradInput Tensor s to the new type.

The default is false.

Narrow

```
module = nn.Narrow(dimension, offset, length)
```

Narrow is application of narrow operation in a module. The module further supports negative length, dim and offset to handle inputs of unknown size.

```
> x = torch.rand(4, 5)

> x

    0.3695    0.2017    0.4485    0.4638    0.0513
    0.9222    0.1877    0.3388    0.6265    0.5659
    0.8785    0.7394    0.8265    0.9212    0.0129
    0.2290    0.7971    0.2113    0.1097    0.3166
[torch.DoubleTensor of size 4x5]

> nn.Narrow(1, 2, 3):forward(x)
    0.9222    0.1877    0.3388    0.6265    0.5659
    0.8785    0.7394    0.8265    0.9212    0.0129
    0.2290    0.7971    0.2113    0.1097    0.3166
```

```
[torch.DoubleTensor of size 3x5]
> nn.Narrow(1, 2, -1):forward(x)
0.9222 0.1877 0.3388 0.6265 0.5659
 0.8785 0.7394 0.8265 0.9212 0.0129
0.2290 0.7971 0.2113 0.1097 0.3166
[torch.DoubleTensor of size 3x5]
> nn.Narrow(1, 2, 2):forward(x)
0.9222 0.1877 0.3388 0.6265 0.5659
0.8785 0.7394 0.8265 0.9212 0.0129
[torch.DoubleTensor of size 2x5]
> nn.Narrow(1, 2, -2):forward(x)
0.9222 0.1877 0.3388 0.6265 0.5659
0.8785 0.7394 0.8265 0.9212 0.0129
[torch.DoubleTensor of size 2x5]
> nn.Narrow(2, 2, 3):forward(x)
0.2017 0.4485 0.4638
 0.1877 0.3388 0.6265
 0.7394 0.8265 0.9212
0.7971 0.2113 0.1097
[torch.DoubleTensor of size 4x3]
> nn.Narrow(2, 2, -2):forward(x)
0.2017 0.4485 0.4638
0.1877 0.3388 0.6265
 0.7394 0.8265 0.9212
0.7971 0.2113 0.1097
[torch.DoubleTensor of size 4x3]
```

Replicate

```
module = nn.Replicate(nFeature [, dim, ndim])
```

This class creates an output where the input is replicated nFeature times along dimension dim (default 1).

There is no memory allocation or memory copy in this module.

It sets the stride along the dim th dimension to zero.

When provided, ndim should specify the number of non-batch dimensions.

This allows the module to replicate the same non-batch dimension dim for both batch and non-batch inputs .

```
> x = torch.linspace(1, 5, 5)
1
2
3
4
[torch.DoubleTensor of dimension 5]
> m = nn.Replicate(3)
> o = m:forward(x)
1 2 3 4 5
1 2 3 4 5
1 2 3 4 5
[torch.DoubleTensor of dimension 3x5]
> x:fill(13)
13
13
13
 13
13
[torch.DoubleTensor of dimension 5]
> print(o)
13 13 13 13 13
13 13 13 13 13
13 13 13 13 13
[torch.DoubleTensor of dimension 3x5]
```

Reshape

```
module = nn.Reshape(dimension1, dimension2, ... [, batchMode])
```

the elements row-wise.

The optional last argument batchMode, when true forces the first dimension of the input to be considered the batch dimension, and thus keep its size fixed.

This is necessary when dealing with batch sizes of one.

When false, it forces the entire input (including the first dimension) to be reshaped to the input size.

Default batchMode=nil, which means that the module considers inputs with more elements than the produce of provided sizes, i.e. dimension1xdimension2x..., to be batches.

Example:

```
> x = torch.Tensor(4,4)
> for i = 1, 4 do
    for j = 1, 4 do
       x[i][j] = (i-1)*4+j
> end
> print(x)
     2
       3
             4
  5
    6 7 8
  9 10 11 12
 13 14 15 16
[torch.Tensor of dimension 4x4]
> print(nn.Reshape(2,8):forward(x))
     2
         3
             4
                 5 6 7
                            8
  9 10 11 12 13 14 15 16
[torch.Tensor of dimension 2x8]
> print(nn.Reshape(8,2):forward(x))
     2
  1
  3
     4
  5
     6
  7
    8
  9 10
 11 12
 13 14
 15 16
[torch.Tensor of dimension 8x2]
> print(nn.Reshape(16):forward(x))
```

```
1
  2
  3
  4
  5
 6
 7
 8
 9
10
11
12
13
14
15
16
[torch.Tensor of dimension 16]
> y = torch.Tensor(1, 4):fill(0)
> print(y)
0 0 0 0
 [torch.DoubleTensor of dimension 1x4]
> print(nn.Reshape(4):forward(y))
0 0 0 0
 [torch.DoubleTensor of dimension 1x4]
> print(nn.Reshape(4, false):forward(y))
0
0
0
 [torch.DoubleTensor of dimension 4]
```

View

```
module = nn.View(sizes)
```

This module creates a new view of the input tensor using the sizes passed to the constructor. The parameter sizes can either be a LongStorage or numbers.

The method setNumInputDims() allows to specify the expected number of dimensions of the inputs of the modules.

This makes it possible to use minibatch inputs when using a size -1 for one of the dimensions. The method resetSize(sizes) allows to reset the view size of the module after initialization.

Example 1:

```
> x = torch.Tensor(4, 4)
> for i = 1, 4 do
    for j = 1, 4 do
       x[i][j] = (i-1)*4+j
    end
> end
> print(x)
     2
       3
  5
     6 7 8
  9 10 11 12
 13 14 15 16
[torch.Tensor of dimension 4x4]
> print(nn.View(2, 8):forward(x))
         3
                 5 6
                       7
                            8
  9 10 11 12 13 14 15 16
[torch.DoubleTensor of dimension 2x8]
> print(nn.View(torch.LongStorage{8,2}):forward(x))
  1
     2
     4
  3
  5
     6
  7
    8
  9 10
 11 12
 13 14
 15 16
[torch.DoubleTensor of dimension 8x2]
```

```
> print(nn.View(16):forward(x))
  1
  2
  3
  4
  5
  6
  7
  8
  9
 10
 11
 12
 13
 14
 15
 16
[torch.DoubleTensor of dimension 16]
```

Example 2:

```
> input = torch.Tensor(2, 3)
> minibatch = torch.Tensor(5, 2, 3)
> m = nn.View(-1):setNumInputDims(2)
> print(#m:forward(input))

6
[torch.LongStorage of size 1]
> print(#m:forward(minibatch))

5
6
[torch.LongStorage of size 2]
```

Contiguous

```
module = nn.Contiguous()
```

Is used to make input, gradOutput or both contiguous, corresponds to torch.contiguous function.

Only does copy and allocation if input or gradOutput is not contiguous, otherwise passes the same Tensor.

Select

```
module = nn.Select(dim, index)
```

Selects a dimension and index of a nxpxqx.. Tensor.

Example:

```
mlp = nn.Sequential()
mlp:add(nn.Select(1, 3))

x = torch.randn(10, 5)
print(x)
print(mlp:forward(x))
```

gives the output:

```
0.9720 -0.0836  0.0831 -0.2059 -0.0871

0.8750 -2.0432 -0.1295 -2.3932  0.8168

0.0369  1.1633  0.6483  1.2862  0.6596

0.1667 -0.5704 -0.7303  0.3697 -2.2941

0.4794  2.0636  0.3502  0.3560 -0.5500

-0.1898 -1.1547  0.1145 -1.1399  0.1711

-1.5130  1.4445  0.2356 -0.5393 -0.6222

-0.6587  0.4314  1.1916 -1.4509  1.9400

0.2733  1.0911  0.7667  0.4002  0.1646

0.5804 -0.5333  1.1621  1.5683 -0.1978

[torch.Tensor of dimension 10x5]
```

```
1.1633
0.6483
1.2862
0.6596
[torch.Tensor of dimension 5]
```

This can be used in conjunction with Concat to emulate the behavior of Parallel, or to select various parts of an input Tensor to perform operations on. Here is a fairly complicated example:

```
mlp = nn.Sequential()
c = nn.Concat(2)
for i = 1, 10 do
   local t = nn.Sequential()
   t:add(nn.Select(1, i))
   t:add(nn.Linear(3, 2))
   t:add(nn.Reshape(2, 1))
   c:add(t)
end
mlp:add(c)
pred = mlp:forward(torch.randn(10, 3))
print(pred)
for i = 1, 10000 do
                       -- Train for a few iterations
   x = torch.randn(10, 3)
   y = torch.ones(2, 10)
   pred = mlp:forward(x)
   criterion = nn.MSECriterion()
   err = criterion:forward(pred, y)
   gradCriterion = criterion:backward(pred, y)
   mlp:zeroGradParameters()
   mlp:backward(x, gradCriterion)
   mlp:updateParameters(0.01)
   print(err)
end
```

MaskedSelect

```
module = nn.MaskedSelect()
```

Performs a torch. Masked Select on a Tensor.

The mask is supplied as a tabular argument with the input on the forward and backward passes.

Example:

```
ms = nn.MaskedSelect()
mask = torch.ByteTensor({{1, 0}, {0, 1}})
input = torch.DoubleTensor({{10, 20}, {30, 40}})
print(input)
print(mask)
out = ms:forward({input, mask})
print(out)
gradIn = ms:backward({input, mask}, out)
print(gradIn[1])
```

Gives the output:

```
10 20
30 40
[torch.DoubleTensor of size 2x2]

1 0
0 1
[torch.ByteTensor of size 2x2]

10
40
[torch.DoubleTensor of size 2]

10
0 0 40
[torch.DoubleTensor of size 2x2]
```

Index

```
module = nn.Index(dim)

Applies the Tensor index operation along the given dimension. So

nn.Index(dim):forward{t,i}

gives the same output as

t:index(dim, i)
```

Squeeze

```
module = nn.Squeeze([dim, numInputDims])

Applies the Tensor squeeze operation. So

nn.Squeeze():forward(t)

gives the same output as

t:squeeze()
```

Setting numInputDims allows to use this module on batches.

Unsqueeze

```
module = nn.Unsqueeze(pos [, numInputDims])
```

Insert singleton dim (i.e., dimension 1) at position pos.

For an input with dim = input:dim(), there are dim + 1 possible positions to insert the singleton dimension.

For example, if input is 3 dimensional Tensor in size $p \times q \times r$, then the singleton dim can be inserted at the following 4 positions

```
pos = 1: 1 x p x q x r

pos = 2: p x 1 x q x r

pos = 3: p x q x 1 x r

pos = 4: p x q x r x 1
```

Example:

```
input = torch.Tensor(2, 4, 3) -- input: 2 x 4 x 3

-- insert at head
m = nn.Unsqueeze(1)
m:forward(input) -- output: 1 x 2 x 4 x 3

-- insert at tail
m = nn.Unsqueeze(4)
m:forward(input) -- output: 2 x 4 x 3 x 1

-- insert in between
m = nn.Unsqueeze(2)
m:forward(input) -- output: 2 x 1 x 4 x 3

-- the input size can vary across calls
input2 = torch.Tensor(3, 5, 7) -- input2: 3 x 5 x 7
m:forward(input2) -- output: 3 x 1 x 5 x 7
```

Indicate the expected input feature map dimension by specifying <code>numInputDims</code> . This allows the module to work with mini-batch. Example:

```
b = 5 -- batch size 5
input = torch.Tensor(b, 2, 4, 3) -- input: b x 2 x 4 x 3
numInputDims = 3 -- input feature map should be the last 3 dims

m = nn.Unsqueeze(4, numInputDims)
m:forward(input) -- output: b x 2 x 4 x 3 x 1

m = nn.Unsqueeze(2):setNumInputDims(numInputDims)
m:forward(input) -- output: b x 2 x 1 x 4 x 3
```

Transpose

```
module = nn.Transpose({dim1, dim2} [, {dim3, dim4}, ...])
```

Swaps dimension dim1 with dim2, then dim3 with dim4, and so on. So

```
nn.Transpose({dim1, dim2}, {dim3, dim4}):forward(t)
```

gives the same output as

```
t:transpose(dim1, dim2)
t:transpose(dim3, dim4)
```

Exp

```
module = nn.Exp()
```

Applies the exp function element-wise to the input Tensor, thus outputting a Tensor of the same dimension.

```
ii = torch.linspace(-2, 2)
m = nn.Exp()
oo = m:forward(ii)
go = torch.ones(100)
gi = m:backward(ii,go)
gnuplot.plot({'f(x)', ii, oo, '+-'}, {'df/dx', ii, gi, '+-'})
gnuplot.grid(true)
```

Log

```
module = nn.Log()
```

Applies the log function element-wise to the input Tensor, thus outputting a Tensor of the same dimension.

Square

```
module = nn.Square()
```

Takes the square of each element.

```
ii = torch.linspace(-5, 5)
m = nn.Square()
oo = m:forward(ii)
go = torch.ones(100)
gi = m:backward(ii, go)
gnuplot.plot({'f(x)', ii, oo, '+-'}, {'df/dx', ii, gi, '+-'})
gnuplot.grid(true)
```

Sqrt

```
module = nn.Sqrt()
```

Takes the square root of each element.

```
ii = torch.linspace(0, 5)
```

```
m = nn.Sqrt()
oo = m:forward(ii)
go = torch.ones(100)
gi = m:backward(ii, go)
gnuplot.plot({'f(x)', ii, oo, '+-'}, {'df/dx', ii, gi, '+-'})
gnuplot.grid(true)
```

Power

```
module = nn.Power(p)
```

Raises each element to its p -th power.

```
ii = torch.linspace(0, 2)
m = nn.Power(1.25)
oo = m:forward(ii)
go = torch.ones(100)
gi = m:backward(ii, go)
gnuplot.plot({'f(x)', ii, oo, '+-'}, {'df/dx', ii, gi, '+-'})
gnuplot.grid(true)
```

Clamp

```
module = nn.Clamp(min_value, max_value)
```

Clamps all elements into the range [min_value, max_value].

Output is identical to input in the range, otherwise elements less than min_value (or greater than max_value) are saturated to min_value (or max_value).

```
A = torch.randn(2, 5)
m = nn.Clamp(-0.1, 0.5)
B = m:forward(A)

print(A) -- input
-1.1321  0.0227 -0.4672  0.6519 -0.5380
  0.9061 -1.0858  0.3697 -0.8120 -1.6759
[torch.DoubleTensor of size 3x5]

print(B) -- output
-0.1000  0.0227 -0.1000  0.5000 -0.1000
  0.5000 -0.1000  0.3697 -0.1000 -0.1000
[torch.DoubleTensor of size 3x5]
```

Normalize

```
module = nn.Normalize(p, [eps])
```

Normalizes the input Tensor to have unit L_p norm. The smoothing parameter eps prevents division by zero when the input contains all zero elements (default = 1e-10).

Input can be 1D or 2D (in which case it's considered as in batch mode)

```
A = torch.randn(3, 5)
m = nn.Normalize(2)
B = m:forward(A) -- B is also 3 x 5
-- take the L2 norm over the second axis:
print(torch.norm(B, 2, 2)) -- norms is [1, 1, 1]
```

Normalize has a specialized implementation for the inf norm, which corresponds to the maximum norm.

```
A = torch.randn(3,5)
m = nn.Normalize(math.huge) -- uses maximum/inf norm
B = m:forward(A)
maxA = torch.abs(A):max(2)
print(A,B,maxA)
```

MM

```
module = nn.MM(transA, transB)
```

Performs multiplications on one or more pairs of matrices. If transA is set to true, the first matrix is transposed before multiplication. If transB is set to true, the second matrix is transposed before multiplication. By default, the matrices do not get transposed.

The module also accepts 3D inputs which are interpreted as batches of matrices. When using batches, the first input matrix should be of size $b \times m \times n$ and the second input matrix should be of size $b \times n \times p$ (assuming transA and transB are not set). If transA or transB is set, transpose takes place between the second and the third dimensions for the corresponding matrix.

```
model = nn.MM()
A = torch.randn(b, m, n)
B = torch.randn(b, n, p)
C = model:forward({A, B}) -- C will be of size `b x m x p`

model = nn.MM(true, false)
A = torch.randn(b, n, m)
B = torch.randn(b, n, p)
C = model:forward({A, B}) -- C will be of size `b x m x p`
```

BatchNormalization

```
module = nn.BatchNormalization(N [, eps] [, momentum] [,affine])
```

where N is the dimensionality of input

eps is a small value added to the standard-deviation to avoid divide-by-zero. Defaults to 1e-5.

affine is a boolean. When set to false, the learnable affine transform is disabled. Defaults to

During training, this layer keeps a running estimate of its computed mean and std. The running sum is kept with a default momentum of 0.1 (unless over-ridden) During evaluation, this running mean/std is used for normalization.

Implements Batch Normalization as described in the paper: "Batch Normalization: Accelerating Deep Network Training by Reducing Internal Covariate Shift" by Sergey Ioffe, Christian Szegedy.

The operation implemented is:

```
x - mean(x)
y = ----- * gamma + beta
standard-deviation(x) + eps
```

where the mean and standard-deviation are calculated per-dimension over the mini-batches and where gamma and beta are learnable parameter vectors of size N (where N is the input size).

The learning of gamma and beta is optional.

The module only accepts 2D inputs.

```
-- with learnable parameters
model = nn.BatchNormalization(m)
A = torch.randn(b, m)
C = model:forward(A) -- C will be of size `b x m`

-- without learnable parameters
model = nn.BatchNormalization(m, nil, nil, false)
A = torch.randn(b, m)
C = model:forward(A) -- C will be of size `b x m`
```

PixelShuffle

```
module = nn.PixelShuffle(r)
```

Rearranges elements in a tensor of shape [C*r, H, W] to a tensor of shape [C, H*r, W*r]. This is useful for implementing efficient sub-pixel convolution with a stride of 1/r (see Shi et. al). Below we show how the PixelShuffle module can be used to learn upscaling

filters to transform a low-resolution input to a high resolution one, with a 3x upscale factor. This is useful for tasks such as super-resolution, see "Real-Time Single Image and Video Super-Resolution Using an Efficient Sub-Pixel Convolutional Neural Network" - Shi et al. for further details.

```
upscaleFactor = 3
inputChannels = 1
model = nn.Sequential()
model:add(nn.SpatialConvolution(inputChannels, 64, 5, 5, 1, 1, 2,
2))
model:add(nn.ReLU())
model:add(nn.SpatialConvolution(64, 32, 3, 3, 1, 1, 1, 1))
model:add(nn.ReLU())
model:add(nn.SpatialConvolution(32, inputChannels * upscaleFactor *
upscaleFactor, 3, 3, 1, 1, 1, 1))
model:add(nn.PixelShuffle(upscaleFactor))
input = torch.Tensor(1, 192, 256);
out = model:forward(input)
out:size()
   1
 576
 768
[torch.LongStorage of size 3]
```

Padding

```
module = nn.Padding(dim, pad [, nInputDim, value, index])
```

This module adds pad units of padding to dimension dim of the input.

If pad is negative, padding is added to the left, otherwise, it is added to the right of the dimension. When nInputDim is provided, inputs larger than that value will be considered batches where the actual dim to be padded will

be dimension dim + 1. When value is provide, the padding will be filled with that value. The default value is zero.

When index is provided, padding will be added at that offset from the left or right, depending on the sign of pad.

Example 1:

```
module = nn.Padding(1, 2, 1, -1) --pad right x2
module:forward(torch.randn(3)) --non-batch input
    0.2008
    0.4848
-1.0783
-1.0000
-1.0000
[torch.DoubleTensor of dimension 5]
```

Example 2:

```
module = nn.Padding(1, -2, 1, -1) --pad left x2
module:forward(torch.randn(2, 3)) --batch input
-1.0000 -1.0000 1.0203 0.2704 -1.6164
-1.0000 -1.0000 -0.2219 -0.6529 -1.9218
[torch.DoubleTensor of dimension 2x5]
```

Example 3:

```
module = nn.Padding(1, -2, 1, -1, 2) --pad left x2, offset to index
2
module:forward(torch.randn(2, 3)) --batch input
1.0203 -1.0000 -1.0000 0.2704 -1.6164
-0.6529 -1.0000 -1.0000 -0.2219 -1.9218
[torch.DoubleTensor of dimension 2x5]
```

L1Penalty

```
penalty = nn.L1Penalty(L1weight, sizeAverage)
```

L1Penalty is an inline module that in its forward propagation copies the input Tensor directly to the output, and computes an L1 loss of the latent state (input) and stores it in the module's

```
loss field.
```

During backward propagation: gradInput = gradOutput + gradLoss.

This module can be used in autoencoder architectures to apply L1 losses to internal latent state without having to use Identity and parallel containers to carry the internal code to an output criterion.

Example (sparse autoencoder, note: decoder should be normalized):

```
encoder = nn.Sequential()
encoder:add(nn.Linear(3, 128))
encoder:add(nn.Threshold())
decoder = nn.Linear(128, 3)

autoencoder = nn.Sequential()
autoencoder:add(encoder)
autoencoder:add(nn.L1Penalty(l1weight))
autoencoder:add(decoder)

criterion = nn.MSECriterion() -- To measure reconstruction error
-- ...
```

GradientReversal

```
module = nn.GradientReversal([lambda = 1])
```

This module preserves the input, but takes the gradient from the subsequent layer, multiplies it by —lambda and passes it to the preceding layer. This can be used to maximise an objective function whilst using gradient descent, as described in "Domain-Adversarial Training of Neural Networks" (http://arxiv.org/abs/1505.07818).

One can also call:

```
module:setLambda(lambda)
```

to set the hyper-parameter lambda dynamically during training.

GPU

```
gpu = nn.GPU(module, device, [outdevice])
require 'cunn'
gpu:cuda()
```

Decorates an encapsulated module so that it can be executed on a specific GPU device.

The decorated module's parameters are thus hosted on the specified GPU device.

All operations on the gpu module are executed on that device.

Calls to forward / backward will transfer arguments input and gradOutput to the specified device,

which are then fed as arguments to the decorated module.

Returned output is located on the specified outdevice (defaults to device).

Returned gradInput is allocated on the same device as the input.

When serialized/deserialized, the gpu module will be run on the same device that it was serialized with.

To prevent this from happening, the module can be converted to float/double before serialization:

```
gpu:float()
gpustr = torch.serialize(gpu)
```

The module is located in the **nn** package instead of **cunn** as this allows it to be used in CPU-only environments, which are common for production models.

The module supports nested table input and gradOutput tensors originating from multiple devices.

Each nested tensor in the returned gradInput will be transferred to the device its commensurate tensor in the input.

The intended use-case is not for model-parallelism where the models are executed in parallel on multiple devices, but

for sequential models where a single GPU doesn't have enough memory.

Example using 4 GPUs:

```
mlp = nn.Sequential()
   :add(nn.GPU(nn.Linear(10000,10000), 1))
   :add(nn.GPU(nn.Linear(10000,10000), 2))
```

```
:add(nn.GPU(nn.Linear(10000,10000), 3))
:add(nn.GPU(nn.Linear(10000,10000), 4, cutorch.getDevice()))
```

Note how the last GPU instance will return an output tensor on the same device as the current device (cutorch.getDevice).

TemporalDynamicKMaxPooling

```
module = nn.TemporalDynamicKMaxPooling(minK, [factor])
```

Selects the highest k values for each feature in the feature map sequence provided. The input sequence is composed of nInputFrame frames (i.e. nInputFrame is sequence length). The input tensor in forward(input) is expected to be a 2D tensor (nInputFrame x inputFrameSize) or a 3D tensor (nBatchFrame x nInputFrame x inputFrameSize), where inputFrameSize is the number of features across the sequence.

If factor is not provided, k = minK, else the value of k is calculated with:

```
k = math.max(minK, math.ceil(factor*nInputFrame)))
```