Lab 3 GPU Parallel Programming in CUDA

CS3210 - 2021/22 Semester 1

Learning Outcomes

- 1. Learn how to compile and execute a CUDA program
- 2. Learn the different memory types available to a CUDA program
- 3. Learn how shared memory accesses are performed in CUDA
- 4. Learn how to vary the number of blocks, threads executed & investigate the effects of changing them

This lab aims to demonstrate the basic concepts in CUDA – a parallel computing platform for NVIDIA GPUs. Details on CUDA, GPGPU and architecture will be provided in the relevant sections of this Lab. We will use the GPUs on the SoC Compute Cluster: xgpc0-7 (Tesla V100 with compute capability of 7.0) and xgpd0-7 (Tesla Titan V with compute capability of 7.0). See Appendix 10 for details about the SoC Compute Cluster. This lab serves as a precursor to Assignment 2.

Part 1: Hello World in CUDA

This section will cover the basics on how to create, compile and execute a CUDA program. Let us do so by using the hello.cu program.

What is a CUDA program?

A CUDA program, with the extension .cu, is a modified C++ program with sections of CUDA code that are executed on the GPU, called kernels. In CUDA's terminology, the CPU is called the **host** and the GPU is called the **device**.

CPU vs GPU Code

In CUDA, the programmer has to explicitly separate the code that will run on the CPU from the code that runs on the GPU.

Function execution space specifiers

The separation of CPU and GPU code is done on the method/function level. That is to say, a C++ function can be marked as "GPU" or "CPU" code. This is done using **function execution space specifiers** that are placed before the return type, as follows

```
--global__ void hello(char *a, int len)
{
  int tid = threadIdx.x;
  if (tid >= len)
    return;
  a[tid] += 'A' - 'a';
}
```

Here are some function specifiers and their effects:

- __device__ will execute on the device. Can only be called from the device.
- __global__ will execute on the device. Callable from both the device and host. Usually serves as
 the entry point to the GPU kernel (CUDA kernel function).
- __host__ executes on the host. Can only be called from the host. Alternatively, a function with no specifiers is deemed to be __host__.



For more information on function specifiers, refer to the CUDA Programming Guide Section B.1

Organizing Threads in CUDA

This section explains how CUDA threads are laid out from the programmer's perspective.

Threads, Blocks and Grid

An invocation of a CUDA kernel function (i.e. functions annotated with <code>__global__</code>) launches a new grid. The grid is a collection of **thread blocks**. A **thread block** contains a collection of **CUDA threads**. Threads in a block can be laid out in one, two or three dimensions. Similarly, blocks in a grid can be laid out in one, two or three dimensions. Figure 1 shows an example of thread organization.

The programmer has to explicitly specify the number of threads per block and the number of blocks per grid. All blocks within the same grid will have the same number of threads, laid out in the same fashion.

Specifying thread organization in CUDA

To specify the size of the block or grid, we can either:

- Specify an integer denoting the number of threads/blocks. This is only applicable if we want a 1 dimensional block/grid.
- Declare a variable of type dim3

dim3 is a type defined by CUDA that stores the values that require dimensions. We can define a dim3 variable as follows:

- dim3 threadsPerBlock(4, 4, 4); creates a variable called threadsPerBlock. In our use case, the value is a grid/block that is three dimensional, with 4 blocks/threads on each dimension
- dim3 blocksPerGrid(8, 4); creates a variable blocksPerGrid. Two dimensional, with the x dimension having 8 elements, while the y dimension has 4 elements.

Such variables are then passed when the program makes the CUDA kernel function call, covered in the next section.




Figure 1: Organization of threads, blocks within grid

Invoking a CUDA kernel function

The block and grid dimensions have to be supplied when we call a kernel function. Recall that a grid is launched when a CUDA kernel function is invoked. Thus, this is when CUDA needs to know the grid and block sizes for that particular invocation. The kernel **has to be invoked from a host function** and this is done with a modified syntax as follows:



kernel_name <<< Dg, Db, Ns, S >>>([kernel arguments]);

- Dg is of type dim3 and specifies the dimensions and size of the grid
- Db is of type dim3 and specifies the dimensions and size of each thread block
- Ns is of type size_t and specifies the number of bytes of shared memory that is dynamically allocated per thread block for this call and addition to statically allocated memory.
 (Optional, defaults to 0)
- S is of type cudaStream_t and specifies the stream associated with this call. The stream must have been allocated in the same thread block where the call is being made. (Optional, defaults to 0)

For instance, if we have a kernel function (i.e. annotated with the __global__ specifier) called void convolve(int a, int b) and we want to invoke it with the following thread dimensions:

- The grid has dimension $3 \times 3 \times 3$
- A block in the grid has dimension 4×3

Then, we write the following code in a **host** function at the point where we want to execute the kernel function:

```
dim3 gridDimensions(3, 3, 3);
dim3 blockDimensions(4, 3);
convolve<<<gridDimensions, blockDimensions>>>(5, 10);
```

Compiling and Execution

A CUDA program (application) is compiled using a proprietary compiler called NVIDIA CUDA Compiler (nvcc). For instance, if we want to compile hello.cu to an executable called my-hello, we can run the following command in a terminal:




> nvcc -o my-hello hello.cu



For CUDA, we will use the SoC Compute Cluster. Thus, you need to SSH into the nodes in the compute cluster (in a similar fashion to what we use fot our lab machines), compile and run the CUDA programs there.

If nvcc does not exists, add /usr/local/cuda-11.2/bin to your PATH environment variable. See the Appendix for how.

This will create an executable called my-hello in the directory where nvcc was executed. To run my-hello, we run it as though it is a normal executable as follows:



Specifying Compute Capability

Nvcc compiler defaults to target Compute Capability to $5.2 \, (sm_52)$. To target a higher Compute Capability, we should set the -arch flag as follows:



> nvcc -arch sm_70 -o my-hello hello.cu



More information on nvcc can be found in the CUDA Compiler Driver NVCC section of the CUDA Toolkit Documentation



■ The GPUs on the SoC Compute Cluster support compute capability of 7.0 (Tesla V100 on xgpc0-7 and Titan V xgpd0-7). For more information on Compute Capability, refer to Section I of the CUDA Programming Guide. Refer to the Appendix 10 for more information.



Exercise 1

Compile and execute hello.cu onone of the SoC Computer Cluster nodes: xgpc0-7, xgpd0-7. Inspect the code and answer the following questions:

- How many threads are there per block? How many blocks are in the grid?
- How many threads are there in total?
- Draw out a diagram as per Figure 1.

Determining the thread's location in grid/block

Once invoked, the code within the kernel runs on the device. Often computation done by the kernel is based on the thread location within the block and grid. CUDA provides the developer with **built-in variables** that can be called in device code to find the following:



- gridDim the dimensions of the grid as dim3 (i.e. dimensions in X direction can be found in gridDim.x, Y in gridDim.y and Z in gridDim.z
- blockIdx the block index the thread is running in (blockIdx.x, blockIdx.y & blockIdx.z)
- blockDim the dimensions of the block (blockDim.x, blockDim.y & blockDim.z)
- threadIdx the index of the thread within its block (threadIdx.x, threadIdx.y & threadIdx.z)



Exercise 2

Modify hello.cu such that it runs on a 3D grid of dimension $2 \times 2 \times 2$ containing 2D block of 2×4 .

Hint: You will need to change how the tid is calculated (in the kernel function hello), so that there's no overlapping work done.

Executing CUDA threads - hardware's perspective

Grouping threads into blocks (and blocks into a grid) is a useful abstraction for the programmer. This section explains how these threads, which are organized by the programmer, is executed by the hardware.

Architecture of the GPU

To better understand the execution model, let us go through the architecture of the GPU. In particular, we will be using the $VoltaGV100\ GPU$ as an example.

The Volta GV100 GPU is used by NVIDIA Tesla V100 accelerator. This GPU is composed of six GPU Processing Clusters (GPCs), each with 14 Streaming Multiprocessors (SMs) and memory controllers. With 84 SMs, a full GV100 GPU has a total of 5376 FP32 cores, 5376 INT32 cores, 2688 FP64 cores, 672 Tensor Cores, and 336 texture units.

Figure 2 shows the full Volta GV100, while Figure 3 shows the diagram of an SM.



Figure 2: Volta GV100 full GPU with 84 SM units.



Figure 3: Streaming Mutiprocessor (SM) for Volta GV100.

Each **thread block** is assigned a **Streaming Multiprocessor** by the GPU. Once it is assigned, it does not migrate (i.e. change SMs). The SM will break down the thread block into **groups of 32 threads each** called **warps**. The warps execute in a Single Instruction Multiple Threads (SIMT) fashion, which is similar to an SIMD execution (i.e. lockstep execution).



If the thread block does not divide by 32 evenly, then a warp might be executing with less than 32 threads. However, the warp will be executed **as though there are 32 threads**.



Exercise 3

Compile and execute slow.cu. Notice the extremely slow runtime when each block contains 1 thread. Calculate the number of warps launched when running 1024 blocks of 1 thread each, versus 1 block of 1024 threads.



Exercise 4

Compile and execute printing.cu. Notice that there is a trend in how the thread IDs are printed out. Notice any correlation with our knowledge on how the GPU executes a CUDA program?

Part 2: CUDA Memory Model

This section presents the CUDA memory model and its usage in a CUDA program.

CUDA Memory Model

CUDA offers the programmer access to various types of memory, that either resides on the host or device. These can be further subdivided based on whether the host can access the memory in question. GPUs can be in a system either as discrete (e.g. most consumer graphics cards) or integrated. Figure 4 shows the memory organization of integrated and discrete GPUs.



Figure 4: Memory organization in discrete (left) and integrated (right) GPUs

These different types of memory in a GPU is akin to the memory hierarchy of computers and can be visualized in Figure 5.




Figure 5: Memory Hierarchy in CUDA (or GPUs in general)

Table 1 provides a summary of the different memory types that are available in CUDA.

Туре	Scope	Access type	Speed	CUDA declaration syntax	Explicit sync
Register	thread	RW	fastest	-	no
Local	thread	RW	depends*	float x;	no
Shared	block	RW	fast	shared float x;	yes
Global	program	RW	slow	device float x;	yes
Constant	program	R	slow	constant float x;	yes
Texture	program	R	slow	texture float x;	yes

Table 1: Different memory types in the CUDA/GPU memory model

Note that the declaration syntax provided in Table 1 can only be used with **fixed size types** (i.e. primitives or structs).

*Local memory is actually an abstraction of global memory that is private to the thread, which means its access speed is slower than shared memory.



Arguments to a kernel invocation (e.g. varibles ad & len in hello<<<1, N>>>(ad, len) in hello.cu) are passed to the device using **constant memory** and are limited to 4KB $^{\rm 1}$



For more details on Variable Memory Space Specifiers, refer to the CUDA Programming Guide Section $B.2\,$

Next, we will discuss details about selected CUDA memory types and their usage in an application.

¹CUDA Programming Guide, G.4.9.3

Global Memory - Static & Dynamically Allocated

The previous section showed that we can declare a variable in global memory using the __device__ specifier. From Table 1, we know that the variable has program scope, which means that it can be accessed by both the host and device.



Exercise 5

Compile and run global_comm.cu. Observe how the variable result can be accessed by both the device and host (albeit indirectly). What's the reason behind this indirect access?

However, there is a limitation when using __device__ variables. From the example in global_comm.cu, we can see that arrays need to have their sizes explicitly specified during compile time. As such, if we only know the size of an array during run-time, the __device__ variable is not a very efficient and scalable solution. Thus, we need a way to define and allocate memory dynamically.

cudaMalloc - malloc for CUDA

One of the ways to allocate memory dynamically is through the use of what CUDA calls **linear arrays**. You can think of it like malloc but on CUDA. One can declare a **linear array** by invoking cudaMalloc in either host or device code, as follows:



Method Signature for cudaMalloc

cudaError_t cudaMalloc (void** devPtr, size_t size)

- devPtr is a pointer to a pointer variable that will receive the memory address of the allocated linear array
- size requested allocation size in **bytes**



Exercise 6

Compile and run cudaMalloc_comm.cu. Observe the following:

- The global memory "declaration"
- The host can only access the linear array through cudaMemcpy
- The device access to global memory
- Like in normal malloc, it is good practice to free your dynamically allocated memory.
 This is done using cudaFree.

Unified Memory

We observes in the previous section that global memory, whether static or dynamically allocated, cannot be accessed by the host directly. However, in CUDA SDK 6.0, there is a new component introduced to CUDA called **Unified Memory**. This defines a managed memory space that has a **common memory addressing space**, allowing both CPU and GPU to access them as though it is part of their memory space (especially for CPU).

The only difference between **unified memory** and the global memory declarations described previously, is how we allocate the memory in code. We can do the following to replace our global memory declarations to use **unified memory**:

- Replacing __device__ with __managed__
- Replacing cudaMalloc with cudaMallocManaged



Exercise 7

Compile and run both global_comm_unified.cu and cudaMalloc_comm_unified.cu (Note that you need to tell nvcc to target architecture sm_70 or below). Compare the code with their non-unified counterparts. What difference(s) do you observe?

Shared Memory

Another important memory type in CUDA is **shared memory**. Since this resides only in the device, the memory is accessible to the device faster than global memory. As such, it allows us to store intermediate values during computation. Unlike **local memory**, as the name suggests, **shared memory** is **shared** within the **same thread block**. Thus, a thread residing in a different **thread block** will not see the same values in the same shared memory location.



Exercise 8

Compile and run shared_mem.cu. Observe/Ponder on the following:

- Are there any difference between shared and global memory?
- Do the results printed out differ between runs?


Part 3: Synchronization in CUDA

This final section presents synchronization constructs in CUDA.

Atomic Memory Accesses

As with any parallel program, there are times where we want CUDA threads to use a shared memory location, be it shared (within block) or global (within device) memory. However, this may lead to race conditions. Hence, there needs to be a way to ensure **mutual exclusion** when accessing these shared locations.

CUDA provides the programmer with a set of **atomic functions**, each performing a different operation on either a 32-bit or 64-bit memory location. These functions are atomic and this guarantees mutual exclusion.





Exercise 9

Compile and run atomic.cu. Observe on the following:

- What are the values that are printed out? Are they consistent across different runs?
- How does the code resolve global memory access race condition?

Synchronization Constructs

Another synchronization construct that we have learnt in this course is **barriers** (such as MPI_Barrier). These prevent a group of processes/threads from proceeding past the barrier till all participating processes/threads reached the barrier.

CUDA provides a simple barrier construct with the __syncthreads() function. Threads in the same block wait on syncthreads until all threads of the block have reached syncthreads. Furthermore, it guarantees that accesses to global and shared memory made up to this point are visible to all threads. Please note that there is no synchronization among threads from different blocks when you use syncthreads.



Exercise 10

Compile and run synchronise.cu. Observe/Ponder on the following:

- What is the significance of counter values printed out with/without syncthreads
- Why does the values vary when __syncthreads is used in a kernel launch containing multiple blocks?




For details on the CUDA synchronization constructs available, refer to CUDA Programming Guide Section B.6.

Appendix - SoC Compute Cluster

The SoC Compute Cluster has a cluster of compute nodes that are able to execute CUDA programs. The following nodes have been reserved for you:

- xgpc0 to xgpc7 nodes with Tesla V100 with compute capability of 7.0
- xgpd0 to xgpd7 nodes with Titan V with compute capability of 7.0

To use these nodes, you must enable SoC Compute Cluster from your MySoC Account page. You must use your SoC account to use these nodes. List of nodes on the SoC Compute Cluster can be found here. To connect to any of these nodes, simply SSH to them from the SoC network (for instance, through sunfire or the computers in the Lab), using your **SoC account details** (used to connect to sunfire) as follows:



The default version of nvcc on the SoC Compute Cluster is 10.2 (SDK version, which is different from the compute capability). You can use the most recent SDK 11.2 found in /usr/local/cuda-11.2. To make

this SDK your default SDK, add /usr/local/cuda-11.1/bin/ to your PATH environment variable. You mght use the following instructions:

- Open the .bashrc file in your home directory in a text editor.
- Add export PATH="/usr/local/cuda-11.2/bin/:\$PATH" as the last line of the file
- Save the .bashrc file.
- Restart your terminal.