What You Must Know about Memory, Caches, and Shared Memory

Kenjiro Taura

Contents

- Introduction
- Many algorithms are bounded by memory not CPU
- Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Introduction

- so far, we have learned
 - parallelization across cores,
 - vectorization (SIMD) within a core, and
 - instruction level parallelism
- ullet another critical factor you must know to understand program performance is $data\ access$

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

• accessing data is sometimes far more costly than calculation

Why data access is so important?

• no data, no computation

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

- ullet accessing data is sometimes $far\ more\ costly$ than calculation
- moreover, the cost of the same data access instruction significantly differs depending on where data are coming from
 - registers
 - caches
 - main memory
 - another processor's cache

Conceptual goals of the study

- understand how are processors, caches and memory are connected
- understand the behavior of caches, so as to reason about how much traffic the algorithm will generate between main memory ↔ caches (and among cache levels)
- ⇒ be able to reason about a performance limit of your program, due to the memory

• latency: get a sense of how many cycles it takes to get data from main memory and caches

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU/GPU can bring from main memory and caches

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU/GPU can bring from main memory and caches
- what does "memory bandwidth" we see in a processor spec sheet really mean? e.g.,
 - the processor data sheet of E5-2698 (68 GB/s):
 http://ark.intel.com/products/81060/Intel-Xeon-Processor-E5-2698-v3-40M-Cache-2_30-GHz
 - in general,
 - 8 bytes × DDR frequency × memory channel, per CPU socket
 - our CPU (Ice Lake Xeon Platinum 8368)
 - 8 bytes \times 3200 MHz \times 8 channels \approx 200 GB/sec per socket $200 \times 2 \text{ sockets } = 400 \text{ GB/sec in the entire node}$

- latency: get a sense of how many cycles it takes to get data from main memory and caches
- bandwidth: get a sense of how much data CPU/GPU can bring from main memory and caches
- what does "memory bandwidth" we see in a processor spec sheet really mean? e.g.,
 - the processor data sheet of E5-2698 (68 GB/s):
 http://ark.intel.com/products/81060/Intel-Xeon-Processor-E5-2698-v3-40M-Cache-2_30-GHz
 - in general,
 - 8 bytes × DDR frequency × memory channel, per CPU socket
 - our CPU (Ice Lake Xeon Platinum 8368)
 - 8 bytes \times 3200 MHz \times 8 channels \approx 200 GB/sec per socket 200 \times 2 sockets = 400 GB/sec in the entire node
- When can we achieve this?

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

What does memory performance imply for FLOPS?

• many computationally *efficient* algorithms do not use (thus touch) the same data too many times

What does memory performance imply for FLOPS?

- many computationally *efficient* algorithms do not use (thus touch) the same data too many times
- e.g., O(n) algorithms \rightarrow uses a single element only a constant number of times (on average)

What does memory performance imply for FLOPS?

- many computationally *efficient* algorithms do not use (thus touch) the same data too many times
- e.g., O(n) algorithms \rightarrow uses a single element only a constant number of times (on average)
- if data \gg cache for such an algorithm, the algorithm's performance is often limited by the memory bandwidth (or, worse, latency), not processor's compute throughput

```
f for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element
- to achieve Skylake-X peak (16 DP FMAs per core per cycle), a core must access 16 matrix elements (= 256 bytes) / cycle 107

```
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
   y[i] += Aij * x[j];
}</pre>
```

- accesses 16 nnz bytes and performs 2 nnz flops
 - assuming elements of double (8 bytes) and indexes of ints (4 bytes × 2), not counting access to x and y
 - details aside, it performs only an FMA / element
- to achieve Skylake-X peak (16 DP FMAs per core per cycle), a core must access 16 matrix elements (= 256 bytes) / cycle 107

- say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)

- say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)
- there are two obvious lower bounds on the time to complete the algorithm

$$T \geq \frac{C}{\text{the peak FLOPS}} \quad \text{(compute)}$$

$$T \geq \frac{N}{\text{the peak memory bandwidth}} \quad \text{(memory)}$$

- ullet say an algorithm performs C flops (or computation in more general) on N bytes of data
 - ullet assume it needs to access every element of the N bytes at least once (likely the case)
- there are two obvious lower bounds on the time to complete the algorithm

$$T \ge \frac{C}{\text{the peak FLOPS}}$$
 (compute)

$$T \ge \frac{N}{\text{the peak memory bandwidth}}$$
 (memory)

- often, the latter is much larger and such algorithms are called "memory-bound"
- O(N), $O(N \log N)$ algorithms are almost always memory bound

 \bullet memory-bound \iff

$$\frac{C}{\text{the peak FLOPS}} \ll \frac{N}{\text{the peak memory bandwidth}}$$

$$\iff \frac{C}{N} \ll \frac{\text{the peak FLOPS}}{\text{the peak memory bandwidth}}$$

- the LHS: arithmetic intensity or compute intensity of the algorithm
- the reciprocal of RHS: the *byte per FLOPS* of the machine
- note that being memory-bound suggests it is inefficient in the processor utilization view point, but it is efficient in time-complexity sense (it is not necessarily a bad thing)

Note: dense matrix-vector multiply

 \bullet the same argument applies even if the matrix is dense

```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];</pre>
```

Note: dense matrix-vector multiply

ullet the same argument applies even if the matrix is dense

```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];</pre>
```

• MN flops on (MN + M + N) elements

Note: dense matrix-vector multiply


 \bullet the same argument applies even if the matrix is dense

```
for (i = 0; i < M; i++)
for (j = 0; j < N; j++)
y[i] += a[i][j] * x[j];</pre>
```

- MN flops on (MN + M + N) elements
- \bullet \Rightarrow it performs only an FMA / matrix element


Dense matrix-matrix multiply

• the argument does *not* apply to matrix-matrix multiply (we've been trying to get close to CPU peak)



Dense matrix-matrix multiply

• the argument does *not* apply to matrix-matrix multiply (we've been trying to get close to CPU peak)



• for $N \times N$ square matrices, it performs N^3 FMAs on $3N^2$ elements

Why dense matrix-matrix multiply *can* be efficient?

• assume $M \sim N \sim K$

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

- a macroscopic argument:
 - $\Theta(N^3)$ flops on $\Theta(N^2)$ bytes
 - each element is used many $(\Theta(N))$ times
 - \Rightarrow the same element may not have to be fetched from main memory every time it is used

A microscopic argument

```
for (i = 0; i < M; i++)

for (j = 0; j < N; j++)

for (k = 0; k < K; k++)

C(i,j) += A(i,k) * B(k,j);
```

• the innermost statement

```
I \left[ C(i,j) += A(i,k) * B(k,j) \right]
```

still performs (only) 1 FMA for accessing 3 elements

- but the same C(i,j) is used in *every* iteration of the *k*-loop (i.e., every 3 memory accesses)
- similarly, the same A(i,k) is used in *every* iteration of the j-loop (i.e., every 3K memory accesses)

An easily achievable bandwidth

• a simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```

An easily achievable bandwidth

• a simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```

```
1  $ gcc -03 memcpy.c
2  $ ./a.out $((1 << 26)) # 64M long elements = 512MB
536870912 bytes copied in 0.117333 sec 4.575611 GB/sec</pre>
```

An easily achievable bandwidth

• a simple memcpy experiment ...

```
double t0 = cur_time();
memcpy(a, b, nb);
double t1 = cur_time();
```

```
$ gcc -03 memcpy.c
$ ./a.out $((1 << 26)) # 64M long elements = 512MB
$ 536870912 bytes copied in 0.117333 sec 4.575611 GB/sec</pre>
```


• much lower than the advertised number ...

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?


Cache and memory in a single-core processor

you almost certainly know this (*caches* and main memory), don't you?




..., with multi level caches, ...

recent processors have *multiple levels* of caches (L1, L2, ...)




..., with multicores in a chip, ...

- a single chip has several cores
- each core has its *private* caches (typically, L1 and L2)
- cores in a chip share a cache (typical, L3) and main memory




..., with simultaneous multithreading (SMT) in a core, ...

• each core has two *hardware threads*, which share L1/L2 caches and some or all execution units




..., and with multiple sockets per node.

- each node has several chips (sockets), connected via an interconnect (e.g., Intel QuickPath, AMD HyperTransport, etc.)
- each socket serves a part of the entire main memory
- each core can still access any part of the entire main memory



Today's typical single CPU node



Typical cache sizes

• L1 : 16KB - 64KB/core

• L2 : 256KB - 1MB/core

• L3 : $\sim 50 \text{MB/socket}$

GPU

Typical configuration

- L1 : $\sim 100\text{-}200\text{KB/SM}$
- L2 : $\sim 40 \mathrm{MB/device}$
- note: we will see later that cache latencies are much higher compared to CPU
- note: NVIDIA GPUs per-SM fast memory can be partitioned into
 - shared memory (\approx) software-managed cache
 - L1 cache (\approx) hardware-managed cache

• speed:

L1 > L2 > L3 > main memory

 \bullet speed:

L1 > L2 > L3 > main memory

• capacity:

L1 < L2 < L3 < main memory

• speed:

• capacity:

• each cache holds a subset of data in the main memory

 $L1, L2, L3 \subset main memory$

• speed:

• capacity:

• each cache holds a subset of data in the main memory

$$L1, L2, L3 \subset main memory$$

• typically but not necessarily,

$$L1 \subset L2 \subset L3 \subset main memory$$

• speed:

• capacity:

• each cache holds a subset of data in the main memory

$$L1, L2, L3 \subset main memory$$

• typically but not necessarily,

$$L1 \subset L2 \subset L3 \subset main memory$$

• which subset is in caches? → cache management (replacement) policy

• a cache generally holds data in *recently accessed* addresses, up to its capacity

- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced

- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced
- $\bullet \Rightarrow$ a (very crude) approximation; data in 32KB L1 cache

 \approx most recently accessed 32K distinct addresses

- a cache generally holds data in *recently accessed* addresses, up to its capacity
- this is accomplished by the LRU replacement policy (or its approximation):
 - every time a load/store instruction misses a cache, the least recently used data in the cache will be replaced
- ullet \Rightarrow a (very crude) approximation; data in 32KB L1 cache

$\approx most\ recently\ accessed\ 32K\ distinct\ addresses$

• due to implementation constraints, real caches are slightly more complex

Cache organization: cache line

- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

Cache organization: cache line

- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,
- a single line is the minimum unit of data transfer between levels (and replacement)



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

Cache organization: cache line

- a cache = a set of fixed size *lines*
 - typical line size = 64 bytes or 128 bytes,
- a single line is the minimum unit of data transfer between levels (and replacement)



a 32KB cache with 64 bytes lines (holds most recently accessed 512 distinct blocks)

data in 32KB L1 cache (line size 64B)

 \approx most recently accessed 512 distinct lines


Associativity of caches

full associative: a block can occupy any line in the cache, regardless of its address

direct map: a block has only *one* designated "seat" (*set*), determined by its address

K-way set associative: a block has K designated "seats", determined by its address

- direct map \equiv 1-way set associative
- full associative $\equiv \infty$ -way set associative



An example cache organization

• Ice Lake Platinum 8368

level	line size	capacity	associativity
L1	64B	48KB/core	12
L2	64B	512KB/core?	8
L3	64B	57MB/socket (38 cores)	??

• Skylake-X Gold 6130

level	line size	capacity	associativity
L1	64B	32KB/core	8
L2	64B	$1 \mathrm{MB/core}$	16
L3	64B	22MB/socket (16 cores)	11

• NVIDIA A100


level	line size	capacity	associativity
L1	128B?	192KB/core	?
L2	32B?	40 MB/core	?

What you need to remember in practice about associativity

- avoid having addresses used together "a-large-power-of-two" bytes apart
- corollaries:
 - avoid having a matrix with a-large-power-of-two number of columns (a common mistake)
 - avoid managing your memory by chunks of large-powers-of-two bytes (a common mistake)
 - avoid experiments only with $n = 2^p$ (a very common mistake)
- why? ⇒ they tend to go to the same set and "conflict misses" result

Conflict misses


- consider 8-way set associative L1 cache with 32KB (line size = 64B)
 - $32KB/64B = 512 (= 2^9)$ lines
 - $512/8 = 64 \ (= 2^6) \text{ sets}$
- \Rightarrow given an address a, a[6:11] (6 bits) designates the set it belongs to (indexing)



• if two addresses a and b are a multiple of 2^{12} (4096) bytes apart, they go to the same set

A convenient way to understand conflicts

• it's convenient to think of a cache as two dimensional array of lines. e.g. 32KB, 8-way set associative = 64 (sets) × 8 (ways) array of lines




A convenient way to understand conflicts

• formula 1:

if addresses are this much apart, they go to the same set

• e.g., 32KB 8-way set associative

 \Rightarrow the worst stride = 4096



A convenient way to understand conflicts


• lesser powers of two are significant too; continuing with the same setting (32KB, 8way-set assocative)

stride	the number of sets	utilization
	they are mapped to	
2048	2	1/32
1024	4	1/16
512	8	1/8
256	16	1/4
128	32	1/2
64	64	1

• formula 2: you stride by


$$P \times \text{line size} \quad (P \text{ divides } S)$$

- \Rightarrow you utilize only 1/P of the capacity
- N.B. formula 1 is a special case, with P = S



A remark about virtually-indexed vs. physically-indexed caches

- ullet caches typically use *physical* addresses to select the set an address maps to
- so "addresses" I have been talking about are physical addresses, not virtual addresses you can see as pointer values



• since virtual → physical mapping is determined by the OS (based on the availability of physical memory),


"two virtual addresses 2^b bytes apart"

does *not* necessarily imply "their physical addresses 2^b bytes apart"

• so what's the significance of the stories so far?

A remark about virtually-indexed vs. physically-indexed caches

- virtual \rightarrow physical translation happens with page granularity (typically, $2^{12} = 4096$ bytes)
- \bullet \to the last 12 bits are intact with the translation




A remark about virtually-indexed vs. physically-indexed caches

• therefore, "two virtual addresses 2^b bytes apart" \rightarrow "their physical addresses 2^b bytes apart"

for up to page size $(2^b \le page \ size)$

 \bullet \to the formula 2 is valid for strides up to page size


_	, оне тоги
stride	utilization
4096	1/64
2048	1/32
1024	1/16
512	1/8
256	1/4
128	1/2
64	1



Remarks applied to different cache levels

- small caches that use only the last 12 bits to index the set make no difference between virtually- and physically-indexed caches
- for larger caches, the utilization will similarly drop up to stride = 4096, after which it will stay around 1/64
- L1 (32KB/8-way) vs. L2 (256KB/8-way)

stride	utilization
	$\sim 1/64$
16384	$\sim 1/64$
8192	$\sim 1/64$
4096	1/64
2048	1/32
1024	1/16
512	1/8
256	1/4
128	1/2
64	1



Avoiding conflict misses

• e.g., if you have a matrix:

```
float a[100][1024];
then a[i][j] and a[i+1][j] go to the same set in L1 cache;
```

- $\bullet \Rightarrow$ scanning a column of such a matrix will experience almost 100% cache miss
- avoid it by:

```
1 float a[100][1024+16];
```

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

• approximation 1.0 (only consider C and Z; $K = \infty$):

Cache \approx most recently accessed C/Z distinct lines

- consider a cache of
 - capacity = C bytes
 - line size = Z bytes
 - associativity = K
- approximation 0.0 (only consider C; $\equiv Z = 1, K = \infty$):

Cache \approx most recently accessed C distinct addresses

• approximation 1.0 (only consider C and Z; $K = \infty$):

Cache \approx most recently accessed C/Z distinct lines

- approximation 2.0 (consider associativity too):
 - depending on the stride of the addresses you use, reason about the utilization (effective size) of the cache
 - in practice, avoid strides of "line size $\times 2^b$ "

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Assessing the cost of data access

- we like to obtain cost to access data in each level of the caches as well as main memory
- latency: time until the result of a load instruction becomes available
- bandwidth: the maximum amount of data per unit time that can be transferred between the layer in question to CPU (registers)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

How to measure a latency?

ullet prepare an array of N records and access them repeatedly

How to measure a latency?

- \bullet prepare an array of N records and access them repeatedly
- to measure the *latency*, make sure N load instructions make a chain of dependencies (link list traversal)


```
for (N times) {
   p = p->next;
}
```

How to measure a latency?

- \bullet prepare an array of N records and access them repeatedly
- to measure the *latency*, make sure N load instructions make a chain of dependencies (link list traversal)


```
for (N times) {
   p = p->next;
}
```

 make sure p->next links all the elements in a random order (the reason becomes clear later)



Data size vs. latency


• main memory is local to the accessing thread




How long are latencies

- heavily depends on in which level of the cache data fit
- environment: Skylake-X Xeon Gold 6130 (32KB/1MB/22MB)


size	level	latency	latency]
		(cycles)	(ns)	
12,736	L1	4.004	1.31] ;
103,616	L2	13.80	4.16	100
2,964,928	L3	77.40	24.24	1
301,307,584	main	377.60	115.45	




- if a cache strictly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest




- if a cache strictly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest



- if a cache strictly follows the LRU replacement policy, once data overflow the cache, repeated access to the data will quickly become *almost-always-miss*
- the "cliffs" in the experimental data look gentler than the theory would suggest




- ullet part of the gap is due to virtual \to physical address translation
- another factor, especially for L3 cache, will be a recent replacement policy for cyclic accesses (c.f. http://blog. stuffedcow.net/2013/01/ivb-cache-replacement/)



Latency to a remote main memory

• make main memory remote to the accessing thread

```
1 $ numactl -N 0 -i 1 ./mem
```




Contents


- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Bandwidth of a random link list traversal


$$bandwidth = \frac{total\ bytes\ read}{elapsed\ time}$$

• in this experiment, we set record size = 64 (cache size)






The "main memory" bandwidth



- \ll the memcpy bandwidth we have seen ($\approx 4.5 \text{ GB/s}$)
- not to mention the "memory bandwidth" in the spec

Why is the bandwidth so low?

• while traversing a single link list, only a single record access (64 bytes) is "in flight" at a time



• in this condition,

$$bandwidth = \frac{a \text{ record size}}{latency}$$


• e.g., take 115.45 ns as a latency

$$\frac{64 \text{ bytes}}{115.45 \text{ ns}} \approx 0.55 \text{ GB/s}$$

(physical) core


How to get more bandwidth?

• just like flops/clock, the only way to get a better throughput (bandwidth) is to perform many load operations concurrently



How to get more bandwidth?

• just like flops/clock, the only way to get a better throughput (bandwidth) is to perform many load operations concurrently




• there are several ways to make it happen; let's look at conceptually the most straightforward: traverse multiple lists

```
for (N times) {
   p1 = p1->next;
   p2 = p2->next;
   ...
}
```

Contents


- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?



• let's zoom into "main memory" regime (size > 100MB)


Bandwidth to the local main memory (not cache)

• an almost proportional improvement up to ~ 10 lists




Bandwidth to a remote main memory (not cache)


- pattern is the same (improve up to ~ 10 lists)
- remember the remote latency is longer, so the bandwidth is accordingly lower



• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, ...




• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, ...



• question: ... but up to ~ 10 , why?

• observation: bandwidth increase fairly proportionally to the number of lists, matching our understanding, ...



- question: ... but up to ~ 10 , why?
- answer: there is a limit in the number of load operations in flight at a time

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

 $\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

• this is what we've seen (still much lower than what we see in the "memory bandwidth" in the spec sheet)

- Line fill buffer (LFB) is the processor resource that keeps track of outstanding cache misses, and its size is 10 in Haswell
 - I could not find the definitive number for Skylake-X, but it will probably be the same
- this gives the maximum attainable bandwidth per core

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

- this is what we've seen (still much lower than what we see in the "memory bandwidth" in the spec sheet)
- how can we go beyond this? ⇒ the only way is to *use* multiple cores (covered later)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)
- fortunately, the life is not always that tough; there are other ways to issue many memory accesses concurrently
 - make addresses sequential
 - 2 make address generations independent
 - operation prefetch by software (make address generations go ahead)
 - use multiple threads/cores

- we've learned:
 - maximum bandwidth \approx as many memory accesses as possible always in flight
 - there is a limit due to LFB entries (10 in Haswell)
- so far, we have achieved larger bandwidth by traversing multiple lists explicitly (sometimes difficult if not impossible to apply)
- fortunately, the life is not always that tough; there are other ways to issue many memory accesses concurrently
 - make addresses sequential
 - 2 make address generations independent
 - operation prefetch by software (make address generations go ahead)
 - use multiple threads/cores
- remember, all boil down to keep as many memory accesses as possible (up to LFB entries) in flight


Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Make addresses sequential

- again build a (single) linked list, but this time, p->next always points to the immediately following block
- note that *the instruction sequence is identical* to before; only addresses differ


 (link all elements in the sequential order)



Bandwidth of traversing address-ordered list


• a factor of 10 faster than random case, but this time with only a single list

bandwidth of random list traversal vs address-ordered list traversal [0,1073741824]



The reason this is faster

- hardware prefetcher
- CPU watches the sequence of addresses accessed
- sequential addresses (addresses of a small constant stride) trigger CPU's hardware prefetcher
- CPU issues load instruction ahead of actual data stream on your behalf, to keep the maximum tumber of loads in flight (link all elements in the sequential order)




Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Make address generations independent

• if addresses of memory accesses can be computed without values returned from previous loads, CPU can issue them concurrently


```
for (N times) {
    j = ... /* not use a[·] */
    a[j];
}
```



• note: it's *not* a prefetch (but a real fetch)

Bandwidth when not traversing a list


- ptrchase : chase pointers of a random list
- random : access random addresses, but w/o pointer chasing
- sequential : access sequential addresses, w/o pointer chasing



Main memory bandwidth

- pointer chase ≪ random < sequential
- random is $\approx 5x$ faster than traversing a single random list


list traversal vs random access vs sequential access $\left[33554432,1073741824\right]$



Main memory bandwidth (random vs. sequential)

- sequential gets $\approx 3x$ more bandwidth than random
- may not be as bad as you thought?
- but why is there *any* difference, if both have the same number of loads in flight?

list traversal vs random access vs sequential access [33554432,1073741824]



Random (index) vs. sequential

- if both can have up to 10 (LFB entries) outstanding L1 cache misses, why is there *any* difference?
- I don't have a definitive answer, but presumably,
 - the hardware prefetcher happens at multiple levels (\rightarrow L1 and \rightarrow L2)
 - prefetchers to L2 are not subject of the LFP entries limit (the limit will be slightly more)
 - prefething to L2 make effective latency to the processor smaller

When "random access" is really bad

• in practice, when random vs. sequential makes a large ($\gg 2$) difference, it's because

a single element < a single cache line

- recall that touching a single byte in a cache line still brings the whole line (64 bytes)
- e.g., if you access an array of float (4 bytes) randomly, the bandwidth of *useful* data is amplified by a factor of 16 (= 64/4)

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- *if* you can generate those addresses much ahead of actual load instructions, you can *prefetch* them

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- *if* you can generate those addresses much ahead of actual load instructions, you can *prefetch* them
- instructions:
 - prefetcht $\{0,1,2\}$
 - prefetchnta

- hardware prefetch happens only for sequential (a small constant stride) accesses
- for other patterns, you the programmer may know addresses you are going to access soon
- *if* you can generate those addresses much ahead of actual load instructions, you can *prefetch* them
- instructions:
 - prefetcht $\{0,1,2\}$
 - prefetchnta
- intrinsics:

```
__builtin_prefetch(a [, rw, hint])
```

• truth is, there are actually not many cicumstances this is useful

- truth is, there are actually not many cicumstances this is useful
- ullet why? by the time you can prefetch it, you can likewise load it!

- truth is, there are actually not many cicumstances this is useful
- why? by the time you can *prefetch* it, you can likewise *load* it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)

- truth is, there are actually not many cicumstances this is useful
- why? by the time you can *prefetch* it, you can likewise *load* it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)


- truth is, there are actually not many cicumstances this is useful
- \bullet why? by the time you can prefetch it, you can likewise load it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)
- the only way to apply it is to change the data structure of the linked list

- truth is, there are actually not many cicumstances this is useful
- why? by the time you can *prefetch* it, you can likewise *load* it!
- in our example,
 - no point in applying it to index-based accesses (CPU will issue many load instructions already)
 - on the other hand, it's difficult to apply it to list traversal (it takes equally long time to generate address to prefetch)
- the only way to apply it is to change the data structure of the linked list
- but how?

• have another pointer pointing many elements ahead


```
for (N times) {
   p = p->next;
   prefetch(p->prefetch);
}
```

• it should point to Q elements ahead to have Q concurrent accesses in flight




"prefetch pointers" pointing to several elements ahead

Result



Summary: bandwidth of various access patterns

• sequential (w/o pointer chase) > sorted list > random (w/o pointer chase) ≈ 5 random lists \approx a random list + software prefetch > a random list



Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?

Memory bandwidth with multiple cores


• the bandwidth to a single core is limited by LFB entries and is much lower than the memory bandwidth itself

$$\frac{\text{transfer (line) size} \times \text{LFB entries}}{\text{latency}}$$

• you can go beyond that by using multiple cores and this is the only way

Memory bandwidth with multiple cores

- run up to 16 threads,
- each running on a distinct physical core of a single socket
- allocate all the data on the same socket (numactl -N 0 -i 0)
- note: they are still random pointer chasing




With random indexing and sequential accesses

- similar experiments with random indexing/sequential accesses
- $\sim 80 \text{ GB/sec}$ with sequential accesses by $\geq 12 \text{ threads}$
- the theoretical peak is

8 bytes $\times 2.666$ GHz $\times 6$ channels = 128 GB/sec

bandwidth with various methods and number of threads [33554432,1073741824]




With multiple CPU sockets

• the total bandwidth depends on how to place threads and data

	threads\data	CPU x	CPU y	all CPUs	local CPU
Ì	CPU x	1-local	1-remote	1-all	1-local
	all CPUs	all-1	all-1	all-all	all-local

- control threads/data placement by numactl command
- combine it with OMP_PROC_BIND=true to get a desired effect



numactl command (1)

- usage (see man numactl for details)
- 1 \$ numactl options command
 - for underlying system calls, see man -s 3 numa
- processors
 - -N x runs threads only on the CPU(s) x. e.g.,

```
$ numactl -N 0 command # threads on CPU 0
```

• --physcpubind x runs threads only on core(s) x. e.g.,

```
# threads on cores 0-11 and 16-27
numactl --physcpubind 0-11,16-27 command
```

numact1 command (2)

- memory (data)
 - ullet -i y allocates data (physical pages) on CPU(s) y

• -1 allocates physical pages to the CPU that touches the page for the first time (*first touch policy*; the default policy of Linux)

```
1 $ numactl -1 command
```

About the -1 option

- -1 (equivalent: --localalloc) allocates the physical page for a logical page on the CPU that first touches it (first touch)
- allocated physical pages do not move thereafter (unless you do so by move_pages() system call)
- don't be fooled by its name; it is *not* a policy that automagically makes memory accesses local
- quite contrary, it often makes a *hotspot* in a single CPU, especially when only one thread initializes (first-touches) the data
- -iall is not optimal, but often much safer for parallel applications

OpenMP thread placement

• combine them with OMP_NUM_THREADS= and OMP_PROC_BIND=true to get a desired effect. e.g.,

```
$ OMP_NUM_THREADS=48 OMP_PROC_BIND=true numactl --physcpubind 0-11,16-27,32-43,48-59 -1 command
```

to

- run 12 threads on each CPU (of a host in the big partition)
- and use the first touch policy

Achieved bandwidth

- Skylake X 6130 ×4 CPUs (a host of the "big" partition)
- use 12 (of 16) cores on each CPU
- in each measurement, each thread reads $\approx 640 \text{MB}$ sequentially 10 times

setting	threads	bandwidth (GB/sec)
1-local	12	85
1-remote	12	16
1-all	12	57
all-1	48	2
all-all	48	97
all-local	48	320

Remarks on remote access bandwidths

- numbers for remote accesses are ridiculously low
- the measurement is repeated 6 times and there were almost no variations in the result (within a few per cents)
- I am suspecting a wrong BIOS snoop setting (https://software.intel.com/en-us/forums/software-tuning-performance-optimization-platform-montopic/602160)


setting	threads	bandwidth (GB/sec)
1-local	12	85
1-remote	12	16
1-all	12	57
all-1	48	2
all-all	48	97
all-local	48	320

Contents

- Introduction
- 2 Many algorithms are bounded by memory not CPU
- 3 Organization of processors, caches, and memory
- 4 So how costly is it to access data?
 - Latency
 - Bandwidth
 - More bandwidth = concurrent accesses
- 5 Other ways to get more bandwidth
 - Make addresses sequential
 - Make address generations independent
 - Prefetch by software (make address generations go ahead)
 - Use multiple threads/cores
- 6 How costly is it to communicate between threads?


Shared memory

• if thread P writes to an address a and then another thread B reads from a, Q observes the value written by P



Shared memory


• if thread P writes to an address a and then another thread B reads from a, Q observes the value written by P



- ordinary load/store instructions accomplish this *(hardware shared memory)*
- this should not be taken for granted; processors have *caches* and a single address may be cached by multiple cores/sockets


Shared memory

- ⇒ processors sharing memory are running a complex, *cache coherence protocol* to accomplish this
- roughly,




Shared memory

- ⇒ processors sharing memory are running a complex, *cache coherence protocol* to accomplish this
- roughly,
 - a write to an address by a processor "invalidates" all other cache lines holding the address, so that no caches hold "stale" values



Shared memory


- ⇒ processors sharing memory are running a complex, *cache coherence protocol* to accomplish this
- roughly,
 - a write to an address by a processor "invalidates" all other cache lines holding the address, so that no caches hold "stale" values
 - 2 a read to an invalid line causes a miss and searches for a cache holding its "valid" value




• each line of a cache is in one of the following states Modified (■), Shared (□), Invalid (■)

- each line of a cache is inone of the following states


 Modified (), Shared (), Invalid ()
 - Modified (■) ⇒ you can read and write the line without invoking a transaction
 - Shared () \iff you can read but not write the line without invoking a transaction
 - Invalid (—) \iff you can neither read nor write the line without invoking a transaction




• a single address may be cached in multiple caches (lines)



- a single address may be cached in multiple caches (lines)
- \bullet \Rightarrow there are only two legitimate states for each line
 - one Modified (owner) + others Invalid (-, -, -, -, -, ...)



- a single address may be cached in multiple caches (lines)
- \bullet \Rightarrow there are only two legitimate states for each line
 - \bullet one Modified (owner) + others Invalid (\bullet , \bullet , \bullet , \bullet , \bullet , ...)
 - ② no Modified (□, ■, □, □, , ■, ...)



Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

- read miss: \rightarrow
 - there may be a cache holding it in Modified state (owner)
 - searches for the owner and if found, downgrade it to Shared
 - —, <mark>—</mark>, —, [—], —, … ⇒ —, —, [—], —, …

Cache states and transaction

- suppose a processor reads or writes an address and finds a line caching it
- what happens when the line is in each state:

	Modified	Shared	Invalid
read	hit	hit	read miss
write	hit	write miss	read miss; write miss

- read miss: \rightarrow
 - there may be a cache holding it in Modified state (owner)
 - searches for the owner and if found, downgrade it to Shared
 - —, <mark>—</mark>, —, [—], —, … ⇒ —, —, [—], —, …
- write miss: \rightarrow
 - there may be caches holding it in Shared state (sharer)
 - searches for sharers and downgrade them to Invalid
 - ullet -, -, -, [-], -, $\dots \Rightarrow$ -, -, -, [-], -, \dots

MESI and MESIF

• exitensions to MSI have been commonly used

MESI and MESIF

- exitensions to MSI have been commonly used
- MESI: MSI + Exclusive (owned but not modified)
 - when a read request finds no other caches that have the line, it owns it as Exclusive
 - Exclusive lines do not have to be written back to main memory when discarded

MESI and MESIF

- exitensions to MSI have been commonly used
- MESI: MSI + Exclusive (owned but not modified)
 - when a read request finds no other caches that have the line, it owns it as Exclusive
 - Exclusive lines do not have to be written back to main memory when discarded
- MESIF: MESI + Forwarding (a cache responsible for forwarding a line)
 - used in Intel QuickPath
 - when a line is shared by many readers, one is designated as the Forwarder
 - when another cache requests the line, only the forwarder sends it and the new requester becomes the forwarder
 - (in MSI or MESI, all sharers forward it)


How to measure communication latency?

• measure "ping-pong" latency between two threads

```
volatile long x = 0;
volatile long y = 0;
```

```
1  (ping thread)
2  for (i = 0; i < n; i++) {
3     x = i + 1;
4     while (y <= i);
5  }

(pong thread)
2  for (i = 0; i < n; i++) {
3     while (x <= i);
4     y = i + 1;
5  }</pre>
```



Environment

- Skylake X Gold 6130 ("big" partition of the IST cluster)
- 2 hardware threads \times 16 cores \times 4 sockets (= 128 processors seen by OS)
- ensure variables x and y are at least 64 bytes apart (not on the same cache line)
- bind both threads on specific processors by OpenMP environment variable OMP_BIND_PROC=true
- try all combinations of threads (i.e., with p threads, measure all the p(p-1) pairs) and show a matrix

Result

• (i, j) indicates the roundtrip latency (in reference clocks) between processor i and j

src	dest	latency
0	1-15	≈ 800
0	16-63	≈ 1100
0	64	≈ 110
0	65-79	≈ 450
0	80-127	≈ 1100

• a beautiful pattern emerges which is obviously telling

Result

- e.g., which processor is "close" to processor 0?
 - 64 is closest
 - 1-15 and 65-79 are close
 - 16-63 and 80-127 are farthest
- a natural interpretation
 - x and (x + 64) are two hardware threads on a core
 - 0-15 (and 65-79) are the 16 physical cores (32 hwts) on a socket
 - others are on different sockets

What they imply to parallel algorithms?

- you do not want to have many threads concurrently updating the same data
- remember SpMV COO?

```
// assume inside #pragma omp parallel
...
#pragma omp for
for (k = 0; k < A.nnz; k++) {
   i,j,Aij = A.elems[k];
#pragma omp atomic
   y[i] += Aij * x[j];
}</pre>
```

• y[i] += may be costing 1000 cycles when its single-thread execution would take just dozens of cycles

Summary (1): latency and bandwidth

• latency of data access heavily depends on which level of caches you actually access:

$$L1 \ (a \ few \ cycles) \le main \ memory \ (> 200 \ cycles)$$

• a single core bandwidth is limited by:

$$\frac{\text{cache line size} \times \text{LFB size}}{\text{latency}}$$

- for main memory, it's much lower than what you see in the spec
- max bandwidth is attainable only with multiple cores

Summary (2): bandwidth differs by access patterns

- $bandwidth = \frac{line \ size \times number \ of \ accesses \ in \ flight}{latency}$
- bandwidth heavily depends on the number of in-flight accesses, which depend on *access patterns*
 - random address pointer chasing
 - random but independent addresses
 - sequential

Common misunderstanding

- pointer chasing is always bad
 - not when data fit in L1 (perhaps L2) cache
 - not when accessed addresses are sequential
 - not when you manage to chase many pointer chains
- random access is always worse than sequential access
 - not so much when an element \approx cache size

Summary (3): inter processor communication

- cores communicate as a side effect of memory accesses (cache misses)
- it is natually as expensive as L2/L3 misses (or more), depending on whom you communicate with
- shared memory is nice, but you cannot forget the cost