
Switch & Router Configuration (Telnet & SSH)

Host Name: Cisco
Banner: RESTRICTED
Console Passw ord: cisco123
Enable Passw ord: cisco123
Secret Passw ord: secret
Telnet Passw ord: telnet123
Management IP: 192.168.0.10/24
Default Gatew ay: 192.168.0.1/24



Host Name: LUS
Domain Namin: cisco.com
user:taw sif
pas:taw sif
SSH Version: 2
Management IP: 172.16.0.10/24
Default Gatew ay: 172.16.0.1/24

S1	S2	Router0
Switch>en	Switch>en	Router>enRouter#config t
Switch#configure terminal	Switch#config t	Router(config)#hostname R1
Switch(config)#hostname	Switch(config)#hostname LUS	R1(config)#int gig0/0
Cisco	LUS(config)#ip domain-name	R1(config-if)#ip add 192.168.0.1
Cisco(config)#banner motd	cisco.com	255.255.255.0
#**** RESTRICTED	LUS(config)#username tawsif	R1(config-if)#no sh
****#	password tawsif	R1(config-if)#int gig0/1
Cisco(config)#line con 0	LUS(config)#enable pass	R1(config-if)#ip add 172.16.0.1
Cisco(config-line)#password	cisco123	255.255.255.0
cisco123	LUS(config)#interface vlan 1	R1(config-if)#no sh R1(config-if)#exit
Cisco(config-line)#login	LUS(config-if)#no sh	R1(config)#security passwords min-
Cisco(config-line)#exit	LUS(config-if)#ip add	length 8
Cisco(config)#enable	172.16.0.10 255.255.255.0	R1(config)#line console 0
password cisco123	LUS(config-if)#ex	R1(config-line)#password cisco123
Cisco(config)#line vty 0 15	LUS(config)#ip default-	R1(config-line)#login R1(config-
Cisco(config-line)#password	gateway 172.16.0.1	line)#exit
telnet123	LUS(config)#crypto key	Router(config)#enable password
Cisco(config-line)#int vlan 1	generate rsa	cisco123
Cisco(config-if)#ip add	LUS(config)#ip ssh version 2	R1(config)#ip domain-name cisco.com
192.168.0.10 255.255.255.0	LUS(config)#line vty 0 15	R1(config)#username tawsif password
Cisco(config-if)#no	LUS(config-line)#transport	tawsif
shutdown	input ssh	R1(config)#username tawsif password
Cisco(config-if)#exit	LUS(config-line)#login local	tawsiflu
Cisco(config)#enable secret	LUS(config-line)#exit	R1(config)#crypto key generate rsa
cisco123	LUS(config)#do show run	R1(config)#ip ssh version 2
Cisco(config)#exit	LUS(config)#do show ip	R1(config)#line vty 0 15
	interface brief	R1(config-line)#transport input ssh
		R1(config-line)#login local
		R1(config)#do show run