
## kathara lab

bgp: stub-as

Version	1.0
Author(s)	G. Di Battista, M. Patrignani, M. Pizzonia, F. Ricci, M. Rimondini
E-mail	contact@kathara.org
Web	http://www.kathara.org/
Description	architecture of a stub network; kathara version of a netkit lab



### customer classification



- stub networks
  - one link to a single isp




- multi-homed stub network
  - two or more links to the same isp
  - purposes: backup or load sharing




- multi-homed network
  - two or more links to different isps
  - purposes: backup or load sharing

© Computer Networks Research Group Roma Tre kathara – [ lab: bgp-stub-as ]

last update: Nov 2018




## stub network architecture




- one of the customer routers is chosen to be the default gateway
- the router is attached to a single router of the isp with a link (possibily more than one)
- a single peering in which as200 announces its route and accepts the default is enough


last update: Nov 2018



## router as 200 r1 configuration



## router as 20r1 configuration



# about default-originate v



- in zebra, using network 0.0.0.0/0 is enough to
  - place a default route in the local bgp routing table
  - announce it
- using default-originate for a specific neighbor
  - does not place a default route in the local bgp routing table
  - announces the default route to that neighbor, regardless of the presence of network 0.0.0.0/0 in the local router configuration

# about default-originate



- network 0.0.0.0/0 may be used at the top of the isp hierarchy to originate the default route
- network 0.0.0.0/0 should not be used at intermediate levels of the hierarchy
  - otherwise, routers would prefer the locally originated default route and remove the one offered by their upstream from the forwarding table
- using default-originate makes the default route appear as if it were originated by the upstream, even if it is not

command syntax

# default-originate and route-maps



- a default route originated with network
   0.0.0.0/0 is handled like any other route
  - route-maps used with a specific neighbor are applied to the default route as well
- a default route originated with defaultoriginate is processed by a different route-map:

```
neighbor <neighbor-ip> default-originate route-map
  <r-map-name> in
```

```
neighbor <neighbor-ip> default-originate route-map
<r-map-name> out
```

start the lab



check the bgpd configuration file



check the bgpd log file

```
    as20r1
as20r1:~# less /var/log/zebra/bgpd.log ■
```

check the routing table of as20r1

```
    as20r1

                                                                   _ _ ×
as20r1:~# route
Kernel IP routing table
Destination
                              Genmask
                                             Flags Metric Ref Use Iface
               Gateway
11.0.0.32
                                                                  0 eth0
                              255.255.255.252 U
                                                                 0 eth1
11.0.0.4
                              255.255.255.252 U
20.1.1.0
                              255.255.255.0
                                             U
                                                                  0 eth2
200.2.0.0 11.0.0.33
                              255.255.0.0
                                                                   0 eth0
                                             UG
as20r1:~# telnet localhost zebra
User Access Verification
Password: zebra
Router> show ip route
Codes: K - kernel route, C - connected, S - static, R - RIP, O - OSPF,
      B - BGP. > - selected route. * - FIB route
C>* 11.0.0.4/30 is directly connected, eth1
C>* 11.0.0.32/30 is directly connected, eth0
C>* 20.1.1.0/24 is directly connected, eth2
C>* 127.0.0.0/8 is directly connected, lo
B>* 200.2.0.0/16 [20/0] via 11.0.0.33, eth0, 00:03:22
Router> ■
```

check the bgpd cli (command line interface)

```
    as20r1

                                                                    _ ≜ ×
as20r1:~# telnet localhost bgpd
User Access Verification
Password: zebra
bgpd> show ip bgp neighbors
BGP neighbor is 11.0.0.33, remote AS 200, local AS 20, external link
 Description: Router as200r1
  BGP version 4, remote router ID 200.2.0.1
  BGP state = Established, up for 00:00:24
  Last read 00:00:23, hold time is 180, keepalive interval is 60 seconds
bgpd> show ip bgp
BGP table version is 0, local router ID is 20.1.1.1
Status codes: s suppressed, d damped, h history, * valid, > best, i - internal
Origin codes: i - IGP, e - EGP, ? - incomplete
                                      Metric LocPrf Weight Path
  Network
                   Next Hop
*> 0.0.0.0
                 0.0.0.0
                                                     32768 i
32768 i
                                                         0 200 i
Total number of prefixes 3
bgpd>
```

- perform several pings on the routers
- terminate the lab



last update: Nov 2018