HDFS Shell Commands

FS Shell

The FileSystem (FS) shell is an interface between the user and HDFS (Hadoop Distributed File System).

The FileSystem (FS) shell is invoked by bin/hadoop fs <args>. All the FS shell commands take path Uniform Resource Identifiers (URIs) as arguments.

The URI format is scheme://autority/path. For HDFS the scheme is hdfs, and for the local filesystem the scheme is *file*. The scheme and authority are optional. If not specified, the default scheme specified in the configuration is used. An HDFS file or directory such as /parent/child can be specified as hdfs://namenodehost/parent/child or simply as /parent/child (given that your configuration is set to point to hdfs://namenodehost). Most of the commands in FS shell behave like corresponding Unix commands. Differences are described with each of the commands. Error information is sent to stderr and the output is sent to stdout i.e.the display device in case of command line.

Please note two important points:

- 1. You can drop 'bin/' and just run hadoop fs <args> as well. Hadoop is a script which is present in the bin folder of the hadoop-1.2.1. We have put that in the active directory, so you need not do bin/.
- 2. If you're running 'hadoop fs -ls'

command first time after the 'hadoop namenode -format' command than you might be getting an error like

'... No such file or directory'

This is because hadoop filesystem is empty. That is why create new directory by running 'hadoop fs -mkdir firstdir' first and then run the 'hadoop fs -ls' command and you shouldn't be getting error.



The one marked should be well practised and known off-hand.

★ First: Other Important Commands

- 1. start-all.sh: This is to start all the demons.
- 2. stop-all.sh: To stop all demons.
- 3. jps: To list down all the java programs that are running.



Usage:

hadoop fs -cat URI [URI ...]

Copies source paths to stdout.

Example:

hadoop fs -cat hdfs://nn1.example.com/file1 hdfs://nn2.example.com/file2

hadoop fs -cat file:///file3 /user/hadoop/file4

Exit Code:

Returns 0 on success and -1 on error.

chgrp

Usage:

hadoop fs -chgrp [-R] GROUP URI [URI ...]

Change group association of files. With -R, make the change recursively through the directory structure. The user must be the owner of files, or else a super-user.

chmod

Usage:

hadoop fs -chmod [-R] <MODE[,MODE]... | OCTALMODE> URI [URI ...]

Change the permissions of files. With -R, make the change recursively through the directory structure. The user must be the owner of the file, or else a super-user.

chown

Usage:

hadoop fs -chown [-R] [OWNER][:[GROUP]] URI [URI]

Change the owner of files. With -R, make the change recursively through the directory structure. The user must be a super-user.



Usage:

hadoop fs -copyFromLocal <localsrc> URI

Similar to put command, except that the source is restricted to a local file reference.

1	copy		ocal
	COPy	ı	LUCA

Usage:

hadoop fs -copyToLocal [-ignorecrc] [-crc] URI <localdst>

Similar to get command, except that the destination is restricted to a local file reference.



Usage:

hadoop fs -cp URI [URI ...] <dest>

Copy files from source to destination. This command allows multiple sources as well in which case the destination must be a directory.

Example:

hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2

hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2 /user/hadoop/dir

Exit Code:

Returns 0 on success and -1 on error.

du

Usage:

hadoop fs -du URI [URI ...]

Displays aggregate length of files contained in the directory or the length of a file in case its just a file. Example:

hadoop fs -du /user/hadoop/dir1 /user/hadoop/file1 hdfs://nn.example.com/user/hadoop/dir1

Exit Code:

Returns 0 on success and -1 on error.

dus

Usage:

hadoop fs -dus <args>

Displays a summary of file lengths.

expunge

Usage:

hadoop fs -expunge

Empty the Trash. Refer to HDFS Design for more information on Trash feature.

* §	get
------------	-----

Usage:

hadoop fs -get [-ignorecrc] [-crc] <src> <localdst>

Copy files to the local file system. Files that fail the CRC check may be copied with the ignorecrc option. Files and CRCs may be copied using the -crc option.

Example:

hadoop fs -get /user/hadoop/file localfile

hadoop fs -get hdfs://nn.example.com/user/hadoop/file localfile

Exit Code:

Returns 0 on success and -1 on error.

getmerge

Usage:

hadoop fs -getmerge <src> <localdst> [addnl]

Takes a source directory and a destination file as input and concatenates files in src into the destination local file. Optionally addnl can be set to enable adding a newline character at the end of each file.



Usage:

hadoop fs -ls <args>

For a file returns stat on the file with the following format:

filename < number of replicas > filesize modification_date modification_time permissions userid groupid

For a directory it returns list of its direct children as in unix. A directory is listed as: dirname <dir> modification time modification time permissions userid groupid

Example:

hadoop fs -ls /user/hadoop/file1 /user/hadoop/file2 hdfs://nn.example.com/user/hadoop/dir1 /nonexistentfile

Exit Code: Returns 0 on success and -1 on error. 🖈 lsr Usage: hadoop fs -lsr <args> Recursive version of ls. Similar to Unix ls -R. mkdir 🖈 Usage: hadoop fs -mkdir <paths> Takes path uri's as argument and creates directories. The behavior is much like unix mkdir -p creating parent directories along the path. Example: hadoop fs -mkdir /user/hadoop/dir1 /user/hadoop/dir2 hadoop fs -mkdir hdfs://nn1.example.com/user/hadoop/dir hdfs://nn2.example.com/user/hadoop/dir Exit Code: Returns 0 on success and -1 on error. **★** movefromLocal Usage: dfs -moveFromLocal <src> <dst> Displays a "not implemented" message. 🖈 mv Usage:

hadoop fs -mv URI [URI ...] <dest>

Moves files from source to destination. This command allows multiple sources as well in which case the destination needs to be a directory. Moving files across filesystems is not permitted.

Exam	nl	e	•
	ρ,		۰

- hadoop fs -mv /user/hadoop/file1 /user/hadoop/file2
- hadoop fs -mv hdfs://nn.example.com/file1 hdfs://nn.example.com/file2 hdfs://nn.example.com/file3 hdfs://nn.example.com/dir1

Exit Code:

Returns 0 on success and -1 on error.



Usage:

hadoop fs -put <localsrc> ... <dst>

Copy single src, or multiple srcs from local file system to the destination filesystem. Also reads input from stdin and writes to destination filesystem.

- hadoop fs -put localfile /user/hadoop/hadoopfile
- hadoop fs -put localfile1 localfile2 /user/hadoop/hadoopdir
- hadoop fs -put localfile hdfs://nn.example.com/hadoop/hadoopfile
- hadoop fs -put hdfs://nn.example.com/hadoop/hadoopfile Reads the input from stdin.

Exit Code:

Returns 0 on success and -1 on error.



Usage:

hadoop fs -rm URI [URI ...]

Delete files specified as args. Only deletes non empty directory and files. Refer to rmr for recursive deletes.

Example:

hadoop fs -rm hdfs://nn.example.com/file /user/hadoop/emptydir

Exit Code:

Returns 0 on success and -1 on error.



ш	-	_	a	$\overline{}$	•
u	,	а	y	ı	

hadoop fs -rmr URI [URI ...]

Recursive version of delete.

Example:

- hadoop fs -rmr /user/hadoop/dir
- hadoop fs -rmr hdfs://nn.example.com/user/hadoop/dir

Exit Code:

Returns 0 on success and -1 on error.

setrep

Usage:

hadoop fs -setrep [-R] <path>

Changes the replication factor of a file. -R option is for recursively increasing the replication factor of files within a directory.

Example:

hadoop fs -setrep -w 3 -R /user/hadoop/dir1

Exit Code:

Returns 0 on success and -1 on error.

stat

Usage:

hadoop fs -stat URI [URI ...]

Returns the stat information on the path.

Example:

hadoop fs -stat path

Exit Code:

Returns 0 on success and -1 on error.

	on Udemy.com
	tail
	Usage:
	hadoop fs -tail [-f] URI
	Displays last kilobyte of the file to stdoutf option can be used as in Unix.
	Example:
•	hadoop fs -tail pathname
	Exit Code: Returns 0 on success and -1 on error.
	test
	Usage:
	hadoop fs -test -[ezd] URI
	Options: -e check to see if the file exists. Return 0 if truez check to see if the file is zero length. Return 0 if true -d check return 1 if the path is directory else return 0.
	Example:
•	hadoop fs -test -e filename
	text
	Usage:
	hadoop fs -text <src></src>
	Takes a source file and outputs the file in text format. The allowed formats are zip and TextRecordInputStream.
	touchz
	Usage:
	hadoop fs -touchz URI [URI]
	Create a file of zero length.
	Example:

hadoop -touchz pathname

Exit Code:

Returns 0 on success and -1 on error.