# **Conditioning of Square Linear Systems**

### **Contents**

O Vector and Matrix Norms

2 Conditioning

# **Vector and Matrix Norms**

#### **Vector Norms**

← generalization of the absolute value function

The "length" of a vector v can be measured by its norm.

### Definition 1 (p-Norm of a Vector)

Let  $p \in [1, \infty)$ . The p-norm of  $\mathbf{v} \in \mathbb{R}^m$  is denoted by  $\|\mathbf{v}\|_p$  and is defined by

$$\|\mathbf{v}\|_p = \left(\sum_{i=1}^m |v_i|^p\right)^{1/p}.$$

When  $p=\infty$ ,

$$\|\mathbf{v}\|_{\infty} = \max_{1 \leqslant i \leqslant m} |v_i| .$$

The most commonly used p values are 1, 2, and  $\infty$ :


$$\begin{split} \|\mathbf{v}\|_1 &= \sum_{i=1}^m |v_i|\,, \quad \|\mathbf{v}\|_2 = \sqrt{\sum_{i=1}^m |v_i|^2}. \end{split}$$
 Pythagorean thu.

#### **Vector Norms**

vectors nonnegative #.

In general, any function  $\|\cdot\|:\mathbb{R}^m\to\mathbb{R}^+\cup\{0\}$  is called a **vector norm** if it satisfies the following three properties:

- $2 \|\alpha \mathbf{x}\| = |\alpha| \|\mathbf{x}\|$  for any constant  $\alpha$  and any  $\mathbf{x} \in \mathbb{R}^m$ .
- **3**  $\|\mathbf{x} + \mathbf{y}\| \le \|\mathbf{x}\| + \|\mathbf{y}\|$  for any  $\mathbf{x}, \mathbf{y} \in \mathbb{R}^m$ . This is called the *triangle inequality*.



Examples Let 
$$\vec{V} = \begin{bmatrix} 3 \\ 3/2 \\ -9 \\ 0 \end{bmatrix}$$

$$\|\vec{y}\|_{1} = |3| + |\frac{3}{2}|$$

$$= 3 + \frac{3}{2} + \frac{3}{2}$$

$$= (9 + 94 + 81)^{1/2} = \sqrt{92.25}$$


$$(3) ||7||_{\infty} = \max\{131, 13/21, 1-91, 101\} = \max\{3, 3/2, 9, 0\} = 9$$

#### **Unit Vectors**

- A vector  $\mathbf{u}$  is called a **unit vector** if  $\|\mathbf{u}\| = 1$ .
- Depending on the norm used, unit vectors will be different.
- For instance:

$$\vec{u} = \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} \in \mathbb{R}^2$$








Figure 1: 1-norm

Figure 2: 2-norm

$$\|\vec{\lambda}\|_{2} = \sqrt{u_{1}^{2} + u_{2}^{2}} = 1$$
i.e.,  $u_{1}^{2} + u_{2}^{2} = 1$ 

Figure 3: ∞-norm

1.5-norm

Q. Why unit vectors W.r.t. 1-norm form a diamond?

$$\|\vec{u}\|_{1} = \|u_{1}| + \|u_{2}| = 1$$

Case 1 
$$u_1 > 0$$
,  $u_2 > 0$ 

$$|u_1| + |u_2| = u_1 + u_2 = 1$$

$$i.e., \quad u_2 = 1 - u_1$$

$$1 \quad \text{Case 1}$$

$$\frac{1}{|u_1| + |u_2|} = u_1 + u_2 = 1$$

$$\frac{|u_1| + |u_2|}{|u_2|} = u_1 + u_2 = 1$$

$$\frac{|u_1| + |u_2|}{|u_2|} = u_1 - u_2 = 1$$

$$\frac{|u_2|}{|u_2|} = u_1 - u_2 = 1$$

#### **Matrix Norms**

The "size" of a matrix  $A \in \mathbb{R}^{m \times n}$  can be measured by its **norm** as well. As above, we say that a function  $\|\cdot\|$   $\mathbb{R}^{m \times n} \to \mathbb{R}^+ \cup \{0\}$  is a **matrix norm** if it satisfies the following three properties:

- **1** ||A|| = 0 if and only if A = 0.
- 2  $\|\alpha A\| = |\alpha| \|A\|$  for any constant  $\alpha$  and any  $A \in \mathbb{R}^{m \times n}$ .
- ③  $\|A+B\| \le \|A\| + \|B\|$  for any  $A,B \in \mathbb{R}^{m \times n}$ . This is called the *triangle inequality*.

#### Matrix Norms (cont')

• If, in addition to satisfying the three conditions, it satisfies

$$\|AB\|\leqslant \|A\|\,\|B\|\quad \text{ for all }A\in\mathbb{R}^{m\times n}\text{ and all }B\in\mathbb{R}^{n\times p}\text{,}$$

it is said to be **consistent**.

If, in addition to satisfying the three conditions, it satisfies

then we say that it is **compatible** with a vector norm.

#### **Induced Matrix Norms**

#### Definition 2 (p-Norm of a Matrix)


Let  $p \in [1, \infty]$ . The p-norm of  $A \in \mathbb{R}^{m \times n}$  is given by

$$\|A\|_p = \max_{\mathbf{x} \neq 0} \frac{\|A\mathbf{x}\|_p}{\|\mathbf{x}\|_p} = \max_{\|\mathbf{x}\|_p = 1} \|A\mathbf{x}\|_p.$$

$$\max. over all max. over all noncero vectors$$

- The definition of this particular matrix norm is induced from the vector p-norm.
- By construction, matrix p-norm is a compatible norm. w.r.t. vector p-norm.
- Induced norms describe how the matrix stretches unit vectors with respect to the vector norm.
  - . matrix p-norm is consistent.

Example A & IR P=2.



Tuput (x GIR2)

output 
$$(\vec{y} = A\vec{x} \in \mathbb{R}^2)$$

#### **Induced Matrix Norms**

The commonly used p-norms (for  $p=1,2,\infty$ ) can also be calculated by

$$\|A\|_1 = \max_{1 \leqslant j \leqslant n} \sum_{i=1}^m \left|a_{ij}\right|, \qquad \max\left(\operatorname{Sum}\left(\operatorname{abs}\left(A\right), 1\right)\right)$$

$$\|A\|_2 = \sqrt{\lambda_{\max}(A^TA)} = \sigma_{\max}(A), \qquad \max_{1 \leqslant i \leqslant m} \sum_{j=1}^n \left|a_{ij}\right|. \qquad \max\left(\operatorname{Sum}\left(\operatorname{abs}\left(A\right), 2\right)\right)$$

In words,

- The 1-norm of A is the maximum of the 1-norms of all column vectors.
- The 2-norm of A is the square root of the largest eigenvalue of  $A^{T}A$ .
- The  $\infty$ -norm of A is the maximum of the 1-norms of all row vectors.

#### Non-Induced Matrix Norm - Frobenius Norm

#### Definition 3 (Frobenius Norm of a Matrix)

The Frobenius norm of  $A \in \mathbb{R}^{m \times n}$  is given by

$$||A||_F = \left(\sum_{i=1}^m \sum_{j=1}^n |a_{ij}|^2\right)^{1/2}.$$

- This is not induced from a vector *p*-norm.
- However, both p-norm and the Frobenius norm are consistent and compatible.
- For compatibility of the Frobenius norm, the vector norm must be the 2-norm, that is,  $\|A\mathbf{x}\|_2 \leqslant \|A\|_F \|\mathbf{x}\|_2$ .

#### Norms in MATLAB

```
\vec{V}^{T}\vec{V} = [V_1 \ V_2 - V_N] \begin{bmatrix} V_1 \\ V_2 \\ \vdots \\ \vdots \end{bmatrix} = V_1^2 + V_2^2 + \dots + V_N^2
```

• Vector *p*-norms can be easily computed:


```
norm(v, 1) % = sum(abs(v))
norm(v, 2) % = sqrt(v'*v) if v is a column
norm(v, 'inf') % = max(abs(v))
```

• The same function norm is used to calculate matrix *p*-norms:

To calculate the Frobenius norm:

```
norm(A, 'fro') % = sqrt(A(:)'*A(:))
% = norm(A(:), 2)
```


# Conditioning



Conditioning (sensitivity) is the ratio of these two.

Case 1





# Conditioning of Solving Linear Systems: Overview

- Analyze how <u>robust</u> (or <u>sensitive</u>) the solutions of  $A\mathbf{x} = \mathbf{b}$  are to perturbations of A and  $\overline{\mathbf{b}}$ .
- For simplicity, consider separately the cases where
  - **1** b changes to b  $+(\delta \mathbf{b})$  while A remains unchanged, that is

Some as 
$$\Delta \vec{b}$$
  $A\mathbf{x} = \mathbf{b}$   $\longrightarrow$   $A(\mathbf{x} + \delta \mathbf{x}) = \mathbf{b} + \delta \mathbf{b}$ .

2 A changes to  $A + \delta A$ , while b remains unchanged, that is

Same as 
$$\triangle A = b \longrightarrow (A + \delta A)(\mathbf{x} + \delta \mathbf{x}) = \mathbf{b}$$
.

· Assume the matrix norm used is consistent and compatible.

Given: A, b
Wont: \( \frac{1}{2} \) such that
(A\( \frac{2}{2} = \frac{1}{2} \))

## Sensitivity to Perturbation of RHS

$$(\overline{1} \rightarrow \overline{1} + 5\overline{1})$$

Case 1. 
$$A\mathbf{x} = \mathbf{b} \to A(\mathbf{x} + \delta \mathbf{x}) = \mathbf{b} + \delta \mathbf{b}$$

• Bound  $\|\delta \mathbf{x}\|$  in terms of  $\|\delta \mathbf{b}\|$ :

$$A\mathbf{x} + A\delta \mathbf{x} = \mathbf{b}' + \delta \mathbf{b}$$

$$A\delta \mathbf{x} = \delta \mathbf{b} \qquad \Longrightarrow \qquad \|\delta \mathbf{x}\| \leqslant \|A^{-1}\| \|\delta \mathbf{b}\|.$$

$$\delta \mathbf{x} = A^{-1}\delta \mathbf{b} \qquad (by compatibility)$$

Sensitivity in terms of relative errors:

$$\frac{|\delta \mathbf{x}|}{|\delta \mathbf{b}|} = \frac{\|\delta \mathbf{x}\|}{\|\delta \mathbf{b}\|} = \frac{\|\delta \mathbf{x}\| \|\mathbf{b}\|}{\|\delta \mathbf{b}\| \|\mathbf{x}\|} \le \frac{\|A^{-1}\| \|\delta \mathbf{b}\| \cdot \|A\| \|\mathbf{x}\|}{\|\delta \mathbf{b}\| \|\mathbf{x}\|} = \|A^{-1}\| \|A\|.$$

# Sensitivity to Perturbation of Matrix

$$(A3+A \leftarrow A)$$

Case 2. 
$$A\mathbf{x} = \mathbf{b} \rightarrow (A + \delta A)(\mathbf{x} + \delta \mathbf{x}) = \mathbf{b}$$

• Bound  $\|\delta \mathbf{x}\|$  now in terms of  $\|\delta A\|$ :

$$A\mathbf{x} + A\delta\mathbf{x} + (\delta A)\mathbf{x} + (\delta A)\delta\mathbf{x} = \mathbf{b}$$

$$A\delta\mathbf{x} = -(\delta A)\mathbf{x} - (\delta A)\delta\mathbf{x} \qquad \Longrightarrow$$

$$\delta\mathbf{x} = -A^{-1}(\delta A)\mathbf{x} - A^{-1}(\delta A)\delta\mathbf{x}$$

for the following, we need a technical tool called Neumann's series.  $\|\delta\mathbf{x}\| \lesssim \|A^{-1}\| \|\delta A\| \|\mathbf{x}\|.$  (first-order truncation) as  $\|\delta A\| \to 0$ 

Sensitivity in terms of relative errors:

$$\frac{\frac{\|\delta \mathbf{x}\|}{\|\mathbf{x}\|}}{\frac{\|\delta A\|}{\|A\|}} = \frac{\|\delta \mathbf{x}\| \|A\|}{\|\delta A\| \|\mathbf{x}\|} \lesssim \frac{\|A^{-1}\| \|\delta A\| \|\mathbf{x}\| \cdot \|A\|}{\|\delta A\| \|\mathbf{x}\|} = \|A^{-1}\| \|A\|.$$

#### **Matrix Condition Number**

 Motivated by the previous estimations, we define the matrix condition number by

$$\kappa(A) = ||A^{-1}|| ||A||,$$

where the norms can be any p-norm or the Frobenius norm.

( consistent & compatible)

• A subscript on  $\kappa$  such as 1, 2,  $\infty$ , or F(robenius) is used if clarification is needed.

$$K_{1}(A)$$
,  $K_{2}(A)$ ,  $K_{\infty}(A)$ ,  $K_{F}(A)$ , ...

## Matrix Condition Number (cont')

Interpretation

| We can write


Case 1. Case 2
$$\frac{\|\delta \mathbf{x}\|}{\|\mathbf{x}\|} \leqslant \kappa(A) \frac{\|\delta \mathbf{b}\|}{\|\mathbf{b}\|}, \quad \frac{\|\delta \mathbf{x}\|}{\|\mathbf{x}\|} \leqslant \kappa(A) \frac{\|\delta A\|}{\|A\|},$$

K(A): magnification ratio of errors

where the second inequality is true only in the limit of infinitesimal perturbations  $\delta A$ .



The matrix condition number  $\kappa(A)$  is equal to the condition number of solving a linear system of equation Ax = b.



- The exponent of  $\kappa(A)$  in scientific notation determines the approximate number of digits of accuracy that will be lost in calculation of x.
- Since  $1 = ||I|| = ||A^{-1}A|| \le ||A^{-1}|| ||A|| = \kappa(A)$ , a condition number of 1 is the best we can hope for.
- If  $\kappa(A) > [eps]^{-1}$ , then for computational purposes the matrix is singular.

#### **Condition Numbers in MATLAB**

• Use cond to calculate various condition numbers:

```
cond(A) % the 2-norm; or cond(A, 2) cf; norm(A) = norm(A,2) cond(A, 1) % the 1-norm cond(A, Inf) % the infinity-norm cond(A, 'fro') % the Frobenius norm
```

A condition number estimator (in 1-norm)

```
condest(A) % faster than cond
```

• The fastest method to estimate the condition number is to use linsolve function as below:

```
[x, inv_condest] = linsolve(A, b);
fast_condest = 1/inv_condest;
```