### Университет ИТМО

Факультет программной инженерии и компьютерной техники

# Лабораторная работа №6 по Администрированию систем и сетей «Создание WLAN»

Работу выполнили студенты группы Р34112: Кульбако Артемий, Неманков Илья Преподаватель:


Афанасьев Дмитрий Борисович

Желаемая оценка: 3

Топология	3
Шаг 1. Настройка основных параметров устройств	3
Шаг 2. Настройка параметров проводной сети	4
Шаг 3. Настройка параметров точек доступа для входа в сет	ь 6
Шаг 4. Настройка параметров сервисов WLAN	7
Шаг 5. Проверка	8
Вывод	10

## Выполнение

#### Топология



#### Шаг 1. Настройка основных параметров устройств

#### Отключение ненужных портов:

[S1]interface GigabitEthernet 0/0/11

[S1-GigabitEthernet0/0/11]shutdown

[S1-GigabitEthernet0/0/11]quit

[S1]interface GigabitEthernet 0/0/12

[S1-GigabitEthernet0/0/12] shutdown

[S1-GigabitEthernet0/0/12]quit

#### Шаг 2. Настройка параметров проводной сети

#### Команда настройки VLAN:

```
[S1]vlan batch 100 101
Info: This operation may take a few seconds. Please wait for a
moment...done.
[S1]interface GigabitEthernet 0/0/13
[S1-GigabitEthernet0/0/13]port link-type trunk
[S1-GigabitEthernet0/0/13]port trunk allow-pass vlan 100 101
[S1-GigabitEthernet0/0/13]quit
[S1]interface GigabitEthernet 0/0/14
[S1-GigabitEthernet0/0/14]port link-type trunk
[S1-GigabitEthernet0/0/14]port trunk allow-pass vlan 100 101
[S1-GigabitEthernet0/0/14]quit
[S1]interface GigabitEthernet 0/0/10
[S1-GigabitEthernet0/0/10]port link-type trunk
[S1-GigabitEthernet0/0/10]port trunk allow-pass vlan 100 101
[S1-GigabitEthernet0/0/10]quit
[AC] vlan batch 100 101
Info: This operation may take a few seconds. Please wait for a
moment...done.
[AC]interface GigabitEthernet 0/0/10
[AC-GigabitEthernet0/0/10]port link-type trunk
[AC-GigabitEthernet0/0/10]port trunk allow-pass vlan 100 101
[AC-GigabitEthernet0/0/10]quit
[S3] vlan batch 100 101
Info: This operation may take a few seconds. Please wait for a
moment...done.
[S3]interface GigabitEthernet 0/0/1
[S3-GigabitEthernet0/0/1]port link-type trunk
[S3-GigabitEthernet0/0/1]port trunk allow-pass vlan 100 101
[S3-GigabitEthernet0/0/1]quit
[S3]interface GigabitEthernet 0/0/4
[S3-GigabitEthernet0/0/4]port link-type trunk
[S3-GigabitEthernet0/0/4]port trunk pvid vlan 100
[S3-GigabitEthernet0/0/4]port trunk allow-pass vlan 100 101
[S3-GigabitEthernet0/0/4]quit
[S4] vlan batch 100 101
Info: This operation may take a few seconds. Please wait for a
moment...done.
[S4]interface GigabitEthernet0/0/1
[S4-GigabitEthernet0/0/1] port link-type trunk
[S4-GigabitEthernet0/0/1] port trunk allow-pass vlan 100 to 101
[S4-GigabitEthernet0/0/1]quit
[S4]interface GigabitEthernet0/0/4
[S4-GigabitEthernet0/0/4] port link-type trunk
[S4-GigabitEthernet0/0/4] port trunk pvid vlan 100
```

[S4-GigabitEthernet0/0/4] port trunk allow-pass vlan 100 to 101

#### Команда настройки ір-адресов интерфейсов:

[S1]interface Vlanif 101
[S1-Vlanif101]ip address 192.168.101.254 24
[S1-Vlanif101]quit
[S1]interface LoopBack 0
[S1-LoopBack0] ip address 10.0.1.1 32
[S1-LoopBack0]quit

#### Команда настройки DHCP:

[S1]dhcp enable
Info: The operation may take a few seconds. Please wait for a moment.done.
[S1]ip pool sta
Info:It's successful to create an IP address pool.
IP address pool for STAs
[S1-ip-pool-sta]network 192.168.101.0 mask 24
[S1-ip-pool-sta]gateway-list 192.168.101.254
[S1-ip-pool-sta]quit
[S1]interface Vlanif 101
[S1-Vlanif101]dhcp select global
[S1-Vlanif101]quit

#### [AC] dhcp enable

Info: The operation may take a few seconds. Please wait for a
moment.done.

[AC] ip pool ap

Info: It is successful to create an IP address pool.

IP address pool for APs

[AC-ip-pool-ap]network 192.168.100.254 mask 24

[AC-ip-pool-ap]gateway-list 192.168.100.254

[AC-ip-pool-ap]quit

[AC]interface Vlanif 100

[AC-Vlanif100]dhcp select global

[AC-Vlanif100]quit

#### Шаг 3. Настройка параметров точек доступа для входа в сеть

#### Команды создания группы АР:

[AC]wlan

[AC-wlan-view]ap-group name ap-group1

Info: This operation may take a few seconds. Please wait for a moment.done.

[AC-wlan-ap-group-ap-group1]quit

#### Команды создания и настройки профиля регулирующего домена:

[AC]wlan

[AC-wlan-view]regulatory-domain-profile name default

[AC-wlan-regulate-domain-default]country-code cn

Info: The current country code is same with the input country code.

[AC-wlan-regulate-domain-default]quit

#### Команды привязки домена резулируюего домена к группе АР:

[AC]wlan

[AC-wlan-view]ap-group name ap-group1

[AC-wlan-ap-group-ap-group1] regulatory-domain-profile default

Warning: Modifying the country code will clear channel, power and antenna gain configurations of the radio and reset the

AP. Continue?[Y/N]:y

## Команды указания интерфейса-источника на АС для установления туннелей CAPWAP:

[AC]capwap source interface Vlanif 100

# Команды импорта точек доступа в AC и добавления их в группу AP с именем ap-group1:

[AC]wlan

 $[{\tt AC-wlan-view}] \, {\tt ap} \, \, {\tt auth-mode} \, \, {\tt mac-auth} \, \,$ 

[AC-wlan-view]ap-id 0 ap-mac 00E0-FCC0-0570

AC-wlan-ap-0]ap-name ap1

[AC-wlan-ap-0]ap-group ap-group1

Warning: This operation may cause AP reset. If the country code

changes, it will clear channel, power and antenna gain

configurations of the radio, Whether to continue? [Y/N]:y //Введите у для подтверждения.

Info: This operation may take a few seconds. Please wait for a moment.. done.

[AC-wlan-ap-0]quit

[AC-wlan-view]ap-id 1 ap-mac 00E0-FC0D-34D0

[AC-wlan-ap-1]ap-name ap2

[AC-wlan-ap-1]ap-group ap-group1

Warning: This operation may cause AP reset. If the country code

changes, it will clear channel, power and antenna gain

configurations of the radio, Whether to continue? [Y/N]:y //Введите у для подтверждения.

Info: This operation may take a few seconds. Please wait for a
moment.. done.
[AC-wlan-ap-1]quit

#### Вывод на экран информации о текущей АР:

[AC-wlan-view]display ap all

Info: This operation may take a few seconds. Please wait for a moment.done.

Total AP information:

nor : normal [2]

ID MAC Name Group IP Type State STA Uptime

0 00e0-fcc0-0570 ap1 ap-group1 192.168.100.14 AP9131DN nor 0 22S

1 00e0-fc0d-34d0 ap2 ap-group1 192.168.100.59 AP9131DN nor 0 -

Total: 2

#### Шаг 4. Настройка параметров сервисов WLAN

# Команды создания профиля безопасности HCIA-WLAN и настройки политики безопасности:

[AC-wlan-view]security-profile name HCIA-WLAN [AC-wlan-sec-prof-HCIA-WLAN]security wpa-wpa2 psk pass-phrase HCIA-Datacom aes

[AC-wlan-sec-prof-HCIA-WLAN] quit

#### Команды создания профиля SSID HCIA-WLAN:

[AC]wlan

[AC-wlan-view]ssid-profile name HCIA-WLAN

SSID profile HCIA-WLAN is created.

[AC-wlan-ssid-prof-HCIA-WLAN]ssid HCIA-WLAN

The SSID name is set to HCIA-WLAN.

Info: This operation may take a few seconds, please wait.done.

[AC-wlan-ssid-prof-HCIA-WLAN]quit

#### Команды создания профиля VAP HCIA-WLAN:

[AC]wlan

[AC-wlan-view]vap-profile name HCIA-WLAN

[AC-wlan-vap-prof-HCIA-WLAN] forward-mode direct-forward

[AC-wlan-vap-prof-HCIA-WLAN] service-vlan vlan-id 101

Info: This operation may take a few seconds, please wait.done.

[AC-wlan-vap-prof-HCIA-WLAN] security-profile HCIA-WLAN

Security profile HCIA-WLAN is bound.

Info: This operation may take a few seconds, please wait.done.

[AC-wlan-vap-prof-HCIA-WLAN]ssid-profile HCIA-WLAN

SSID profile HCIA-WLAN is bound.

Info: This operation may take a few seconds, please wait.done.


[AC-wlan-vap-prof-HCIA-WLAN]quit

Команды установки привязки профиля VAP к группе AP и примения конфигурацию профиля VAP HCIA-WLAN к радиомодулю 0 и радиомодулю 1 точек доступа в группе A:

[AC]wlan
[AC-wlan-view]ap-group name ap-group1
[AC-wlan-ap-group-ap-group1]vap-profile HCIA-WLAN wlan 1 radio all nfo: This operation may take a few seconds, please wait...done.
[AC-wlan-ap-group-ap-group1]quit

#### Шаг 5. Проверка

#### Подключение к WLAN:



#### Проверка связи с S1:

STA>ping 10.0.1.1

```
Ping 10.0.1.1: 32 data bytes, Press Ctrl_C to break
From 10.0.1.1: bytes=32 seq=1 ttl=255 time=125 ms
From 10.0.1.1: bytes=32 seq=2 ttl=255 time=125 ms
From 10.0.1.1: bytes=32 seq=3 ttl=255 time=141 ms
From 10.0.1.1: bytes=32 seq=4 ttl=255 time=141 ms
From 10.0.1.1: bytes=32 seq=5 ttl=255 time=140 ms
--- 10.0.1.1 ping statistics ---
5 packet(s) transmitted
5 packet(s) received
0.00% packet loss
round-trip min/avg/max = 125/134/141 ms
```

#### Вывод команды "display station all" на AC:

[AC-wlan-view] display station all

Rf/WLAN: Radio ID/WLAN ID

Rx/Tx: link receive rate/link transmit rate(Mbps)

STA MAC AP ID Ap name Rf/WLAN Band Type Rx/Tx RSSI VLAN IP address SSID

5489-985e-0826 0 ap1 0/1 2.4G - -/- - 101 192.168.101.252 HCIA-WLAN

Total: 1 2.4G: 1 5G: 0

## Вывод

В процессе выполнения лабораторной работы мы получили базовые навыки конфигурации WLAN. По ходу выполнения потебовалось настроить некоторые параметры WLAN, а также создать и настроить профиль WLAN. В результате получилось создать сеть, обеспечивающую мобильность устройств в ней, благодаря двум точкам доступа.