

## /connectors

Connector management: `/connectors list [--verbose] [--category ] | claude [query] [--category ] [--refresh] | add <id|source> [--force] | remove | enable | disable | connect | disconnect | auth | test | stores [--check] | help`

### Overview

`/connectors` manages **connectors**: named, user-facing integrations (Google Drive, Slack, GitHub, Git, Postgres, Puppeteer, and the wider community catalogue) that reach an external system through one or more **MCP servers**. A connector is a catalogue entry carrying a display name, a category, an authentication requirement, and one or more MCP servers; the MCP server remains the transport ragent already speaks (`McpClient`), so the connector system is a management and catalogue layer over machinery that already exists.

A bare `/connectors`, `/connectors help`, and any unrecognised subcommand all print the same usage block and create or modify no files.

The same operations are available from a shell via the ragent `connectors <sub>` CLI parity surface; the two surfaces share one help text and one set of command handlers.

The system is specified in `specs/connectors/SPEC.md` (FR-001..FR-041); the manual test plan is `specs/connectors/TESTPLAN.md`.

### Syntax

```
/connectors list [--verbose] [--category <name>]    # installed connectors + state
/connectors claude [query] [--category <name>] [--refresh] # interactive catalogue browser
/connectors add <id|source> [--force]                # install (recorded enabled)
/connectors remove <id>                               # uninstall (refused while enabled)
/connectors enable <id>                               # enable + connect now
/connectors disable <id>                              # disable + disconnect
/connectors connect <id>                              # connect an enabled connector
/connectors disconnect <id>                           # disconnect, leave enabled
/connectors auth <id>                                 # manage credential / report auth state
/connectors test <id>                                 # isolated connect-and-invoke harness
/connectors stores [--check]                          # report catalogue endpoints + provenance
/connectors help                                     # usage block
```

### Options / Subcommands

| Form                                                                | Description                                                                                                                                                                                                                                                                                                                 |
|---------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>/connectors list [--verbose] [--category &lt;name&gt;]</code> | One row per installed connector showing state, auth state, category, and bridged server/tool counts. <code>--verbose</code> adds detail. <code>--category</code> restricts the rows; ALL (any case) or a blank value clears the filter; an unknown category is refused with an <code>[err]</code> row and changes no state. |

| Form                                                                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>/connectors claude [query] [--category &lt;name&gt;] [--refresh]</code> | Open the interactive Claude connector-catalogue browser: a title line (catalogue name, query, active category, visible/total count), a scrollable result list with the block cursor on the highlighted row, an <code>[installed]</code> marker and distinct colour on already-installed connectors, and a footer of key hints. The optional query pre-fills the search field, <code>--category &lt;name&gt;</code> pre-selects the category filter (an unknown category is refused in the footer and no row is hidden), and <code>--refresh</code> bypasses the catalogue cache. Press <code>c</code> while the panel is open to cycle the filter through the catalogue's categories and back to ALL. |
| <code>/connectors add &lt;id\ source&gt; [--force]</code>                     | Install a connector from a catalogue id, a local directory holding a connector manifest, a local <code>.zip/.tar.gz</code> , or an <code>https://</code> URL naming a package. A fresh install is recorded <b>enabled</b> ; run <code>/connectors enable &lt;id&gt;</code> to connect its servers now in a running session. A duplicate id is refused unless <code>--force</code> is given.                                                                                                                                                                                                                                                                                                           |
| <code>/connectors remove &lt;id&gt;</code>                                    | Uninstall a connector. Refused while the connector is enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <code>/connectors enable &lt;id&gt;</code>                                    | Enable a connector and connect its servers now.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>/connectors disable &lt;id&gt;</code>                                   | Disable a connector and disconnect its servers.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>/connectors connect &lt;id&gt;</code>                                   | Connect an enabled connector's servers without a session restart.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <code>/connectors disconnect &lt;id&gt;</code>                                | Disconnect a connector's servers, leaving it enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <code>/connectors auth &lt;id&gt;</code>                                      | Manage a connector's credential (token, client secret) and report its auth state. Secrets live in the encrypted credential store; the manifest stores only the credential <i>name</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <code>/connectors test &lt;id&gt;</code>                                      | Connect in isolation with a throwaway probe, invoke one tool, and report per-step <code>[ ok ]/[fail]</code> results. Never touches the live session.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <code>/connectors stores [--check]</code>                                     | Report each catalogue endpoint and its provenance (default or config); <code>--check</code> also probes each endpoint.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <code>/connectors help</code>                                                 | Print the usage block. A bare <code>/connectors</code> or an unknown subcommand does the same.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

#### Sources accepted by `/connectors add`

- a catalogue connector id;
- a local directory holding a connector manifest;
- a local `.zip` or `.tar.gz` package;
- an `https://` URL naming a `.zip/.tar.gz` package (non-https URLs are refused).

## Examples

List everything with the productivity filter:

```
/connectors list --category productivity
```

Browse the catalogue interactively, filtered by query and category, then install and enable the result:

```
/connectors claude drive --category productivity
/connectors add google-drive
/connectors auth google-drive
/connectors enable google-drive
```

Test a connector without touching the live session:

```
/connectors test google-drive
```

Check where the catalogue endpoint comes from:

```
/connectors stores --check
```

## Output

Every report is prefixed with a From: `/connectors <sub>` attribution line (FR-006). A bare `/connectors`, `/connectors help`, and an unrecognised subcommand all render the same usage block (FR-017). All report text is ASCII.

`test` renders one line per harness step:

```
[ ok ] resolve servers (1 ms)
[ ok ] connect (12 ms)
[ ok ] tool invoke (3 ms)
```

and ends by confirming the harness was torn down with the live session untouched.

## Configuration

The `connectors` block in `ragent.json` controls the subsystem (`enabled`, `store_dir`, the catalogue stores endpoints and fetch budgets, and the non-secret `credentials` name mapping). With `connectors.enabled: false`, every subcommand other than `help` reports the subsystem is disabled and no discovery, catalogue fetch, or connection occurs. Connectors are discovered under `.ragent/connectors/` (project), falling back to `~/.config/ragent/connectors/` (user-global).

See `docs/howtos/config.md §7.39` and `specs/connectors/SPEC.md`.

## Related

- `docs/howtos/connectors.md` - the full connector-system manual
- `/mcp` - MCP server status, discovery, and enable/disable
- `/plugins` - the sandboxed Codex/Claude plugin system (a sibling catalogue)
- `ragent connectors <sub>` - CLI parity for the same subcommands
- `specs/connectors/SPEC.md` - the full connector-system specification