/provider

Change provider, show config, or configure model router: /provider [show|router|help]

Overview

`/provider` is the entry point for provider configuration in the TUI. The bare form opens the interactive provider setup dialog, `/provider show` opens a viewer over the configured providers, and `/provider router` opens the model-router setup dialog seeded from the providers you have already configured. Provider setup covers API key entry, model selection, and provider-specific options; `/model` then picks a model from the configured provider.

Syntax

```
/provider               Open the interactive provider setup dialog
/provider show          Show configured providers
/provider router        Open the model-router setup dialog
/provider help          Show the help table
```

Options / Subcommands

Form	Description
`/provider`	Open the interactive provider setup dialog
`/provider show`	Show configured providers (and the router virtual provider when configured)
`/provider router`	Open the model-router setup dialog seeded from configured providers
`/provider help`	Show the help table

Any other argument prints a one-line usage reminder in the chat: `/provider` | `/provider show` | `/provider router` | `/provider help`.

Behaviour

- **Bare form.** Opens the provider selection step with API key entry forced (`force_key_entry: true`), so it can be used both for first setup and for adding another provider.
- **`show`.** Lists all configured providers from storage in a selection dialog. When a saved router configuration exists, a virtual `router` provider ("Model Router") is appended to the list so the cluster can be viewed inline. With no configured providers it reports `[warn] No configured providers`.
- **`router`.** Requires at least one concrete provider; without one it reports `[warn] No concrete providers - configure one first`. The router setup dialog is seeded with the concrete providers so tiers can be assigned to them.
- `/provider help` prints a four-row subcommand table into the chat.

Scrolling

Every list in the provider dialogs windows around its cursor, so a long list never hides the highlighted row: `Up`/`Down` move the painted slice one entry at a time and a clipped list says so (`Showing a-b of N`, or

a window in the pane title such as `Providers (*) 11-20 of 30`). The router setup's provider palette and each tier bucket scroll the same way, the bucket window following the selected model's own group of lines so its properties stay with it. The mouse wheel over an open setup dialog moves the cursor one entry per notch and is swallowed anywhere else, so the chat behind the modal never scrolls.

Examples

`/provider`

Opens the provider setup dialog to add or reconfigure a provider.

`/provider show`

Opens the provider-config viewer listing every configured provider, including the Model Router virtual entry when router config has been saved.

`/provider router`

Opens the router setup dialog seeded from the configured providers for tier assignment.

`/provider help`

Prints the subcommand table with status line `provider: help`.

`/provider models`

Unknown subcommand - prints the usage reminder line.

Dialog layout

Every step of provider setup shares one composition (the calm-slate chrome the plugin and connector catalogue panels wear):

```
 Provider Setup
Select a Provider                          2 of 14 configured
Provider                Id             Kind     Status
Ollama (Local)          ollama         [local]
Anthropic (Claude)      anthropic                  [ok]
          ^/v navigate  Enter select  Esc cancel
```

- The frame title names the step and, where there is one, its subject (the provider name in `Enter API Key`, the provider and target tier in the router assignment).
- The heading strip carries the step name on the left and a live count on the right (`N of 14 configured`, `N configured`, `N available  * = in use`).
- Steps that are lists carry a pinned black-on-grey column band above the rows, so the columns stay identified while the list scrolls: provider name / id / kind (`[local]`) / status (`[ok]` when a credential is stored).
- The selected row is a filled accent bar, rows alternate a near-black stripe, and the key-hint footer is muted. `Provider Reset` keeps its yellow warning frame and yellow cursor bar.
- `Switch Provider` (`/model` with several configured providers) names where each key came from (`stored`, `env`, `auto`) beside its `[ok]`.
- The model list steps out of the API-key dialog is the shared model picker; see `/model` for its column layout.

Output

- Bare and `show` forms: no chat text; a dialog state is set and the TUI renders the interactive provider UI.
- `router` form: dialog state when providers exist; otherwise the `[warn] No concrete providers - configure one first` status line plus a log entry.
- `help` form: help table in the message window with status `provider: help`.
- Unknown form: usage line in chat with status `provider: usage`.

Related

- `/model` - pick a model from the configured provider
- `/provider_reset` - remove the current provider and its stored credentials
- `/router` - manage router runtime state (enable/disable, test, reload)
- `ragent config` - CLI view of the resolved configuration
- `ragent auth` - CLI provider authentication setup