

How-To: The Connector System

agent can reach external systems through **connectors**: named, user-facing integrations (Google Drive, Slack, GitHub, Git, Postgres, Puppeteer, and the wider community catalogue) that connect through one or more **MCP servers**. A connector is a catalogue entry carrying a display name, a category, an authentication requirement, and one or more MCP servers; the MCP server remains the transport agent already speaks, so the connector system is a management and catalogue layer over machinery that already exists.

This document is the practical manual: what a connector is, how to browse, install, authenticate, and manage one, and how the configuration works.

Table of Contents

- 1. Overview
 - 2. What a Connector Is
 - 3. The Connector Store
 - 4. Browsing the Catalogue
 - 5. Installing, Enabling, and Managing
 - 6. Authentication
 - 7. Testing a Connector
 - 8. Configuration Reference
 - 9. Troubleshooting
 - 10. Reference
-

1. Overview

agent already has the transport (`McpClient`), a durable enable/disable ledger (`mcp_state.json`), an MCP discovery scanner, and a plugin-store browser. What the connector system adds is the **connector abstraction**: a catalogue entry that names an integration, points at one or more MCP servers, and carries its authentication shape, managed through one coherent surface (`/connectors`).

If you have used Claude's connectors, this is the equivalent: pick an integration from a catalogue, authenticate it, and its tools appear in the session.

2. What a Connector Is

A connector is a normalised descriptor with:

- an **id** and a **display name**;
- a **category** (for example `productivity`, `developer`, `data`);
- one or more **MCP server definitions** (`stdio`, `SSE`, or `HTTP`);
- an optional **authentication shape** and the **name** of a credential held in the encrypted credential store.

Because every connector resolves to one or more MCP servers, its tools surface to the model under the normal `mcp_<sanitized-server>_<tool>` names, and the permission system treats them exactly as any other MCP tool.

Bridged server ids are `<connector-id>.<server>` (the same collision-avoidance shape the plugin MCP bridge uses).

3. The Connector Store

Connectors are discovered under:

- `.ragent/connectors/` (project; highest priority), or
- `~/.config/ragent/connectors/` (user-global),

with an optional `connectors.store_dir` override. A freshly installed connector is recorded **disabled**, so installing can never silently connect a server; run `/connectors enable <id>` to connect it.

The durable enable state is the existing global `mcp_state.json` ledger shared with the rest of MCP, so a connector disabled once stays disabled everywhere and survives a restart.

4. Browsing the Catalogue

`/connectors claude [query] [--refresh]` opens an interactive catalogue browser:

- a title line with the catalogue name, the current query, the active category, and the visible/total result count;
- a scrollable list of results, with the block cursor on the highlighted row;
- an `[installed]` marker and distinct colour on connectors you already have;
- a footer of key hints.

While the panel is open it owns the keyboard: Up/Down move the cursor, ENTER installs the highlighted result, Backspace and Esc edit the query (and Esc on an empty query dismisses the panel). The catalogue fetch runs off the event loop, so the UI keeps animating while it loads.

`/connectors search <query>` searches the catalogue non-interactively, and `/connectors stores [--check]` reports each catalogue endpoint and its provenance (default or config).

5. Installing, Enabling, and Managing

Step	Command
Install	<code>/connectors add <id\ source></code> (recorded disabled)
Enable and connect now	<code>/connectors enable <id></code>
Disconnect but keep enabled	<code>/connectors disconnect <id></code>
Reconnect	<code>/connectors connect <id></code>
Disable and disconnect	<code>/connectors disable <id></code>
Uninstall	<code>/connectors remove <id></code> (refused while enabled)
List	<code>/connectors list [--verbose] [--category <name>]</code>

`/connectors add` accepts a catalogue connector id, a local directory holding a connector manifest, a local `.zip/.tar.gz`, or an `https://` URL naming a package. A duplicate id is refused unless `--force` is given; an archive member that would escape the store root is refused; a non-https package URL is refused.

`/connectors list --category <name>` restricts the rows to one category; ALL (any case) or a blank value clears the filter, and an unknown category is refused with an `[err]` row and changes no state.

6. Authentication

A connector's secrets (tokens, client secrets, refresh tokens) live in the existing **encrypted credential store**; the connector manifest stores only the credential *name*, never the value.

`/connectors auth <id>` reports a connector's auth state and lets a credential be supplied. A connector that requires authentication and has no valid credential reports `needs auth`, and its servers are refused until it is satisfied (there is no retry loop on an auth failure).

7. Testing a Connector

`/connectors test <id>` connects the connector's servers **in isolation** with a throwaway probe, invokes one tool, and reports per-step [`ok`]/[`fail`] results. It never touches the live session, so it is safe to run against a connector you are unsure about.

8. Configuration Reference

The `connectors` block in `ragent.json` controls the subsystem:

```
{
  "connectors": {
    "enabled": true,                // master switch; default true
    "store_dir": null,             // optional store-path override
    "stores": {
      "community": { "url": "https://example.org/connectors/index.json" },
      "timeout_ms": 10000,
      "max_index_bytes": 2097152,
      "cache_ttl_secs": 3600
    },
    "credentials": {
      "google-drive": { "token": "GDRIVE_TOKEN" }
    }
  }
}
```

The section merges overlay-wins (project config overrides user-global). With `connectors.enabled: false` the subsystem performs no discovery, no catalogue fetch, and no connection, and every subcommand other than `help` reports that it is disabled. See `docs/howtos/config.md §7.39` for the full field table.

9. Troubleshooting

- **the connector subsystem is disabled** - set `connectors.enabled: true`.
- **A connector lists as needs auth** - run `/connectors auth <id>` and supply the credential.
- **remove is refused** - disable the connector first with `/connectors disable <id>`.
- **A catalogue fetch fails** - check `/connectors stores --check` for the endpoint and its provenance, and confirm network access to the https URL.
- **An unexpressible entry is skipped** - a catalogue entry whose transport cannot be expressed as an MCP server (for example `grpc`) is skipped and counted, not fatal.

10. Reference

- docs/howtos/slashcommands/connectors.md - the /connectors slash-command reference
- docs/howtos/config.md §7.39 - the connectors config block
- docs/howtos/mcp.md - MCP server status, discovery, and enable/disable
- docs/howtos/plugins.md - the sandboxed plugin system (a sibling catalogue)
- `ragent connectors <sub>` - CLI parity for the same subcommands
- specs/connectors/SPEC.md - the full connector-system specification