

/connectors

Connector management: /connectors list [-verbose] [-category] | search [-category] | claude [query] [-refresh] | add <id|source> [-force] | remove | enable | disable | connect | disconnect | auth | test | stores [-check] | help

Overview

/connectors manages **connectors**: named, user-facing integrations (Google Drive, Slack, GitHub, Git, Postgres, Puppeteer, and the wider community catalogue) that reach an external system through one or more **MCP servers**. A connector is a catalogue entry carrying a display name, a category, an authentication requirement, and one or more MCP servers; the MCP server remains the transport ragent already speaks (McpClient), so the connector system is a management and catalogue layer over machinery that already exists.

A bare /connectors, /connectors help, and any unrecognised subcommand all print the same usage block and create or modify no files.

The same operations are available from a shell via the ragent connectors <sub> CLI parity surface; the two surfaces share one help text and one set of command handlers.

The system is specified in specs/connectors/SPEC.md (FR-001..FR-041); the manual test plan is specs/connectors/TESTPLAN.md.

Syntax

/connectors list [--verbose] [--category <name>]	# installed connectors + state
/connectors search <query> [--category <name>]	# search the catalogue
/connectors claude [query] [--refresh]	# interactive catalogue browser
/connectors add <id source> [--force]	# install (recorded disabled)
/connectors remove <id>	# uninstall (refused while enabled)
/connectors enable <id>	# enable + connect now
/connectors disable <id>	# disable + disconnect
/connectors connect <id>	# connect an enabled connector
/connectors disconnect <id>	# disconnect, leave enabled
/connectors auth <id>	# manage credential / report auth state
/connectors test <id>	# isolated connect-and-invoke harness
/connectors stores [--check]	# report catalogue endpoints + provenance
/connectors help	# usage block

Options / Subcommands

Form	Description
/connectors list [--verbose] [--category <name>]	One row per installed connector showing state, auth state, category, and bridged server/tool counts. --verbose adds detail. --category restricts the rows; ALL (any case) or a blank value clears the filter; an unknown category is refused with an [err] row and changes no state.

Form	Description
<code>/connectors search <query> [--category <name>]</code>	Search the catalogue by name, category, or tag, with the same <code>--category</code> filter.
<code>/connectors claude [query] [--refresh]</code>	Open the interactive Claude connector-catalogue browser: a title line (catalogue name, query, active category, visible/total count), a scrollable result list with the block cursor on the highlighted row, an <code>[installed]</code> marker and distinct colour on already-installed connectors, and a footer of key hints. <code>--refresh</code> bypasses the catalogue cache.
<code>/connectors add <id\ source> [--force]</code>	Install a connector from a catalogue id, a local directory holding a connector manifest, a local <code>.zip/.tar.gz</code> , or an <code>https://</code> URL naming a package. A fresh install is recorded disabled ; run <code>/connectors enable <id></code> to connect its servers. A duplicate id is refused unless <code>--force</code> is given.
<code>/connectors remove <id></code>	Uninstall a connector. Refused while the connector is enabled.
<code>/connectors enable <id></code>	Enable a connector and connect its servers now.
<code>/connectors disable <id></code>	Disable a connector and disconnect its servers.
<code>/connectors connect <id></code>	Connect an enabled connector's servers without a session restart.
<code>/connectors disconnect <id></code>	Disconnect a connector's servers, leaving it enabled.
<code>/connectors auth <id></code>	Manage a connector's credential (token, client secret) and report its auth state. Secrets live in the encrypted credential store; the manifest stores only the credential <i>name</i> .
<code>/connectors test <id></code>	Connect in isolation with a throwaway probe, invoke one tool, and report per-step <code>[ok]/[fail]</code> results. Never touches the live session.
<code>/connectors stores [--check]</code>	Report each catalogue endpoint and its provenance (default or config); <code>--check</code> also probes each endpoint.
<code>/connectors help</code>	Print the usage block. A bare <code>/connectors</code> or an unknown subcommand does the same.

Sources accepted by `/connectors add`

- a catalogue connector id;
- a local directory holding a connector manifest;
- a local `.zip` or `.tar.gz` package;
- an `https://` URL naming a `.zip/.tar.gz` package (non-https URLs are refused).

Examples

List everything with the productivity filter:

```
/connectors list --category productivity
```

Search the catalogue, then install and enable the result:

```
/connectors search drive
/connectors add google-drive
/connectors auth google-drive
/connectors enable google-drive
```

Browse the catalogue interactively (filter, browse, install with one key):

```
/connectors claude
```

Test a connector without touching the live session:

```
/connectors test google-drive
```

Check where the catalogue endpoint comes from:

```
/connectors stores --check
```

Output

Every report is prefixed with a From: `/connectors <sub>` attribution line (FR-006). A bare `/connectors`, `/connectors help`, and an unrecognised subcommand all render the same usage block (FR-017). All report text is ASCII.

`test` renders one line per harness step:

```
[ ok ] resolve servers (1 ms)
[ ok ] connect (12 ms)
[ ok ] tool invoke (3 ms)
```

and ends by confirming the harness was torn down with the live session untouched.

Configuration

The `connectors` block in `ragent.json` controls the subsystem (enabled, `store_dir`, the catalogue stores endpoints and fetch budgets, and the non-secret credentials name mapping). With `connectors.enabled: false`, every subcommand other than `help` reports the subsystem is disabled and no discovery, catalogue fetch, or connection occurs. Connectors are discovered under `.ragent/connectors/` (project), falling back to `~/.config/ragent/connectors/` (user-global).

See `docs/howtos/config.md §7.39` and `specs/connectors/SPEC.md`.

Related

- `docs/howtos/connectors.md` - the full connector-system manual
- `/mcp` - MCP server status, discovery, and enable/disable
- `/plugins` - the sandboxed Codex/Claude plugin system (a sibling catalogue)
- `ragent connectors <sub>` - CLI parity for the same subcommands
- `specs/connectors/SPEC.md` - the full connector-system specification