

Tools — MCP

Bridge to external Model Context Protocol (MCP) servers with auto-discovery of known server types and stdio clients.

Tool	Description
mcp_tool	Bridge to external Model Context Protocol servers.

MCP server tools surface dynamically as `mcp_<server>_<tool>` at runtime after discovery via the `/mcp discover` TUI command, or after `/mcp connect <id>` enables and connects a server live. Servers bridged from an enabled plugin's `mcpServers` section connect as `<plugin-id>.<server>` at startup.

mcp_tool

The `McpToolWrapper` calls a tool hosted on a connected MCP server.

Arguments

Argument	Type	Required	Description	Typical value
server	string	yes	MCP server name (as configured/discovered)	"filesystem"
tool	string	yes	Tool name exposed by the server	"read_file"
arguments	object	no	JSON payload forwarded to the server tool	{"path": "/tmp/x"}

Example:

```
mcp_tool server="github" tool="create_issue" arguments={"title": "Bug report"}
```

TUI commands: `/mcp /` `/mcp status` (server table), `/mcp discover` (probe for known servers), `/mcp connect <id>` and `/mcp disconnect <id>` (enable/disable and connect/disconnect live, persisted globally in `<state dir>/mcp_state.json`). The wrapper refuses to call a disabled server's tools even when the tool is still registered, and names the command that re-enables it.

Connection lifecycle

Every `McpClient::connect` attempt runs under a bounded per-attempt timeout (default 30 s, overridable with `RAGENT_MCP_CONNECT_TIMEOUT_SECS`) and is retried once on timeout only. A launcher such as `npx/npm exec` that stalls resolving a package, or a server that accepts the connection and then never answers the handshake, fails within the bound with an actionable error instead of hanging startup; a timed-out stdio attempt has its partially-started child torn down before the retry so the two attempts cannot collide. Genuine errors are surfaced immediately without a retry.

Startup does not block on the connect loop. The TUI adopts whatever state the loop has published and prints its one-shot per-server report off the loop's completion sentinel, an empty-id initialized event:

```
[mcp] Starting <id> (<transport>)
```

```
[mcp] Connected to mcp server <id> via <transport>
```

```
[mcp] Failed to connect to mcp server <id> via <transport>: <reason>
```

Every connect failure path records the server as `McpStatus::Failed { error }` before returning, so a server rejected by config validation (e.g. a stdio entry with no command) or otherwise failing before a transport is attempted is reported here and listed by `/mcp` with its reason, rather than only a single warn in the log panel. The startup connect loop publishes this client-derived status (connected, else failed: <reason>) on its per-server `McpStatusChanged` event, so `/mcp` shows the reason too.