

TITLE: CMSMS Config Variables

AUTHOR:

Copyright and License:

Copyright © 2011-12 by the CMS Made Simple Development Team. All Rights Are Reserved.

This document is free. You can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

However, as a special restriction to the GPL, when modifying and redistributing this document this notice in its entirety, along with a list of further copyright entitlements must be provided.

This document is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the

GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA. Or read it online

© 2011 CMS Made SimpleTM Page 1 of 12



Table of Contents

Copyright and License:	1
Introduction:	3
Scope:	3
Organization:	3
Variable Reference:	3
dbms	3
db_hostname	3
db_name	3
db_usemame	4
db_password	4
db_prefix	4
db_port	4
timezone	4
root_path	5
root_url	5
ssl_url	5
admin_url	5
uploads_path	5
uploads_url	6 C
ssl_uploads_url	6
	6 R
image_uploads_url	6
ssl_image_uploads_url	6
css_path	7
css_url	7
ssl_css_url	7

debug	7
admin_dir	7
persist_db_conn	8
previews_path (deprecated)	8
auto_alias_content	8
url_rewriting	8
page_extension	8
query_var	9
image_manipulation_prog (deprecated)	9
image_transform_lib_path	9
locale	
admin_encoding (deprecated)	9
default_encoding (deprecated)	10
set_names	
wiki_url (removed in CMSMS 1.11.3 and later)	10
show_performance_info	
debug_to_log	
php_memory_limit (deprecated)	
VISIVIS Config Variables	
showbase	
evision History:	
August 2011 – Robert Campbell	
October 2011 – Robert Campbell	
April 2012 – Robert Campbell	
July 2012 – Robert Campbell	12



Introduction:

This document is intended to provide a reference to the various config variables available in CMS Made Simple, and how to use them. It is intended as a reference for those people familiar with such concepts as database connectivity, file paths, permissions, and url rewriting. This document is not a tutorial or how-to guide.

Scope:

This document describes the variables as available in CMS Made Simple version 1.11 it does not include descriptions of variables used by third party addon modules, or for previous versions of CMSMS. Additionally, this document cannot be considered a complete reference. Third party modules and plugins may ignore some of these values or add their own.

Organization:

This document is organized roughly by the priority of the variables, from the top down. Most commonly used configuration variables will be described first.

Variable Reference:

dbms

Description: Specifies the database management system and libraries that CMSMS should use.

Status:RequiredType:StringAccepted Values:mysql, mysqli

Note: Postgres support was removed in CMSMS 1.11

db hostname

Description: Specifies the hostname of the system that hosts the database.. This should be

provided by your host.

Status: Required Type: String

Accepted Values: Any hostname, or IP address. 'localhost' is the proper value on most hosts.

db name

Description: Specifies the name of the database that CMSMS should use

Status: Required Type: String

Accepted Values: A valid database name. If you are unsure of this value, contact your hosting provider.

© 2011 CMS Made SimpleTM Page 3 of 12



db_usemame

Description: The usemame of the database user that has sufficient privilege to the database name

specified above. This is used to allow CVISVIS to connect to the database.

Status: Required Type: String

Accepted Values: The username of your account, or the database username created in the admin

console. Contact your host for the proper value for this field if you are uncertain.

db_password

Description: Specify the password associated to the database user. This is used to allow CMSMS

to connect to the database.

Status: Required Type: String

Accepted Values: The password (plain text) that is associated with the database username specified

above.

db_prefix

Description: Specify a prefix to use infront of all table names. This variable can be used to allow

multiple applications to coexist inside the dame database.

Status:RequiredType:StringDefault Value:cms_

db_port

Description: Specify an alternate port number to use when connecting to the database. This is

useful when your database is available on a port that is not the standard. The

information provided from your host should indicate this.

Status: Optional Type: integer

Default Value: 3306 for mysql, may be different for postgres or other systems.

timezone

Description: The server system timezone. This is used for ensuring that time calculations between

the database and the server itself are synchronized.

Note: Note: Behaviour has changed regarding timezones between PHP versions, when

running PHP 5.2 this variable may not need to be set. However in PHP 5.3 it needs to

be set to a valid value for your server.

Status: Required Type: String

Example: \$config['timezone'] = 'America/Denver';

Accepted Values: See this link: http://www.php.net/manual/en/timezones.php
See Also: http://php.net/manual/en/timezone-set.php

© 2011 CMS Made SimpleTM Page 4 of 12



root_path

Description: Specify the full and complete filesystem path to this CMSMS installation

Status: Optional Type: String

Accepted Values: A valid path specification

Default Value: Determined automatically from the script location.

root url

Description: Specify the normal (insecure) URL to the top of your website.

Status:OptionalType:String

Accepted Values: The valid fully qualified URL to the home page of the website.

Default Value Determined Automatically from server variables.

ssl url

Description: Specify the secure URL to the top of your website

Status: Optional Type: String

Accepted Values: A valid fully qualified HTTPS url to the home page of the website

Default Value: The root url with http:// replaced with https://

admin_url

Description: A url to specify a web accessible url to the CMSMS admin console

Status: Optional Type: String

Default Value: \$config['root_url'].'/'.\$config['admin_dir']

uploads_path

Description: This variable contains the absolute filesystem path to the location where files should

be uploaded.

Status: Optional Type: String

Accepted Values: A valid filesystem path that exists under the CMSMS root directory. Please ensure

permissions are set correctly to allow the web server to write files to this directory.

Default Value: \$config['root_path'].'/uploads';

Note: If you change this path to another directory you may also need to specify the

uploads_url, image_uploads_path, and image_uploads_url values. Additionally, the ssl_uploads_url and ssl_image_uploads_url values may need to be adjusted if using

HTTPS.

© 2011 CMS Made SimpleTM Page 5 of 12



uploads_url

Description: The web accessible URL that corresponds to the uploads path

Status: Optional Type: String

Accepted Values: A valid web acceptable URL. Please ensure that it corresponds to the uploads_path

variable specified above.

Default Value: \$config['root_url'].'/uploads';

Note: Specifying this path may be required if the uploads_path has been changed from its

default value.

ssl_uploads_url

Description: Specify the secure version of the URL corresponding to your uploads_url above. This

is only necessary when using SSL for some or all pages.

Status: Optional Type: String

Accepted Values: A valid, web accessible URL. Please ensure that it corresponds to the uploads_path

variable specified above.

Default Value: \$config['ssl_url'].'/uploads';

image_uploads_path

Description: The path used by the image manager and other functionality to upload and manages

images for your website.

Status:OptionalType:String

Accepted Values: A fully qualified filesystem path where images should be stored.

Default Values: \$config['uploads_path'].'/images';

image_uploads_url

Description: Specify the web accessible URL where images will be available. This must

correspond to the image_uploads_path above.

Status: Optional. Type: String

Accepted Values: A web accessible URL pefault Values: \$config['uploads_url'].'/images'

ssl_image_uploads_url

Description: Specify the secure version of the web accessible URL where images will be available.

This must correspond to the image_uploads_path above.

Status: Optional.

Type: String

Accepted Values: A web accessible URL

Default Values: \$config['uploads_url'].'/images'



css_path

Description: The path in which cms_stylesheet should generate css files.

Status: Optional.

Type: String

Accepted Values: A fully qualified filesystem path where generated stylesheet files should be stored.

Default Values: \$config['root_path'].'/tmp/cache';

css url

Description: The web location where css files generated by cms_stylesheet can be found.

Status:Optional.Type:String

Accepted Values: A web accessable URL where generated stylesheet files can be found.

Default Values: \$config['root_url'].'/tmp/cache';

ssl_css_url

Description: The secure web location where css files generated by cms_stylesheet can be found.

This value is used when generating web requests from secure pages.

Status:Optional.Type:String

Accepted Values: A secure web accessable URL where generated stylesheet files can be found.

Default Values: \$config['ssl_url'].'/tmp/cache';

debug

Description: Indicates whether debug mode is enabled. When debug mode is enabled automatic

redirection is disabled and query and trace information is appended to the output.

This mode should also be enabled to assist in diagnosing errors when error

messages are hidden by default.

Status:OptionalType:booleanAccepted Values:true or falseDefault Value:FALSE

admin dir

Description: Specify the name of the admin directory. This option can be used by advanced users

to specify an alternate admin directory name. Although this may cause difficulty with

the upgrade process.

Status: Optional Type: String

Accepted Values: A valid directory name (relative to the root_path above).

Default Value: admin

© 2011 CMS Made SimpleTM Page 7 of 12



persist_db_conn

Description: A flag that indicates whether persistent database connections should be used. This

variable may be of use on high load servers. Contact your host if encountering

problems and wondering whether this setting should be used.

Status:OptionalType:booleanAccepted Values:true or falseDefault Value:FALSE

previews_path (deprecated)

Description: Specify a location where the temporary information used for generating previews

should be stored.

Status: Optional Type: string

Accepted Values: A complete path specification that has write permissions by the web server process.

Default Value: Internal value.

auto alias content

Description: Specify whether page aliases should automatically be created for new pages.

Status: Optional Type: Boolean Default Value: FALSE

url_rewriting

Description: What type of URL rewriting should we be using for pretty URLs. The possible values

for this variable are system dependant.

Status: Optional Type: String

Accepted Values: none, internal, mod_rewrite

Example:: \$config['url_rewriting'] = 'internal';

Default Value: none

See Also: http://wiki.cmsmadesimple.org/index.php/FAQ/Installation/Pretty_URLs#Pretty_URLs

page_extension

Description: Used when the url_rewriting is a value other than 'none' this variable specifies the

extension that should be appended to all URLS that the system generates.

Status:OptionalType:StringDefault Value:n/a

Example: \$config['page_extension'] = '.html';

© 2011 CMS Made SimpleTM Page 8 of 12



query_var

Description: Specifies the name of the URL variable that will indicate the page alias. You should

not need to override this value unless the default value interferes with another

software package.

Status: Optional Type: String Default Value: page

image_manipulation_prog (deprecated)

Description: Specify the program (or library) that should be used for image manipulation.

Status: Optional Type: String Default Value: gd

Accepted Values gd or imagemagick

See Also: http://wiki.amsmadesimple.org/index.php/User_Handbook/Admin_Panel/Content/Imag

e Manager

image_transform_lib_path

Description: When using imagemagick as a manipulation program specify the library path to that

program.

Status:OptionalType:String

Default Value: /usr/bin/ImagelVlagick

locale

Note:

Description: Locale to use for various default date handling functions, etc. Leaving

this blank will use the value associated with the currently selected 'language' for

frontend or admin actions. Specifying this value will only be used once per request.

Though you can specify any valid locale, the locale information you specify must be

installed on the server.

Status: Optional Type: String Default Value: n/a

See Also: http://php.net/manual/en/function.setlocale.php
Note:
Behavior of this config variable changed in 1.11

admin_encoding (deprecated)

Description: Specify the encoding to use for admin translations.

Note: In almost all cases, default_encoding should be empty (which defaults to utf-8) and

admin_encoding should be utf-8. If you'd like this to be different, change both. Keep in mind, however, that the admin interface translations are all in utf-8, and will be converted on the fly to match the admin_encoding. This could seriously slow down

the admin interfaces for users.

Status: Optional Type: string
Default Value: utf-8

© 2011 CMS Made SimpleTM Page 9 of 12



default_encoding (deprecated)

Description: Specify the encoding to use for admin translations.

Note: In almost all cases, default_encoding should be empty (which defaults to utf-8) and

admin_encoding should be utf-8. If you'd like this to be different, change both. Keep in mind, however, that the admin interface translations are all in utf-8, and will be converted on the fly to match the admin_encoding. This could seriously slow down

the admin interfaces for users.

Status: Optional Type: string Default Value: n/a

set names

Description: A flag indicating whether a 'set names' command should be given to a mysql

database upon connection. Applies to mysql only

Status:OptionalType:BooleanDefault Value:FALSE

wiki_url (removed in CVISIVIS 1.11.3 and later)

Description: A URL indicating where the CMSMS wiki is located. Used for help links

Status: Optional Type: string

Default Value: http://wiki.cmsmadesimple.org/index.php/User Handbook/Admin Panel

show_performance_info

Description: A flag indicating whether performance information should be appended to all output

from CMSMS requests.

Note: This setting when enabled could interfere with the output of some modules, for

example when downloading files or exporting XVIL information. This variable is not normally set in the config file, setting this variable to any value will enable the feature.

Status:OptionalType:BooleanDefault Value:unset

debug_to_log

Description: A flag indicating whether the debug_to_log method should actually output anything.

This variable should be set to false for production environments.

Status:OptionalType:BooleanDefault Value:FALSE

© 2011 CMS Made SimpleTM Page 10 of 12



php_memory_limit (deprecated)

Description: This config variable, if set will attempt to override the memory available to PHP for

various tasks. Note: that this may have no success depending upon server

configuration.

Status: Optional

Type: String representing a memory amount. **Example**:: \$config['php_memory_limit'] = '32M';

Default Value: n/a

showbase

Description: This config variable, indicates wether the <base> tag should be output by the

{metadata} tag. This config variable can also be overridden by the showbase

parameter of the {metadata} tag.

Status: Optional Type: boolean

Example:: \$config['php_memory_limit'] = '32M';

Default Value: true

 $\ \odot$ 2011 CMS Made SimpleTM Page 11 of 12





Revision History:

August 2011 - Robert Campbell

Initial Revision

October 2011 - Robert Campbell

Fixes to minor spelling and puctuation errors.

April 2012 – Robert Campbell

Updated for CMSMS 1.11

- Adds css_path
- Adds css_url
- Adds ssl_css_url
- Removes process_whole_template
- Removes output_compression
- Removes use_adodb_lite
- Remove use_smarty_php_tags
- Removes default_upload_permission

July 2012 - Robert Campbell

Final corrections for 1.11

© 2011 CMS Made SimpleTM Page 12 of 12