Take Command 9.0

Published By JP Software Inc. P.O. Box 328 Chestertown, MD 21620 USA http://jpsoft.com

Table of Contents

Part I	Overview		2
Part II	What's New		3
Part III	Take Command		16
1	Starting Take Command		17
	Take Command Startup Op	ptions	17
	TCC (4NT) Startup Options	5	19
	TCSTART and TCEXIT		22
	TCC Exit Codes		24
2	Configuration Options		24
	Initialization (.INI) Files		24
	Directives		26
	Key Mapping Direc	ctives ·····	28
	General Input I	Keys	29
	Backspace		29
	BeginLine		29
	Copy (directive	ə)·····	29
	Del (directive)		30
	DelToBeginnin	ng	30
	DelToEnd		30
	DelWordLeft		30
	DelWordRight		30
	Down		30
	EndLine		31
	EraseLine		31
	ExecLine		31
	Ins		31
	Left		31
	NormalKey		31
	Paste		32
	Right		32
	Up		32
	WordLeft		32
	WordRight		32
	Command Line	e Editing Keys·····	32
	AddFile		
	AliasExpand		33
	CommandEsca	ape·····	33

DelHistory		33
DirWinOpen		34
EndHistory		34
Help (directive)		34
HelpWord		34
HistWinOpen		34
LastHistory		34
LFNToggle		35
LineToEnd		35
NextFile		35
NextHistory		35
NormalEditKey	/	35
PopFile		35
PrevArgument		35
PrevFile		36
PrevHistory		36
RepeatFile		36
SaveHistory		36
VariableExpan	d	36
LIST Keys		36
ListBack		37
ListClipboard		37
ListContinue		37
ListExit		37
ListFind		37
ListFindRegex		38
ListFindRegexF	Reverse	38
ListFindRevers	e	38
ListHex		38
ListHighBit		38
ListInfo		38
ListNext		38
ListOpen		39
ListPrevious		39
ListPrint		39
ListRefresh		39
ListUnicode		39
ListWrap		39
NormalListKey		40
Popup Window	/ Keys	40
NormalPopupK	(ey	40
PopupWinDel		40
PopupWinEdit		40

	PopupWinEditWin	40
	PopupWinExec	41
	Advanced Directives	41
	ClearKeyMap	41
	Debug	41
	INIQuery	42
	LanguageDLL	42
	MSAAMenu	43
	UpdateINI	43
	Take Command Configuration Dialog	43
	Windows ····	43
	Tabs	44
	Advanced	45
	Registration	46
	TCC (4NT) Configuration Dialog	46
	Startup	47
	Windows ····	49
	Command Line	50
	Advanced ·····	51
	Internet	53
	Debugger	54
	Updates ····	55
	Registration	55
3 The	Take Command Interface	56
	The Take Command Window	56
	Menus	58
	File	58
	Edit	59
	Tabs	60
	View	60
	Options	61
	Window	61
	Help	61
	Tool Bars	62
	Folders	63
	List View ·····	63
	Tab Windows ·····	64
	Status Bar	64
	Keyboard Shortcuts	64
	Context Menus	65
	Running DOS apps·····	66
	Using the Scrollback Buffer	66
	Highlighting & Copying Text	67

	Resizing the Take Command Window	68
	Drag & Drop	68
	Take Command Dialogs	68
	Run Program	. 69
	Tab Toolbar	. 69
	Skins and Themes	. 70
4	Directory Navigation	71
	CDPATH feature	. 72
	Extended Directory Searches	. 73
	Automatic Directory Changes	. 76
	Directory Aliases	. 76
5	File Selection	77
	Wildcards	. 77
	Ranges	. 80
	Size Ranges	82
	Date Ranges	82
	Time Ranges·····	84
	File Exclusion Ranges	85
	Description Ranges	86
	Attribute Switches	. 86
	Multiple Filenames	. 87
	Include Lists	. 88
	Delayed Variable Expansion	. 89
	LFN File Searches	. 89
	File Lists	. 90
	Switches for File Selection	91
6	Executable Extensions	91
7	Using Internet URLs	92
8	Using FTP and HTTP Servers	93
9	Input / Output Redirection	
	Redirection and Piping	
	Redirection	
	Piping	101
	ANSI X3.64 Support	101
	Keystack	102
	Page and File Prompts ······	102
10	OpenAFS	103
	The TCC (4NT) Command Line	
• •	Command Line Editing	103
	Command Line Editing	104
		100
	Command History Window	107
	Local and Global History Lists	100

	Command Names & Parameters	
	Conditional Expressions	
	Filename Completion	
	Customizing Filename Completion	
	Filename Completion Window	
	Converting Between Long & Short Filenames	
	Appending Backslashes to Directory Names	
	Extended Parent Directory Names	
	Directory History Window	
	Variable Name Completion	
	Expanding and Disabling Aliases	
	Multiple Commands	
	Conditional Commands	
	Command Grouping	
	Starting Applications	
	Waiting for Applications to Finish	
	Escape Character	
	Command Parsing	
	Command Line Length Limits	
	Special Character Compatibility	
	Date Input Formats	
	Date Input Formats	
2 Ali	·	
2 Ali	Case Sensitivity	
2 Ali	Case Sensitivity	
2 Ali	Case Sensitivity Ises & Batch Files Aliases	
2 Ali	Case Sensitivity Ises & Batch Files Aliases Batch Files	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files .BAT, .CMD & .BTM Files	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files .BAT, .CMD & .BTM Files Using .BAT Files Under TCC	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility	
2 Ali	Case Sensitivity Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters	······································
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files .BAT, .CMD & .BTM Files .Using .BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables	······································
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files .BAT, .CMD & .BTM Files .Using .BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands	······································
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, .CMD & .BTM Files Using .BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File	
2 Ali	Case Sensitivity ISSES & Batch Files Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command	
2 Ali	Case Sensitivity uses & Batch Files Aliases Batch Files .BAT, .CMD & .BTM Files .BAT, Elso Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command Using Aliases in Batch Files	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command Using Aliases in Batch Files Debugging Batch Files	
2 Ali	Case Sensitivity Isses & Batch Files Aliases Batch Files BAT, .CMD & .BTM Files Using .BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command Using Aliases in Batch Files Debugging Batch Files String Processing	
2 Ali	Case Sensitivity Aliases Batch Files Batch Files BAT, CMD & BTM Files Using .BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command Using Aliases in Batch Files Debugging Batch Files String Processing Batch File Line Continuation	
2 Ali	Case Sensitivity Aliases Batch Files BAT, CMD & BTM Files Using BAT Files Under TCC Echoing in Batch Files Special syntax for CMD.EXE compatibility Batch File Parameters Parameter Quoting Using Environment Variables Batch File Commands Interrupting a Batch File Detecting TCC and Take Command Using Aliases in Batch Files Debugging Batch Files String Processing Batch File Continuation Batch File Compression	

	EXTPR	ROC and SHEBANG Support	143
13	TCC (4NT) Inter	nal Commands	. 144
	Commands	by Name	144
	Commands	by Category	147
	?		152
	ACTIVATE		152
	ALIAS		154
	ASSOC		162
	ATTRIB		163
	BATCOMP		166
	BDEBUGGE	ER	166
	BEEP		173
	BREAK		174
	BREAKPOII	NT	174
	CALL		175
	CANCEL		176
	CD / CHDIR		177
	CDD		178
	CHCP		180
	CLS		181
	COLOR		181
	COPY		182
	DATE		189
	DEBUGSTR	ING	190
	DEFER		190
	DEL / ERAS	E	190
	DELAY		194
	DESCRIBE		195
	DETACH		197
	DIR		198
	DIRHISTOR	Υ	208
	DIRS		209
	DO		210
	DRAWBOX		214
	DRAWHLIN	E	215
	DRAWVLIN	E	216
	ECHO		217
	ECHOERR		218
	ECHOS		219
	ECHOSERR	}	220
	EJECTMED	IA	220
	ENDLOCAL		220
	ESET		222

EVENTLOG		223
	IITOR	224
EXCEPT		225
EXIT		227
FFIND		227
FIREWIREM	IONITOR	232
FOLDERMO	NITOR	232
FOR		234
FREE		241
FTYPE		241
FUNCTION		242
GLOBAL		245
GOSUB		247
GОТО		248
HEAD		249
HELP		251
HISTORY		251
IF		253
IFF		254
IFTP		255
INKEY		257
INPUT		259
JABBER		260
KEYBD		261
KEYS		261
KEYSTACK		262
LIST		264
LOADBTM		269
LOADMEDIA	4	269
LOG		269
MD/MKDIR		271
MEMORY		272
MKLINK		272
MKLNK		273
MOVE		274
MSGBOX		279
NETMONITO	OR	281
ON		282
OPTION		284
OSD		286
PATH		286
PAUSE		287
DUID		288

PLAYAVI	
PLAYSOUN	D
PLUGIN	
POPD	
POSTMSG	
PRINT	
PRIORITY	
PROCESSM	IONITOR
PROMPT	
PUSHD	
QUERYBOX	(
QUIT	
RD / RMDIR	
REBOOT	
RECYCLE	
REM	
REN/RENA	ME
RETURN	
REXEC	
RSHELL	
SCREEN	
SCRIPT	
SCRPUT	
SELECT	
SENDMAIL	
SERVICEMO	ONITOR
SERVICES	
SET	
SETDOS	
SETLOCAL	
SHIFT	
SHORTCUT	
SHRALIAS	
SMPP	
SNMP	
SNPP	
START	
SWITCH	
SYNC	
TAIL	
	OG
TASKEND	
TASKLIST	
-	

14

. O. ILILIK "		
TCTOOLBAR		
TEE		
TEXT		
TIME		
TIMER		
TITLE		
TOUCH		
TRANSIENT		
TREE		
TRUENAME		
TYPE		
UNALIAS		
UNFUNCTION	l	
UNSET		
USBMONITOR	R	
VER		
VERIFY		
VOL		
VSCRPUT		
WHICH		
WINDOW		
WMIQUERY		
Υ		
riables & Func	tions	3
System Varial	bles	
-	bles	
CDPATH		
CDPATH CMDLINE	ļ	
CDPATH CMDLINE COLORD	E	
CDPATH CMDLINE COLORD COMSPE	 E	
CDPATH CMDLINE COLORD COMSPE	E	
CDPATH CMDLINE COLORD COMSPE FILECON HISTORY		
CDPATH CMDLINE COLORD COMSPE FILECOM HISTORY	DIR	
CDPATH CMDLINE COLORD COMSPE FILECON HISTORY PATH	E	
CDPATH CMDLINE COLORD COMSPE FILECOM HISTORY PATH PATHEX	E	
CDPATH CMDLINE COLORD COMSPE FILECON HISTORY PATH PATHEX PROMPT RECYCL	E	
CDPATH CMDLINE COLORD COMSPE FILECOM HISTORY PATH PATHEX PROMPT RECYCL TEMP	E	
CDPATH CMDLINE COLORD COMSPE FILECON HISTORY PATH PATHEX PROMPT RECYCL TEMP TCMD	E	
CDPATH CMDLINE COLORD COMSPE FILECOM HISTORY PATH PATHEX PROMPT RECYCL TEMP TCMD TCMDVE	E	
CDPATH CMDLINE COLORD COMSPE FILECON HISTORY PATH PATHEX PROMPT RECYCL TEMP TCMD TCMDVE TITLEPR	E	
CDPATH CMDLINE COLORD COMSPE FILECOM HISTORY PATH PATHEX' PROMPT RECYCL TEMP TCMD TCMDVE TITLEPR TMP	E	

D.EXE Compatibility Variables	
COPYCMD variable	
DIRCMD variable	
String substitution	
rnal Variables	
Variables by Name	
Variables by Category	
! (Variable)	
? variable	
_? variable·····	
= pseudovariable	
+ pseudovariable	
_4VER	
_ACSTATUS	
_ADMIN	
_AFSWCELL	
_ALT	
_ANSI	
_BATCH	
_BATCHLINE	
_BATCHNAME	
_BATCHTYPE	
_BATTERY	
_BATTERYLIFE	
_BATTERYPERCENT	
_BDEBUGGER	
_BG	
_BOOT	
_BUILD	
_CAPSLOCK	
_CDROMS	
_CHILDPID	
_CI	
_CMDLINE	
_CMDPROC	
_CO	
_CODEPAGE	
_COLUMN	
_COLUMNS	
_CONSOLEPIDS······	
_COUNTRY	
_CPU	

_CPUUSAGE	
_CTRL	
_CWD	
_CWDS	
_CWP	
_CWPS	
DATE	
_DATETIME	
DAY	
DETACHPID	
DISK	
DOSVER	
DOW	
DOWF	
DOWI	
DOY	
_DRIVES	
DST	
DVDS	
ECHO	
EDITMODE	
EXECSTR	
_EXIT	
EXPANSION	
_FG	
_FTPERROR	
HDRIVES	
HLOGFILE	
HOST	
_HOUR	
HWPROFILE	
IDLETICKS	
_IDOW	
_IDOWF	
JFTP	
JFTPS	
_IMONTH	
ININAME	
IP	
ISODATE	

_KBHIT	388
_LALT	388
_LASTDISK	389
_LCTRL	389
_LOGFILE	389
_LSHIFT	389
_MINUTE	389
_MONITORS	389
_MONTH	389
_MONTHF	389
_NUMLOCK	389
_OPENAFS	390
_OSBUILD	390
_PARENT	390
_PID	390
_PIPE	390
_PPID	390
_RALT	390
_RCTRL	390
_READY	390
_REGISTERED	390
_ROW	390
_ROWS	391
_RSHIFT	391
_RUBYTYPE	391
_RUBYVALUE	391
_SCROLLLOCK	391
_SECOND	391
_SELECTED	391
_SHELL	391
_SHELLS	391
_SHIFT	391
_SHORTCUT	392
_SHRALIAS	392
_STARTPATH	392
_STARTPID	392
_STDIN	392
_STDOUT	392
_STDERR	392
_STZN	392
_STZO	392
_SYSERR	392
_TCFILTER	392

_TCFOLDER	
_TCTAB	
_TIME	
_TRANSIENT	
_TZN	
_TZO	
_UNICODE	
_UTCDATE	
_UTCDATETIME	
_UTCHOUR	
_UTCISODATE	
_UTCMINUTE	
_UTCSECOND	
_UTCTIME	
_VIRTUALPC	
_VMWARE	
_VXPIXELS	
_VYPIXELS	
_WINDIR	
_WINFGWINDOW	
_WINNAME	
_WINSYSDIR	
_WINTICKS	
_WINUSER	
_WINVER	
_WINTITLE	
_WOW64	
_XPIXELS	
_YEAR	
_YPIXELS	
ERRORLEVEL	
Variable Functions	
Functions by Name·····	39
Functions by Category	40
Date Display Formats	40
@ABS	40
@AFSCELL	40
@AFSMOUNT	40
@AFSPATH	40
@AFSSYMLINK	40
@AFSVOLID	40
	40
@AGEDATE	40

@ALTNAME	408
@ASCII	409
@ASSOC	409
@ATTRIB	409
@AVERAGE	410
@CAPI	410
@CAPS	411
@CDROM	411
@CEILING	411
@CHAR	411
@CLIP4	412
@CLIPW	412
@COLOR	412
@COMMA	412
@COMPARE	413
@CONSOLE	413
@CONVERT	413
@COUNT	413
@CRC32	413
	414
	414
@DATE	414
@DAY	414
@DEC	415
	415
	415
	416
	416
	416
@DISKFREE	416
	417
	417
	417
	417
@ DOWF	418
	418
	419
	419
	419
	419
	420
	420

@EVAL	420
@EXEC	424
@EXECSTR	424
@EXETYPE	424
@EXPAND	425
@EXT	425
@FIELD	426
@FIELDS	427
@FILEAGE	427
@FILECLOSE	427
@FILEDATE	428
@FILENAME	428
@FILEOPEN	428
@FILEREAD	429
@FILEREADB	429
@FILES	430
@FILESEEK	431
@FILESEEKL	431
@FILESIZE	432
@FILETIME	432
@FILEWRITE	433
@FILEWRITEB	433
@FINDCLOSE	434
@FINDFIRST	434
@FINDNEXT	435
@FLOOR	435
@FORMAT	435
@FORMATN	436
@FORMATNC	436
@FSTYPE	436
@FTYPE	437
@FULL	437
@FUNCTION	437
@GETDIR	437
@GETFILE	438
@GETFOLDER	438
@GROUP	438
@HISTORY	439
@IDOW	439
@IDOWF	439
@IF	439
@INC	440
@INDEX	440

@INIREAD	441
@INIWRITE	441
@INODE	442
@INSERT	442
@INSTR	443
@INT	443
@IPADDRESS	443
@IPNAME	444
@ISALNUM	444
@ISALPHA	444
@ISASCII	444
@ISCNTRL	445
@ISDIGIT	445
@ISPRINT	445
@ISPROC	445
@ISPUNCT	445
@ISSPACE	446
@ISXDIGIT	446
@JUNCTION	446
@LABEL	446
@LCS	446
@LEFT	446
@LEN	447
@LFN	447
@LINE	447
@LINES	448
@LINKS	448
@LOWER	448
@LTRIM	448
@MAKEAGE	449
@MAKEDATE	449
@MAKETIME	449
@MAX	450
@MD5	450
@MIN	450
@MONTH	450
@NAME	451
@NUMERIC	451
@OPTION	452
@PATH	452
@OWNER	452
@PERL	452
@PING	453

@QUOTE	453
@RANDOM	453
@READSCR	453
@READY	453
@REGCREATE	454
@REGDELKEY	454
@REGEX	454
@REGEXINDEX	454
@REGEXIST	454
@REGEXSUB	455
@REGQUERY	455
@REGSET	455
@REGSETENV	455
@REGTYPE	455
@REMOTE	456
@REMOVABLE	456
@REPEAT	456
@REPLACE	456
@REVERSE	457
@REXX	457
@RIGHT	457
@RTRIM	457
@RUBY	458
@SCRIPT	458
@SEARCH	458
@SELECT	458
@SERIAL	459
@SERVER	459
@SFN	460
@SHA1	460
@SHA256	460
@SHA384	460
@SHA512	460
@SHFOLDER	461
@SIMILAR	462
@SNAPSHOT	462
@STRIP	462
@SUMMARY	462
@SUBSTR	463
@SUBST	463
@SYMLINK	463
@TIME	463
@TIMER	463

	@UNICODE	464
	@UNIQUE	
	@UNQUOTE	
	@UNQUOTES	465
	@UPPER	
	@VERINFO	
	@WATTRIB	466
	@WILD	466
	@WINAPI	
	@WINCLASS	467
	@WINEXENAME	
	@WININFO	
	@WINMEMORY	468
	@WINMETRICS	
	@WINPOS	470
	@WINSTATE	470
	@WINSYSTEM	
	@WMI	
	@WORD	
	@WORDS	
	@WORKGROUP	
	@XMLCLOSE	
	@XMLNODES	
	@XMLOPEN	
	@XMLXPATH	
	@YEAR	4/4
Part IV	Troubleshooting	474
1	Registration	474
2	Troubleshooting, Service & Support	475
	Technical Support	475
	Contacting JP Software	477
3	Supported Platforms	477
_	Help File	
	Is	
_	Frror Messages	478
5	Error Messages	
5	Reference Information	478 484
5	•	484

3	File Systems & File Name Conventions	490
	Drives & Volumes	491
	File Systems	491
	Directories & Subdirectories	492
	File Names	493
	File Attributes	
	File Time Stamps	
	NTFS File Streams	
	Regular Expression Syntax	
5	XML in Take Command	502
6	Miscellaneous Reference Information	504
	Executable Files & File Searches	504
	Windows File Associations	506
	Popup Windows	
	Windows System Errors	
7	ASCII and Key Names	510
	ASCII Tables ·····	
	Key Names	515
8	ANSI X3.64 Command Reference	516
9	Colors, Color Names & Codes	518
Part VI	Glossary	519
	Glossary - A	
1		520
1 2	Glossary - A	520 521
1 2 3	Glossary - A	520 521 522
1 2 3 4	Glossary - A	520 521 522 525
1 2 3 4 5	Glossary - A	520521522525
1 2 3 4 5 6	Glossary - A	
1 2 3 4 5 6 7	Glossary - A	
1 2 3 4 5 6 7 8	Glossary - A	
1 2 3 4 5 6 7 8	Glossary - A	
1 2 3 4 5 6 7 8 9	Glossary - A	
1 2 3 4 5 6 7 8 9 10	Glossary - A	
1 2 3 4 5 6 7 8 9 10 11	Glossary - A	
1 2 3 4 5 6 7 8 9 10 11 12 13	Glossary - A	
1 2 3 4 5 6 7 8 9 10 11 12 13 14	Glossary - A	
1 2 3 4 5 6 7 8 9 10 11 12 13 14 15	Glossary - A Glossary - B Glossary - C Glossary - D Glossary - E Glossary - F Glossary - G Glossary - H Glossary - I Glossary - J Glossary - K Glossary - K Glossary - M Glossary - M	
1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16	Glossary - A	

^ -	4		4 -
Сი	nt	en	ITS.

XX

19	Glossary - S	534
	Glossary - T	
	Glossary - U	
	Glossary - V	
	Glossary - W	
	Glossary - X	
Part VII	Copyright & Version	537
		538
	Index	538

ACKNOWLEDGEMENTS

We couldn't produce products like Take Command without the dedication and quality work of many people. A special thanks to all of you who helped make Take Command elegant, reliable, and friendly.

Copyright © 2008, JP Software Inc., All Rights Reserved. Take Command® is a registered trademark and JP Software, jpsoft.com, and all JP Software designs and logos are trademarks of JP Software Inc. Other product and company names are trademarks of their respective owners.

1 Overview



Indispensable Windows Scripting & Console Tools For 15 years & Over 250,000 Licenses

TAKE COMMAND 9.0

Welcome to our help! We have designed this help file to accompany our product *Take Command*. *Take Command* is designed for Windows XP, Windows 2003, Windows Vista, and Windows 2008. *Take Command* combines the best features of the GUI and character-mode interfaces. You can have multiple console applications open in tabbed windows, with a Windows Explorer-like interface available for those times when you need a visual look at your folders.

Take Command is composed of three elements which work closely together:

Take Command Environment - A rich development and operations environment that allows you to:

- · Create and edit command scripts
- Debug scripts
- Run multiple console applications simultaneously in tabbed windows, including our own Take Command Console (TCC), CMD.EXE, PowerShell and bash. *Take Command* will display output much faster (up to 10x!) than running the application in a console window.
- Cut and paste text
- Drag and drop files into tab windows from an Explorer-like environment, other applications, or the desktop


Take Command Console (**TCC**) - A command processor compatible with CMD.EXE (the default command processor in Windows XP / 2003 / Vista / 2008) but substantially enhanced with thousands of additional features. **TCC** provides the ability to:

- Interactively run commands, such as DIR, COPY, etc
- Interactively run batch script files, such as .CMD, .BAT or .BTM scripts
- Run batch scripts as background processes based on timed schedules or operational triggers, such as changes in the system environment

Take Command Language - A mature scripting language based on and compatible with CMD. EXE, but massively enhanced. It includes:

- 150+ internal commands
- 220+ functions
- 140+ variables
- Hundreds of additional options for CMD compatible commands
- Additional underlying capabilities, such as the ability to treat FTP and HTTP sites as if they
 were local disk drives

The following image shows how the pieces fit together. The overall environment surrounds a set of consoles, each with its own tab. Each console can run commands in the Take Command language (or other languages, such as PowerShell, if you open additional tab windows).



JP Software Inc. 8. Chestertown, MD 21620

P.O. Box 328, Chestertown, MD 21620, USA phone: (800) 595-8197 email:support@jpsoft.com web:http://jpsoft.com/

2 What's New

NEW VERSION OVERVIEW - Take Command 9.0

This new version of Take Command incorporates three of our products (Take Command, 4NT, and TCI) into a single product with a new interface. 4NT (now renamed **TCC**) can still be run separately from Take Command for those users who don't want to use the new GUI, or who need to invoke a non-interactive command processor from batch or make files.

This is a summary of the compatibility fixes and new features. For complete details, see the appropriate topics in this help file.

FEATURE LIST:

Take Command now supports multiple tabbed windows.

The maximum command line size has been increased to 65,535 characters.

The maximum single command size has been increased to 32,767 characters.

The maximum single argument size has been increased to 4,095 characters.

The maximum filename size has been increased to 4,095 characters.

The maximum number of command arguments has been increased to 4096.

Take Command now supports mouse select / copy screen regions

The commands that use /P (DIR, ALIAS, SET, etc.) will now overwrite the page prompt when they display the next line.

Added support for FTP access where the user does not have access to the root directory.

Added regular expression support to FTP / IFTP. The syntax for IFTP is:

```
"ftp:::regex"
```

FTP.CFG now supports multiple users/passwords for a single FTP site. You need to add an "alias" (enclosed in parentheses) for the ftp site following the name in the ftp.cfg file. For example:

```
jpsoft.com (jpadmin) Bob AdminPassword jpsoft.com (jppublic) anonymous Bob@jpsoft.com
```

You can then access the server as "ftp://jpadmin" or "ftp://jppublic".

Removed full-screen support in 4NT.

Directory aliases can now also be a single numeric character. For example:

```
alias 1:=c:\program files
```

Tweaked the parser a bit to better handle filenames with embedded back quotes.

If you try to reference a network disk that has become disconnected, Take Command will automatically try to reset the connection.

The password entries in the option dialogs (Email and Firewall) now display dots rather than showing the password in clear text. (It is still saved in the TCMD.INI file in clear text.)

Added support for key mapping the Alt punctuation keys `-=[]\;',./ (for example: Alt-.). Note that you cannot combine these key definitions with the Ctrl and/or Shift keys (Windows does not generate keystrokes for those key combinations).

The popup windows (history, directory history,

The default 4NT .INI file name has changed from 4NT.INI to TCMD.INI. (You can still override the name on the 4NT command line.)

Dropped the Spanish language dll (I haven't been able to find anybody to do the string translations).

Startup Options:

Added a new startup switch:

```
/I[ips]
```

/li - don't load default .INI file /lp - don't load plugins

/Is - don't execute TCSTART

.INI directives:

DirJunctions=YES|no - display symbolic links in DIR and PDIR.

DirHistFile=file - load directory history at startup & save it at shutdown.

ErrorColors - display error messages (written to STDERR) in a different color.

MSAAMenu=yes|NO - If you're using a screen reader that has problems with the new *Take Command* detachable menu, set MSAAMenu to YES.

PrevArgument=Key Keystroke to recall the last argument from the previous command line (see Command Line Editing). The default is Ctrl-P.

UpdateIni=YES|no - option to allow or disallow changes to the .INI.

CDDWinColors, PopupWinColors - have been removed (obsolete).

PopupWinBegin, PopupWinEnd - have been removed (obsolete).

ScrollUp, ScrollDown, ScrollPgUp, ScrollPgDn - have been removed (obsolete).

ListColors, ListboxBarColors, ListInverseColors, SelectColors, SelectStatBarColors - have been removed from the OPTION dialog.

SaveDirCase - has been removed. (It now always defaults to preserving the directory case.)

Command Line Editing:

The command history and directory history popup windows have a toolbar which allows you to edit, remove, or move the history entries.

(4NT) The popup windows are now GUI (like Take Command) rather than character mode.

A Ctrl-0 through Ctrl-9 will insert the matching argument from the previous command line. For example:

c:\> echo now is the time for all good men

A Ctrl-0 will insert "echo" at the current cursor position; a Ctrl-4 will insert "time", etc.

A Ctrl-P will insert the last argument from the previous command line.

New Commands:

DEFER - execute a command line after the batch file exits. The syntax is:

DEFER command

EVENTMONITOR - Monitor event logs. The syntax is:

EVENTMONITOR [/C name] [server name /S"source" /T"type" /D"description" n command]

server UNC name of the computer with the log file, or LOCAL for the local

computer

name log name

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(ancel) | 224 | /S"source" | 225 | /T"type" | 225 |

FIREWIREMONITOR - monitor FireWire connections and execute a command when a device is connected or disconnected. The syntax is:

firewiremonitor [/C name] [name CONNECTED | DISCONNECTED n command...]

/C - cancel monitoring the FireWire device. If no name is provided, cancels all FireWire monitoring.

name - device name. The device name can either be the device ID name or the "friendly" name. The name can include wildcards.

n - number of repetitions (or "FOREVER")

FOLDERMONITOR - Monitor folder and/or file creation, modification, and deletion. The syntax is:

FOLDERMONITOR [/C name] [/S name /I"file" /E"file" CREATED DELETED MODIFIED RENAMED n command]

name Folder or file name

CREATED Execute the command if the folder or file is created Execute the command if the folder or file is deleted Execute the command if the folder or file is modified Execute the command if the folder or file is renamed

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(ancel) 234 /I(include) 234 /S(ubdirectories) 232

LOADMEDIA - like EJECTMEDIA, but closes the drive door.

NETMONITOR - monitor network connections and execute a command when a network is connected or disconnected. The syntax is:

NETMONITOR [/C name] [name CONNECTED | DISCONNECTED n command...]

name - network name ("LAN" for local network, "WAN" for dialup, or (wireless) network name.

 $\slash\hspace{-0.6em}\sla$

n - number of repetitions (or "FOREVER")

PROCESSMONITOR - monitor processes and execute a command when a process is started or ended. The syntax is:

PROCESSMONITOR [/C name] [name STARTED | PAUSED | STOPPED n command...]

name - the full process pathname (may include wildcards).

/C - cancel monitoring the specified process. If no name is provided, cancels all process monitoring.

n - number of repetitions (or "FOREVER")

SERVICEMONITOR - monitor Windows services and execute a command when a service is started, paused, or stopped. The syntax is:

SERVICEMONITOR [/C name] [name STARTED | PAUSED | STOPPED n command...]

name - the service name (may include wildcards).

/C - cancel monitoring the specified service. If no name is provided, cancels all service monitoring.

n - number of repetitions (or "FOREVER")

SERVICES - display, stop, or start system services. The syntax is:

SERVICES [/P /R /S] [name ...]

The *name* is the service name, not the display name. *name* can contain wildcards.

/P(ause) after each page /R(un) the specified service(s) /S(top) the specified service(s)

TASKDIALOG - Display a Windows Vista Task Dialog (requires Vista or later). The syntax is:

TASKDIALOG [/I /S /W] buttontype "title" "instruction" [text]

buttontype One or more of OK, CANCEL, YES, NO, RETRY, CANCEL, and/or

CLOSE

title Text for the task dialog title **instruction** Text for the main instruction

text Optional additional text that appears below the main instruction, in a

smaller font

/I(nformation icon) /S(top icon) /W(arning icon)

TCFILTER - Display or set the filter for the Take Command list view. The syntax is:

TCFILTER [/C filter]

/C(lear filter)

filter New filter value (i.e., *.doc)

USBMONITOR - monitor USB connections and execute a command when a device is connected or disconnected. The syntax is:

USBMONITOR [/C name] [name CONNECTED | DISCONNECTED n command...]

- name device name. The device name can either be the device ID name or the "friendly" name. The name can include wildcards.
- /C cancel monitoring the USB device. If no name is provided, cancels all USB monitoring.
- **n** number of repetitions (or "FOREVER")

Commands:

ACTIVATE - added two new options:

DISABLE - disable the specified window (no keyboard or mouse input)

ENABLE - enable the specified window

ACTIVATE - RESTORE now supports restoring any app from the system tray.

ASSOC - now ignores remarks (lines prefixed with ":") in files read with /R.

CDD - Added several new options:

/NJ -skip junctions when indexing subdirectories.

/Sn - limit the directory recursion depth when indexing subdirectories.

/T - also change the TCMD Folders and List View directory.

/TO - only change the Take Command Folders and List View directory

COPY - added several new options:

- /LD When used with /S, if the source is a symbolic or hard link to a directory, COPY will create a copy of the link in the target directory instead of copying the subdirectory tree.
- /MD create the target directory if it doesn't exist. (Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise COPY cannot tell what you want for the directory and what you want for the filename!)
- /ND skip hidden subdirectories when used with /S
- /NJ skip junctions when used with /S

COPY - the /G (percent copied) option now also tells you the remaining time (with local, network, ftp, ftps, iftps, and tftp copies).

COPY - the /V(erify) option when combined with the /G (percent copied) option now also tells you the remaining time (with local, network, ftp, ftps, iftps, and tftp copies).

COPY - added support for connected web folder names in non-English environments. (For example, in French Windows uses "_fichiers" instead of ".files".)

DEL - added new options:

- /B if DEL can't delete the file (i.e., access denied) it will schedule it to be deleted at the next reboot.
- /ND skip hidden subdirectories when used with /S
- /NF don't display "bytes freed" summary
- /NJ skip junctions when used with /S
- DIR added option to skip junctions (/NJ) when used with /S.
- DIR added option to skip hidden subdirectories (/ND) when used with /S.
- DIR added option to display file times in UTC. The syntax is:

/T:[ACW][U]

For example to display the last write time in UTC:

dir /t:wu

- DIR added option (/NF) to suppress "bytes free" display.
- DO added option to skip junctions (/NJ) when used with /S.
- DO added option to skip hidden subdirectories (/ND) when used with /S.
- DO added an option to specify the start directory (primarily for use with /S). The syntax is:

/D"directoryname"

DO - the UNTIL DATETIME syntax now supports either YYYY-MM-DD HH:MM:SS or YYYYMMDDHHMMSS format.

FTYPE - now ignores remarks (lines prefixed with ":") in files read with /R.

IF ISFILE - supports wildcards with FTP files.

LIST - /X will now display 32 bytes per row if the screen column width is >= 144.

LIST - added a new option (/XS) to display spaces rather than periods for non-printable characters when in hex mode. You can also toggle between spaces & periods with the 'S' key while displaying a file in hex mode.

- LIST added a new option (/U) which displays a ruler on the second line of the display.
- LIST the various popup windows (search, goto, etc.) are now GUI windows rather than character mode windows.
- LOG you can now specify up to four different log names:

The command log (default name *TCCommandLog*).

The history log (default name TCHistoryLog).

The error log (default name TCErrorLog).

The "log all output" (default name TCLogAll).

(The logs can also be combined into common log names if desired with the LOG /W filename option.)

MKLINK - now copies an existing description to the link.

MKLNK - now copies an existing description to the link.

MOVE - added new options:

- /B if MOVE can't move the file (i.e., access denied) it will schedule it to be moved at the next reboot.
- /LD When used with /S, if the source is a symbolic or hard link to a directory, MOVE will create the link in the target directory instead of moving the subdirectory tree.
- /MD create the target directory if it doesn't exist. (Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise MOVE cannot tell what you want for the directory and what you want for the filename!)
- /ND skip hidden subdirectories when used with /S
- /NJ skip junctions when used with /S

MOVE - the /G (percent moved) option now also tells you the remaining time (with local, network, ftp, ftps, iftps, and tftp copies).

MOVE - the /V(erify) option when combined with the /G (percent moved) option now also tells you the remaining time (with local, network, ftp, ftps, iftp, iftps, and tftp copies).

ON - added several new tests:

ON CLOSE - invoked when the *Take Command* tab is closed.

ON LOGOFF - invoked when the user logs off.

ON SHUTDOWN - invoked when the system is shut down.

ON LBUTTON - invoked when the left mouse button is clicked.

ON MBUTTON - invoked when the middle mouse button is clicked.

ON RBUTTON - invoked when the right mouse button is clicked.

OPTION - The OPTION dialogs have been redone. With the exception of the debugging and key directives, all of the .INI directives are now configurable from OPTION.

- OSD added an option (/C) to close an existing OSD display. (Note that this will only close the most recent OSD; if you have multiple OSDs running you cannot select which one to close!)
- OSD added support for multiple lines of text.
- OSD now expands tabs (^t).
- OSD now accepts leading whitespace if the string is enclosed in single back quotes.

OSD - added an option (/V) for vertical display.

PDIR - added option to skip junctions (/NJ) when used with /S.

PDIR - added option to skip hidden subdirectories (/ND) when used with /S.

PDIR - added option to display file times in UTC. See DIR for the syntax.

PLAYSOUND - added two new options:

/M - mute

/U - unmute

PUSHD - now sets ERRORLEVEL (for compatibility with CMD.EXE).

QUERYBOX - added new option:

/POS=top,left - set the dialog position. (The default is to center the QUERYBOX dialog within the 4NT / TCMD window.)

REN - added new options:

/B - if REN can't rename the file (i.e., access denied) it will schedule it to be renamed at the next reboot.

/MD - create the target directory if it doesn't exist. (Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise REN cannot tell what you want for the directory and what you want for the filename.)

SETDOS - added new argument for /X:

/X-A - disable user-defined functions

/X+A - enable user-defined functions

SENDMAIL - added support for multiple /H (header) arguments.

START - if you specify * as the password for /RUNAS, START will prompt you to enter the password. (Useful when you don't want to put the password in a batch file.)

START - added support for alternate Windows shells when using the "start c:\directory" syntax (which normally invokes an Explorer shell starting in the specified directory).

START - added new options:

/MONITOR=n - start the process on a specific monitor (1 - n). (Note that this will only work with apps that do not try to position their window at startup.)

/TAB - start the process in a new *Take Command* tab window.

START - removed the /CM option.

SYNC - added option to skip junctions (/NJ) when used with /S.

SYNC - added option to skip hidden subdirectories (/ND) when used with /S.

SYNC - the /G (percent copied) option now also tells you the remaining time (with local, network, ftp, ftps, iftps, iftps, and tftp copies).

TASKLIST - now adds a * after the PID of the current process.

TOUCH - added UTC time option to the /D /T switches. The syntax is:

```
/D:[ACW][U]
/T:[ACW][U]
```

TREE - added option to skip junctions (/NJ) when used with /S.

UNALIAS - added option to preserve the specified aliases on a wildcard UNALIAS (i.e., "UNALIAS *" or "UNALIAS A*"). The syntax is:

unalias (aliasname1 aliasname2) *

UNFUNCTION - added option to preserve the specified variables on a wildcard UNFUNCTION. See UNALIAS for details.

UNSET - added option to preserve the specified variables on a wildcard UNSET. See UNALIAS for details.

WINDOW - removed the FS and WIN options.

WINDOW - added two new options:

DISABLE - disable the window (no keyboard or mouse input)

ENABLE - enable the window

Environment Variables:

TCMD creates two environment variables that can be queried by its child tab window processes:

TCMD - the full pathname of the Take Command executable TCMDVER - the version & build number (i.e., 9.00.39).

Internal Variables:

_ADMIN - returns 1 if the current process is running as an administrator.

_CONSOLEPIDS - returns a space-delimited list of the PIDs of all processes attached to this console.

_MONITORS - returns the number of monitors.

_PARENT - returns the name of the parent process.

_SHORTCUT - full pathname of the shortcut file that started this process (or an empty string if it wasn't started by a shortcut).

_TCFOLDER - returns the selected folder in the Folders window if in a Take Command tab window.

TCTAB - returns 1 if 4NT is in a Take Command tab window.

- _UTCTIME returns the current time in UTC.
- _UTCDATE returns the current UTC date.
- _UTCISODATE returns the current UTC date in ISO format (yyyy-mm-dd).
- _UTCDATETIME returns the current date and time in UTC.
- _UTCHOUR current UTC hour.
- _UTCMINUTE current UTC minute.
- UTCSECOND current UTC second.
- _VXPIXELS virtual screen (multiple monitor) horizontal size in pixels.
- _VYPIXELS virtual screen (multiple monitor) vertical size in pixels.

Variable Functions:

@EVAL - added large number support. The maximum number size is now 20,000 digits (10,000 digits to the left of the decimal and 10,000 decimal places). If you want to use more than the default decimal values you'll need to change your EvalMax directive or use the "=x.y" format in @EVAL. (Note that this should also

eliminate the rounding errors sometimes seen in floating point calculations in previous versions.)

- @FILEAGE will display the age in UTC if you append a "u" to the second argument.
- @FILEDATE- will display the date in UTC if you append a "u" to the second argument.
- @FILEREADB[n,length] new function to return bytes from a file as a string of numeric ASCII values.
- @FILES added a new optional argument to scan the specified directory and its subdirectories. The syntax is:

```
%@files[/S[n] ...]
```

For example, to return the number of *.EXE files in the \Windows directory and all its subdirectories:

%@files[/s \windows*.exe]

- @FILESIZE added optional range support. See the @FILE syntax for details.
- @FILESIZE added a new optional argument to scan the specified directory and its subdirectories. The syntax is:

```
%@filesize[/S[n] ...]
```

For example, to return the size of all of the *.EXE files in the \Windows directory and all its subdirectories:

%@filesize[/s \windows*.exe]

@FILETIME - will display the time in UTC if you append a "u" to the second argument.

@FILEWRITEB - if the length argument is -1, @FILEWRITEB will read the string argument as a series of ASCII values in decimal or hex to write to the file. For example:

echo %@filewriteb[%file,-1,0xe0 0xF2 0xA9]

- @FORMATNC new function; like @FORMATN, but inserts thousands separators.
- @FSTYPE added support for UNC names.
- @GETFOLDER added optional second argument to set the text displayed above the tree list. For example:

echo %@getfolder[c:\windows,Browse the Windows Directories]

- @ISPROC new function which returns 1 if the specified process ID is an active process.
- @REGTYPE returns the registry variable type.
- @REGSET now allows setting REG_MULTI_SZ.
- @SERVER return information about the specified server. The syntax is:

@server[machinename,info]

where "info" is the type of information you want. The types are:

Name - return the server name

Comment - return the server comment

Version - the OS version (major version + minor version).

Users - the number of users who can attempt to log on the server.

Disconnect - the auto-disconnect time, in minutes.

Hidden - returns 1 if the server is hidden, 0 if it is visible

UserPath - the path to user directories

Type - return the type of the server. This is a combination of the following flags (you can use the .AND. operator in IF / IFF to test individual flags):

1	A LAN Manager workstation
2	A LAN Manager server
4	Any server running with Microsoft SQL Server
8	Primary domain controller
0x10	Backup domain controller
0x20	Server running the Timesource service
0x40	Apple File Protocol server
0x80	Novell server
0x100	LAN Manager 2.x domain member
0x200	Server sharing print queue
0x400	Server running dial-in service
0x800	UNIX / Linux server
0x1000	Windows Server 2003, Windows XP, Windows 2000, or Windows NT
0x2000	Server running Windows for Workgroups

0x4000	Microsoft File and Print for NetWare
0x8000	Windows server that is not a domain controller
0x10000	Server that can run the browser service
0x20000	Server running a browser service as backup
0x40000	Server running the master browser service
0x80000	Server running the domain master browser
0x40000	Windows 95/98/Me
0x1000000	Server clusters available in the domain
0x2000000	Terminal Server
0x4000000	Cluster virtual servers available in the domain
0x40000000	Servers maintained by the browser
00000000000000000000000000000000000000	Primary domain

@SHFOLDER - returns Windows folder locations (which vary in different versions of Windows and if the user has altered the defaults). The syntax is:

@SHFOLDER[n]

Where "n" is:

- 0 Desktop
- 2 Start Menu\Programs
- 5 My Documents
- 6 <user name>\Favorites
- 7 Start Menu\Programs\Startup
- 8 <user name>\Recent
- 9 <user name>\SendTo
- 11 <user name>\Start Menu
- 13 "My Music" folder
- 14 "My Videos" folder
- 16 <user name>\Desktop
- 19 <user name>\nethood
- 20 windows\fonts
- 21 templates
- 22 All Users\Start Menu
- 23 All Users\Start Menu\Programs
- 24 All Users\Startup
- 25 All Users\Desktop
- 26 <user name>\Application Data
- 27 <user name>\PrintHood
- 28 <user name>\Local Settings\Application Data (non roaming)
- 29 non localized startup
- 30 non localized common startup
- 31 common favorites
- 32 Internet cache
- 33 cookies
- 34 history
- 35 All Users\Application Data
- 36 Windows directory
- 37 Windows system directory
- 38 Program Files
- 39 Program Files\My Pictures
- 40 USERPROFILE
- 41 X86 system directory on RISC
- 42 x86 c:\Program Files on RISC
- 43 c:\Program Files\Common
- 44 x86 Program Files\Common on RISC
- 45 All Users\Templates

- 46 All Users\Documents
- 47 All Users\Start Menu\Programs\Administrative Tools
- 48 <user name>\Start Menu\Programs\Administrative Tools
- 53 All Users\My Music
- 54 All Users\My Pictures
- 55 All Users\My Video
- 56 Resource Directory
- 59 USERPROFILE\Local Settings\Application Data\Microsoft\CD Burning
- @UNIQUE added optional second argument to specify the prefix to use for the filename (Windows will only use the first three characters).
- @XMLPATH removed and replaced with the following (more powerful) XML functions.
- @XMLCLOSE close an XML file previously opened by @XMLOPEN. The syntax is:
 - @XMLCLOSE[]
- @XMLOPEN open an XML file for use by @XMLXPATH and/or @XMLNODES. The syntax is:
 - @XMLOPEN[filename]
- @XMLNODES return the number of nodes (children) for the specified path in an XML file. The syntax is:
- @XMLOPEN[["filename"],path]

If you don't specify a filename (which *must* be in double quotes), @XMLNODES will use the XML file previously opened by @XMLOPEN.

- @XMLXPATH XML XPath query. (See the XML XPath docs for details on XPath syntax.) The syntax is:
 - @XMLXPATH[["filename"],path]

If you don't specify a filename (which *must* be in double quotes), @XMLXPATH will use the XML file previously opened by @XMLOPEN.

3 Take Command

This section provides a general description of *Take Command* and *TCC* operation.

- ▶ Starting Take Command 17
- Configuration Options 43
- ▶ The Take Command Interface 56
- Directory Navigation 71
- File Selection 77
- ▶ Executable Extensions 91
- ▶ Using Internet URLs 92
- Using FTP and HTTP Servers 93
- Input / Output Redirection 98
- OpenAFS 103
- ► The TCC Command Line 103
- Aliases & Batch Files 128
- ▶ TCC Internal Commands 144
- Variables & Functions 365

3.1 Starting Take Command

You will typically start *Take Command* from a Windows shortcut, located:

- on the desktop, or
- in the Quick Launch bar, or
- in the Programs section of the Start menu (including its Startup subdirectory).

You may also start it from the Start / Run dialog.

The installation software will optionally create both a *Take Command* folder or group (in the **Programs** section of the **Start** menu) and a desktop object (shortcut) which starts *Take Command*. Usually these are sufficient, but if you prefer, you can create multiple desktop objects or items to start *Take Command* with different startup commands or options, or to run different applications in the tab windows.

Each item or icon represents a different *Take Command* window. You can set any necessary command line parameters for *Take Command* such as a program to run in a tab window, and the name and path for the .INI file 26. See <u>Take Command Startup Options</u> 17 for more information on startup command line options.

When you configure a *Take Command* item, place the full path and name for the file in the Command Line field, and put any startup options that you want passed to *Take Command*. For example:

C:\Program Files\JPSoft\TCMD\TCMD.EXE

Working directory: C:\

You do not need to use the Change Icon button, because TCMD.EXE already contains icons.

Each Windows program has a command line which can be used to pass information to the program when it starts. The command line is entered in the Command Line field for each shortcut or each item in a Program Manager group (or each item defined under another Windows shell), and consists of the name of the program to execute, followed by any startup options.

The *Take Command* startup command line does not need to contain any information. When invoked with an empty command line, *Take Command* will configure itself from the <u>TCMD.INI file</u> [26], and then display a prompt and wait for you to type a command. However, you may add information to the startup command line [17] that will affect the way *Take Command* operates.

3.1.1 Take Command Startup Options

The *Take Command* command line includes the program name with drive and path, followed by any options. For example:

```
"c:\program files\jpsoft\tcmd9\tcmd.exe" @c:\tcmd\tcmd.ini
```

There are several *Take Command* startup options. The complete syntax for the *Take Command* startup command line is (all on one line):

```
d:\path\tcmd.exe [[/]@d:\path\inifile] [//directive=value...] [/D
    d:\path] [/N] [/T [d:\path\]program]
```

(Do not include the square brackets shown in the command line above. They are there to indicate that

the items within the brackets are optional.)

The command line must start with the full *Take Command* path and executable name (TCMD.EXE):

```
d: \mathfrak{d}:
```

The additional items below may be included on the command line:

```
@d:\path\inifile OR
/@d:\path\inifile
```

This option sets the path and name of the .INI file 26. You don't need this option if

- 1) your .INI file 26 is named *TCMD.INI*, and
- 2) it is in one of the following directories:
 - 2.1) the same directory as Take Command
 - 2.2) the %localappdata% directory

This option is most useful if you want to start the program with a specific and unique .INI file

To start *Take Command* without any .INI file 26, you can create an empty file and specify it as your .INI file 26.

To get around a Windows limitation that causes the displayed command line of a shortcut to be truncated when a parameter begins with @, you can use the alternative syntax

```
/@d:\path\inifile
```

Take Command will skip the leading forward slash.

Options:

This option tells *Take Command* to treat the text appearing between the // and the next space or tab as an initialization directive. The directive should be in the same format as a line in TCMD.INI 26, but may not contain spaces, tabs, or comments. This option may be repeated. It is a convenient way to place a few simple directives on the startup line without having to modify or create a new .INI file 26.

/D Start **Folders** and **List View** in the specified directory.

/N Don't load *TCMD.INI* (useful when trying to isolate configuration problems).

T You can specify the program to start in the first tab with the /T option:

d:\path\tcmd.exe /t d:\path\program

If there is already a *Take Command* session running, /T creates a new tab in the existing *Take Command* rather than starting a new session.

/T must be the last option on the command line (otherwise *Take Command* can't tell if additional options belong to *Take Command* or the program to start in the tab).

If you have Startup Tabs 44 defined, *Take Command* will display them

following the tab created by /T.

3.1.2 TCC (4NT) Startup Options

The command line that starts *TCC* will typically include the program name with drive and path, followed by any options. For example:

```
"c:\program files\jpsoft\tcmd9\4nt.exe" @c:\4nt\4nt.ini
```

Although the startup command line is usually very simple, you can add several options. You can do this manually in the Windows **RUN** dialog, in a Windows shortcut file (.*LNK*), at the *TCC* prompt or in a batch file (with or without using the internal <u>START</u> (33) command). Each of these methods will start a new instance of the selected command processor, which will run in a new window, except when *TCC* is started from *TCC* (either at the command prompt or within a batch file) without the <u>START</u> (33) command.

When you use a pipe [10th] in a command, either at the command prompt or in a batch file, **TCC** starts another instance of itself, using the same command line parameters (except as required for the pipe).

The complete syntax for the **TCC** startup command line is (all on one line):

Do not include the square brackets shown in the command line above. They are there to indicate that the items within the brackets are optional. Some options are available only in specific products; see below for details.

If you include any of the options below, you should use them in the order that they are described. If you do not do so, you may find that they do not operate properly.

The command line must start with the path and name of the executable program file (TCC.EXE):

```
d:\path\tcc.exe
```

The additional items below may be included on the command line:

```
d:\path
```

If included, this second copy $d: \path$ of TCC path must be identical to $d: \path$ in the command line segment above. It sets the drive and directory where the program is stored, called the COMSPEC path. This option is included for compatibility with other character mode command processors, but is not needed in normal use. TCC can find its own directory without a COMSPEC path.

```
@d:\path\inifile OR
/@d:\path\inifile
```

This option sets the path and name of the .INI file 26. You don't need this option if

- 1) your .INI file 26 is named TCMD.INI, and
- 2) it is in one of the following directories:
 - 2.1) the same directory as Take Command
 - 2.2) the %localappdata% directory

This option is most useful if you want to start the program with a specific and unique .INI file

26

To start *TCC* without any .INI file 26, you can create an empty file and specify it as your .INI file 26.

To get around a Windows limitation that causes the displayed command line of a shortcut to be truncated when a parameter begins with @, you can use the alternative syntax

```
/@d:\path\inifile
```

TCC will skip the leading slash.

```
//directive=value
```

This option tells *TCC* to treat the text appearing between the // and the next space or tab as a directive. The directive should be in the same format as a line in the .INI file 26, but may not contain spaces, tabs, or comments. This option may be repeated. It is a convenient way to place a few simple directives on the startup line without having to modify or create a new .INI file 26.

Directives on the command line override any corresponding directive in the .INI file 267.

- This option causes the output of internal commands to a pipe or redirected to a file to be in ASCII when **TCC** starts. This is the default value, and isn't necessary unless you want to override a Unicode Output of configuration option.
- **/D** Disable execution of AutoRun commands from Registry. If /D is not specified when *TCC* starts, it will look for and execute the following registry variables:

HKEY LOCAL MACHINE\Software\Microsoft\Command Processor\AutoRun

and / or

HKEY CURRENT USER\Software\Microsoft\Command Processor\AutoRun

See also the AutoRun 47 configuration option.

/H Start *TCC* in a hidden window. The window will not appear on the task bar, or in the Alt-tab list of applications.

/I Don't load the .INI file, execute TCSTART, or load plugins.

/II Don't load the .INI file.

/IP Don't load plugins.

/IS Don't execute TCSTART.

/L: Forces the use of local lists for aliases, functions directory history and command history, overriding any configuration options. This method allows you to use global lists as the default, but start a specific session with local aliases, functions and histories. See the topics ALIAS 1541, FUNCTION 2421, and Local and Global History Lists 1081 for more details. Note the required trailing colon (:)!

/LA Forces the use of local aliases.

/LD Forces the use of a local directory history.

/LF Forces the use of local functions.

/LH Forces the use of a local command history list.

/Q This option has no effect. It is included only for compatibility with *CMD.EXE*.

This option tells **TCC** that you do not want it to set up a Ctrl-C / Ctrl-Break handler. It is included for compatibility with **CMD.EXE**.

Warning: It may cause the system to operate incorrectly if you use this option without other software to handle Ctrl-C and Ctrl-Break. This option should be avoided by most users.

This option sets the foreground and background colors in the *TCC* command window. Both **b** and **f** are hexadecimal digits. **b** specifies the background color and **f** specifies the foreground color. This option is included only for compatibility with *CMD.EXE*. See the *CMD.EXE* color codes in <u>Colors, Color Names & Codes</u>

In most cases you should set default colors with the corresponding $\underline{\text{Output Colors}}$ configuration option. If you use both, the /T switch overrides the configuration options.

/U This option causes the output of internal commands to a pipe or redirected to a file to be in Unicode when **/CC** starts. The command:

OPTION 284 //UnicodeOutput=yes | no

may be used at any time to switch between Unicode and ASCII output.

N Tells TCC to handle the CMD.EXE syntax !varname! as a delayed expansion of %varname. Since CMD.EXE, unlike TCC, doesn't support delayed expansion of variable references in the %varname% format, it introduced a special !varname! notation. Using IV simply tells TCC to handle that syntax as an alternative to %varname% or %varname or %[varname].

This option forces *TCC* to alter the operation of the MD [27th] (MKDIR [27th]) command to automatically create all necessary intermediate directories when it creates a new subdirectory. Its effect is the same as adding a /S option to all MD [27th] (MKDIR [27th]) commands. This option is included for compatibility with *CMD.EXE*, where it also enables other options. However, in *TCC* those options are already enabled by default.

IC command or IK command or command

Only one of these options may be used to specify for *TCC* what it must do after startup, and what it should do after completing *command*. *Command* will be executed after the automatic *TCC* startup program <u>TCSTART</u> but before a prompt is displayed. *Command* may be any valid alias, internal or external command, or batch file, including parameters.

All other startup options must be placed before **command**, because **TCC** will treat characters after **command** as parameters for **command** and not as additional startup options.

If **command** is preceded by **/C**, **TCC** will execute **command** and then exit, returning to the parent program or the desktop without displaying a prompt.

The **/K** switch has no effect. Using it is the same as placing **command** (with neither **/C** nor **/K**) at the end of the startup command line. It is included only for compatibility with **CMD.EXE**.

Example 1

Assume that C: is the boot drive, and you execute the command line below:

```
c:\4NT\4NT.exe c:\4NT\start.btm
```

The events below will take place in the order shown:

- 1 Windows starts c:\TCC\TCC.exe
- 2 TCC initializes from

1st choice: c:\TCC\TCMD.INI

2nd choice: TCMD.INI in the %localappdata% directory.

3.1 If the initialization file was found, and it contains the directive

TCStartPath=c:\start

and one of the files

```
c:\start\tcstart.btm
c:\start\tcstart.bat
c:\start\tcstart.cmd
c:\start\tcstart.exe
c:\start\tcstart.com
```

- exists, that file is executed by *TCC*.

 3.2 If no initialization file was found in Step 2. or
 - the initialization file either does not contain the TCStartPath directive, or the value of the directive is *c:\TCC*, and a TCSTART program is found in directory *c:\TCC*, it is executed by *TCC*
- **TCC** executes c:\4NT\start.btm (or, if not found, it displays an error message).
- **TCC** displays the command prompt, unless an EXIT (227) command was executed in c:\\(\frac{4NT\\start.btm}{c}\), terminating **TCC**.

Example 2

The command line below, when executed by **TCC**, **CMD.EXE**, the RUN dialog, or a shortcut, will start **TCC**, select local aliases, execute any **TCSTART** file you have created, execute the file **PROCESS.BTM**, and exit. No prompt will be displayed by this session:

```
c:\tcmd9\tcc.exe /la /c c:\tcmd9\process.btm
```

3.1.3 TCSTART and TCEXIT

TCC Startup Programs

Each time *TCC* starts, it looks for a program named <u>TCSTART</u> ²². TCSTART is normally a batch file (.BAT, .BTM, or .CMD), but it can be any executable file. If you specify a path in the <u>TCSTART</u> / <u>TCEXIT</u> ⁴⁷ configuration option, the file must be in the specified directory. If the configuration option is not used, the *TCSTART* program, if any, in the same directory as your command processor is executed. Use of TCSTART is optional, and *TCC* will not display an error message if it cannot find the program. If you do not want to use a startup program, set the <u>TCSTART / TCEXIT</u> ⁴⁷ path to a directory which does not have one, or leave it unspecified, and make sure that no matching executable file is in *TCC*'s directory.

TCSTART is a convenient place to change the color or content of the prompt for each session, LOG

269 the start of a session, or execute other special startup or configuration commands. It is also one way to set aliases 1541, functions 2421, and environment 3651 variables. See the section below on Pipes etc. about changing directories via TCSTART.

With the exception of some <u>initialization switches</u> 19, the entire startup command line passed to *TCC* is available to *TCSTART* as <u>batch file parameters</u> 133 (%1, %2, etc.). For example, to pause if any parameters are passed, you could include this command in *TCSTART*:

```
if %# GT O pause Starting %_cmdproc with parameters [%$]
```

Pipes, Transient Sessions / Processes, and TCSTART

When you set up the *TCSTART* program, remember that it is executed every time the command processor starts, including when running a pipe for when a transient copy of *TCC* is started with the /c startup option fight. For example, suppose you enter a command line like this, which uses a pipe:

```
[c:\data] myprog | sort > out.txt
```

Normally this command would create the output file C:\DATA\OUT.TXT. However, if your **TCSTART** program changes to a different directory, the output file will be written there — not in C:\DATA. This is because **TCC** starts a second copy (instance) of itself to run the commands on the right hand side of the pipe, and that new copy executes **TCSTART** before processing the commands from the pipe.

The same thing occurs if you use a transient session (one started with the **/C** option) to run an individual command, then exit — the session will execute in the directory set by *TCSTART*, not the directory in which it was originally started (e.g., by specifying a working directory in a shortcut). For example, suppose you set up a desktop object with a command line like this, which starts a transient session:

Command: d:\tc\tcmd.exe /c list myfile.txt

Working Directory: c:\data

Normally this shortcut would LIST 264 the file *C:\DATA\MYFILE.TXT*. However, if *TCSTART* changes the default to a different directory, *TCC* will look for *MYFILE.TXT* there — not in C:\DATA.

Similarly, any changes to environment variables, aliases, or other settings in *TCSTART* will affect all copies of *TCC*, including those used for pipes and transient sessions.

You can work around these potential problems with the <u>IF</u> 253 or <u>IFF</u> 254 commands and the <u>PIPE</u> 390 and <u>TRANSIENT</u> 393 internal variables. For example, to skip all *TCSTART* processing when running in a pipe or in a transient session, you could use a command like this at the beginning of *TCSTART*:

```
if %_pipe != 0 .or. %_transient != 0 quit
```

TCC Termination Program

Whenever a *TCC* session ends, it looks for a program named <u>TCEXIT</u> [22]. *TCEXIT* is normally a batch file (.*BAT*, .*BTM*, or .*CMD*), but it can be any executable file. The location of this optional program is determined by the same rule as the location of the *TCSTART* program for the session, and is not necessary in most circumstances. However, it is a convenient place to put commands to save information from one session to another, such as a (command) history list before *TCC* exits, or to <u>LOG</u> the end of the session. You can use a termination program even if you have no startup program.

No parameters are passed to the termination program.

3.1.4 TCC Exit Codes

If you start **TCC** from another program (e.g. to run a batch file or internal command), it will return a numeric code to the other program when it exits. This code indicates whether or not the operation performed was successful, with **0** indicating success and a non-zero value indicating a failure or other numeric result.

TCC's exit code is normally the numeric exit code from the last internal or external command. However, for compatibility reasons and to avoid conflicts with external commands, only some internal commands set the exit code; others leave it unchanged from the most recent external command.

You can also use the $\frac{\text{EXIT}}{227}$ n command to explicitly set the exit code. This overrides the rules above, and sets the return code to the parameter of your $\frac{\text{EXIT}}{227}$ command.

3.2 Configuration Options

Take Command and **TCC** offer a wide range of configuration options, allowing you to customize their operation for your needs and preferences. The **Take Command** menu entry **Options / Configure Take Command** invokes the Take Command Configuration Dialog (45), and the **TCC** OPTION (284) command invokes the TCC Configuration Dialog (46).

We also discuss many ways of configuring **TCC** in other parts of the online help:

- With aliases and user-defined functions you can set default options for internal commands and create new commands (see Aliases 128) and the ALIAS 154 and FUNCTION 242 commands).
- With <u>executable extensions</u> [91] you can associate data files with the applications you use to open them.
- With the <u>FILECOMPLETION</u> 60 environment variable or the <u>Filename Completion Options</u> 60 configuration option, you can customize filename completion to match the command you are working with.
- With the <u>COLORDIR</u> (368) environment variable or the <u>Directory Colors</u> (49) configuration option you can set the colors used by the <u>DIR</u> (198) command.
- With <u>command line options</u> you can specify where *TCC* looks for its startup files and how it operates for a specific instance.

3.2.1 Initialization (.INI) Files

Part of the power of **Take Command** is its flexibility, in allowing you to alter its configuration to match your style of computing. **Take Command**'s configuration is controlled through a file of initialization information.

See Locating the .INI files 25 below to find out how *Take Command* locates its *TCMD.INI* file.

Modifying the TCMD.INI File

You can create, add to, and modify the *TCMD.INI* file with the **Configure Take Command** selection on the Options menu of the

Most of the changes you make in the configuration dialog 46 or with the OPTION 284 command take

effect immediately. A few (e.g., those associated with the startup screen size) only take effect when you start a new *Take Command* session. See the online help for each individual dialog page if you are not sure when a change will take effect.

The dialogs handle most of the configuration options. The <u>Advanced directives</u> and the <u>Key Mapping directives</u> do not have corresponding fields in the configuration dialogs, and must be entered manually.

Take Command reads its *TCMD.INI* file (see Locating the .INI file 25) when it starts, and configures itself accordingly. The .INI file is not reread when you change it manually. For manual changes to take effect, you must restart **Take Command**.

Each item that you can include in the .INI file has a default value. You only need to include entries in the file for settings that you want to change from their default values.

Using the TCMD.INI File

Some settings in the .INI file are initialized when you install **Take Command**; others are modified as you use and when you exit **Take Command**.

Locating the TCMD.INI File

- 1) When starting *Take Command* or a *Take Command Console* primary shell:
 - If there is an @d:\path\inifile option on the startup command line, Take Command will use the path and file name specified there.
 - Otherwise, the default .INI file name in the table below is used, and the search starts in the directory where the *Take Command* program file is stored. If the .INI file is not found, *Take Command* will look in the %LOCALAPPDATA% directory.

If no .INI file is found, all options are set to their default values. A new .INI file will be created, using the default location and name, as explained above.

2) When starting a TCC secondary shell:

TCC retrieves the primary shell's .INI file data, processes the [Secondary] section of the original .INI file if necessary, and then processes any @d:\path\inifile\ option on the secondary shell command line

See Command Line Options 19 for more details about the startup command line.

TCMD.INI File Sections

The *TCMD.INI* file has a number of sections. Each section is identified by the section name in square brackets on a line by itself. *Take Command* stores the user-defined options in **[TakeCommand]**; *TCC* stores its user-defined options in **[4NT]**.

The **[Primary]** and **[Secondary]** sections include directives that are used only in **TCC** primary and secondary shells, respectively. You don't need to set up these sections unless you want different directives for primary and secondary shells.

Directives in the **[Primary]** section are used for the first or primary shell. The values are passed automatically to all secondary shells, unless overridden by a directive with the same name in the **[Secondary]** section.

Directives in the [Secondary] section are used in secondary shells only, and override any

corresponding primary shell settings.

See Primary 5331 and Secondary Shells 5341 for an explanation of those terms

3.2.1.1 Directives

This topic contains general information on *Take Command* and *TCC* initialization. For information on specific directives see the separate topic for each type of directive:

- ▶ Key Mapping Directives 28
- Advanced Directives 41th

These topics list the directives, with a short description of each, and a cross reference which selects a full description of that directive. A few of the directives are simple enough that the short description is sufficient, but in most cases you should check for any additional information in the cross reference topic if you are not already familiar with the directive.

Syntax for Directives

Most lines in the .INI file consist of a one-word **directive**, an equal sign =, and a **value**. For example, in the following line, the word **History** is the directive and **2048** is the value:

```
History = 2048
```

Any spaces before or after the equal sign are ignored.

Regardless of how long a string value is, for example the list for the ColorDir directive, you must enter it all on one line. Strings cannot be continued to a second line.

Each line must be within the command line length limit 1261.

The format of the **value** part of a directive line depends on the individual directive. It may be a numeric value, a single character, a choice (like **Yes** or **No**), a color setting, a key name, a path, a filename, or a text string. The value begins with the first non-blank character after the equal sign and ends at the end of the line or the beginning of a comment.

Blank lines are ignored in the .INI file and can be used to separate groups of directives.

You can place comments in the file by beginning a line with a semicolon; You can also place comments at the end of any line except one containing a text string value. To do so, enter at least one space or tab after the value, a semicolon, and your comment, like this:

```
History = 2048 ;set history list size
```

If you try to place a comment at the end of a string value, the comment will become part of the string and will probably cause an error.

If you use the <u>configuration dialogs</u> to modify the *.INI* file, comments on lines modified from within the dialogs will not be preserved when the new lines are saved. To be sure *.INI* file comments are preserved, put them on separate lines in the file.

When **Take Command** or **TCC** detects an error while processing the .INI file, it displays an error message and prompts you before processing the remainder of the file. This allows you to note any errors before the startup process continues. The directive in error will retain its previous or default value.

If you need to test different values for an ./N/ directive without repeatedly editing the ./N/ file, use the

OPTION 2841 command or see the INIQuery 421 directive.

The <u>SETDOS</u> Command can override several of the .*INI* file directives. For example, the cursor shape used by *TCC* can be adjusted either with the CursorIns and CursorOver directives or the <u>SETDOS</u> (Section 23) /S command. The correspondence between a <u>SETDOS</u> (Section 23) option and a .*INI* directive is noted under both the individual help topic for that directive and under that option in the <u>SETDOS</u> (Section 23) help topic.

Secondary shells automatically inherit the configuration settings currently in effect in the previous shell. If values have been changed by <u>SETDOS</u> or <u>OPTION</u> since the primary shell started, the current values will be passed to the secondary shell. If the previous shell's .*INI* file had a [Secondary] section, it will then be read and processed. If not, the previous shell's settings will remain in effect.

If you want to force secondary shells to start with a specific value for a particular directive, regardless of any changes made in a previous shell, repeat the directive in the **[Secondary]** section of the *.INI* file.

Types of Directives

There are various types of directives in the .INI file. The type of a directive is shown under the individual help topic for that directive. The types are distinguished by the kind of data, if any, that must be entered after the = (equal sign):

- **Name = nnnn (1234)**: This directive takes a numeric value which replaces the "nnnn." The default value is shown in parentheses or listed below the directive's description.
- Name = c (X): This directive accepts a single character as its value. The default character is shown in parentheses. You must type in the actual character; you cannot use a key name.
- Name = CHOICE1 | Choice2 | ...: This directive must be set to one of the vertical bar separated values listed between the braces. The default value is shown in all upper case letters in the directive description, but in your file any one of the choices can be entered, using any case. (Do not enter the vertical bar.) For example, if the choices were shown as YES | no then YES is the default.
- Name = *Color*: This directive takes a color specification. See <u>Colors and Color Names</u> of the format of color names.
- ▶ Name = Key: This directive takes a key specification. See Keys and Keynames 515 for the format of key names.
- ▶ Name = Path : This directive takes a path specification, without a filename. The value should include both a drive and path (e.g., C:\TCMD\) to avoid any possible ambiguities. A trailing backslash \ at the end of the path name is accepted but not required. Any default path is described in the text.
- ▶ Name = File : This directive takes a filename. We recommend that you use a full filename including the drive letter and path to avoid any possible ambiguities. Any default filename is described in the text.
- ▶ Name = String : This directive takes a string in the format shown. The text describes the default value and any additional requirements for formatting the string correctly. No comments are allowed.
- Name: This directive accepts NO parameters and the = is unnecessary (e.g. ClearKeymap 41).

Evaluation of Directives

The directives are evaluated sequentially from top to bottom within each section processed. When a directive is processed more than once during startup, it replaces any previous value(s).

Most key mapping and advanced 4th directives are cumulative and may appear several times when several concurrent values are desired, such as when assigning several different keystrokes to the same function.

3.2.1.1.1 Key Mapping Directives

These directives allow you to change the keys used for *TCC* command line editing and other internal functions. They cannot be entered via the <u>configuration dialogs</u> (see the .INI file 26) topic for details).

They are divided into four types, depending on the context in which the keys are used. For a discussion and list of directives for each type see:

- ▶ General Input Keys 29
- Command Line Editing Keys 32
- Popup Window Keys 40
- LIST Keys 36

Using a key mapping directive allows you to assign a different or additional key to perform the function described. For example, to use function key **F3** to invoke the $\frac{\text{HELP}}{25}$ facility (normally invoked with **F1**):

```
Help = F3
```

Any directive can be used multiple times to assign multiple keys to the same function. For example:

```
ListFind = F ;F does a find in LIST
ListFind = F4 ;F4 also does a find in LIST
```

Use some care when you reassign keystrokes. If you assign a default key to a different function, it will no longer be available for its original use. For example, if you assign **F1** to the AddFile and directive (a part of filename completion), the **F1** key will no longer invoke the help system, so you will probably want to assign a different key to Help.

See Keys and Key Names [515] before using the key mapping directives.

Key assignments are processed before looking for keystroke aliases. For example, if you assign Shift-F1 to HELP and also assign Shift-F1 to a key alias, the key alias will be ignored.

Assigning a new keystroke for a function does not deassign the default keystroke for the same function. If you want to deassign one of the default keys, use the NormalKey 31, NormalEditKey 35, NormalPopupKey 40 or NormalListKey 40 directive. You must also deassign default keys before you can assign them to a different usage.

Note: if you assign the same key to two different functions, the first assignment found in the list will be used.

3.2.1.1.1.1 General Input Keys

These directives apply to all input. They are in effect whenever *TCC* requests input from the keyboard, including during command line editing and the DESCRIBE [195], ESET [222], INPUT [255], LIST [264], and SELECT [312] commands. The general input keys are:

Backspace 29	Deletes the character to the left of the cursor
BeginLine 29 ⁵	Moves the cursor to the start of the line
Copy 29 ¹	Copies highlighted text to the keyboard
Del 30 ²	Deletes the character at the cursor
DelToBeginning 30 th	Deletes from the cursor to the start of the line
DelToEnd 30 ⁵	Deletes from the cursor to the end of the line
DelWordLeft 30 ^h	Deletes the word to the left of the cursor
DelWordRight 30 ^h	Deletes the word to the right of the cursor
Down 30 ^h	Moves the cursor or scrolls the display down
EndLine 31 ^h	Moves the cursor to the end of the line
EraseLine 31	Deletes the entire line
ExecLine 31 ¹	Executes or accepts a line
Ins 31 ¹	Toggles insert / overstrike mode
Left 31 ¹	Moves the cursor or scrolls the display left
NormalKey 31 [△]	Deassigns a key
Paste 32	Pastes line from clipboard
Right 32	Moves the cursor or scrolls the display right
Up 32	Moves the cursor or scrolls the display up
WordLeft 32 ¹	Moves the cursor left one word
WordRight 32	Moves the cursor right one word

Backspace = Key

Default: Backspace

Adds **Key** to the list of keys available during command line entry to delete the character to the left of the cursor.

See other General Input Keys 29.

BeginLine = Key

Default: Home

Specifies key during command line entry as a request to move the cursor to the beginning of the line.

See other General Input Keys 29.

Copy = Key

Default: Ctrl-Y

Adds *Key* to the list of keys available during command line entry to copy the highlighted text to the clipboard.

See other General Input Keys 29.

Del = Key

Default: Del

Deletes the character at the cursor.

See other General Input Keys 29.

DelToBeginning = Key

Default: Ctrl-Home

Deletes from the cursor to the start of the line.

See other General Input Keys 29.

DelToEnd = Key

Default: Ctrl-End

Deletes from the cursor to the end of the line.

See other General Input Keys 29.

DelWordLeft = Key

Default: Ctrl-L

Deletes the word to the left of the cursor.

See other General Input Keys 29.

DelWordRight = Key

Default: Ctrl-R, Ctrl-Bksp

Deletes the word to the right of the cursor. See ClearKeyMap 41 if you need to remove the default mapping of Ctrl-Bksp to this function.

See other General Input Keys 29.

Down = Key

Default: Down

Scrolls the display down one line in LIST 264; moves the cursor down one line in SELECT 312 and in the command line history, directory history, or @SELECT 458 window.

See other General Input Keys 29.

EndLine = Key

Default: End

Moves the cursor to the end of the line.

See other General Input Keys 29.

EraseLine = Key

Default: Esc

Deletes the entire line.

See other General Input Keys 29.

ExecLine = Key

Default: Enter

Executes or accepts a line.

See other General Input Keys 29.

Ins = Key

Default: Ins

Toggles insert / overstrike mode during line editing.

See other General Input Keys 29.

Left = Key

Default: left arrow, **←**

Specifies a key, such the using the key will move the cursor left.

See other General Input Keys 29.

NormalKey = Key

Deassigns a general input key in order to disable the usual meaning of the key and/or make it available for keystroke aliases. This will make the keystroke operate as a "normal" key with no special function. For example:

NormalKey = Ctrl-End

will disable Ctrl-End, which is the standard "delete to end of line" key. Ctrl-End could then be assigned to a keystroke alias. Another key could be assigned the "delete to end of line" function with the DelToEnd of directive.

See other General Input Keys 29.

Paste = Key

Default: Ctrl-V

Paste the first line of the clipboard to the input line at the cursor position.

See other General Input Keys 29.

Right = Key

Default: Right

Moves the cursor right one character on the input line; scrolls the display right 8 columns in LIST 264; scrolls the display right 4 columns in the command line history, directory history, or @SELECT 458 window.

See other General Input Keys 29.

Up = Key

Default: Up

Scrolls the display up one line in LIST 264; moves the cursor up one line in SELECT 312 and in the command line history, directory history, or @SELECT 458 window.

See other General Input Keys 29.

WordLeft = Key

Default: Ctrl-Left

Moves the cursor left one word; scrolls the display left 40 columns in LIST 2641.

See other General Input Keys 29.

WordRight = Key

Default: Ctrl-Right

Moves the cursor right one word; scrolls the display right 40 columns in LIST 264.

See other General Input Keys 29.

3.2.1.1.1.2 Command Line Editing Keys

These directives apply only to *TCC* command line editing 104. They are only effective at the prompt. The command line editing keys are:

AddFile 33 ^h	Keeps filename completion entry and adds another
AliasExpand 33 ⁵	Expands aliases on the command line

	Allows direct entry of a keystroke
DelHistory 33 ⁵	Deletes a history list entry
DirWinOpen 34 th	Opens the directory history window
	Displays the last entry in the history list
Help 34 ¹	Invokes this help system
HelpWord 34 ^h	Invokes help for the word at the cursor
HistWinOpen 34	Opens the command history window
	Recall the last history entry
LFNToggle 35 ^A	Toggles between long and short filenames
LineToEnd 35 th	Copies a line to the end of the history, then executes it
NextFile 35	Gets the next matching filename
NextHistory 35 ⁵	Recalls the next command from the history
	Deassigns a command line editing key
	Opens the filename completion window
PrevFile 36 ⁵	Gets the previous matching filename
PrevHistory 36 th	Recalls the previous command from the history
RepeatFile 36	Repeats previous match during filename completion
SaveHistory 36 ⁵	Saves the command line without executing it
VariableExpand 36 ⁵	Expand variables on the command line

AddFile = Key

Default: F10

Adds **Key** to the list of keys available during command line entry to keep the current filename completion entry and insert the next matching filename.

See other Command Line Editing Keys 32.

AliasExpand = Key

Default: Ctrl-F

Adds *Key* to the list of keys available during command line entry to expand all aliases in the current command line without executing them.

See other Command Line Editing Keys 32.

CommandEscape = Key

Default: Alt-255

Adds **Key** to the list of keys available during command line entry to signify that the immediately subsequent keystroke is to be used literally, and not for command line editing control.

See other Command Line Editing Keys 32.

DelHistory = Key

Default: Ctrl-D

Deletes the displayed history list entry and displays the previous entry.

See other Command Line Editing Keys 32.

DirWinOpen = Key

Default: Ctrl-PgUp, F6

Opens the directory history window while at the command line.

See other Popup Window Keys 40.

EndHistory = Key

Default: Ctrl-E

Displays the last entry in the history list.

See other Command Line Editing Keys 32.

Help = Key

Default: F1

Displays the Help File 477 topic for the current command. See also: the HELP 251 command and the HelpWord 341 directive.

See other Command Line Editing Keys 32.

HelpWord = Key

Default: Ctrl-F1

Invokes the HELP [477] facility for the word at the cursor.

See other Command Line Editing Keys 32.

HistWinOpen = Key

Default: PgUp

Brings up the history window while at the command line.

See other Popup Window Keys 40.

LastHistory = Key

Default: F3

Returns the last history entry. (Mostly useless; it is for compatibility with CMD.EXE.)

See other Command Line Editing Keys 32.

LFNToggle = Key

Default: Ctrl-A

Toggles filename completion between long filename and short filename modes on LFN drives.

See other Command Line Editing Keys 32.

LineToEnd = Key

Default: Ctrl-Enter

Copies the current command line to the end of the history list, then executes it.

See other Command Line Editing Keys 32.

NextFile = *Key*

Default: F9, Tab

Gets the next matching filename during filename completion. See ClearKeyMap 41 if you need to remove the default mapping of Tab to this function.

See other Command Line Editing Keys 32.

NextHistory = Key

Default: Down

Recalls the next command from the command history.

See other Command Line Editing Keys 32.

NormalEditKey = Key

Deassigns a command line editing key in order to disable the usual meaning of the key while editing a command line, and/or make it available for keystroke aliases. This will make the keystroke operate as a "normal" key with no special function. See NormalKey [31] for an example.

PopFile = Key

Default: F7, Ctrl-Tab

Opens the filename completion window. Note that *Take Command* uses Ctrl-Tab to select windows. See ClearKeyMap 41 if you need to remove the default mapping of Ctrl-Tab to this function.

See other Command Line Editing Keys 32.

PrevArgument = Key

Default: Ctrl-P

Recall the last argument from the previous command line.

See other Command Line Editing Keys 32.

PrevFile = Key

Default: F8, Shift-Tab

Gets the previous matching filename. See <u>ClearKeyMap [41]</u> if you need to remove the default mapping of Shift-Tab to this function.

See other Command Line Editing Keys 32.

PrevHistory = Key

Default: Up

Recalls the previous command from the command history.

See other Command Line Editing Keys 32.

RepeatFile = Key

Default: F12

Repeats the previous matching filename during filename completion.

See other Command Line Editing Keys 32.

SaveHistory = Key

Default: Ctrl-K

Saves the command line in the command history list without executing it.

See other Command Line Editing Keys 32.

VariableExpand = Key

Default: Ctrl-X

Expands variables at the command prompt.

See other Command Line Editing Keys 32.

3.2.1.1.1.3 LIST Keys

These directives are effective only inside the *TCC* LIST 2641 command.

ListBack 37	Return to the previous file
ListClipboard 37	Copy the current filename tot he clipboard
ListContinue 37	Continue to the next file

	Exits the current file
ListFind 37	Prompts and searches for a string
ListFindReverse 38 ⁵	Prompts and searches backwards
ListFindRegex 38	Prompt and search for a regular expression
ListFindRegexReverse 38	Prompt and search backwards for a regular expression
ListHex 38 ⁵	Toggles between hexadecimal and character display modes
ListHighBit 38 ⁵	Toggles LIST's "strip high bit" option
ListInfo 38 ⁵	Displays information about the current file
ListNext 38 ⁵	Finds the next matching string
ListOpen 39 ⁵	Displays the "open file" dialog
ListPrevious 39 ⁵	Finds the previous matching string
ListPrint 39 ⁵	Prints the file on the default printer
ListRefresh 39 ⁵	Refresh the display
ListUnicode 39	Toggles Unicode display mode
ListWrap 39	Toggles LIST's wrap option
NormalListKey 40 th	Deassigns a LIST key

ListBack = Key

Default: B

Returns to the previous file.

See other LIST Keys 36.

ListClipboard = Key

Default: Ctrl-B

Copy the current LIST 264 filename to the clipboard

See other LIST Keys 36.

ListContinue = Key

Default: C

Go to the next file.

See other LIST Keys 36.

ListExit = Key

Default: Esc

Exits from the LIST 264 command.

See other LIST Keys 36.

ListFind = Key

Default: F

Prompts and searches for a string.

See other LIST Keys 36.

```
ListFindRegex = Key
Default:
                R
Perform a regular expression search in LIST 264).
See other LIST Keys 36.
ListBack = Key
Default:
                Ctrl-R
Perform a backwards regular expression search in LIST 264).
See other LIST Keys 36.
ListFindReverse = Key
Default: Ctrl-F
Prompts and searches backward for a string.
See other LIST Keys 36.
ListHex = Key
Default:
                 Χ
Toggles between hexadecimal and character display modes.
See other LIST Keys 36.
ListHighBit = Key
Default: H
Toggles LIST's "strip high bit" option, which can aid in displaying files from certain word processors.
See other LIST Keys 36.
ListInfo = Key
Default: |
Displays information about the current file.
See other LIST Keys 36.
ListNext = Key
Default: N
```

Finds the next matching string. See other LIST Keys 36. ListOpen = Key 0 Default: Opens the common Windows "open file" dialog to select a new file to LIST 264). See other LIST Keys 36. ListPrevious = Key Default: Ctrl-B Finds the previous matching string. See other LIST Keys 36. **ListPrint** = *Key* Default: Ρ Prints the file on the default printer. See other LIST Keys 36. ListRefresh = Key **Default:** F5 Refresh the LIST 264 display. (Useful when viewing a growing log file.) See other LIST Keys 36. ListUnicode = Key Default: U

Toggles the LIST 264 display mode between Unicode and ASCII.

ListWrap = Key

Default: W

See other LIST Keys 36.

Toggles LIST 264's wrap option on and off. The wrap option wraps text at the right margin.

See other LIST Keys 36.

NormalListKey = Key

Deassigns a <u>LIST 264</u> key in order to disable the usual meaning of the key within LIST. This will make the keystroke operate as a "normal" key with no special function. See NormalKey 31 for an example.

See other LIST Keys 36.

3.2.1.1.4 Popup Window Keys

The following directives apply to popup windows, including the command history window, the directory history window, the filename completion window, the extended directory search window, and the @SELECT 458 window.

NormalPopupKey 40 40	Deassigns a popup window key
PopupWinDel 40 th	Deletes a line from within the popup window
PopupWinEdit 40 ⁵	Moves a line from the popup window to the prompt
PopupWinEditWin 40 ⁵	Edit a line in the popup window
PopupWinExec 41 ⁵	Selects the current item and closes the popup window

NormalPopupKey = Key

Deassigns a popup window key in order to disable the usual meaning of the key within the popup window. This will make the keystroke operate as a "normal" key with no special function. See NormalKey [31] for an example.

See other Popup Window Keys 40.

PopupWinDel = Key

Default: Ctrl-D

Deletes a line from within the command history or directory history window.

See other Popup Window Keys 40.

PopupWinEdit = Key

Default: Ctrl-Enter

Moves a line from the command history or directory history window to the prompt for editing.

See other Popup Window Keys 40.

PopupWinEdit = Key

Default: Ctrl-E

Edit a line in the command history or directory history window.

See other Popup Window Keys 40.

PopupWinExec = Key

Default: Enter

Selects the current item and closes the window.

See other Popup Window Keys 40.

3.2.1.1.2 Advanced Directives

These directives are generally used for unusual circumstances, or for diagnosing problems. Most often they are not needed in normal use. They cannot be entered via the configuration dialogs 46; you must enter them manually (see the .INI file 26 for details).

ClearKeyMa	Clear default key mappings
Debug 41 ^h	Set debugging options
INIQuery 42 42	Query for each line in the .INI file
LanguageDL L 42	Set localized language DLL
UpdateINI 43	Enable / disable changes to the .INI file.

3.2.1.1.2.1 ClearKeyMap

ClearKeyMap

Clears all current key mappings 28. ClearKeyMap is a special directive which has no value or = after it. Use ClearKeyMap with caution - it deletes all of the default definitions, and also any definitions in your .INI file directives that are processed before ClearKeyMap is processed. It is useful only if you want to make available most of the keys which have default assignments for other purposes, e.g., for keystroke aliases. ClearKeyMap should appear before any other key mapping directives. You may restore default mappings to keys you want to retain using the appropriate key assignment directives, e.g., NextFile 3 = Tab.

To clear the default mappings for just a few keys, use the NormalEditKey 35, NormalKey 17, NormalListKey 40, and/or NormalPopupKey 40 directives.

See other Advanced Directives 41.

3.2.1.1.2.2 Debug

Debuq = n

Default: 2

Controls certain debugging options which can assist you in tracking down unusual problems. Use the following values for **Debug** (to enable more than one option, add the desired values together):

- Disabled.
- 1 During the startup process, display the complete command tail passed to *Take Command*, then wait for a keystroke.
- 2 (default) Include the product name with every error message displayed by *Take Command*. This may be useful if you are unsure of the origin of a particular error message.

See also: the batch file debugger 1661, a separate and unrelated facility for stepping through batch files.

See other Advanced Directives 41.

3.2.1.1.2.3 INIQuery

INIQuery = yes | NO

If set to **Yes**, a prompt will be displayed before execution of each subsequent line in the current .*INI* file . This allows you to modify certain directives when you start *Take Command* in order to test different configurations. INIQuery can be reset to **No** at any point in the file. Normally INIQuery = Yes is only used during testing of other .*INI* file directives.

The dialog displayed by *Take Command* when INIQuery = Yes gives you three options:

Yes Executes the directive

No Skips the directive

Cancel Executes the directive and all remaining directives in the [TakeCommand] section of the .//N/ file (i.e., cancels the INIQuery = Yes setting)

The **TCC** prompt generated by INIQuery = Yes is:

[contents of the line] (Y/N/O/R/E) ?

At this prompt, you may enter:

- Y Process this line and go on to the next.
- **N** Skip this line and go on to the next.
- Q Skip this line and all subsequent lines.
- R Execute this and all subsequent lines.
- **E** Prompt for a new value for this entry.

If you choose E, you can enter a new value for the directive, but not a new directive name.

See other Advanced Directives 41.

3.2.1.1.2.4 LanguageDLL

LanguageDLL = filename

Specifies the filename of the language DLL *Take Command* and *TCC* should use (English.dll, French.dll, or German.dll). *Take Command* normally uses the language dll that matches the default Windows user language, but you can override it with this directive.

(In most cases you shouldn't set this directive -- if you use a non-default language dll, you will get a mix of one language from *Take Command* and another from Windows for the system error messages.)

See other Advanced Directives 41.

3.2.1.1.2.5 MSAAMenu

MSAAMenu = yes | NO

Take Command checks to see if a screen reader is installed, and if so it sets MSAAMenu=Yes. This is to avoid problems with the **Take Command** detachable menus and some screen readers.

3.2.1.1.2.6 UpdateINI

```
UpdateINI = YES | no
```

Enable or disable changes to the .INI file. (Useful for administrators who want to prevent users from changing their configuration.)

3.2.2 Take Command Configuration Dialog

This dialog, available from the Options menu of in Take Command, contains four pages or "tabs" of options that let you change the way Take Command looks and works.

Unless you select the **Cancel** button, any changes you make will take effect immediately. If you select **Apply**, the settings will only apply for the duration of that session. If you select **Save**, the settings will be recorded in the appropriate section of the <u>TCMD.INI file</u> and will be in effect each time you start **Take Command**.

While you are using the dialog, you can move between sets of configuration options by clicking on the individual tabs. The options available in this dialog are:

```
Windows 43 Tabs 44 Advanced 45 Registration 46
```

3.2.2.1 Windows

If you are not familiar with the purpose or use of the configuration dialogs, review the main $\frac{\text{configuration dialogs}}{\text{46}}$ topic before continuing.

Take Command Window

Single Instance restricts *Take Command* to a single instance. (If you try to start another copy of *Take Command*, the previous instance will be brought to the foreground.)

Always on Top makes *Take Command* a topmost window (i.e., it will remain on top of all other non-topmost windows).

Minimize to Tray minimizes Take Command to the system tray instead of the task bar.

Startup Mode - The **Normal**, **Max**, **Min**, and **Custom** buttons select the initial state for the **Take Command** windows.

Transparency:

Transparency sets the transparency level for the *Take Command* window. The range is from 20 (nearly invisible) to 255 (completely opaque). You can define both the active transparency (when *Take Command* is the foreground window, and the inactive transparency (when *Take Command*)

is in the background).

Cursor:

The **Pointer** and **I-Beam** buttons let you select the type of cursor which **Take Command** will use in the tab windows.

3.2.2.2 Tabs

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Tabs:

Tab Size sets the maximum length of the tab label text (in characters).

Tab Icons displays the application's icon in the tab label.

Top puts the tab labels at the top of the window, and **Bottom** puts them at the bottom.

Close Tab Button defines the close button (X) on the tab labels. You must restart **Take Command** for this option to take effect.

Windows:

The **Font** button opens a standard Windows font dialog that lets you select the font, point size, and font style for *Take Command* tab windows.

Colors lets you select the default foreground and background colors for text in the *Take Command* tab windows. (These colors will be overwritten if the application in the tab window sets its own colors.)

Buffer Rows sets the number of rows in the console-mode screen buffer.

Left Alt Key sends the left Alt key to *Take Command*, so you can use it to invoke the *Take Command* menu or scroll the window. (The right Alt key will be passed to the application in the tab window.)

Right Alt Key sends the right Alt key to *Take Command*, so you can use it to invoke the *Take Command* menu or scroll the window. (The left Alt key will be passed to the application in the tab window.)

Left Ctrl Key sends the left Ctrl key to **Take Command**. (The right Ctrl key will be passed to the application in the tab window.)

Right Ctrl Key sends the right Ctrl key to *Take Command*. (The left Ctrl key will be passed to the application in the tab window.)

COMSPEC:

Set the program you want to start in new tabs. If no COMSPEC option is set, *Take Command* will run the program defined in the **COMSPEC** environment variable. If no **COMSPEC** variable is set, *Take Command* will run its default command processor (*TCC*).

Startup Tabs:

The Startup Tabs specify programs to run in each tab at startup. You can specify an optional title,

the command line, an optional startup directory, and optionally the user context where the tab should run.

3.2.2.3 Advanced

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Advanced Options:

- **Linux-style Selection :** Copy selected text automatically to the clipboard when the left mouse button is released.
- MouseWheel Support for TCC LIST: If enabled, *Take Command* will pass the mouse wheel messages to *TCC* when it detects that *TCC* is executing its internal LIST 2041 command.
- **Notify Windows Shell on File or Directory Change :** Notify the system shell when changing files or directories.
- **Show File Extensions**: If enabled, **List View** will always show file extensions even if they are disabled in the Windows Shell folder properties.
- Show Hidden Files: If enabled, the Folders and List View windows will show hidden files.
- **Single Click to Open Folders:** Single click to open an item in the **Folders** window. (This will also close any other expanded items.) If this option is not enabled, **Take Command** will open folders in the **Folders** window with a double click and will not close other expanded items.
- Update Environment on System Change: If enabled, *Take Command* will monitor the WM_SETTINGCHANGE message and if the environment is specified, update the environment from the User, Volatile, and System registry entries. The updates are done whenever *Take Command* displays a prompt (to prevent the environment from changing in the middle of a batch file).
- **Win64 File System Redirection :** If disabled, overrides the default Win64 behavior of remapping *windows\system32* calls to *windows\SysWOW64*.
- **Zone ID**: Set the NTFS Zone ID security when running executables downloaded from the Internet. (Note that CMD.EXE never checks for the Zone ID, so setting it may introduce a minor incompatibility.)
- Start Dir: The initial directory to display in the Folders / List View windows.

Regular Expression Syntax:

Sets the regular expression syntax.

Descriptions:

Enable Descriptions: Set description display for the List View window.

NTFS Descriptions: If set, *Take Command* uses the Comments field in the NTFS SummaryInformation stream for each file to hold its description, instead of the *DESCRIPT.ION* file. The advantages are that the description will always remain with the file regardless of

what program copies, moves, or renames it. The disadvantage is that you cannot attach a description to directories.

Maximum Length: Set the description length limit. The allowable range is 20 to 511 characters.

Filename : Sets the file name in which to store file descriptions. The default file name is DESCRIPT.ION.

3.2.2.4 Registration

There are no separate **trial** and **registered** versions of our products. Without registration, a trial version is fully functional for 30 days of use. After 30 days, you will be limited in the number of commands you can run in a session.

The Register tab allows you to register *Take Command*. When you purchase a new or upgrade copy of *Take Command*, you will receive an email with your name and registration key. Enter the registration information exactly as you received it in the email (preferably by cutting & pasting). Remember to save your registration key in a safe place in case you need to reinstall. If you have lost your registration key, you can request a replacement by contacting JP Software at support@jpsoft.com, or at one of the addresses listed at the start of this file.

3.2.3 TCC (4NT) Configuration Dialog

This dialog, available via the OPTION COMMAND CONTAINS several "pages" or "tabs" of options that let you change the way **TCC** looks and works.

Unless you select the **Cancel** button, any changes you make will take effect immediately. If you select **Apply**, the settings will only apply for the duration of that session. If you select **Save**, the settings will be recorded in the appropriate main section (**[4NT]**) of the TCMD.INI file and will be in effect each time you start that command processor. If you want to set configuration directives in the **[Primary]** or **[Secondary]** sections of the .INI file, you must edit the file directly instead of using the dialog. Similarly, if you modified directives that originally resided in a separate included INI file, new directives will be saved to the main .INI file but the included file itself will not be altered. It would be wise to verify that no "old" directive in included files override the changes you made into the main file.

For details about the .INI file and .INI file directives, the allowable ranges for each, and the effect of each, see Initialization (.INI) Files 4 and Directives 26.

While you are using the dialog, you can move between sets of configuration options by clicking on the individual tabs. The options available in this dialog are:

Startup 47
Windows 49
Command Line 50
Advanced 51
Internet 53
Batch Debugger 54
Updates 55
Registration 55

3.2.3.1 Startup

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Logging:

Command: Save internal and external commands (after alias and variable expansion) executed either from the command prompt or a batch file to the log file. See LOG [269] for more details.

Errors: Save error messages to the log file. If you enter a file name in the File field, that file will be used for error logging. See LOG [269] for more details.

History: Save each command executed from the command prompt exactly as it was entered (before aliases and variable expansion) to the log file. If you enter a file name in the File field, that file will be used for history logging. See LOG before more details.

TCSTART / TCEXIT:

You can set the path to your TCSTART / TCEXIT 22 files if they aren't in the same directory as **Take Command**.

Local Lists:

Local Aliases instructs TCC to use a local or (if unchecked) global alias list.

Local Functions instructs TCC to use a local or (if unchecked) global function list.

Local History instructs **TCC** to use a local or (if unchecked) global command history list.

Local Directory History instructs TCC to use a local or (if unchecked) global directory history.

Scripting:

REXX: Enable the internal REXX 142 support (Open Object REXX and Regina REXX).

Perl: Enable the internal Perl 142 (ActiveState 5.8) support.

Ruby: Enable the internal Ruby [143] (1.8 or 1.9) support.

Note: you must restart the TCC tab window for the REXX, Perl, and Ruby options to take effect.

Search for SFNs: If enabled, filename searches will search for both long filenames and short filenames. See LFN File Searches of for details.

PathExt: Determines whether *TCC* will use the PATHEXT environment variable. If disabled, the PATHEXT variable is ignored. If enabled, the PATHEXT variable will be used to determine extensions to look for when searching the PATH for an executable file. For details, see the PATHEXT variable and the PATH command. If you enable PathExt and then fail to set the PATHEXT variable, path searches will fail as there will be no extensions for which to search!

Delete to Recycle Bin: If enabled, files deleted by the DEL / ERASE (190) commands and by RD /S (301) are placed in the Windows Recycle Bin. If disabled, the files are deleted without being placed in the Recycle Bin. DEL (190) s and RD (301) s /K and /R switches allow you to override this setting for individual commands. The RecycleExclude (369) environment variable can be used to exclude

- specific files.
- Prompt on Wildcard Deletes: Enable the confirmation prompt from DEL 1907 /Q when doing a wildcard-only or directory deletion. Use caution if you disable this option, as this will allow DEL /Q to delete an entire directory without prompting for confirmation. See DEL 1907 for additional details.
- Copy Prompt on Overwrite: If enabled COPY 182 and MOVE 274 will prompt before overwriting an existing file if the command is being performed at the command prompt. (This duplicates the behavior of the current version of CMD.EXE.)
- **Default Batch Echo:** Set the default batch echo mode. If enabled, all batch file commands are echoed unless <u>ECHO [217]</u> is explicitly set off in the batch file. If disabled, no batch file commands are echoed unless <u>ECHO [217]</u> is explicitly set on. See also: <u>SETDOS /V [323]</u>.
- Protect Redirected Output Files: If enabled, standard output redirection will be prevented from overwriting an existing file, and will require that the output file already exist for append redirection. (You can override this option by adding the exclamation point to the output redirection symbol; i.e. >!.) See also: SETDOS 323 /N.
- Wait for External Apps: Determines whether *TCC* waits for an external program started from the command line to complete before redisplaying the prompt. See <u>Waiting for Applications to Finish</u> 123) for details on the effects of this option.
- **Update Titles:** *Take Command* normally changes the window titles to include the command or batch file name each time a new command is executed. If you prefer a static title bar which does not change with each command, disable this option.
- UNIX/Linux-style Paths: Enables the forward slash as a path separator in the command name (the first item on the command line). Note that setting UnixPaths to Yes does not change the switch character, it simply allows you to put forward slashes in the command name. When this option is enabled, command switches beginning with a forward slash must be preceded by a space to avoid confusion (this is a good general practice).
- **Zone ID**: Set the NTFS Zone ID security when running executables downloaded from the Internet. (Note that CMD.EXE never checks for the Zone ID, so setting it may introduce a minor incompatibility.)
- Notify Windows Shell on File or Directory Change: Notify the system shell when changing files or directories. The shell notification is done by the ASSOC 162, COPY 182, DEL 190, MD 271, MOVE 274, and RD 301 commands. Note that setting this option could introduce a slight incompatibility with CMD.EXE, which doesn't notify the system shell about anything.
- **Update Environment on System Change:** If enabled, *TCC* will monitor the WM_SETTINGCHANGE message and if the environment is specified, update the environment from the User, Volatile, and System registry entries. The updates are done whenever *TCC* displays a prompt (to prevent the environment from changing in the middle of a batch file).
- **MouseWheel Support in LIST :** Set mouse wheel support in LIST 264. Disable this option if you experience incompatibilities with other applications.
- **AutoRun**: If enabled when a *TCC* tabbed window starts, execute the AutoRun registry variables (HKEY_LOCAL_MACHINE\Software\Microsoft\Command Processor\AutoRun and/or HKEY CURRENT USER\Software\Microsoft\Command Processor\AutoRun).
- **Win64 File System Redirection :** If disabled, overrides the default Win64 behavior of remapping windows\system32 calls to windows\SysWOW64.

Show Symbolic Links : Displays the symbolic link in DIR or PDIR (Windows Vista or later only).

Cancel Batch File on Ctrl-C: Cancel batch file processing without the usual prompt when you press Control-C.

Duplicate CMD.EXE bugs : Tells the **TCC** parser to duplicate bugs in CMD.EXE. The only bug currently replicated is in the IF 2531 command.

Unicode Output: The TCC output files (such as redirected output) will be written in Unicode format.

3.2.3.2 Windows

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Command Prompt Window

(These options are only used when TCC is not running in a Take Command tab window.)

The Normal, Max, Min, and Custom buttons select the initial state for the TCC window.

The **X**, **Y**, **Width**, and **Height** fields set the initial size and position of the **TCC** window. They are ignored unless the **Custom** button is also selected.

Colors:

ANSI Colors: Enable ANSI X3.64 string processing of the output of Take Command internal commands. Note that ANSI X3.64 processing of the output of external applications is not supported. See the ANSI X3.64 Commands Reference of for a list of the ANSI X3.64 commands supported by *TCC*.

Colors: Select foreground and background colors for input, output, and error messages.

Directory Colors: Sets the directory colors used by DIR 1981 and SELECT 3121. The format is the same as that used for the COLORDIR 3681 environment variable. See Color-Coded Directories 2031 for a detailed explanation.

Pop-Up Windows:

Set the size and position of :

- The command 107 and directory 118 history search windows.
- The directory popup window used by extended directory searches 73.

The position can be either in column/row coordinates, relative to the upper left corner of the console window, or in screen coordinates relative to the upper left corner of the *Take Command* window. If the *width* is < 150, the position is assumed to be in column/row format.

Editor:

Editor : The pathname of the editing program to run from LIST 264). (The default is NOTEPAD.EXE.)

3.2.3.3 Command Line

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Command History:

Minimum Length: Set the minimum command line size to save in the command history list. Any command line whose length is less than this value will not be saved. Legal values range from 0, which saves everything, to 8192. You can prevent any command line from being saved in the history by beginning it with an "at" sign ("@"). See also the HISTORY 100 command.

Copy to end : This option controls what happens when you re-execute a line from the command history. If this option is set, the line is appended to the end of the history list. The original copy of the command is always retained at its original position in the list. If this option is set, it will override **Move to End**.

Move to end: If enabled, a recalled line will be moved to the end of the command history. The difference between this directive and Copy to end is that Copy to end copies each recalled line to the end of the history but leaves the original in place. Move to end copies the line to the end of history and removes the original line. This directive has no effect if Copy to end is set.

Wrap: If enabled, the command history "wraps" when you reach the top or bottom of the list (so the list appears "circular"). If this option is disabled, history recall will stop (and beep) at the beginning and end of the list rather than wrapping.

Duplicates: Controls duplicate entry placement in the history list 1061.

Off Always add new entries

First Add new entry only if it does not match any old entries

Last Add new entry unconditionally, and delete matching older entries

History File: Load the specified history list file before running <u>TCSTART</u> 22, and save the command history to the file after running <u>TCEXIT</u> 22.

Directory History File: Load the specified directory history list file before running TCSTART 22, and save the directory history to the file after running TCEXIT 22.

Filename Completion:

Complete hidden files: If enabled, hidden and system files and directories will be displayed by filename completion [368]. CDD /S [180] will also index hidden directories if this option is set.

Add '\' to Directories: If enabled, a \ (backslash) is automatically appended to directory names (or / to FTP directories) in filename completion [368].

Search PATH: If enabled, the directories in the PATH 286 variable are searched if a match isn't found in the current directory.

Options: Sets the files returned during filename completion set for selected commands. The format is the same as that used for the FILECOMPLETION set environment variable. See Customizing Filename Completion for a detailed explanation of selective filename completion.

Server Completion: Configures server name completion (see Filename Completion 113) for

information on how to use server name completion). **Local** lists only local servers (i.e., those in your "network neighborhood"). **Global** will enumerate the entire network. **None** will disable server completion; this may be necessary to prevent "hanging" if you start typing a server name and accidentally press Tab, and your local domain is very large or slow to respond.

Editing:

Edit Mode: Starts the command line editor in either Insert or Overstrike mode. If you specify Initial Overstrike or Initial Insert, the command line editor will start in the specified state, but if you toggle insert mode while editing a line, the editor will continue to use the new mode on subsequent lines. See also: SETDOS 323 /M.

Overstrike Cursor: The shape of the cursor for insert mode during command line editing, and all commands which accept line input (DESCRIBE, ESET, etc.). The size is a percentage of the total character cell size, between 0% and 100%. Because of the way video drivers map the cursor shape, you may not get a smooth progression in cursor shapes as Insert Cursor and Overstrike Cursor change. If you set Insert Cursor and Overstrike Cursor to -1, the cursor shape won't be modified at all. If you set them to 0, the cursor will be invisible. See also: SETDOS /S 323).

Insert Cursor: The shape of the cursor for overstrike mode during command line editing and all commands which accept line input. The size is a percentage of the total character cell size, between 0% and 100%. See also: Overstrike Cursor (above) and SETDOS 323 /S.

Extended Directory Search:

Search Level : Configure extended directory searches. **0** disables extended searches. For complete details on the meaning of the other settings see Extended Directory Searches [73].

Path: The path to JPSTREE.IDX, the file used for the extended directory search 3 database.

History Buffer Sizes

Command History: Set the amount of memory allocated to the command history list (in characters). The allowable range of values is from 4000 to 131071. If you use a global history list list list, this value is ignored in all sessions except that which first establishes the global list. (To change the size, you will need to close all of the *TCC* windows, and any SHRALIAS session.)

Directory History: Set the amount of memory allocated to the directory history history list (in characters). The allowable range is 1,024 to 32767. If you use a global directory history list, this value is ignored in all sessions except that which first establishes the global list. (To change the size, you will need to close all of the *TCC* windows, and SHRALIAS 329 session.)

3.2.3.4 Advanced

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Special Characters:

Separator: The character used to separate multiple commands on the same line. The default is an ampersand (&). It can be dynamically modified by the /C option of the <u>SETDOS</u> (323) command. You cannot use any of the <u>redirection</u> (982) characters (| > <) or any of the white space characters (space, tab, comma, or equal sign).

Escape: The character used to suppress the normal meaning of the following character. The default is a caret (^). See Escape Character for a description of the special escape sequences. You cannot use any of the redirection characters (|, >, or <) or the white space characters (space, tab, comma, or equal sign) as the escape character. See also: SETDOS 323) /E.

Parameter: The character used after a percent sign to specify all or all remaining command line parameters in a batch file or alias (e.g., %\$ or %n\$; see Batch File Parameters and ALIAS 154). The default is the dollar sign [\$]. See also: SETDOS 323 /P.

Switch: The character used to delineate options. The default is a forward slash (/). Note that this will only affect internal commands, not any external applications, and will probably break all of your existing batch files and aliases!

Localization:

Time: The format of time displays in the output of the DATE [188], DIR [198], SELECT [312], TIME [347] and TIMER [347] commands, and in LOG [269] files. It has no effect on %_TIME [393], %@MAKETIME [449], the \$t and \$T options of PROMPT [297], or date and time ranges [80].

Country am/pm CountryFormats the time according to the country code set for your system.
Displays the time in 12-hour format with a trailing "a" for AM or "p" for PM.
Display **the time** in 24-hour time format.

Decimal: Sets the character used as the decimal separator for @EVAL 420, numeric IF 253 and IFF 254 tests, version numbers, and other similar uses. The only valid settings are period [.], comma [,], and Auto (the default). A setting of Auto tells *TCC* to use the decimal separator associated with your current country code. If you change the decimal character you will need to adjust the thousands character so that the two characters are different. See also: SETDOS /G 323.

Thousands: Sets the character used as the thousands separator for numeric output. The only valid settings are period [.], comma [,], and **Auto** (the default). **Auto** tells **TCC** to use the thousands separator associated with your current country code. If you change the thousands character you will need to adjust the decimal character so that the two characters are different. See also: SETDOS /G 323].

Default Beep:

Length: The default BEEP 173 length in system clock ticks (approximately 1/18 of a second per tick). Also the default length for "error" beeps (for example, if you press an illegal key).

Frequency: The default frequency (in Hz) for the BEEP [773] command. This is also the frequency for "error" beeps (for example, if you press an illegal key). To disable all error beeps set this to 0. If you do, the BEEP [173] command will still be operable, but will not produce sound unless you explicitly specify the frequency and duration.

Tabs:

Tabs: Sets the tab stops for LIST 264 output. The allowable range is 1 to 32.

Descriptions:

Enable Descriptions: Set description handling for the file processing commands (COPY, DEL, MOVE, REN, etc.). If disabled, *TCC* will not update the description file when files are moved, copied, deleted or renamed. See also: SETDOS 323 /D.

NTFS Descriptions: If set, *TCC* uses the Comments field in the NTFS SummaryInformation stream for each file to hold its description, instead of the *DESCRIPT.ION* file. The advantages are that the description will always remain with the file regardless of what program copies, moves, or renames it. The disadvantage is that you cannot attach a description to directories.

Maximum Length : Set the description length limit for DESCRIBE 195. The allowable range is 20 to 511 characters.

Filename: Sets the file name in which to store file descriptions. The default file name is DESCRIPT.ION. See also: SETDOS 323 /D.

@EVAL Precision

Minimum: The minimum number of digits after the decimal point in values displayed by @EVAL
420). The allowable range is 0 to 1000. This directive will be ignored if Minimum is larger than Maximum. You can override this setting with the construct @EVAL[expression=n,n]. See also: SETDOS 323) /F.

Maximum: The maximum number of digits after the decimal point in values displayed by <u>@EVAL</u> 420. You can override this setting with the construct @EVAL[expression=n,n]. The allowable range is 0 to 1000; if you use the "=n,n" syntax the maximum is 10,000. See also: <u>SETDOS</u> 323 /F.

Regular Expression Syntax

Sets the type of regular expression syntax to use.

3.2.3.5 Internet

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

SMTP:

Server: The SMTP server name to use in <u>SENDMAIL</u> [316] for outgoing mail. (If not set, SENDMAIL will attempt to get the address from the registry.)

Address: The email address to use in <u>SENDMAIL and for outgoing mail</u>. (If not set, SENDMAIL will attempt to get the current user's email address from the registry.)

User: The email username (if your SMTP server requires it for authentication).

Password: The email password of the user (if your SMTP server requires it for authentication).

Port: The SMTP port number for use by SENDMAIL 316). (The default port number is 25).

Firewall:

Type: The type of firewall in use on your network.

Host: The server name of the firewall (if any) for FTP and HTTP access.

User: The user name if the firewall requires authentication.

Password : The password if the firewall requires authentication.

RSHELL / REXEC:

Host: The name of the local host or user-assigned IP interface through which connections are initiated or accepted (for REXEC 308) and RSHELL 309).

User: The name of the user on the local machine (for RSHELL 309).

Port: The port number (or communication endpoint) in the local machine to bind to for REXEC and RSHELL and RSH

JABBER:

Server is the JABBER 260 server to log into.

User : The default user name for logging onto a Jabber server and sending IM's via the <u>JABBER</u> command.

Password: The logon password for the default Jabber user.

Time Server:

Time Server: The URL for the internet time server for TIME /S 347. If no server is specified, TIME uses clock.psu.edu.

HTTP Proxy:

Server: The proxy server address to use for HTTP calls

User: The user name if Basic authentication is to be used for the HTTP proxy.

Password: The user password if Basic authentication is to be used for the HTTP proxy.

Port: The proxy port number to use for HTTP calls.

FTP:

Passive FTP: Set passive mode for FTP calls (sometimes required by a firewall).

FTP.CFG: Specify the location and name of the file containing the FTP user names and passwords, and optionally the directory format for non-standard FTP servers. The default is FTP.CFG in the *Take Command* installation directory. See <u>Using FTP/HTTP Servers</u> of the details.

Timeouts:

Set the timeout (inactivity) period in seconds for FTP, TFTP, and HTTP operations.

3.2.3.6 Debugger

If you are not familiar with the purpose or use of the configuration dialogs, review the main configuration dialogs 46 topic before continuing.

Transparency: Set the default transparency level of the <u>debugger reserved</u> windows (40 to 255). 40 is almost invisible; 255 is opaque (no transparency). You can also set the debugger window transparency with the slider control on the bottom left of the debugger window.

Extensions: Set the batch file extensions supported by the <u>debugger left</u>. If you don't specify an extension when creating a new file, the debugger will use the first extension in the list. Extensions must be separated by a semicolon. This option will take effect the next time a debugger window is opened.

Auto Bracket Match: Enable on bracket matching - (), [], and {}. This option will take effect the next time a debugger bind window is opened.

Syntax Coloring: Display key words (as defined in *BATCH.BCP*) in color.

Auto Indent: Automatically indent new lines to match the previous line. This option will take effect the next time a debugger bild window is opened.

Smart Indent: Increase the indent for new lines if the command on the previous line matches one in the smart indent list in *BATCH.BCP*. This option will take effect the next time a <u>debugger</u> window is opened.

Case Fixing: Automatically change the case of key words to match that in *BATCH.BCP*. (Syntax Coloring must also be enabled so that Case Fixing can recognize the keywords.) This option will take effect the next time a debugger window is opened.

Show Line Numbers: Display line numbers before each line. This option will take effect the next time a <u>debugger</u> window is opened.

Backup Files : Save a backup copy of the file when you do a Save. The file will be saved with a *.BAK* extension. The option will take effect the next time a debugger sign window is opened.

Font: Display a font dialog to select the font style and size to use in the <u>debugger</u> 166 windows.

Foreground RGB: Display a color picker dialog to select the foreground text color for debugger windows.

Background RGB: Display a color picker dialog to select the background text color for debugger windows.

3.2.3.7 **Updates**

The **Check for Updates** button queries the JP Software web server to see if there is an updated version of **Take Command** available. If there is, the new version information will be displayed and you can choose to download and automatically update your existing version.

3.2.3.8 Registration

There are no separate **trial** and **registered** versions of our products. Without registration, a trial version is fully functional for 30 days of use. After 30 days, you will be limited in the number of commands you can run in a session.

The Register tab allows you to register *Take Command*. When you purchase a new or upgrade copy of *Take Command*, you will receive an email with your name and registration key. Enter the registration information exactly as you received it in the email (preferably by cutting & pasting). Remember to save your registration key in a safe place in case you need to reinstall. If you have lost your registration key, you can request a replacement by contacting JP Software at support@jpsoft.com, or at one of the addresses listed at the start of this file.

3.3 The Take Command Interface

The Take Command Window

- ▶ The Take Command Window 56 1
- Menus 58
- Tool Bars 62
- Folders 63
- List View 63
- Tab Windows 64
- Status Bar 64 64
- Keyboard Shortcuts 64
- Context Menus 65
- ▶ Using the Scrollback Buffer 66
- ▶ Highlighting and Copying Text
- ▶ Take Command Dialogs 68

Starting Applications


▶ Starting Windows Applications 122

Take Command and the Windows Environment

- ▶ Resizing the Take Command Window 68 1
- ▶ Drag and Drop 681

3.3.1 The Take Command Window

The **Take Command** window has eight parts:



- 1. The **Title Bar** is the same as the one used in most Windows applications, with a control menu button on the left and the minimize, maximize, and close buttons on the right. You can also adjust the size of the **Take Command** window using standard window techniques, but see Resizing the Take Command Window about how **Take Command**'s display changes when you do so.
- 2. See <u>Take Command Menus</u> 58 for details about the **Menu Bar** and all of its menus.
- 3. The **Toolbar** is used to execute internal or external commands, aliases, batch files, and applications with the click of a mouse. You can define up to 32 Tool Bar buttons; see <u>Tool Bar Dialog 69</u> for instructions. You can customize and show or hide the Tool Bar with a choice on the Options Menu 61.
- 4. The Tab Toolbar is an optional tool bar that you can use to execute internal or external commands, aliases, or batch files with the click of a mouse (or an accelerator key). You can define up to 50 tab toolbar buttons. To create buttons for the tab toolbar, select Configure Tab Toolbar from the Options of menu. This selection displays the tool bar dialog of can also configure the tab toolbar from TCC with the TCTOOLBAR (343) command.
- **5.** The **Folders** window shows a tree view of your desktop.
- **6.** The **List View** window shows the contents of the item selected in the **Folders** window. You can display the **List View** window in a number of ways (Large Icons, Small Icons, List, and Details views).

- 7. The Tab Windows run the Take Command Console, or any other Windows console application (including CMD, PowerShell, or bash). You can use the scroll bars or the Alt cursor keys to view text that has scrolled through the window. You can also save the contents of a tab window and scrollback buffer to a file, copy text from a tab Window to the clipboard, and copy text from the clipboard or from the tab window scrollback buffer to the command line. See Highlighting and Copying Text [67] for information about saving and retrieving text in the tab window and The Command Line 103 for complete details about using the Take Command console command line.
- **8.** Finally, the **Status Bar** at the bottom of the **Take Command** window displays information about your system:
 - ▶ Tooltips for the menu selections
 - ▶ The tab window size (columns x rows)
 - ▶ The CPU usage (0 100%)
 - ▶ The memory load (0-100%)
 - ▶ The state of the Caps Lock key
 - ▶ The state of the Num Lock key
 - ▶ The state of the Scroll Lock key
 - ▶ The current date
 - ▶ The current time
 - ▶ A slider control to change the *Take Command* transparency

If you find the "I-Beam" cursor in the *Take Command* tab windows difficult to see, change it in the Tabs 4 page of the configuration dialog to force the use of an arrow cursor in all parts of the window.

3.3.1.1 Menus

Like most Windows applications, *Take Command* displays a menu bar along the top of the *Take Command* window. To select a particular menu item, click once on the menu heading, or use *Alt-x* where *x* is the underlined letter on the menu bar (for example, *Alt-F* displays the *File* menu). You can also select a menu by pressing *Alt* or *F10* and then moving the highlight with the cursor keys.

The *Take Command* menu bar is movable, dockable, and customizable. To move or dock the menu, move the mouse cursor over the grabber bar on the left side of the menu, press the left mouse button, and drag the menu to its new position. To customize the menu, click on **View / Toolbars and Menus / Customize.**

The menu bar entries allow you to select a variety of *Take Command* features:

File 58
Edit 59
Tabs 60
View 60
Options 61
Window 61
Help 61

3.3.1.1.1 File

The File menu allows you to create new tabs, save or print the screen buffer, or exit *Take Command*.

New Tab

Opens the default *Take Command Console* command processor in a new tab window. (If you want to run a different application in a new tab, use the Run menu entry in the Tabs 60 menu.)

Save to File...

Saves the contents of the current tab window's scrollback buffer to a file. A Save As dialog box appears in which you can enter the name of the file that you wish to use.

Print...

Sends the contents of the current tab window's scrollback buffer to the printer. A Print dialog box appears in which you can choose the portion of the screen buffer you wish to print.

Setup Printer...

Displays a standard printer setup dialog box. The options available in the dialog box depend on the printer driver(s) you are using.

Refresh

Redraws everything in the current *Take Command* window (use this selection if the display appears incorrect).

Exit

Ends the current Take Command session.

3.3.1.1.2 Edit

The Edit menu allows you to copy text between the *Take Command* windows and the Windows clipboard. You can also access the clipboard in *TCC* with redirection story to or from the CLIP: device, or with the @CLIP [412] variable function.

To use the Cut, Copy, or Delete commands, you must first select a block of text with the mouse, the keyboard, or with the Select All command, below. If you hold down the right mouse button while you select a block of text, that block will be copied to the clipboard automatically when you release the button.

For more information on copying text see Highlighting and Copying Text 67.

Copy

Copies selected text from the command line or scrollback buffer to the clipboard.

Paste

Copies text from the clipboard to the command line. If the text you insert contains a line feed or carriage return, the command line will be executed just as if you had pressed Enter. If you insert multiple lines, each line will be treated like a command typed at the prompt.

Copy + Paste

Copies the selected text from the scrollback buffer directly to the command line.

Copy + Paste + Run

Copies the selected text from the scrollback buffer directly to the command line and executes the resulting command line.

Paste + Run

Copies text from the clipboard to the command line and executes the resulting command line.

Select All

Marks the entire contents of the scrollback buffer as selected text.

Find

Search the scrollback buffer for a string

Console Mouse

Send mouse moves and clicks to the console window. This option is specific to each tab, and is rarely necessary because few console apps use the mouse. You can also toggle this option with **Ctrl-M** in the tab window.

3.3.1.1.3 Tabs

New Tab

Opens the default command processor in a new tab window. *Take Command* defaults to the program specified in your COMSPEC environment variable; if that isn't found then *Take Command* will start **TCC.EXE**.

Run

Displays the <u>run dialog box sell</u> from which you can run an application or batch file. **Take Command** remembers the commands you have run from this dialog in the current session. To select from this list click on the drop-down arrow to the right of the "Command Line" field, or press the down-arrow.

Attach Tabs

Displays a popup dialog of all of the console sessions that are **not** already displayed in a **Take Command** tab window, and allows you to select one or more to convert to a **Take Command** tab. You can select multiple sessions by clicking on individual entries and then on **OK**, or you can select a single session by double clicking on the entry.

Detach Tab

Disconnects the current tab window from *Take Command* and displays it on the desktop.

Rename Tab

Rename the current tab text (and the console title). If you set the title with this option, *Take*Command will not change the tab title if the application subsequently changes the console title. If you set the title to an empty string, the title will revert to that set by the console application.)

Close Tab

Closes the current tab window.

3.3.1.1.4 View

Toolbars and Menus

Customize the Take Command toolbars and menus.

Folder and List Views

Show or hide the **Folders** and **List View** windows. If you want to have more room for your tab windows, you can set the **Folders** and **List View** windows to AutoHide (i.e., they will be collapsed to a single tab label when not in use). If you don't want the view windows to appear at all, you can toggle them off with this option.

Status Bar

Show or hide the status bar.

Toggle Tabs Top/Bottom

Move the tab labels to the top or bottom of the tab window.

Large Icons

Display items in the List View using large icons.

List

Display items in the List View as a list.

Details

Display directory entries in the List View with a DIR-style display (Name, Size, Date/Time, Attributes, Type, and Description).

Set Filter

You can enter an expression to use to filter the directory entries displayed in the List View.

3.3.1.1.5 Options

Configure Take Command

Opens a dialog 46 which you can use to change the *Take Command* configuration.

Configure Tab Toolbar

Opens a dialog 69 in which you can define up to 50 buttons for the **Take Command** tab window tool bar 62.

Skins

Opens the Skins and Themes dialog to select a custom skin. *Take Command* uses the standard Windows MSSTYLES format; thousands of skins are freely available on the Internet. You will need to copy your downloaded skin(s) to the **Styles** subdirectory in the *Take Command* installation directory.

Theme

Select a predefined theme for *Take Command*. This will change the color and appearance of the *Take Command* window and its components (such as the tab window labels).

3.3.1.1.6 Window

Toggle View Windows

Minimize or restore the Folder and List View windows.

New Horizontal Tab Group

Create a new tab bar by splitting the tabs window horizontally, and move the current tab window to the new tab bar.

New Vertical Tab Group

Create a new tab bar by splitting the tabs window vertically, and move the current tab window to the new tab bar.

This menu will also display the names of all of the tabs, and allow you to switch to a new tab by selecting it in the menu.

3.3.1.1.7 Help

See also: the Help File 477 topic.

Contents

Displays the **Table of Contents** of the **Take Command** help file, from which you can directly navigate to any topic. This is the same display you will see if you select the **Contents** tab from within the help system.

Search Topics

Displays the **Search dialog** of the **Take Command** help file, from which you can search for any topic. This is the same dialog you will see if you select the **Search** tab from within the help system.

Index

Displays the **Index dialog** of the **Take Command** help file, from which you can search for any keyword. This is the same dialog you will see if you select the **Index** tab from within the help system.

http://jpsoft.com/

A hyperlink to the JP Software web site. Clicking it will attempt to display the JP Software home page in your default browser. Depending on your configuration, you may need to first establish an Internet connection.

Check for Updates

Query the JP Software web server to see if there is an updated version of **Take Command** available. If there is, the new version information will be displayed and you can choose to download and automatically update your existing version.

Order from JP Software

A hyperlink to our secure online store. Clicking it will attempt to display the store's first page in your default browser. Depending on your configuration, you may need to first establish an Internet connection.

Send Feedback to JP Software

Email us with suggestions or bug reports.

About Take Command

Displays the *Take Command* version, copyright, and license information.

3.3.1.2 Tool Bars

The *Take Command* window has two toolbars: the **Explorer toolbar** and the **Tab toolbar**.

You can hide or show the toolbars with the **View / Toolbars** menu entry, and you can detach and dock a toolbar by clicking on the left edge of the toolbar and dragging it to its new position. The new position of the toolbar will be saved when you close **Take Command** and restored when you restart.

Explorer Toolbar

The Explorer Toolbar has five default controls:

- The **Find** combo box searched for text in the current tab window's buffer.
- The Views button toggles the view type in the List View window between Large Icons, List, and Details). You can also select the view type from a drop-down list by clicking on the down arrow.
- The Select Folder combo box changes the current directory for the Folders and List View windows.
- The Up button changes to the parent directory in the Folders and List View windows.
- The **Filter** combo box allows you to enter <u>wildcards</u> or <u>regular expressions</u> to filter the directories and files displayed in the **List View** window. You can enter multiple wildcards by enclosing each argument in double guotes and separating them with a comma. For example:

```
"*.cmd", "*.txt", "*.doc"
```

To enter a regular expression in the **Filter** combo box, precede it with two colons. For example:

::/c

You can also set the filter from *TCC* with the TCFILTER [343] command.

You can customize the Explorer Toolbar by clicking on the button on the right edge and selecting **Add or Remove Buttons**, or by right-clicking on the blank space to the right of the toolbar and selecting **Customize**.

Tab Toolbar

The Tab Toolbar is an optional tool bar that you can use to execute internal or external commands, aliases, or batch files with the click of a mouse (or an accelerator key). You can define up to 50 tab toolbar buttons.

To create buttons for the tab toolbar, select **Configure Tab Toolbar** from the Options of menu. This selection displays the tool bar dialog of Nou can also configure the tab toolbar from *TCC* with the TCTOOLBAR of Nounand.

3.3.1.3 Folders

The **Folders** window displays a tree view of the folders on your system. You can optionally select the folder by entering the name in the combo box on the Explorer Toolbar 62.

You can detach, move and dock the **Folders** window by moving the mouse cursor to the upper left corner, left-clicking on the grabber bar, and holding the left mouse button down while dragging the window to its new location.

You can AutoHide the **Folders** window by clicking on the "push-pin" in the upper right corner, or selecting it from the drop-down menu. When in AutoHide, the window will be minimized to a single tab, and will automatically expand again when you move the mouse cursor over the tab.

You can hide the **Folders** and **List View** windows completely by toggling the **View / Folder and List Views** menu entry.

3.3.1.4 List View

The **List View** window displays the contents of the directory selected in the **Folders** window. You can choose the format (Large Icons, List, or Details) with the Views button on the Explorer Toolbar 62.

You can optionally filter the contents of the **List View** window by entering a regular expression in the Filter combo box on the Explorer Toolbar (62). You can also set the filter from **TCC** with the TCFILTER 343 command.

You can detach, move and dock the **List View** window by moving the mouse cursor to the upper left corner, left-clicking on the grabber bar, and holding the left mouse button down while dragging the window to its new location.

You can AutoHide the **List View** window by clicking on the "push-pin" in the upper right corner, or selecting it from the drop-down menu. When in AutoHide, the window will be minimized to a single tab, and will automatically expand again when you move the mouse cursor over the tab.

You can hide the **Folders** and **List View** windows completely by toggling the **View / Folder and List Views** menu entry.

3.3.1.5 Tab Windows

The **Take Command** tab windows allow you to run multiple console applications in their own tab inside a single **Take Command** session.

Although you can run any character-mode application in a tab window, the most common usage will be command processors or utilities. *Take Command* includes its own console-mode command processor (*TCC*, formerly known as *4NT*), but you can run any other command processor, including *CMD*, **PowerShell**, **bash**, etc. in a tab window.

You can use the scroll bars or the **Alt** cursor keys to view text that has scrolled through the window. You can also save the contents of a tab window and scrollback buffer to a file, copy text from a tab Window to the clipboard, and copy text from the clipboard or from the tab window scrollback buffer to the command line. See <u>Highlighting and Copying Text</u> or information about saving and retrieving text in the tab window and <u>The Command Line</u> of for complete details about using the **Take Command** console command line.

You cannot run a GUI application in a tab window.

3.3.1.6 Status Bar

The *Take Command* window has a Status Bar that displays tooltips when you move the cursor over menu entries.

The status bar also displays the following information:

- ▶ The tab window size (columns x rows)
- ▶ The CPU usage (0 100%)
- ▶ The memory load (0 100%)
- ▶ The state of the Caps Lock key
- ▶ The state of the Num Lock key
- ▶ The state of the Scroll Lock key
- ▶ The current date (yyyy-mm-dd)
- ▶ The current time

You can hide the status bar fields (except for Caps Lock, Num Lock, and Scroll Lock) in the Windows configuration dialog.

There is a slider in the right corner that allows you to dynamically change the transparency level of the *Take Command* window. (You can also set the transparency in the **Options / Configure Take Command / Windows** dialog.)

3.3.1.7 Keyboard Shortcuts

Take Command offers a number of keyboard shortcuts to change windows or select entries in the **Folders** and **List View** windows. If you are in a tab window, you need to set the **Left Alt Key** or **Right Alt Key** and **Left Ctrl Key** or **Right Ctrl Key** options in the **Take Command** tab options (Otherwise the keystroke will be sent to the console application rather than being interpreted by **Take Command**.)

All Windows

Alt-F4 Closes the Take Command window

Ctrl-Tab Pops up a window allowing you to select the **Folder**, **List View**, or any of the tab

windows.

Alt-F6 Cycle through the Folders View, List View, and the active tab windows.

Tab Window

Ctrl-F4 Closes the active tab window

Ctrl-T Open a new tab

Ctrl-C Copy the selected text to the clipboard

Ctrl-V Paste the clipboard contents to the command line

Alt-Left Change to the previous tab window
Change to the next tab window
Scroll tab window buffer up one line
Alt-Down Alt-PgUp Scroll tab window buffer up one page
Alt-PgDn Scroll tab window buffer down one page

Folders and/or View Windows

Alt-Enter Display the Properties dialog for the selected folder or file

Ctrl-Enter Open the selected folder or file **Shift-Enter** Explore the selected folder

Del Delete the selected file(s) in the List View window to the recycle bin

Shift-Del Permanently the selected file(s) in the List View window Rename the selected file(s) in the List View window

3.3.1.8 Context Menus

Take Command displays a variety of context menus when you click on the right mouse button, depending on the location of the mouse cursor. If the mouse cursor is on the:

Menu Bar

You can customize the menu and toolbars.

Toolbar

You can customize the menu and toolbars.

Folders caption bar

You can detach, dock, AutoHide, or Hide the Folders window.

Folders view

Displays the Windows Shell context menu.

List View caption bar

You can detach, dock, AutoHide, or Hide the List View window.

List View

Displays the Windows Shell context menu.

Tab Bar

You can create a new tab or move an existing console window to a *Take Command* tab window.

Tab Labels

You can attach, detach, rename, and close tabs;

Tab Windows

You can copy selected text to the clipboard or paste the clipboard contents to the application in the tab window. (Paste works by sending the contents of the clipboard to the tab window as a series of keystrokes, so it will work with any application that accepts input.)

3.3.1.9 Running DOS apps

If you want to run 16-bit DOS programs in *Take Command* tab windows, you need to be aware of some limitations in the 16-bit support in Windows.

32-bit and 64-bit console applications can be run in any size tab window (subject to any internal limitations in the program itself). However, when Windows starts a 16-bit DOS program, it will always force the console buffer to resize itself to 80x25, 80x43, or 80x50 (whichever is nearest to the current console size). This has three implications:

- If Windows increases the console window size, Take Command has to increase its window height to match, and
- You will lose everything in your scrollback buffer when you start the DOS program, and
- You will not be able to scroll through the output of the DOS program.

When the DOS program exits, Windows will resize the screen buffer to its original size (but it keeps the screen window at the same size). If *Take Command* increased its window height, it will not resize itself to its previous size.

If you size your *Take Command* tab windows to 25, 43, or 50 lines, *Take Command* will not need to resize itself when running DOS programs.

You can also start a DOS program in a tab window (with the Run solution). *Take Command* will not need to resize its window in this case, as the console manager will be forced to size the console downwards rather than upwards. Or you can run the DOS program in a separate console window (with the Run solution) dialog or the *TCC* START solution.

Whenever possible, we recommend you retire your DOS programs and replace them with Windows console applications!

3.3.1.10 Using the Scrollback Buffer

Take Command retains the text displayed on its tab windows in a "scrollback buffer". You can scroll through this buffer using the mouse and the vertical scroll bar at the right side of the **Take Command** window, just as you can in any Windows application. You can also use the **Alt-Up** and **Alt-Down** keys to scroll the display one line at a time from the keyboard, and the **Alt-PgUp** and **Alt-PgDn** keys to scroll one page at a time.

If you scroll back through the buffer to view previous output, and then enter text on the command line,

Take Command will automatically return to the bottom of the buffer to display the text.

You can set the size of the scrollback buffer on the Windows tab 49 of the configuration dialogs 46.

3.3.1.11 Highlighting & Copying Text

While you are working at the *Take Command Console* prompt you can use common Windows keystrokes to edit commands, and use the Windows clipboard to copy text between *Take Command* and other applications. You can also select all of the text in a *Take Command* tab window buffer by using the **Select All** command on the Edit menu.

The right mouse button will pop up an **Edit** context menu.

To copy text from a *Take Command* tab window to the clipboard, first use the mouse to highlight the text, then right click and select Copy, or use the COPY command on the <u>Edit menu selection</u>. You can optionally combine multiple selected lines into a single line before placing it in the keyboard by holding down the Ctrl key and selecting Copy (or Copy+Paste or Copy+Paste+Run) from the right-click context menu or the Edit menu. If you have an existing multiline selection in the clipboard, you can copy it to a single line (with the CR/LF's replaced by a space) in the *Take Command* window by holding down the Ctrl key and selecting Paste. (If you hold down the Ctrl key and the selection wraps around the last screen column, the lines will be appended without an intervening space.)

If you double-click on a word in the *Take Command* window, the entire word is highlighted or selected.

To highlight text on the command line use the **Shift** key in conjunction with the **Left**, **Right**, **Ctrl-Left**, **Ctrl-Right**, **Home**, and **End** cursor movement keys. The **Del** key will delete any highlighted text on the command line, or you can type new text to replace the highlighted text.

While *Take Command* tab windows contain text, they are not document windows like those used by word processors and other similar software, and you cannot move the cursor throughout the window as you can in text processing programs. As a result, you cannot use the Windows shortcut keys like **Shift-Left** or **Shift-Right** to highlight text in the window. These keys work only at the command line; to highlight text elsewhere in the window you must use the mouse.

To copy text from the clipboard to the command line use **Ctrl-V**, or the Paste command on the Edit menu.

To paste text from elsewhere in a *Take Command* tab window directly onto the command line, highlight the text with the mouse and press *Ctrl-Shift-Ins*, or use the *Copy+Paste* command on the Edit menu. This is equivalent to highlighting the text and pressing *Ctrl-C* followed by *Ctrl-V*. It's a convenient way to copy a filename from a previous DIR or other command directly to the command line.

You should use caution when pasting text containing carriage return or line feed characters onto the command line. If the text you insert contains one of these characters the command line will be executed just as if you had pressed Enter. If you insert multiple lines, the text will be treated just like multiple lines of commands typed at the prompt.

You can also use Windows' <u>Drag and Drop less</u> facility to paste a filename from another application onto the command line, and you can access the clipboard with <u>redirection less</u> to or from the CLIP: device, or with the <u>@CLIP less</u> variable function.

3.3.1.12 Resizing the Take Command Window

You can resize the *Take Command* window at any time by dragging a corner with the mouse. Resizing the window changes the number of rows and columns of text which will fit in the command window (the actual number of rows and columns for any given window size depends on the font you are using). *Take Command* reacts to these changes using two sets of rules: one for the height and one for the width.

When the height of the command window changes, future commands simply use the new height as you see it on the screen. For example, if you reduce the window to three rows high and do a DIR /P (display a directory of files and pause at the bottom of each visual "page"), DIR will display two lines of output, a prompt ("Press any key to continue ..."), and then pause. If you expand the window to 40 lines high and repeat the same command, DIR will display 39 lines, a prompt, and then pause.

However, when the width of the window changes, *Take Command* must check the current virtual screen width. The virtual width is the maximum number of characters on each line in *Take Command* 's internal screen buffer. You can think of it as the width of the data which can be displayed in the *Take Command* window, including an invisible portion to the right of the window's right-hand edge. When the virtual width is larger than the actual width, a standard horizontal scroll bar is displayed to allow you to see any hidden output.

The _ROWS [391] internal variable can be used to determine the current screen height.

The virtual screen width starts at 80 columns or the number of columns which fit into the startup *Take Command* window, whichever is larger. The <u>COLUMNS</u> set internal variable can be used to determine the current virtual screen width.

If you expand the *Take Command* window beyond its previous virtual width, the virtual width is automatically increased. This ensures that the internal buffer can hold lines which will fill the newly enlarged window. If you shrink the window, the virtual width is not reduced because this might require removing output already on the screen or in the scrollback buffer.

As a result, widening the window will make future commands use the new enlarged size (for example, as the window is widened DIR /W, which displays a "wide" directory listing, will display additional columns of file names). However, if the window is narrowed future commands will still remember the enlarged virtual width, and display data to the right of the window edge. Use the horizontal scroll bar to make this data visible.

When the font is changed, *Take Command* will recalculate the virtual screen width.

3.3.1.13 Drag & Drop

Take Command is compatible with Windows' Drag-and-Drop facility.

To add a filename to the command line using drag and drop simply drag the file from an application (or the *Take Command* folder or list view windows), and drop it anywhere inside a *Take Command* tab window. The full name of the file will be pasted at the current cursor position.

Take Command is a drag and drop "client", which means it can accept files dragged in from other applications and paste their names onto the command line as described above. It is not a drag and drop "server", so you cannot drag filenames from the **Take Command** window into other applications. However you can copy filenames and other text from the **Take Command** window to other applications using the clipboard; see Highlighting and Copying Text

3.3.1.14 Take Command Dialogs

The *Take Command* menus lead to several dialog boxes. Each is listed here for quick reference, though in general you will find it easier to learn about each one from the context in which it is used (for

example, the information referenced below on the tool bar dialog will be more useful after you have read the section on the tool bar 62).

Take Command uses standard Windows dialogs for tasks like printing, selecting a font, or browsing files and directories. Since these dialogs are provided by Windows, not **Take Command**, and are common to many different Windows programs; they are not documented within this help system.

The reference in parentheses after certain dialogs listed below shows the name of the menu solution value to access that dialog.

Run Program Dialog 69 (Apps 60) (Options 61) Startup Tab 47 Windows Tab 43 Command Line Tab 50 AdvancedTab 51 Internet Tab 53 (Options 61)

3.3.1.14.1 Run Program

The Run Program dialog, started from the <u>Tabs menu</u> of, allows you to run a program by typing its name or browsing the disk.

In the **Command Line** edit box, you can enter the name of any executable program plus command line parameters. If you click on the arrow to the right of the edit box, the dialog displays a list of previous commands you have entered during the current **Take Command** session.

The **Browse** button leads to a standard file browser from which you can select any executable program. Your choice will be placed in the Command Line edit box, and you can add parameters before selecting OK to run the program.

You can enter an optional startup directory in the **Directory** edit box.

You can specify an optional user name and password in whose context the program should be run. (Depending on your user privileges, you may not be able to run the program in a *Take Command* tab window.)

Start in a New Tab will start a console application in a new *Take Command* tab window. (You cannot start a GUI application in a tab window.)

The **Normal**, **Minimized**, and **Maximized** buttons determine the type of window that will be used for the program. If you select Minimized, the program will start as an icon on the Taskbar. Maximized starts the program in a full-screen window. The Normal button lets the operating system select the size and position of the program's window.

3.3.1.14.2 Tab Toolbar

This dialog (called from the *Take Command* Options menu) allows you to define or modify buttons on the tool bar. The tool bar dialog will display 50 buttons (1-25 in the first row, and 26-50 in the second row).

Select the button you want to define, modify, or delete by clicking on it. A second dialog opens to let you define the label, command, directory, and mode for the button.

A toolbar button can either open a new tab, send keystrokes to the current tab, or change the directory displayed in the Folder and List views.

You can define a toolbar button to display either an icon, a text label, or both. You must specify either the **Icon** or **Label** fields. If you enter both, **Take Command** will display the text to the right of the icon on the button.

In the **Icon** field, enter the filename for the icon (.ico) that you want to display on the button. If you specify an .exe filename, *Take Command* will use the first icon in that file. You can use the **Browse** button to find the file.

In the **Label** field, enter the text that you want to display on the button.

In the **Command** field, you can enter either the command to be started in a new window ("Start a new window"), or the keystrokes to be sent to the current tab ("Send to current tab"). You can use the **Browse** button to find a file to be entered at the beginning of the Command field.

If the tab is sending keystrokes to the current tab, the text is in the same format as the KEYSTACK [262] command in the **Take Command Console**:

If you're starting a new window, the **Directory** field will set the startup directory for the command. If you are changing the Folders directory, the **Directory** field specifies the new directory. You can use the **Browse** button to find the directory.

Keystroke Interpretation

Characters entered within double quotes, e.g., "*abc*" will be sent to the active console application as is. The only items allowed outside the quotes are key names, the ! and /W options, and a repeat count.

If *keyname* is a number, it is interpreted as an ASCII character value.

Repetition. To send **keyname** several times, follow it with a space, left bracket [, the repetition count, and a right bracket]. For example, the command below will send the Enter key 4 times:

enter [4]

The repeat count works only with an individual *keyname*. It cannot be used with quoted strings. You must have a blank space between the *keyname* and the repetition count.

If you exit by choosing the **OK** button, any changes you have made will be saved in TCMD.INI, and reloaded automatically the next time you start *Take Command*. If you use the **Cancel** button, your changes will be discarded.

The tool bar can also be configured with the TCTOOLBAR 3431 command.

3.3.1.14.3 Skins and Themes

Take Command supports Windows *.msstyle skins to change the visual style of the **Take Command** window. (These are available from a number of web sites.) Once you have downloaded skins to the **Styles** subdirectory in your **Take Command** installation directory, you will see them when you select "Local Skins" on the "Skins and Themes" tab. (If you have any system-wide skins installed in your **\Windows** directory, they will appear when you select "System Skins".)

Changing skins will only affect the appearance of *Take Command*; other programs on your system will be unaffected.

If you want to restore the default configuration, click on the **Default** button in the **Default Skins** group.

The *Controls* tab shows you how the selected skin will look. (You cannot change anything in this tab; use the *Skins and Themes* tab to change the appearance.)

3.4 Directory Navigation

TCC remembers both a current or default drive for your system as a whole, and a current or default directory for every drive in your system. The current directory on the current drive is sometimes called the current working directory.

With traditional command processors, you change the current drive by typing the new drive letter plus a colon at the prompt. You change the current working directory with the <u>CD</u> representation command. *TCC* supports these standard features, and offer a number of enhancements to make directory navigation much simpler and faster.

This section begins with a summary of all the *TCC* directory navigation features. It also provides detailed documentation on the enhanced directory search features: Extended Directory Searches and CDPATH 72.

The **TCC** directory navigation features are in three groups: features which help **TCC** find the directory you want, methods for initiating a directory change with a minimal amount of typing, and methods for returning easily to directories you've recently used. Each group is summarized below.

Finding Directories

Traditional command processors require you to explicitly type the name of the directory you want to change to. *TCC* supports this method, and also offers two significant enhancements:

- The <u>CDPATH 72</u> variable allows you to enter a specific list of directories to be searched, rather than searching a database. Use <u>CDPATH 72</u> instead of Extended Directory Searches if you find the extended searches too broad, or your hard drive has too many directories for an efficient search.
- Extended Directory Searches 3 allows **TCC** to search a database of all the directories on your system to find the one you want.

Changing Directories

TCC supports the traditional methods of changing directories, and also offers several more flexible approaches:

- Automatic directory changes allow you to type a directory name at the prompt and switch to it automatically, without typing an explicit CD 1777 or similar command.
- The CD 1777 command can change directories on a single drive, and can return to the most recently used directory.
- The CDD 178 command changes drive and directory at the same time, and can return to the most recently used drive and directory.
- The PUSHD [299] command changes the drive and directory like CDD [178], and records the previous directory in a directory "stack." You can view the stack with the DIRS [209] command or the @DIRSTACK [416] function, and return to the directory on the top of the stack with POPD [294]

CDD [178], PUSHD [299], and <u>automatic directory changes</u> [76] can also change to network drives and directories mapped to drive letters and to ones specified with UNC names (see <u>File Systems</u> [491] for details).

Returning to a Previous Directory

CMD.EXE does not remember previously-used directories, and can only "return" to a directory by changing back to it with a standard drive change or CD command. *TCC* supports three additional, simpler methods for returning to a previous directory:

- The <u>CD</u> 177 and <u>CDD</u> 178 commands can be used to return to the previous working directory (the one you used immediately before the current directory). Use these commands if you are working in two directories and alternating between them.
- The <u>directory history window allows</u> you to select one of several recently-used directories from a popup list and return to it immediately. The window displays the contents of the directory history list.
- The POPD 2941 command returns to the last directory saved by PUSHD 2991. The directory stack holds 2048 characters, enough for 40 to 80 typical drive and directory entries.

3.4.1 CDPATH feature

When you change directories with an <u>automatic directory change</u> or the <u>CD</u> (177), <u>CDD</u> (178), or <u>PUSHD</u> (299) command, **TCC** must find the directory you want to change to. If it cannot find an exact match of the directory path and name, **TCC** tries to find the directory you requested via the <u>CDPATH</u> (72), then via an Extended Directory Search (73).

Enabling both <u>CDPATH</u> and <u>Extended Directory Searches</u> can yield confusing results. If you prefer to explicitly specify where **TCC** should look for directories, use <u>CDPATH</u>. If you prefer to have **TCC**look at all of the directory names on your disk, use Extended Directory Searches.

CDPATH 72 is an environment variable, and is similar to the PATH 368 variable used to search for executable files: it contains an explicit list of directories to search when attempting to find a new directory. **TCC** appends the specified directory name to each directory in CDPATH 72 and attempts to change to that drive and directory. It stops when it finds a match or when it reaches the end of the CDPATH 72 list.

CDPATH [72] is ignored if a complete directory name (one beginning with a backslash \) is specified, or if a drive letter is included in the name. It is only used when a name is given with neither drive letter nor leading backslash.

CDPATH 72 provides a quick way to find commonly used subdirectories in an explicit list of locations. You can create CDPATH 72 with the SET 319 command. The format of CDPATH 72 is similar to that of PATH 388: a list of directories separated by semicolons. For example, if you want the directory change commands to search the C: DATA directory, the D:DATA directory, and the root directory of drive E: for the subdirectories that you name, you should create CDPATH 72 with this command:

```
set cdpath=c:\data;d:\software;e:\
```

Suppose you are currently in the directory *C:\WP\LETTERS\JANUARY*, and you'd like to change to *D:\SOFTWARE\UTIL*. You could change directories explicitly with the command:

```
[c:\wp\letters\january] cdd d:\software\util
```

However, because the $D: \SOFTWARE$ directory is listed in your CDPATH variable as shown in the previous example (we'll assume it is the first directory in the list with a UTIL subdirectory), you can simply enter the command

```
[c:\wp\letters\january] cdd util
```

or, using an automatic directory change:

```
[c:\wp\letters\january] util\
```

to change to *D:\SOFTWARE\UTIL*.

TCC looks first in the current directory, and attempts to find the C:\WP\LETTERS\JANUARY\UTIL subdirectory. Then it looks at CDPATH 72, and appends UTIL to each entry in the CDPATH 72 variable — in other words, it tries to change to C:\DATA\UTIL, then to D:\SOFTWARE\UTIL. Because this change succeeds, the search stops and the directory change is complete.

If you often switch between "sibling" directories, i.e., between subdirectories of a common parent directory. you can enter .. as a search entry in your CDPATH 72. You can use ... to find "uncles", i.e., a directory one level up (a sibling of the parent directory), thus a subdirectory of the directory 2 levels up.

3.4.2 Extended Directory Searches

When you change directories with an <u>automatic directory change [76]</u>, <u>CD [177]</u>, <u>CDD [178]</u>, or <u>PUSHD [299]</u> command, **TCC** must find the directory you want to change to. To do so, it first checks to see whether you have specified either the name of an existing subdirectory below the current directory, or the name of an existing directory with a relative or full path or a drive letter. If you have, **TCC** changes to that directory, and does no further searching.

This search method requires that you navigate manually through the directory tree, and type the entire name of each directory you want to change to. Extended Directory Searches speed up the navigation process dramatically by allowing *TCC* to find the directory you want, even if you only enter a small part of its name.

When the first search method fails, *TCC* tries to find the directory you requested via the <u>CDPATH</u> 72 variable, then via an Extended Directory Search. This section covers only Extended Directory Searches, which are more flexible and more commonly used than <u>CDPATH</u>. 72

Extended Directory Searches use a database of directory names to facilitate changing to the correct directory. The database is used only if Extended Directory Searches are enabled, and if the explicit directory search and CDPATH 2 search fail to find the directory you requested.

An extended directory search automatically finds the correct path to the requested directory and changes to it if that directory exists in your directory database. If more than one directory in the database matches the name you have typed, a popup window appears and you can choose the directory you want.

You can control the position and size of the popup directory search window from the Windows tab of the configuration dialogs 46. You can also change the keys used in the popup window with key mapping directives 28.

To use extended directory searches, you must explicitly enable them (see below) and also create the directory database.

The Extended Search Database

To create or update the database of directory names, use the CDD /S 178 command. When you create

the database with CDD /S, you can specify which drives should be included. If you enable Extended Directory Searches and do not create the database, it will be created automatically the first time it is required, and will include all local hard drives.

The database is stored in the file *JPSTREE.IDX*. By default, the file is placed in the root directory of drive C:. Because of security restrictions in Windows Vista, the the default directory in Vista is defined as the value of the environment variable APPDATA (predefined by Windows). If you are running Vista and don't have APPDATA in your environment, the default directory will be the directory where *TCC* is installed. You can specify a different location for this file on the Command Line tab of the configuration dialogs 46.

If you use an internal command to create or delete a directory, the directory database is automatically updated to reflect the change to your directory structure.

The TREEEXCLUDE 370 variable can be used to specify which drives/directories should be excluded from inclusion in the directory database.

The internal commands which can modify the directory structure and cause automatic updates of the file are MD 27th, RD 30th, COPY /S 182th, DEL /X 190th, MOVE /S 27th, and REN 30sth. The MD 27th /N command can be used to create a directory without updating the directory database. This is useful when creating a temporary directory which you do not want to appear in the database.

Enabling Extended Searches

To enable extended directory searches and control their operation, you must set the Search Level on the Command Line tab 50 of the configuration dialogs 46.

- If Search Level = 0, extended searches are disabled, the *JPSTREE.IDX* database is ignored, and CD 177, CDD 178, PUSHD 299 and automatic directory changes search for directories using only explicit names and CDPATH 72. This is the default.
- If Search Level = 1 and an extended search is required, TCC will search the JPSTREE.IDX database for directory names which exactly match the name you specified.
- If Search Level = 2 and an extended search is required, *TCC* will search the database for
 exact matches first, just as when Search Level = 1. If the requested directory is not found, it
 will search the database a second time looking for directory names that begin with the name
 you specified.
- If Search Level = 3 and an extended search is required, TCC will search the database for
 exact matches first, just as when Search Level = 1. If the requested directory is not found, it
 will search the database a second time looking for directory names that contain the name you
 specified anywhere within them.

For example, suppose that you have a directory called *C*: \DATA\MYDIR, CDPATH 72\ is not set, and *C*: \DATA is not the current directory on drive C:. The following chart shows what CDD 178\ command you might use to change to this directory.

Search Level	Type of extended search	Typical CDD Command
0	CDPATH 72 only (default)	cdd c:\data\mydir
1	CDPATH 72 or exact match	cdd mydir
2	CDPATH 72 or leading match	cdd myd
3	CDPATH 72 or any match	cdd yd

An extended directory search is not used if you specify a full directory path (one beginning with a

backslash \, or a drive letter and a backslash). If you use a name which begins with a drive letter (e.g. C:MYDIR), the extended search will examine only directories on that drive.

Forcing an Extended Search with Wildcards

Normally you type a specific directory name for *TCC* to locate, and the search proceeds as described in the preceding sections. However, you can also force *TCC* to perform an extended directory search by using wildcard characters in the directory name. If you use a wildcard, an extended search will occur whether or not extended searches have been enabled.

When *TCC* is changing directories and it finds *wildcards* in the directory name, it skips the explicit search and CDPATH 2 steps and goes directly to the extended search.

If a single match is found, the change is made immediately. If more than one match is found, a popup window is displayed with all matching directories.

Wildcards can only be used in the final directory name in the path (after the last backslash in the path name). For example you can find *COMM*A** (all directories whose parent directory is *COMM* and which have an *A* somewhere in their names), but you cannot find *CO?M*A** because it uses a wildcard before the last backslash.

If you use wildcards in the directory name as described here, and the extended directory search database does not exist, it will be built automatically the first time a wildcard is used. You can update the database at any time with CDD 178 /s.

Internally, extended directory searches use wildcards to scan the directory database. If Search Level is set to 2, an extended search looks for the name you typed followed by an asterisk (*i.e.* DIRNAME*). If Search Level is set to 3, it looks for the name preceded and followed by an asterisk (*i.e.* *DIRNAME*).

These internal wildcards will be used in addition to any wildcards you use in the name. For example if you search for *ABC?DEF* (*ABC* followed by any character followed by *DEF*) and Search Level is set to 3, **TCC**will search the directory database for *ABC?DEF*.

Disabling Extended Searches in Batch Files

When writing batch files you may want to use the CD TO or CDD TO CDD TO

To disable extended searches, use the /N option of CD 177 or CDD 178. When this option is used and a directory does not exist below the current directory or on the CDPATH 72, the command will fail with an error message, and will not search the extended search database. For example this command might trigger an extended search:

```
cdd testdir
```

but this one will not:

```
cdd /n testdir
```

Note that this option is not available for PUSHD [299]. To perform the same function when using PUSHD [299], save the current directory with PUSHD [299] (without parameters) and then use CDD [178] /N to change directories, for example:

```
pushd
cdd /n testdir
```

3.4.3 Automatic Directory Changes

Automatic directory changes are part of the comprehensive directory navigation features built into *TCC*. For a summary of these features, and more information on Extended Directory Searches and CDPATH (72), see Directory Navigation (71).

Automatic directory changes let you change directories quickly from the command prompt, without entering an explicit CD 177 or CDD 178 command. Simply type the name of the directory you want to change to at the prompt, with a terminating backslash (\) (either entered manually, or automatically via the Add \ to Directories 50 configuration option). For example:

```
[c:\] tcmd\
[c:\tcmd]
```

This can make directory changes very simple when it's combined with Extended Directory Searches 73 or CDPATH 72. If you have enabled either of those features, *TCC* will use them in searching for a directory with an automatic directory change.

For example, suppose Extended Directory Searches 73 are enabled, and the directory WIN exists on drive E:. You can change to this directory with a single word on the command line:

```
[c:\tcmd] win\
[e:\win]
```

This depends on the way Extended Directory Changes are configured, and the number of subdirectories on your disk whose names contain the string **WIN**, when you execute such a command you may see an immediate change as shown above, or a popup window which contains a list of subdirectories matching **WIN** to choose from.

The text before the backslash can include a drive letter, a full path, a partial path, or a <u>UNC name</u> see <u>File Systems</u> for details on UNC names). Commands like "....\" can be used to move up the directory tree quickly (see <u>Extended Parent Directory Names</u> 118).

If you enter a directory name without the trailing backslash, the parser will change to that directory if no internal or external command of that name is found (and before the UNKNOWN_CMD alias is executed.)

All directory changes, including automatic ones, save the current directory so it can be recalled with a $\frac{\text{CDD}}{178}$ - or $\frac{\text{CD}}{178}$ - command.

For example, any of the following are valid automatic directory change entries:

```
[c:\] d:\data\finance\
[c:\] archives\
[c:\] ...\util\scanner\
[c:\] \\server\vol1\george\
```

The first and last examples change to the named directory. The second changes to the *ARCHIVES* subdirectory of the current directory, and the third changes to the *UTIL\SCANNER* subdirectory of the directory which is two levels up from the current directory in the tree.

3.4.4 Directory Aliases

Directory Aliases are a shorthand way of specifying pathnames. For example, if you define an alias:

```
alias pf:=c:\program files
```

You can then reference the files in **c:\program files\jpsoft** by entering **pf:\jpsoft**. Directory aliases work in places that accept filenames and directory names (internal command arguments or the first argument in a command line), including filename completion. You cannot use them in arguments to external applications, as **TCC** has no way of knowing what is a valid argument for external applications.

Directory aliases support alias arguments, but they do not support environment variable expansion.

3.5 File Selection

Most internal commands (like <u>COPY 182</u>), <u>DIR 198</u>), etc.) work on a file or a group of files. You can use several shorthand forms for naming or selecting files and the applications associated with them, or for accessing files on remote systems.

Most of the features explained in this section apply to *TCC* commands only, and generally cannot be used to pass file names to external programs (unless those programs were specifically written to support these features).

The features discussed in this section are:

- ▶ Wildcards 77
- Ranges 80
- Attribute Switches 86
- Multiple Filenames 87
- Include Lists 88
- ▶ Extended Parent Directory Names 118
- Directory Aliases 76
- LFN File Searches 89
- @File Lists 90
- ▶ Command Switches for File Selection 91

3.5.1 Wildcards

Wildcards let you specify a file or group of files by typing a partial filename. The appropriate directory is scanned to find all of the files that match the partial name.

Wildcards are usually used to specify which files should be processed by a command. If you need to specify which files should not be processed, see File Exclusion Ranges (for internal commands), or EXCEPT (for external commands).

Most internal commands accept filenames with wildcards anywhere that a full filename can be used. There are two wildcard characters, the <u>asterisk 777 * and the question mark 78 ?</u>. Additionally, you can specify a <u>set of characters 78 .</u> Note the issues about <u>matching short file names 79 .</u>

WARNING: When you use a wildcard search for files to process in a command like FOR [234] or DO [210], and you create new filenames (whether by renaming existing files or by creating new files), the new filenames may match your selection wildcard, and cause you to process them again.

Asterisk * wildcard

An asterisk * in a file specification means "a set of any characters or no character in this position". For example, this command will display a list of all files (including directories, but excluding those files and directories with at least one of the attributes *hidden* and *system*) in the current directory:

```
dir *
```

If you want to see all of the files with a .TXT extension:

```
dir *.txt
```

If you know that the file you are looking for has a base name that begins with ST and an extension that begins with D, you can find it this way. Filenames such as STATE.DAT, STEVEN.DOC, and ST.D will all be displayed:

```
dir st*.d*
```

TCC also lets you also use the asterisk to match filenames with specific letters somewhere inside the name. The following example will display any file with a <code>.TXT</code> extension that has the letters **AM** together anywhere inside its base name. It will, for example, display <code>AMPLE.TXT</code>, <code>STAMP.TXT</code>, <code>CLAM.TXT</code>, and <code>AM.TXT</code>, but it will ignore <code>CLAIM.TXT</code>:

```
dir *am*.txt
```

Question mark? wildcard

A question mark? matches any single filename character. You can put the question mark anywhere in a filename and use as many question marks as you need. The following example will display files with names like *LETTER.DOC*, *LATTER.DAT*, and *LITTER.DU*:

```
dir 1?tter.d??
```

The use of an asterisk wildcard before other characters, and of the character ranges discussed below, are enhancements to the standard Microsoft wildcard syntax, and are not likely to work properly with software other than *TCC*.

"Extra" question marks in your wildcard specification are ignored if the file name is shorter than the wildcard specification. For example, if you have files called *LETTER.DOC*, *LETTER1.DOC*, and *LETTERA.DOC*, this command will display all three names:

```
dir letter?.doc
```

The file *LETTER.DOC* is included in the display because the "extra" question mark at the end of **LETTER?** is ignored when matching the shorter name *LETTER*.

Specific character set

In some cases, the ? wildcard may be too general. *TCC* also allows you to specify the exact set of what characters you want to accept (or exclude) in a particular position in the filename by using square brackets []. Inside the brackets, you can put the individual acceptable characters or ranges of characters. For example, if you wanted to match *LETTERO*. *DOC* through *LETTER9*. *DOC*, you could use this command:

```
dir letter[0-9].doc
```

You could find all files that have a vowel as the second letter in their name this way. This example also demonstrates how to mix the wildcard characters:

```
dir ?[aeiouy]*
```

You can exclude a group of characters or a range of characters by using an exclamation mark [!] as the first character inside the brackets. This example displays all filenames that are at least 2

characters long except those which have a vowel as the second letter in their names:

```
dir ?[!aeiouy]*
```

The next example, which selects files such as AIP, BIP, and TIP but not NIP, demonstrates how you can use multiple ranges inside the brackets. It will accept a file that begins with an A, B, C, D, T, U, or V:

```
dir [a-dt-v]ip
```

You may use a question mark character inside the brackets, but its meaning is slightly different than a normal (unbracketed) question mark wildcard. A normal question mark wildcard matches any character, but will be ignored when matching a name shorter than the wildcard specification, as described above. A question mark inside brackets will match any character, but will **not** be discarded when matching shorter filenames. For example:

```
dir letter[?].doc
```

will display LETTER1.DOC and LETTERA.DOC, but not LETTER.DOC.

A pair of brackets with no characters between them [], or an exclamation point and question mark together [!?], will match only if there is no character in that position. For example,

```
dir letter[].doc
```

will not display *LETTER1.DOC* or *LETTERA.DOC*, but it will display *LETTER.DOC*. This is most useful for commands like

```
dir /I"[]" *.btm
```

which will display a list of all •BTM files which don't have a description, because the empty brackets match only an empty description string (DIR 1981)/I selects files to be displayed based on their descriptions).

You can repeat any of the wildcard characters in any combination you desire within a single file name. For example, the following command lists all files which have an **A**, **B**, or **C** as the third character, followed by zero or more additional characters, followed by a **D**, **E**, or **F**, followed optionally by some additional characters, and with an extension beginning with **P** or **Q**. You probably won't need to do anything this complex, but we've included it to show you the flexibility of extended wildcards:

```
dir ??[abc]*[def]*.[pq]*
```

You can also use the square bracket wildcard syntax to work around a conflict between long filenames containing semicolons [;], and the use of a semicolon to indicate an <u>include list [88]</u>. For example, if you have a file on an LFN drive named *C:\DATA\LETTER1;V2* and you enter this command:

```
del \data\letter1;v2
```

you will not get the results you expect. Instead of deleting the named file, **TCC**will attempt to delete *LETTER1* and then *V*2, because the semicolon indicates an <u>include list 880</u>. However if you use square brackets around the semicolon it will be interpreted as a filename character, and not as an include list separator. For example, this command would delete the file named above:

```
del \data\letter1[;]v2
```

Matching short file names

If the Search for SFNs 4 configuration option is set, wildcard searches accept a match on either the LFN or the SFN to match the behavior of CMD.EXE. This may cause some files to be found because of SFN match only. In most situations this is not actually desirable, and can be avoided by disabling the option (the default).

Note: The wildcard expansion process will attempt to allow both CMD.EXE-style "extension" matching (only one extension, at the end of the word) and the advanced *TCC* filename matching (allowing things like *.*.abc) when an asterisk is encountered in the destination of a <u>COPY 182</u>, <u>MOVE 274</u> or <u>REN/RENAME 305</u> command.

Regular Expressions

You can also use regular expressions for file name tests. (The type of regular expressions to use is specified by the Regular Expressions Syntax 51 option.)

The syntax is:

::regex

For example:

dir ::ca[td]

Note that using regular expressions will slow your directory searches -- since Windows doesn't support them, the parser has to convert the filename to *, retrieve all filenames, and then match them to the expression.

If you have any special characters (whitespace, redirection characters, escape characters, etc.) in your regular expression, you will need to enclose it in double guotes. For example:

$$dir :: "^\w{1,8}\.btm$"$$

For more information on the syntax, see Regular Expression Syntax 4961.

3.5.2 Ranges

Most internal commands which accept wild cards also allow size, date, time, exclusion, and description ranges to further define the files that you wish to work with. **TCC** will examine each file's properties to determine whether or not the file meets the range criteria that you have specified.

A size, date, time, or exclusion range specification begins with the switch character /, followed by a left square bracket [and a character that specifies the range type: **s** for size range, **d** for date range, **t** for time range, or ! for exclusion range. The **s**, **d**, or **t** is followed by a start value, and an optional comma and end value. The range ends with a right square bracket]. For example, to select files between 100 and 200 bytes long you could use the range /[s100,200].

A description range begins with /I. See Description Ranges 6 for the full syntax.

General Rules

You can reverse the range test by preceding the range argument with the ! character. For example, to select files that are less than 100 bytes or more than 1000 bytes:

/![s100,1000]

If you combine different types of ranges, a file must satisfy all range specifications to be included. For example,

```
/[d2006-2-8,2008-2-9] /[s1024,2048]
```

means files last modified between February 8, 2006 and February 9, 2008, which are also between 1,024 and 2,048 bytes long.

You may not repeat the same range type in a command.

When you use range specifications in a command, they should immediately follow the command name, so that any additional switches for the command are after any range(s) used. If the range is placed later in the command it may be ignored, or cause an error. Unlike some command switches which apply to only part of the command line, the range usually applies to all file names specified for the command. Any exceptions are noted in the descriptions of individual commands.

For example, to get a directory of all the *.C files dated October 1, 2007, you could use this command:

```
dir / [d2007-10-1,+0] *.c
```

To delete all of the 0-byte files on your disk, you could use this command:

```
del /[s0,0] * /s
```

And to copy all of the non-zero byte files that you changed yesterday or today to your floppy disk, you can use this command:

```
copy / [d-1] / [s1] * a:
```

It can be tedious to type all of the elements of a range, especially when it involves multiple dates and times. In this case you may find it easier to use aliases for common operations. For example, if you often wish to select from .DAT files modified over the last three days and copy the selected files to another drive, you might define an alias like this:

```
alias workback=`select /[d-2] copy (*.dat) e:\datfiles\`
```

For more complex requirements, you may want to use internal variables (e.g. _DATE | 385 | or _TIME | 393) and built-in variable functions (e.g. _@DATE | 414 | @TIME | 463 | , @MAKEDATE | 445 | , @MAKEDATE | 445 | , @MAKETIME | 445 | , @MAKETIME | 445 | , @FILETIME | 432 | , or _@EVAL | 420). These variables and functions allow you to perform arithmetic and date / time calculations. You may also define your own variable functions, to perform more complex manipulations repetitively.

See the individual types for details on specifying ranges:

- Size Ranges 82
- Date Ranges 82 82
- Time Ranges 84
- Exclusion Ranges 85
- Description Ranges 86th

Ranges can be used with many commands, including ATTRIB 1631, COPY 1821, DEL 1901, DESCRIBE 1951, DIR 1981, DO 2101, EXCEPT 2251, FFIND 2271, FOR 2341, LIST 2641, MOVE 2741, RD 3051, REN 3051, SELECT 3121, and TYPE 3541

Ranges cannot be used with filename completion or in filename parameters for variable functions, except as described under the individual functions.

Do not use ranges with @file lists. See @file lists 90 for details.

Date, Time, and Size Ranges

All ranges are inclusive. For example, a size range which selects files from 10,000 to 20,000 bytes long will match files that are exactly 10,000 bytes or 20,000 bytes long, as well as all sizes in between; a date range that selects files last modified between 2007-10-27 and 2007-10-30 will include files modified on each of those dates, and on the two days in between.

If you reverse range start and end values **TCC** will recognize the reversal, and will use the second (lower) value as the start point of the range and the first (higher) value as its end point. For example, to select files between 100 and 200 bytes long could also be entered as /[s200,100].

3.5.2.1 Size Ranges

Size ranges select files whose size is between the inclusive limits specified. The second parameter of a size range is optional. If you use a single parameter, you will select all files of the specified size or larger. You can also precede the second parameter with a plus sign [+]; when you do, it is added to the first value to determine the largest file size to include in the search.

You can exclude a size range by preceding the range with the ! character.

When you use a size range in a command it should immediately follow the command name. See General Rules for Using Ranges of for additional details.

Either or both values in a size range can be suffixed with a scale factor from the table below. Lower case letters denote a power of 1,000, upper case letters a power of 1,024 (2**10).

Code	Scale Factor		Code	Scale Factor		Unit Name
k	1,000	10**3	K	1,024	2**10	kilobyte
m	1,000,000	10**6	M	1,048,576	2**20	megabyte
g	1,000,000,000	10**9	G	1,073,741,824	2**30	gigabyte
t	1,000,000,000,000	10**12	T	1,099,511,627,776	2**40	terabyte

Examples of size ranges:

Specification Selects Files of Length

/[s0,0] zero (empty)

/[s1M] 2**20 bytes or larger

/[s10k,+200] between 10,000 and 10,200 bytes, inclusive between 10 and 153,000 bytes, inclusive

/![s1K,5K] less than 1K or greater than 5K

3.5.2.2 Date Ranges

Date ranges select files dated at any time of day between the inclusive limits specified. For example, **/[d12-1-07,12-5-07]** selects files that were last modified on *or* after December 1, 2007, but not modified *after* December 5, 2007.

When you use a date range in a command, only other range specifications may be between the command name and the date range. See General Rules for Using Ranges 80 for additional details.

You can use hyphens, slashes, or periods to separate the month, day, and year. The year can be entered as a 2-digit or 4-digit value. Two-digit years between 80 and 99 are interpreted as 1980...1999; values between 00 and 79 are interpreted as 2000...2079. For example, /[d2006-12-31,2008-1-1] selects files modified between December 31, 2006 and January 1, 2008.

If either parameter begins with a four digit year (which must greater than 1900), it is assumed to be a

date in the international format **yyyy-mm-dd**, otherwise it is assumed that the date elements are in the order appropriate for your locale. All non-ISO date examples in the HELP use the USA format: mm-dd-yy, unless otherwise stated explicitly.

The default time for the first date is the beginning of that day, and for the second date it is the end of that day. This is true even if the dates are in descending order, i.e., the first date is later than the second one. You can alter these defaults by including specific start and stop times inside the date range. The time is separated from the date with an at sign @. For example, the range /[d2007-7-15@8:00a,2007-7-35@6:00p] selects files that were modified at any time between 8:00:00 am on July 1, 2007 and 6:00:00 pm on July 3, 2007. If you prefer, you can specify the times in 24-hour format (e.g., @18:00 for the end time in the previous example).

If you omit the second parameter in a date range, **TCC** substitutes the current date and time. For example, **/[d2007-10-1]** selects files dated between October 1, 2007 and the instant of command execution.

Instead of an explicit date, you may use an offset value for either the beginning or ending date, or both. An offset begins with a plus sign [+] or a minus sign [-] followed by an integer. If you use an offset for the second value, it is calculated relative to the first. If you use an offset for the first (or only) value, the current date is used as the basis for calculation. For example:

Specification	Selects Files
/[d2008-1-27,+3]	modified between January 27, 2008 and January 30, 2008
/[d2008-1-27,-3]	modified between January 24, 2008 and January 27, 2008
/[d-0]	modified today (from today minus zero days, to today)
/[d-1]	modified yesterday or today (from today minus one day, to today)
/[d-1,+0]	modified yesterday (from today minus one day, to zero days after that)

As a shorthand way of specifying files modified today, you can also use /[d]; this has the same effect as the /[d-0] example shown above.

To select files last modified *n* days ago or earlier, use /[d-n,1/1/80]. For example, to get a directory of all files last modified 3 days or more before today (*i.e.*, those files not modified within the last 3 days), you could use this command:

$$dir /[d-3,1/1/80]$$

This reversed date range (with the later date given first) will be handled correctly by *TCC*. It takes advantage of the facts that an offset in the start date is relative to today, and that the base or "zero" point for PC file dates is January 1, 1980, or earlier.

You cannot use offsets in the time portion of a date range (the part after an @ sign), but you can combine a time with a date offset. For example, /[d2007-12-85@12:00,+2@12:00] selects files that were last modified between noon on December 8 and noon on December 10, 2007. Similarly, /[d-2@15:00,+1] selects files last modified between 3:00 pm the day before yesterday and the end of the day one day after that, *i.e.*, yesterday. The second time defaults to the end of the day because no time is specified.

You can exclude a date range by preceding the range with the ! character.

Notes:

• If the second date is the termination date, and it includes an explicit termination time, it is considered an exact value. For example, in the last example the termination time was 6PM. Files with a timestamp of 6:00:01 PM or later are not included in the date range. This is different from the behavior of time ranges 84.

- If you include seconds in the times you specify, they will be silently ignored (no error or warning).
- If the first date is later than the second, any time of day modifiers for the first date are silently ignored.

Date types and selection

Windows file systems keep track of three dates for a file: when it was created, when it was last modified (written), and when it was last accessed. You specify which date and time is used in a date range by adding **a** (access), **c** (creation), or **w** (write) after the **d** in the range. For example, to select all files created between February 1, 2008 and February 7, 2008, inclusive, you would use /[dc2008-02-1,2008-2-7]. If you don't specify which date and time to use, *TCC* will use the date the file was last modified (written).

NOTE: On FAT32 drives which support long filenames, only the last access date is recorded; the last access time is always returned as 00:00. However, on NTFS drives, last access information includes both date and time.

Date and time ranges may not always work as you expect across a network, including on FTP or HTTP servers, due to differences in time zone and file time storage method between the local and remote systems. Be sure to do some non-destructive testing before depending on date or time ranges to yield the results you want on a remote system.

Defaults for Date Ranges

Start date: Today End date: Today

Time of first parameter:

Time of second parameter:

Missing second parameter:

Date type

Beginning of the day (00:00:00)

End of the day (23:59:59)

Current date and time

Modification (write)

3.5.2.3 Time Ranges

Time ranges select files timed at any time between the two specified times of day. For example, to select files modified at or between noon and 2:00 PM on any day, use /[t12:00p,2:00p]. The times in a time range can either be in 12-hour format, with a trailing **a** for AM or **p** for PM, or in 24-hour format.

When you use a time range in a command it should immediately follow the command name. See General Rules for Using Ranges of radditional details.

If you omit the second parameter in a time range, you will select files that were modified between the first time and the current time, on any date. You can also use offsets, beginning with a plus sign [+] or a minus sign [-] for either or both of the parameters in a time range. The offset values are interpreted as minutes. Some examples:

Specification	Selects Files
/[t12:00p,+120]	modified between noon and 2:00 PM on any date
/[t-120,+120]	modified between two hours ago and the current time on any date
/[t0:00,11:59]	modified in the morning on any date

The separator character used in the time may vary depending upon your country information.

You can exclude a time range by preceding the range with the ! character.

Time types and selection

Windows keeps track of three times for a file: when it was created, when it was last modified (written), and when it was last accessed. You can specify which time is used in a time range by adding a (access), c (creation), or w (write) after the t in the range specification. For example, to select all files created between noon and 2:00 pm, you would use /[tc12:00p,2:00p]. If you don't specify which time to use, *TCC* will use the time the file was last modified (written).

NOTE: On FAT drives which support long filenames, only the last access date is recorded; the last access time is always returned as 00:00. However, on NTFS drives, last access information includes both date and time.

Time ranges may not always work as you expect across a network, including on FTP or HTTP servers, due to differences in time zone and file time storage method between the local and remote systems. Be sure to do some non-destructive testing before depending on time ranges to yield the results you want on a remote system.

When you use a time range in a command it should immediately follow the command name. See General Rules for Using Ranges of radditional details.

Defaults

Start time: Current time End time: Current time

Time type: Modification (last write)

3.5.2.4 File Exclusion Ranges

Most internal commands which accept wildcards also accept file exclusion ranges to further define the files that you wish to work with. **TCC** examines each file name and excludes files that match the names you have specified in the exclusion range.

When you use an exclusion range in a command it should immediately follow the command name. See General Rules for Using Ranges of for additional details.

A file exclusion range begins with the switch character (usually a slash), followed by a left square bracket and an exclamation mark [! The range ends with a right square bracket].

Inside the brackets, you can list one or more filenames to be excluded from the command. The filenames can include wildcards and extended wildcards \overrightarrow{m} , but may not include path names or drive letters. You can exclude directories by appending a \to the name.

The following example will display all files in the current directory except backup files (files with the extension .BAK or .BK):

```
dir /[!*.bak *.bk] *
```

You can combine file exclusion ranges with <u>date</u>, <u>time</u>, <u>and size ranges</u> 80. This example displays all files that are 10K bytes or larger in size and that were created in the last 7 days, except .*C* and .*H* files:

```
dir /[s10k] /[d-7] /[!*.c *.h] *
```

File exclusion ranges, a unique feature of *TCC*, work for internal commands. The <u>EXCEPT</u> [225] command can also be used to exclude files from processing by any external or internal command which ignores files with the hidden attribute. You can utilize the file exclusion range with external commands utilizing the <u>DO</u> [210] or <u>FOR</u> [234] command; however, the performance will not be as good, since the external command is started separately for each match.

Note: File exclusion first checks to see if a file specification with embedded brackets exactly matches an existing file. If no such file is found, it interprets the brackets as wildcards.

See also: Include Lists 88.

3.5.2.5 Description Ranges

Most internal commands which accept wildcards also accept description ranges to further define the files that you wish to work with.

When you use a description range in a command it should immediately follow the command name. See General Rules for Using Ranges of for additional details.

A description range is specified as /l"text" where text is the description to be matched. Wildcards resupported. For example, /l"*agua*" selects all files with the string agua somewhere in the file description. The search text must be enclosed in double quotes, and must immediately follow the /l, with no intervening spaces.

You can select all files that have a description with /I"[?]*" (the [?] requires that the description contain at least one character, and the * allows any text).

You can select all files that do not have a description with /\(\bilde{I}\)"[]" (the [] requires that the first character, and therefore the descriptor itself, does not exist).

You can also search descriptions using regular expressions 4961 with /R" text".

If you precede the I or R with a !, the result is reversed. For example, /!I"*beta*" will select all of the files that do **not** have the word **beta** in their description.

See DESCRIBE 1951 for details on file descriptions.

3.5.3 Attribute Switches

Most file commands in *TCC* include the **/A**: switch, which allows you to select files for the command to process based on their attributes [494]. These switches all use the format **/A[:][-+]RHSAD**. The colon after /A is optional in DIR [198], FFIND [227], and SELECT [312], but is required in all other commands. The characters after the /A: specify which attributes to select, as follows:

- R Read-only
- н Hidden
- s System
- A Archive
- D Directory

On NTFS 532 volumes, the extended attributes below are also available.

- **E** Encrypted
- c Compressed
- I Not content-indexed
- L Symbolic link or Junction (reparse point)
- Normal (cannot be used for file selection)
- o Offline
- P Sparse file
- T Temporary

The \mathbf{n} (normal) attribute is not stored on disk. It is dynamically generated by the operating system if none of the other attributes is set. Its use for file selection is not supported in either commands or variable functions.

If no attributes are listed at all (*i.e.*, /A:), the command will process all files, and (where applicable) all subdirectories, including hidden and system files and directories.

If attributes are combined, all the specified attributes must match for a file to be selected. For example, **/A:RHS** will select only those files with all three attributes set.

If you precede an attribute with a hyphen –, files with that attribute will be excluded. For example, **/A:RH-S** selects files which have the read-only and hidden attributes set and which do not have the system attribute set.

If you precede an attribute with a plus +, files will be selected which have that attribute turned on or off. When multiple attributes are preceded by +, only files which have at least one of these attributes will be selected. For example, /A:+H+S will select files with the hidden or system attribute, or both, but will not select files which have neither attribute set. /A:R+H+S will select files which are read-only, and also have the hidden or system attribute, or both.

You can combine the plus sign, hyphen, and unmarked attributes to build a specification as complex as you need.

Example

The (dangerous!) command below will make all hidden, system, and/or read-only files in the default directory visible and writeable, but not modify the attributes of files which are neither hidden nor system nor read-only (thus not reporting files already in the desired state):

```
attrib /e /p /a:+r+h+s -r -h -s
```

3.5.4 Multiple Filenames

Most file processing commands can work with multiple files at one time. To use multiple file names, you simply list the files one after another on the command line, separated by spaces. You can use wildcards in any or all of the filenames. For example, to copy all <code>.TXT</code> and <code>.DOC</code> files from the current directory to drive <code>A</code>, you could use this command:

```
copy *.txt *.doc a:
```

If the files you want to work with are not in the default directory, you must include the full path with each filename:

```
copy a:\details\file1.txt a:\details\file1.doc c:
```

Multiple filenames are handy when you want to work with a group of files which cannot be defined with a single filename and wildcards. They let you be very specific about which files you want to work with in a command.

When you use multiple filenames with a command that expects both a source and a destination, like COPY 182 or MOVE 274, be sure that you always include a specific destination on the command line. If you don't, the command will assume that the last filename is the destination and may overwrite important files.

Like <u>extended wildcards</u> and <u>include lists</u>, multiple filenames will work with internal commands but not with external programs, unless those programs have been written to handle multiple file names on the command line.

If you have a list of files to process that's too long to put on the command line or too time-consuming to type, see <u>@File Lists</u> as well as the <u>DO [210]</u>, <u>FOR [234]</u> and <u>SELECT [312]</u> commands for other ways of passing multiple file names to a command.

3.5.5 Include Lists

Any internal command that accepts multiple filenames are will also accept one or more include lists. An include list is simply a group of filenames, with or without wildcards, separated by semicolons [;]. Only the first entry in each include list may specify a path. All files an include list must be in the same directory. You may not add a space on either side of the semicolon. See the rule below to determine when a semicolon is part of a file name and when it is an include list separator.

For example, you can shorten this command which uses multiple file names:

```
copy a:\details\file1.txt a:\details\file1.doc c:
```

to this using an include list:

```
copy a:\details\file1.txt;file1.doc c:
```

Include lists are similar to multiple filenames, but have three important differences.

- First, you don't have to repeat the path to your files if you use an include list, because all of the included files must be in the same directory.
- Second, if you use include lists, you aren't as likely to accidentally overwrite files if you forget a destination path for commands like COPY list, and won't be seen as the destination file name. Include lists can only be used as the source parameter the location files are coming from for COPY list and other similar commands. They cannot be used to specify a destination for files.
- Third, multiple filenames and include lists are processed differently by the DIR 198 and SELECT commands. If you use multiple filenames, all of the files matching the first filename are processed, then all of the files matching the second name, and so on. When you use an include list, all files that match any entry in the include list are processed together, and will appear together in the directory display or SELECT 1912 list. You can see this difference clearly if you experiment with both techniques and the DIR 198 command. For example,

```
dir \doc\*.txt *.doc
```

will list all the .TXT files in directory $\DOC\$ with a directory header, the file list, and a summary of the total number of files and bytes used. Then it will do the same for the .DOC files in the current directory. However,

```
dir \doc\*.txt;*.doc
```

will display all the .TXT and .DOC files in directory \DOC\ in one list.

Like <u>extended wildcards</u> and <u>multiple filenames</u>, include lists work with internal commands, but not with external programs (unless they have been programmed especially to support them).

The maximum length of an include list is 2,047 characters (same as the maximum length of a single file name).

Semicolons in filenames

Since a semicolon (";") is a valid (albeit unfortunate) character in a file name, you must quote any such name if you don't want **TCC** to treat it as an include list.

If a filename parameter includes a semicolon, **TCC** first attempts to find a filename containing an embedded semicolon. If found, that filename is used. If no file is found, the semicolon is considered to be an include list separator.

See also: Exclusion Ranges 85.

3.5.6 Delayed Variable Expansion

Some of the internal commands (COPY 182), MOVE 274), PDIR 288), REN 305) support delayed variable expansion for the target filename. The function argument must be an asterisk (*), which will be replaced by the name of each matching source file. The variable function name must be preceded by two %%'s; the first one will be removed before the command is called, and the second when the command calls the variable expansion routine. This allows much greater flexibility in building the target filenames.

For example, to copy all of your *.MP3 files, and append the string "_saved" to the filename part:

```
copy *.mp3 %%@name[*] saved.mp3
```

3.5.7 LFN File Searches

There are some special considerations applicable to volumes which support long file names (including VFAT, FAT32, and NTFS volumes). All files on such volumes have a short (FAT-compatible 8.3) file name (SFN). A file which was created (or renamed to) a name which contains lower case letters or other characters not compatible with SFNs, or a name longer than 8 characters, or an extension longer than 3 characters, or more than one period (.) in its name will have both the long file name state of (LFN) specified, and an SFN automatically generated by the file system. The SFN associated with an LFN may change when the file is moved or copied even when the LFN is not changed.

When *CMD.EXE* performs a wildcard search, it searches for both forms of each file name. The long filenames are checked first, followed by the short file names. Matching files which have only a short filename will be found during the first search, because in that case the file system treats the SFN name as if it were a LFN.

For example, suppose you have two files in a directory with these names:

Long NameShort NameLetter Home.DOCLETTER~1.DOCLetter02.DOCLETTER02.DOC

A search for *LETTER??.DOC* will find both files. The second file (*Letter02.DOC*) will be found during the search of long filenames. The first file (*Letter Home.DOC*) will be found during the search of short filenames but will return LFN.

Because this dual search can result in some very unexpected or even disastrous results, *TCC* defaults to searching only for the LFN. You can change the default with the **Search for SFNs** option in the OPTION / Startup dialog.

Take extra care when you use wildcards to perform operations on LFN volumes if you have set **Search for SFNs**, because you may select more files than you intended. For example, Windows often generates short filenames that end with ~1, ~2, etc. If you use a command such as:

del *1.*

you will delete all such files, including most files with long filenames, which is probably not the result you intended!

3.5.8 File Lists

Many internal commands allow you to specify a file containing a list of all of the files you want to process in the command line (instead of enumerating them individually). You specify that a file is a file list by prefixing its name with the @ sign, e.g., LIST 264 @XXX specifies that LIST 264 is to operate on the files listed in the file XXX instead of on XXX itself.

A file list is simply a standard text file state containing the names of the files to process, one per line. This allows you to create a list of files for processing using output from DIR state of JR DIR st

Commands supporting the @File syntax include:

ATTRIB 163	FOR 234	SYNC 336
COPY 182	HEAD 249	TAIL 339
DEL / ERASE 190	LIST 264	TOUCH 349
DESCRIBE 195	MOVE 274	TYPE 354
DO 210	RD / RMDIR 301	
EXCEPT 225	REN / RENAME 305	

To use a file list, precede its name with an @ sign in the command. For example, to copy all of the files listed in MYLIST.TXT to D:\SAVE\:

```
copy @mylist.txt d:\save\
```

If you use a drive and/or path specification the @ sign can appear before the path or before the file name. For example, these are equivalent:

```
copy @e:\lists\mylist.txt d:\save\
copy e:\lists\@mylist.txt d:\save\
```

To use appropriately formatted data on the Windows clipboard as an catalog file use **@CLIP**: as the file name, for example:

```
copy @clip: d:\save\
```

@File Lists and "@" Signs in File Names

Note that the @ sign is a rarely used, but legal filename character in Windows. If a file whose name begins with @ exists and you attempt to use an @file list with the same name, the file whose name begins with @ will take precedence. For example, if c:\ contains both a file named @MYLIST.TXT and another named MYLIST.TXT, this command:

```
[c:\] copy @mylist.txt d:\save\
```

will copy the single file @MYLIST.TXT to D:\SAVE\, and will not process the list of files in MYLIST.TXT . To avoid this confusion, use a different name for one of the files.

3.5.9 Switches for File Selection

Many of the file processing commands (<u>ATTRIB</u> 163), <u>COPY</u> 182), <u>DEL</u> 190), <u>DESCRIBE</u> 195, <u>MOVE</u> 274), <u>REN</u> 305), <u>TYPE</u> 354), etc.) support several standard switches for selecting files to process. Be sure to see the individual commands for details on which switches are supported for each command and how they work, and for additional switches specific to each command. Make sure that any <u>range</u> 80° selections precede the options below in the command line.

The common file selection switches include:

/A:[[-+]rhsadecijSelect files based on their attributes, for example /A:RH selects files which have the read-only and hidden attributes set. See Attribute Switches see File Attributes for more information on attributes.
 /N Don't actually process any files. This allows you to test what the results of a command would be, without actually performing the operation.
 /P Process files in the current directory and all of its subdirectories.

3.6 Executable Extensions

Normally, when you type a filename (as opposed to an alias or internal command name) as the first word on the command line, *TCC* looks for a file with that name to execute.

The file's extension may be .EXE or .COM to indicate that it contains a program; .PIF or .LNK to indicate that it contains information on how to execute a program under Windows; or .BTM, .BAT, or .CMD to indicate a batch file. 130

You can add to the default list of extensions, and have *TCC* take the action you want with files that are not executable programs or batch files. The action taken is always based on the file's extension. For example, you could start your text editor whenever you type the name of a *.DOC* file, or start your database manager whenever you type the name of a *.DAT* file.

Windows also includes the ability to associate file extensions with specific applications. See Windows File Associations on this feature and its relationship to executable extensions. See also: Executable Files and File Searches 504).

You use environment variables to define the internal command, external program, batch file, or alias to run for each defined file extension. To create an executable extension for use only in *TCC*, use the SET 319 command to create a new environment variable. An environment variable is recognized as an executable extension if its name begins with a period.

The syntax for creating an executable extension is:

```
set .ext[;.ext[;...]]=command [options]
```

where •EXT is the executable file extension; *command* is the name of the internal command, alias, external program, or batch file to run; and **[options]** are any command line startup options you want to specify for the program, batch file, or alias. You can specify multiple extensions for a single command by separating them with semicolons.

For example, if you want to run a word processor called *EDITOR* whenever you type the name of a file that has an extension of *.EDT*, you could use this command:

```
set .edt=c:\edit\editor.exe
```

If the command specified in an executable extension is a batch file or external program, *TCC* will search the PATH search for it if necessary. However, you can make sure that the correct program or batch file is used, and speed up the executable extension, by specifying the full name including drive, path, filename, and extension. You can utilize other environment variables in the specification.

Once an executable extension is defined, any time you name a file with that extension as a command, it is equivalent to having typed the value of the extension variable, followed by the name of the file.

The next example defines WORDPAD.EXE (a Windows editor) as the processor for .TXT files:

```
set .txt="c:\program files\accessories\wordpad.exe"
```

Now, if you have a file called HELLO.TXT and enter the command

hello

TCC will execute the command:

```
"c:\program files\accessories\wordpad.exe" c:\source\hello.txt
```

Notice that the full pathname of <code>HELLO.TXT</code> is automatically included. If you enter parameters on the command line, they are appended to the end of the command. For example, if you changed the above entry to:

```
[c:\source] hello -w
```

TCC would execute the command:

```
"c:\program files\accessories\wordpad.exe" c:\source\hello.txt -w
```

In order for executable extensions to work, the command, program, batch file, or alias must be able to interpret the command line properly. For example, if a program you want to run doesn't accept a file name on its command line as shown in these examples, then executable extensions won't work with that program.

Executable extensions may include wildcards T, so you could, for example, run your text editor for any file with an extension beginning with T by defining an executable extension called T. Extended wildcards (e.g., **DO[CT]** for DOC and DOT files) may also be used.

To remove an executable extension, use UNSET (357) to remove the corresponding variable.

3.7 Using Internet URLs

If you type an Internet URL (Uniform Resource Locator) which begins with **http:** or **https:** at the prompt, **TCC** will pass the URL to Windows. Normally Windows will start your web browser, and request that the browser retrieve the page pointed to by the URL. This feature will only work if Windows can find the proper association between the **http:** or **https:** prefix and the browser software. While this association is standard for most browser installations, it may not be present on all systems.

The ability to "start" URLs in this way is restricted to those beginning with **http:** or **https:**. Other standard prefixes such as **ftp:**, **mail:**, and **news:** cannot be started directly from the prompt; you must enter these URLs directly into your browser.

See Waiting for Applications to Finish 123 for information on problems with waiting for the browser to

finish after starting a URL.

3.8 Using FTP and HTTP Servers

TCC allows direct access to remote servers from internal commands such as COPY 1821, DEL 1901, DIR 1981, MOVE 2741, MD 2711, RD 3011, REN 3051, and SELECT 3121 via several protocols:

- FTP 93 (basic FTP)
- TFTP 96 (Trivial FTP)
- FTPS (SSL FTP)
- HTTP 96 (basic Web access)
- ▶ HTTPS 96 (SSL HTTP)

Note: Not all protocols are supported in every internal command. For example, DIR will not work with HTTP or HTTPS (because of limitations in the HTTP / HTTPS protocol).

• FTP support:

The basic filename syntax for anonymous connections is:

```
ftp://ftp.abc.com/...
```

For example, to get a directory of the JP Software FTP site, you could use this command:

```
Dir ftp://jpsoft.com/*
```

If you don't specify a username and password, *TCC* will look for your FTP user names and passwords in the file *FTP.CFG* (which defaults to the *Take Command* directory). You can specify another directory with the FTP.CFG configuration option. You must add entries to the *FTP.CFG* file manually. The format for each line is:

```
url username [(alias)] password [directory template]
```

For example:

```
ftp://jpsoft.com fred secret
ftp://microsoft.com anyone mypassword
```

You can have multiple users for a single FTP site (for example, an admin user and and a normal user). You need to ad an alias (enclosed in parentheses) following the name of the ftp site. For example:

```
ftp://jpsoft.com (jpadmin) Bob AdminPassword ftp://jpsoft.com (jppublic) anonymous Bob@jpsoft.com
```

You can then access the server as ftp://jpadmin or ftp://jppublic.

We recommend you encrypt this file if you're using NTFS. If *FTP.CFG* doesn't exist the first time *TCC* looks for it, it will be created as an encrypted file (NTFS only). **Note**: If you are using FAT / VFAT, the file will not be encrypted and your user names and passwords will be unprotected in plain text.

You can also specify an explicit username and password on the command line:

```
ftp://[username:password@]ftp.abc.com/...
```

If you have FTP permission on server ftp.abc.com and a subdirectory of the root directory on that

server is called *mydir*, you can display the files with this command (enter this on one line):

```
dir ftp://username:password@ftp.abc.com/mydir/*
```

You can also use the internal IFTP [255] command to start an FTP session with a server and then use a simplified syntax to manipulate files on the server.

TCC also supports symbolic hostnames (defined in \windows\system32\drivers\etc\hosts).

TCC normally connects to the FTP server on the default FTP port 21. If the FTP server you are connecting to uses a non-standard port, enter the port number (with a preceding colon) just after the server name, for example:

```
dir ftp://username:password@ftp.abc.com:8765/mydir/*
```

To log on to a server which supports "anonymous" logins, enter the required user name (usually "anonymous") and password (usually your email address) using the syntax shown above, for example:

```
dir ftp://anonymous:email@domain.com@jpsoft.com/
```

TCC will distinguish between the @ in the email address and the @ before the server name in order to separate the parts of the URL properly.

If you use a partial file or path reference, such as

```
dir ftp:myfile.txt
```

TCC will attempt to build a fully qualified directory name in which to find the requested file or path, based on what the server reports as the current working directory. If an ftp file or path specification begins with a ~ (tilde, typically indicative of a path relative to the user's home directory), **TCC** will instead pass the exact string directly to the remote server.

TCC uses standard FTP commands to retrieve information about files and directories and manipulate those files and directories on FTP servers, and relies on the server's compliance with Internet FTP standards. If your server is not fully compliant, or does not operate in the manner that **TCC** expects, the results may not be what you intend. For example, if the FTP server you are connecting to is case-sensitive, you may have to use the stored case of file and directory names when you use FTP commands. We urge you to test each server you use with nondestructive commands like DIR before you try to copy or delete files, create or remove directories, etc.

Time-related operations (e.g. switches like COPY 182)/C or /U) may not always work reliably on FTP and HTTP servers, due to differences in time zone and in the file time representations between your local system and the server. Be sure to experiment with the particular server in question before depending on commands which compare file times to yield the results you want.

Note: If you use a partial reference such as £tp:mydir outside the scope of an IFTP 255 command, **TCC** will attempt to re-establish the last connection, if any. That new connection may or may not be logged to the last used directory on that sever. We recommend you always use a full reference (including server name) unless you are specifically taking advantage of an active IFTP 255 connection. You can determine if there is an active IFTP 255 connection with the _iftp 388 and _iftps 388 variables.

Before you can use the built-in FTP support or the IFTP 255 command, you must establish the necessary connection to the Internet. For example, if you use Windows Dial-Up Networking to connect to the Internet, you must start your dial up connection first. If you connect through a proxy server, you must set the Proxy 53 configuration options.

Non-standard FTP servers:

TCC supports directory formats for the following:

EPLF WFTP VMS (single-line filenames only) NetPresenz (Macintosh) Netware All known UNIX and Linux formats Windows FTP Server

If you have a non-standard FTP server that creates an unusual directory format, you can create an entry in your *FTP.CFG* file to allow *TCC* to parse the FTP server output. The format is described in the FTP.CFG following the host name, username, and password. The format characters are:

I"text" Do a wildcard comparison of "text" and the directory line; if it matches, discard the entire line. (This is to allow you to skip header & footer lines that would otherwise return garbage.)

"text" Compare (and skip) a literal string (does NOT support wildcard searches)

<space> Skip whitespace (spaces, tabs)

- ! Skip non-whitespace
- Ignore a single character
- Filename. If the F is followed by a . (i.e., "F."), the extension is the next non-whitespace string. The extension will be appended (preceded by a '.') to the filename.
- Subdirectory flag. If the S is followed by a =, the next character is the character in a "raw" directory listing that denotes a directory. If you don't specify a =, 'D' is assumed.
- T Month as a string (i.e., "Jan", "Feb", etc.)
- **U Linux**-style year (2004) or time (18:30) in the same field.
- Y Year
- M Month
- **D** Day
- **h** Hour
- m Minute
- **H** a or p (for am/pm)
- **Z** File size. If the Z is followed by a =, the number following that is the block size.

(Note that upper/lower case is significant for the format characters.)

For example, the FTP.CFG entry for JPSOFT.COM can be described as:

jpsoft.com,anonymous,JPUser@,S!!!ZTDUF

• TFTP ("trivial FTP") support:

See the FTP 33 section above for general notes and requirements.

TFTP is only available with COPY (and with MOVE 274) when the source is a local file). The syntax is:

```
tftp://server[:port]/filename
```

For example:

```
copy update tftp://190.189.188.0/update
```

• HTTP ("basic Web") support:

See the FTP 33 section above for general notes and requirements.

The **HTTP** syntax is:

```
http://[user:password@]server[:port]/filename
```

For example:

```
copy http://jpsoft.com/
```

• FTPS ("SSL FTP") support:

See the FTP 33 section above for general notes and requirements.

The **FTPS** syntax is:

```
ftps://[user:password@]server[:port]/filename
```

For example:

```
copy ftps://jpsoft.com/tcmd/tcmd.exe
```

• HTTPS ("SSL HTTP") support:

See the FTP 93 section above for general syntax and requirements.

The **HTTPS** syntax is:

```
https://[user:password@]server/filename
```

For example:

```
copy https://jpsoft.com/xyz.htm
```

3.9 Input / Output Redirection

This section covers features to change how *TCC* and some application programs handle input and output.

Internal commands and some external programs get their input from the computer's standard input device and send their output to the standard output device. Some programs, including *TCC*, also send special messages to the standard error device. Normally, the keyboard is used for standard input and the video display for both standard output and standard error, but you can temporarily change these assignments for special tasks.

For example, suppose you want a printed list of the files in a directory. If you change the standard output to the printer and issue a DIR 1981 command, the task is easy. DIR's output goes to the standard output device, and you have redirected standard output to the printer, so the DIR command prints filenames instead of displaying them on the screen. You can just as easily send the output of DIR (or any other command) to a file or a serial port.

We offer three methods of manipulating input and output: Redirection, Piping, All three are explained in this section. In addition, TCC supports a subset of ANSI X3.64 control sequences in displayed text. The last topic in this section explains ANSI X3.64 support on in detail.

Redirection and piping affect the standard input, standard output, and standard error devices. They do not work with application programs which read the keyboard hardware directly, or which write directly to the display. Because most Windows applications fall into that category, you will find that redirection and piping are most useful when they are combined with internal commands.

The TEE 344 and Y 364 commands are "pipe fittings" which add more flexibility to pipes.

- Redirection and Piping 97
- ANSI X3.64 Support 101
- Keystack 102
- Page and File Prompts 102

3.9.1 Redirection and Piping

This section covers redirection and piping. You can use these features to change how *TCC* and some application programs handle input and output.

Internal commands and some external programs get their input from the computer's standard input device and send their output to the standard output device. Some programs also send special messages to the standard error device. Normally, the keyboard is used for standard input and the video screen for both standard output and standard error, but you can temporarily change these assignments for special tasks.

For example, suppose you want a printed list of the files in a directory. If you change the standard output to the printer and issue a DIR scommand, the task is easy. DIR scompared is output goes to the standard output device, and you have redirected standard output to the printer, so the DIR scommand prints filenames instead of displaying them on the screen. You can just as easily send the output of DIR scompared in the printer of the p

Redirection and piping affect the standard input, standard output, and standard error devices. They do not work with application programs which read the keyboard hardware directly, or which write directly to the screen. Because most Windows applications fall into that category, you will find that redirection and piping are most useful when they are combined with internal commands.

The TEE 344 and Y 364 commands are "pipe fittings" which add more flexibility to pipes.

3.9.1.1 Redirection

Redirection can be used to reassign the standard input (stdin [535]), standard output (stdout [535]), and standard error (stderr [535]) devices from their default settings (the keyboard and screen) to another device such as the printer or serial port, to a file, or to the Windows clipboard. You must use some discretion when you use redirection with a device. There is no way to get input from the printer, for example.

Redirection always applies to a specific command, and lasts only for the duration of that command. When the command is finished, the assignments for standard input, standard output, and standard error revert to whatever they were before the command.

In the descriptions below, *filename* means either the name of a file or of an appropriate device (**COM***n* for serial ports; **CON** for the keyboard and screen; **CLIP:** for the clipboard; **NUL** for the "null" device, etc.).

Here are the standard redirection options supported by **TCC** (see below for additional redirection options using numeric file handles):

- Input redirection 98
- Output redirection 98
- Special considerations for specific commands 99
- NoClobber 99
- Multiple redirections 99
- Creating an empty file 99
- Redirection by handle 99
- ▶ "Here-document" redirection 100

Input redirection

< filename To get input from a file or device instead of from the keyboard.

Output redirection

		overwrite		append
standard output	>	filename	>>	filename
standard error	>&>	filename	>>&>	filename
merge standard output and standard error	>&	filename	>>&	filename

To use redirection, place the redirection symbol and *filename* at the end of the command line, after the command name and any parameters. For example, to redirect the output of the <u>DIR</u> ommand to a file called *DIRLIST*, you could use a command line like this:

```
dir /b *.dat > dirlist
```

You can use any combination of input and output redirection for the same command, as appropriate for your purpose. For example, this command sends input to the external program **SORT** from the file *DIRLIST*, and sends output from **SORT** to the file *DIRLIST.SRT*:

```
sort < dirlist > dirlist.srt
```

You can redirect text to or from the Windows clipboard by using the pseudo-device name CLIP: (the colon is required).

If you redirect the output of a single internal command like <u>DIR [198]</u>, the redirection ends automatically when that command is done. If you start a batch file with redirection, all of the batch file's output is

redirected, and redirection ends when the batch file is done. Similarly, if you use redirection after the closing parenthesis of a <u>command group</u> (e.g., ...) > *report*), all of the output from the command group is redirected, and redirection ends when the command group is done.

Special considerations for specific commands

You cannot redirect all output from the execution of a DO [210] loop due to the restriction that the DO [210] command and its matching ENDDO [210] may not be part of a command group.

To redirect the output of a <u>TEXT</u> 345 command, append the redirection syntax to the <u>TEXT</u> 345 command.

When you execute a FOR 234 or GLOBAL 245 command, redirection is separately performed for each iteration, based on the directory current for that iteration. This can result in repeated overwriting of the output file, or the creation of a separate output file in each directory. To generate a single, cumulative output file, use Command Grouping 121 as in the example below:

```
( for /r %f in (*.btm) echo %@full[%f] ) > c: \temp\btmlst
```

NoClobber

When output is directed to a file with >, >&, or >&>, and that file already exists, it will be overwritten. You can protect existing files by using the <u>SETDOS</u> | 323 /N1 command, the **Protect redirected output files** setting on the <u>Startup tab</u> | 47 of the configuration dialogs, or the <u>Protect redirected output file</u> | 47 option.

When output is appended to a file with >>, >>&, or >>&>, the file will be created if it doesn't already exist. However, if the NoClobber mode is set as described above, append redirection will not create a new file; instead, if the output file does not exist a "File not found" or similar error will be displayed.

You can temporarily override the current setting of NoClobber by using an exclamation mark [!] after the redirection symbol. For example, to redirect the output of DIR to the file *DIROUT*, and allow overwriting of any existing file despite the NoClobber setting:

```
dir >! dirout
```

Multiple redirections

Redirection is fully nestable. For example, you can invoke a batch file and redirect all of its output to a file or device. Output redirection on a command within the batch file will take effect for that command only; when the command is completed, output will revert to the redirected output file or device in use for the batch file as a whole.

Creating an empty file

You can use redirection to create an empty (zero-byte) file. To do so, enter **>filename** as a command, with no actual command before the **>** character. If you have enabled Protect redirected output file 47, use **>!filename**.

Redirection by handle

In addition to the redirection options above, **TCC** also supports the **CMD.EXE** syntax:

n>file Redirect handle n to the named file n>em Redirect handle n to the same place as handle m

Warning: You may not put any spaces between the n and the >, or between the >, &, and m in the second form. The values of n and m must be single decimal digits, and represent file handles. Windows defines 0, 1, and 2 as shown in the table below.

Handle	Assignment
0	standard input
1	standard output
2	standard error

The *n>file* syntax redirects output from handle *n* to *file*. You can use this form to redirect two handles to different places. For example:

```
dir > outfile 2> errfile
```

sends normal output to a file called OUTFILE and any error messages to a file called ERRFILE.

The $n>\infty m$ syntax redirects handle n to the same destination as the previously assigned handle m. For example, to send standard error to the same file as standard output, you could use this command:

```
dir > outfile 2>&1
```

Notice that you can perform the same operations by using standard redirection features. The two examples above could be written as

```
dir > outfile >&> errfile
and
  dir >& outfile
```

"Here-document" redirection

Wherever input redirection is supported, you can use a Linux-like "here-document" approach. The syntax is:

```
program << word
```

The current batch file is read up to the next occurrence of **word**, and the resulting text becomes standard input to **program**. For example:

```
c:\test\program.exe << endinput
input 1
input 2
input 3
endinput
echo This is the next line after "program.exe"</pre>
```

Special features of "here document":

- If the << is followed by a hyphen (-), the leading white space on the following lines will be removed before passing them to **program** (i.e. they will be effectively left-justified).
- The parser will perform variable expansion on each line, unless the word following << is
 enclosed in double quotes.

3.9.1.2 Piping

Piping is a special form of redirection, using an additional instance of **TCC** for each instance of the **piping** specified in the command line.

You can create a **pipe** to send the *standard output* of a command (command1) to the *standard input* of another command (command2), and optionally also send the *standard error* as well:

what is sent to pipe	command format
standard output only	command1 command2
merge standard output and standard error	command1 & command2

For example, to take the output of the ALIAS sommand (which displays a list of your aliases and their values) and pipe it to the external SORT utility to generate a sorted list, you would use the command:

```
alias | sort
```

To do the same thing and then pipe the sorted list to the internal \underline{LIST}_{264} command for full-screen viewing:

```
alias | sort | list /s
```

The TEE 344 and Y 364 commands are "pipe fittings" which add more flexibility to pipes.

Like redirection, pipes are fully nestable. For example, you can invoke a batch file and send all of its output to another command with a pipe. A pipe on a command within the batch file will take effect for that command only; when the command is completed, output will revert to the pipe in use for the batch file as a whole. You may also have 2 or more pipes operating simultaneously if, for example, you have the pipes running in different windows or processes.

Processing each line received from a pipe

To process each line of text sent by the left side of a pipe in *TCC*, you may use the syntax below:

```
dir | for %file in (@CON:) command %file
```

This example shows how to pass each line of piped data to a *command*.

WARNINGS: *TCC* implements pipes by starting a new process for the receiving program. This process goes through the standard secondary shell start-up procedure, including execution of the TCSTART [22] file, for EACH receiving program. All of the sending and receiving programs run concurrently; the sending program writes to the pipe and the receiving program reads from the pipe. When the receiving program finds an End of File signal, it finishes reading and processing the piped data, and terminates. When you use pipes with *TCC*, make sure you consider the possible consequences from using a separate process to run the receiving program, especially that it cannot create/modify/delete environment variables of the sending program, and inclusion of a command to change directories in the TCSTART [22] file may cause the new process to execute in a different directory. When you use more than one pipe in a single command, e..g. the second example above with LIST [264], each pipe adds another instance of *TCC*.

3.9.2 **ANSI X3.64 Support**

There is no support for ANSI X3.64 in Windows. For this reason, *TCC* contains its own limited ANSI X3.64 support (key substitutions are not supported, nor are double-width or double-height characters, or blinking characters). *TCC* interprets only its own output, not the output of external. In some cases

you can redirect the output of an application program to a temporary file, then send it through *TCC* ANSI X3.64 interpreter, e.g., by using the <u>TYPE</u> solution. This will display ANSI X3.64 correctly, but will not work with an interactive application.

To utilize the *TCC* built-in ANSI X3.64 support you must enable it from the <u>Windows tab</u> of the <u>configuration dialogs</u> 46, or with the <u>SETDOS</u> 323 /A command. You can determine whether or not <u>ANSI X3.64</u> support is enabled with the <u>ANSI</u> 382 internal variable.

Several commands in *TCC* provide alternatives for ANSI X3.64 commands. For example, there are commands to set the screen colors and display text in specific colors and locations. These commands are easier to understand and use than the ANSI X3.64 control sequences.

For information on the specific ANSI X3.64 commands supported by *TCC* see the ANSI X3.64 Command Reference 516.

3.9.3 Keystack

The KEYSTACK 2621 command overcomes two weaknesses of input redirection:

1) some programs ignore standard input and read the keyboard through Windows APIs, and

2) input redirection doesn't end until the program or command terminates. You can't, for example, use redirection to send the first few commands to a program and then type the rest of the commands yourself. But KEYSTACK 262 lets you do exactly that.

KEYSTACK 262 sends keystrokes to an application program. Once the KEYSTACK 262 buffer is empty, the program will receive the rest of its input from the keyboard. KEYSTACK 262 is useful when you want a program to take certain actions automatically when it starts. It is most often used in batch files and aliases.

To place the letters, digits, and punctuation marks you would normally type for your program into the KEYSTACK 262 buffer, enclose them in double quotes:

```
keystack "myfile"
```

Many other keys can be entered into the Keystack using their names. This example puts the **F1** key followed by the **Enter** key in the KEYSTACK [262]:

```
keystack F1 Enter
```

See <u>Keys and Key names [515]</u> for details on how key names are entered. See the <u>KEYSTACK [262]</u> command for information on using numeric key values along with or instead of key names, and other details about using the Keystack.

You must activate the window for the program that will receive the characters before you place them into the Keystack. See KEYSTACK [262] for additional details; see ACTIVATE [152] for information on activating a specific window.

3.9.4 Page and File Prompts

Page Prompts

Several *TCC* commands can generate prompts, which wait for you to press a key to view a new page or to perform a file activity. When *TCC* is displaying information in page mode, for example with a DIR 1981 /P or SET 1919 /P command, it displays the message

Press Esc to Quit or any other key to continue...

At this prompt, you can press **Esc**, **Ctrl-C**, or **Ctrl- Break** if you want to quit the command. You can press almost any other key to continue with the command and see the next page of information.

File Prompts

During file processing, if you have activated prompting with a command such as DEL 190 /P, you will see a prompt similar to the following before processing every file:

Y/N/A/R?

You can answer this prompt by pressing

Υ	Yes	process this file
N	No	do not process this file
Α	All	remaining files without further prompting
R	Remaining	files without further prompting

The **R** and **A** responses are equivalent; **A** was added for compatibility with **CMD.EXE** versions which display a **Yes/No/All** prompt . You can also press **Esc**, **Ctrl-C**, or **Ctrl-Break** at this prompt to cancel the remainder of the command.

If you press **Ctrl-C** or **Ctrl-Break** while a batch file is running, you will see a **Cancel batch job** prompt. For information on responses to this prompt see Interrupting a Batch File [137].

3.10 OpenAFS

TCC has built-in support for OpenAFS. The parser will recognize Linux-style AFS names (i.e., **/afs/athena/user**) and convert them to Windows-compatible names (i.e., **/afs/athena/user**). (It will also check for custom AFS mount points, and use that name instead of **afs**.)

See http://www.openafs.org for more information on OpenAFS.

3.11 The TCC (4NT) Command Line

A *TCC* window displays a prompt when it is waiting for you to enter a command. The actual text depends on the current drive and directory as well as your PROMPT [297] settings. (The default will look something like [c:\]). This is called the command line and the prompt is asking you to enter a command.

This section explains the features that will help you while you are entering commands, how keystrokes are interpreted when you enter them at the command line, and how to transfer text between *TCC* and other applications.

The keystrokes discussed here are the ones normally used by *TCC*. If you prefer using different keystrokes to perform these functions, you can assign new ones with key mapping directives 28.

Some of the command line features documented in this section are:

- ▶ Command Line Editing 104
- Command History and Recall 106
- Command History Window 107
- Command Names and Parameters 109
- Filename Completion 113

- ▶ Filename Completion Window 116
- Variable Completion 119
- Automatic Directory Changes 76
- Directory History Window 118
- Multiple Commands 120
- Expanding and Disabling Aliases 120
- ▶ Command Line Length Limits 126
- Command Grouping 121
- Starting Applications 122
- ▶ Command Parsing 124
- Date Formats 127

Additional command line features are documented under <u>File Selection</u> 77 and under <u>Directory</u> Navigation 71.

3.11.1 Command Line Editing

The command line works like a single-line word processor, allowing you to edit any part of the command at any time before you press Enter to execute it (or Esc 31) to erase it).

The command line as typed can contain up to a maximum of 32,767 characters, and it can expand to a maximum of 65,535 characters after variable, function and alias substitution. See Command Line Length Limits (126).

You can use the following editing keys (among others) when you are typing a command (the words **Ctrl** and **Shift** mean to press the *Ctrl* or *Shift* key together with the other key named). The keystrokes listed here are the default values, but most editing keys can be redefined via Command Line Editing Keys 32 or General Input Keys 29 directives.

Cursor Movement Keys:

Left 31 Move the cursor left one character.

Right 32 Move the cursor right one character.

Ctrl-Left 32 Move the cursor left one word.

Ctrl-Right 32 Move the cursor right one word.

Home 29 Move the cursor to the beginning of the command.

End 31 Move the cursor to the end of the command.

Insert and Delete Keys:

Toggle between insert and overstrike mode (cursor shape indicates mode).

Del 30

Delete the character under (or to the right of) the cursor, or the highlighted

text.

Bksp 29 Delete the character to the left of the cursor, or the highlighted text.

Ctrl-L 30 Delete the word or partial word to the left of the cursor.

Ctrl-R 30 or Ctrl-Bksp Delete the word or partial word to the right of the cursor.

Ctrl-Home 30 Delete from the beginning of the line to the cursor.

Ctrl-End 30 Delete from the cursor to the end of the line.

Esc 31 Delete the entire line.

Ctrl-V 32 Paste the first line of text from the clipboard at the current cursor position.

Ctrl-C Paste all of the text from the clipboard at the current cursor position.

Ctrl-P 35 Paste the last argument from the previous command line.

Ctrl-0 to Ctrl-9 Paste the corresponding argument from the previous command line.

Highlighting:

Shift-Right Highlight character right of cursor and move cursor
Shift-Left Highlight character left of cursor and move cursor
Shift-Home Highlight from cursor to beginning-of-line and move cursor
Shift-End Highlight word right of cursor and move cursor

Ctrl-Shift-Right Highlight word right of cursor and move cursor Ctrl-Shift-Left Highlight word left of cursor and move cursor

Ctrl-Y 29 Copy highlighted text to the clipboard

Execution:

Ctrl-K 36 Save the current command line in the history list without executing it, and

then clear the command line

Ctrl-C or Ctrl-Break Cancel the command line without saving in the history list.

Enter 31 Execute the command line.

Miscellaneous:

Get help for the command (first argument on the line)

Ctrl-F1 34 Get help for the current word.

Ctrl-F 33 Expand an alias.

Ctrl-X 36 Expand an environment variable.
Ctrl-A 35 Toggle between LFN and SFN.

Alt-PgUp, Alt-PgDn, Scroll the window within the console buffer. (Use the cursor pad keys, not

Alt-Home, Alt-End, the numeric keypad keys.)

Alt-Up, Alt-Down

To highlight text on the command line use the mouse or hold down the **Shift** key and use any of the cursor movement keys listed above. You can select a complete word by placing the cursor anywhere in the word and double-clicking with the mouse. Once you have selected or highlighted text on the command line, any new text you type will replace the highlighted text. If you press **Bksp** or **Del** while there is text highlighted on the command line, the highlighted text will be deleted.

While you are working at the prompt you can use the clipboard to copy text between *TCC* and other applications (see <u>Highlighting and Copying Text</u> of for additional details). You can also use <u>Drag and Drop</u> to paste a filename from another application onto the command line.

Most of the command line editing capabilities are also available when you are prompted for a line of input. For example, you can use the command line editing keys when <u>DESCRIBE [195]</u> prompts for a file description, when <u>INPUT [259]</u> prompts for input from an alias or batch file, or when <u>LIST [264]</u> prompts you for a search string.

If you want your input at the command line to be in a different color, you can use the Windows tab of the configuration dialogs 46.

TCC will prompt for additional command line text when you include the escape character as the very last character of a typed command line. The default escape character is the caret "^", but you can also use the symbolic "%=" representation for portability. For example:

```
echo The quick brown fox jumped over the lazy %=
More? sleeping dog. > alphabet
```

Sometimes you may want to enter one of the command line editing keystrokes on the command line instead of performing the key's usual action. For example, suppose you have a program that requires a Ctrl-R character on its command line. Normally you couldn't type this keystroke at the prompt, because it would be interpreted as a "Delete word right" command. To get around this problem, use the special keystroke Alt-255 33. You enter Alt-255 by holding down the Alt key while you type 0255 on the numeric keypad, then releasing the Alt key. This forces *TCC* to interpret the next keystroke

literally and place it on the command line, ignoring any special meaning it would normally have as a command line editing or history keystroke. You can use **Alt-255** to suppress the normal meaning of command line editing keystrokes even if they have been reassigned with key mapping directives and **Alt-255** itself can be reassigned with the CommandEscape configuration option.

Alternative Keyboard Input Method:

The method mentioned above for **Alt-255** can be used to generate other characters. You must use the number keys on the numeric keypad, not the row of keys at the top of your keyboard. When this **Alt + keypad** approach is used in a Unicode environment, **TCC** will assume that a 3-digit decimal value means an ASCII character, while a 4-digit decimal value mean a Unicode glyph. Make sure that your hardware, character set, code page and font all support the desired combination. Use caution with this method if you plan on manipulating the generated character in other Windows components. See the section on ASCII, Key Codes and ANSI X3.64 Commands [510] for some additional information.

3.11.2 Command History and Recall

Each time you execute a command, the entire command line is saved in a command history list. You can display the saved commands, search the list, modify commands, and rerun commands. The command history is available at the command prompt and in a special command history window You can choose to use either a local or global command history.

Command History Keys:

Up	Recall the previous (or most recent) command, or the most recent command that matches a partial command line.
Down	Recall the next (or oldest) command, or the oldest command that matches a partial command line.
PgUp	Display a popup window of the command history (or all entries matching a partial command line).
F3	Fill in the rest of the command line from the previous command, beginning at the current cursor position.
Ctrl-D	Delete the currently displayed history list entry, erase the command line, and display the previous (matching) history list entry.
Ctrl-E	Display the last entry in the history list.
Ctrl-K	Save the current command line in the history list without executing it, and then clear the command line.
Ctrl-Enter	Copy the current command line to the end of the history list even if it has not been altered, then execute it.
@	As the first character in a line: Do not save the current line in the history list when it is executed, nor store it in the CMDLINE (368) environment variable.

Note: The keystrokes shown above are the default values. See Key Mapping Directives for details on how to assign different keystrokes.

The simplest use of the command history list is to repeat a command exactly. For example, you might enter the command

```
dir a:*.wks;*.doc
```

to see some of the files on drive A. You might move some new files to drive A and then want to repeat the DIR of command. Just press **Up** repeatedly to scan back through the history list. When the DIR command appears, press **Enter** to execute it again. You can also view the command history in a window 107.

After you have found a command, you can edit it before pressing **Enter**. You will appreciate this feature when you have to execute a series of commands that differ only slightly from each other. You can also view and manage the command history list with the HISTORY 25th command.

The history list is normally "circular". If you move to the latest command in the list and then press **Up** once more, you'll see the oldest command in the list. Similarly, if you move to the first command in the list and then press **Up** once more, you'll see the last command in the list. You can disable this feature and make command history recall stop at the beginning or end of the list by turning off History Wrap on the "History" tab of the configuration dialog.

You can search the command history list to find a previous command quickly using command completion. Just enter the first few characters of the command you want to find and press **Up**. You only need to enter enough characters to identify the command that you want to find. For example, to find a DIR command, enter DI and then press **Up**. If you press **Up** a second time, you will see the previous command that matches. The system will beep if there are no matching commands. The search process stops as soon as you type one of the editing keys, whether or not the line is changed. At that point, the line you're viewing becomes the new line to match if you press **Up** again.

You can specify the size of the command history list on the **Command Line** tab of the configuration dialog. When the list is full, the oldest commands are discarded to make room for new ones. You can also use the **Minimum Length** option to enable or disable history saves and to specify the shortest command line that will be saved.

You can prevent any command line from being saved in the history by beginning it with an at sign (@) or by including it in the contents of the HistoryExclude 368 variable.

When you execute a command from the history, that command remains in the history list in its original position. The command is not copied to the end of the list (unless you modify it). If you want each command to be copied or moved to the end of the list when it is reexecuted, select Copy to End or Move to End on the "History" tab of the configuration dialogs. If you select either of these options, the list entry identified as "current" (the entry from which commands are retrieved when you press **Ctrl-Up**) is also adjusted to refer to the end of the history list after each recalled command is executed.

Use **F3** when your new command is different from your previous one by just a character or two at the beginning. For example, suppose you want to execute a DIR on several file names then use DEL to delete those same files. After the DIR is complete type DEL and press **F3**; the rest of the command line will be completed for you. Check that it's correct, and then press **Enter** to delete the files. **F3** also retrieves the entire previous command (like **Up**) if nothing has been typed on the line.

Use **Ctrl-E** to "get your bearings" by returning to the end of the list if you've scrolled around so much that you aren't sure where you are any more.

Use **Ctrl-K** to save some work when you've typed a long command and then realize that you weren't quite ready. For example, if you forget to change directories and notice it after a command is typed or mostly typed, but before you press **Enter**, just press **Ctrl-K** to save the command without executing it. Use the CD or CDD command to change to the right directory, press **Up** twice to retrieve the command you saved, make any final changes to it, and press **Enter** to execute it.

Use **Ctrl-Enter** to organize the history list for repetitive tasks. Instead of searching through the command history for the next command in a sequence, you can place all of the necessary commands next to each other and make them easier to repeat.

3.11.3 Command History Window

You can view the command history in a scrollable popup window, and select the command to re-execute or modify from those displayed in the window. The directory history window includes a

toolbar with buttons for editing, deleting, and moving lines.

To activate the command history window press **PgUp** or **PgDn** at the command line. A window will appear in the upper right corner of the screen, with the command you most recently executed marked with a highlight. (If you just finished re-executing a command from the history, then the next command in sequence will be highlighted.)

You can view a "filtered" history window by typing some characters on the command line, then pressing **PgUp** or **PgDn**. Only those commands matching the typed characters will be displayed in the window.

Command History Window Keys:

Up Scroll the display up one line. Down Scroll the display down one line. Left 31^D Scroll the display left 4 columns. Right 32 Scroll the display right 4 columns. PgUp Scroll the display up one page. Scroll the display down one page. PgDn Home Go to the beginning of the list. End Go to the end of the list.

Ctrl-Enter 40 Move the selected line to the command line for editing

Enter 41 Execute the selected line

Ctrl-C
Ctrl-D 40 or Del
Ctrl-E
Ctrl-Up
Ctrl-Up
Ctrl-Up
Ctrl-D 40 or Del
Ctrl-E
Ctrl-Up

Ctrl-Down Move the selected line up one row

Move the selected lien down one row

Esc 31 Close the window without making a selection.

Note: The keystrokes shown above are the default values. See Key Mapping Directives on how to assign different keystrokes.

Once you have selected a command in the history window, press **Enter** or double-click with the mouse to execute it immediately. Press **Ctrl-Enter** or hold down the Ctrl key while you double-click with the mouse to move the line to the prompt for editing (you cannot edit the line directly in the history window).

You can control the position and size of the history window with the corresponding items on the Windows tab (49) of the configuration dialogs (46). You can also change the keys used in the window with key mapping directives (28).

3.11.4 Local and Global History Lists

The command history 25th and directory history 208 can be stored in either local or global lists.

With a local list, any changes made to the history will only affect the current **TCC** tab window. They will not be visible in other tabs or other copies of **TCC**.

With a global list, all *TCC* windows will share the same history, and any changes made to the history in one copy (e.g., by executing commands from the prompt) will affect all other copies. Global lists are the default.

You can control the type of history list with the <u>Local History</u> and <u>Local Directory History</u> options, and with the **/L**, **/LD** and **/LH** options of either the START and command or **TCC**.

If you select a global history list for **TCC**, you can share the history among all **TCC** sessions running concurrently. When you close all of the **TCC** sessions, the memory for the global history list is released, and a new, empty history list is created the next time you start **TCC**.

If you want the histories to be retained in memory even when no *TCC* session is running, see the SHRALIAS command, which retains the global alias, user-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command history, and directory history lists. SHRALIAS super-defined function, command super-define

3.11.5 Command Names & Parameters

When you enter a command you type its name at the prompt, followed by a space and any parameters for the command. For example, all of these could be valid commands:

```
dir
copy file1 file2 d:\
f:\util\mapmem /v
"c:\program files\JPSoft\tcmd9\tcc.exe" /LF
```

The last three commands above include both a command name, and one or more parameters. There are no spaces within the command name (except in quoted file names), but there is a space between the command name and any options or parameters, and there are spaces between the options and parameters.

Some commands may work when options or parameters are entered directly after the command (without an intervening space, $e.g. \, \text{dir}/p$), or when several options or parameters are entered without spaces between them (e.g. $\, \text{dir}/2/p$). A very few older programs may even require this approach. However, leaving out spaces this way is usually technically incorrect, and is not recommended as a general practice, as it may not work for all commands.

If the command name includes a path, the elements must be separated with backslashes (*e.g. F:\UTILWAPMEM*). If you are accustomed to Linux syntax where forward slashes are used in command paths, and want *TCC* to recognize this approach, you can set the <u>Unix/Linux-style Paths</u> option.

For more information on command entry see Multiple Commands and Command Line Length Limits 1261. For details on how *TCC* handles the various elements it finds on the command line see Command Parsing 1241.

3.11.6 Conditional Expressions

The commands DO [210] (when used with the UNTIL or WHILE keyword), IF [253], IFF [254]/ELSEIFF, and the variable function (@IF [439]) evaluate a conditional expression, and perform a different action based on whether or not the expression is TRUE. The SWITCH [335] command tests pairs of values for equality. Most of the examples [113] below use the IF [253] command, but conditional expressions could be used in the other cases above as well.

A conditional expression can be one of the following, as described below:

- relational expression 110
- status test 111
- logical expression 112

Relational Expression

A relational expression compares two character strings, using one of the <u>relational operators [110]</u> in the table below. Each of these two character strings can contain literal text, environment and internal variables, and variable functions, including user defined ones, in any combination. Note that double quotes are significant.

Numeric and String Comparison

When comparing the two character strings, either a numeric or a string comparison will be used. A numeric comparison treats the strings as numeric values and tests them arithmetically. A string comparison treats the strings as text. The parser uses the rules described for the MVIMERIC [45] function to determine whether or not the strings are numeric, and only if both are numeric is a numeric comparison performed. If either value is non-numeric, a string comparison is used. To force a string comparison when both values may be numeric, use double quotes around the values you are testing, as shown below. Because the quote mark is not a numeric character, string comparison is performed. Numeric comparison cannot be forced. To compare hexadecimal numbers numerically, you must convert them to decimal numbers using @CONVERT [413]. This is not necessary if both are the same length - string comparison and numeric comparison yield the same result.

The example below demonstrates the difference between numeric and string comparisons, as shown in the table below. Numerically, 2 is smaller, but as a string it is "larger" because its first digit is larger than the first digit of 19. So the first of these conditions will be true, and the second will be false:

expression	value	comparison type
2 lt 19	true	numeric
"2" lt "19"	false	string

Relational Expression Formats

The format of a relational expression is one of

num1 relational operator num2 string1 relational operator string2

Note: The correct syntax requires a space both before and after **operator** to separate it from its operands. Commonly seen constructs such as %a==b may or may not work depending on the specific parameters, but they are **never** recommended.

Relational Operators

operator	numeric comparison: expression is true	string comparison: expression is true if, when
	if	ignoring character case:
EQ or ==	num1 equals num2	string1 equals string2
NE or !=	num1 does not equal num2	string1 does not equal string2
LT	num1 is less than num2	string1 alphabetically precedes string2
LE	•	string1 alphabetically precedes or is equal to string2
		string1 alphabetically succeeds or is equal to string2
GT	num1 is greater than num2	string1 alphabetically succeeds string2
EQC		string1 is identical to string2, including character case

Case differences are ignored in string comparisons (except by EQC). If two strings begin with the same text but one is shorter, the shorter string is considered to precede (be less than) the longer one. For

example, "a" is less than "abc", and "hello_there" is greater than "hello".

When you compare text strings, you may need to enclose the parameters in double quotes in order to avoid syntax errors which can occur if one of the parameter values is empty (e.g., due to an environment variable which has never been assigned a value). This technique will not work for numeric comparisons, as the quotes will force a string comparison, so with numeric tests you must be sure that all variables are assigned values before the test is done.

In order to maintain compatibility with *CMD.EXE*, *TCC* recognizes the following additional names for conditions:

CMD.EXE	TCC
EQL or EQU	EQ
NEQ	NE
LSS	LT
LEQ GTR	LE
	GT
GEQ	GE

Internal variables [372] and variable functions [395] are very powerful when combined with string and numeric comparisons. They allow you to test the state of your system, the characteristics of a file, date and time information, or the result of a calculation. You may want to review the variables and variable functions when determining the best way to set up a condition test.

Status Test

These conditions test operating system, file system or *TCC* status. In addition to the tests below, there are many internal variables and variable functions which allow you to test the status of many other parts of the system.

In the descriptions below of the various status tests, the status tests are true if and only if the specified condition is true.

DEFINED	variable
---------	----------

If variable exists in the environment, the expression is true. This is equivalent to testing whether or not variable is nonempty.

Note: GOSUB variables 247 and internal variables 372 always fail the DEFINED test.

ERRORLEVEL [relational operator 110] n

This test retrieves the exit code of the preceding external program. By convention, programs return an exit code of 0 when they are successful and a non-zero number to indicate an error. The relational operator in may be any of those listed above (e.g., EQ, GT). If no operator is specified, the default is GE. The comparison is done numerically.

Not all programs return an explicit exit code. For programs which do not, the behavior of ERRORLEVEL is undefined.

EXIST filename

If filename matches a file which exists, the expression is true. You can use wildcards in filename, in which case the expression is true if any file matching the wildcard name exists. filename may include an absolute or relative path.

WARNING: In Windows the expression will be true if there is either a file or a directory named filename. Use ISFILE or ISDIR instead.

The special filename NUL is commonly used in CMD.EXE batch files to test the existence of a directory. The expression exist xxx\NUL is

true only if xxx is a directory.

ISALIAS aliasname If aliasname is defined as an alias, the expression is true.

ISAPP appname If appname matches the name of an application which is currently

running, the expression is true. To match a specific application, you must enter the full pathname of the application. Partial names and wildcards will yield undependable results. Both the short and long filename forms of the name will be checked (see LFN File Searches for details on the correspondence between short and long

filenames).

This test may require DEBUG privilege.

ISDIR path
DIREXIST path

If the directory specified by path exists, the expression is true. Path may be either absolute or relative. DIREXIST may be used as a

synonym for ISDIR.

ISFILE *filename* If filename matches a file which exists, the expression is true. You

can use wildcards in the filename, in which case the expression is true if any file matching the wildcard name exists. ISFILE matches

only files, not directories.

ISFUNCTION *name* If the user-defined function name is loaded, the expression is true.

ISINTERNAL *command* If command is an active internal command, the expression is true.

Commands can be activated and deactivated with the SETDOS 323 /I

command.

ISLABEL *label* If label exists in the current batch file, the expression is true. Labels

may be one or more words long. Note that this test has nothing to do

with disk partition labels.

ISPLUGIN *name* If name is a plugin [293] variable, function, or command, the

expression is true.

ISWINDOW "title" If a window which matches the title exists, the expression is true.

double quotes must be used around the title, which may contain

wildcards and extended wildcards.

PLUGIN *module* If the plugin module is loaded, the expression is true.

Logical Expressions

A logical expression is one of the following:

- a relational expression 110
- a status test
- the unary logical operator **NOT** followed by a logical expression 112
- two logical expression 112's connected by a binary logical operator

Logical operators

operator	type	usage	value is TRUE if
NOT	unary	NOT cond	cond is FALSE.
.AND.	binary	cond1 .AND. cond2	both cond1 and cond2 are TRUE.
.OR.	binary	cond1 .OR. cond2	at least one of cond1 and cond2 is TRUE.

.XOR.	binary	cond1.XOR. o	cond2	one of cond1 and cond2 is TRUE, and the other one is
				FALSE.

This example runs a program called DATALOAD if today is Monday or Tuesday (enter this on one line):

```
if "% dow" == "Mon" .or. "% dow" == "Tue" dataload
```

Test conditions are always scanned from left to right – there is no implied order of precedence, as there is in some programming languages. You can, however, force a specific order of testing by grouping conditions with parentheses, for example (enter this on one line):

```
if (%a == 1 .or. (%b == 2 .and. %c == 3)) echo something
```

Combining logical expressions

Parentheses can be used only when the portion of the **expression** inside the parentheses contains at least one of the binary logical operators .and., .or., or .xor.. Parentheses on a simple expression which does not combine two or more tests will be taken as part of the string to be tested, and will probably make the test fail. For example, the first of these tests is **FALSE**, the second is **TRUE**:

```
(a == a)
(a == a .and. b == b)
```

Parentheses may be nested.

Examples

This batch file fragment runs a program called WEEKLY if today is Monday:

```
if "%_dow" == "mon" weekly
```

This batch file fragment tests for a string value:

```
input "Enter your selection : " %%cmd
if "%cmd" == "WP" goto wordproc
if "%cmd" NE "GRAPHICS" goto badentry
```

This example calls GO.BTM if the first two characters in the file MYFILE are GO:

```
if "%@left[2,%@line[myfile,0]]" == "GO" call go.btm
```

The first batch file fragment below tests for the existence of *A:UAN.DOC* before copying it to drive c (this avoids an error message if the file does not exist):

```
if isfile a:\jan.doc copy a:\jan.doc c:\
```

This example tests the exit code of the previous program and stops all batch file processing if an error occurred:

```
if errorlevel == 0 goto success
echo "External Error - Batch File Ends!"
cancel
```

3.11.7 Filename Completion

Filename completion can help you by filling in a complete file name on the command line when you only remember or want to type part of it. Filename completion can be used at the command line, which

is explained here, and in a filename completion window 116).

Filename Completion Keys:

F8 or **Shift-Tab F9** or **Tab**Get the previous matching filename.
Get the next matching filename.

F10 Keep the current matching filename and display the next

matching name immediately after the current one.

F12 Repeat the filename just returned from an F9 / Tab match.

Ctrl-A Toggle between long and short filename.

Note: The keystrokes shown above are the default values. See Key Mapping Directives for details on how to assign different keystrokes.

For example, if you know the name of a file begins AU but you can't remember the rest of the name, type:

```
copy au
```

and then press the **Tab** key or **F9** key. **TCC** will search the current directory for filenames that begin with AU and insert the first one onto the command line in place of the AU that you typed.

If this is the file that you want, simply complete the command. If **TCC** didn't find the file that you were looking for, press **Tab** or **F9** again to substitute the next filename that match your pattern (in the above example, begins with AU). When there are no more filenames that match your pattern, the system will beep each time you press **Tab** or **F9**.

If you go past the filename that you want, press **Shift-Tab** or **F8** to back up and return to the previous matching filename. After you back up to the first filename, the system will beep each time you press **Shift-Tab** or **F8**.

If you want to enter more than one matching filename on the same command line, press **F10** when each desired name appears. This will keep that name and place the next matching filename after it on the command line. You can then use **Tab** (or **F9**) and **Shift-Tab** (or **F8**) to move through the remaining matching files.

The pattern you use for matching may contain any valid filename characters, as well as wildcard characters and extended wildcards $\neg \tau$. For example, you can copy the first matching .TXT file by typing

```
copy *.txt
```

and then pressing **Tab**.

If you don't specify part of a filename before pressing **Tab**, **TCC** will match all files. For example, if you enter the above command as "**COPY**", without the *.TXT, and then press **Tab**, the first filename in the current directory is displayed. Each time you press **Tab** or **F9** after that, another name from the current directory is displayed, until all filenames have been displayed. **Note:** you must terminate the command (e.g., by space) before file completion becomes available.

If you type a filename without an extension, *TCC* will append * to the name on <u>LFN</u> [53] drives, and *.* on drives which only support short file names [53]. It will also place a * after a partial extension. If you are typing a group of file names in an <u>include list</u> [88], the part of the include list at the cursor will be used as the pattern to match.

When filename completion is used at the start of the command line, it will only match directories,

executable files, and files with executable extensions of his since these are the only file names that it makes sense to use at the start of a command. If a directory is found, a will be appended to it to enable an automatic directory change of his start of the command line, press **Space** before starting to type the name. Filename completion will then match any name, not just directory and executable names. *Note* that you can also "execute" files whose extension has an association in the Windows Registry, but such files are not considered executable by *TCC*, and only the method above using a space will work.

Filename completion occurs in the physical order in which matching filenames are stored in the directory, the same order in which DIR [198] /O:U would list them. That order is determined by the underlying file system.

TCC also supports network server and sharename completion. If the filename begins with \\, the completion routines will enumerate the network resources for matching server and/or share names. You can control the way server name completion functions with the Server Completion option.

Filename completion will search the PATH [286] for an executable filename if you have set the **Search** Path option in the **Command Line** configuration tab, and you are :

- (1) at the beginning of the command line, and
- (2) there are no matching entries in the current directory, and
- (3) the name you are attempting to match doesn't contain a full or partial path specification.

If all three conditions are met, filename completion will return the first matching executable found in the $PATH^{286}$.

If you are on an NTFS drive, you can also complete stream names. For example:

```
copy test:t
```

and then pressing **Tab** will search the file *test* for streams beginning with "t". Note that you cannot complete a filename and a stream name simultaneously (i.e., **t*:t***).

Several topics are related to filename completion. See:

- ▶ Converting Between Long and Short Filenames 117
- Appending Backslashes to Directory Names 117
- Customizing Filename Completion 115
- Filename Completion Window 116
- Variable Name Completion 119

3.11.8 Customizing Filename Completion

You can customize filename completion for any internal or external command or alias. This allows *TCC* to display filenames intelligently based on the command you are entering. For example, you might want to see only .*TXT* files when you use filename completion in the EDIT command.

To customize filename completion you can use the Filename Completion 50 configuration options. You can also use the FILECOMPLETION 308 environment variable. If you use both, the environment variable will override the configuration option. You may find it useful to use the environment variable for experimenting, then create permanent settings with the configuration dialog.

The format for both the environment variable and the directive is:

```
cmd1:ext1 ext2 ...; cmd2: ...
```

where

cmd1 etc. are command names

ext1 etc. are file extensions (which may include wildcards) or one of the following file types:

DIRS Directories
RDONLY Read-only files
HIDDEN Hidden files
SYSTEM System files

ARCHIVE Files modified since the last backup **FILES** Everything that's not a directory

Note that if a file uses one of the reserved file type names shown above as its extension (e.g. xyz. hidden), that file will be treated as if it were of that type.

The command name is the internal command, alias, or executable file name (without a path). For example, to have file completion return only directories for the CD (177) command and only .C and .ASM files for a Windows editor called WinEdit, you would use this setting for filename completion in the configuration dialog:

```
cd:dirs; winedit:c asm
```

To set the same results using the FILECOMPLETION 3681 environment variable:

```
set filecompletion=cd:dirs; winedit:c asm
```

With this setting in effect, if you type "CD" and then pressed **Tab**, **TCC** returns only directories, not files. If you type **WINEDIT** and press **Tab**, you will see only names of .C and .ASM files.

When testing for a customized filename match, *TCC* checks the actual command line you type (but without expanding any aliases). For example, if you use the definition above and have "W" aliased to "WINEDIT" and then enter a "W" command, filename completion — which refers only to "WINEDIT" — will be ignored. To use customized filename completion for aliases you must enter the alias name:

```
FileCompletion=cd:dirs; winedit:c asm; w:c asm
```

3.11.9 Filename Completion Window

You can view matching filenames in a filename completion window. To activate the window, press **F7** or **Ctrl-Tab** at the command line. You will see a popup window, with a sorted list of files that match any partial filename you have entered on the command line. If you haven't yet entered a file name, the window will contain the name of all files in the current directory. You can search for a name by typing the first few characters. See Popup Windows soft for details.

Filename Completion Window Keys:

F7 or Ctrl-Tab 35 (from the command line) Open the window. Up Scroll the display up one line. Down Scroll the display down one line. Left 31 Scroll the display left 4 columns. Right 32 Scroll the display right 4 columns. PgUp Scroll the display up one page. Scroll the display down one page. PgDn Home Go to the beginning of the list. Go to the end of the list. End

Enter or Double Click Insert the selected filename into the command line.

Note: The keystrokes shown above are the default values. See Key Mapping Directives for details on how to assign different keystrokes.

See also: Filename Completion 113

3.11.10 Converting Between Long & Short Filenames

On LFN drives, *TCC* will search for and display long filenames during filename completion. If you want to search for 8.3 short filenames (SFNs), press Ctrl-A before you start using filename completion. This allows you to use filename completion on LFN drives with applications that do not support long filenames. The LFNToggle directive can be used to change the keystroke assigned to this feature.

You can press **Ctrl-A** at any time prior to beginning filename completion. The switch to SFN format remains is in effect for the remainder of the current command line. When **TCC** begins a new command line it returns to long filename format until you press **Ctrl-A** again.

You can also press **Ctrl-A** just after a filename is displayed, and the name will be converted to short filename format. However, this feature only affects the most recently entered file or directory name (the part between the cursor and the last backslash [\] on the command line), and any subsequent entries. It will not automatically convert all the parts of a previously entered path.

Ctrl-A toggles the filename completion mode, so you can switch back and forth between long and short filename displays by pressing **Ctrl-A** each time you want to change modes.

3.11.11 Appending Backslashes to Directory Names

If you set the **Add \ to Directories** option in the Command Line tab of the configuration dialogs, **TCC** will add a trailing backslash \ to directory names. The character appended is a slash \ for directory names in FTP URLs or (if you have set the UNIX/Linux-style Paths option in the Startup tab) to all directory names.

This feature can be especially handy if you use filename completion to specify files that are not in the current directory — a succession of **Tab** or **F9** and **F10** keystrokes can build a complete path to the file you want to work with.

The following example shows the use of this technique to edit the file *C:\DATA\FINANCEWAPS.DAT*. The lines which include "<F9>" show where F9 (or Tab) is pressed; the other lines show how the command line appears after the previous F9 or Tab (the example is displayed on several lines here, but all appears at a single command prompt when you actually perform the steps):

```
1 edit \da <F9>
2 edit \data\
3 edit \data\f <F9>
4 edit \data\frank.doc <F9>
5 edit \data\finance\
6 edit \data\finance\map <F9>
7 edit \data\finance\maps.dat
```

Note that F9 was pressed twice in succession on lines 3 and 4, because the file name displayed on line 3 was not what was needed — we were looking for the *FINANCE* directory, which came up the second time F9 was pressed.

3.11.12 Extended Parent Directory Names

TCC has an extended syntax for referencing parent directories, by adding additional . characters. Each additional . represents an additional directory level above the current directory. For example, .\FILE.DAT refers to a file in the current directory, ..\FILE.DAT refers to a file one level up, i.e., in the parent directory, and ...\FILE.DAT refers to a file two levels up, i.e., in the parent of the parent directory. If your default directory is C:\DATA\FINANCE\JANUARY, you can copy the file LETTERS.DAT from directory C:\DATA to drive A: with the command

```
[C:\DATA\FINANCE\JANUARY] copy ...\LETTERS.DAT A:
```

Note: This extended notation may not be understood by external programs. Consider using the @FULL [437] function to expand file and directory references when necessary:

```
[C:\DATA\FINANCE\JANUARY] myprog %@full[...\LETTERS.DAT]
```

3.11.13 Directory History Window

[The directory history window is part of a set of comprehensive directory navigation features built into **TCC**. For a summary of these features, and more information on enhanced directory navigation features, see Directory Navigation [71].]

The directory history window includes a toolbar with buttons for editing, deleting, and moving lines.

Directory History Window Keys:

F6 or Ctrl-PgUp 34 Open the window from the command line Scroll the display up one line. Up Down Scroll the display down one line. Left 31 Scroll the display left 4 columns. Right 32 Scroll the display right 4 columns. PgUp Scroll the display up one page. PgDn Scroll the display down one page. Go to the beginning of the list. Home End Go to the end of the list. Ctrl-Enter 40 Move the selected line to the command line for editing Enter 41 Change to the selected drive/directory Ctrl-C Copy the selected line to the clipboard Ctrl-D 40 or Del Delete the selected line from the list Ctrl-E 40 Edit the selected line in the directory history window Ctrl-Up Move the selected line up one row Move the selected lien down one row Ctrl-Down Esc 31 Close the window without making a selection.

Note: The keystrokes shown above are the default values. See Key Mapping Directives for details on how to assign different keystrokes.

The current directory is recorded automatically in the directory history list just before each change to a new directory or drive.

You can view the directory history from the scrollable directory history window and change to any drive and directory on the list. To activate the directory history window, press F6 34 at the command line. You can then select a new directory with the Enter 41 key or by double-clicking with the mouse.

If the directory history list becomes full, old entries are deleted to make room for new ones. You can set the size of the list with the Command History Buffer Size on Configuration option. You can change the keys used in the window with key mapping directives

In order to conserve space, each directory name is recorded just once in the directory history, even if you move into and out of that directory several times. The directory history can be stored in either a local or global list; see below for details.

When you switch directories, the original directory is saved in the directory history list, regardless of whether you change directories at the command line, from within a batch file, or from within an alias. However, directory changes made by external directory navigation utilities or other external programs are not recorded by *TCC*.

You can also view and manage the directory history list with the DIRHISTORY [208] command.

Local and Global Directory History

The directory history can be stored in either a local or global list. With a local directory history list, any changes made to the list will only be known only to the current copy of *TCC*. They will not be visible in other sessions. Whenever you start a secondary shell which uses a local history list, it inherits a copy of the directory history from the previous shell. However, any changes to the history made in the secondary shell will affect only that shell.

All copies of **TCC** using global directory history list will share a single copy of directory history. Any directory changes made in any of these copies of **TCC** will be recorded in that shared list, and be accessible by all of them. However, any additional copies of **TCC** which use local directory history will see their own local lists. Global lists are the default for **TCC**.

You can control the type of history list with the <u>Local Directory History</u> (47) configuration option, with the /L and /LD command line options (19), and with the /L and /LD options of the START (331) command.

When you close all *TCC* sessions, the memory for the global directory history list is released, and a new, empty directory history list is created the next time you start *TCC*. If you want the directory history list to be retained in memory even when no copy of *TCC* is running, you need to execute the SHRALIAS command, which performs this service for the global command history, directory history, user-defined functions, and aliases.

There is no fixed rule for deciding whether to use a local or global directory history list. Depending on your work style, you may find it most convenient to use one type, or a mixture of types in different sessions or shells. We recommend that you start with a global directory history, then modify it if you find a situation where the default is not convenient.

3.11.14 Variable Name Completion

Variable name completion works like <u>filename completion</u>. It the parameter begins with a %, the completion routines will scan the environment for matching variable names. For example, if the <u>PROMPT</u> and <u>PATH</u> are variables are in the environment, in that order, and no other variables start with p, the sequence below may be used to display the value of <u>PATH</u> are

```
echo %p<Tab>
echo %PROMPT<Tab>
echo %PATH<Enter>
```

Note: Variable name completion does not work for variable functions.

3.11.15 Expanding and Disabling Aliases

A few command line options are specifically related to aliases, and are documented briefly here for completeness. If you are not familiar with aliases, see Aliases and the ALIAS and the ALIAS and the Command for complete details.

You can expand an alias on the command line and view or edit the results by pressing Ctrl-F Defore the command is executed. This is useful when you are developing and debugging a complex alias or if you want to make sure that an alias that you may have forgotten won't change the intent of your command.

At times, you may want to temporarily disable an alias that you have defined. To do so, precede the command with an asterisk (*). For example, if you have an alias for DIR which changes the display format, you can use the following command to bypass the alias and display the directory in the standard format:

*dir

Note: The leading asterisk is crucial in aliases that redefine existing commands, such as:

DIR=*dir /w

Without the asterisk, you would trigger an **alias loop error** whenever you try to use that alias, since it will endlessly try to redefine itself.

3.11.16 Multiple Commands

You will often know the next two or three commands that you want to execute. Instead of waiting for each one to finish before you type the next, you can type them all on the same command line, separated by the <u>command separator [524]</u> (by default, an ampersand &) or the %+ pseudovariable. For example, if you know you want to copy all of your .TXT files to **D:\TEXT** and then delete all of them beginning with 'A', you could enter the following command:

```
copy *.txt d:\text\ & del a*.txt
```

You may put as many commands on the command line as you wish, as long as the total length of the command line does not exceed 32,767 characters before alias and variable expansion, and 65,535 characters after expansion.

You can use multiple commands in <u>alias [154]</u> definitions and <u>batch files [130]</u> as well as from the command line.

If you don't like using the default command separator, you can pick another character using the SETDOS 3231 command's /C option, or the Separator character 5112 configuration option.

3.11.17 Conditional Commands

When an internal command or external program finishes, it returns a result called the exit code 24h. Conditional commands allow you to perform tasks based upon the previous command's exit code 24h. Many programs return 0 if they are successful and a non-zero value if they encounter an error.

AND operator &&

If you separate two commands by && (AND), the second command will be executed only if the first command's exit code 24 is 0. For example, the following command will only erase files if the BACKUP operation succeeds:

```
backup c:\ a: && del c:\*.bak;*.lst
```

OR operator ||

If you separate two commands by || (OR), the second command will be executed only if the first command's exit code 24 is non-zero. For example, if the following BACKUP operation fails, then ECHO 217 will display a message:

```
backup c:\ a: | echo Error in the backup!
```

All internal commands return an exit code 24, but not all external programs do. Conditional commands will behave unpredictably if you use them with external programs which do not return an explicit exit code 24. To determine whether a particular external program returns a meaningful exit code 24 use an ECHO %? command immediately after the program is finished. If the program's documentation does not discuss exit code 24, you may need to experiment with a variety of conditions to see how the exit code 24 changes.

3.11.18 Command Grouping

Command grouping allows you to group a set of commands together logically by enclosing them in parentheses.

There are two primary uses for command grouping. One is to execute multiple commands in a place where normally only a single command is allowed. For example, suppose you wanted to execute two different REN ob commands in all subdirectories of your hard disk. You could do it like this:

```
global ren *.wx1 *.wxo
global ren *.tx1 *.txo
```

But with command grouping you can do the same thing in one command:

```
global (ren *.wx1 *.wxo & ren *.tx1 *.txo)
```

The two REN of commands enclosed in the parentheses appear to GLOBAL as if they were a single command, so both commands are executed for every directory, but the directories are only scanned once, not twice, typically saving time.

This kind of command grouping is most useful with the <u>EXCEPT [225]</u>, <u>FOR [234]</u>, <u>GLOBAL [245]</u>, and <u>IF [253]</u> commands. When you use this approach in a batch file, you must either place all of the commands in the group on one line, or place the opening parenthesis at the end of a line and place the commands on subsequent lines. Examples 1 and 2 below will work properly, but Example 3 will not:

```
Example 1 (correct):
```

```
for %f in (1 2 3) (echo hello %f & echo goodbye %f)
Example 2 (correct):
```

for %f in (1 2 3) (echo hello %f

echo goodbye %f

Example 3 (incorrect):

)

```
for %f in (1 2 3) (echo hello %f
  echo goodbye %f)
```

If the above examples are typed at the command line, **TCC** will issue a **More?** prompt in response to each line until the command group is closed (i.e. the final parenthesis is recognized) as discussed below.

The second common use of command grouping is to redirect input or output for several commands without repeatedly using the redirection symbols. For example, consider the following batch file fragment which places some header lines (including today's date) and directory displays in an output file using redirection. The first ECHO 217 command creates the file using >, and the other commands append to the file using >>:

```
echo Data files %_date > filelist
dir *.dat >> filelist
echo. >> filelist
echo Text files %_date >> filelist
dir *.txt >> filelist
```

Using command grouping, these commands can be written much more simply. Enter this example on one line:

```
(echo Data files %_date & dir *.dat %+ echo `` & echo Text files %_date
& dir *.txt) > filelist
```

The redirection, which appears outside the parentheses, applies to all the commands within the parentheses. Because the redirection is performed only once, the commands will run slightly faster than if each command was entered separately. The same approach can be used for input redirection and piping and pi

You can also use command grouping in a batch file or at the prompt to split commands over several lines. This last example is like the redirection example above, but is entered at the prompt. Note the More? prompt after each incomplete line. None of the commands are executed until the command group is completed with the closing parenthesis. This example does not have to be entered on one line:

```
[c:\] (echo Data files %_date
More? dir *.dat
More? echo.
More? echo Text files %_date
More? dir *.txt) > filelist
[c:\]
```

Limitations

A group of commands in parentheses is like a long command line. The total length of the group may not exceed 32,767 characters before alias and variable expansion, and 65,535 characters after expansion, whether the commands are entered from the prompt, an alias, or a batch file.

Each line you type at the normal prompt or the **More?** prompt, and each individual command within the line, must be within the usual command line length limit 126.

3.11.19 Starting Applications

TCC offers several ways to start applications.

First, you can simply type the name of any application at the prompt. As long as the application's executable file is in one of the standard search directories (see below), **TCC** will find it and start it. If you type the full path name of the executable file at the prompt the application will be started even if it

is not in one of the standard search directories.

TCC offers two methods to simplify and speed up access to your applications. One is to create an alias 154, for example:

```
alias myapp d:\apps\myapp.exe
```

In **Take Command** you can also use the Tool Bar to start frequently used applications. For example, a tool bar button named **MyApp** which invokes the command *d:\apps\myapp.exe* would accomplish the same thing as the alias shown above. You can use these methods together. For example, if you define the alias shown above you can set up a tool bar button called **MyApp** and simply use the command **myapp** for the button, which would then invoke the previously-defined alias.

You can also start an application by typing the name of a data file associated with the application. *TCC* will examine the file's extension and run the appropriate application, based on executable extensions or Windows file associations or Windows file associations

For additional flexibility, you can also start applications with the <u>START</u> and command. <u>START</u> rovides a number of switches to customize the way an application is started.

Searching for Applications

When you start an application without specifying a path, *TCC* searches for the application in the current directory, and then all directories on the PATH. *TCC* also searches the **Windows** and **Windows system** directories; see the PATH command for details. (If you do enter an explicit path, *TCC* will only look in the directory you specified.)

If you enter a file name with no extension, *TCC* will search each directory for a matching *.COM*, *.EXE*, *.BTM*, *.BAT*, or *.CMD* file (and *.REX* and/or *.REXX* if a REXX interpreter is loaded), then for a file matching a Windows file association or executable extension. That search order may be altered via the PathExt 47 configuration option. If no such file is found, *Take Command* will move on to the next directory in the search sequence.

Take Command Application Windows

Take Command runs console (character mode) applications either in a tab window within **Take Command** or in their own console window. **Take Command** always starts GUI applications in their own window.

3.11.20 Waiting for Applications to Finish

When you start a Windows GUI application from the prompt, *TCC* does not normally wait for the application to finish before returning to the prompt. This allows you to continue your work at the prompt while the application is running. You can force *TCC*to wait for applications to finish before continuing by selecting the Wait for External Apps (START) configuration option, or with the START (START) command's /WAIT switch (START) can also control many other aspects of how your applications are started).

TCC always waits for applications that are run from transient shells (with a /C), or from batch files before continuing with subsequent commands in the batch file. To start an application from a transient shell or a batch file and continue without waiting for the application to finish, use the START said command (without the /WAIT switch).

Due to the way Windows handles URLs, you cannot wait for the browser to finish when you enter an HTTP: URL at the prompt. In this situation, *TCC* always displays the next prompt immediately.

3.11.21 Escape Character

TCC recognizes a user-definable escape character. This character gives the character that follows a special meaning; it has a different purpose than the ASCII **ESC** that is often used in ANSI X3.64 and printer control sequences.

The default escape character is a caret (^, ASCII: 94). If you don't like the default escape character, you can pick another character using the <u>SETDOS</u> 323 /E command, or the <u>Escape character 51</u> configuration option. If you plan to share aliases or batch files between several *TCC* configurations, use the %= 381 pseudovariable, which is accepted in all of them, regardless of the actual value assigned to the escape character. See the section on <u>Special Character Compatibility</u> 126 for details about choosing compatible escape characters. Note that if you change the default, your batch files will not work under *CMD.EXE* and you won't be able to run third-party batch files.

Ten special characters are recognized when they are preceded by the escape character. The combination of the escape character and one of these characters is translated to a single character, as shown below. The special characters which can follow the escape character are:

Codes for Escape Characters

- **b** backspace
- c comma,
- e the ASCII ESC character (code 27)
- f form feed
- k back quote `
- n line feed
- q double quote "
- r carriage return
- s space
- t horizontal tab character

If you follow the escape character with any other character, the escape character is removed and the second character is copied directly into the command line. This allows you to suppress the normal meaning of special characters (such as ? * / \ | " $^{\circ}$ > < and &). For example, to display a message containing a > symbol, which normally indicates redirection:

```
echo 2 is %=> 4
```

The escape character has an additional use when it is the last character on any line of a batch file. **TCC** recognizes this use of the escape character to signal line continuation: it removes the escape character and appends the next line to the current line before executing it.

WARNING: Escape characters are considered to be normal characters on the right side of a pipe.

Note: The term **escape character** has two additional usages not related to the above description, as detailed in the description of the PROMPT (29) command and in ASCII, Key Codes and Key Names (510).

3.11.22 Command Parsing

Whenever you type something at the command line and press the Enter sheep, or include a command in a batch file, you pass a command to *TCC*, which must determine how to execute it. If you understand the general process that is used, you will be able to make the best use of the commands. Understanding these steps can be especially helpful when working with complex aliases or batch file commands.

TCC goes through several steps when parsing a command line. Before it starts, it writes the entire command line (which may contain multiple commands 120) to the history log file if history logging has

been enabled (with the LOG /H 2691 command) and the command did not come from a batch file. The first command is then isolated for processing. The following steps outline the basic processing required for each command. During that processing, additional parsing tasks may be triggered as noted and some steps may be repeated multiple times.

1. Separating the command from its tail

TCC begins by dividing the command into a command name and a command tail. The command name is the first word in the command, and the tail is everything that follows the command name. For example, in the command line

```
dir *.txt /2/p/v
```

The command name is dir, and the command tail is "*.txt /2/p/v". In some instances, the parser will be able to understand incorrect syntax such as dir/w, but there should always be at least one space between the command name and its parameters.

2. Expanding aliases

Next, *TCC* tries to match the command name against its list of <u>aliases 128</u>. If it finds a match between the command name and one of the aliases you've defined, it replaces the command name with the contents of the alias. This substitution is done internally and is not normally visible to you; however, you can view a command line with aliases expanded by pressing <u>Ctrl-F</u> 33 after entering the command at the prompt.

If the alias included parameters (%1, %2, etc.), the parameter values are filled in from the text on the command line, and any parameters used in this process are removed from the command line. The process of replacing a command name that refers to an alias with the contents of the alias, and filling in the alias parameters, is called alias expansion.

This expansion of an alias creates a new command name: the first word of the alias. This new command name is again tested against the list of aliases, and if a match is found the contents of the new alias is expanded just like the first alias. This process, called nested alias expansion, continues until the command name no longer refers to an alias.

3. Expanding variables

The next step is to locate any batch file parameters, environment variables, internal variables, or variable functions in the command, and replace each one with its value (see "Environment: Variables and Functions (365)"). This process is called variable expansion, and is not normally visible. However, you can view an expanded command line by pressing Ctrl-X (36) after entering the command at the prompt.

The variable expansion process is modified for certain internal commands, such as <u>EXCEPT</u> 225, <u>IF</u> 253, and <u>GLOBAL</u> 245. These commands are always followed by another command, so variable expansion takes place separately for the original command and the command that follows it.

4. Identifying a plugin or internal command

Once it has finished variable expansion, *TCC* next tries to match the resulting command name with its list of <u>plugin [293]</u> commands or <u>internal commands [144]</u>. If it is unsuccessful, it knows that it will have to search for a batch file or external program to execute your command.

5. Displaying the command

When all of the aliases and environment variables have been expanded, **TCC** will echo the complete command to the screen (if command line echo has been enabled) and write it to the log file (if

command logging log has been turned on).

6. Processing redirection and piping

Before it can actually execute your command, *TCC* must scan the command tail to see if it includes redirection or piping or p

7. Processing escape characters

At this stage, any remaining Escape Characters | 124| are processed. However, this might also already have taken place inside some of the variable functions (such as @IF | 439) that are likely to pass escaped strings in their parameters. If you are referencing one of those in an ECHO | 217 or similar command, you need to escape twice ("^^") or use SETDOS /X | 323 to avoid premature evaluation. Carefully test those situations to make sure the results are as you intended.

8. Executing the command

Finally, it is time to execute the command. *TCC* will first look for a matching <u>plugin</u> command name; if it doesn't exist then it tries to match an internal command. Otherwise, *TCC* searches for an executable (.*COM* or .*EXE*) file, a batch file, or a file with an executable extension that matches the command name (see the detailed description of this search in <u>Executable Files and File Searches</u> [504]).

9. Cleaning up

Once the internal command or external program has terminated, *TCC* saves the result or exit code that the command generated, cleans up any redirection that you specified, and then returns to the original command line to retrieve the next command. When all of the commands in a command line are finished, the next line is read from the current batch file, or if no batch file is active, the prompt is displayed.

Note: You can disable and reenable several parts of command parsing (for example alias expansion, variable expansion, and redirection) with the SETDOS /X 3231 command.

3.11.23 Command Line Length Limits

When you first enter a command at the command prompt, in an alias or function definition, or in a batch file, it can be up to 32,767 characters long.

As **TCC** scans the command line and substitutes the contents of aliases user defined functions, and environment variables for their names, the line usually gets longer. This expanded line is limited to 65,535 characters. If your use of aliases, user defined functions, or environment variables causes the command line to exceed the applicable one of these limits as it is expanded, you will see a **Command line too long** error and the remainder of the line will not be executed.

3.11.24 Special Character Compatibility

If you want to share aliases, user defined functions, and batch files with other users, you need to be aware of possible differences in three important characters: the Command Separator (see Multiple Commands 120), the Escape Character (see Escape Character 124), and the Parameter Character (see Batch File Parameters 133).

The default values of each of these characters is shown in the following chart.

Product	Separator	Escape	Parameter
4DOS (obsolete)	۸	Ctrl-X	&
Take Command	&	۸	\$
pseudovariable	%+	%=	

In your batch files and aliases, and even at the command line, you can smooth over these differences in three ways:

1. Use internal pseudovariables that contain the current special character, rather than using the character itself (see %+38f) and %=38f). For example, this command:

```
if "%1" == "" (echo Parameter missing! ^ quit)
```

will only work if the command separator is a caret. However, this version works regardless of the current command separator:

```
if "%1" == "" (echo Parameter missing! %+ quit)
```

- 2. Select a consistent set of characters from the Advanced tab 51 of the configuration dialogs 46 .
- 3. In a batch file, use the <u>SETLOCAL [326]</u> command to save the command separator, escape character, and parameter character when the batch file starts. Then use <u>SETDOS</u> [323] as described below to select the characters you want to use within the batch file. Use an <u>ENDLOCAL</u> [220] command at the end of the batch file to restore the previous settings.

You can also use the SETDOS 3231 command to change special characters on the command line.

3.11.25 Date Input Formats

Date Input Formats

Commands and functions which accept a date as a parameter expect the same field order displayed by the DIR [198] command and functions returning a date without a format code specifier. The year can be entered as a 4-digit or 2-digit value. Two-digit years from 80 to 99 are interpreted as 1980...1999; values from 0 to 79 are interpreted as 2000...2079. Month and day may be entered without a leading zero. Most non-numeric printing characters are accepted as field separators. All three fields must be specified.

3.11.26 Case Sensitivity

With the following exceptions, **TCC** treats upper case and lower case letters identically:

The relational operator **EQC**

The character manipulation functions @ascii, @unicode, @repeat, @replace, @similar, @strip and @wild.

The codes used to specify units of storage size (kkmMgGtT) in:

- size ranges
- · disk space and file size reporting functions

3.12 Aliases & Batch Files

Whenever you have a command (internal or external) that you need to execute often, one that's too complex to be dependably typed manually at the Command Line one that needs to be part of an exact sequence of other commands, one that you want to be able to easily repeat from another location or share with others, or you repeat very often and therefore want to have a very short name, you can store that command as part of a convenient ALIAS and/or batch file.

- ▶ Aliases 128
- Batch Files 130
- Special Character Compatibility 126

3.12.1 Aliases

Much of the power of *TCC* comes together in **aliases**, which give you the ability to create your own commands. An alias is a name that you select for a command or group of commands. Simple aliases substitute a new name for an existing command. More complex aliases can redefine the default settings of internal or external commands, operate as very fast in-memory batch files, and perform commands based on the results of other commands. *TCC* also supports <u>Directory Aliases</u> 76, a shorthand way of specifying pathnames.

This section shows you some examples of the power of aliases. See the <u>ALIAS</u> 154 command for complete details about writing your own aliases.

The simplest type of alias gives a new name to an existing command. For example, you could create a command called R (for Root directory) to switch to the root directory this way:

```
alias r=cd \
```

After the alias has been defined this way, every time you type the command R, you will actually execute the command $CD^{(177)}$ \.

Aliases can also create customized versions of commands. For example, the DIR of command can sort a directory in various ways. You can create an alias called **DE** that means "sort the directory by filename extension, and pause after each page while displaying it" like this:

```
alias de=dir /oe /p
```

Aliases can be used to execute sequences of commands as well. The following command creates an alias called <code>MUSIC</code> which saves the current drive and directory, changes to the <code>SOUNDS</code> directory on drive <code>C</code>, runs the program <code>E:WUSICVPLAYER.EXE</code>, and, when the program terminates, returns to the original drive and directory (enter this on one line):

```
alias music=`pushd c:\sounds & e:\music\player.exe & popd`
```

This alias is enclosed in back-quotes because it contains multiple commands. You must use the back-quotes whenever an alias contains multiple commands, environment variables, parameters (see below), redirection, or piping. See the ALIAS 154 command for full details.

When an alias contains multiple commands, the commands are executed one after the other. However, if any of the commands runs an external Windows application (such as the fictitious *PLAYER.EXE* shown above), you must be sure the alias will wait for the application to finish before continuing with the other commands. See Waiting for Applications to Finish 123 for additional details.

Aliases can be nested; that is, one alias can invoke another. For example, the alias above could also

be written as:

```
alias play=e:\music\player.exe
alias music=`pushd c:\sounds & play & popd`
```

If you enter *MUSIC* as a command, *TCC* executes the <u>PUSHD</u> command, detects that the next command (**PLAY**) is another alias and executes the program *E:WUSICVPLAYER.EXE*, and — when that program exits — returns to the first alias, executes the <u>POPD</u> command, and returns to the prompt.

You can use aliases to change the default options for both internal commands and external commands. Suppose that you always want the DEL (190) command to prompt before it erases a file:

```
alias del=*del /p
```

An asterisk * is used in front of the second DEL to tell *TCC* to use the original internal command, not an alias. See Temporarily Disabling Aliases 156 for more information about this use of the asterisk.

You may have a program on your system that has the same name as an internal command. Normally, if you type the command name, you will start the internal command rather than the program you desire, unless you explicitly add the program's full path on the command line. For example, if you have a program named <code>DESCRIBE.EXE</code> in the <code>C:\WUTIL</code> directory, you could run it with the command <code>C:\WUTIL\DESCRIBE.EXE</code>. However, if you simply type <code>DESCRIBE</code>, the internal <code>DESCRIBE</code> ocmmand will be executed instead. Aliases give you two simple ways to get around this problem.

First, you could define an alias that runs the program in question, but using a different name:

```
alias desc=c:\winutil\describe.exe
```

Another approach is to use an alias to rename the internal command and use its original name for the external program. The following example creates the alias *FILEDESC* for the DESCRIBE (1986) command, and then uses a second alias to run DESCRIBE. EXE whenever you type DESCRIBE:

```
alias filedesc=*describe
alias describe=c:\winutil\describe.exe
```

You can also assign an alias to a key, so that every time you press the key, the command will be invoked. You do so by naming the alias with an at sign [@] followed by a key name. After you enter this next example, you will see a 2-column directory with paging whenever you press **Shift-F5** followed by **Enter**:

```
alias @Shift-F5=*dir /2/p
```

This alias will put the DIR sommand on the command line when you press **Shift-F5**, then wait for you to enter file names or additional switches. You must press Enter when you are ready to execute the command. To execute the command immediately, neither displaying it on the command line, nor waiting for you to press Enter, use two @ signs at the start of the alias name:

```
alias @@Shift-F5=*dir /2/p
```

The next example clears the window whenever you press Ctrl-F2:

```
alias @@Ctrl-F2=cls
```

Aliases have many other capabilities as well. The next example creates a simple command line calculator. Once you have entered the example, you can type **CALC 4*19**, for example, and you will see the answer:

```
alias calc=`echo The answer is: %@eval[%$]`
```

Our last example in this section creates an alias called **IN**. It temporarily changes directories, runs an internal or external command, and then returns to the current directory when that command is finished:

```
alias in=`pushd %1 & %2$ & popd`
```

Now if you type:

```
in c:\sounds play furelise.wav
```

you will change to the *C:\SOUNDS* subdirectory, execute the command **PLAY FURELISE.WAV**, and then return to the current directory.

Alias Parameters

The above example uses two parameters: **%1** means the first parameter on the command line, and **%2\$** means the second and all subsequent parameters.

Aliases can use command line parameters or parameters like those in batch files. The command line parameters are numbered from %0 to %511. (%0 contains the alias name.) You can use double quotes to pass spaces, tabs, commas, and other special characters in an alias parameter; see Parameter Quoting [134] for details. Alias examples in this section assume the *TCC*default of ParameterChar=\$.

Parameters that are referred to in an alias, but which are missing on the command line, appear as empty strings inside the alias. For example, if you only put two parameters on the command line, any reference in the alias to **%3** or any higher-numbered parameter will be interpreted as an empty string.

The parameter **%n\$** has a special meaning. **TCC** interprets it to mean "the entire command line, from parameter **n** to the end." If **n** is not specified, it has a default value of **1**, so **%\$** means "the entire command line after the alias name."

The parameter %-n\$ means "the command line from parameter 1 to *n* - 1".

The special parameter **%#** contains the number of command line parameters.

Aliases cannot use indirect access to command parameters, e.g., %[%n] (where n is a parameter number) does not return the selected parameter.

See the ALIAS 154 and UNALIAS 355 commands for more information and examples.

3.12.2 Batch Files

A batch file is a file that contains a list of commands to execute. *TCC* reads and interprets each line as if it had been typed at the keyboard. Like <u>aliases list</u>, batch files are handy for automating computing tasks. Unlike aliases, batch files can be as long as you wish. Batch files take up separate disk space for each file, and can't usually execute quite as quickly as aliases, since they must be read from the disk.

Some of the topics included in this section are:

- ▶ .BAT, .CMD, and .BTM 131
- ▶ Using .BAT Files Under TCC 131
- ▶ Echoing in Batch Files 132
- Batch File Line Continuation 141
- Batch File Parameters 133

- ▶ Using Environment Variables 135
- Batch File Commands 135
- Interrupting a Batch File 137
- Automatic Batch Files 22
- Detecting Take Command 137
- ▶ Using Aliases in Batch Files 137
- Debugging Batch Files 139
- ▶ String Processing 139
- ▶ Batch File Compression 141
- Parameter Quoting 134
- Perl Support 142
- REXX Support 142
- Ruby Support 143
- ► EXTPROC / Shebang Support 143

3.12.2.1 .BAT, .CMD & .BTM Files

A batch file can run in two different modes. In the first, traditional mode, each line of the batch file is read and executed individually, and the file is opened and closed to read each line. In the second mode the batch file is opened once, the entire file is read into memory, and the file is closed. Only the first mode can be used for self-modifying batch files (which are rare).

The batch file's extension determines its initial mode. Files with a *.BAT* or *.CMD* extension are run in the first mode. Files with a *.BTM* extension are run in the more efficient second mode. You can change the execution mode inside a batch file with the LOADBTM [269] command.

3.12.2.2 Using .BAT Files Under TCC

In most cases under **TCC** your batch files will be stored as .CMD or .BTM files. However, you may also choose to use some .BAT files, especially if you are moving from Win98 to XP / 2003 / Vista / 2008. If you do, you need to be aware of the way **TCC**executes .BAT files, which is slightly different from the method used by CMD.EXE.

CMD.EXE passes all .BAT files to Windows' DOS command processor, COMMAND.COM, for execution (yes, there is a skeletal DOS command processor in Windows). COMMAND.COM handles a few DOS-related commands, but passes most internal commands to a second copy of CMD.EXE so that they are executed in the Windows environment. This convoluted system allows you to load memory-resident DOS programs (TSRs), and run other programs which use them, all from the same .BAT file. However, it reduces performance for all .BAT files in order to support those rare files which load DOS TSRs under Windows.

TCC does not use this system; it executes .BAT files directly, just like .CMD and .BTM files. This works better for most files, but may render DOS TSRs loaded from a .BAT file ineffective because other commands in the file are not executed in a DOS-based environment.

In most cases this difference will not affect your *.BAT* files, because you will not be loading DOS TSRs in Windows. If you do need to load TSRs from *.BAT* files, we recommend that you obtain a copy of our DOS command processor, *4DOS*, start it from your Windows desktop, and run the *.BAT* files from *4DOS*. You could also use CMD.EXE, but of course the *.BAT* files then cannot use *4DOS* or *TCC* features. While we do not generally recommend using *4DOS* under Windows 2000 / XP / 2003, it works well in this specific situation.

When invoking DOS programs from a **TCC** batch file, we recommend that you enable the *CONFIG.NT* command **NTCMDPROMPT** without which Windows tends to "forget" to return control to a calling 32-bit program (such as **Take Command**) and may leave you at an unexpected COMMAND.COM prompt. *CONFIG.NT* typically resides in the Windows SYSTEM32 directory. See your Windows

documentation for additional information.

3.12.2.3 Echoing in Batch Files

By default, each line in a batch file is displayed or "echoed" as it is executed. You can change this behavior, if you want, in several different ways:

- Any batch file line that begins with an @ symbol will not be displayed.
- The display can be turned off and on within a batch file with the <u>ECHO 217</u> OFF and <u>ECHO 217</u> ON commands.
- The default setting can be changed with the <u>SETDOS</u> 323 /V command, or the <u>Default Batch</u> Echo 47 configuration option.

For example, the following line turns off echoing inside a batch file. The @ symbol keeps the batch file from displaying the ECHO OFF command itself:

@echo off

TCC also has a command line echo that is unrelated to the batch file echo setting. See ECHO 217 for details about both settings.

3.12.2.4 Special syntax for CMD.EXE compatibility

For compatibility with CMD.EXE, *TCC* supports additional syntax to qualify references to parameters of batch files and the control variable of the FOR [234] command when referenced by the *command* it executes. However, this syntax can usually be replaced by the more flexible Variable Functions [395].

CMD.EXE syntax	Expands to	Suggested replacement
%*	All parameters	%\$
%~n	unquoted (")	%@replace[%=",,%n]
%~fn	Fully qualified name of %n	%@full[%n]
%~dn	Drive letter portion of %n	%@left[2,%@full[%n]]
%~pn	Full path (no drive letter) of %n	<pre>%@right[-2,%@path[%@full[%n]]]</pre>
%~nn	Root name (no extension) of %n	%@name[%n]
%~xn	File extension of %n	.%@ext[%n]
%~sn	Fully qualified short name of %n	%@sfn[%n]
%~an	File attributes of %n	%@attrib[%n]
%~tn	File date and time of %n	%@filedate[%n] %@filetime[%n]
%~zn	File size of %n, bytes	%@filesize[%n]
	Full name of the first match for %n in %PATH 368	%@search[%n]

Notes

In the special case where the parameter to a %~ variable is **0**, e.g., %~**f0**, the returned file name will always include the extension, as it does under CMD.EXE.

%~**\$PATH:** returns an empty string if the file %n is not found in the path.

References qualified by the tilde ~ trigger an error message when used improperly, e.g. if attempting to display the size of a string parameter which is not the name of a file.

3.12.2.5 Batch File Parameters

Like <u>aliases 154</u>, user-defined <u>functions 242</u> and application programs, batch files can examine the command line that is used to invoke them. The command tail (everything on the command line after the batch file or alias name) is separated into individual positional parameters (also called parameters or batch variables) by scanning for the spaces, tabs, and commas that separate them. For aliases and functions, a forward slash (/) triggers the beginning of a new parameter, e.g. the string **xyz/abc** is separated into parameters **foo** and **/abc**.

These parameters are numbered from %1 to %4095. %1 refers to the first parameter on the command line, %2 to the second, and so on. It is up to the batch file to determine the meaning of each parameter. You can use double quotes to pass spaces, tabs, commas, and other special characters in a batch file parameter; see Parameter Quoting [134] for details.

Parameters that are referred to in a batch file, but which are missing on the command line, appear as empty strings inside the batch file. For example, if you start a batch file and put two parameters on the command line, any reference in the batch file to %3, or any higher-numbered parameter, will be interpreted as an empty string.

A batch file can use the special parameters shown in the table below:

parameter	value
	the name of the batch file as entered on the command line
%#	the number of command line parameters, modified by SHIFT 327
	the command tail starting with parameter number <i>n</i> , modified by SHIFT 327
%-n\$	the command tail from parameter 1 to <i>n</i> - 1
%\$ %*	the complete command tail, modified by SHIFT 327
%*	the complete command tail, unmodified by SHIFT 327

For example, **%3\$** means the third and all subsequent parameters. The values of **%#**, **%n\$**, **%-n\$**, and **%\$** will change if you use the SHIFT (327) command. To emulate CMD.EXE, SHIFT (327) does not affect the value of **%***.

For example, if your batch file interprets the first parameter as a subdirectory name then the following line would move to the specified directory:

```
cd %1
```

A friendlier batch file would check to make sure the directory exists and take some special action if it doesn't:

```
iff isdir %1 then
   cd %1
else
   echo Subdirectory %1 does not exist!
   quit
endiff
```

(See the IF 253) and IFF 254 commands.)

Batch files can also use environment variables [365], internal variables [372], and variable functions [395].

Batch file parameters may also use the special CMD.EXE compatibility syntax [132].

3.12.2.5.1 Parameter Quoting

```
As TCC parses 124 the command line, it looks for the <u>command separator</u> 120, <u>conditional commands</u> 120 (| | and &&), white space (spaces, tabs, and commas), percent signs % which indicate <u>variables</u> 365 or batch file 130 parameters to be expanded, and redirection and piping 97 characters >, <, and |.
```

Normally, these special characters cannot be passed to a command as part of a parameter. However, you can include any of the special characters in a parameter by enclosing the entire parameter in single back quotes ['] or double quotes ["]. Although both back quotes and double quotes will let you build parameters that include special characters, they do not work the same way.

No alias or variable expansion is performed on a parameter enclosed in back quotes. Redirection symbols inside the back quotes are ignored. The back quotes are removed from the command line before the command is executed.

No alias expansion is performed when an expression is enclosed in double quotes. Redirection symbols inside double quotes are ignored. However, variable expansion **is** performed in expressions inside double quotes. The double quotes themselves will be passed to the command as part of the parameter.

For example, suppose you have a batch file *CHKNAME.BTM* which expects a name as its first parameter (%1). Normally the name is a single word. If you need to pass a two-word name with a space in it to this batch file you could use the command:

```
chkname `MY NAME`
```

Inside the batch file, %1 will have the value **MY NAME**, including the space. The back quotes caused **TCC** to pass the string to the batch file as a single parameter. The quotes keep characters together and reduce the number of parameters in the line.

For a more complex example, suppose the batch file *QUOTES.BAT* contains the following commands:

```
@echo off
echo Arg1 = %1
echo Arg2 = %2
echo Arg3 = %3
```

and that the environment variable FORVAR has been defined with this command:

```
set FORVAR=for
```

Now, if you enter the command

```
quotes `Now is the time %forvar` all good
```

The output from QUOTES.BAT will look like this:

```
Arg1 = Now is the time %forvar
Arg2 = all
Arg3 = good
```

But if you enter the command:

```
quotes "Now is the time %forvar" all good
```

The output from QUOTES.BAT will look like this:

```
Arg1 = "Now is the time for"
Arg2 = all
Arg3 = good
```

Notice that in both cases, the quotes keep characters together and reduce the number of parameters in the line.

The following example has 7 command line parameters, while the examples above only have 3:

```
quotes Now is the time %%forvar all good
```

(The double percent signs are needed in each case because the parameter is parsed twice, once when passed to the batch file and again in the ECHO command.)

When an alias is defined in a batch file or from the command line, its parameter can be enclosed in back quotes to prevent the expansion of replaceable parameters, variables, and multiple commands until the alias is invoked. See ALIAS 1541 for details.

You can disable and reenable back quotes and double quotes with the SETDOS 323 /X command.

3.12.2.6 Using Environment Variables

Batch files can use <u>environment variables [366]</u>, <u>internal variables [372]</u>, <u>variable functions [395]</u>, or <u>user-defined functions [242]</u>. You can use these variables and functions to determine system status (*e.g.*, the CPU type), resource levels (*e.g.*, the amount of free disk space), file information (*e.g.*, the date and time a file was last modified), and other information (*e.g.*, the current date and time). You can also perform arithmetic operations (including date and time arithmetic), manipulate strings and substrings, extract parts of a filename, and read and write files.

To create temporary variables for use inside a batch file, just use the <u>SET</u> [319] command to store the information you want in an environment variable. Pick a variable name that isn't likely to be in use by some other program (for example, PATH would be a bad choice), and use the <u>UNSET</u> [357] command to remove these variables from the environment at the end of your batch file. You can use <u>SETLOCAL</u> [326] and <u>ENDLOCAL</u> [220] to create a "local" environment so that the original environment will be restored when your batch file is finished.

Environment variables used in a batch file may contain either numbers or text. It is up to you to keep track of what's in each variable and use it appropriately; if you don't (for example, if you use %@EVAL to add a number to a text string), you'll get an error message or a meaningless return value.

3.12.2.7 Batch File Commands

Some commands are particularly suited to batch file processing. Each command is explained in detail in the Command Reference [147]. Here is a list of some of the commands you might find most useful:

```
ACTIVATE 152 activates another window
BEEP 173
                produces a sound of any pitch and duration through the computer's speaker
BREAKPOINT
                set a breakpoint in the batch debugger
174
CALL 175
                executes one batch file from within another
CANCEL 176
                terminates all batch file processing
CLS 18th
                clears the TCC window
COLOR 181
                sets the TCC display colors
DEBUGSTRING send text to the debugger
DEFER 190
                defers a command until the batch file ends
DO 210
                starts a loop. The loop can be based on a counter, or on a conditional expression,
                strings, or files. ENDDO terminates the loop
```

DRAWBOX 214 draws a box on the screen DRAWHLINE draws horizontal lines on the screen 215 DRAWVLINE 216 draws vertical lines on the screen ECHO 217 sends text to the standard output device ECHOS 219 sends text to the standard output device ECHOERR 217 sends text to the standard error device ECHOSERR 219 sends text to the standard error device ENDLOCAL 220 restores the settings that were saved and allows specific variables to be exported (see SETLOCAL 3261) ENDTEXT 345 ends the block of text started with TEXT 345 EVENTLOG 223 writes a string to the Windows application event log FOR 234 executes commands for each file that matches a set of wildcards, or each entry in a list GOSUB 247 executes a subroutine inside a batch file (see RETURN 307). GOTO 248 branches to a different location in the batch file F 253 execute commands based on a conditional expression IFF 254 INKEY 257 collects keyboard input and store it in environment variables INPUT 259 collects keyboard input and store it in environment variables JABBER 260 send an instant message (IM) KEYSTACK 262 sends keystrokes to applications LOADBTM 269 changes the batch file operating mode MSGBOX 279 displays a dialog box with standard buttons like Yes, No, OK, and Cancel, and returns the user's selection ON 282 initializes error handling for Ctrl-C / Ctrl-Break, or for program and command errors OSD 286 Display floating text on the desktop PAUSE 287 displays a message and waits for the user to press a key PDIR 288 creates a customized DIR-like display of directory contents PLAYAVI 29 plays Windows .AVI files **PLAYSOUND** plays Windows sound files POSTMSG 294 send a message to a window QUERYBOX 3001 displays a dialog box for text input QUIT 301 ends the current batch file and optionally returns an exit code **REM** 304 places a remark in a batch file RETURN 307 terminates a subroutine (see GOSUB 247) SCREEN 310 positions the cursor on the screen and optionally prints a message at the new location SCRPUT 31A displays a message in color SENDMAIL 316 sends an email message SETLOCAL 326 saves the current disk drive, default directory, environment, alias list, and special character settings (see ENDLOCAL 2201). SHIFT 327 changes the numbering of the batch file parameters SMPP 330 sends messages using the SMPP protocol SNPP 33A sends a message to an alphanumeric pager START 33 starts another session or window SWITCH 335 selects a group of statements to execute based on the value of a variable **TCTOOLBAR** changes the TC tool bar buttons 343 TEXT 345 displays a block of text (see ENDTEXT 345) TIMER 347 starts or reads a stopwatch TITLE 349 changes the window title VSCRPUT 360 displays a vertical message in color

These commands, along with the internal variables and variable functions, make the enhanced batch

WMIQUERY 364 Query the Windows Management Instrumentation interface

file language extremely powerful. Your copy of *Take Command* includes a sample batch file (EXAMPLES.BTM), that demonstrates some of the things you can do with batch files.

3.12.2.8 Interrupting a Batch File

You can usually interrupt a batch file by pressing **Ctrl-C** or **Ctrl-Break**. Whether and when these keystrokes are recognized will depend on whether **TCC** or an application program is running, how the application, if any, was written, whether <u>BREAK 174</u> is ON or OFF, and whether the <u>ON BREAK 282</u> command is in use.

If **TCC** detects a **Ctrl-C** or **Ctrl-Break** when ON BREAK is not in use, it displays a prompt, for example:

```
Cancel batch job C:\CHARGE.BTM ? (Y/N/A) :
```

Enter **N** to continue, **Y** to terminate the current batch file and continue with any batch file which called it, or **A** to end all batch file processing regardless of the batch file nesting level. Answering **Y** is similar to the QUIT ommand; answering **A** is similar to the CANCEL ommand.

3.12.2.9 Detecting TCC and Take Command

From a batch file, you can determine if **TCC** is loaded by testing for the variable function <u>@EVAL</u> 420, with a test like this:

```
if "%@eval[2 + 2]%" == "4" echo Take Command is loaded!
```

This test can never succeed in CMD.EXE. (Other variable functions could also be used for the same purpose.)

You can determine if **TCC** is running in a **Take Command** tab window with the internal variable _TCTAB [393]:

if % tctab == 1 echo TCC is running in a Take Command tab window!

3.12.2.10 Using Aliases in Batch Files

One way to simplify batch file programming is to use aliases to hide unnecessary detail inside a batch file. For example, suppose you want a batch file to check for certain errors, and display a message and exit if one is encountered. This example shows one way to do so:

```
setlocal
unalias *
setdos /e%=^ /c%=& /p%=$
alias error `echo. & echo ERROR: %$ & goto dispmenu`
alias fatalerror `echo. & echo FATAL ERROR: %$ & quit`
alias in `pushd %1 & %2$ & popd`
if not exist setup.btm fatalerror Missing setup file!
call setup.btm
cls
:dispmenu
text
          1. Word Processing
          2. Solitaire
          3. Internet
          4. Exit
endtext
echo.
```

```
inkey Enter your choice: %%userchoice
switch %userchoice
case 1
   input Enter the file name:
                               %%fname
   if not exist fname error File does not exist
   in d:\letters c:\windows\wordpad.exe
case 2
   in d:\finance c:\windows\sol.exe
case 3
   in d:\comm c:\windows\iexplore.exe
case 4
   goto done
default
  error Invalid choice, try again
endswitch
goto dispmenu
:done
endlocal
```

The first alias, ERROR, simply displays an error message and jumps to the label DISPMENU to redisplay the menu. The %\$ in the second <u>ECHO[217]</u> command displays all the text passed to ERROR as the content of the message. The similar FATALERROR alias displays the message, then exits the batch file.

The last alias, IN, expects 2 or more command line parameters. It uses the first as a new working directory and changes to that directory with a <u>PUSHD</u> command. The rest of the command line is interpreted as another command plus possible command line parameters, which the alias executes. This alias is used here to switch to a directory, run an application, and switch back. It could also be used from the command line.

The following 9 lines print a menu on the screen and then get a keystroke from the user and store the keystroke in an environment variable called *userchoice*. Then the <u>SWITCH [335]</u> command is used to test the user's keystroke and to decide what action to take.

There's another side to aliases in batch files. If you're going to distribute your batch files to others, you need to remember that they may have aliases defined for the commands you're going to use. For example, if the user has aliased CD 177 to CDD 178 and you aren't expecting this, your file may not work as you intended. There are two ways to address this problem.

The simplest method is to use <u>SETLOCAL</u> [326], <u>ENDLOCAL</u> [220], and <u>UNALIAS</u> [335] to clear out aliases before your batch file starts, and <u>SETDOS</u> [323] to select the special characters you depend on, and restore them at the end, as we did in the previous example. Remember that <u>SETLOCAL</u> [326] and <u>ENDLOCAL</u> [220] will save and restore not only the aliases but also the environment, the current drive and directory, and various special characters.

If this method isn't appropriate or necessary for the batch file you're working on, you can also use an asterisk * before the name of any command. The asterisk means the command that follows it should not be interpreted as an alias. For example the following command redirects a list of file names to the file <code>FILELIST</code>:

```
dir /b > filelist
```

However, if the user has redefined DIR with an alias this command may not do what you want. To get around this just use:

```
*dir /b > filelist
```

The same can be done for any command in your batch file. If you use the asterisk, it will disable alias

processing, and the rest of the command will be processed normally as an internal command, external command, or batch file. Using an asterisk before a command will work whether or not there is actually an alias defined with the same name as the command. If there is no alias with that name, the asterisk will be ignored and the command will be processed as if the asterisk wasn't there.

You can use the pseudovariables %= 381 and %+ 381 to represent the command escape 124 and command separator 51 characters, respectively, There is no pseudovariable for the parameter character 51.

3.12.2.11 Debugging Batch Files

Take Command includes a built-in full-featured batch file debugger invoked with the <u>BDEBUGGER</u> 166 command. The debugger gives you a detailed, step-by-step view of batch file execution, and will help solve particularly difficult batch file problems.

3.12.2.12 String Processing

As you gain experience with batch files, you're likely to find that you need to manipulate text strings. You may need to prompt a user for a name or password, process a list of files, or find a name in a phone list. All of these are examples of string processing – the manipulation of readable text.

TCC includes several features that make string processing easier. For example, you can use the INPUT [259], MSGBOX [279], and QUERYBOX [300] commands for user input; the ECHO and ECHOERR [219], ECHOS and ECHOSERR [219], SCREEN [310], SCRPUT [311], and VSCRPUT [360] commands for output; and the FOR [234] command or the @FILEREAD [429] function to scan through the lines of a file. In addition, variable functions [395] offer a wide range of strings and character handling [404] capabilities.

For example, suppose you need a batch file that will prompt a user for a name, break the name into a first name and a last name, and then run a hypothetical LOGIN program. LOGIN expects the syntax /F:first /L:last with both the first and last names in upper case and neither name longer than 8 characters. Here is one way to write such a batch file:

```
@echo off
setlocal
unalias *
input Enter your name (no initials): %%name
set first=%@word[0,%name]
set flen=%@len[%first]
set last=%@word[1,%name]
set llen=%@len[%last]
iff %flen gt 8 .or. %llen gt 8 then
    echo First or last name too long
    quit
endiff
login /F:%@upper[%first] /L:%@upper[%last]
endlocal
```

The SETLOCAL 326 command at the beginning of this batch file saves the environment and aliases. Then the UNALIAS * 355 command removes any existing aliases so they won't interfere with the behavior of the commands in the remainder of the batch file. The first block of lines ends with a INPUT command which asks the user to enter a name. The user's input is stored in the environment variable NAME.

The second block of lines extracts the user's first and last names from the NAME variable and

calculates the length of each. It stores the first and last name, along with the length of each, in additional environment variables. Note that the @word function numbers the first word as 0, not as 1.

The IFF 254 command in the third block of lines tests the length of both the first and last names. If either is longer than 8 characters, the batch file displays an error message and ends. (QUERYBOX can limit the length of input text more simply with its /L switch. We used a slightly more cumbersome method above in order to demonstrate the use of string functions in batch files.)

Finally, in the last block, the batch file executes the LOGIN program with the appropriate parameters, then uses the ENDLOCAL command to restore the original environment and alias list. At the same time, ENDLOCAL discards the temporary variables that the batch file used (NAME, FIRST, FLEN, etc.).

When you're processing strings, you also need to avoid some common traps. The biggest one is handling special characters.

Suppose you have a batch file with these two commands, which simply accept a string and display it:

```
input Enter a string: %%str
echo %str
```

Those lines look safe, but what happens if the user enters the string "some > none" (without the quotes). After the string is placed in the variable STR, the second line becomes

```
echo some > none
```

The ">" is a redirection symbol, so the line echoes the string "some" and redirects it to a file called NONE – probably not what you expected. You could try using double quotes [134] to avoid this kind of problem, but that won't quite work. If you use back-quotes (ECHO `%STR`), the command will echo the four-character string %STR. Environment variable names are not expanded when they are inside back-quotes.

If you use double quotes (ECHO "%STR"), the string entered by the user will be displayed properly, and so will the double quotes. With double quotes, the output would look like this:

```
"some > none"
```

As you can imagine, this kind of problem becomes much more difficult if you try to process text from a file. Special characters in the text can cause all kinds of confusion in your batch files. Text containing back-quotes, double quotes, or redirection symbols can be virtually impossible to handle correctly.

One way to overcome these potential problems is to use the <u>SETDOS /X 3231</u> command to temporarily disable redirection symbols and other special characters. The two-line batch file above would be a lot more likely to produce the expected results if it were rewritten this way:

```
setdos /x-15678 input Enter a string: %%str echo %str setdos /x0
```

The first line turns off alias processing and disables several special symbols, including the command separator and all redirection symbols. Once the string has been processed, the last line re-enables the features that were turned off in the first line.

If you need advanced string processing capabilities beyond those provided by *TCC*, you may want to consider using the Perl [142], REXX [142], or Ruby [143] languages. Our products can execute Perl, REXX, and Ruby programs internally, and also support evaluating individual Perl, Rexx, and Ruby

expressions internally.

3.12.2.13 Batch File Line Continuation

TCC will combine multiple lines in the batch file into a single line for processing when the Escape Character (the actual token or the symbolic "%= 381" reference) is the last character of each line to be combined (except the last). For example:

```
c:\> echo The quick brown fox jumped over the ^
sleeping ^
dog. > alphabet
```

You cannot use this technique to extend a batch file line beyond the normal command line length limit

3.12.2.14 Batch File Compression

You can compress your *.BTM* files with <u>BATCOMP</u> [166]. That command compresses batch files by about a third and makes them unreadable with the <u>LIST</u> [264] command and similar utilities. Compressed batch files run at approximately the same speed as uncompressed *.BTM* files.

You may want to consider compressing batch files if you need to distribute them to others and keep your original code secret or prevent your users from altering them. You may also want to consider compressing batch files to save some disk space on the systems where compressed files are used.

The full syntax for the batch compression command is

```
BATCOMP [/Ekkkk /K][/Q][/O] InputFile [OutputFile]
```

You must specify the full name of the input file, including its extension, on the BATCOMP command line. If you do not specify the output file, BATCOMP will use the same base name as the input file and add a •BTM extension. For example, to compress MYBATCH.CMD and save the result as MYBATCH.BTM, you can use either one of these commands:

```
batcomp mybatch.cmd
batcomp mybatch.cmd mybatch.btm
```

If the output file (*MYBATCH.BTM* in the examples above) already exists, BATCOMP will prompt you before overwriting the file. You can disable the prompt by including **/O** on the BATCOMP command line immediately before the input file name. Even if you use the **/O** option, BATCOMP will not compress a file into itself.

By default, BATCOMP does not remove comment lines, i.e. lines starting with **REM** or ::, since in some instances, such as when a comment line occurs between a TEXT and ENDTEXT, the compressed file would behave differently from the original by not displaying the comment line. To override that default and force deletion of comment lines, use the **/K** option. Lines starting with "REM >" (used to create a new, empty file, or to delete the old contents of one) are never considered comments to be removed.

The /Q ("quiet") option suppresses informational messages from BATCOMP.

JP Software does not provide a utility to decompress batch files. If you use BATCOMP, make sure that you also keep a copy of the original batch file for future inspection or modification.

You can adopt one of two strategies for keeping track of your original source files and compressed batch files. First, you may want to create the source files with a *.BAT* or *.CMD* extension and reserve the *.BTM* extension for compressed batch files. The advantage of this approach is that you can modify

and test the uncompressed versions at any time, although they will run in the slower, traditional mode unless they begin with a LOADBTM command.

If you prefer, you can use a .BTM extension for both the source and compressed files. In this case you will have to use a different directory or a different base name for each file. For example, you might use SOURCEMYBATCH.BTM for the source file and COMPWYBATCH.BTM for the compressed version, or use MYBATCHS.BTM for the source file and MYBATCH.BTM for the compressed file (however, the latter approach may make it more difficult to keep track of the correspondence between the source file and the compressed file).

If you plan to distribute batch files to users of different platforms, see Special Character Compatibility for important information on the command separator, escape character, and parameter character used in each product.

The BATCOMP (see command replaces the external program BATCOM32.EXE which was included in previous versions and is now obsolete.

3.12.2.15 REXX Support

REXX is a powerful file and text processing language developed by IBM, and available on many platforms. REXX is an ideal extension to the *TCC* batch language, especially if you need advanced string processing capabilities.

The REXX language is not built into **TCC**, and must be obtained separately through (free) add-on REXX software, such as Open Object REXX (http://regina-rexx.sourceforge.net/).

TCC automatically recognizes the presence of a REXX interpreter on your system. When **TCC** loads, it asks Windows to locate specific REXX libraries associated with Open Object REXX or Regina REXX. Specifically, it looks for *REGINA.DLL*, *WREXX32.DLL*, *RXREXX.DLL*, *REXX.DLL*, or *REXXAPI.DLL*. If a suitable library is found, **TCC** checks to see if you are running a **.REX** or **.REXX** file, or if the first two characters on the first line of a **.** *CMD* file are [/*], the beginning of a REXX comment. If either of these tests succeeds, **TCC** passes the file to your REXX interpreter for processing.

(TC) When working with a REXX processor, **TCC** automatically handles all input and output for the REXX program, and any standard REXX processor window for input and output is not displayed. If you need to run a REXX program inside your REXX processor's window, and not under **TCC**, you should start the REXX processor's executable file explicitly, then load and run the REXX program from there.

When you send a command from a REXX program back to **TCC** to be executed (for example, if you execute a DIR command within a REXX script), the REXX software must use the correct address for **TCC**. **TCC** uses the address **CMD**.

For details on communication between REXX and **TCC**, or for more information on any aspect of REXX, see your REXX documentation.

See also: the @REXX 457, @PERL 452 and @RUBY 458 functions.

3.12.2.16 Perl support

Perl is a powerful file and text processing language available on many platforms. Perl is an ideal extension to the *TCC* batch language, especially if you need advanced string processing capabilities.

The Perl language is not built into **TCC**, and must be obtained separately. The version supported by **TCC** is Active State Perl 5.8 (free from www.activestate.com).

TCC automatically recognizes the presence of a Perl interpreter on your system. If a suitable library is

found, **TCC** checks to see if you are running a **.PL** file. If so, **TCC** passes the file to your Perl interpreter for processing.

See also: the @PERL 4521, @REXX 4571 and @RUBY 4581 functions.

3.12.2.17 Ruby support

Ruby is a powerful object-oriented file and text processing language available on many platforms. Ruby is an ideal extension to the *TCC* batch language, especially if you need advanced string processing capabilities.

The Ruby language is not built into **TCC**, and must be obtained separately. The version supported by **TCC** is Ruby 1.8 (free from www.ruby-lang.org).

TCC automatically recognizes the presence of a Ruby interpreter on your system. If a suitable library is found, **TCC** checks to see if you are running a **.rb** file. If so, **TCC** passes the file to your Ruby interpreter for processing.

See also: the @RUBY 458, @REXX 457 and @PERL 452 functions.

3.12.2.18 EXTPROC and SHEBANG Support

TCC offers an external processor option for batch files that lets you define an external program to process a particular .*CMD* file. To identify a .*CMD* file to be used with an external processor, place the string **EXTPROC** as the first word on the first line of the file, followed by the name of the external program that should be called. **TCC** will start the program and pass it the name of the .*CMD* file and any command line parameters that were entered.

For example, suppose *GETDATA.CMD* contains the following lines:

```
EXTPROC D:\DATAACQ\DATALOAD.EXE
OPEN PORT1
READ 4000
DISKWRITE D:\DATAACO\PORT1\RAW
```

Then if you entered the command:

```
[d:\dataacq] getdata /p17
```

TCC would read the *GETDATA.CMD* file, determine that it began with an EXTPROC command, read the name of the processor program, and then execute the command:

```
D:\DATAACQ\DATALOAD.EXE D:\DATAACQ\GETDATA.CMD /p17
```

The hypothetical *DATALOAD.EXE* program would then be responsible for reopening the *GETDATA.CMD* file, ignoring the EXTPROC line at the start, and interpreting the other instructions in the file. It would also have to respond appropriately to the command line parameter entered (/p17).

Do not try to use **TCC** as the external processor named on the EXTPROC line in the .CMD file. It will interpret the EXTPROC line as a command to reopen itself. The result will be an infinite loop that will continue until the computer runs out of resources and locks up.

TCC also provides **SHEBANG** support. It works identically to **EXTPROC**, but the first line begins with a #!.

Note that EXTPROC and SHEBANG only work with files with a .CMD extension, not .BTM or .BAT.

3.13 TCC (4NT) Internal Commands

TCC (formerly **4NT**) gives you instant access to more than 150 internal commands. (By contrast, Microsoft's CMD.EXE 484) has fewer than 40 internal commands.) The best way to learn about commands is to experiment with them. This section will help you find the one(s) that you need, categorized in the lists below by name and by category.

- ▶ Commands By Name 144
- ► Commands By Category 147

Note: Remember that you can replace any internal command with an ALIAS 154 or plugin 293, or disable an internal command with SETDOS /I 323.

3.13.1 Commands by Name

See also: Internal Commands Listed by Category 147)

	Description
? 152	Display list of internal commands or Prompt to execute a command
ACTIVATE 152	Activate or set window state
ALIAS 154	Define or display aliases
ASSOC 162	Windows file associations
ATTRIB 163	Change or display file attributes
BATCOMP 166	Batch file compression
BDEBUGGER 166	Batch file debugger
BEEP 173	Beep the speaker
BREAK 174	Define or display Ctrl-C state
BREAKPOINT 174	Set a batch debugger breakpoint
CALL 175	Call another batch file
CANCEL 176	End batch file processing
CD 177	Display or change directory
CDD 178	Change drive and directory
CHCP 180	Display or change code page
CHDIR 177	Display or change directory
CLS 181	Clear the display window
COLOR 18th	Change the display colors
COPY 182	Copy files and/or directories
DATE 189	Display or change date
DEBUGSTRING 190	Send text to system debugger
DEFER 190	Defer a command until batch file exit
DEL 190	Delete files and/or directories
DELAY 194	Wait for specified time
DESCRIBE 195	Display or change descriptions
DETACH 197	Start app detached
DIR 198	Display files and/or directories
DIRHISTORY 208	Display directory history list
DIRS 209	Display directory stack

	la
DO 210	Create batch file loops
DRAWBOX 214	Draw a box
DRAWHLINE 215	Draw a horizontal line
DRAWVLINE 216	Draw a vertical line
ECHO 217	Echo a message
ECHOERR 217	Echo a message to stderr 535
ECHOS 219	Echo a message with no CR/LF
ECHOSERR 219	Echo with no CR/LF to stderr 535
EJECTMEDIA 220	Eject a removable drive
ENDLOCAL 220	Restore from a SETLOCAL
ERASE 190	Delete files and/or directories
ESET 222	Edit variables or aliases
EVENTLOG 223	Write Windows event log
EVENTMONITOR	Monitor event log
224	•
EXCEPT 225	Exclude files from a command
EXIT 227	Exit TCC
FFIND 227	Search for files or text
FIREWIREMONITO	Monitor FireWire devices
R 232	
FOLDERMONITOR 232	Monitor folders and/or files
FOR 234	Repeat a command
FREE 24	Display disk space
FTYPE 241	Display or edit file types
FUNCTION 242	Create or edit user functions
GLOBAL 245	Run command in subdirectories
GOSUB 247	Call batch subroutines
GOTO 248	Branch in a batch file
HEAD 249	Display beginning of file
HELP 251	Help for internal commands
HISTORY 25	Display or change history
IF 253	Conditional command execution
IFF 254	Conditional command execution
IFTP 255	Open FTP connection
INKEY 257	Get a single keystroke
INPUT 259	Get a text string
JABBER 260	Send an IM
KEYBD 261	Set keyboard toggles
KEYS 261	Enable or disable history list
KEYSTACK 262	Send keystrokes to app
LIST 264	Display content of files
LOADBTM 269	Load batch file as .BTM
LOADMEDIA 269	Close CD-ROM / DVD drive door
LOG 269	Save log of commands
MD 271	Create subdirectories
MEMORY 272	
IVIEIVIUR I 12121	Display memory statistics

MKDIR 271	Create subdirectories
MKLNK 273	Create NTFS hard or soft link
MOVE 274	Move files or directories
MSGBOX 279	Popup message box
NETMONITOR 282	Monitor networks
ON 282	Batch file error trapping
OPTION 284	Configure the <i>TCC</i> console
OSD 286	Display floating text
PATH 286	
PAUSE 287	Set or display PATH
PAUSE 287 PDIR 288	Wait for input User-formatted DIR
PLAYAVI 29	
PLAYSOUND 292	Display an .AVI file
	Play a sound file
PLUGIN 293 POPD 294	Load or unload plugin DLL
POPD 294 POSTMSG 294	Restore from directory stack
PRINT 295	Send a message to a Window Print a file
PRINT 12951	
	Set process priority
PROCESSMONITO R 296	Monitor processes
PROMPT 297	Change command line prompt
PUSHD 299	Save directory to stack
QUERYBOX 300	Popup input box
QUIT 30th	Exit batch file
RD 301	Remove subdirectory
REBOOT 303	Reboot system
RECYCLE 304	Display or empty recycle bin
REXEC 308	Remotely execute commands
REM 304	Remark
REN 305	Rename files or directories
RENAME 305	Rename files or directories
RETURN 307	Return from GOSUB
RMDIR 30th	Remove subdirectory
RSHELL 309	Remotely execute commands
SCREEN 310	Position cursor
SCRPUT 31h	Write directly to screen
SELECT 312	Select files for a command
SENDMAIL 316	Send email
SERVICEMONITOR	Monitor Windows services
SERVICES 319	Display stop or start system consisses
SET 319	Display, stop, or start system services Set or display environment variables
SETDOS 323	
SETLOCAL 326	Set or display console options
SETLOCAL (326)	Save environment, aliases and functions
SHIFT 327	Shift batch file parameters
SHORTCUT 328	Create a Windows shortcut
01101(1001	Ordate a villuows shortcut

CLIDALIAC	Chara aliana
SHRALIAS 329 SMPP 330	Share aliases
	Simple message transfer
SNMP 330	Send SNMP traps
SNPP 331	Send message to pager
START 33	Start a new session
SWITCH 335	Batch file switch / case
SYNC 336	Synchronize directories
TAIL 339	Display end of file
TASKDIALOG 341	Popup Vista task dialog
TASKEND 342	End a task
TASKLIST 342	Display Windows task list
TCFILTER 343	Filter Take Command List View
TCTOOLBAR 343	Edit Toolbar
TEE 344	Pipe "tee-fitting"
TEXT 345	Display text in batch file
TIME 347	Set or display time
TIMER 347	Stopwatch
TITLE 349	Set window title
TOUCH 349	Change file timestamps
TRANSIENT 352	Toggle shell transient mode
TREE 352	Display directory tree
TRUENAME 353	Display true pathname
TYPE 354	Display files
UNALIAS 355	Remove aliases
UNFUNCTION 356	Remove user-defined functions
UNSET 357	Remove environment variable
USBMONITOR 358	Monitor USB devices
VER 359	Display version
VERIFY 360	Display or set disk verification
VOL 360	Display or set disk volume label
VSCRPUT 360	Write text vertically
WHICH 36h	Display command information
WINDOW 362	Window management
WMIQUERY 364	WMI queries
Y 364	Pipe "y-fitting"
_	. , ,

3.13.2 Commands by Category

See also: Internal Commands Listed by Name 1441

The best way to learn about commands is to experiment with them. The lists below categorize the available commands by topic and will help you find the one(s) you need.

- File and directory management Subdirectory management 1481

- Input and output 149
- Window management commands 149
 Commands primarily for use in or with batch files and aliases 149
 Environment and path commands 150
- System configuration and status Monitoring commands
- Other commands 15

File and directory management

	Description
ATTRIB 163	Change or display file attributes
COPY 182	Copy files and/or directories
DEL 190	Delete files and/or directories
DESCRIBE 195	Display or change descriptions
ERASE 190	Delete files and/or directories
FFIND 227	Search for files or text
HEAD 249	Display beginning of file
IFTP 255	Open FTP connection
LIST 264	Display contents of files
MOVE 274	Move files or subdirectories
RECYCLE 304	Display or empty recycle bin
REN 305	Rename files or directories
RENAME 305	Rename files or directories
SELECT 312	Select files for a command
SYNC 336	Synchronize directories
TAIL 339	Display end of file
TOUCH 349	Change file dates/times
TREE 352	Display directory tree
TRUENAME 353	Display true pathname
TYPE 354	Display files
<u>Y</u> 364	Pipe "y-fitting"

Subdirectory management

	Description
CD 177	Display or change directory
CDD 178	Change drive and directory
CHDIR 177	Display or change directory
DIR 198	Display files and/or directories
DIRS 209	Display directory stack
MD 271	Create subdirectories
MKDIR 27	Create subdirectories
MKLNK 273	Create NTFS hard or soft link
PDIR 288	User-formatted DIR
POPD 294	Restore from directory stack
PUSHD 299	Save directory to stack
RD [301]	Remove subdirectory
RMDIR 301	Remove subdirectory

Input and output

	Description
DRAWBOX 214	Draw a box
DRAWHLINE 215	Draw a horizontal line
DRAWVLINE	Draw a vertical line
ECHO 217	Echo a message
ECHOERR 217	Echo a message to stderr
ECHOS 219	Echo a message with no CR/LF
	Echo with no CR/LF to stderr
INKEY 257	Get a keystroke
INPUT 259	Get an input line
KEYSTACK 262	Send keystrokes to app
MSGBOX 279	Popup message box
OSD 286	Display floating text
PLAYAVI 29	Play an .AVI file
PLAYSOUND	Play a sound file
PRINT 295	Print a file
	Popup input box
SCREEN 310	Position cursor
SCRPUT 311	Write directly to screen
SENDMAIL 316	Send email
SMPP 330	Send SMS message
SNMP 330	Send SNMP trap
SNPP 33	Send message to pager
TASKDIALOG	Popup Vista task dialog
VSCRPUT 360	Write text vertically

Window management commands

	Description
ACTIVATE 152	Activate or set window state
POSTMSG 294	Send a message to a Window
TITLE 349	Set window title
WINDOW 362	Window management

Commands primarily for use in or with batch files and aliases

(some work only in batch files; see the individual commands for details)

	Description
	Define or display aliases
BATCOMP 166	Batch file compression
BDEBUGGER 166	Batch file debugger
BEEP 173	Beep the speaker
BREAKPOINT 174	Set a batch debugger breakpoint

CALL 175	Call another batch file
CANCEL 176	End batch file processing
DEBUGSTRING	Send text to system debugger
190	
DEFER 190	Defer a command until the batch file exits
DELAY 1941	Wait for specified time
DO 210	Batch file looping
ENDLOCAL 220	Restore a SETLOCAL
EJECTMEDIA 220	Eject a removable drive
FOR 234	Repeat a command
FUNCTION 242	Create or edit user functions
GLOBAL 245	Run command in subdirectories
GOSUB 247	Call batch subroutines
GOTO 248	Go to a batch file label
IF 253	Conditional command execution
IFF 254	Conditional command execution
JABBER 260	Send an IM
LOADBTM 269	Load batch files as .BTM
LOADMEDIA 269	Close CD-ROM / DVD drive door
ON 282	Batch file error trapping
PAUSE 287	Wait for input
QUIT 30th	Exit batch file
REM 304	Remark
RETURN 307	Return from GOSUB
SETLOCAL 326	Save environment, aliases, and functions
SHIFT 327	Shift batch file parameters
SWITCH 335	Batch file switch / case
TEXT 345	Display text in batch file
TRANSIENT 352	Toggle shell transient mode
UNALIAS 355	Remove aliases
UNFUNCTION 356	Remove user-defined functions

Environment and path commands

	Description
ESET 222	Edit variables or aliases
PATH 286	Set or display PATH
SET 319	Set or display environment variables
UNSET 357	Remove environment variables

System configuration and status

	Description
ASSOC 162	Windows file associations
BREAK 174	Define or display Ctrl-C state
CHCP 180	Display or change code page
CLS 18th	Clear the display window
COLOR 18th	Change the display colors

DATE 189	Display or change date
DIRHISTORY	Display directory history list
208	
EVENTLOG 223	Write to Windows event log
FREE 241	Display disk space
FTYPE 241	Display or edit file types
HISTORY 25	Display or change history
KEYBD 261	Set keyboard toggles
KEYS 261	Enable or disable history list
LOG 269	Save log of commands
MEMORY 272	Display memory statistics
OPTION 284	Configure the <i>TCC</i> console
PLUGIN 293	Load or unload plugin DLL
PROMPT 297	Change command line prompt
REBOOT 303	Reboot system
SETDOS 323	Internal options
SERVICES 319	Display, stop, or start services
SHORTCUT 328	Create a Windows shortcut
TASKEND 342	End a task
TASKLIST 342	Display Windows task list
TCFILTER 343	Filter <i>Take Command</i> List View
TCTOOLBAR	Edit <i>Take Command</i> toolbar
343	
TIME 347	Set or display time
VERIFY 360	Display or set disk verification
VER 359	Display version
VOL 360	Display or set disk volume label

Monitoring commands

	Description
EVENTMONITOR 224	Monitor event log
FIREWIREMONITOR 232	Monitor FireWire devices
	Monitor folders and/or files
NETMONITOR 281	Monitor network connections
PROCESSMONITOR 296	Monitor processes
SERVICEMONITOR 318	Monitor Windows services
USBMONITOR 358	Monitor USB devices

Other commands

	Description
<u>?</u> 152	Display list of internal commands, or prompt to execute a command
DETACH 197	Start app detached
EXCEPT 225	Exclude files from a command
EXIT 227	Exit TCC

HELP 25	<i>TCC</i> help
SHRALIAS 329	Share aliases & functions
START 33	Start a new session
REXEC 308	Remotely execute command
RSHELL 309	Remotely execute command
TEE 344	Pipe "tee-fitting"
TIMER 347	Stopwatch
WHICH 36T	Display command information

3.13.3 ?

Purpose: Display a list of internal and plugin commands, or prompt for a command.

Format: ? ["prompt" command]

Usage:

The ? command has two separate meanings:

- 1. When you use the ? command by itself, it displays a list of internal and plugin commands. For help with any individual command, see the HELP [25] command. If you have disabled a command with SETDOS / [323], it will not appear in the list.
- 2. The second function of ? is to prompt the user before executing a specific command line. If you add a *prompt* and a *command*, ? will display the prompt followed by (Y/N)? and wait for the user's response. If the user presses Y or y, the command line will be executed. If the user presses N or n, it will be ignored.

Example

```
? "Load the network" call netstart.btm
```

When this command is executed, you will see the prompt

```
Load the network (Y/N)?
```

If you answer Y, the CALL 175 command will be executed:

3.13.4 ACTIVATE

Purpose: Activate a window, set its state, or change its title.

Format: ACTIVATE [/R] "title" [MAX | MIN | RESTORE | CLOSE | ENABLE | DISABLE | TOPMOST

| NOTOPMOST | TOP | BOTTOM | HIDE | /POS=left,top,width,height | /TRANS=n | TRAY

| "newtitle"]

title Current title of the window to be activated

left New location of the left border of the window, in pixelstop New location of the top border of the window, in pixels

widthheightNew width of the window, in pixelsNew height of the window, in pixels

newtitle New title for window

/R(estore original window)

See also: START 331, TITLE 349, and WINDOW 362).

Usage:

ACTIVATE 1521 activates, and optionally modifies, another session's window. It is not intended to modify the characteristics of the current **TCC** session (use TITLE 349) or WINDOW 3621 for that purpose).

Title specifies the name of the target window to be activated. You can use wildcards , in title. This is useful with applications that change their window title to reflect the file currently in use. **Title** must be enclosed in quotes.

Each execution of ACTIVATE allows you to modify one property of the target window. To perform multiple operations, use multiple ACTIVATE commands.

The options are:

Expands the window to its maximum size and activates it.
Reduces the window to an icon.
Activates the window at its default size and location.
Sends a "close" message to close the window.
Enable mouse and keyboard input
Disable mouse and keyboard input
Sets the window position and size (in pixels).
Keeps the window on top of all other windows until it closes, or NOTOPMOST is used.
Transparency level, where n=0 (invisible) to 255 (opaque) (does not work for console windows)
Allows other windows to overlay the window (this is the normal state for most windows).
Moves the window to the top of the window order, above all other non- TOPMOST windows.
Moves the window to the bottom of the window order.
Makes the window invisible (to make the window visible again, use RESTORE).
Move the specified window to the system tray.
Changes the window title.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

If you specify *newtitle*, it must be enclosed in double quotes (which will not appear as part of the title text).

ACTIVATE is often used before KEYSTACK to make sure the proper window receives the keystrokes.

ACTIVATE works by sending messages to the named *window*. If the window ignores or misinterprets the messages, ACTIVATE may not have the effect you want.

If ACTIVATE is used in a batch file, and the batch file is not itself running in the active window (the window with its title bar highlighted), then ACTIVATE may not activate the desired window. This is because under Windows you cannot make another window active except when the window which issues the command is itself active already. This is a Windows feature which helps to prevent windows which are not in the foreground from grabbing input intended for other windows.

Example

The example below first maximizes, and then renames the window originally called "Take Command":

```
activate "Take Command" max
activate "Take Command" "Take Command is Great!"
```

3.13.5 ALIAS

Purpose: Create new command names that execute one or more commands or redefine default

options for existing commands; assign commands to keystrokes; load or display the list of

defined alias names.

Format: Display mode:

ALIAS [/G /L /P] [wildname]

Definition mode:

ALIAS /R [file...] | name[=]value

file One or more input files to read alias definitions from

wildname Name of alias whose definition is to be displayed (may contain * and ?

wildcards)

nameName for an alias, or for the key to execute the aliasvalueText to be substituted for the alias name or key

/G(lobal) 162 /P(ause) 162 /R(ead file) 162 /R(ead file) 162

See also: UNALIAS 355, ESET 222, and Aliases 128.

Usage:

- Overview 154
- Displaying Aliases 155
- Multiple Commands and Special Characters in Aliases 1551
- Nested Aliases 156
- Temporarily Disabling Aliases 156
- Partial (Abbreviated) Alias Names 157
- Keystroke Aliases 157
- Saving and Reloading Your Aliases 159
- Alias Parameters 159
- Expanding Aliases at the Prompt 1601
- Local and Global Aliases 160
- Retaining Global Aliases with SHRALIAS 161
- The PRE_INPUT, PRE_EXEC, and POST_EXEC Aliases 161
- ► The UNKNOWN_CMD Alias 16th
- Warnings 162

Overview

The ALIAS command lets you create new command names or redefine internal commands. It also lets you assign one or more commands to a single keystroke. An alias is often used to execute a complex series of commands with a few keystrokes or to create "in memory batch files" that run much faster than disk-based batch files.

For example, to create a single-letter command **d** to display a wide directory, instead of using DIR 1981 /W, you could use the command:

```
alias d = dir /w
```

Now when you type a single **d** as a command, it will be translated into a **DIR /W** command.

If an ALIAS command specifies a *value*, and there was an alias already assigned to *name*, the old alias value is discarded.

If you define aliases for commonly used application programs, you can often remove the directories they're stored in from the PATH set. For example, if you use Microsoft Word and had the *C:\WINWORD* directory in your path, you could define the following alias:

```
alias ww = c:\winword\winword.exe
```

With this alias defined, you can probably remove *C:\WINWORD* from your path. Word will now load more quickly than it would if *TCC* had to search the <u>PATH</u> for it. In addition, <u>PATH</u> can be shorter, which will speed up searches for other programs.

If you apply this technique for each application program, you can often reduce your PATH 368 to just two or three directories containing utility programs, and significantly reduce the time it takes to load most software on your system. Before removing a directory from the PATH 368, you will need to define aliases for all the executable programs you commonly use which are stored in that directory.

TCC also supports Directory Aliases 76, a shorthand way of specifying pathnames.

Aliases are stored in memory, and are not saved automatically when you turn off your computer or end your current *TCC* session. See below for information on saving and reloading your aliases.

Displaying Aliases

If you want to see a list of all currently defined aliases, type:

```
alias
```

You can view the definition of a single alias. For example, if you want to see the definition of the alias **LIST**, you can type:

```
alias list
```

You can also view the definitions for all aliases matching a specific pattern by specifying a single parameter containing wildcards (* or ?). For example:

```
alias *win*
```

will display all aliases containing the string win.

You can use the /P 157 option to control display scrolling when displaying aliases.

Multiple Commands and Special Characters in Aliases

An alias can represent more than one command. For example:

```
alias letters = `cd \letters & tedit`
```

This alias creates a new command called **LETTERS**. The command first uses **CD** 177 to change to a subdirectory called **LETTERS** of the directory current at the time of its execution, and then runs a program called **TEDIT**.

Aliases make extensive use of the <u>command separator</u> [120], and the <u>parameter character</u> [51], and may also use the escape character [124].

When an alias contains multiple commands, the commands are executed one after the other. However, if any of the commands runs an external Windows application, you must be sure the alias will wait for the application to finish before continuing with the other commands. This behavior is controlled by the **Wait for completion** setting in the configuration dialogs [46].

When you use the alias command at the command prompt or in a batch file, you must use back quotes ` around the alias definition if it contains multiple commands, or parameters (discussed below), or environment variables, or variable functions, or redirection, or piping. If you do not use back quotes, parameters, variables and functions are evaluated, and redirection or piping performed during the alias definition, and only the first command becomes part of the alias, the remaining ones are performed immediately. The back quotes prevent this premature expansion. You may use back quotes around other definitions, but they are not required. You do not need back quotes when your aliases are loaded from an ALIAS /R file; see below for details. The examples above and below include back quotes only when they are required.

Nested Aliases

Aliases may invoke internal commands, external commands, or other aliases. However, an alias may not invoke itself, except in special cases where an IF 253 or IFF 254 command is used to prevent an infinite loop. The two aliases below demonstrate alias nesting (one alias invoking another). The first line defines an alias which runs in the current directory, and executes **Word** located in the **E:** \WINWORD\. The second alias changes directories with the PUSHD 299 command, runs the **WP** alias, and then returns to the original directory with the POPD 294 command:

```
alias wp = e:\winword\winword.exe
alias w = `pushd c:\wp & wp & popd`
```

The second alias above could have included the full path and name of **WINWORD.EXE** instead of calling the **WP** alias. However, writing two aliases makes the second one easier to read and understand, and makes the first alias available for independent use. If you rename the **WINWORD.EXE** program or move it to a new directory, only the first alias needs to be changed.

Temporarily Disabling Aliases

If you put an asterisk * immediately before a command in the *value* of an alias definition (the part after the equal sign), it tells *TCC* not to attempt to interpret that command as another (nested) alias. An asterisk used this way must be preceded by a space or the command separator and followed immediately by an internal or external command name.

By using an asterisk, you can redefine the default options for any internal or external command. For example, suppose that you always want to use the DIR options command with the /2 (two column) and /P (pause at the end of each page) options:

```
alias dir = *dir /2/p
```

If you didn't include the asterisk, the second DIR on the line would be the name of the alias itself, and *TCC* would repeatedly re invoke the **DIR** alias, rather than running the <u>DIR</u> of command. This would cause an "Alias loop" or "Command line too long" error. The asterisk forces interpretation of the second <u>DIR</u> 1981 as a command, not an alias.

An asterisk also helps you keep the names of internal commands from conflicting with the names of external programs. For example, suppose you have a program called *DESCRIBE.EXE*. Normally, the internal DESCRIBE 1951 command will run anytime you type DESCRIBE. But two simple aliases will

give you access to both the DESCRIBE.EXE program and the DESCRIBE 1951 command:

```
alias describe = c:\winutil\describe.exe
alias filedesc = *describe
```

The first line above defines **describe** as an alias for the *DESCRIBE.EXE* program. If you stopped there, the external program would run every time you typed DESCRIBE and you would not have easy access to the internal <u>DESCRIBE [195]</u> command. The second line defines **FILEDESC** as a new name for the internal <u>DESCRIBE [195]</u> command. The asterisk is needed in the second command to indicate that the following word means the internal command <u>DESCRIBE [195]</u>, not the **describe** alias which runs your external program.

Another way to understand the asterisk is to remember that a command is always checked for an alias first, then for an internal or external command, or a batch file. The asterisk at the beginning of a command name simply skips over the usual check for aliases when processing that command, and allows **TCC** to go straight to checking for an internal command, external command, or batch file.

You can prevent alias expansion by using an asterisk before a command that you enter at the command line or in a batch file. This can be useful when you want to be sure you are running the original command and not an alias with the same name, or temporarily defeat the purpose of an alias which changes the meaning or behavior of a command. For example, above we defined an alias for DIR which made directories display in 2-column paged mode by default. If you wanted to see a directory display in the normal single-column, non-paged mode, you could enter the command *DIR and the alias would be ignored for that command.

You can disable aliases temporarily with the SETDOS /X 323 command.

Partial (Abbreviated) Alias Names

You can also use an asterisk in the *name* of an alias. When you do, the characters following the asterisk are optional when you invoke the alias command. (Use of an asterisk in the alias *name* is unrelated to the use of an asterisk in the alias *value* discussed above.) For example, with this alias:

```
alias wher*eis = dir /s /p
```

The new command, *WHEREIS*, can be invoked as WHER, WHERE, WHEREI, or WHEREIS. Now if you type:

```
where myfile.txt
```

The WHEREIS alias will be expanded to the command:

```
dir /s /p myfile.txt
```

Keystroke Aliases

There are two kinds of keystroke aliases: insert-only 157 and autoexecute 1581.

Insert-only Keystroke Aliases

Assignment: To assign an insert-only alias to a keystroke, use the key name on the left side of the equal sign, preceded by one at sign @, and the value of the alias on the right side of the equal sign:

```
alias @key=value
```

Operation: When you press the key to which you assigned an insert-only alias, **TCC** displays and inserts the alias value in the current command line, at the current cursor position. If your command line

editing mode is overwrite, and the cursor is not at the end of the line, the alias value will overwrite part of the command line. You can continue to edit the command line, e.g., adding other parameters to the command. You must press **Enter** to execute the command.

Examples:

To assign the command **DIR** /**W** to the **F4** key, type:

```
alias @F4 = dir /w
```

To use it, press **F4** at the command prompt, and **DIR** /**w** will be placed on the command line for you. You can type additional parameters if you wish, and press **Enter** to execute the command. With the example alias, you can define the files that you want to display after pressing **F4** and before pressing **Enter** to execute the command.

You can also define a keystroke alias to insert a frequently used string into the middle of a command, e.g.,

```
alias @shift-F4 =%@expand[
```

which specific example can assist in processing wildcards for a program without such a feature.

Autoexecute Keystroke Aliases

Assignment: To assign an autoexecute alias to a keystroke, use the key name on the left side of the equal sign, preceded by two at signs @@, and the value of the alias on the right side of the equal sign:

```
alias @@key=value
```

Operation: When you press the key to which you assigned an autoexecute alias, **TCC** inserts the alias value in the current command line, at the current cursor position. If your command line editing mode is overwrite, and the cursor is not at the end of the line, the alias value will overwrite part of the command line. After the insertion/overwrite the command line is automatically executed.

Example: This command will assign an alias to the **F11** key that uses the CDD 178 command to take you back to the previous default directory:

```
alias @@f11 = cdd -
```

Special Considerations for Keystroke Aliases

When you define keystroke aliases, the assignments will only be in effect at the command line, not inside application programs or batch files.

To insure that a keystroke alias, esp. an autoexecute one, is on the command line by itself, use the character defined by the <u>EraseLine alias</u> option (by default, the **Esc** key, best represented as **%=e**) as the first character of the alias value.

To force a visible indication that an autoexecute keystroke alias was used, include a descriptive $\frac{\text{ECHO}}{217}$ command in the alias value.

Be careful not to assign aliases to keys that are already used at the command line (e.g., **F1** for HELP [25]). The command line meanings take precedence and the keystroke alias will never be invoked. If you want to use one of the command line keys for an alias instead of its normal meaning, you must first disable its default use with the NormalKey [31] or NormalEditKey [35] options.

The value of an alias, including a keystroke alias, may contain only characters. It cannot contain

representations of keys such as F1 .. F12, Home, etc.

See Keys and Key Names 515 for a complete listing of key names and a description of the key name format.

Saving and Reloading Your Aliases

You can save your aliases to a file:

```
alias > alias.lst
```

You can then reload all the alias definitions in the file the next time you start up with the command:

```
alias /r alias.lst
```

This is much faster than defining each alias individually in a batch file. If you keep your alias definitions in a separate file which you load when **TCC** starts, you can edit them with a text editor, reload the edited file with **ALIAS**/**R**, and know that the same alias list will be loaded the next time you start **TCC**.

When you define aliases in a file that will be read with the **ALIAS/R** command, you do not need back quotes around the value, even if back quotes would normally be required when defining the same alias at the command line or in a batch file.

To remove an alias, use the UNALIAS 355 command.

Alias Parameters

Aliases can use command line parameters or parameters like those in batch files. The command line parameters are numbered from %0 to %511. (%0 contains the alias name.) You can use double quotes to pass spaces, tabs, commas, and other special characters in an alias parameter; see Parameter Quoting (Alias examples in this section assume the *TCC* default of ParameterChar=\$.)

Parameters that are referred to in an alias, but which are missing on the command line, appear as empty strings inside the alias. For example, if you only put two parameters on the command line, any reference in the alias to %3 or any higher-numbered parameter will be interpreted as an empty string.

The parameter **%n\$** has a special meaning. **TCC** interprets it to mean "the entire command line, from parameter **n** to the end." If **n** is not specified, it has a default value of **1**, so **%\$** means "the entire command line after the alias name."

The parameter %-n\$ means "the command line from parameter 1 to *n* - 1".

The special parameter **%#** contains the number of command line parameters.

For example, the following alias will change directories, perform a command, and return to the original directory:

```
alias in `pushd %1 & %2$ & popd`
```

When this alias is invoked as:

```
in c:\comm mycomm /zmodem /56K
```

The first parameter, **%1**, has the value *c:\comm.* **%2** is *mycomm*, **%3** is */zmodem*, and **%4** is */56K*. The command line expands into these three separate commands:

```
pushd c:\comm
mycomm /zmodem /56K
popd
```

This next example uses the <u>IFF</u> 254 command to redefine the defaults for <u>SET</u> 319. It should be entered on one line:

```
alias set = `iff %# == 0 then & *set /p & else & *set %$ & endiff`
```

This modifies the <u>SET [319]</u> command so that if <u>SET [319]</u> is entered with no parameters, it is replaced by SET /P (pause after displaying each page), but if <u>SET [319]</u> is followed by a parameter, it behaves normally. Note the use of asterisks (*set) to prevent alias loops.

If an alias uses parameters, command line parameters will be deleted up to and including the highest referenced parameter. For example, if an alias refers only to %1 and %4, then the first and fourth parameters will be used, the second and third parameters will be discarded, and any additional parameters beyond the fourth will be appended to the expanded command (after the *value* portion of the alias). If an alias uses no parameters, all of the command line parameters will be appended to the expanded command. A convenient way to prevent unwanted command line parameters from being appended is to add a reference to %511 within the alias.

Aliases also have full access to all variables in the environment, internal variables, and variable functions. For example, you can create a simple command line calculator this way:

```
alias calc = `echo The answer is: %@eval[%$]`
Now, if you enter:
   calc 5 * 6
The alias will display:
   The answer is: 30
```

Expanding Aliases at the Prompt

You can expand an alias on the command line and view or edit the results by pressing **CtrI-F** after typing the alias name, but before the command is executed. This replaces the alias with its contents, and substitutes values for each alias parameter, just as if you had pressed the **Enter** key. However, the command is not executed; it is simply redisplayed on the command line for additional editing.

Ctrl-F is especially useful when you are developing and debugging a complex alias, or if you want to make sure that an alias that you may have forgotten won't change the effect of your command.

Local and Global Aliases

Aliases can be stored in either a local or global list. The selection is made during *TCC* startup, using the /L or /LA START (331) or startup options (191), or by the Local Aliases (471) configuration option, or interactively with the ALIAS/G and ALIAS/L options. The global alias list is limited to 128K characters; the local alias list is limited only by memory size.

With a local alias list, any changes made to the aliases will only affect the current copy of *TCC*. They will not be visible in other shells or other sessions.

With a global alias list, all copies of *TCC*, which are started with global alias list will share the same alias list, and any changes made to the aliases in one copy will affect all other copies. This is the default for *TCC*.

There is no fixed rule for determining whether to use a local or global alias list. Depending on your work style, you may find it most convenient to use one type, or a mixture of types in different sessions or shells. We recommend that you start with the default approach, then modify it if you find a situation where the default is not convenient.

When you use <u>SETLOCAL [326]</u> / <u>ENDLOCAL [220]</u> inside a batch file, changes in alias definitions are restored by the <u>ENDLOCAL [220]</u>. However, if the session uses the global alias list, any concurrent sessions also using the global alias list are affected.

Whenever you start a second copy of *TCC* which uses a local alias list, it inherits a copy of the aliases from the previous shell. However, any changes to the aliases made in the secondary shell will affect only that shell. If you want changes made in a secondary shell to affect the previous shell, use a global alias list in both shells.

Retaining Global Aliases with SHRALIAS

If you select a global alias list for **TCC** you can share the aliases among all running copies of **TCC**. When you close all **TCC** sessions, the memory for the global alias list is released, and a new, empty alias list is created the next time you start **TCC**.

If you want the alias list to be retained in memory even when no *TCC* session is running, you need to execute the SHRALIAS (329) command, which performs this service for the global alias list, the global user-defined functions list, the global command history list, and the global directory history list. You may find it convenient to execute SHRALIAS (329) from your TCSTART (227) file.

SHRALIAS (329) retains the alias list in memory, but cannot preserve it when Windows itself is shut down. To save your aliases when restarting Windows, you must store them in a file and reload them after the system restarts. For details on how to do so, see Saving and Reloading Your Aliases (159) above.

The PRE_INPUT, PRE_EXEC, and POST_EXEC Aliases

When at the command prompt (i.e., not executing a batch file), *TCC* will look for (and execute them if found) the following aliases:

PRE_INPUT - executed immediately before accepting input for a new command line.

PRE_EXEC - executed immediately after a command line is entered (before any expansion or redirection).

POST_EXEC - executed immediately after returning from a command and before displaying the prompt.

None of these aliases will be passed any arguments.

The UNKNOWN_CMD Alias

If you create an alias with the name **UNKNOWN_CMD**, it will be executed any time *TCC* would normally issue the "Unknown command" error message. This allows you to define your own handler for unknown commands. When the **UNKNOWN_CMD** alias is executed, the command line which generated the error is passed to the alias for possible processing. For example, to just display the command that caused the error:

alias unknown cmd `echo Error in command "%\$"`

If the **UNKNOWN_CMD** alias contains an unknown command, it will call itself repeatedly. If this occurs, **TCC** will loop up to 10 times, then display the **UNKNOWN_CMD loop** error.

Warnings

When you define an alias in the command line (i.e., without using the /R left option), variables and functions not protected by back quotes or doubled % signs are immediately evaluated, and the result becomes part of the alias value.

Syntax errors in an alias are not detected until the alias is executed.

Options:

- **/G** Switch from a local to a global alias list.
- **/L** Switch from a global to a local alias list.
- This option is only effective when ALIAS is used to display existing definitions. It pauses the display after each page and waits for a keystroke before continuing (see Page and File Prompts 102).
- /R This option loads an alias list from a file. The format of the file is the same as that of the ALIAS display:

name=value

where **name** is the *name* of the alias and **value** is its *value*. You can use an equal sign = or space to separate **name** and **value**. Back quotes are not required around the value. Variables and functions referenced in the definitions remain in the definitions, to be evaluated each time the alias is executed. You can add comments to the file by starting each comment line with a colon: You can load multiple files with one **ALIAS**/R command by placing the names on the command line, separated by spaces:

```
alias /r alias1.lst alias2.lst
```

Each definition in an **ALIAS /R** file can be up to 8,191 characters long. The definitions can span multiple lines in the file if each line of the definition, except the last, is terminated with an <u>escape character</u> 1241.

ALIAS/R will read from stdin [535] if no filename is specified and input is redirected:

alias /r <

3.13.6 ASSOC

Purpose: Modify or display relationships between file extensions and file types stored in the

Windows registry.

Format: ASSOC [/P /R [file...] | [.ext[=[filetype]]]

file One or more input files to read association definitions from..ext The file extension whose file type you want to display or set.

filetype A file type stored in the Windows registry.

/P(ause) 163 /R(ead) 163

See also: FTYPE [241], and Executable Extensions [91].

Usage:

ASSOC allows you to create, modify, or display associations between file extensions and file types stored in the Windows registry.

ASSOC manages Windows file associations stored under the registry handle HKEY_CLASSES_ROOT, and discussed in more detail under Windows File Associations of your are not familiar with file associations be sure to read about them before using ASSOC.

If you invoke ASSOC with no parameters, it will display the current associations. If you include a **.ext**, with no equal sign or **filetype**, ASSOC will display the current association for that extension.

If you include the equal sign and *filetype*, ASSOC will create or update the association for extension .ext to refer to the specified file type. The valid file types depend on the contents of your Windows registry. See the FTYPE 24h command or your Windows documentation for additional details.

ASSOC cannot delete an extension from the registry. However, you can create a similar effect by associating the extension with an empty file type using **ASSOC** .ext=, without the *filetype* parameter.

ASSOC should be used with caution, and only after backing up the registry. Improper changes to file associations can prevent applications and / or the operating system from working properly.

Options:

- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102).
- /R This option loads an association list from a file. The format of the file is the same as that of the ASSOC display:

```
.ext=filetype
```

where .ext is an extension, which is to be associated with filetype.

You can load multiple files with one ASSOC /R command by placing the names on the command line, separated by spaces:

```
assoc /r assoc1.lst assoc2.lst
```

You can insert comments in the file by prefixing the line with a colon (:).

ASSOC /R will read from stdin [535] if no filename is specified and input is redirected.

3.13.7 ATTRIB

Purpose: Change or view file and subdirectory attributes.

Format: ATTRIB [/A:[[-+]rhsa] /D /E /I"text" /P /Q /S[n]] [+|-[AHIORST]] [@file] files ...

files A file, directory, or list of files or directories to process.

@file A text file containing the names of the files to process, one per line (see @file

lists 90 for details).

/A: (Attribute select) 165 /P(ause) 165

```
/D(irectories) | 165 | /Q(uiet) | 165 | /S(ubdirectories) | 165 | /I"text" (match description) | 165 |
```

Attribute flags:

Clear	Set	Attribute affected
-A	+A	archive
-H	+H	hidden
-	+1	not content indexed
-O	+0	offline
-R	+R	read-only
-S	+S	system
-T	+T	temporary

File Selection

Supports <u>attribute switches</u> (extended <u>wildcards</u> (fig. and <u>include</u> (lists) (see LFN File Searches) (see LFN File Searches

Usage:

Every file and subdirectory has attributes that can be turned on (set) or turned off (cleared): **Archive**, **Hidden**, **Not content indexed**, **Offline**, **Read-only**, **System**, and **Temporary**. For details on the meaning of each attribute, see File Attributes 494.

The ATTRIB command lets you view, set, or clear attributes for any file, group of files, or subdirectory.

You can view file attributes by entering ATTRIB without specifying new attributes (*i.e.*, without the **[+]-[AHIORST]]** part of the format), or with the **DIR** /T [198] command.

The primary use of ATTRIB is to set attributes. For example, you can set the read-only and hidden attributes for the file *MEMO*:

```
attrib +rh memo
```

Attribute options apply to the file(s) that follow the options on the ATTRIB command line. The example below shows how to set different attributes on different files with a single command. It sets the archive attribute for all .TXT files, then sets the system attribute and clears the archive attribute for TEST.COM:

```
attrib +a *.txt +s -a test.com
```

When you use ATTRIB on an LFN drive, you must double quote any file names which contain white space or special characters.

To change directory attributes, use the **/D** switch. If you give ATTRIB a directory name instead of a file name, and omit **/D**, it will append "*" to the end of the name and act on all files in that directory, rather than acting on the directory itself.

NTFS also supports **D** (subdirectory), **V** (volume label), **E** (encrypted), **C** (compressed), **J** or **L** (junction / symbolic link) and **P** (sparse file) attributes. These attributes will be displayed by ATTRIB, but cannot be altered; they are designed to be controlled only by Windows.

ATTRIB will ignore underlines in the new attribute (the **[+|-[ADHIORST]]** part of the command). For example, ATTRIB sees these 2 commands as identical:

```
attrib +a filename
```

```
attrib +__A_ filename
```

This allows you to use a string of attributes from either the <u>@ATTRIB</u> variable function or from ATTRIB itself (both of which use underscores to represent attributes that are not set) and send that string back to ATTRIB to set attributes for other files. For example, to clear the attributes of *FILE2* and then set its attributes to match those of *FILE1*:

```
attrib -arhs file2 & attrib +%@attrib[file1] file2
```

When ATTRIB encounters a +p or -p in the attribute string it treats it as equivalent to the **/D** switch, and allows modification of the attributes of a directory. When combined with @ATTRIB, or with ATTRIB's output, both of which return a **D** to signify a directory, this feature allows you to transfer attributes from one directory to another. For example, to clear the attributes of all files and directories beginning with *ABC* and then set their attributes to match those of *FILE1* (enter this on one line):

```
attrib -arhs abc* & attrib +%@attrib[file1] abc*
```

Options:

/A: Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Warning: the colon after /A is not optional.

This switch specifies which files to select, not which attributes to set. For example, to remove the archive attribute from all hidden files, you could use this command:

```
attrib /a:h -a *
```

Do not use /A: with @file lists. See @file lists 90 for details.

/D If you use the **/D** option, ATTRIB will modify the attributes of directories in addition to files (yes, you can have a hidden directory):

```
attrib /d +h c:\mydir
```

If you use a directory name instead of a file name, and omit **/D**, ATTRIB will append "*" to the end of the name and act on all files in that directory, rather than acting on the directory itself.

- /E Suppress all non-fatal error messages, such as "File Not Found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files and aliases, and when recursing through the directory hierarchy, where many directories have no files matching your selection criteria.
- /I"text" Select files by matching text in their descriptions. The text can include wildcards // and extended wildcards. The search text must be enclosed in double quotes, and must immediately follow the /I, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]". Do not use /I with @file lists. See @file lists of for details
- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102
- /Q This option turns off ATTRIB's normal screen output. It is most useful in batch files.
- If you use the **/S** option, the ATTRIB command will be applied to all matching files in the current or named directory and all of its subdirectories. Do not use **/S** with @file lists; see

@file lists 90 for details.

If you specify a number after the /S, ATTRIB will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

3.13.8 BATCOMP

Purpose: Compress and optionally encrypt batch files. See Batch File Compression 14h for

additional details.

Format: BATCOMP [/Ekkkk /K /O /Q] InputFile [OutputFile]

Inputfile A file to compress and/or encrypt.

OutputFile A file to hold the output from the command

File Selection

The single input file must be specified explicitly.

Usage:

BATCOMP is a batch file compressor and optionally allows for simple key-based encryption.

If you do not specify *OutputFile*, it defaults to the *InputFile* name with a **BTM** extension. If you specify *OutputFile*, you must give an extension or the output file will not have one. In other words there is no BTM default if you just give a file name. If *OutputFile* already exists it will not be overwritten unless /O is used.

The output BTM file will not be legible, but it will run under *TCC*. The behavior and performance of the file should be the same as if it were run in its original source form as a *.BTM* file.

Compression is not effective for very small files and may even result in a slightly larger file.

Options:

/E Specify a key (string) to be used for encryption.

/K By defaults, comments (i.e. lines starting with **REM** or :: but not **REM >**) are retained in the compressed file. /K forces those lines to be stripped for additional size reduction.

/O Forces overwriting of any existing *OutputFile*.

/Q Suppresses all progress reports (stdout [535]). Errors (stderr [535]) are still shown.

3.13.9 BDEBUGGER

Purpose: Calls the internal batch file debugger. This is an extremely powerful command that includes support for breakpoints, bookmarks, syntax coloring, and editing.

Format: BDEBUGGER [/A /B /C /E /F /I /K /N /W] batchfilename [parameters]

batchfilename Full name of the batch file to debug.

parameters parameters for the batch file

/A(lias list window) 173 /I(nactive) 173

/B(atch variable window) 173 /K(eep debugger window) 173

/C(reate new batch file) 173 /N (do Not hide the debugger window)

/E(nvironment variable window) 173 /W(atch window) 173 /W(atch window) 173

/F (user-defined Functions window) 173

Usage:

BDEBUGGER opens a special window in which a batch file can be examined, modified, and executed.

The debugger window includes a slider control on the lower left corner of the status bar to control the transparency level of the debugger window. If the debugger window is at least partially transparent, it will not be hidden while individual commands in the batch file are being executed (see the /N option).

The batch debugger window toolbar has a number of icons to control debugging. Each has a tooltip for quick reference:

New Create a new batch file. If you have an existing file open, you will be

prompted to save any changes before it exits.

Open Open an existing batch file.
Save Save the current batch file.
Print Print the current batch file.

Copy Copy the highlighted selection to the clipboard.

Cut Copy the highlighted selection to the clipboard and delete it from the file.

Paste Copy the contents of the clipboard to the current cursor location.

Find Search for text.

Replace Replace the text with other text.

Undo the last edit.

Redo Restore the last Undo.

Start Debugging Starts the debugger. The cursor will be placed on the first line.

Stop DebuggingStops the debugger.Step IntoExecute the current line.

Step Over Execute the current line but turn off the debugger for the duration of a

CALL or GOSUB.

Run to Breakpoint Execute the batch file, stopping at the next breakpoint. Sets or turns off a breakpoint on the current line.

Clear Breakpoints Turns off all breakpoints.

File Properties Displays information on the current batch file.

Start New Shell Start another copy of TCC (this is useful if you need to perform some

tasks while debugging a file.)

You can also set a breakpoint by moving the mouse cursor to the left margin of a line and left-clicking. You can only set a breakpoint on an executable line (i.e., not on a blank line, comment, label, etc.),

You can get help for the currently selected (highlighted) command / variable / function by pressing Ctrl-F1, or right-clicking the mouse and selecting **Help** from the context menu.

You can change the line to be executed next when in debugging mode with either the "GOTO" dialog or by moving the caret to the line and either right clicking & selecting "Jump to This Line" or by pressing Ctrl-Shift-F11. Note that if you attempt to jump into or out of a DO loop or IFF block, bad

things will happen!

The debugger's Watch window allows you to monitor environment variables or to pause execution when a specified condition is met. The Watch window appears at the bottom of the debugger window. Enter the variable name or expression in the left column; the debugger will automatically display the current value in the right column. You can also add a variable to the Watch window by selecting it in the main debugger window, then clicking the right mouse button and selecting "Add to Watch". If the string in the left column is a single argument, it is assumed to be a variable name. Otherwise, it is assumed to be an expression. Expressions can be anything that IF can evaluate; for example:

```
%i = 3
ERRORLEVEL GT 12
```

Note that expressions require variable names to be prefixed by a %. If you're entering a single variable argument to monitor, do not use a %.

When the value of a monitored variable changes, the Watch window will change its background color (to a light red).

Alt-F11 will invoke the Evaluate Expression dialog. Ctrl-F9 will invoke the Evaluate Expression dialog for the current selection, or if no text is selected, for the current line.

You can open popup windows to display and/or modify aliases, batch variables, environment variables, and user functions. These windows will "dock" to the outer edges of the debugger window and will move with the debugger window. The variable windows also have a toolbar, with a couple of additional buttons:

Update List Save a modified list.

Import a File Add the contents of a file to the list.

The environment variables window displays any variables changed during debugging in a different color. (The default is red; you can change it by adding a ChangeRGB=... line to BATCH.BCP with the appropriate RGB value.) You can specify variables to exclude from the environment variable window with the DebugVariableExclude variable. For example, to suppress the display of the processor and user variables:

set DebugVariableExclude=proc*;user*

Note that this option doesn't affect the existence of the variables, just whether they're displayed in the environment variable window.

If you press Ctrl-C or Ctrl-Break while debugging, you will see the prompt:

Cancel batch job filename (Y/N/A/D):

Pressing **D** will return you to single-step mode in the debugger. (This allows you to interrupt a **run-to-breakpoint** without terminating the debugger and batch file.)

The default settings for the BDEBUGGER (Batch File Debugger) command are kept in ASCII text file BATCH.BCP (in the program directory). Only modify the contents of that file if you're positive you know what you're doing. We strongly recommend that you keep a copy of the original, should your modifications prove unworkable or undesirable.

The text processing commands available in the batch debugger and variable windows are listed below. The default "hard coded" values used in the BATCH.BCP file are shown in parentheses after each command name. The text commands can be classified into general categories:

- ▶ Caret commands 169
- View commands 170
- Edit commands 170
- Mark / Clipboard commands 172
- Search commands 172
- File commands 172
- ▶ Bookmark commands 172
- ▶ Breakpoint commands 173
- Expression evaluation commands 173

• Caret commands

Right

Ctrl-Left

J	()	caret is on the last position of the current line it is moved to the first
	>	position of the next line.
Shift-Right	(2)	In addition to the caret movement this command will also extend the
	(0)	current selection to the new caret position.
Left	(3)	This command will move the caret one character to the left. When the
		caret is on the first position of the current line it is moved to the last
61.16.1.6	(4)	position of the previous line.
Shift-Left	(4)	In addition to the caret movement, this will also extend the current
11	(-)	selection to the new position.
Up	(5)	This command will move the caret one line up. The caret column position
01.14.11	(0)	will be set as close to its previous column position as possible.
Shift-Up	(6)	In addition to the caret movement this command will also extend the
D	/- \	current selection to the new position.
Down	(7)	This command will move the caret one line down. The caret column
		position will be set as close to it's previous column position as possible.
		When the caret is on the last line but not on the last column it will be
Shift-Down	(0)	moved to the last column. In addition to the caret movement this command will also extend the
Siliit-Dowii	(8)	current selection to the new position.
End	(9)	This command will move the caret to the end of the line it is currently on.
Eliu	(9)	If the caret is already at the end nothing happens.
Shift-End	(10)	In addition to the caret movement this command will also extend the
Omit-Liid	(10)	current selection to the new position.
Home	(11)	This command will move the caret to the start of the line it is currently on.
1101110	(' ' ')	If the caret is already at the start nothing happens.
Shift-Home	(12)	In addition to the caret movement this command will also extend the
	(-/	current selection to the new position.
Ctrl-Right	(13)	This command will move in one of the following ways:
J	` '	When the caret is located on a delimiter character the caret is
		moved right until the first non-delimiter and non-white space is
		found.
		When the caret is located on a non-delimiter character and not on a
		white space character the caret is moved to the start of the next
		word.
		When the caret is located on a white space the caret is moved to the
		start of the next word or the next delimiter depending on what comes
		first.
		When the caret is located on the last word, delimiters or white-space
		of the current line the caret is moved to the first word or delimiter of
		the next line.

Ctrl-Shift-Right (14) In addition to the caret movement this command will also extend the current selection to the new caret position.

(15) This command will move in one of the following ways:

(1) This command will move the caret one character to the right. When the

- When the caret is located on a delimiter character and it is preceded by delimiters the caret is moved left to the first delimiter.
- When the caret is located on a delimiter character and it is not preceded by delimiters the caret is move to the start of the previous word or delimiters.
- When the caret is located on a non-delimiter character and not on a white-space character the caret is moved to the start of the current word
- When the caret is located on a white space the caret is moved to the start of the previous word or the previous delimiters depending on what comes first.
- When the caret is located on the start of the first word, delimiters or white-space of the current line the caret is moved to the start of the last word or delimiters of the previous line.

Ctrl-Shift-Left

(16) In addition to the caret movement this command will also extend the current selection to the new position.

Ctrl-Home

(17) This command will move the caret to the beginning of the text. When the caret is already at this location nothing happens.

Ctrl-Shift-Home

(18) In addition to the caret movement this command will also extend the current selection to the new position.

Ctrl-End

(19) This command will move the caret to the end of the text. When the caret is already at this location nothing happens.

Ctrl-Shift-End

(20) In addition to the caret movement this command will also extend the current selection to the new position.

Ctrl-Tab

(21) This command will move the caret to the previous tab-stop position. When the caret is located at the start of the line nothing happens.

Ctrl-Shift-Tab

(22) In addition to the caret movement, this command will also extend the current selection to the new position.

PqUp

(23) This command will move the caret one view up when it is located on the top line currently in the view. When the caret is not located on the top line of the view, it will be moved there.

Shift-PgUp

(24) In addition to the caret movement this command will also extend the current selection to the new position.

PgDn

(25) This command will move the caret one view down when it is located on the bottom line currently in the view. When the caret is not located on the bottom line of the view, it will be moved there.

Shift-PgDn

(26) In addition to the caret movement, this command will also extend the current selection to the new position.

View commands

Ctrl-Down

(80) This command will scroll the view one line up. The command will always keep the caret inside the view. When it reaches the bottom of the view, the caret is automatically moved to the next line.

Ctrl-Up

(81) This command will scroll the view one line down. The command will always keep the caret inside the view. When it reaches the top of the view, the caret is automatically moved to the previous line.

Ctrl-PgDn

(82) This command will scroll the view one column to the left. The caret is not moved.

Ctrl-PgUp

(83) This command will scroll the view one column to the right. The caret is not moved.

Edit commands

Ctrl-Z

(100) This command will undo the last change made to the edit control contents. You can undo any number of changes made to the control contents up to the maximum number of undo/redo hops.

Ctrl-Y	(101)	This command will redo the last change you have undone. You can
		re-do any number of changes up to the number of changes undone.
Shift-Del	(103)	This command will remove all characters to the right of the current caret
Dookonooo	(404)	position.
Backspace	(104)	This command will remove the character to the left of the caret. When the caret is located at the start of the line, the characters right of the
		caret are appended to the previous line and the caret is moved to be
		positioned between the old line contents and the appended characters.
Delete	(105)	This command removes the character to the right of the caret. When
	(/	there are no characters to the right of the caret, the contents of the next
		line is appended to the current line.
Alt-Delete	(106)	This command deletes the current line.
Return	(107)	This command will split the current line and create a new line of the
		characters, if any, right of the caret. The caret is moved to the start of
A 1/ 1 1	(400)	the newly created line.
Alt-U	(108)	This command will convert all lower-case characters of the word under
		the caret to upper-case characters. If the caret is not located on a word,
Alt-L	(100)	nothing happens. This command will convert all upper-case characters of the word under
AIL-L	(103)	the caret to lower-case characters. If the caret is not located on a word,
		nothing happens.
Alt-S	(110)	This command will convert all lower-case characters to upper-case
	, ,	characters and upper-case characters to lower-case characters of the
		word under the caret. If the caret is not located on a word, nothing
		happens.
Ctrl-Delete	(113)	When the caret is located on a word, this command will delete all
Ctrl Booksnoos	(444)	characters in the word right of the caret position. When the caret is located on a word, this command will delete all
Ctrl-Backspace	(114)	characters in the word left of the caret position.
		orial adicional in the word left of the darct position.
Tab	(115)	
Tab	(115)	This command does one of the two following things:
Tab	(115)	
Tab	(115)	This command does one of the two following things:When there is a valid text selection, this command will indent the
	. ,	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position.
Tab Shift-Tab	. ,	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things:
	. ,	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the
	. ,	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop.
	. ,	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the
Shift-Tab	(116)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position.
	(116)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the
Shift-Tab	(116)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position.
Shift-Tab	(116)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case
Shift-Tab Shift-Alt-T	(116)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid
Shift-Tab Shift-Alt-T Shift-Ctrl-U	(116) (117) (118)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens.
Shift-Tab Shift-Alt-T	(116) (117) (118)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all
Shift-Tab Shift-Alt-T Shift-Ctrl-U	(116) (117) (118)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U	(116) (117) (118) (119)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there is no valid selection, nothing happens.
Shift-Tab Shift-Alt-T Shift-Ctrl-U	(116) (117) (118) (119)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U	(116) (117) (118) (119)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection,
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U Ctrl-U	(116) (117) (118) (119) (120)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection, nothing happens.
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U	(116) (117) (118) (119) (120)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection to lower-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection, nothing happens. This command will insert the system date at the current caret location.
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U Ctrl-U Ctrl-D	(116) (117) (118) (119) (120) (121)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection, nothing happens. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection, nothing happens. This command will insert the system date at the current caret location. The date output is formatted using the user's default format.
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U Ctrl-U	(116) (117) (118) (119) (120) (121)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection, this command will convert all lower-case characters in the selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection, nothing happens. This command will insert the system date at the current caret location. The date output is formatted using the user's default format. This command will insert the system time at the current caret location.
Shift-Tab Shift-Alt-T Shift-Ctrl-U Ctrl-U Ctrl-U Ctrl-D	(116) (117) (118) (119) (120) (121) (122)	 This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection right by one tab-stop. When there is no text selection, a tab is inserted at the current caret position. This command does one of the two following things: When there is a valid text selection, this command will indent the lines covered by the selection left by one tab-stop. When there is no text selection, the caret is moved back to the previous tab-stop position. This command will swap the line on which the caret is located with the previous line. When the caret is located on the first line, nothing will happen. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters. If there is no valid selection, nothing happens. When there is a valid selection, this command will convert all upper-case characters in the selection, nothing happens. When there is a valid selection, this command will convert all lower-case characters in the selection to upper-case characters and all upper-case characters in the selection to lower-case characters and all upper-case characters in the selection to lower-case. If there is no valid selection, nothing happens. This command will insert the system date at the current caret location. The date output is formatted using the user's default format.

and insert.

• Mark / Clipboard commands

Shift-Ctrl-W	(200) This command will select the word on which the caret is currently located. When the caret is not located on a word, nothing happens.
Ctrl-A	(201) This command will select all the text.
Shift-Ctrl-L	(203) This command will select the line on which the caret is currently located.
Ctrl-V	(225) This command will, when there is text present in the clipboard, paste the clipboard contents at the current position.
Ctrl-C	(226) This command will, when there is a selection, copy the selected text to the clipboard.
Ctrl-X	(227) This command will, when there is a selection, copy the selected text to the clipboard and remove the selection from the text.
Shift-Ctrl-C	(229) This command will copy the line on which the caret is located to the clipboard.
Shift-Ctrl-X	(230) This command will copy the line on which the caret is located to the clipboard and remove the line from the text.
Alt-C	(232) This command will, if there is a selection, append the selection to the current clipboard contents. The result is placed on the clipboard again.
Alt-X	(233) This command will, if there is a selection, append the selection to the current clipboard contents. The result is placed on the clipboard again, and the selection is removed from the text.

• Search commands

Ctrl-F3	(275) This command will find the next occurrence of the word under the caret. When the next occurrence is found, it is selected.
F3	(277) This command will find the next occurrence of the current search
Shift-F3	pattern. When the search pattern is found, it is selected. (278) This command will find the previous occurrence of the current search pattern. When the search pattern is found, it is selected.
Ctrl-]	(279) This command will find the matching closing bracket if the caret is located on an opening bracket, or the matching open bracket if the caret is located on a closing bracket.
Shift-Ctrl-]	(280) This command will find the matching closing bracket if the caret is located on an opening bracket, or the matching opening bracket if the caret is located on a closing bracket. In addition the text from the opening bracket up to and including the closing bracket is selected.
Ctrl-G Ctrl-F Ctrl-H	(300) This command will show the <i>goto</i> dialog.(301) This command will show the <i>find</i> dialog.(302) This command will show the <i>replace</i> dialog.

• File commands

Ctrl-S	(401) This command will save the control contents using its current name
Shift-Ctrl-Del	(402) This command will delete all text. If the text has been modified the user
	will be prompted to save the contents first.
Ctrl-P	(403) This command will open the printer properties dialog.

• Bookmark commands

Ctrl-F2	(252) This command will clear the bookmark on the current line if it is set, or set the bookmark if it is cleared.
Shift-Ctrl-F2	(253) This command will clear all bookmarks.
F2	(254) This command will place the caret on the next line which has a bookmark set. When there is no next line with a bookmark, the text is

searched starting at the first line.

Shift-F2 (255) This command will place the caret on the previous line which has a

bookmark set. When there is no previous line with a bookmark, the text

is searched from the last line up again.

Breakpoint commands

Ctrl-B (262) This command will toggle a breakpoint on the current line.

Ctrl-Shift-F9 (263) This command will clear all breakpoints.

Expression evaluation commands

Invoke the Evaluate Expression dialog. Alt-F11

Invoke the Evaluate Expression dialog for the current selection. If no Ctrl-F9

text is selected, evaluate the current line.

Options:

/A Start with the alias window open.

/B Start with the batch variables window open.

/C If the specified batch file doesn't exist, create it without prompting.

/E Start with the environment variables window open.

/F Start with the user-defined functions window open.

/I Load the batch file, but do not start execution

/K Keep the batch debugger window open and switch to edit mode after the batch file exits.

/N By default, the debugger window hides itself while the debugged batch file is executing. /N keeps that window visible in the background (the TCC window is brought to the foreground).

/W Open the Watch window when the debugger starts.

3.13.10 BEEP

Purpose: Beep the speaker or play simple music.

Format: BEEP [frequency duration ...] [asterisk | exclamation | hand | question | ok]

> The beep frequency in Hertz (cycles per second). frequency

duration The beep length in 1/18th second intervals.

asterisk Plays the system default "asterisk" sound. exclamation Plays the system default "exclamation" sound. hand Plays the system default "hand" sound. question Plays the system default "question" sound.

Plays the system default "ok" sound. ok

See also: the Length 51 and Frequency 51 configuration options.

Usage:

BEEP generates a sound through your computer's speaker. You can use it in batch files to signal that an operation has been completed, or that the computer needs attention.

Because BEEP allows you to specify the frequency and duration of the sound, you can also use it to play simple music or to create different kinds of signals for the user.

You can include as many frequency and duration pairs as you wish. No sound will be generated for frequencies less than 20 Hz, allowing you to use BEEP as a way to create short delays. The default value for *frequency* is 440 Hz; the default value for *duration* is 2.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This batch file fragment runs a program called *DEMO*, then plays a few notes and waits for you to press a key:

```
demo
beep 440 4 600 2 1040 6
pause Finished with the demo - hit a key...
```

The following table gives the *frequency* values for a five octave range (middle C is 262 Hz):

С	131	262	523	1046	2096
C# / Db	139	277	554	1108	2217
D	147	294	587	1175	2349
D# / Eb	156	311	622	1244	2489
Е	165	330	659	1318	2637
F	175	349	698	1397	2794
F# / Gb	185	370	740	1480	2960
G	196	392	784	1568	3136
G# / Ab	208	415	831	1664	3322
Α	220	440	880	1760	3520
A# / Bb	233	466	932	1866	3729
В	248	494	988	1973	3951

3.13.11 BREAK

Purpose: Enable or disable Ctrl-C and Ctrl-Break

Format: BREAK [ON | OFF]

Usage:

BREAK OFF will disable all **Ctrl-C** and **Ctrl-Break** handling in **TCC** (though not necessarily in child processes). In CMD.EXE, BREAK OFF doesn't actually do anything, so setting it in **TCC** will introduce a possible incompatibility with existing batch files.

3.13.12 BREAKPOINT

Purpose: Set a batch debugger breakpoint on the current line

Format: BREAKPOINT

Usage:

If the batch debugger is active, BREAKPOINT sets a breakpoint on the current line, stopping a "Step Out" sequence. If the batch debugger is not active, BREAKPOINT is ignored.

3.13.13 CALL

Purpose: Execute one batch file from within another.

Format: CALL file | :label [p1 [p2 ...]]

file The batch file to execute.

:label A label 530 in the current batch file.

p1, p2,... Parameters for the batch file or subroutine

See also: CANCEL 176 and QUIT 301.

Usage:

Calling other batch files

CALL allows batch files to call other batch files (batch file nesting). The calling batch file is suspended while the called (second) batch file runs. When the second batch file finishes (without executing the CANCEL command), execution of the original batch file resumes at the next command.

WARNING! If you execute a batch file from inside another batch file without using CALL, the original batch file is terminated before the other one starts. This method of invoking a batch file from another is usually referred to as chaining. Note that if the batch file *A.BTM* uses **CALL B**, and *B.BTM* chains to the batch file *C.BTM*, on exit from *C.BTM* (without executing a <u>CANCEL</u> 1761 command) processing of batch file *A.BTM* is resumed as if it had used **CALL C**.

```
File A.BTM:
```

```
call b echo xxx
```

File B.BTM:

... C

File C.BTM:

... quit

In the example above, after execution of the QUIT of command in *C.BTM* the **ECHO xxx** command in *A.BTM* is executed next.

The following batch file fragment compares an input line to **wp** and calls another batch file if it matches:

```
input Enter your choice: %%option
if "%option" == "wp" call wp.bat
```

Batch files may be nested up to 32 levels deep.

The current ECHO state is inherited by a called batch file.

The called batch file should always either return (by executing its last line, or by using the QUIT of command), or it should terminate batch file processing with CANCEL 176. Do not restart or CALL the original batch file from within the called file as this may cause an infinite loop or a stack overflow.

Calling a label

To provide compatibility with CMD.EXE, which does not support the GOSUB [247] command for subroutines in the same batch file, you may create a subroutine starting with a label [530] and terminated by any of the following:

- the end of the batch file
- QUIT 301
- EXIT 227
- CANCEL 176

Note that the last two do NOT return control to the CALL command. Do not use the RETURN or command!

Parameters passed to the subroutine are accessible as **%1**, **%2**, etc., in the same manner as in a batch file.

Exit code

CALL returns an exit code which matches the batch file return code. You can test this exit code with the %_? 380 or %? 380 environment variables, and use it with conditional commands 120 (&& and ||).

See also GOSUB [247] and user-defined functions [242].

3.13.14 CANCEL

Purpose: Terminate batch file processing.

Format: CANCEL [value]

value The numeric exit code to return to TCC.

See also: CALL 175 and QUIT 301.

Usage:

The CANCEL command ends all batch file processing, regardless of the batch file nesting level. Use QUIT 30th to end a nested batch file and return to the previous batch file.

You can CANCEL at any point in a batch file. If CANCEL is used from within an alias it will end execution of both the alias and any batch files which are running at the time.

The following batch file fragment compares an input line to "end" and terminates all batch file processing if it matches:

```
input Enter your choice: %%option
if "%option" == "end" cancel
```

If you specify a *value*, CANCEL will set the ERRORLEVEL or exit code to that value (see the <u>IF</u> 253) command, and the <u>%?</u> 380 variable). Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

3.13.15 CD / CHDIR

Purpose: Display or change the current directory.

Format: CD [/D /N /X] [path | -]

path The directory to change to, optionally including a drive letter

/D(rive) 178 /X (exclude) 178

/N(o extended search) 178

See also: CDD 1781, MD 2711, PUSHD 2991, RD 3011, and Directory Navigation 711.

Internet: Can be used with FTP Servers 93.

Usage:

CD and CHDIR are synonyms. You can use either one.

CD lets you navigate through a drive's subdirectory structure by changing the current working directory. If you enter CD and a directory name, the named directory becomes the new current directory. For example, to change to the subdirectory *C:\FINANCEMYFILES*:

```
[c:\] cd \finance\myfiles
[c:\finance\myfiles]
```

Every disk drive on the system has its own current directory. Specifying both a drive and a directory in the CD command will change the current directory on the specified drive, but will not change the default drive (unless you use the /D | 178| option). For example, to change the default directory on drive A:

```
[c:\] cd a:\utility
[c:\]
```

Notice that this command does not change to drive A:. Use the /D | 178 option, or preferably the CDD | 178 command to change the current drive and directory at the same time.

If *path* contains white space or special characters (which is valid only for an <u>LFN</u> 5311 drive), you must enclose it in double quotes .

You can change to the parent directory with **CD** ..; you can also go up one additional directory level with each additional .. For example, **CD** will go up three levels in the directory tree (see Extended Parent Directory Names 118). You can move to a sibling directory — one that branches from the same parent directory as the current subdirectory — with a command like **CD** ... **Newdir**.

If you enter CD with no parameter or with only a disk drive name, it will display the current directory on the default or named drive.

If CD cannot change to the directory you have specified it will attempt to search the CDPATH T2 and the extended directory search disables in order to find a matching directory and switch to it. You can disable this default extended search with N 178. You can also use wildcards in path to force an extended directory search. Read the section on Directory Navigation 71 for complete details on these and other directory navigation features.

CD saves the current directory before changing to a new directory. You can switch back to the previous directory by entering CD -. (There must be a space between the CD command and the hyphen.) You can switch back and forth between two directories by repeatedly entering CD -. The saved directory is the same for both the CD and CDD 178 commands. Drive changes and automatic directory changes 76 also modify the saved directory, so you can use CD - to return to a directory that you exited with an automatic directory change.

Directory changes made with CD are recorded in the directory history list and can be displayed in the directory history window [118], which allows you to return quickly to a recently-used directory.

```
cd ftp:
ftp://jpsoft.com/
cd ftp:/pub
```

Note: FTP directory changes use neither the <u>CDPATH feature</u> 72 nor the <u>Extended Directory</u> Searches 73 database.

CD never changes the default drive, unless the /D | option is specified. If you change directories on one drive, switch to another drive, and then enter CD -, the directory will be restored on the first drive but the current drive will not be changed.

Options:

- Changes the current drive as well as directory. This option is included only for compatibility with the same option available in some versions of CMD.EXE. In most cases you should use CDD [178], which performs the same function.
- /N Skips the standard extended directory search 3 when the directory is not found. This option is useful in batch files to force an error (rather than an extended search) if a directory is not found.
- /X Don't save the current directory to the Directory History list.

3.13.16 CDD

Purpose: Change the current disk drive and directory.

Format: CDD [/A /D[drive ...] /N[J] /S[n][drive ...] /U[drive...] /X] [path | -]

path The name of the directory (or drive and directory) to change to.

drive A drive or list of drives to include in the extended directory search database.

```
/A(II drives) 179 /T (Also change Folders directory) 180 /D(elete from JPSTREE.IDX) 179 /TO Only change Folders directory) 180 /V(o extended search) 179 /U(pdate tree) 180 /X (exclude from JPSTREE.IDX) 180 /S(earch tree) 180
```

See also: CD 177, MD 271, PUSHD 299, RD 301, and Directory Navigation 711.

Usage:

CDD is similar to the CD (177) command, except that it also changes the default disk drive if one is specified. For example, to change from the root directory on drive A to the subdirectory C:\WP:

```
[a:\] cdd c:\wp
[c:\wp]
```

If no drive / path argument is supplied, CDD displays the current drive and directory.

CDD can also be used to create and update the Extended Directory Search (73) database (JPSTREE.IDX).

You can change to the parent directory with **CDD** ..; you can also go up one additional directory level with each additional [.]. For example, **CDD** ... will go up three levels in the directory tree.

CDD can also change to a network drive and directory specified with a UNC name (see File Systems 49th for details).

When you use CDD to change to a directory on an LFN drive, you must quote the *path* name if it contains white space or special characters.

If CDD cannot change to the directory you have specified it will first search the CDPATH [72], then the extended directory search [73] database in order to find a matching directory and switch to it. You can disable this default extended search with **/N**. You can also use wildcards in the **path** to force an extended directory search. Read the section on Directory Navigation [71] for complete details on these and other directory navigation features.

CDD saves the current drive and directory before changing to a new directory. You can switch back to the previous drive and directory by entering **CDD** -. (There must be a space between the CDD command and the hyphen.) You can switch back and forth between two drives and directories by repeatedly entering **CDD** -. The saved directory is the same for both the CD and CDD commands. Drive changes and <u>automatic directory changes</u> 16 also modify the saved directory, so you can use **CDD** - to return to a directory that you exited with a drive change or an automatic directory change.

Directory changes made with CDD are recorded in the directory history list and can be displayed in the directory history window [118], which allows you to return quickly to a recently-used directory.

Windows limits the permissible length of the full subdirectory name (see the <u>Directories and Subdirectories</u> topic for information on directory names).

When changing directories, *TCC* maintains the original case of each path element. This is necessary for a few programs which are case-sensitive in their use of directory names.

Options:

- When CDD is used with this option, it displays the current directory on all drives from C: to the last drive in the system. You cannot move to a new drive and directory and use /A in the same command.
- Removes the specified drives or directory trees from the Extended Directory Search (73) database (JPSTREE.IDX). Uses the same syntax for drive and directory names as /S. For example, to delete the directories under F:WYDIR from JPSTREE.IDX:

```
cdd /d f:\mydir
```

/N Skips the standard extended directory search 3 when the directory is not found. This option is useful in batch files to force an error – rather than an extended search – if a directory is not found.

- /NJ Skips junctions when indexing directories (see /S).
- Builds or rebuilds the Extended Directory Search (73) database (JPSTREE.IDX). You cannot move to a new drive and directory and use /S in the same command.

To include all local hard drives in the database, use the command:

```
cdd /s
```

To limit or add to the list of drives included in the database, list the drives and network volume names after the **/S** switch. For example, to include drives C, D, E, and the network volume \server\dir1 in the database, use this command:

```
cdd /s cde \\server\dir1
```

All non-hidden directories on the listed drives will be indexed. CDD /S will also index the hidden directories if the <u>Complete Hidden Files</u> option is set. Each time you use /S, everything in the previous directory database is replaced by the new database that is created. To update the database see /U below.

You can index specific subdirectories rather than an entire drive. For example, to index all directories on drive C but only the MSSDK directory tree on drive D:

```
cdd /s c:\ d:\mssdk
```

If you specify a number after the /S, CDD will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only index the "a", "b", and "c" directories.

- /T Also change the current directory in the *Take Command* Folders and List View windows.
- Change the current directory in the *Take Command* Folders and List View windows without changing the *TCC* current directory.
- Updates the Extended Directory Search (JPSTREE.IDX) with the specified drives and directories instead of rebuilding the whole directory database. Uses the same syntax for drive and directory names as /S. For example, to update the D:WSSDK tree and all of drive E:

```
cdd /u d:\mssdk e:\
```

/X Don't save the current directory to the Directory History list.

Note: The TREEEXCLUDE 370 variable can be used to specify which drives and directories should be ignored when updating the directory database.

3.13.17 CHCP

Purpose: Display or change the current system code page

Format: CHCP [n]

n A system code page number.

Usage:

Code page switching allows you to select different character sets for language support.

If you enter CHCP without a number, the current code page is displayed.

```
chcp
Active code page: 437
```

If you enter CHCP plus a code page number, the code page is changed. For example, to set the code page to multilingual:

```
chcp 850
```

When you use CHCP under Windows it only affects the current process, and any new programs started from within that process; the active code page in other processes remains unchanged.

3.13.18 CLS

Purpose: Clear the window and move the cursor to the upper left corner; optionally change the

default display colors.

Format: CLS [/C /S] [[BRIght] fg ON [BRIght] bg

fg The new foreground colorbg The new background color

/C(lear buffer) 18th /S(croll buffer) 18th

Usage:

CLS can be used to clear the window without changing colors, or to clear the window and change the colors simultaneously, or to clear the entire scrollback buffer. These two examples show how to clear the window to the default colors, and to bright white letters on a blue background:

```
cls
cls bright white on blue
```

CLS is often used in batch files before displaying text.

See Colors and Color Names 518 for details about colors.

Options:

/C Clears the entire scrollback buffer. If /C is not used, only the visible portion of the window is cleared.

Clear the screen by scrolling the buffer, rather than filling the screen with blanks (the default method). This saves the text on the screen into the scrollback buffer if it is larger than the visible window. This switch may not give the expected results when the buffer size is less than twice the window size.

3.13.19 COLOR

Purpose: Change the default display colors.

Format: COLOR [BRIght] fg ON [BRIght] bg

fg The new foreground colorbg The new background color

See also: CLS 18th and Colors and Color Names 518 for details about using colors and the name and numeric codes for colors.

Usage:

COLOR is normally used in batch files before displaying text. For example, to set screen colors to bright white on blue, you can use this command:

```
color bright white on blue
```

TCC also supports the CMD.EXE syntax:

```
COLOR bf
```

In this syntax, b is a hexadecimal digit that specifies the background color and f is a hexadecimal digit that specifies the foreground color.

If you have ANSI enabled and StdColors and/or InputColors set, they will override a COLOR command.

3.13.20 COPY

Purpose: Copy data between disks, directories, files, or physical hardware devices (such as your

printer or serial port).

Format: COPY [/I"text"] [/A:... /C /D /E /F /FTP:A /G /H /J /K /L /M /MD /N[dejst] /O /P /Q /R /S[n] /T

/U /V /X /Z] [@file] source [+] ... [/A|/B] [TO:] target [...] [/A|/B]

source A file or list of files or a device to copy from.

target A file, directory, or device to copy to

@file A text file containing the names of the source files, one per line (see @file

lists 90 for details)

```
/A(SCII) copy 186
                                       /LD (create link) 188
/A:... (Attribute select) 187
                                       /M(odified files 188)
/B(inary copy) 187
                                       /MD (Create target directory) 1881
/C(hanged source files) 187
                                       /N (Disable) 188
/D (Copy encrypted files) 187
                                       /O(nly if no target) 188
                                       /P(rompt) 188
/E (No error messages) 187
/F (No empty subdirectories) 187)
                                       /Q(uiet) 188
/FTP:A (ASCII copy) 187)
                                       /R(eplace) 188
/G (Display percentage) 187
                                       /S(ubdirectories) 188
                                       /T(otals) 189
/H (Include hidden files) 187
                                       /U(pdate target) 189
/I"text" (Match description) 187)
/J (Restartable) 187
                                       /V(erify) 189
/K (Keep read-only attribute) 187
                                       /X (Clear archive) 189
/L Copy symbolic links 1881
                                       /Z (overwrite) 189
```

See also: ATTRIB 1631, MOVE 2741, and REN 3051.

File Selection

Supports <u>attribute switches 86</u>, extended <u>wildcards 77</u>, <u>ranges 80</u>, <u>multiple file names 87</u>, <u>delayed variable expansion 89</u>, and <u>include lists 88</u>. Date, time, size or exclude ranges anywhere on the line

apply to all *source* files. Use wildcards with caution on LFN volumes; see <u>LFN File Searches</u> of details.

Internet

Can be used with FTP / FTPS / TFTP / HTTP / HTTPS Servers 931.

Usage

The simplest use of COPY is to make a copy of a file, like this example which makes a copy of a file called *FILE1.ABC*:

```
copy file1.abc file2.def
```

You can also copy a file to another drive and/or directory. The following command copies *FILE1* to the *WYDIR* directory on drive **E**:

```
copy file1 e:\mydir
```

When you COPY files to or from an LFN drive, you must quote any file names which contain white space or special characters.

To emulate an approach used by some implementations of CMD.EXE, see the COPYCMD | 37th topic.

Copying Files

You can copy several files at once by using wildcards 77:

```
copy *.txt e:\mydir
```

You can also list several **source** files in one command. The following command copies 3 specific files from the current directory to the \mbox{MYDIR} directory on drive **E**:

```
copy file1 file2 file3 e:\mydir
```

COPY also understands include lists 88, so you can specify several different kinds of files in the same command. This command copies the .TXT, .DOC, and .BAT files from the $E: \MYDIR$ directory to the root directory of drive A:

```
copy e:\mydir\*.txt;*.doc;*.bat a:\
```

If there is only one parameter on the line, COPY assumes it is the **source**, and uses the current drive and directory as the **destination**. For example, the following command copies all the **.DAT** files from the current directory on drive **A** to the current directory on the current drive:

```
copy a:*.dat
```

If there are two or more parameters on the line separated by spaces, then COPY assumes that the last parameter is the **destination** and copies all **source** files to this new location. If the **destination** is a drive, directory, or device name, the **source** files are copied individually to the new location. If the **destination** is a file name, the first **source** file is copied to the **destination**, and any additional **source** files are then appended to the new **destination** file.

For example, the first of these commands copies the .DAT files from the current directory on drive A individually to C:\WYDIR (which must already exist as a directory); the second appends all the .DAT files together into one large file called C:\DATA (assuming C:\DATA is not a directory):

```
copy a:*.dat c:\mydir\
copy a:*.dat c:\data
```

When you copy to a directory, if you add a backslash \ to the end of the name as shown in the first example above, COPY will display an error message if the name does not refer to an existing directory. You can use this feature to keep COPY from treating a mistyped **destination** directory name as a file name and attempting to append all your **source** files to a single **destination** file, when you really meant to copy them individually to a **destination** directory.

To copy text to or from the clipboard use CLIP: as the device name. Using CLIP: with non-text data will produce unpredictable results. See Redirection 98 for more information on CLIP:

Appending Files

A plus sign + tells COPY to append two or more **source** files to a single **destination** file. If you list several **source** files separated with + and don't specify a **destination**, COPY will use the name of the first **source** file as the destination, and append each subsequent file to the first file.

For example, the following command will append the contents of *MEMO2* and *MEMO3* to *MEMO1* and leave the combined contents in the file named *MEMO1*:

```
copy memo1+memo2+memo3
```

To append the same three files but store the result in BIGMEMO:

```
copy memo1+memo2+memo3 bigmemo
```

If no **destination** is specified, the destination file will always be created in the current directory even if the first **source** file is in another directory or on another drive. For example, this command will append C:\text{WEMWEMO3} and C:\text{WEMWEMO3} to D:\text{DATAMEMO1}, and leave the result in C:\text{WEMWEMO1}:

```
[c:\mem] copy d:\data\memo1+memo2+memo3
```

You cannot append files to a device (such as a printer); if you try to do so, COPY will ignore the + signs and copy the files individually. If you attempt to append several **source** files to a **destination** directory or disk, COPY will append the files and place the copy in the new location with the same name as the first **source** file.

You cannot append a file to itself.

FTP Usage

If you have appropriate permissions, you can copy to and from Internet URLs (FTP, TFTP and HTTP). Many FTP servers, including our own **ftp://jpsoft.com**, use case sensitive file systems. For example:

```
copy ftp://ftp.abc.com/xyz/index index
```

Files copied to or from FTP/HTTP Servers are normally transferred in binary mode. To perform an ASCII transfer use the <u>/L [188]</u> switch. File descriptions are not copied when copying files to an Internet URL.

COPY supports the special syntax

```
copy con: ftp:...
```

to directly copy text from the console to an ftp location.

Wildcard characters such as * and ? will be treated as wildcards in FTP URLs, but will be treated as normal characters in HTTP URLs.

Note: The <u>/G laft</u> option (percentage copied) may report erratic values during transfer of files larger than 4 Gb (an ftp limitation) and during http downloads.

You can also use the IFTP [255] command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want. For more information, see Using FTP/HTTP Servers [937] and IFTP [255].

NTFS File Streams

COPY supports file streams on NTFS drives. You can copy an individual stream by specifying the stream name, for example:

```
copy myfile:mystream stream.copy
```

If no stream name is specified the entire file is copied, including all streams. However, if you copy a file to a drive or device which does not support streams, only the file's primary data is copied; any additional streams are not processed.

See NTFS File Streams 496 for additional details.

Advanced Features

If your **destination** has wildcards in it, COPY will attempt to match them with the **source** names. For example, this command copies the .DAT files from drive **A** to C:WYDIR and gives the new copies the extension .DX:

```
copy a:*.dat c:\mydir\*.dx
```

This feature can give you unexpected results if you use it with multiple **source** file names. For example, suppose that drive \mathbf{A} contains XYZ. DAT and XYZ. TXT. The command:

```
copy a:\*.dat a:\*.txt c:\mydir\*.dx
```

will copy A:XYZ.DAT to C:WYDIR\XYZ.DX. Then it will copy A:XYZ.TXT to C:WYDIR\XYZ.DX, overwriting the first file it copied.

You can use <u>date, time, and size ranges</u> so to further define the files that you want to copy. This example copies every file in the *E:WYDIR* directory, which was created or modified yesterday, and which is also 10,000 bytes or smaller in size, to the root directory of drive **A**:

```
copy / [d-1] / [s0,10000] e:\mydir\* a:\
```

You can also use file exclusion ranges to restrict the list of files that would normally be selected with wildcards. This example copies every file in the *E:WYDIR* directory except backup (.BAK or .BK) files:

```
copy /[!*.bak *.bk] e:\mydir\* a:\
```

COPY will normally process **source** files which do not have the hidden or system attribute, and will ignore the read-only and archive attributes. It will always set the archive attribute and clear the read-only attribute of **destination** files. In addition, if the **destination** is an existing file with the read-only attribute, COPY will generate an **Access Denied** error and refuse to overwrite the file. You can alter some of these behaviors with switches:

/A: 187). Forces COPY to process **source** files with the attributes you specify after the :, or to

process all **source** files regardless of attributes, if /A: 187 is used by itself.

- Forces COPY to process hidden and system **source** files, as well as normal files. The hidden and system attributes from each source file will be preserved when creating the **destination** files.
- Retains the read-only attribute from each **source** file when creating the **destination** file. See /K 187 below for a special note if you are running under Novell NetWare.
- /Z 189 Forces COPY to overwrite an existing *destination* file regardless of its attributes.

Use caution with /A: [187], /H [187], or /K [187] when both the **source** and **destination** directories contain file descriptions. If the **source** file specification matches the description file name (normally **DESCRIPT.ION**), and you use a switch which tells COPY to process hidden files, the **DESCRIPT.ION** file itself will be copied, overwriting any existing file descriptions in the **destination** directory. For example, if the \DATA directory contains file descriptions this command would overwrite any existing descriptions in the \SAVE directory:

```
[c:\data] copy /h d* \save\
```

If you remove the hidden attribute from the **DESCRIPT.ION** file, the same caution applies even if you do not use /A: 1887, /H 1887, or /K 1887, as **DESCRIPT.ION** is then treated like any other file.

You can copy files to multiple destinations with the TO: option. For example, to copy *letter.doc* to three different directories:

```
copy letter.doc TO: \save\ f:\backups\ q:\letters\
```

Note: The wildcard expansion process will attempt to allow both CMD.EXE-style "extension" matching (assumes only one extension, at the end of the word) and the advanced **TCC** string matching (allowing things like *.*.abc) when an asterisk is encountered in the **destination** of a COPY command.

COPY supports connected web folders. If an HTML file (i.e., with an .htm or .html extension) is copied, COPY will look for a folder in the same directory with the same name and an extension of ".files". If it is found, the .files directory will be copied to the target directory. You can disable connected web folders by setting the registry key:

HKCU\Software\Microsoft\Windows\CurrentVersion\Explorer\NoFileFolderConnection=0

Options

The /A 186 (ASCII copy) and /B 187 (binary copy) options apply to the preceding filename and to all subsequent filenames on the command line until the file name preceding the next /A 186 or /B 187, if any. All other options apply to all filenames on the command line, no matter where you put them.

Some options do not make sense in certain contexts, in which case COPY will ignore them. For example, you cannot prompt before replacing an existing file when the **destination** is a device such as the printer — there's no such thing as an "existing file" on the printer. If you use conflicting output options, like $\frac{1}{2}$ and $\frac{1}{2}$ and $\frac{1}{2}$ will generally take a "conservative" approach and give priority to the option which generates more prompts or more information.

If you use /A with a **source** filename, the file will be copied up to, but not including, the first Control-Z (ASCII: 26) character in the file. If you use /A with a **destination** filename, a Control-Z will be added to the end of the file. /A is the default when appending files, or when the **destination** is a device like **NUL**, rather than a disk file.

This option applies to the filename immediately preceding it, and to all subsequent

- filenames until the file name preceding the next /A or /B 187 option.
- /A:... Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. See the cautionary note under Advanced Features above before using /A: when both source and destination directories contain file descriptions. You must include the colon with this option to distinguish it from the /A switch, above. Do not use /A: with @file lists. See @file lists for details. Hidden or system files
- If you use /B with a **source** filename, the entire file is copied; <SUB> characters, if any, in the file are considered ordinary data to be copied. Using /B with a **destination** filename prevents addition of a <SUB> to the end of the **destination** file. /B is the default unless source files are appended to the target file, or the target is a device, e.g., NUL.
 - This option applies to the filename immediately preceding it, and to all subsequent filenames until the file name preceding the next /A labor or /B option.
- Copy files only if the *destination* file exists and is older than the *source* (see also /U 1891). This option is useful for updating the files in one directory from those in another without copying any files not already in the target directory. Before using /C in a network environment, be sure to read the note under /U 1891. Do not use /C with @file lists. See @file lists 991 for details.
- (Windows XP+ Only) Force copy of an encrypted file even when the target will be decrypted (for CMD.EXE compatibility).
- (No error messages) Suppress all non-fatal error messages, such as **File not found** or **Can't copy file to itself**. Fatal error messages, such as <code>Drive not ready</code>, will still be displayed. This option is most useful in batch files and aliases.
- /F When used with /S, COPY will not create any empty subdirectories.
- /FTP:A Perform FTP transfers in ASCII mode, instead of the default binary mode.
- Displays the percentage copied, the transfer rate (in Kbytes/second), and the estimated time remaining. Useful when copying large files across a network or via FTP to ensure the copy is proceeding. When Missi is also used, reports percentage verified.
- /H Copy all matching files including those with the hidden and/or system attribute set. See the cautionary note under **Advanced Features** above before using /H when both **source** and **destination** directories contain file descriptions.
- /I"text" (Match descriptions) Select **source** files by matching text in their descriptions. See Description Ranges of for details.
- Copy the file in restartable mode. The copy progress is tracked in the destination file in case the copy fails. The copy can be restarted by specifying the same source and destination file names.
- /K (Keep read-only attribute) To maintain compatibility with CMD.EXE, COPY normally maintains the hidden and system attributes, sets the archive attribute, and removes the read-only attribute on the target file. /K tells COPY to also maintain the read-only attribute on the destination file. However, if the destination is on a Novell NetWare volume, this option will fail to maintain the read-only attribute. This is due to the way NetWare handles file attributes, and is not a problem in COPY.

- **/L** (Windows Vista or later only) If the source is a symbolic link, copy the link to the target instead of the actual file.
- **/LD** When used with /S, if the source is a symbolic or hard link to a directory, COPY will create the link in the target directory instead of copying the subdirectory tree.
- Copy only those files with the archive attribute set, *i.e.*, those which have been modified since the last backup. The archive attribute of the **source** file will not be cleared after copying; to clear it use the /X | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189 | 189
- /MD Create the target directory if it doesn't exist. Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise COPY cannot tell what you want for the directory and what you want for the filename.
- /N Do everything except actually perform the copy. This option is useful for testing what the result of a complex COPY command will be. /N displays how many files would be copied. /N does not prevent creation of *destination* subdirectories when it is used with /S [188].

A /N with one of the following arguments has an alternate meaning:

- **d** Skip hidden directories (when used with /S)
- **e** Don't display errors.
- j Skip junctions (when used with /S)
- **s** Don't display the summary.
- t Don't update the CD / CDD extended directory search 3 database (JPSTREE.IDX).
- **/O** Only copy the source file if the target file doesn't exist.
- Ask the user to confirm each *source* file. Your options at the prompt are explained in detail under Page and File Prompts [102]. Note: the Copy Prompt on Overwrite [47] configuration option can be used to force prompting at the command line only. See also: the Q188 option below.
- Don't display filenames, percentage copied, total number of files copied, etc... When used in combination with the /P last option above, it will prompt for filenames but will not display the totals. This option is most often used in batch files. See also /T last.
- Prompt the user before overwriting an existing file. Your options at the prompt are explained in detail under Page and File Prompts
 See also: the Copy Prompt on Overwrite
 Overwrite AT configuration option. (For compatibility with CMD.EXE, a /Y option on the command line is changed to /R.)
- Copy the subdirectory tree starting with the files in the **source** directory plus each subdirectory below that. The **destination** must be a directory; if it doesn't exist, COPY will attempt to create it. COPY will also attempt to create needed subdirectories on the tree below the **destination**, including empty **source** directories. If COPY /S creates one or more destination directories, they will be added automatically to the <u>extended directory search</u> database.

If you attempt to use COPY /S to copy a subdirectory tree into part of itself, COPY will detect the resulting infinite loop, display an error message and exit. Do not use /S with @file lists. See @file lists 90 for details.

If you specify a number after the **/S**, COPY will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", **/S2** will only affect the "a", "b", and "c" directories.

- Turns off the display of filenames, like /Q 1881, but does display the total number of files copied.
- Copy each **source** file only if it is newer than a matching **destination** file or if a matching **destination** file does not exist (see also /C 187). This option is useful for keeping one directory matched with another with a minimum of copying. Do not use /U with @file lists. See @file lists 90 for details. When used with file systems that have different time resolutions (such as FAT 528) and NTFS 532), /U will attempt to use the "coarsest" resolution of the two.
- Verify each disk write by performing a true byte-by-byte comparison between the source and the newly-created target file. This option will significantly increase the time necessary to complete a COPY command.
- Clear the archive attribute from the source file after a successful copy. This option is most useful if you are using COPY to maintain a set of backup files.
- Overwrite *destination* files regardless of their attributes. Without this option, COPY will fail with an "Access denied error" if the *destination* file has its read-only attribute set, or (depending on other options) its hidden or system attribute set. Required to overwrite read-only targets regardless of other options. Required to overwrite hidden or system targets unless the source also has the attribute, and either /H | 187 | or /A: | 187 | is used to select it.

3.13.21 DATE

Purpose: Display and optionally change the system date.

```
Format: DATE [/T] [mm -dd -yy]

mm The month (1 - 12)
dd The day (1 - 31)
yy The year (80 - 99 or a 4- digit year)

/T (Display only) 1901
```

See also: TIME 347.

Usage:

If you simply type DATE without any parameters, you will see the current system date and time, and be prompted for a new date. Press **Enter** if you don't wish to change the date. If you type a new date, it will become the current system date, which is included in the directory entry for each file as it is created or altered:

```
date
Fri Sep 1, 2006 9:30:06
Enter new date (mm-dd-yy):
```

You can also enter a new system date by typing the DATE command plus the new date on the command line:

date 11-16-2006

You can use hyphens, slashes, or periods to separate the month, day, and year entries. The year can be entered as a 2-digit or 4-digit value. Two-digit years between 80 and 99 are interpreted as 1980 - 1999; values between 00 and 79 are interpreted as 2000 - 2079.

DATE adjusts the format it expects depending on your country settings. When entering the date, use the correct format for the country setting currently in effect on your system.

You can also use the international date format yyyy-mm-dd.

Option:

T Displays the current date but does not prompt you for a new date. If a new date is specified in the same command as T the new date will be ignored.

3.13.22 DEBUGSTRING

Purpose: Write text to the debugger for display.

Format: DEBUGSTRING string.

Usage:

If the application has no debugger, the system debugger displays the message. If the application has no debugger and the system debugger is not active, DEBUGSTRING does nothing.

3.13.23 **DEFER**

Purpose: Execute a command after the batch file exits

Format: DEFER command

Usage:

A batch file can have multiple DEFER commands. They will be executed in first in, first out order when the batch file exits.

If you have variables on the DEFER command line, they will be expanded before the DEFER command is processed, not when *command* is executed. To delay variable expansion until *command* is executed, use single back quotes around the variable names, or double the %'s before the variable names.

3.13.24 DEL / ERASE

Purpose: Erase one file, a group of files, or entire subdirectories.

Format: DEL [ranges] [/A:[[-|+]rhsadecijopt /E /F /I"text" /K /N[defjst] /P /Q /R /S[n] /T /W /X /Y /Z] [

@file] file...

file The file, subdirectory, or list of files or subdirectories to erase.

@file A text file containing the names of the files to delete, one per line (see @file

lists 90 for details).

/A: (Attribute select) 1931 /Q(uiet) 1931 /R(ecycle bin) 1931 /E (No error messages) 1931 /S(ubdirectories) 1931

```
/F(orce delete) 1931 / (T(otal) 1941 / W(ipe) 1941 / W(ipe) 1941 / X (remove empty subdirectories) 1941 / Y(es to all prompts) 1941 / Z(ap hidden and read-only files) 1941
```

File Selection

Supports attribute switches 6, extended wildcards 7, ranges 6, multiple file names 6, and include lists 8. Use wildcards with caution on LFN volumes; see LFN File Searches 6, for details.

Internet

Can be used with FTP/HTTP Servers 93.

Usage

DEL and ERASE are synonyms. You can use either one. In the description below, every reference to DEL applies equally to ERASE.

Use the DEL command with caution. The files and subdirectories that you erase may be impossible to recover without specialized utilities and a lot of work.

To erase a single file, simply enter the file name:

```
del letters.txt
```

You can also erase multiple files in a single command. For example, to erase all the files in the current directory with a .BAK or .PRN extension:

```
del *.bak *.prn
```

When you use DEL on an LFN drive 53th, you must quote any file names which contain white space or special characters.

To exclude files from a DEL command, use a <u>file exclusion range 85</u>. For example, to delete all files in the current directory except those whose extension is .TXT, use a command like this:

```
del /[!*.TXT] *
```

When using exclusion ranges or other more complex options you may want to use the **/N** switch first, to preview the effects of the DEL without actually deleting any files.

If you enter a subdirectory name, or a filename composed only of wildcards (* and/or ?), DEL asks for confirmation (Y or N) unless you specified the /Y option. If you respond with a Y, DEL will delete all the files in that subdirectory (hidden, system, and read-only files are only deleted if you use the /Z option). NOTE: The Windows command processor, CMD.EXE, behaves the same way but does not ask for confirmation if you use /Q to delete files quietly. If you want *TCC* to follow CMD.EXE's approach and skip the confirmation prompt when /Q is used, set the Prompt on Wildcard Deletes 47 configuration option. Use caution if you disable this option, as this will allow DEL /Q to delete an entire directory without prompting for confirmation.

DEL displays the amount of disk space recovered, unless the /Q option is used (see below). It does so by comparing the amount of free disk space before and after the DEL command is executed. This amount may be incorrect if you are using a deletion tracking system which stores deleted files in a hidden directory, or if another program performs a file operation while the DEL command is executing.

Remember that DEL removes file descriptions along with files. Most deletion tracking systems will not be able to save or recover a file's description, even if they can save or recover the data in a file. This applies to the use of DEL with the Windows Recycle Bin, too - the description will be lost.

When a file is deleted without using the Recycle Bin, its disk space is returned to the operating system for use by other files. However, the contents of the file remain on the disk until they are overwritten by another file. If you wish to obliterate a file or wipe its contents clean, use the /W option, which overwrites the file with zeros before deleting it. Use this option with caution. Once a file is obliterated, it is impossible to recover. Remember: /W overrides using the Recycle Bin.

DEL returns a non-zero exit code if no files are deleted, or if another error occurs. You can test this exit code with the %_? | 380| internal variable, and use it with conditional commands | 120| (&& and ||).

Use caution when using wildcards with DEL on LFN drives, because *TCC*'s wildcard matching can match both short and long filenames. This can delete files you did not expect; see <u>LFN File Searches</u> for additional details.

• Recycle Bin

When you delete files with DEL, *TCC* does not move the deleted files to the Windows Recycle Bin by default. You can change this default with the <u>Delete to Recycle Bin and place deleted files</u> in the recycle bin with the <u>Isolated Recycle Bin and place deleted files</u> in the recycle bin with the <u>Isolated Recycle Bin and place deleted files</u> in the recycle bin with the <u>Isolated Recycle Bin and place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and Place deleted files</u> in the recycle bin with the <u>Isolated Bin and B</u>

```
del /r letters.txt
```

If you have enabled Recycle Bin support, but want to override the default setting on a one-time basis, and delete some files without placing them in the recycle bin, use the /K (193) option:

```
del /k letters.txt
```

You can also exclude files from the Recycle bin, even if Delete to Recycle Bin 47 is enabled, or if the command use the /R 1931 option, with the RecycleExclude 3691 environment variable.

FTP Usage

If you have appropriate permissions, you can delete files on FTP servers 3. For example:

```
del ftp://ftp.abc.com/index
```

You can also use the IFTP | 255 command to start an FTP session on a server and then use one of the following syntax examples:

```
del ftp:path/*.txt
del ftp:/path/*.txt
```

The first syntax will normally be interpreted by the server as relative to the path you specified when you used the IFTP command to start the FTP session. The second syntax, with a slash before the path name, is interpreted as starting from the root.

NTFS File Streams

DEL supports file streams on NTFS drives. You can delete an individual stream by specifying the stream name, for example:

del streamfile:s1

If no stream name is specified the entire file is deleted, including all streams.

See NTFS File Streams 496 for additional details.

Options

- Delete only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Do not use /A: with @file lists. See @file lists | 90 | for details.
- /B If DEL can't delete the file (for example, if access is denied) it will schedule it to be deleted at the next reboot.
- /E Suppress all non-fatal error messages, such as "File Not Found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files and aliases.
- This option has the same effect as \(\begin{align*} \frac{\Z}{194} \end{align*} \) (see below): it deletes read-only, hidden, and system files as well as normal files.. It is included for compatibility with CMD.EXE.
- /I"text" Select filenames by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]".
- /K Physically delete files instead of sending them to the Windows Recycle Bin.
- /N Do everything except actually delete the file(s). This is useful for testing the result of a DEL.

A /N with one of the following arguments has an alternate meaning:

- **d** Skip hidden directories (when used with /S)
- e Don't display errors
- f Don't display the bytes freed in the summary
- j Skip junctions (when used with /S)
- **s** Don't display the summary
- t Don't update the CD / CDD extended directory search (JPSTREE.IDX)
- /P Prompt the user to confirm each erasure. Your options at the prompt are explained in detail under Page and File Prompts 102.
- Don't display filenames as they are deleted, or the number of files deleted or bytes freed. If Prompt on Wildcard Deletes is disabled then /Q also disables the normal confirmation prompt when performing wildcard deletions (e.g. DEL *), for compatibility with CMD.EXE. Use caution if you disable Prompt on Wildcard Deletes (47), as this will allow DEL /Q to delete an entire directory without prompting for confirmation. See also /T
- /R Delete files to the Windows Recycle Bin.
- Delete the specified files in this directory and all of its subdirectories. This is like a GLOBAL DEL, and can be used to delete all the files in a subdirectory tree or even a whole disk. Do not use /s with @file lists. See @file lists 90 for details.

If you specify a number after the /S, DEL will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

Don't display filenames as they are deleted, but display the total number of files deleted plus the amount of free disk space recovered. Unlike /Q [193], the /T option will not speed up deletions under DOS.

Clear the file to zeros before deleting it. Use this option to completely obliterate a file's contents from your disk. Once you have used this option it is impossible to recover the file even if you are using an undelete utility, because the contents of the file are destroyed before it is deleted. /W overwrites the file only once; it does not adhere to security standards which require multiple overwrites with varying data when destroying sensitive information. /W will override a /R [193].

- Removes empty subdirectories (only useful when used with /S [193]). If DEL deletes one or more directories, they will be removed automatically from the extended directory search database [73].
- The reverse of /P 193 it assumes a Y response to everything, including deleting an entire subdirectory tree. **TCC** normally prompts before deleting files when the name consists only of wildcards or a subdirectory name (see above); /Y overrides this protection and should be used with extreme caution!
- Delete read-only, hidden, and system files as well as normal files. Files with the read-only, hidden, or system attribute set are normally protected from deletion; /Z overrides this protection, and should be used with caution. Because EXCEPT works by hiding files, /Z will override an EXCEPT command. However, files specified in a file exclusion range sh will not be deleted by DEL /Z.

For example, to delete the entire subdirectory tree starting with $C: \UTIL$, including hidden and read- only files, without prompting (use this command with CAUTION!):

del /s /x /y /z c:\util\

3.13.25 DELAY

Purpose: Pause for a specified length of time.

Format: DELAY [/B /M time]

time The number of seconds or milliseconds to delay.

/B(reak enabled) 195 /M(illiseconds) 195

Usage:

DELAY is useful in batch file loops while waiting for something to occur. For example, to wait for 10 seconds:

delay 10

DELAY is most useful when you need to wait a specific amount of time for an external event, or check a system condition periodically. For example, this batch file checks the battery status (as reported by your Advanced Power Management drivers) every 15 seconds, and gives a warning when battery life falls below 30%:

```
do forever
  iff %_apmlife lt 30 then
    beep 440 4 880 4 440 4 880 4
    echo Low Battery!!
  endiff
  delay 15
enddo
```

The *time* value can be as large as about 1 billion seconds (34 years!). If you don't enter a *time*, the default is 1 second.

TCC uses the minimum possible processor time during a DELAY, in order to allow other applications full use of system resources.

You can cancel a delay by pressing Ctrl-C or Ctrl-Break.

Options:

/B Allows terminating a DELAY by pressing a key.

/M Count by milliseconds instead of seconds. Normally only used for delays of less than 1 second.

3.13.26 DESCRIBE

Purpose: Create, modify, or delete file and subdirectory descriptions.

Format: Creating or modifying descriptions

DESCRIBE [ranges... /I"text"] [/A:atrlst] [@file] file [[/D]"description"]] ...]

Description file updating

DESCRIBE /U [[d:\path\descript.ion] ...]]

file The file or files to operate on.

@file A text file containing the names of the files to describe, one per line

(see @file lists 90 for details).

"description" The description to attach to the file.

/A: (Attribute select) 197 /I (match description) 197 /U(pdate) descriptions file 197

See also: @DESCRIPT [415], DIR [198], and SELECT [312]

File Selection

Supports attribute switches 66, extended wildcards 77, ranges 80, multiple file names 87, and include lists 88. Use wildcards with caution on LFN volumes; see LFN File Searches 89 for details.

Usage:

DESCRIBE adds descriptions to files and subdirectories. (Volume root directories cannot have descriptions.) The descriptions are displayed by <u>DIR [198]</u> in single-column mode and by <u>SELECT [312]</u>, and can be retrieved using the <u>@DESCRIPT [415]</u> function. Descriptions let you identify your files in much more meaningful ways than you can in a filename alone.

You enter a description on the command line by typing the DESCRIBE, the filename, and the description in double quotes, like this:

```
describe memo.txt "Memo to Bob about party"
```

If you don't put a description on the command line, DESCRIBE will prompt you for it:

```
describe memo.txt
Describe "memo.txt" : Memo to Bob about party
```

If you use wildcards or multiple filenames with the DESCRIBE command and don't include the description text, you will be prompted to enter a description for each file. If you do include the description on the command line, all matching files will be given the same description.

When you use DESCRIBE on an LFN start drive, you must quote *file* if it contains white space or special characters.

If you enter a quoted description on the command line, and the text matches the name of a file in the current directory, *TCC* will treat the string as a quoted file name, not as description text as you intended. To resolve this problem use the /D | switch immediately prior to the quoted description (with no intervening spaces). For example, if the current directory contains the files *DATA.TST* and "*Test File*", the first of these commands will work as intended, but the second will not (in the second example the string "test file" will be treated as a second file name, when it is intended to be description text):

```
describe data.tst /D"test file" correct command
describe data.tst "test file" incorrect command
```

On <u>LFN</u> [53] drives you will not see file descriptions in a normal <u>DIR</u> [198] display, because <u>DIR</u> [198] must leave space for the long filenames. To view the descriptions, use <u>DIR</u> [198] /Z to display the directory in FAT format. See <u>DIR</u> [198] for more details.

Each description can be up to 511 characters long. You can change this limit with the Maximum Length option. In order to fit your descriptions on a single line in a standard DIR display, keep them to 40 characters or less (longer descriptions are wrapped in the DIR output). DESCRIBE can edit descriptions longer than Maximum Length of (up to a limit of 511 characters), but will not allow you to lengthen the existing text.

The descriptions are stored either in the NTFS SummaryInformation stream (if you have set the NTFS Descriptions option), or in each directory in a hidden file called DESCRIPT.ION. Use the ATTRIB option command to remove the hidden attribute from this file if you need to copy or delete it. DESCRIPT.ION is always created as a hidden file, but will not be rehidden by **TCC** if you remove the hidden attribute.

You can change the description file name with the Description Filename of Configuration option or the SETDOS /D (323) command, and retrieve it with the MDNAME (385) internal variable. Use caution when changing the description file name, as changing the name from the default will make it difficult to transfer file descriptions to another system.

The description file is modified appropriately whenever you perform an internal command which affects it (such as COPY 182), MOVE 274), DEL 190), or RENAME 305), but not if you use an external program (such as XCOPY or Explorer). You can disable description processing with the Enable Descriptions configuration option, or with SETDOS /D 323).

When you COPY [182], MOVE [274] or REN [305] files between two directories, both of which have descriptions, and you use switches which enable processing of hidden files (or you have removed the hidden attribute from DESCRIPT.ION), you must use caution to avoid overwriting existing file descriptions in the *destination* directory with the DESCRIPT.ION file from the *source* directory. See the notes under the **Advanced Features** sections of COPY [182] and MOVE [274] for additional details.

If you disable descriptions with the <u>SETDOS</u> [323] /D0 option, DESCRIBE will return with an error message.

Options:

/A:

Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Do not use /A: with @file lists. See @file lists 90 for details.

/D"description"

The quoted string following the /p switch without any separation is used as a description, not a file name, avoiding ambiguity in the meaning of quoted strings. See the **Usage** section above for details.

/I"text"

Select files by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the // immediately, with no intervening spaces. You can select all filenames that have a description with // "[?]*", or all filenames that do not have a description with // "[]". Do not use // with @file lists. See @file lists 90 for details.

Update the *DESCRIPT.ION* file (or the file specified by the <u>Description Filename and Configuration option</u>), deleting the entries for any nonexistent files. If no filename is supplied, DESCRIBE will process *DESCRIPT.ION* in the current directory. Otherwise, DESCRIBE will process *DESCRIPT.ION* in the specified path(s). This option may not be used in conjunction with other DESCRIBE options.

3.13.27 DETACH

Purpose: Start a console (character-mode) application program in detached mode.

Format: DETACH [/Q] command

/Q(uiet) 1981

command

The name of a command to execute, including an optional drive and path specification and any parameters. The name must be enclosed in double

quotes if it contains any spaces.

See also: START 33 and TASKEND 342.

Usage:

When you start a program with DETACH, that program cannot use the keyboard, mouse, or video display. It is "detached" from the normal means of user input and output. However, you can redirect the program's standard I/O to other devices if necessary, using redirection symbols. In most cases, you should only DETACH text-mode programs, since most graphical applications cannot run without a screen or keyboard, or have their input and output redirected.

The **command** can be an internal command, external command, alias, or batch file. If it is not an external command, **TCC** will detach a copy of **TCC** to execute the command.

For example, the following command will detach a copy of TCC to run the batch file XYZ.BTM:

detach xyz.btm

You can also include any parameters or command line switches which the command knows how to interpret:

```
detach "xyz.btm Monday Nebraska"
```

Once the program has started, *TCC* returns to the prompt immediately. It does not wait for a detached program to finish.

The Process ID of the detached program is returned in the _DETACHPID [385] variable.

You can use the <u>TASKEND</u> [342] command to stop a detached program which does not terminate on its own.

Options:

/Q Don't display the new process's ID.

3.13.28 DIR

Purpose: Display information about files and subdirectories.

one or more ranges 80

Format: DIR [ranges] [options] [file...]

ranges

options

```
file
            The file, directory, or list of files or directories to display.
/1 205
        1 column output
                                       /L 206
                                                 Lower case
                                       /M 206
/2 205
        2 column output
                                                 suppress footer
                                       /N 206
/4 205
        4 column output
                                                 New format or disable options
                                       [eshv]
/: 205
        show streams
                                       /0 206
                                                 Order
/A 205
                                       /P 207
        Attribute select
                                                 Pause
/B 205
                                       /Q 207
                                                 show owner
        Bare (name only)
/C 206
                                       /R 207
        show Compression
                                                 disable wrap
/D 206
        Disable color coding
                                       /S 207 n
                                                 show Subdirectories to depth n
                                       /T 207
/E 206
        upper case
                                                 show aTtribute
/F 206
        Full path
                                       /T: 207
                                                 time type
/G 206
                                       /U 208
                                                 show summary information
        allocated size
/H 206
                                       / 208
        Hide dots
                                                 Vertical sort
/ 206
                                       /W 208
        description range
                                                 Wide
"text"
```

/X 208

/Z 208

show short names

use FAT format

one or more file selection or report format options 205

See also: ATTRIB 1631, DESCRIBE 1951, PDIR 2881, SELECT 3121, and SETDOS 3231.

File Selection

/J 206

/K 206

Supports extended wildcards 77, ranges 80, multiple file names 87, and include lists 88.

Internet: Can be used with FTP servers 93.

Justify names

suppress header

Usage:

DIR can be used to display information about files from one or more directories (local or remote), in a

wide range of formats. Depending on the options chosen, you can display the file name, attributes, and size; the time and date of the last change to the file; the file description; and the file's compression ratio. You can also display information in 1, 2, 4, or 5+ columns, sort the files several different ways, use color to distinguish file types, and pause after each full screen.

If you want to produce customized output that will be subsequently parsed by another program or batch file, or if you need a special-purpose directory display, see the PDIR | 288 | command. DIR and PDIR are related, but they do not have identical switches and they are not intended to produce identical output.

The various DIR displays are controlled through options or switches. The best way to learn how to use the many options available with the DIR command is to experiment. You will soon know which options you want to use regularly. You can select those options permanently by using the ALIAS 1541 command.

For example, to display all the files in the current directory, in 2 columns, sorted vertically (down one column then down the next), and with a pause at the end of each page:

```
dir /2/p/v
```

To set up this format as the default, using an alias:

```
alias dir=*dir /2/p/v
```

When you use DIR on an LFN drive, you must quote any file names which contain white space or special characters.

The following sections group DIR's features together in several categories. Many of the sections move from a general discussion to more technical material. If you find some of the information in a category too detailed for your needs, feel free to skip to the beginning of the next section. The sections are:

- ▶ Selecting Files 199
- Default DIR Output Format 2007
- ▶ Switching Formats 201
- Multiple Column Displays 202
- Color-Coded Directories 203
- Redirected Output 204
- Other Notes 204
- Options 205
- ▶ FTP usage 204

Selecting Files

DIR can display information about a single file or about several, dozens, hundreds, or thousands of files at once. To display information about a single file, just add the name of the file to the DIR command line:

```
dir january.wks
```

The simplest way to view information about several files at once is to use wildcards. DIR can work with the normal wildcard characters (* and ?) and the <u>extended wildcards</u> 77. For example to display all of the .*WKS* files in the current directory:

```
dir *.wks
```

To display all . TXT files whose names begin with A, B, or C:

```
dir [abc]*.txt
```

If you don't specify a filename, DIR defaults to * on LFN drives, and *.* on drives which do not support long file names. This default displays all non-hidden files and subdirectories in the current directory. If you specify a filename for a **non-LFN** drive which includes some wildcards, and does not include an extension, DIR will append .* to it to match all extensions.

If you link two or more filenames together with spaces, DIR will display all of the files that match the first name and then all of the files that match the second name. You may use a different drive and path for each filename. This example lists all of the .WKS and then all of the .WK1 files in the current directory:

```
dir *.wks *.wk1
```

If you use an include list 88 to link multiple filenames, DIR will display the matching filenames in a single listing. Only the first filename in an include list can have a path; the other files must be in the same path. This example displays the same files as the previous example, but the .WKS and .WK1 files are intermixed:

```
dir *.wks; *.wk1
```

You can include files in the current or named directory plus all of its accessible subdirectories by using the /s option. This example displays all of the .WKS and .WK1 files in the D:\DATA directory and each of its subdirectories:

```
dir /s d:\data\*.wks;*.wk1
```

You can also select files by their attributes by using the **/A** option. For example, this command displays the names of all of the subdirectories of the current directory:

```
dir /a:d
```

Finally, with the /I option, DIR can select files to display based on their descriptions (see <u>DESCRIBE</u> for more information on file descriptions). DIR will display a file if its description matches the text after the /I switch. The search is not case sensitive. You can use wildcards and extended wildcards as part of the text. For example, to display any file described as a "Test File" you can use this command:

```
dir /i"test file"
```

If you want to display files that include the words "test file" anywhere in their descriptions, use extended wild cards like this:

```
dir /i"*test file*"
```

To display only those files which do not have descriptions, use:

```
dir /I"[]"
```

In addition, you can use ranges to select or exclude specific sets of files. For example, to display all files modified in the last week, all files except those with a *.BAK* extension, and all files over 500 KB in size:

```
dir /[d-7]
dir /[!*.bak]
dir /[s500K]
```

You can mix any of these file selection techniques in whatever ways suit your needs.

Default DIR Output Format

DIR's output varies based on the type of volume or drive on which the files are stored. If the volume supports long file names, the default DIR format contains 4 columns: the date of the last file modification or write, the time of last write, the file size in bytes, and the file name. The name is displayed as it is stored on the disk, in upper, lower, or mixed case. DIR will wrap filenames from one line to the next if they are too long to fit the width of the display. The standard output format is:

(See Switching Formats below for information on changing the standard long filename format to allow room for file descriptions.)

On FAT volumes which do not support long file names, the default DIR format contains 5 columns: the file name, the file size in bytes, the date of the last write, the time of the last write, and the file's description. File names are listed in lower-case; directory names in upper case:

DIR's output is normally sorted by name, with directories listed first. You can change the sort order with the **/O** option. For example, these two commands sort the output by date — the first command lists the oldest file first; the second command lists the oldest file last:

```
dir /o:d
dir /o:-d
```

When displaying file descriptions, DIR wraps long lines to fit on the screen. DIR displays a maximum of 40 characters of text in each line of a description (unless your screen width allows a wider display). If you disable description wrapping with the **/R** option, the description is truncated at the right edge of the screen, and a right arrow is added at the end of the line to alert you to the existence of additional description text.

DIR's default output is sorted. It displays directory names first, with "<DIR>" inserted instead of a file size, and then filenames. DIR assumes that sequences of digits should be sorted numerically (for example, the file *DRAW2* is listed before *DRAW03* because 2 is numerically smaller than 03), rather than strictly alphabetically (where *DRAW2* would come second because "2" follows "0" in alphanumeric order). You can change the sort order with the **/O** option. When DIR displays file names in a multi-column format, it sorts file names horizontally unless you use the **/V** option to display vertically sorted output.

DIR's display can be modified in many ways to meet different needs. Most of the following sections describe the various ways you can change DIR's output format.

Switching Formats

On volumes which support long file names, you can force DIR to use a FAT-like format (file name first, followed by file information) with the **/Z** option. If necessary, DIR /Z truncates long file names on LFN drives, and adds a right arrow to show that the name contains additional characters.

The standard LFN output format does not provide enough space to show descriptions along with file names. Therefore, if you wish to view file descriptions as part of the DIR listing on a volume which supports long file names, you must use the **/Z** option.

DIR will display the alternate, short file names for files with long file names if you use the /X option. Used alone, /X causes DIR to display names in 2 columns after the size, time, and date: one column for alternate or short file names and the other for long file names. If a file does not have a short or alternate name which is different from the long filename, the first filename column is empty.

If you use /X and /Z together, DIR will display the short or alternate file names in the FAT-style display format.

If you use the **/B** option, DIR displays just file names and omits the file size, time stamp, and description for each file, for example:

```
[c:\] dir w* /b
WINDOWS
WINNT
WINALIAS
WINENV.BTM
```

There are several ways to modify the display produced by /B. The /F option is similar to /B, but displays the full path and name of each file, instead of just its name. To view the same information for a directory and its subdirectories use /B /S or /F /S. You can use /B /X to display the short name of each file, with no additional information.

Multiple Column Displays

DIR has three options, 12, 14, and 1W, that create multi-column displays.

The /2 option creates a 2-column display. On drives which support long filenames, only the name of each file is displayed, with directory names placed in square brackets to distinguish them from file names. On drives which do not support long filenames, or when /Z or /X is used (see below), the display includes the short name, file size, and time stamp for each file.

The /4 option is similar to /2, but displays directory information in 4 columns. On drives which do not support long filenames, or when /Z or /X is used (see below), the display shows the file name and the file size in kilobytes (KB) or megabytes (MB), with "<D>" in the size column for directories.

The **/W** option displays directory information in 5 or more columns, depending on your screen width. Each entry in a DIR /W display contains either the name of a file or the name of a directory. Directory names are placed in square brackets to distinguish them from file names.

If you use one of these options on a drive that supports long file names, and do not select an alternate display format with /Z or /X, the actual number of columns will be based on the longest name to be displayed and your screen width, and may be less than the number you requested (for example, you might see only three columns even though you used /4). If the longest name is too long to fit in on a single line the display will be reduced to one column, and each name will be wrapped, with "extra" blank lines added so that each name takes the same number of lines.

On LFN drives you can use **/Z** with any of the multi-column options to create a FAT-format display, with long names truncated to fit in the available space. If you use **/X**, the FAT-format display is also used, but short names are displayed (rather than truncated long names). The following table summarizes the effects of different options when using **TCC** on an LFN drive:

	default or /1 205	/2 or /4 columns	/W (wide)
Normal	date, time, size, LFN		No. of columns based on longest LFN
	truncated LFN, size, date, time		5+ columns, truncated LFNs only
	date, time, size, SFN, LFN	2 - 4 columns, SFNs plus date, time, size	5+ columns, SFNs only
/X 2081 /Z	SFN, size, date, time	(Same as /X)	(Same as /X)

Color-Coded Directories

DIR can display each file name and the associated file information in a different color, depending on the file's extension.

To choose the display colors, you must either use the <u>SET</u> (319) command to create an environment variable called <u>COLORDIR</u> (368), or use the <u>Directory Colors</u> (49) configuration option. If you use neither the variable nor the configuration option, DIR will use the default screen colors for all files.

If you use the COLORDIR variable, it will override the <u>Directory Colors [49]</u> option. You may find it useful to use the COLORDIR variable for experimenting, then to set permanent directory colors with the <u>Directory Colors [49]</u> option.

The format for both the COLORDIR environment variable and the Directory Colors option is:

```
ext ... :ColorName; ...
```

where "ext" is either a file extension (which may include wildcards) or one or more of the following file types:

type	files affected
ARCHIVE	Files with archive attribute set (modified since the last backup)
COMPRESSED	Compressed files
DIRS	Directories
ENCRYPTED	Encrypted files
HIDDEN	Hidden files
JUNCTION	Junctions or symbolic links
NORMAL	File with no attribute set
NOTINDEXED	Files whose content is not indexed
OFFLINE	Offline files
RDONLY	Read-only files
SPARSE	Sparse files
SYSTEM	System files
TEMPORARY	temporary files

and "ColorName" is any valid color name (see Colors and Color Names 518) for information on color names).

Note that if a file uses one of the reserved file type names shown above as its extension (e.g. *xyz.hidden*), that file will receive the color defined for the file type.

Unlike most color specifications, the background portion of the color name may be omitted for directory colors. If you don't specify a background color, DIR will use the current screen background color.

For example, to display .COM and .EXE files in red on the current background, .C and .ASM files in bright cyan on the current background, read-only files in green on white, and everything else in the default color:

```
set colordir=com exe:red; c asm:bright cyan; rdonly:green on white
```

Extended wildcards \(\overline{\pi} \) can be used in directory color specifications. For example, to display \(.BAK, \) \(.BAX, \) and \(.BAC \) files in red, and everything else in the default color:

```
set colordir=BA[KXC]:red
```

You can combine attribute tests with the .and. / .or. / .xor. / .not. keywords. For example, to display directories that are also hidden in blue:

```
set colordir=dirs .and. hidden:blue
```

COLORDIR processes the line from left to right, and does not support parentheses.

Redirected Output

The output of the DIR command, like that of most other internal commands, can be redirected stop to a file, printer, serial port, or other device. However, you may need to take certain DIR options into account when you redirect DIR's output.

DIR wraps both long file names and file descriptions at the width of your display. Its redirected output will also wrap at the screen width. Use the **/R** option if you wish to disable wrapping of long descriptions.

If you redirect a color-coded directory to a file or a character device, DIR will remove the color data as it sends the directory information to a file.

To redirect DIR output to the clipboard, use **CLIP:** as the output device name, for example:

```
dir *.exe > clip:
```

FTP Usage

You can display directories on FTP servers 93. For example:

```
dir ftp://jpsoft.com/tcmd
```

You can also use the IFTP |255| command to start an FTP session on a server, and then use a simplified syntax to specify the files and directories you want.

Other Notes

If you have selected a specific country code for your system, DIR will display the date in the format for that country. The default date format is U.S. (mm-dd-yy). The separator character in the file time will also be affected by the country code. Thousands and decimal separators in numeric displays are affected by the country code, and by the ThousandsChar and DecimalChar settings selected with the configuration dialogs or in the .INI file [26].

DIR can generally display any file date between January 1, 1980 and December 31, 2099 if the date is supplied properly by the operating system.

If you are using NTFS disk compression, you can use the /C switch to view the amount of compression

achieved for each file. When you do, the compression ratio is displayed instead of the file's description. You can also sort the display by compression ratios with the **/O:c** switch. Details for both switches are in the Options section below. **/C** and **/O:c** will be ignored for uncompressed drives. **/C** will not display compression ratios on drives that support long file names unless you also use **/Z** to switch to the old-style short filename format.

If the OFFLINE attribute is set, DIR will display the file size enclosed in parentheses (for compatibility with CMD.EXE).

Options:

Options on the command line apply only to the filenames which follow the option, and options at the end of the line apply to the preceding filename only. This allows you to specify different options for different groups of files, yet retains compatibility with the traditional DIR command when a single filename is specified.

- Single column display display the filename, size, date, and time; also displays the description on drives which do not support long filenames. This is the default. If /T is used the attributes are displayed instead of the description; if /C or /O:c is used the compression ratio is displayed instead of the description. This option is most useful if you wish to override a default /2, /4, or /W setting stored in an alias. In Windows Vista or later on NTFS drives, single column displays will also show the target of symbolic links following the filename.
- Two column display display just the name (on LFN drives), or display the filename, size, date, and time on other drives. See **Multiple Column Displays** above for more details.
- Four column display display just the name (on LFN drives); or display the filename and size, in K (kilobytes) or M (megabytes) on other drives, with files between 1 and 9.9 megabytes in size displayed in tenths (*i.e.*, "2.4M"). See **Multiple Column Displays** above for more details.
- *I*: Display file stream names and sizes on NTFS volumes. When combined with the /B or /F options, the size is omitted.

When **/**: is used in conjunction with **/B** (Bare), the file name is displayed on the first line, then any streams, indented two spaces, on subsequent lines:

```
c:\test\myfile.dat
  xyz:$DATA
  abc:$DATA
```

When **/:** is used in conjunction with **/F** (Full path), the file name is displayed on the first line, then any streams are appended to the filename on subsequent lines:

```
c:\test\myfile.dat
c:\test\myfile.dat:xyz
c:\test\myfile.dat:abc
```

- /A[:] Display only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:.
- Suppress the header and summary lines, and display file or subdirectory names only, in a single column. This option is most useful when you want to redirect a list of names to a file or another program. If you use /B with /S, DIR will show the full path of each file (the same display as /F) instead of simply its name and extension. If you use /B with /X on an LFN drive, DIR will display the short name of each file instead of the long name. /B also

sets /H.

- Display per-file and total compression percentage on NTFS drives with compression enabled. /C only works in single-column mode; it is ignored if /2, /4, or /W is used.
- Temporarily disable directory color coding. May be required when color-coded directories are used and DIR output is redirected to a character device like a serial port (e.g., COM1). /D is not required when DIR output is redirected to a file.
- **/E** Display filenames in upper case.
- /F Display each filename with its drive letter and path in a single column, without other information. If you use /F with /X, the "short" version of the entire path is displayed.
- /G Display the allocated disk space instead of the actual size of each file.
- **/H** Suppress the display of the "." and ".." directories.
- /I"text" Select filenames by matching text in their descriptions. The text can include wildcards real and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]".

The /I option may be used to select files even if descriptions are not displayed (for example, if /2 is used). However, /I will be ignored if /C or /O:c is used.

- Justify (align) filename extensions and display them in the FAT format. If on an LFN drive, you must also specify the /X and /Z options.
- **/K** Suppress the header (disk and directory name) display.
- **/L** Display file and directory names in lower case.
- **/M** Suppress the footer (file and byte count totals) display.
- **/N** Use the long filename display format, even if the files are stored on a volume which does not support long filenames. See also **/Z**.

A /N with one of the following arguments has an alternate meaning:

- **d** Skip hidden directories (when used with /S)
- **e** Don't display an error message if no files match.
- f Don't display "bytes free" in the summary
- j Skip junctions (when used with /S)
- h Don't display the header
- **s** Don't display the summary.
- **v** Don't display the volume information.
- Set the sorting order. You may use any combination of the sorting options below. If multiple options are used, the listing will be sorted with the first sort option as the primary key, the next as the secondary key, and so on:
 - n Sort by filename and extension, unless **e** is explicitly included. This is the default.
 - Reverse the sort order for the next sort key
 - a Sort names and extensions in standard ASCII order, rather than sorting by magnitude when numeric substrings are included in the name or extension.

- Sort by compression ratio (the least compressed file in the list will be displayed first). For single-column directory displays in the short filename format, the compression ratios will be used as the basis of the sort and will also be displayed. For wider displays (/2, /4, and /W) and displays in LFN format, the compression ratios will be used to determine the order but will not be displayed. For information on supported compression systems see /C above.
- d Sort by date and time (oldest first); also see /T:acw
- Sort by extension
- g Group subdirectories first, then files
- i Sort by file description (ignored if **/C** or **/O:c** is also used)
- Sort by owner
- r Reverse the sort order for all options
- s Sort by size
- u Unsorted
- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts Prompts Prompts
- /Q Display the file or directory owner (NTFS and remote directories only).
- /R Forces long descriptions to be displayed on a single line, rather than wrapped onto two or more lines. Use /R when output is redirected to a character device, such as a serial port or the printer; or when you want descriptions truncated, rather than wrapped, in the on-screen display.
- Display file information from the current directory and all of its accessible subdirectories. DIR will only display headers and summaries for those directories which contain files that match the filename(s), ranges, and attributes that you specify on the command line. DIR will display hidden subdirectories for compatibility with **CMD.EXE**.

If you specify a number after the /S, DIR will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

Display the filenames and attributes in the format RHSADENTPCOIJ, regardless of volume type:

R Read-only Α Archive Н Hidden Subdirectory S System C Ε Encrypted Compressed Normal 0 Offline Ν

T Temporary
 P Sparse file
 I Not content-indexed
 J Junction or symbolic link

Attributes which are set are represented by their letter, unset attributes by the _ (underscore) character.

If you wish to add another option after /T, you must start the next option with a forward slash. If you don't, TCC will interpret the /T as the $/T:{acw}$ time display switch (see below) and the following character as a time selector. For example:

/T:a|c|w[u] Specify which of the date and time fields on a drive which supports long filenames

should be displayed and used for sorting:

- Last access date and time (on VFAT volumes access time is always midnight).
- c Creation date and time.
- w Last modification (write) date and time (default).

If you append a \boldsymbol{u} after the field, DIR will display the file time in UTC.

- Only display the number of files, the total file size, and the total amount of disk space used. Information on individual files is not displayed. /U1 will display summaries for each directory, but no total summary for each parent directory. /U2 displays the grand total only.
- Display the filenames sorted vertically rather than horizontally (use with the /2 205), /4 205) or /W 208) options).
- Display filenames only, horizontally across the screen. On drives which do not support long filenames, or when used with /z or /x, /w displays as many columns as it can fit into *TCC* window, using 16 characters in each column. Otherwise (*i.e.*, when long filenames are displayed) the number of columns depends on the width of the longest name in the listing. See **Multiple Column Displays** above for more details.
- Display both the short name (8-character name plus 3-character extension) and the long name of each file on an LFN drive. In normal single-column output the short name is displayed first, followed by the long name. The short name column is left blank if the short name and long name are the same. On *NTFS* volumes this means case insensitive match, but on *VFAT* volumes this means case sensitive match (i.e., no lower case letters in the *SFN*). /X also selects short filenames in the /2 205, /4 205, /B 205, /W 208, and /Z displays, and short file and path names in the /F display.
- Display filenames on LFN drives in the old-style format, with the filename on the left and the description (when available) on the right. Long names will be truncated to 12 characters unless /X 200 is also used. If the name is longer than 12 characters, it will be followed by a → "right arrow" symbol to show that one or more characters have been truncated. If a description file 51 exists, /Z defaults to using the name of the . and .. directories as description for those entries

3.13.29 DIRHISTORY

Purpose: Display, add to, clear, or read the directory history list.

Format: DIRHISTORY [/A directory /F /G /L /N /P /R filename]

directory The name of a directory to be added to the directory history.

filename The name of a file containing entries to be added to the directory history.

/A(dd) 209 /N(o duplicates) 209 /P(ause) 209 /P(ause) 209 /R(ead) 209 /R(ead)

See also: HISTORY 25 h.

Usage

Every time you change to a new directory or drive, TCC saves the previous directory in an internal

directory history list. The <u>directory history window</u> allows you to use the list to return to a previous directory. See also: <u>directory navigation</u> 71.

The DIRHISTORY command lets you view and manipulate the directory history list directly. If no parameters are entered, DIRHISTORY will display the current directory history list:

```
dirhistory
```

With the options explained below, you can clear the list, add new directories to the list without changing to them, save the list in a file, or read a new list from a file.

The number of directories saved in the directory history list depends on the length of each directory name. The list size can be specified at startup with the <u>Directory History Buffer Size</u> on figuration option. The default size is 2,048 characters.

Your directory history list can be stored either locally (a separate history list for each copy of *TCC*) or globally (all copies of *TCC* share the same list). For details see the discussion of <u>local and global</u> <u>history lists</u> 1081. If you use global lists, <u>SHRALIAS</u> 3291 can save the list when no copy of *TCC* is active, as long as you do not restart Windows.

You can save the directory history list by redirecting the output of DIRHISTORY to a file. This example saves the history to a file called *DIRHIST* and reads it back again.

```
dirhistory > dirhist
    ....
dirhistory /r dirhist
```

Because the directory history stores each name only once, you don't have to delete its contents before reading back the file unless you want to delete the directories that were visited by the intervening commands.

TCC can also load and save the history list automatically if you use the <u>Directory History File</u> on Configuration option.

Options

/A Add a directory to the directory history list.

/F Erase all entries in the directory history list.

/G Switch from a local to a global directory history list.

/L Switch from a global to a local directory history list.

/N Removes duplicate entries (oldest first) from the directory history list.

Wait for a key after displaying each page of the list. Your options at the prompt are explained in detail under Page and File Prompts 102.

/R Read the directory history from the specified file and append it to the list currently held in memory.

3.13.30 DIRS

Purpose: Display the current directory stack.

Format: DIRS

See also: PUSHD [299], POPD [294], @DIRSTACK [416] and Directory Navigation [71].

Usage:

The PUSHD [299] command adds the current default drive and directory to the directory stack, a list maintained by **TCC**. The POPD [294] command removes the top entry of the directory stack and makes that drive and directory the new default. The DIRS command displays the contents of the directory stack, with the most recent entries on top (*i.e.*, the next POPD will retrieve the first entry that DIRS displays).

For example, to change directories and then display the directory stack:

```
[c:\] pushd c:\database
[c:\database] pushd d:\wordp\memos
[d:\wordp\memos] dirs
c:\database
c:\
```

The directory stack holds 2048 characters, enough for 40 to 80 typical drive and directory entries.

3.13.31 DO

Purpose: Create loops in batch files.

Format: DO loop_control

commands
[ITERATE 213]
commands
[LEAVE 213]
commands
ENDDO

Loop_control formats

```
DO 211 count
DO FOREVER 211
DO 211 varname = start TO end [BY step]
DO WHILE 212 condition
DO UNTIL 212 condition
DO UNTIL DATETIME 212 date time
DO FOR 212 n [SECONDS | MINUTES | HOURS]
DO 212 varname IN [range...] /D"directory" [/I:"text" /S[n] /A:[[-|+]rhsadecijopt] fileset
DO 212 varname IN [/T"delimiters"] /L stringset
DO 212 varname IN /C stringset
DO 212 varname IN @file
```

count Integer in the range [0, 2 147 483 647], or an internal variable or variable

function that evaluates to such a value, specifying the number of times

the loop is executed.

varname The environment variable containing the current value of the loop index,

or the current filename or string, or the current line from a file. Do not

prefix the variable name with %.

start, end, step Integers in the range [-2 147 483 647,2 147 483 647] or internal variables

or variable functions that evaluate to such values, controlling the number

of times the loop is executed.

condition A conditional expression to determine whether or not the loop should

be executed

fileset
A filename or list of filenames, possibly using wildcards restringset
An arbitrary set of strings. Wildcards are not interpreted.

A file each line of which contains a string the loop is to be executed for A date, time, size or exclusion range. At most one of each, in any order. One or more commands to execute each time through the loop. If you

use multiple commands, they must be separated by command

separators or be placed on separate lines.

time

separators or be placed on separate lines.

The loop termination date in ISO 9601 format

The loop termination time in 24-h hh:mm:ss format

/A: 213 (Attribute select)

/C 213 Loop through each character in expression

/D"directory" 213 Start directory

/l"text" 214 (match description) Description range. /L(iteral) 214 members of **set** are strings, not filenames

/S 214 Perform the loop in the current directory and all its subdirectories

Supports extended wildcards , ranges , and include lists for the **set**. Use wildcards with caution on LFN volumes; see LFN File Searches for details.

Usage

DO can only be used in batch files 1301.

Types of DO Loops

DO can be used to create several different kinds of loops.

DO count, is a counted loop. The batch file lines between DO and ENDDO are repeated count times. TCC does not provide the user with the count of how many times the loop has been executed, though it is possible for the user to create a such a mechanism. For example::

```
set ct=0
do 5
  beep
  set ct=%@inc[%ct]
enddo
```

- DO FOREVER creates an endless loop. You must use LEAVE 213 or GOTO 248 to exit such a loop.
- DO varname = start TO end [BY step] is similar to a "for loop" in programming languages like BASIC. DO creates an environment variable, varname, and sets it equal to the value start. If varname already exists in the environment, it will be overwritten. DO then begins the loop process by comparing the value of varname with the value of end. If step is positive or not specified, and varname is less than or equal to end, DO executes the batch file lines up to the ENDDO. Next, DO adds to the value of varname either the value of step if BY step is specified, or 1, and repeats the compare and execute process until varname is greater than end. This example displays the even numbers from 2 through 20:

```
do i = 2 to 20 by 2
echo %i
enddolea
```

DO can also count down, rather than up. If **step** is negative, **varname** will be decreased by the absolute value of **step** with each loop, and the loop will stop when **varname** is less than **end**. For example, to display the even numbers from 2 through 20 in reverse order, replace the first line of the example above with:

```
do i = 20 to 2 by -2
```

- DO WHILE *condition* evaluates *condition* each time through the loop as a <u>conditional expression</u>

 | before executing the loop, and will execute it only if it is true. If *condition* is FALSE when the DO is first executed, the loop will never be executed.
- DO UNTIL *condition* evaluates *condition* as a <u>conditional expression rose</u> each time **after** execution of the loop, and repeats the loop only if it is FALSE. Therefore, the statements within the loop will always be executed at least once.
- DO UNTIL DATETIME *date time* executes the loop until the current date and time is equal to or greater than the specified date (ISO format) and time (24-hour format). The date and time can be in either YYYY-MM-DD HH:MM:SS or YYYYMMDDHHMMSS format. (The date and/or time can be a variable.)
- DO FOR *n* SECONDS | MINUTES | HOURS executes the loop for the specified amount of time.
- DO *varname* IN *fileset* executes the commands between DO and ENDDO by creating an environment variable, *varname*, and setting it equal to every filename in the *fileset*, ignoring items not matching file or directory names. This is similar to the *set* used in the FOR (234) command, but it can only include file and directory names, not arbitrary text strings. If *varname* already exists in the environment, it will be overwritten (unlike the control variable in FOR) (234). For example:

```
do x in *.txt
...
enddo
```

will execute the loop once for every .TXT file in the current directory; each time through the loop the variable x will be set to the name of the next file that matches the file specification. The order of matches is dependent on the file system, and is totally unrelated to any characteristics of the filenames matched.

If, between DO and ENDDO, you create a new file that could be included in the list of files, it may or may not appear in an iteration of the DO loop. Whether the new file appears depends on its physical location in the directory structure, a condition over which **TCC** has no control.

To use date, time, size, description, or file exclusion $\underline{\text{ranges}}^{\text{80}}$ for the **set** place them just before the filename(s), for example:

```
do x in /[d9-1-2004,9-31-2004] *.txt
```

- DO *varname* IN /L *stringset* executes the commands between DO and ENDDO once for every string literal in *stringset*, setting *varname* to each in turn.
- DO varname IN /C stringset executes the commands between DO and ENDDO once for every character in stringset (including whitespace and special characters), setting varname to each in turn.
- DO *varname* IN *@file* executes the commands between DO and ENDDO once for every line in *file*, setting *varname* to the content of each one in turn. Beware of characters with special meaning to *TCC*, such as redirection and piping symbols, within the file (use <u>SETDOS</u> 323) /X as needed).

To execute the loop once for each line of text in the clipboard, use **CLIP**: as the file name (*e.g.* DO X IN @CLIP:). **CLIP**: will not return any data unless the clipboard contains text. See Redirection for more information on **CLIP**:

Special DO keywords: ITERATE and LEAVE

Two special keywords, ITERATE and LEAVE, may be used inside a DO / ENDDO loop. ITERATE ignores the remaining commands inside the loop and returns to the beginning of loop for another iteration, unless DO determines that the loop is finished. LEAVE exits from the current DO loop and continues with the command following its ENDDO. Both keywords may be repeated as often as desired. Both ITERATE and LEAVE are most often used in an IF 255 or IFF 254 command (group):

```
do while "%var" != "%val1"
    ...
    if "%var" == "%val2" leave
enddo
```

Usage Notes

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

DO loops can be nested, i.e. you can have a DO/ENDDO loop within another DO/ENDDO loop.

The DO and ENDDO commands must be on separate lines, and cannot be placed within a command group [12th], or on the same line as other commands. (This is the reason DO loops cannot be used in aliases.) However, commands within the DO loop can use command groups or the command separator in the normal way. For example, the following command will not work properly, because the DO and ENDDO are inside a command group and are not on separate lines:

```
if "%a" == "%b" (do i = 1 to 10 & echo %i & enddo) invalid command line
```

However, this batch file fragment uses multiple commands and command grouping within the DO, and will work properly:

```
do i = 1 to 10
    ...
    if "%x1" == "%x2" (echo Done! & leave)
    ...
enddo
```

You can exit from all DO / ENDDO loops by using GOTO 248 to a line past the corresponding ENDDO. However, be sure to read the cautionary notes about GOTO 248 and DO under the GOTO 248 command before using GOTO in any other way inside any DO loop.

You cannot use RETURN 307 to return from a GOSUB 247 while inside a DO loop.

Note: Do not confuse the DO command with the unrelated optional **do** keyword of the FOR 234 command.

Options:

Select the files in a DO 212x IN ... by their specified attribute(s). See Attribute

Switches 86 for information on the attributes which can follow /A:.

/C For each loop, assign the next character (including whitespace and special characters) in the expression to the DO variable.

/D" directory Set the start directory (for use with /S).

- /I" text" Select files in a DO 212x IN ... by matching text in their descriptions. See Description Ranges 86 for details.
- /L The parameters following DO 212x IN /L are strings, not filenames. Each parameter will be assigned in sequence, from left to right, to the loop control variable on consecutive passes through the loop.
- /N Disable options:
 - d Skip hidden directories (when used with /S)
 - Skip junctions (when used with /S) i
- /S Perform the DO loop in the current directory and then on all of its subdirectories. (DO also supports /R as a synonym, for compatibility with FOR.)

If you specify a number after the /S, DO will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", \S2 will only affect the "a", "b", and "c" directories.

/T"text" Specify the delimiters to be used when parsing a string set.

3.13.32 DRAWBOX

Purpose: Draw a box on the screen.

Format: DRAWBOX ulrow ulcol Irrow Ircol style [BRIght] fg ON [BRIght] bg [FILL [BRIght] bgfill]

[ZOOm] [SHAdow]

ulrow Row for upper left corner ulcol Column for upper left corner Irrow Row for lower right corner Column for lower right corner Ircol

style Box drawing style:

No lines (box is drawn with blanks)

- 1 Single line 2 Double line
- Single line on top and bottom, double on sides

Double line on top and bottom, single on sides Foreground character color fg

Background character color bg Background fill color (for the inside of the box) bafill

See also: DRAWHLINE 215 and DRAWVLINE 216.

Usage:

DRAWBOX is useful for creating attractive screen displays in batch files.

For example, to draw a box around the edge of an 80x25 window with bright white lines on a blue background:

drawbox 0 0 24 79 1 bri whi on blu fill blu

See Colors and Color Names 518 for details about colors.

If you use ZOOM, the box appears to grow in steps to its final size. The speed of the zoom operation

depends on the speed of your computer and video system.

If you use SHADOW, a drop shadow is created by changing the characters in the row under the box and the 2 columns to the right of the box to normal intensity text with a black background (this will make characters displayed in black disappear entirely).

The row and column values are zero-based, so on a standard 25 line by 80 column display, valid rows are 0 - 24 and valid columns are 0 - 79.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). DRAWBOX checks for valid row and column values, and displays a "Usage" error message if any values are out of range.

The maximum **row** value is determined by the current height of the **TCC** window. The maximum **column** value is determined by the current virtual screen width (see <u>Resizing the Take Command Window</u> for more information).

If *ulrow* is set to 999, *Irrow* is assumed to be the desired height, and the box will be centered vertically. If *ulcol* is set to 999, *Ircol* is assumed to be the desired width, and the box will be centered horizontally.

Unlike DRAWHLINE and DRAWVLINE, DRAWBOX does not automatically connect boxes to existing lines on the screen with the proper connector characters. If you want to draw lines inside a box and have the proper connectors drawn automatically, draw the box first, then use DRAWHLINE and DRAWVLINE to draw the lines.

DRAWBOX uses the standard line and box drawing characters in a Unicode or U.S. English extended ASCII character set. If you use an ASCII or raster font which does not include these line drawing characters, the box or lines will not be displayed correctly.

3.13.33 DRAWHLINE

Purpose: Draw a horizontal line on the screen.

Format: DRAWHLINE row column len style [BRIght] fg ON [BRIght] bg

rowStarting rowcolumnStarting columnlenLength of linestyleLine drawing style:1Single line

2 Double line

fg Foreground character colorbg Background character color

See also: DRAWBOX 214 and DRAWVLINE 216.

Usage:

DRAWHLINE is useful for creating attractive screen displays in batch files. It detects other lines and boxes on the display, and creates the appropriate connector characters when possible (not all types of lines can be connected with the available characters).

For example, the following command draws a double line along the top row of the display with green characters on a blue background:

drawhline 0 0 80 2 green on blue

The row and column values are zero-based, so on a 25 line by 80 column display, valid rows are 0 - 24 and valid columns are 0 - 79.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). If either value is out of range, DRAWHLINE displays a "Usage" error message.

The maximum row value is determined by the current height of the **TCC** window. The maximum column value is determined by the current virtual screen width (see Resizing the Take Command Window 68 for more information).

If **row** is set to 999, the line will be centered vertically. If **column** is set to 999, the line will be centered horizontally.

See Colors and Color Names 518 for details about colors.

DRAWHLINE uses the standard line and box drawing characters in a Unicode or U.S. English extended ASCII character set. If you use an ASCII or raster font which does not include these line drawing characters, the box or lines will not be displayed correctly.

3.13.34 DRAWVLINE

Purpose: Draw a vertical line on the screen.

Format: DRAWVLINE row column len style [BRIght] fg ON [BRIght] bg

> row Starting row Starting column column Length of line len style Line drawing style: Single line 1

Double line

Foreground character color fg Background character color bg

See also: DRAWBOX 214 and DRAWHLINE 215.

Usage:

DRAWVLINE is useful for creating attractive screen displays in batch files. It detects other lines and boxes on the display, and creates the appropriate connector characters when possible (not all types of lines can be connected with the available characters).

For example, to draw a double width line along the left margin of the display with bright red characters on a black background:

```
drawvline 0 0 25 2 bright red on black
```

The row and column values are zero-based, so on a 25 line by 80 column display, valid rows are 0 - 24 and valid columns are 0 - 79. Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). If either value is out of range, DRAWVLINE displays a "Usage" error message.

The maximum row value is determined by the current height of the **TCC** window. The maximum column value is determined by the current virtual screen width (see Resizing the Take Command Window 68 for more information).

See Colors and Color Names 518 for details about colors.

DRAWVLINE uses the standard line and box drawing characters in a Unicode or U.S. English extended ASCII character set. If you use an ASCII or raster font which does not include these line drawing characters, the box or lines will not be displayed correctly.

3.13.35 ECHO

Purpose: Enable or disable batch file or command line echoing, display the echoing status on stdout

535), or display a message on stdout 535).

Format: ECHO [ON | OFF | message]

message Text to display.

See also the commands ECHOS [219], ECHOSERR [220], ECHOERR [218], SCREEN [310], SCRPUT [311], TEXT [345] and VSCRPUT [360], and the internal variable ECHO [386].

Usage:

The ECHO command has two unrelated, independently functioning purposes:

- Command line echoing 217
- Message display 217

Command line echoing

When command line echoing is enabled, each command is displayed on stdout stdout after it is fully parsed, aliases, functions, and variables expanded, but before it is executed.

Echoing control

TCC controls command line echoing in batch files and at the interactive prompt independently.

Executing ECHO ON at the command prompt enables, and ECHO OFF disables echoing at the command prompt. ECHO defaults to OFF at the command line. The command-line ECHO is most useful when you are learning how to use advanced features.

Similarly, executing ECHO ON in a batch file enables, and ECHO OFF disables echoing of batch file commands. ECHO defaults to ON in batch files. The current ECHO state is inherited by called batch files. You can change the default setting to OFF with the <u>SETDOS /VO [323]</u> command, or the <u>Batch Echo [47]</u> configuration option.

Regardless of the relevant echoing state, any command prefixed with the at-sign @ will not be echoed.

Echoing state display

To see the current echoing state, use the ECHO command with no parameters. This displays either the batch file or command line echo state, depending on where the ECHO command is performed. Alternately, you can examine the value of the internal variable _ECHO 3861.

Message display

If the ECHO command has a message (the whole <u>command tail [524]</u>, excluding redirection or piping, if any), and message is neither of the words ON or OFF (though it can include those words), message is fully parsed, then displayed on <u>stdout [535]</u>, regardless of the applicable echoing state. Any display sent to <u>stdout [535]</u> after message has been displayed will start on a new line.

Display rules

- The first space after the command name is ignored.
- Trailing spaces in *message* are ignored.
- Functions and variables not enclosed between back quotes are evaluated.
- To include special characters, .e.g, < | >, in *message*, enclose them in double quotes or back quotes (see Parameter Quoting [134]) or precede them with the escape character [124], or use the /X option of the SETDOS [323] command.
- To display % you may alternately use two % marks for each one to be displayed, e.g., %%
- To display trailing spaces, either enclose them in back quotes, or append a pair of back quotes behind them, e.g., echo trailers
- The ASCII 51th NUL character cannot be included in message.
- If <u>stdout [538]</u> is the console, after displaying *message* on the current line, the cursor will be moved to the beginning of the next line.
- If stdout 535 is a file, the CR LF sequence will be appended to message.

To display a blank line, use one of the forms below:

```
echo `` (two consecutive back quotes), or echo. (special syntax for compatibility with CMD.EXE).
```

Examples

This command will display a message:

```
echo Processing your print files...

The command

echo This text is indented 3 spaces ``
will display 3 leading and 3 trailing spaces.
```

3.13.36 ECHOERR

Purpose: Display a message to the standard error device (stderr [535]).

Format: ECHOERR message

message Text to display.

See also: ECHO 217, ECHOS 219, and ECHOSERR 220.

Usage:

ECHOERR (like <u>ECHO 217</u>) in message display mode) parses and expands *message*, and displays it on <u>stderr [535]</u> (usually the screen), instead of <u>stdout [535]</u>. Even if <u>stdout [535]</u> of a batch file is redirected or piped, ECHOERR will still display a screen message, unless <u>stderr [535]</u> is redirected or piped (see <u>Redirection [97]</u>). Any display sent to <u>stderr [535]</u> after *message* has been displayed will start on a new line.

Display rules

• The first space after the command name is ignored.

- Trailing spaces in *message* are ignored.
- Functions and variables not enclosed between back quotes are expanded.
- To include special characters, .e.g, < | >, in *message*, enclose them in double quotes or back quotes (see Parameter Quoting [134]) or precede them with the escape character [124], or use the /X option of the SETDOS [323] command.
- To display % you may alternately use two % marks for each one to be displayed, e.g., %%
- To display trailing spaces, either enclose them in back quotes, or append a pair of back quotes behind them, e.g., echoerr trailers
- The ASCII 511 NUL character cannot be included in message.
- If <u>stderr [535]</u> is the console, after displaying *message* on the current line, the cursor will be moved to the beginning of the next line.
- If stderr [535] is a file, the CR LF sequence will be appended to message.

3.13.37 ECHOS

Purpose: Display a message to standard output (stdout) [535] without a trailing carriage return / line

feed.

Format: ECHOS message

message Text to display.

See also: ECHO 217, ECHOERR 218, ECHOSERR 220, SCREEN 310, SCRPUT 311, TEXT 345, and VSCRPUT 360.

Usage:

ECHOS, like ECHO 217 in message display mode, parses, expands, and displays **message** on stdout 535. However, any display sent to stdout 535 after **message** has been displayed will continue on the same line.

Display rules

- The first space after the command name is ignored.
- Trailing spaces in *message* are ignored.
- Functions and variables not enclosed between back guotes are evaluated.
- To include special characters, .e.g, < | >, in *message*, enclose them in double quotes or back quotes (see Parameter Quoting [134]) or precede them with the escape character [124], or use the /X option of the SETDOS [323] command.
- To display % you may alternately use two % marks for each one to be displayed, e.g., %%
- To display trailing spaces, either enclose them in back quotes, or append a pair of back quotes behind them, e.g., echo trailers
- The ASCII 51th NUL character cannot be included in message.
- ECHOS keeps the cursor on the same line, thus permitting building a line of display using multiple commands

ECHOS is useful for text output when you don't want to add a carriage return / linefeed pair at the end of the line. This is useful if your whole line of text requires more than one command to build, and also for controlling character devices.

3.13.38 ECHOSERR

Purpose: Display a message to the standard error device (stderr start) without a trailing carriage

return / line feed.

Format: ECHOSERR message

message Text to display.

See also: ECHO 217, ECHOS 219, and ECHOERR 218.

Usage:

ECHOSERR acts as a combination of <u>ECHOS</u> and <u>ECHOERR</u> and <u>ECHOERR</u> and expands *message*, and displays it on <u>stderr</u> sab. However, any display sent to <u>stderr</u> after *message* has been displayed will continue on the same line.

Display rules

- The first space after the command name is ignored.
- Trailing spaces in *message* are ignored.
- Functions and variables not enclosed between back quotes are evaluated.
- To include special characters, .e.g, < | >, in *message*, enclose them in double quotes or back quotes (see Parameter Quoting [134]) or precede them with the escape character [124], or use the /X option of the SETDOS [323] command.
- To display % you may alternately use two % marks for each one to be displayed, e.g., %%
- To display trailing spaces, either enclose them in back quotes, or append a pair of back quotes behind them, e.g., echo trailers
- The ASCII 511 NUL character cannot be included in message.
- ECHOSERR keeps the cursor on the same line, thus permitting building a line of display using multiple commands

3.13.39 EJECTMEDIA

Purpose: Eject removable media in the specified drive(s)

Format: EJECTMEDIA drive ...

Usage:

EJECTMEDIA will eject removable media, such as CD-ROMs, DVDs, etc. (It is not intended for unmounting USB drives.)

See also LOADMEDIA 269.

3.13.40 ENDLOCAL

Purpose: Restore the saved disk drive, directory, environment, alias list, and special characters, and

exports selected variables.

Format: ENDLOCAL [/D] [exportvar ...]

/D(ont restore) 22h

See also: SETLOCAL 3261.

Usage:

The <u>SETLOCAL</u> 326 command in a batch file saves the current disk drive, default directory, all environment variables, the alias list, and the command separator, escape character, parameter character, decimal separator, and thousands separator. It does not save the user-defined function list. ENDLOCAL restores everything that was saved by the previous <u>SETLOCAL</u> 326 command, except as described below.

For example, this batch file fragment saves everything, removes all aliases so that user aliases will not affect batch file commands, changes the disk and directory, changes the command separator, runs a program, and then restores the original values:

```
setlocal
unalias *
cdd d:\test
setdos /c~
program ~ echo Done!
endlocal
```

SETLOCAL [326] / ENDLOCAL may be nested within a single batch file up to 16 levels of nesting. You can also have multiple, separate SETLOCAL [326] / ENDLOCAL pairs within a batch file, and nested batch files can each have their own SETLOCAL [326] / ENDLOCAL.

You cannot use SETLOCAL 326 and ENDLOCAL in an alias or at the command line.

An ENDLOCAL is performed automatically at the end of a batch file, or when returning from a "

GOSUB [247] filename". If you invoke one batch file from another without using CALL [175], the first batch file is terminated, and an automatic ENDLOCAL is performed; the second batch file inherits the settings as they were prior to any SETLOCAL [326].

· Exporting environment variables

The environment variables whose names are specified in the ENDLOCAL command are exported. This means that their names and values from inside the <u>SETLOCAL</u> [326] / ENDLOCAL will be placed into the restored environment, either adding variables, or possibly modifying them. In the example below, the variable TEST will have the value **abcd** after the ENDLOCAL is executed, regardless of what its value was, or even if it had not been previously defined:

```
setlocal
set test=abcd
endlocal test
```

The list of variables to export may contain wildcards. All variables matching the requested pattern will be exported.

Exporting current working directory

See option /D 221 below.

Options:

(Don't restore directory) Export the current directory: the original drive and directory saved by SETLOCAL 3261 will not be restored.

3.13.41 ESET

Purpose: Edit an environment variable, alias or function definition.

Format: ESET [/A /D /F /M /S /U /V /W] name

name The name of an environment variable, function or alias to edit.

/A(lias) 223 /S(ystem variable) 223 /U(ser variable) 223 /V(olatile variable) 223 /V(olatile variable) 223 /W(indowed Editing) 223 /W(indowed Editing) 223

See also: ALIAS 154), FUNCTION 242), SET 319), UNALIAS 355), UNFUNCTION 356), and UNSET 357).

Usage:

ESET allows you to edit an environment variable, alias or function definition using line editing commands (see Command Line Editing 104).

For example, to edit the executable file search path:

```
eset path
path=c:\ic:\dosic:\util
```

To create and then edit an alias:

```
alias d = dir /d/j/p
eset d
d=dir /d/j/p
```

Unless a specific data type is specified by one of the option switches /A, /D, /F, /M, /S, /U or /V, ESET will search for *name* among environment variables first and then among aliases, thus if *name* is both a variable and an alias, ESET will edit the variable *name*, and ignore the alias *name*.

To edit variables defined in the Windows Registry or to edit functions, you **must** use the appropriate option switch.

Environment variable and alias names are limited to 80 characters. The total length of the name and value combined is limited by the maximum line length (8,191 characters). If you use special techniques to create a longer environment variable, ESET will edit it, provided it contains no more than 8,191 characters.

Note: You cannot use ESET with GOSUB variables 247).

If you have enabled global aliases (see ALIAS [154]), any changes made to an alias with ESET will immediately affect all other copies of **TCC** which are using the same alias list. Similarly, if you have enabled global functions (see FUNCTION [242]), any changes made to a function using ESET /F will immediately affect all other copies of **TCC** which are using the same function list.

Registry Variables: Default, System, User, and **Volatile** registry variables can be manipulated with the ESET command's **/D**, **/S**, **/U** and **/V** switches, respectively. For example, to edit volatile variable **myvar** from the registry, use:

```
eset /v myvar
```

Use caution when directly modifying registry variables as they may be essential to various Windows

processes and applications.

Options:

/A Edit the named alias even if an environment variable of the same name exists. If you have an alias and an environment variable with the same name, you must use this switch to be able to edit the alias.

/F Edit a user-defined function.

/D Edit a "default" variable in the registry (HKU\.DEFAULT\Environment).

/M Edit the "master" environment (inherited by TCC at startup). Note that the master environment is only used if you run START 331 with the /I option.

/S Edit a "system" variable in the registry (HKLM\System\CurrentControlSet\Control\Session Manager\Environment).

/U Edit a "user" variable in the registry (HKCU\Environment).

/V Edit a "volatile" variable in the registry (HKCU\Volatile Environment).

/W Edit the environment variable, alias, or function list in a popup window like that used by the Batch File Debugger 1661. Note that any variable name passed to ESET will be ignored when this option is used. Non-environment variables (/D, /S, /U, /V) may not be edited with this option.

3.13.42 EVENTLOG

Purpose: Write a string to the Windows event log.

Format: EVENTLOG [/Cn /E /I /S source /W] message

> message The text to write.

source The source for this message.

/C(ategory) 224 /S(ource) 224 /E(rror) 224 /W(arning) 224

/I(nformational) 224

See also: HISTORY 25th and LOG 2691.

Usage:

EVENTLOG posts messages to the Windows application event log. Each message can be a maximum of 8,191 characters long. You cannot use the command separator 5th character ([&]) or the redirection [97] symbols (| > <) in an EVENTLOG message, unless you enclose the message in quotes or precede the special characters with the escape character 1241.

By default, the text written with EVENTLOG is stored in the event log as informational messages. You can store warning and error messages by using the /W and /E switches.

Messages in the log can be reviewed with the Windows Event Log viewer.

If you do not have proper registry permissions when you execute the EVENTLOG command and/or the

key cannot be created, EVENTLOG will fail and display an error. EVENTLOG is primarily intended for use by users with **Administrator** status.

Options:

/Cn Set the event category. The value can be from 0-999999; Windows defines 0-7 as:

- 0 None
- 1 Devices
- 2 Disk
- 3 Printers
- 4 Services
- 5 Shell
- 6 System
- 7 Network
- /E Store the message as an error entry in the event log.
- /I Store the message as an informational entry in the event log. This is the default if no switch is used.
- /S Specify the event log entry source. (If the source contains white space, it must be double-quoted). For example:

```
eventlog /sCompiling /I Your message here.
```

/W Store the message as a warning entry in the event log.

3.13.43 EVENTMONITOR

Purpose: Monitor event logs

Format: EVENTMONITOR [/C [name]]

EVENTMONITOR server name /S"source" /T"type" /D"description" n command

server UNC name of the machine with the log file

name log name

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(lear) | 224 | /S"source" | 225 | /T"type | 225 |

Usage:

If you don't enter any arguments, EVENTMONITOR will display the events it is currently monitoring.

The command line will be parsed and expanded before EVENTMONITOR is executed, so if you want to pass redirection characters or variables to **command** you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

You can specify multiple /D, /S, and /T arguments. If you want to monitor multiple events in a log, put them into a single EVENTMONITOR command. EVENTMONITOR creates a separate thread for each EVENTMONITOR command, so if you have multiple commands you will be wasting CPU time, RAM, and risk having *command* executed simultaneously in different threads.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the

command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use <u>START ash</u> or <u>DETACH ash</u> in *command* to avoid conflicts.

EVENTMONITOR creates environment variables when an event is triggered that can be queried by *command*. The variables are deleted after *command* is executed.

_eventcomputer The name of the computer than generated the event

_eventcount The number of times the condition has been triggered

_eventdesc The event description

_eventlog The name of the event log

_eventsource The name of the source that wrote the event

_eventtype The event type (see /T 225) below)

Options:

If name is specified, remove the monitor for that event. Otherwise, remove all event monitors.

/D Description for the event to be monitored. Only events with a matching description will set the trigger. The description may contain regular expressions.

Source for the event to be monitored. Only events with a matching source will set the trigger. The source may contain regular expressions.

Type of event to be monitored. Only events with a matching type will set the trigger. The types of events are:

Success Error Warning Information Audit_Success Audit Failure

3.13.44 EXCEPT

Purpose: Perform a command on all available files except those specified.

Format: EXCEPT [/I"text"] [(@file) | (file ...)] command

file The file or files to exclude from the command.

@file A text file containing the names of the files to exclude, one per line (see

@file lists 90 for details).

command The command to execute, including all appropriate parameters and

switches.

/I (match description) 227

See also: ATTRIB 163 and File Exclusion Ranges 85.

File Selection

Supports extended wildcards , ranges , multiple file names , and include lists . Date, time, size, or file exclusion ranges must appear immediately after the EXCEPT keyword.

Use wildcards with caution on LFN volumes; see LFN File Searches 89 for details.

Usage:

EXCEPT provides a means of executing a command on a group of files and/or subdirectories, and excluding a subgroup from the operation. The *command* can be an internal command or alias, an external command, or a batch file.

You may use wildcards to specify the files to exclude from the *command*. The first example erases all the files in the current directory except those beginning with *MEMO*, and those whose extension is .*WKS*. The second example copies all the files and subdirectories on drive C to drive D except those in *C:WSC* and *C:VDOS*, using the COPY command:

```
except (memo* *.wks) erase *
except (c:\msc c:\dos) copy c:\* d:\ /s
```

When you use EXCEPT on an LFN drive, you must quote any file names inside the parentheses which contain white space or special characters. For example, to copy all files except those in the "Program Files" directory to drive E:\:

```
except ("Program Files") copy /s * e:\
```

EXCEPT will assume that the files to be excluded are in the current directory, unless another directory is specified explicitly.

EXCEPT prevents operations on the specified file(s) by setting the hidden attribute, performing the command, and then clearing the hidden attribute. If the command is aborted in an unusual way, you may need to use the ATTRIB command to remove the hidden attribute from the file(s). Files which already had the hidden attribute, and are included in the set matching EXCEPT, will not be hidden after EXCEPT is competed. The hidden attribute of files not matching EXCEPT will not be changed.

Caution: EXCEPT will not work with programs or commands that ignore the hidden attribute or which work explicitly with hidden files, including <u>DEL [190]</u>/Z, and the **/H** (process hidden files) switch available in internal file processing commands.

File exclusion ranges 85 provide a faster and more flexible method of excluding files from internal commands, and do not manipulate file attributes, as EXCEPT does. However, exclusion ranges can only be used with internal commands; you must use EXCEPT for external commands.

Date, time, and size ranges can be used immediately after the word EXCEPT to further qualify which files should be excluded from the *command*. If the *command* is an internal command that supports ranges, an independent range can also be used in the *command* itself. You can also use a file exclusion range within the EXCEPT command; however, this will select files to be excluded from EXCEPT, and therefore included in execution of the *command*.

You can use <u>command grouping</u> 121 to execute multiple *commands* with a single EXCEPT. For example, the following command copies all files in the current directory whose extensions begin with .DA, except the .DAT files, to the D:\SAVE directory, then changes the first two characters of the extension of the copied files to .SA:

```
except (*.dat) (copy *.da* d:\save & ren *.da* *.sa*)
```

If you use filename completion (see Filename Completion 113) to enter the filenames inside the

parentheses, type a space after the open parenthesis before entering a partial filename or pressing Tab. Otherwise, the command line editor will treat the open parenthesis as the first character of the filename to be completed.

Option:

/I"text"

Select files by matching text in their descriptions. The text can include wildcards wildcards. The search text must be enclosed in double quotes, and must follow the // immediately, with no intervening spaces. You can select all filenames that have a description with // immediately. The control of the con

3.13.45 EXIT

Purpose: Exit the current TCC session.

Format: EXIT [/B] [value]

value The numeric exit code to return.

/B (exit from batch file) 227

Usage:

EXIT terminates the current copy of the command processor.

To close the session, or to return to the application that started the command processor, type:

exit

If you specify a value, EXIT will return that value to the program that started the command processor. For example:

exit 255

The *value* is a number you can use to inform the program of some result, such as the success or failure of a batch file. It can range from 0 - 4,294,967,295.

Option:

/B

Exit the current batch file, rather than the shell. This switch is for compatibility with **CMD.EXE**. The <u>CANCEL</u> 176 and <u>QUIT</u> 301 commands are generally more flexible for use in batch files.

3.13.46 FFIND

Purpose: Search for files by name or contents.

FFIND [/A[[:][-]rhsadecijopt /B /C /D[/ist] /E["text"] /F /G /I /I"text" /K /L /M /N

/O[[:][-]acdeginorsu] /P /R /S[n] /[T|X]"xx" /U /V /Y /+n /-n] file...

list A list of disk drive letters (without colons).

file The file, directory, or list of files or directories to display.

 /A(ttribute select) | 229 |
 /M (no footers) | 230 |

 /B(are) | 229 |
 /N(ot) | 230 |

 /C(ase sensitive) | 229 |
 /O(rder) | 230 |

 /D(rive) | 229 |
 /P(ause) | 230 |

```
/E (upper case) 230
                                     /R(everse search order) 231
/E"xx" (regular expression) 230
                                     /S(ubdirectories) 231
/F (stop after match) 230
                                     /T"xx" (text search string) 231
/G (goto directory) 230
                                     /U (summary only) 231
/I(gnore wildcards) 230
                                    /V (verbose) 231
/I"text" (match description) 230
                                    /X["xx"] (hex display / search string) 23
                                    /Y (prompt to stop after match) 231
/K (no headers) 230
/L(ine numbers) 230
                                    /[+|-] skip matches 232
```

File Selection

Supports extended wildcards 77, ranges 80, multiple file names 87, and include lists 88.

Internet: Can be used with FTP Servers 93.

Usage:

FFIND is a flexible search command that looks for files based on their names and their contents. Depending on the options you choose, FFIND can display filenames, matching text, or a combination of both in a variety of formats.

If you don't supply a file name, FFIND will read from standard input. (This allows you to pipe or redirect input to FFIND.)

If you want to search for files by name, FFIND works much like the DIR command. For example, to generate a list of all the <code>.BTM</code> files in the current directory, you could use the command

```
ffind *.btm
```

The output from this command is a list of full pathnames, followed by the number of files found.

For example, if you want to limit the output to a list of *.BTM files which contain the string *color*, you could use this command instead:

```
ffind /t"color" *v.btm
```

The output from this command is a list of files that contain the string *color* along with the first line in each file that contains that string. By default, FFIND uses a case-insensitive search, so the command above will include files that contain *COLOR*, *Color*, *color*, or any other combination of upper-case and lower-case letters.

If you would rather see the last line of each file that contains the search string, use the /R option, which forces FFIND to search from the end of each file to the beginning. This option will also speed up searches somewhat if you are looking for text that will normally be at the end of a file, such as a signature line:

```
ffind /r /t"Sincerely," *.txt
```

You can use **TCC** extended wildcards in the search string to increase the flexibility of FFIND's search. For example, the following command will find .TXT files which contain either the string June or July. It will also find Juny and Jule. The **/C** option makes the search case-sensitive:

```
ffind /c/t"Ju[nl][ey]" *.txt
```

If you want to search for text that contains wildcard characters (*, ?, [, or]), you can use the /I option to force FFIND to interpret these as normal characters instead of wildcards. The following command, for example, finds all .TXT files that contain a question mark:

```
ffind /i/t"?" *.txt
```

Sometimes you may need to search for data that cannot be represented by ASCII characters. You can use FFIND's /X option to represent the search string in hexadecimal format (this option also changes the output to show hexadecimal offsets rather than text lines). With /X, the search must be represented by pairs of hexadecimal digits separated by spaces (in the example below, 41 63 65 is the hex code for "Ace"):

```
ffind /x"41 63 65" *.txt
```

You can also search using Regular Expressions using the **/E** option. See Regular Expression Syntax for supported expressions.

When you use FFIND on an LFN drive, you must quote any file names which contain white space or special characters.

FFIND can also find files on FTP servers. For example:

```
ffind /t"tcmd" ftp://jpsoft.com/index
```

You can also use the IFTP command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want. For more information, see <u>Using</u> FTP/HTTP Servers 3 and IFTP 25.

Note that searching for text in files on FTP servers (as in the command above) will be slow as the data from each file searched must be retrieved from the server and transferred to your computer to be checked for the search string

Options:

- /A: Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:.
- /B Display file names only and omit the text that matches the search. This option is only useful in combination with /T or /X, which normally force FFIND to display file names and matching text.
- Perform a case-sensitive search. This option is only valid with /T, which defaults to a case-insensitive search. It is not needed with a /X hexadecimal search, which is always case-sensitive.
- Search all files on one or more drives. If you use /D without a list of drives, FFIND will search the drives specified in the list of files. If no drive letters are listed, FFIND will search all of the current drive. You can include a list of drives or a range of drives to search as part of the /D option. For example, to search drives C:, D:, E:, and G:, you can use either of these commands:

```
ffind /dcdeg ... ffind /dc-eg ...
```

Drive letters listed after **/D** will be ignored when processing file names which also include a drive letter. For example, this command displays all the <code>.BTM</code> files on C: and E:, but only the <code>.BAT</code> files on D:

```
ffind /s /dce *.btm d:\*.bat
```

/E Display filenames in upper case.

/E"text" Search for a <u>regular expression [496]</u>. The regular expression must be contained in double quotes if it contains spaces, punctuation, or wildcard characters. See also /T.

/F Stops the search after the first match.

/G Change to the directory where the match was found (must be used with /F).

Only meaningful when used in conjunction with the /T "text" option. Suppresses the recognition of wildcard characters in the search text. This option is useful if you need to search for characters that would normally be interpreted as wildcards: *, ?, [, and].

Select filenames by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the // immediately, with no intervening spaces. You can select all filenames that have a description with //"[?]*", or all filenames that do not have a description with //"[]".

/K Suppress the display of the header or filename for each matching text line.

Include the line number for each text line displayed. FFIND numbers lines beginning with 1. A new line is counted for every CR or LF character (FFIND determines automatically which character is used for line breaks in each file), or when line length reaches the command line length limit 126, whichever comes first.

/M Suppress the footer (the number of files and number of matches) at the end of FFIND's display.

/N Reverse the meaning of the search, i.e., report only files which contain no match. Setting /N will also set /B, i.e. searches are on a file-by-file basis; FFIND cannot search for all lines without match.

Set the sort order for the files that FFIND displays. You may use any combination of the following sorting options; if multiple options are used, the listing will be sorted with the first sort option as the primary key, the next as the secondary key, and so on:

- Reverse the sort order for the next option
- **a** Sort names and extensions in standard ASCII order, rather than sorting numerically when digits are included in the name or extension
- **c** Sort by compression ratio (the least compressed file in the list will be displayed first)
- d Sort by date and time (oldest first); for drives which support long file names
- e Sort by extension
- **g** Group subdirectories first, then files
- i Sort by file description (ignored if /O:c is also used)
- **n** Sort by filename (this is the default)
- Sort by owner
- **r** Reverse the sort order for all options
- **s** Sort by size
- u Unsorted
- Wait for a key to be pressed after each screen page before continuing the display.

 Your options at the prompt are explained in detail under Page and File Prompts 1021.

- /R Only meaningful when used in conjunction with the /T "text" or /X options. Searches each file from the end backwards to the beginning. This option is useful if you want to display the last occurrence of the search string in each file instead of the first (the default). It may also speed up searches for information that is normally at the end of a file, such as a signature.
- Display matches from the current directory and all of its subdirectories. By default, FFIND processes only those subdirectories without the Hidden or System attributes. To view hidden or system subdirectories use /A along with /S. If you specify a number following the /S, FFIND will limit the subdirectory recursion to the number specified. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only go to the "a", "b", and "c" directories.
- /T"text" Specify the text search string. /T must be followed by a text string in double quotes (e.g., /t"color"). FFIND will perform a case-insensitive search unless you also use the /C option. For a hexadecimal search and/or hexadecimal display of the location where the search string is found, see /X. You can specify a search string with either /T or /X, but not both.
- **/U** Display only the summary.
- N Show every matching line. FFIND's default behavior is to show only the first matching line, then to the next file. This option is only valid with /E, /T and /X.
- /X["xx.."] Specify hexadecimal display and an optional hexadecimal search string.

If /X is followed by one or more pairs of hexadecimal digits in quotes (e.g., /x"44 63 65"), FFIND will search for that exact sequence of characters or data bytes without regard to the meaning of those bytes as text. If those bytes are found, the offset is displayed (in both decimal and hexadecimal). A search of this type will always be case-sensitive.

If /X is **not** followed by a hexadecimal search string it must be used in conjunction with /T, and will change the output format to display offsets (in both decimal and hexadecimal) rather than actual text lines when the search string is found. For example, this command uses /T to display the first line in each BTM file containing the word "hello":

```
ffind /t"hello" *.btm
-- c:\test.btm:
echo hello

1 line in 1 file
```

If you use the same command with /X, the offset is displayed instead of the text:

```
ffind /t"hello" /x *.btm
-- c:\test.btm:
Offset: 1A
1 line in 1 file
```

You can specify a search string with either /T or /X, but not both.

/Y Prompt to stop searching after each match. This option is most useful when you are using FFIND to search for one specific file, and don't want to display all files which include a particular search string.

/[+|-]n "/+n" causes FFIND to skip the first n matches. "/-n" causes FFIND to stop after n

matches.

3.13.47 FIREWIREMONITOR

Purpose: Monitor FireWire device connection and disconnection

Format: FIREWIREMONITOR [/C [name]]

FIREWIREMONITOR name CONNECTED | DISCONNECTED n command

name Device name

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(lear) 234

Usage:

The FireWire device name can include wildcards. You can use either the device ID or the "friendly" name for the device.

The command line will be parsed and expanded before FIREWIREMONITOR is executed, so if you want to pass redirection characters or variables to **command** you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

If you don't enter any arguments, FIREWIREMONITOR will display the FireWire devices it is currently monitoring.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use <u>START</u> or <u>DETACH</u> in *command* to avoid conflicts.

FIREWIREMONITOR creates three environment variables when a device is connected or disconnected that can be queried by *command*. The variables are deleted after *command* is executed.

_firewiredeviceid The device ID

_firewirename The "friendly" name of the device

_firewirecount The number of times the condition has been triggered

Options:

/C If **name** is specified, remove the monitor for that FireWire device. Otherwise, remove all FireWire monitors.

3.13.48 FOLDERMONITOR

Purpose: Monitor folder and/or file creation, modification, and deletion

Format: FOLDERMONITOR [/C [folder]]

FOLDERMONITOR /S folder /I file / E file CREATED DELETED MODIFIED RENAMED

n command

folder Folder (directory) name

CREATED Execute the command if the folder or file is created Execute the command if the folder or file is deleted Execute the command if the folder or file is modified Execute the command if the folder or file is renamed

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(lear) 234 /I(include) 234 /S(ubdirectories) 232

Usage:

If you don't enter any arguments, FOLDERMONITOR will display the folders and files it is currently monitoring, in the format:

folder (include/exclude) condition (n) command

The command line will be parsed and expanded before FOLDERMONITOR is executed, so if you want to pass redirection characters or variables to *command* you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

The *MODIFIED* condition is set if the file's size, attributes, or last access date and time are changed.

If you want to monitor multiple conditions for a file or folder, put them into a single FOLDERMONITOR command. FOLDERMONITOR creates a separate thread for each FOLDERMONITOR command, so if you have multiple commands you will be wasting CPU time, RAM, and risk having **command** executed simultaneously in different threads.

When the condition is triggered, the command will be executed immediately in the separate thread. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use START and or DETACH is in *command* to avoid conflicts.

FOLDERMONITOR creates several environment variables when a file or folder is created, deleted, modified, or renamed that can be queried by *command*. The variables are deleted after *command* is executed.

_folderaction The type of change to the file or folder. The possible values are:

CREATED DELETED MODIFIED RENAMED

_foldercount The number of times the condition has been triggered

_foldername The name of the folder being monitored

_folderfile1 The name of the file or folder that was created/deleted/modified/renamed. If the

file was renamed, folderfile1 is the old name.

_folderfile2 If a file was renamed, *folderfile2* is the new name

For example, to monitor your *d:\tesults* directory and copy any new or modified files to a web page:

foldermonitor d:\results created modified forever copy "% folderfile1"

"http://mycompany.com/results/"

Options:

If **name** is specified, remove the monitor for that folder. Otherwise, remove all folder / file monitors. **/C** cannot be combined with any other options.

/E Filename to be excluded. If you want to exclude multiple files, use multiple /E options. If you want to exclude a file in a specific subdirectory, the filename should include the relative path from the folder *name*. The name can include wildcards.

Filename to be included. If you want to include multiple files, use multiple /I options. If you want to include a file in a specific subdirectory, the filename should include the relative path from the folder *name*. The name can include wildcards.

/S Include subdirectories.

3.13.49 FOR

Purpose: Repeat a command for several values of a variable.

Format: File and string mode

FOR [range...] [/I"text"] [/A:[[-|+]rhsadecijopt /D /F ["options"] /H /R [path] [/T"delimiters"]]

%var IN ([@]set) DO command | (command ... [LEAVEFOR])

Counted mode

FOR /L %var IN (start, step, end) DO command | (command ... [LEAVEFOR])

options Parsing options for a "file parsing" FOR.

range One or more range specifications

path The starting directory for a "recursive" FOR.

%var The variable to be used in the command ("FOR variable").

set A set of values for the variable.

start The starting value for a "counted" FOR.step The increment value for a "counted" FOR.end The limit value for a "counted" FOR.

command A command or group of commands to be executed for each value of the

variable.

/A: (Attribute select) 240 / L (counted loop) 240 / R(ecursive) 240 / H(ide dots) 240 / T (delimiter list) 241

File Selection

Supports <u>attribute switches</u> 86, extended <u>wildcards</u> 77, <u>ranges</u> 80, <u>multiple file names</u> 87, and <u>include lists</u> 88.

Ranges must appear immediately after the FOR keyword after alias expansions (if any), and only affect the selection of files specified using wildcards.

Use wildcards with caution on LFN volumes; see LFN File Searches 89 for details.

Usage:

FOR begins by creating a set. It then set the executes a command for every member of set. The

command can be an internal command, an alias, an external command, or a batch file. The members of **set** can be a list of file names, text strings, a group of numeric values, or text read from a list of files.

When **set** is made up of text or several separate file names (not an include list), the elements must be separated by spaces, tabs, or commas.

FOR includes a large number of options, some of which duplicate functions available in other internal commands. It also supports additional conventions not found in our other commands, included for compatibility with *CMD.EXE*.

The first three sections below (Working with Files 235), Working with Text 236), and Retrieving Text from Files 236) describe the FOR command and the enhancements to it which are included in *TCC*. The sections on Parsing Text from Files 236) and Counted FOR Loops 237) describe features added for compatibility with *CMD.EXE*. The sections Directory Recursion 238) and Output Redirection 238) warn of special considerations. The section entitled Other Notes 238) contains information you may need if you use any aspect of the FOR command extensively.

Working with Files

Normally, set is a list of files specified with wildcards. For example, if you use this line in a batch file:

```
for %x in (*.txt) list %x
```

Then LIST 264 will be executed once for each file in the current directory with the extension • TXT. The FOR variable %x is set equal to each of the file names in turn, then the LIST command is executed for each file. (You could do the same thing more easily with a simple LIST *.TXT. We used FOR here so you could get a feel for how it operates, using a simple example. Many of the examples in this section are constructed in the same way.)

Set can include multiple files and include lists, like this:

```
for %x in (d:\*.txt;*.doc;*.asc e:\test\*.txt;*.doc) type %x
```

FOR supports wildcards and extended wildcards $\neg \tau$, as well as extended parent directory 118 names, e.g., . . . \ * . txt to process all of the . TXT files that are contained in the directory 2 levels above the current directory.

By default those members of **set** that include wildcards match only files, not directories.

When you use FOR on an LFN drive, you must quote any file names within set which contain white space or special characters. The same restriction may apply to names returned in the FOR variable, if you pass them to *TCC* internal commands, or other commands which require quoting filenames with white space. FOR does not quote returned names automatically, even if you included quotes in set.

If set includes filenames, the file list can be further refined by using date, time, size, description and file exclusion ranges after the word FOR. Ranges affect only those members of set which contain wildcards. For example, the FOR below will process all of the *.TXT files that were created or updated on December 4, 2005, and of the file ABC.LST regardless of its timestamp:

```
for /[d12-4-2005,+0] %x in (*.txt abc.lst) ...
```

If **command** is an internal command that supports ranges, an independent range can also be used in **command** itself.

You can also refine the list by limiting it with the /A: 240 option to select only files that have specific attributes.

When you use wildcards to specify **set**, FOR scans the directory and finds each file which matches the wildcard name(s) you specified. If, during the processing of the FOR command, you create a new file that could be included in **set**, it may or may not appear in a some later iteration of the same FOR command. Whether or not the new file appears depends on its physical location in the directory structure. For example, if you use FOR to execute a command for all .*TXT* files, and the command also creates one or more new .*TXT* files, those new files may or may not be processed during the current FOR command, depending on where they are placed in the physical structure of the directory. This is a Windows constraint over which **TCC** has no control. Therefore, in order to achieve consistent results you should construct FOR commands which do not create files that could become part of set for the current command.

Working with Text

Set can also be made up of text instead of file names. For example, to create three files named file1, file2, and file3, each containing a blank line:

```
for %suffix in (1 2 3) echo. > file%suffix
```

You can also use the names of environment variables as the text. This example displays the name and content of several variables from the environment (see the general discussion of the Environment of the use of square brackets when expanding environment variables):

```
for %var in (path prompt comspec) echo %var=%[%var]
```

Retrieving Text from Files

If the name of a file in set is prefixed with @ ("at" sign), it is considered as an @file list | 901. FOR extracts each line from the file and places it in the FOR variable.

Warning: if the line contains characters which are syntactically significant for **TCC**, for example, one of the characters <"[]|>, it may have undesirable effects. You may use the /X option of <u>SETDOS</u> 12231 to mitigate them.

If you use @CON as the filename, FOR will read from standard input (typically a redirected input file) or from a pipe. If you use @CLIP: as the filename, FOR will read any text available from the Windows clipboard. See Redirection and Piping of for more information on these features.

See @file list 90 for additional details.

Parsing Text from Files

Another method of working with text from files is to have FOR parse each line of each file for you. To begin a file-parsing FOR, you must use the $\frac{|F|}{240}$ option and include one or more file names in set. When you use this form of FOR, the variable name must be a single letter, for example, **%a**.

This method of parsing, included for compatibility with *CMD.EXE*, can be cumbersome and inflexible. For a more powerful method, use FOR with @filename astable as the set to retrieve each line from the file, as described in the previous section, and use variable functions like @FIELD[426], <a href="mailto:@INSTR]443], <a href="mailto:@LEFT[446], <a href="mailto:@RIGHT[457], and @WORD[472] to parse the line (see Variable Functions[395] for information on variable functions).

By default, FOR will extract the first word or token from each line and return it in the variable. For example, to display the first word on each line in the file *FLIST.TXT*:

```
for /f %a in (flist.txt) echo %a
```

You can control the way FOR /F parses each line by specifying one or more parsing options in a quoted string immediately after the /F. The available options are:

skip=n: FOR /F will skip **n** lines at the beginning of each file before parsing the remainder of the file.

tokens=*n*, *m*, ...: By default, FOR /F returns just the first word or *token* from each parsed line in the variable you named. You can have it return more than one token in the variable, or return tokens in several variables, with this option.

This option is followed by a list of numbers separated by commas. The first number tells FOR /F which token to return in the first variable, the second number tells it which to return in the second variable, etc. The variables follow each other alphabetically starting with the variable you name on the FOR command line. This example returns the first word of each line in each text file in \$d\$, the second in \$e\$, and the third in \$f\$:

```
for /f "tokens=1,2,3" %d in (*.txt) ...
```

You can also indicate a range of tokens by separating the numbers with a hyphen -.

eol=c: If FOR /F finds the character c in the line, it will assume that the character and any text following it are part of a comment and ignore the rest of the line.

delims=xxx..: By default, FOR /F sees spaces and tabs as word or token delimiters. This option replaces those delimiters with all of the characters following the equal sign to the end of the string. This option must therefore be the last one used in the quoted options string.

usebackq: Duplicates the awkward **CMD.EXE** syntax. A back quoted string is executed as a command; a single quoted string is a literal string; and double quotes quote filenames in the file set. We don't recommend **usebackq** for batch files written for **TCC**, as **TCC** has much more elegant ways of doing the same things.

You can also use FOR /F to parse a single string instead of each line of a file by using the string, in quotes, as **set**. For example, this command will assign variable **A** to the string **this**, **B** to **is**, etc., then display **this**:

```
for /f "tokens=1,2,3,4" %a in ("this is a test") echo %a
```

"Counted" FOR Loop

The "counted FOR" loop is included for compatibility with *CMD.EXE*. In most cases, you will find the DO 210 command more useful for performing counted loops.

In a counted FOR command, the **set** is made up of numeric values instead of text or file names. To begin a counted FOR command, you must use the /L 240 option and then include three values, separated by commas, in **set**. These are the **start**, **step**, and **end** values. During the first iteration of the FOR loop, the variable is set equal to the **start** value. Before each iteration, the variable is increased by the **step** value. The loop ends when the variable exceeds the **end** value. This example will print the numbers from 1 to 10:

```
for /1 %val in (1,1,10) echo %val
```

This example will print the odd numbers from 1 to 10 (1, 3, 5, 7, and 9):

```
for /1 %val in (1,2,10) echo %val
```

The **step** value can be negative. If it is, the loop will end when the variable is less than the **end** value.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

WARNING! You must not have white space between **start** and the subsequent comma, nor between **step** and its subsequent comma. White space after the comma is accepted.

Directory Recursion

By default, FOR works only with files in the current directory or a specified directory. Option switch $\frac{R}{240}$ specifies that the search should recursively process subdirectories. If you specify a directory name immediately after $\frac{R}{240}$, FOR will start in that directory and then search each of its subdirectories. If no directory is specified after the R, the search starts in the current default directory. If you do specify a directory, and its name includes any special characters, it must be enclosed in double quotes. For example, it must be quoted if it is specified with the aid of an environment variable, e.g., **%windir\command**.

There are two differences in the invocation of *command* caused by directory recursion:

- The loop control variable contains the full name of the matching file
- command is executed with the default directory set to the directory in which the file was found

This example processes all .TXT files in the current directory and its subdirectories:

```
for /r %x in (*.txt) ...
```

This example works with all of the .BAK files on drive D:

```
for /r d:\ %x in (*.bak) ...
```

Output Redirection

The default output redirection (i.e., **for ... > filename**) creates a new output file in each iteration. If **filename** does not include an absolute file path, it will be created relative to the then current default directory. If you use directory recursion, this path will change for each directory processed. The simplest way to force a single target file is to enclose the whole command in parentheses, e.g.,:

```
(for %x in (set) command) > filename
```

Other Notes

- You can use either % or %% in front of the variable name (var) in the command. Either form will work, whether the FOR command is typed from the command line or is part of an alias or batch file. (CMD.EXE which requires a single % if FOR is used at the command line, but requires %% if FOR is used in a batch file.) Note that you must have at least one % sign present.
- The variable name can be up to 80 characters long.
- If the FOR command is an alias, e.g., alias for=*for /h, range specifications will be ignored.
- The word DO is unnecessary but accepted. Do not confuse it with the completely unrelated DO command.
- If the name of the FOR variable *var* is a single character, for compatibility with *CMD.EXE*, it is created in the environment in a special way that does not overwrite an existing environment variable with the same name. Wherever *command* contains the % sign immediately followed by the character which is the name of the FOR variable, it is replaced by its value, regardless of any characters following it. For example, the following command tries to add *a:* and *b:* to the end of PATH (368), but will not work as intended:

```
for %p in (a: b:) path %path;%p
path
b:ath;b:
```

The **%p** in **%path** was interpreted as the FOR variable **%p** followed by the text **ath**, not what was intended. To get around this, use a different letter or a longer name for the FOR variable, or use square brackets around the variable name, as shown in the examples below, any one of which accomplishes the original goal:

```
for %p in (a: b:) path %[path];%p
for %x in (a: b:) path %path;%x
for %px in (a: b:) path %path;%px
```

• If the name of the FOR variable contains more than one character, it is created in the environment, and erased when FOR is completed, whether or not a variable by that name existed before the FOR. It cannot be modified with the <u>SET [319]</u>, <u>ESET [222]</u>, or <u>UNSET [357]</u> commands. If you already had a variable with that name, it will no longer be accessible. For example, a command that begins

```
for %path in ...
```

will write over your current PATH sets setting, then erase the PATH sets variable completely when FOR is done.

- Command may also use the FOR variable with the special syntax of CMD.EXE described in Special syntax for CMD.EXE compatibility [132].
- The following example uses FOR with variable functions to delete the .BAK files for which a corresponding .TXT file exists in the current directory (this should be entered on one line):

```
for %file in (*.txt) del %@name[%file].bak
```

The above command may not work properly on an LFN drive, because the returned *FILE* variable might contain white space. To correct this problem, you need two sets of quotes, one for DEL 190 and one for %@NAME 451:

```
for %file in (*.txt) del "%@name["%file"].bak"
```

• You can use <u>command grouping list</u> to execute multiple commands for each element in **set**. For example, the following command copies each .*WKQ* file in the current directory to the *D:\WKSAVE* directory, then changes the extension of each file in the current directory to .**SAV**:

- In a batch file you can use GOSUB [247] to execute a subroutine for every element in **set**. Within the subroutine, the FOR variable can be used just like environment variable. This is a convenient way to execute a complex sequence of commands for every element in **set** without CALL [175] ing another batch file.
- One unusual use of FOR is to execute a collection of batch files or other commands with the

same parameter. For example, you might want to have three batch files all operate on the same data file. The FOR command could look like this:

```
for %cmd in (filetest fileform fileprnt) %cmd datafile
```

This line will expand to three separate commands:

```
filetest datafile
fileform datafile
fileprnt datafile
```

• FOR statements can be nested.

LEAVEFOR

The special keyword LEAVEFOR can be used inside a FOR command group. LEAVEFOR terminates the current FOR processing and continues with the line following the FOR command, in a manner similar to that of the LEAVE keyword in a DO 210 command.

```
for %i in (*) (
    ...
    if "%i" == "xyz.abc" leavefor
    ...
)
```

Options:

Process only those files that have the specified attribute(s). /A: will be used only when processing wildcard file names in set. It will be ignored for filenames without wildcards or other items in set. See Attribute Switches for information on the attributes which can follow /A:.

For example, to process only those files with the archive attribute set:

```
for /a:a %f in (*) echo %f needs a backup!
```

Default: /A:-D-H-S, i.e. include only *files* without the *hidden* and *system* attributes.

- /D Only return subdirectories, excluding "." and "..".
- Return one or more words or tokens from each line of each file in **set**. The **/F** option can be followed by one or more options in a quoted string which control how the parsing is performed. See Parsing Text From Files 236.
- /H Suppresses the assignment of the "." and ".." directories to the FOR variable when directories are explicitly included using the /A: 240 option.

/I"text" Select filenames by matching text in their descriptions. See Description Ranges 86.

- Interpret the three values in **set** as the **start**, **step**, and **end** values of a counted loop. See Counted FOR Loops [237]
- /R [path] Look in the current directory and all of its subdirectories for files in set. If the /R is followed by a directory name, look for files in that directory and all of its subdirectories. Warning: if the directory name includes special characters, including "%" to indicate an environment variable, it must be enclosed in double quotes (").

/T"text" Specify the delimiters to be used when parsing a string set.

3.13.50 FREE

Purpose: Display the total disk space, total bytes used, and total bytes free on the specified (or

default) drive(s).

Format: FREE [drive: ...]

drive One or more drives to include in the report.

See also: MEMORY 272.

Usage:

A colon [:] is required after each drive letter. This example displays the status of drives A and C:

```
free a: c:
```

If the volume serial number is available, it will appear after the drive label or name.

FREE supports OpenAFS 103 names.

3.13.51 FTYPE

Purpose: Modify or display the command used to open a file of a type specified in the Windows

registry.

Format: FTYPE [/P /R[filename] | filetype[=[command]]

filename One or more input files to read file type definitions from.

filetype A file type stored in the Windows registry.

command The command to be executed when a file of the specified type is opened.

/P(ause) 242 /R(ead from file) 242

See also: ASSOC 162, and Executable Extensions 91.

Usage

FTYPE allows you to display or update the command used to open a file of a specified type stored in the Windows registry.

FTYPE modifies the behavior of Windows file associations stored under the registry handle HKEY_CLASSES_ROOT, and discussed in more detail under Windows File Associations are not familiar with file associations be sure to read about them before using FTYPE.

The entry modified by FTYPE is the Shell\Open\Command entry for the specified file type, which defines the application to execute when a file of that type is opened. The open action is generally invoked by selecting **Open** on the popup menu for a file from the Windows Explorer. Note that opening a file and double-clicking its icon (or selecting the icon and pressing Enter) may not be the same thing — double-clicking or pressing Enter invokes the default action for the file type, which may or may not be **Open**.

If you invoke FTYPE with no parameters, it will display the current file types and associated shell open commands. Use the **/P** switch to pause the display at the end of each page. If you include a **filetype**, with no equal sign or **command**, FTYPE will display the current command for that file type.

If you include the equal sign and *command*, FTYPE will create or update the shell open command for the specified file type. The *command* generally includes an application name, including full path, plus parameters. The specific syntax required depends on the internal operation of both Windows and the application involved, and is beyond the scope of this help file. You can learn about typical syntax by reviewing appropriate Windows and application documentation, and / or by checking through the current contents of your registry. If the value contains the percent mark character %, the value stored will be type REG_EXPAND_SZ, otherwise it will be type REG_SZ.

To remove the shell open command for a file type, use a command like FTYPE **filetype=**, with no **command** parameter. This will not delete the shell open command entry from the registry; it simply sets the command to an empty string.

FTYPE should be used with caution, and only after backing up the registry. Improper changes to file associations can prevent applications and / or the operating system from working properly.

Options

Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102.

This option loads a list of file types and associated shell open commands. If no filename is specified and the input is redirected, FTYPE will read from stdin [535]. The format of the file is the same as that of the FTYPE display.

You can insert comments in the file by prefixing the line with a colon (:).

3.13.52 FUNCTION

Purpose: Create, modify or display user-defined variable functions

Format: Display mode:

FUNCTION [/G /L /P] [wildname]

Direct definition mode:

FUNCTION name[=]definition

Definition file mode:

FUNCTION /R [file...]

file One or more input files to read function definitions from.

wildname Name of function whose definition is to be displayed (may contain * and ?

wildcards)

name The name of the function you want to define.

definition The value or definition of what the function should return.

 $\frac{|G(lobal)|^{24\delta}}{|L(ocal)|^{24\delta}}$ $\frac{|P(ause)|^{24\delta}}{|R(ead file)|^{24\delta}}$

See also: UNFUNCTION 356 and ESET 222.

Usage:

Overview 243

Displaying Functions 243

Defining Functions 243

- ▶ Deleting Functions 244
- Local and Global Functions 244
- Saving and Reloading Your Functions 244
- Warnings 245

Overview

FUNCTION allows you to create or display user-defined variable functions that can be used anywhere Variable Functions are powerful alternatives to subroutines 247

Displaying Functions

If you invoke the FUNCTION command with no parameters, it will display the current function list:

```
function
```

If you include a *wildname*, which may include wildcards (* or ?), with no equal sign and no *definition*, FUNCTION will display the current values, if any, of all functions matching *wildname*, .e.g.:

```
function *dx*
```

will display all functions which contain **dx** in their name.

You can use the /P 245 option to control display scrolling when displaying functions.

Defining Functions

If you include the equal sign and **definition**, FUNCTION will create or update the function referred to by **name**. Any previous **definition** associated with **name** is discarded. Instead of the = sign, you may use one or more spaces or tab characters to separate **name** and **definition**.

Once a function is defined, the definition may be edited using ESET [222] /F.

A function can optionally use references to parameters numbered from %0 to %511 which will be replaced with the matching parameter value when the function is called. %0 refers to the function name, %1 to the first parameter, etc. For example, the function

```
function leftmost=`%@left[1,%1]`
```

will return the leftmost character in its parameter, e.g. %@leftmost[xyz] will return x.

The parameter **%n\$** has a special meaning. **TCC** interprets it to mean "the entire command line, from parameter **n** to the end." If **n** is not specified, it has a default value of **1**, so **%\$** means "the entire command line after the alias name."

The parameter %-n\$ means "the command line from parameter 1 to *n* - 1".

The special variable reference **%#** expands to the number of parameters passed to the function.

A function definition need not reference any parameters at all. For example:

```
function tomorrow=`%@makedate[%@inc[%@date[%_date]]]`
```

could be simply invoked as %@tomorrow[].

To use the function **name** you invoke is as **@name[parameters]**, where you must specify enough parameters to assign a value to the highest numbered parameter **referenced** in the function definition. It may have more parameters, which will be silently ignored.

The Colors, Color Names and Codes [518] topic shows a simple example of the use of a function in a batch file.

Deleting Functions

The normal method is to use the <u>UNFUNCTION</u> (356) command. However, it is also possible to delete a function by redefining it without a *definition*, e.g., the command

```
function fs=
```

deletes the function fs.

Local and Global Functions

Functions can be stored in either a local or global list.

With a local function list, any changes made to the functions will only affect the current copy of *TCC*. They will not be visible in other shells or other sessions.

With a global function list, all copies of *TCC* will share the same function list, and any changes made to the functions in one copy will affect all other copies. This is the default in *TCC*.

You can control the type of function list with the <u>Local Functions</u> 47 configuration option, with the /L and /LF options of the START 331 command, and with the /L and /LF startup options 19.

There is no fixed rule for determining whether to use a local or global function list. Depending on your work style, you may find it most convenient to use one type, or a mixture of types in different sessions or shells. We recommend that you start with the default approach, then modify it if you find a situation where the default is not convenient.

Whenever you start a second copy of *TCC* which uses a local function list, it inherits a copy of the functions from the previous shell. However, any changes to the functions made in the secondary shell will affect only that shell. If you want changes made in a secondary shell to affect the previous shell, use a global function list in both shells.

Saving and Reloading Your Functions

You can save your functions to a file (e.g., FUNCTIONS.LST) this way:

```
function > function.lst
```

You can then reload all the function definitions in the file the next time you start up with the command:

```
function /r function.lst
```

This is much faster than defining each function individually in a batch file. If you keep your function definitions in a separate file which you load when *TCC* starts, you can edit them with a text editor, reload the edited file with FUNCTION /R, and know that the same function list will be loaded the next time you start *TCC*.

When you define functions in a file that will be processed by the FUNCTION /R command, you do not need back quotes around definition, even if back quotes would normally be required when defining the same function at the command line or in a batch file.

Warnings

When you define a function in the command line (i.e., without using the /R 245) option), variables and functions not protected by back quotes or doubled % signs are immediately evaluated, and the result becomes part of the function definition.

Syntax errors in a function definition are not detected until it is used.

Options:

- **/G** Switch from a local to a global function list.
- **/L** Switch from a global to a local function list.
- /P Wait for a key to be pressed after each screen page before continuing the display.
- This option loads a list of functions from a file. If no filename is specified and input is redirected, /R will read from stdin stdin from the file is the same as that of the FUNCTION display:

name=definition

where *name* is the name of the function and *definition* specifies how to determine its value. You may use the equal sign = or whitespace to separate *name* and *definition*. Back-quotes are not required.

You can add comments to the file by starting each comment line with a colon :.

You can load multiple files with one FUNCTION /R command by placing the names on the command line, separated by spaces:

```
function /r func1.lst func2.lst
```

Each definition in a FUNCTION /R file can be up to 8,191 characters long. The definitions can span multiple lines in the file if each line, except the last, is terminated with an Escape Character 1241.

If there is no filename parameter and input is redirected, FUNCTION /R will read from stdin [535].

3.13.53 GLOBAL

Purpose: Execute a command in the current directory and its subdirectories.

Format: GLOBAL [/H /I /J /N /P /Q /Sn] command

command The command to execute, including parameters and switches.

/H(idden directories) 246 /P(rompt) 247 /Q(uiet) 247 /Q(uiet) 247 /Q(uiet) 247 /Q(uiet) 247 /N(o junctions) 246 /N(o junctions

Usage:

GLOBAL performs *command* first in the current directory. Then it makes every subdirectory under the current directory the current working directory in turn, and performs *command* in that directory. *Command* can be an internal command, an alias, an external command, or a batch file. When *command* is executed, it may be necessary to utilize one of the variable functions which convert a relative path to an absolute one, e.g., <u>@truename[][464]</u>, <u>@full[][437]</u>, etc to make sure that files of the same name in different directories are correctly handled.

The example below copies the files in every directory on drive **A** to the directory *C:\TEMP*:

```
[a:\] global copy * c:\temp
```

If a specific filename is found in more than one directory on **A**:, assuming <u>COPY 182</u> is the default internal command, the one found last will be left in C:\TEMP. Which one of multiple, identically named files is found last is unpredictable!

If you use the /P 24 option, GLOBAL will prompt for each subdirectory before performing *command*. You can use this option if you want to perform *command* in most, but not all subdirectories of the current directory.

You can use <u>command grouping list</u> to execute multiple *commands* in each subdirectory. For example, the following command copies each *.TXT* file in the current directory and all of its subdirectories to drive **D**. It then changes the extension of each of the copied files to *.SAV*:

```
global (copy *.txt d: & ren *.txt *.sav)
```

Output Redirection

The default output redirection (i.e., **global command** > **filename**) creates a new output file named **filename** as each directory visited. If **filename** does not include an absolute file path, these files will be created relative to the currently visited directory. If **filename** does include an absolute file path, that file will be overwritten as each directory is visited, and only the data from the last visited directory will survive.

The simplest way to force a single target file is to enclose the whole command line in parentheses, e.g.,:

```
(global command) > filename
```

Options:

- **/H** Forces GLOBAL to look for hidden directories. If you don't use this switch, hidden directories and their subdirectories are ignored without error indication.
- If this option is not specified, GLOBAL will terminate if *command* returns a non-zero exit code. Use /I if you want *command* to continue in additional subdirectories even if it returns an error in one subdirectory. GLOBAL will normally halt execution if *TCC* receives a **Ctrl-C** or **Ctrl-Break** even if you use /I.

Without this option, if GLOBAL is unable to change to a directory (for example, if user does not have access rights), GLOBAL will stop with an error message. With this option set, GLOBAL will ignore that directory, and all of its subdirectories, and continue in the next accessible directory.

- /J Forces GLOBAL to only recurse through Junctions, not subdirectories.
- /N Forces GLOBAL to ignore Junctions and only recurse through subdirectories.

/P Forces GLOBAL to prompt with each directory name before it performs *command* in that directory. Your options at the prompt are explained in detail under Page and File Prompts

/Q Do not display the directory names as each directory is processed.

/S GLOBAL will limit the subdirectory recursion to the number specified. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only go to the "a", "b", and "c" directories.

3.13.54 GOSUB

Purpose: Execute a subroutine in the current batch file.

Format: GOSUB ["filename"] label [variables]

filename The file containing the subroutine

label The batch file label at the beginning of the subroutine.

variables Optional GOSUB variables.

See also: CALL 1751, GOTO 2481, and RETURN 3071.

Usage:

GOSUB can only be used in batch files.

TCC allows subroutines in batch files. A subroutine must start with a **label** (a colon [:] followed by a label name) which appears on a line by itself. Case differences are ignored when matching labels. The subroutine must end with a RETURN statement.

The subroutine is invoked with a GOSUB command from another part of the batch file. After the RETURN, processing will continue with the command following the GOSUB command. For example, the following batch file fragment calls a subroutine which displays the directory and returns:

```
echo Calling a subroutine
gosub subr1
echo Returned from the subroutine
quit
:subr1
dir /a/w
return
```

GOSUB begins its search for the *label* on the line of the batch file immediately after the GOSUB command. If the *label* is not found between the current position and the end of the file, GOSUB will restart the search at the beginning of the file. If the label still is not found, the batch file is terminated with the error message "Label not found".

You can define GOSUB variables by placing them after the label name on the GOSUB line. For example:

```
Gosub Sub1 abc 15 "Hello World"
```

The variable names are defined on the label line. For example:

```
:Sub1 [str n world]
```

defines three variables - **%str** (set to "abc"), **%n** (set to 15), and **%world** (set to "Hello World"). Note that the square brackets are required on the label line. GOSUB variables are only defined for the duration of the subroutine. They are not inherited by nested GOSUBs, and are destroyed by the

RETURN 307 call.

If you define GOSUB variables on the label but do not supply them on the GOSUB line, they will be set to an empty string.

GOSUB calls with variables are limited to a maximum of 22 levels deep. There is no limit on normal GOSUB calls.

GOSUB variables are placed in the environment in a special form for the duration of the subroutine, and will "mask" any environment variables of the same name that existed before the subroutine was called. GOSUB variables can be referenced like normal environment variables, but are not stored in the same way, cannot be modified with the SET 319, ESET 2221, or UNSET 357 commands, and cannot be used with the DEFINED test of IF 253, IFF 254, or @IF 439.

You cannot use <u>SET</u> [319] within a subroutine to change the value of a GOSUB variable. If you attempt to do so, the SET command will set the standard environment variable of the same name, not the GOSUB variable, but this value will be "masked" by the GOSUB variable and will remain inaccessible until the subroutine ends.

You can call a subroutine in another file by specifying *filename* (the name must be enclosed in double quotes). This allows you to create libraries of subroutines, without having to duplicate them in each batch file. For example:

```
gosub "c:\library\batlib.btm" Evaluate [%1 %2 %3]
```

GOSUB saves the IFF and DO states, so IFF and DO statements inside a subroutine won't interfere with statements in the part of the batch file from which the subroutine was called. If the subroutine has executed a SETLOCAL without a matching ENDLOCAL, an ENDLOCAL will be executed before returning to the calling batch file.

You cannot RETURN 307 from a GOSUB while inside a DO 210 loop.

If **TCC** reaches the end of the batch file while inside a subroutine, it will automatically return to the command after the GOSUB, just as if an explicit <u>RETURN</u> command had been included as the last line of the file.

Subroutines can be nested.

See also: user-defined functions 242.

3.13.55 GOTO

Purpose: Branch to a specified line inside the current batch file.

Format: GOTO [/I] label

label The batch file label to branch to.

/I(FF and DO continue) 249

See also: GOSUB 247, CALL 1751.

Usage:

GOTO can only be used in batch files.

After a GOTO command in a batch file, the next line to be executed will be the one immediately following the *label*. The *label* must begin with a colon [:] and appear on a line by itself. The colon is

required on the line where the *label* is defined, but is not required in the GOTO command itself. Case differences are ignored when matching labels.

This batch file fragment checks for the existence of the file *CONFIG.SYS*. If the file exists, the batch file jumps to C_EXISTS and copies all the files from the current directory to the root directory on A:. Otherwise, it prints an error message and exits.

```
if exist config.sys goto C_EXISTS
echo CONFIG.SYS doesn't exist - quitting.
quit
:C_EXISTS
copy * a:\
```

GOTO begins its search for the *label* on the line of the batch file immediately after the GOTO command. If the *label* is not found between that position and the end of the file, GOTO will restart the search at the beginning of the file. If the label is still not found, the batch file is terminated with the error message "Label not found."

To avoid errors in the processing of nested statements and loops, GOTO cancels all active IFF 2541 statements and DO 2101 / ENDDO loops unless you use /I. This means that a normal GOTO (without /I) may not branch to any label that is between an IFF and the corresponding ENDIFF or between a DO and the corresponding ENDDO.

For compatibility with CMD.EXE, the command

```
GOTO : EOF
```

will end processing of the current batch file if the label :EOF does not exist. However, this is less efficient than using the QUIT 30th or CANCEL 176 command to end a batch file.

Option:

Prevents GOTO from canceling IFF statements and DO loops. Use this option only if you are absolutely certain that your GOTO command is branching entirely within any current IFF statement **and** any active DO / ENDDO block. Using // under any other conditions will cause an error later in your batch file.

You cannot branch into another IFF statement, another DO loop, or a different IFF or DO nesting level, whether you use the /I option or not. If you do, you will eventually receive an "unknown command" error (or execution of the UNKNOWN_CMD alias) on a subsequent ENDDO, ELSE, ELSEIFF, or ENDIFF statement.

3.13.56 HEAD

Purpose: Display the beginning of the specified file(s).

Format: HEAD [/A:[[-][+]rhsadecijopt] /Cn /I"text" /Nn /P /Q /V] [@file] file...

file The file or list of files that you want to display.

@file A text file containing the names of the files to display, one per line (see @file

lists 90 for details).

```
/A: (Attribute select) 250 /P(ause) 251 /C (number of bytes) 250 /Q(uiet) 251 /V(erbose) 251 /N(umber of lines) 250 /V(erbose) 251
```

See also: LIST 264, TAIL 339, and TYPE 354).

File Selection

Supports <u>attribute switches</u> (86), extended <u>wildcards</u> (77), <u>ranges</u> (80), <u>multiple file names</u> (87), and <u>include</u> lists (88).

Internet: Can be used with FTP/HTTP Servers 3, e.g.

head "http://jpsoft.com/notfound.htm"

Usage:

The HEAD command displays the first part of a file or files. It is normally only useful for displaying ASCII text files (i.e. alphanumeric characters arranged in lines separated by CR/LF). Executable files (.COM and .EXE) and many data files may be unreadable when displayed with HEAD because they include non-alphanumeric characters or unusual line separators.

You can press Ctrl-S to pause HEAD's display and then any key to continue.

The following example displays the first 15 lines of the files MEMO1 and MEMO2:

```
head /n15 memo1 memo2
```

To display text from the clipboard use **CLIP**: as the file name. CLIP: will not return any data if the clipboard does not contain text. See <u>Highlighting and Copying Text</u> or additional information on CLIP:.

FTP Usage

HEAD can also display files on FTP/HTTP Servers 3. For example:

```
head ftp://jpsoft.com/index
```

NTFS File Streams

HEAD supports file streams on NTFS drives. You can type an individual stream by specifying the stream name, for example:

```
head streamfile:s1
```

Options:

- /A: Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Do not use /A: with @file lists. See @file lists 90 for details.
- **/C**: Display the specified number of bytes. **/C** accepts a **b**, **k**, or **m** modifiers at the end of the number. **b** is the number of 512-byte blocks, **k** is the number of kilobytes, and **m** the number of megabytes.
- /I"text" Select files by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[]*", or all filenames that do not have a description with /I"[]". Do not use /I with @file lists. See @file lists 90 for details.
- /N n Display *n* lines. The default is 10.

/P Pause and prompt after displaying each page.

/Q Do not display a header for each file. This is the default behavior, but an explicit /Q may

be needed to override an alias that forces /V.

/V Display a header for each file.

3.13.57 HELP

Purpose: Display help for internal commands.

Format: HELP [topic]

topic A help topic (internal command, variable or function).

See also: The Online Help System 477).

Usage:

Online help is available for all of *TCC*'s internal commands, variables, and other features.

The **TCC** help system (tcmd.chm) uses Microsoft's HTML Help Viewer (*HH.EXE*) included in all their current Windows bundles.

If you type the command **HELP** by itself (or press <u>F1</u> ³⁴ when the command line is empty), an introductory page (**Overview**) is displayed. If you type HELP plus a topic name, that topic is displayed. For example:

```
help copy
```

displays information about the COPY command and its options. All internal commands, internal variables, variable functions, and key mapping directives have their own topic.

You can also invoke help for the word immediately above (or immediately to the left of) the cursor by pressing Ctrl-F1 (this can be useful when you need the syntax for a variable function).

3.13.58 **HISTORY**

Purpose: Display or modify the history list.

Format: HISTORY [/A command /F /G /L /N /P /R filename]

command A command to be added to the history list.

filename The name of a file containing entries to be added to the history list.

/A(dd) | 252 | /N(o duplicates) | 253 | /F(ree) | 252 | /P(ause) | 253 | /R(ead) | 253 | /L(ocal) | 253 | /R(ead) | 253 | /R(e

See also: DIRHISTORY 208, History Exclude 368 and LOG 269.

Usage:

TCC keeps a list of the commands you have entered on the command line. See Command History

and Recall 106 for information on command recall, which allows you to use the history list to repeat or edit commands you have previously executed.

The HISTORY command lets you view and manipulate the command history list directly. If no parameters are entered, HISTORY will display the current command history list.

With the options explained below, you can clear the list, add new commands to the list without executing them, save the list in a file, or read a new list from a file.

The number of commands saved in the history list depends on the length of each command line. The history list size can be specified at startup from 8192 to 131071 characters (see the Command History Buffer Size 50) configuration option). The default size is 8192 characters.

Your history list can be stored either locally (a separate history list for each copy of **TCC**) or globally (all copies of **TCC** share the same list). For full details see local and global history 1081.

You can use the HISTORY command as an aid in writing batch files by redirecting the HISTORY output to a file and then editing the file appropriately. However, it is easier to use the LOG /H command for this purpose.

You can disable the history list or specify a minimum command line length to save with the Minimum Length on Configuration option. You can prevent any command line from being saved in the history by beginning it with an "at" sign (@).

You can exclude specific commands from the History List with the HistoryExclude 368 variable.

You can control whether duplicate entries will be saved in the history list with the <u>Duplicates of Configuration</u> option.

You can save the history list by redirecting the output of HISTORY to a file. This example saves the command history to a file called *HISTFILE* and reads it back again immediately. If you leave out the HISTORY /F command on the second line, the contents of the file will be appended to the current history list instead of replacing it:

```
history > histfile
history /f
history /r histfile
```

If you need to save your command history at the end of each day's work, you might use the first of these commands in your *TCSTART.BTM*:

```
if exist c:\histfile history /r c:\histfile
history > c:\histfile
```

This restores the previous history list if it exists, and saves the history when *TCC* exits.

TCC can also load and save the history list automatically if you use the <u>History File</u> on configuration option.

Options:

- /A Add a command to the history list. This performs the same function as the Ctrl-K key at the command line.
- /F Erase all entries in the command history list.

/G Switch from a local to a global history list.

/L Switch from a global to a local history list.

/N Removes duplicate entries (oldest first) from the history list.

Wait for a key after displaying each page of the list. Your options at the prompt are explained in detail under Prompts 102.

/R Read the command history from the specified file and append it to the history list currently held in memory.

If you are creating a HISTORY /R file by hand, and need to create an entry that spans multiple lines in the file, you can do so by terminating each line, except the last, with an escape character [124]. However, you cannot use this method to exceed the command line length limit.

3.13.59 IF

Purpose: Execute a single command if a condition is true.

Format: IF [/I] condition command

IF [/I] condition (command1) ELSE (command2)

condition A conditional expression 109

command The command to execute if condition is TRUE.
 command1 The command to execute if condition is TRUE.
 command2 The command to execute if condition is FALSE.

/I(gnore case) 254

See also: Conditional expressions 109, IFF 254, @IF 439.

Usage:

IF is most often used only aliases and batch files. It is always followed by a **condition** (see <u>Conditional expressions 109</u>), and then a **command**. First <u>condition 109</u> is evaluated, and if it is TRUE, **command** is executed. Otherwise, **command** is ignored.

If the condition is FALSE, **IF** returns a non-zero result, so it can be evaluated by one of the conditional expression operators (**II** or &&).

The IF ... ELSE ... syntax of CMD.EXE is also supported:

IF [/I] condition (command1) ELSE (command2)

The commands to be executed must be enclosed in parentheses (as in a <u>command group [12]</u>). If **condition** is TRUE, **command1** is executed, if FALSE, **command2** is executed. **Note:** this syntax is much less powerful than the IFF [254] command, which is recommended.

When an IF test fails, the remainder of the command is discarded. Whether *TCC* continues with the next command on the line, or discards the rest of the line and goes to the next line is dependent upon the <u>Duplicate CMD.EXE Bugs [47]</u> configuration option. CMD.EXE will discard all remaining commands on the line when an IF test fails, including those after a command separator or pipe character. If you do not want to reproduce CMD.EXE's behavior of an IF affecting all commands on a line, set **DuplicateBugs** to **No** in the .INI file.

For example, if <u>Duplicate CMD.EXE Bugs 4</u> is enabled (the default), the following command will display nothing, because the second ECHO command is discarded along with the first when the condition fails. If <u>Duplicate CMD.EXE Bugs 4</u> is disabled, it will display "hello":

[c:\] if 1 == 2 echo Wrong! & echo hello

Option:

/I

This option is included only for compatibility with CMD.EXE. It has no effect in *TCC*, since all string comparisons are case-insensitive unless you specify a case-sensitive test (EQC).

3.13.60 IFF

Purpose: Perform one of several alternate sets of commands based on the values of conditional

expressions.

Format: IFF condition1 THEN

commandset1

[ELSEIFF condition2 THEN

commandset2]

IELSE

commandset3]

ENDIFF

condition1,2,3 Conditional expressions 109

commandset1 One or more commands to execute if condition1 is TRUEcommandset2 One or more commands to execute if condition1 is FALSE, but

condition2 is TRUE.

commandset3 One or more commands to execute if both condition1 and

condition2 are FALSE.

See also: IF 253 and @IF 439.

Usage:

IFF is similar to IF 253, but it can perform one **commandset** when a <u>conditional expression 109</u> is true and a different **commandset** when it is false. Repeated use of the optional ELSEIFF clause permits IFF to sequentially evaluate multiple, independent <u>conditional expression 109</u>, or, if none are true, the **commandset** associated with the first TRUE <u>conditional expression 109</u>, or, if none are true, the **commandset** associated with the optional ELSE clause. After execution of any one of the **commandsets** the command after the ENDIFF clause will be executed.

You must start a new line or include a command separator 1201:

- after each THEN
- before each ELSEIFF
- both before and after the ELSE.

The individual commands in each *commandset* may be *separate lines* of a batch file, or they may be separated by <u>command separators</u> 1201, in any combination. A *commandset* may also be empty, The individual commands in a *commandset* may include any internal command, alias, external command, or batch file.

IFF statements can be **nested**, i.e., a **commandset** may include another IFF / ENDIFF group. You must make sure that each individual command / **commandset** is syntactically correct. If an "inner" IFF / ENDIFF group is in error, it may not be detected until after the "outer" ENDIFF has been executed.

Notes

Be sure to read the cautionary notes about GOTO 248 and IFF under the GOTO 248 command before using a GOTO 248 inside an IFF statement.

If you pipe at data to an IFF, the data will be passed to the command(s) following the IFF, not to IFF itself.

Example

The alias in this example checks to see if the parameter is a subdirectory. If so, the alias deletes the subdirectory's files and removes it (enter this on one line):

```
alias prune `iff isdir %1 then & del /s /x /z %1 & else & echo %1 is not a directory! & endiff`
```

3.13.61 IFTP

Purpose: Open or close an FTP/FTPS session

Format: IFTP [/S command /C /N /Pn /Q /V] ["ftp://[user[:password]@]server[/path]"]

user The user name to login to the FTP sitepassword The password to login to the FTP site.

server The FTP server name.

path The default directory on the server for this session.

/C(lose) | 257 | /Q(uiet) | 257 | /S(end) | 257 | /V(erbose) | 257 | /

Usage:

Most file processing commands and functions in *TCC* can access files on FTP servers in the same manner as files on local hard drives and a local network. Normally, each time you use the FTP feature of one of these commands or functions, it starts an FTP session, performs its task, and then closes the FTP session.

IFTP starts an FTP session which remains open until you close it or it is closed by the remote server. There are several advantages to using IFTP: the FTP connection remains open so commands execute more quickly, the syntax for accessing files on the server is shorter, and you can specify a default directory on the server for file operations.

For example, to open an FTP connection using IFTP:

```
iftp ftp://user:pwd@jpsoft.com/dir1
```

For an FTPS connection, use something like:

```
iftp ftps://user:pwd@jpsoft.com/dir1
```

This command tells IFTP to open an FTP/FTPS session with the server *jpsoft.com*, send *user* as the login username and *password* as the login password, and to establish the directory */dir1* as the

default directory for this session. The user name and password are optional; if they are not used, IFTP will attempt to log in anonymously. The double quotes are required. If you specify a password of *, you will be prompted to enter the password (which will be appear on the screen as asterisks).

Note that in the example above *dir1* is a subdirectory of the FTP "root" directory – the home directory for the named FTP user. In most server configurations this is not the same as the FTP server's physical root directory.

Note: If you enter IFTP with no parameters while a connection is active, the current server name and directory will be displayed.

If you enter IFTP with only the /Q or /V switch, you change the amount of information displayed without disturbing the existing connection (if any).

Once you have established an FTP session with IFTP, you can refer to files on the server by using **ftp**: (or **ftps**:) but leaving out the user name, password, and URL of the server. On most servers, file and path names which begin **ftp**: are relative to the default directory, if any, that you specified when you opened the IFTP session; file and path names which begin **ftp**:// are relative to the root directory for the login name.

The difference can be seen in these four DIR (1981) commands, assuming the IFTP session started above:

```
1. dir "ftp:*.txt"
2. dir "ftp:dir2/*.txt"
3. dir "ftp:/*.txt"
4. dir "ftp:/dir2/*.txt"
```

The first command lists the .TXT files in the default session directory, **dir1**. The second command lists the .TXT files in /dir1/dir2 because it interprets the path dir2/*.txt to be relative to the default directory. The quotes could be omitted from example 1 because it contains no forward slash that could be mistaken as an option switch. The third and fourth commands above, because they include a / immediately following the **ftp:** designator, are relative to the root directory. Command 3 lists the .TXT files in the root directory and command 4 lists the files in the **dir2** subdirectory of the root directory.

Note: If an ftp file or path specification begins with a ~ (tilde), **TCC** will not attempt to build a full directory name but will instead pass the entire string to the remote server.

You can only have one IFTP connection open at a time within a **TCC** tab window. However, while you have an IFTP connection open, you can still use a complete FTP URL to perform an operation on a different server. For example, while the session above is open, you can use this command to display all files in the root directory of **ipsoft.com**:

```
dir "ftp://jpsoft.com/*"
```

An IFTP session remains open until you explicitly close it with this command:

```
iftp /c
```

Most FTP servers "time out" after a period of inactivity. *TCC* will attempt to detect if the connection has been closed by the server, and reconnect if you reference the IFTP session again. You should not assume that an IFTP connection will continue to function if you leave it open but unused for a significant period of time. You can determine if the connection is still active with the _iftp | 388 | and _iftps | 388 | variables.

IFTP and the other FTP features of *TCC* rely on the server's compliance with Internet FTP standards. If your server is not fully compliant, or does not operate in the manner that *TCC* expects, commands

may not work as you intend. We urge you to test each server you use with nondestructive commands like DIR 1981 before you try to copy or delete files, create or remove directories, etc.

Before you can use IFTP, you must establish the necessary connection to the Internet.

Options:

/C Use this switch, with no URL, to close an IFTP session (see the example above).

/N Pass both source and target names to the server "as is" without any attempt at expanding the paths. This option should be used with caution and only for "non standard" servers for which the default processing fails to build a suitable name.

/P /P0 disables passive mode; /P1 enables it

/Q Turn off the display of the conversation with the FTP server.

/S Allows you to send commands directly to an FTP server. The connection must have already been opened by a previous IFTP command.

N Display the dialog with the FTP server while opening the connection. This can be useful for debugging connection problems.

See FTP Servers 3 for additional information on formatting and usage of FTP and FTPS references.

3.13.62 INKEY

Purpose: Get a single keystroke from the user and store it in an environment variable.

Format: INKEY [/C /D /K"keys" /P /M /Wait /X] [prompt] %%varname

> prompt Optional text that is displayed as a prompt. The variable that will hold the user's keystroke. varname wait Time to wait for a keystroke, in seconds

/P 259 Password /C Clear buffer

258 /D Digits only Wait

258

valid keystrokes /X 259 no carriage return

258 /M Mouse buttons

See also: INPUT 2591.

Usage:

INKEY optionally displays a prompt, then it waits for a specified time (or indefinitely) for a keystroke, and places the keystroke into an environment variable. It is normally used in batch files and aliases to get a menu choice or other single-key input. Along with the INPUT 259 command, INKEY allows great flexibility in reading input from within a batch file or alias.

If prompt is included in an INKEY command, it is displayed while INKEY waits for input.

The following batch file fragment prompts for a character and stores it in the variable **NUM**:

```
inkey /D Enter a number from 1 to 9: %%num
```

INKEY reads standard input for the keystroke, so it will accept keystrokes from a redirected file or from KEYSTACK 262. You can supply a list of valid keystrokes with the /K 258 option.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

A standard keystroke is stored directly in the environment variable. An extended keystroke (for example, a function key or a and cursor key) is stored as a string, consisting of a leading @, followed by its scan code as a decimal number, e.g., the *F1* key is stored as @59. The **Enter** key is stored as an extended keystroke @28. See ASCII, Key Codes, and ANSI X3.64 Commands [510] for scan codes.

When the \underline{M}^{259} option enables recognition of mouse buttons, (and \underline{W}^{259} is not specified), the variable is set to a single character with one of the codes below:

button	code
left	240
middle	498
right	497

To test for a non-printing value returned by INKEY use the <u>@ASCII</u> function to get the numeric value of the key, or convert the expected value of the code to a code using <u>@CHAR</u> [41]. For example, to test for **Esc**, which has an <u>ASCII</u> [51] value of 27 or a left mouse button:

```
inkey Enter a key: %%key
if "%@ascii[%key]" == "27" echo Esc pressed
if %key EQ 240 echo Left mouse button clicked
```

If you press **Ctrl-C** or **Ctrl-Break** while INKEY is waiting for a key, execution of an alias will be terminated, and execution of a batch file will be suspended while you are asked whether to cancel the batch job. A batch file can handle **Ctrl-C** and **Ctrl-Break** with the ON BREAK [282] command.

INKEY works within the command line window. If you prefer to use a dialog for user input, see the MSGBOX 279 and QUERYBOX 300 commands.

Options:

- Clears the keyboard buffer before INKEY accepts keystrokes. If you use this option, INKEY will ignore any keystrokes which you type, either accidentally or intentionally, before it is ready to accept input.
- **/D** Only accept numbers from **0** to **9**.

/K"keys" Specifies the permissible keystrokes. The list of valid keystrokes should be enclosed in double quotes. For alphabetic keys the validity test is not case sensitive. You can specify extended keys by enclosing their names in square brackets (within the quotes), for example:

```
inkey /k"ab[Ctrl-F9]" Enter A, B, Ctrl-F9 %%var
```

See <u>Keys and Key Names</u> [515] for a complete listing of the key names you can use within the square brackets, and a description of the key name format.

If an invalid keystroke is entered, **TCC** will echo the keystroke if possible, beep, move the cursor back one character, and wait for another keystroke.

/M Enabled only if Windows' Quick Edit is disabled (alt-space -> Properties -> Options).

/P Prevents INKEY from echoing the character.

Time-out period, in seconds, to wait for a response. If no keystroke is entered by the end of the time-out period, INKEY returns with the variable unchanged. This allows you to continue the batch file if the user does not respond in a given period of time. You can specify /W0 to return immediately if there are no keys waiting in the keyboard buffer. If /W is specified, mouse buttons are ignored.

For example, the following batch file fragment waits up to 10 seconds for a character, then tests to see if a "y" was entered:

```
set netmon=N
inkey /K"YN" /w10 Network monitor (Y/N)? %%netmon
iff "%netmon" == "Y" then
  rem Commands to load the monitor program
endiff
```

/X Prevents INKEY from displaying a carriage return and line feed after the user's entry.

3.13.63 INPUT

Purpose: Get a string from the keyboard and save it in an environment variable.

Format: INPUT [/C /D /E /Ln /N /P /Wn /X] [prompt] %%varname

prompt Optional text that is displayed as a prompt.**varname** The variable that will hold the user's input.

 /C(lear buffer)
 260
 /N(o colors)
 260

 /D(igits only)
 260
 /P(assword)
 260

 /E(dit)
 260
 /W(ait)
 260

 /L(ength)
 260
 /X (no carriage return)
 260

See also: SET 319, INKEY 257, KEYSTACK 262, MSGBOX 279, and QUERYBOX 300).

Usage:

INPUT optionally displays a prompt, then waits for your entry and stores it in an environment variable. INPUT is normally used in batch files and aliases to get multi-character input (for single keystroke input, see INKEY [257]).

INPUT works within the command line window. If you prefer to us a dialog for user input, see the MSGBOX 279 and QUERYBOX 300 commands.

If **prompt** text is included in an INPUT command, it is displayed while INPUT waits for input. Standard command line editing keys may be used to edit the input string as it is entered. If you use the **/P** password option, INPUT will echo asterisks instead of the keys you type.

All characters entered up to, but not including, the carriage return are stored in the variable.

The following batch file fragment prompts for a string and stores it in the variable FNAME:

```
input Enter the file name: %%fname
```

INPUT reads standard input, so it will accept text from a redirected file or from the KEYSTACK 2621.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

If you press Ctrl-C or Ctrl-Break while INPUT is waiting for input, execution of an alias will be terminated, and execution of a batch file will be suspended while you are asked whether to cancel the batch job. A batch file can handle Ctrl-C and Ctrl-Break itself with the ON BREAK 282 command.

You can pipe 1001 text to INPUT, but it will set the variable in the "child" process used to handle the right hand side of the pipe. This variable will not be available in the original copy of *TCC* used to start the pipe.

Options:

- /C Discard any keystrokes pending in the keyboard buffer before INPUT begins accepting characters.
- **/D** Only accept numbers from 0 to 9.
- /E Allows you to edit an existing value. If there is no existing value for *varname*, INPUT proceeds as if /E had not been used, and allows you to enter a new value.
- **/Ln** Sets the maximum number of characters which INPUT will accept to **n**. If you attempt to enter more than this number of characters, INPUT will beep and prevent further input (you will still be able to edit the characters typed before the limit was reached).
- /N Disables the use of input colors defined in the Colors (49) configuration options, and forces INPUT to use the default display colors.
- /P Tells INPUT to echo asterisks, instead of the characters you type.
- Time-out period, in seconds, to wait for a response. If no keystroke is entered by the end of the time-out period, INPUT returns with the variable unchanged. This allows you to continue the batch file if the user does not respond in a given period of time. If you enter a key before the time-out period, INPUT will wait indefinitely for the remainder of the line. You can specify /W0 to return immediately if there are no keys waiting in the keyboard buffer.
- /X Prevents INPUT from adding a carriage return and line feed after the user's entry.

3.13.64 JABBER

Purpose: Send an IM via the JABBER network.

Format: JABBER [/S(erver) /U(ser) / P(assword)] /B target[@server] message

message The message to send

 $\frac{\text{/B(uddy)}}{\text{/P(assword)}}$ $\frac{\text{/S(erver)}}{\text{/U(sername)}}$ $\frac{\text{/S(erver)}}{\text{/U(sername)}}$

Usage:

If /S, /U, and/or /P are not specified, JABBER will use the default values defined in the .INI file (JabberServer, JabberUser, and JabberPassword).

JABBER is intended to send single short messages on an event (for example, when a large series of file transfers is completed), not as a general replacement for an interactive IM client.

Before using JABBER, you will need to create an account on a JABBER network server. See www.jabber.org for more information on the JABBER network and for open JABBER servers.

Options:

/B Address where the message will be sent

/P Logon password on the JABBER server

/S JABBER server to log onto

/U User logon name on the JABBER server

3.13.65 KEYBD

Purpose: Set the state of the keyboard toggles Caps Lock, Num Lock, and Scroll Lock.

Format: KEYBD [/Cn /Nn /Sn]

n can be either **0** to turn off the toggle or **1** to turn on the toggle.

/C(aps lock) 261 /S(croll lock) 261 /N(um lock) 261

Usage:

Most keyboards have 3 toggle keys, the Caps Lock, Num Lock, and Scroll Lock. KEYBD lets you turn any toggle key on or off. It is most useful in batch files and aliases if you want the keys set a particular way before collecting input from the user.

For example, to turn off the Num Lock and Caps Lock keys, you can use this command:

keybd /c0 /n0

If you use the KEYBD command with no switches, it will display the present state of the toggle keys.

The toggle key state is typically the same for all sessions, and changes made with KEYBD in one session will therefore affect all other sessions.

Options:

/C Turn the Caps Lock key on or off.

/N Turn the Num Lock key on or off.

/S Turn the Scroll Lock key on or off.

3.13.66 KEYS

Purpose: Enable, disable, or display the history list.

Format: KEYS [ON | OFF | LIST]

See also: HISTORY 251.

Usage

This command is provided for compatibility with KEYS command in CMD.EXE, which controls the history list in Windows. The same functions are available by setting the Command History Minimum Length of configuration option, and by using the HISTORY command. (CMD.EXE's KEYS command no longer has an effect, because command line editing is always enabled.)

The history list collects the commands you type for later recall, editing, and viewing. You can view the contents of the list through the history list window or by typing any of the following commands:

```
history
history /p
keys list
```

The first command displays the entire history list. The second displays the entire list and pauses at the end of each full screen. The third command produces the same output as the first, except that each line is numbered.

You can disable the collection and storage of commands in the history list by typing:

```
keys off
```

You can turn the history back on with the command:

```
keys on
```

If you issue the KEYS command without any parameters, *TCC* will show you the current state of KEYS.

3.13.67 KEYSTACK

Purpose: Feed keystrokes to a program or command automatically.

Format: KEYSTACK [/R filename] [!] [/Wx] ["abc"] [keyname[n]] ...

/Wx Delay in clock ticks before next insertion into the keystack.

"abc" Literal characters to be placed in the Keystack.

keyname Name of a key whose code is to be placed in the Keystack or its ASCII. Number of times to repeat the immediately preceding **named** key.

/R(ead file) 264 /W(ait) 264

Usage:

Operation

KEYSTACK takes a series of keystrokes and feeds them to a program or command as if they were typed at the keyboard. When the program has used all of the keystrokes in the keystack buffer, it will begin to read the keyboard for input, as it normally would.

KEYSTACK will send the keystrokes to the currently active window. If you want to send keystrokes to another program (rather than have them function with *TCC* itself), you must start the program or ACTIVATE its window so it can receive the keystrokes. You must do this before executing the KEYSTACK command.

KEYSTACK is most often used for programs started from batch files. In order for KEYSTACK to work in a batch file, you must start the program with the <u>START 33 h</u> command, then use the KEYSTACK command. If you start the program directly (without using <u>START 33 h</u>) the batch file will wait for the application to complete before continuing and running the KEYSTACK command, and the keystrokes

will not appear in the target program.

If you use KEYSTACK in an alias executed from the prompt, the considerations are essentially the same, but depend on whether or not the <u>Wait for External Apps</u> (configuration option is set. If it is **not** set (the default), you can use KEYSTACK immediately after an application is started. However, if <u>Wait for External Apps</u> (47) is set, *TCC* will not execute any other operation until the program has finished, including the KEYSTACK command, and instead of the target program, the keystrokes will be sent to whatever program is running in the active window when KEYSTACK is executed.

You may not be able to use KEYSTACK effectively if you have programs running in the background which change the active window (for example, by popping up a dialog box). If a window pops up in the midst of your KEYSTACK sequence, keystrokes stored in the KEYSTACK buffer may go to that window, and not to the application you intended.

Keystroke Interpretation

Characters entered within double quotes (for example, "*abc"*) will be sent to the target program as is. The only items allowed outside the quotes are key names, the ! and $|W|^{264}$ options, and a repeat count.

If **keyname** is a single letter, it is inserted in the keystack buffer as if it had been quoted, without any spaces. For example, you could enter the string **abc** as **a b c**, instead of the quoted string method described above.

If **keyname** is a number, it is interpreted as a virtual key code (0 - 255).

Repetition. To send **keyname** several times, follow it with a space, left bracket [, the repetition count, and a right bracket]. For example, the command below will send the **Enter** key 4 times:

```
keystack enter [4]
```

The repeat count works only with an individual *keyname*. It cannot be used with quoted strings. You must have a blank space between the *keyname* and the repetition count.

See Keys and key names of the key name and numeric key code format.

Limitations

You can store a maximum of 4,095 characters in the KEYSTACK buffer. The count is determined by the number of characters on the KEYSTACK command line, not by the actual number of characters sent to the application.

Each time the KEYSTACK command is executed, it will clear any remaining keystrokes stored by a previous KEYSTACK command.

Note

You may need to experiment with your programs and insert delays (see the /W 264) option) to find the window activation and keystroke sequence that works for a particular program.

Example

To start Word and open the last document you worked on, you could use the command:

```
start word & keystack /w54 alt-f "1"
```

This start *Word*, delays about three seconds (54 clock ticks at about 1/18 second each) for *Word* to get started, places the keystrokes for alt-F (File pulldown menu), and 1 (open the most recently used file) into the buffer. *Word* receives these keystrokes and performs the appropriate actions. Notice that the two commands, <u>START</u> and KEYSTACK are issued on a single command line. This ensures that the keystrokes are sent to *Word*'s window, not back to *TCC*.

Option:

/R Read the KEYSTACK input from a file. (You can only read a single line.)

Delay the next keystroke in the KEYSTACK buffer by a specified number of **clock ticks**. A clock tick is approximately 1/18 second. The number of clock ticks to delay should be placed immediately after the **W**, and must be between **1** and **65535** (65,535 ticks is about 1 hour). Do not use the Thousands Separator in the number! You can use the **/W** option as many times as desired and at any point in the string of keystrokes except within double quotes. Some programs may need the delays provided by **/W** in order to receive keystrokes properly from KEYSTACK. The only way to determine what delay is needed is

3.13.68 LIST

Purpose Display a text file, with forward and backward paging and scrolling.

Format LIST [range...] [/A:[[-|+]rhsadecijopt /B[-]n /C /Etext"/H /I /L[-]n /N /R /S /T"text" /U /W /X[s]] [@file] [file...]

file A file or list of files to display.

@file A text file containing the names of the files to view, one per line (see @file

lists 90 for details).

to experiment.

range A file selection range 80 (date 82), description 86, exclusion 85, size 82, time

/A: (Attribute select) 267 /N (line numbers) 268 /B(yte offset) 267 /R(everse) 268 /R(everse) 268 /C (separate console) 267 /S(tandard input) 268 /E (regular expression) 268 /H(igh bit off) 268 /U (Ruler) 269 /U (Ruler) 269

/I(gnore wildcards) 268 /W(rap) 269

See also: HEAD 249, TAIL 339, and TYPE 354.

File Selection

Supports <u>attribute switches</u> 86, extended <u>wildcards</u> 77, <u>ranges</u> 80, <u>multiple file names</u> 87, and <u>include</u> lists 88.

Internet

Can be used with FTP/HTTP Servers 93.

Usage

LIST provides a fast and flexible way to view a file, without the overhead of loading and using a text editor.

For example, to display a file called *MEMO.DOC*:

list memo.doc

Note: LIST is primarily intended for displaying the contents of ASCII and Unicode text files (i.e. alphanumeric characters arranged in lines separated by CR/LF). It can be used for other files which contain non-alphabetic characters or unusual line separators, but you may need to use hexadecimal mode (see below) to display or search these files. Lines longer than 16,383 characters will be truncated unless you're in Wrap or Hex modes.

LIST displays files in the *TCC* window. In *TCC*, the standard tool and scroll bars are replaced with the LIST tool and scroll bars. Use the scroll bars or the cursor pad to scroll through the file. You can select the LIST command either with the mouse (on the tool bar and scrollbars) or from the keyboard. LIST recognizes the following keys and buttons:

Key (Button)	Meaning
Home	Display the first page of the file
End	Display the last page of the file
Esc (ListExit 37)	Exit the current file
Ctrl-C (Quit)	Quit LIST
Ctrl-PgUp	Display previous file
Ctrl-PgDn	Display next file
Up Arrow	Scroll up one line
Down Arrow	Scroll down one line
Left Arrow	Scroll left 8 columns
Right Arrow	Scroll right 8 columns
Ctrl Left Arrow	Scroll left 40 columns
Ctrl Right Arrow	Scroll right 40 columns
Del	Prompt whether to delete the file
Ins	Prompt whether to save the pipe or file to a new name
Tab	Prompt for a new default tab size
F1	Display online help
F5 (ListRefresh 39)	Refresh the display
B (ListPrevious 39 ⁵)	Go back to the previous file in the current group of files
Ctrl-B (ListClipboard 3	
C (ListContinue 37)	Continue with the next file
е	Edit the file (with the default editor; see the Editor 49 configuration
	option). If LIST is displaying a pipe, the contents are saved to the
	clipboard and the editor is started. (You will need to manually paste the
- (-: N	clipboard contents.)
F (Find)	Prompt and search for a string or a sequence of hexadecimal values
Ctrl-F	Prompt and search for a string, searching backward from the end of the
C (Coto)	file
G (Goto)	Go to a specific line or, in hex mode, to a specific hexadecimal offset
H (High)	Toggle the "strip high bit" (/H 268) option
l (Info)	Display information on the current file (the full name, size, date, and time)
L(ine numbers)	Toggle the line numbering option
N (<u>ListNext</u> 38 ¹) Ctrl-N	Find next matching string in the file
O (ListOpen 39)	Find previous matching string in the file
Ctrl-O	Open a new file
	Open a new file
P (Print)	Print selected pages or the entire file (make your selection in the Windows "Print" dialog)
R ListFindRegex 38	Prompt and search for a regular expression
Ctrl-R	Prompt and search local regular expression Prompt and search backwards for a regular expression
U (ListUnicode 39)	Toggle the Unicode display mode
W (Wrap)	Toggle the "line wrap" (/W 2691) option
vv (vviap)	Toggie the line with (/VV)2001) option

X (Hex) Toggle the hex-mode display (/X 269) option

Text searches performed with **F**, **N**, **Ctrl-F**, and **Ctrl-N**, or with the corresponding buttons, are not case-sensitive unless you check the Match case box in the search dialog. LIST remembers the search strings you have used in the current session; to select a previous string, use the drop-down arrow to the right of the string entry field (the **N** key and the Next button search for the top item in this drop-down list).

When the search string is found LIST displays the line containing the string at the top of the window, and highlights the string it found. Any additional occurrences of the string on the same display page are also highlighted. Highlighting is intended for use with text files. In binary files, the search string will be found but may not be highlighted properly.

If the display is currently in hexadecimal mode and you press **F** or **Ctrl-F**, you will be prompted for whether you want to search in hexadecimal mode. If so, you should then enter the search string as a sequence of 2-digit hexadecimal numbers separated by spaces, for example **41 63 65** (ASCII string values for the string "Ace"). Hexadecimal searches are case-sensitive, and search for exactly the string you enter.

LIST saves the search string used by F, N, Ctrl-F, and Ctrl-N so you can LIST multiple files and search for the same string simply by pressing N in each file, or repeat your search the next time you use LIST.

You can use extended wildcards \overrightarrow{to} in the search string. For example, you can search for the string to*day to find the next line which contains the word to followed by the word day later on the same line, or search for the numbers to*100 or to*100 with the search string to*100 lf you begin the search string with a back-quote to*100, or enclose it in back-quotes, wildcard characters in the string will be treated as normal text with no special wildcard meaning.

You can use the /T 268 switch to specify search text for the first file. When you do so, LIST begins a search as soon as the file is loaded. Use /I 268 to ignore wildcards in the initial search string, and /R 268 to make the initial search go backwards from the end of the file. When you LIST multiple files with a single LIST command, these switches affect only the first file; they are ignored for the second and subsequent files.

You can also search using Regular Expressions using the **R** and **Ctrl-R** keys. See <u>Regular</u> Expression Syntax 496 for supported expressions.

You can use the **G** key to go to a specific line number in the file (or to a specified hexadecimal offset in hex mode). LIST numbers lines beginning with **1**. A new line is counted for every **CR** or **LF** character (LIST determines automatically which character is used for line breaks in each file), or when line length reaches 16,383 characters, whichever comes first.

LIST normally allows long lines in the file to extend past the right edge of the screen. You can use the horizontal scrolling keys (see above) to view text that extends beyond the screen width. If you use the W command or /W | 269 switch to wrap the display, each line is wrapped when it reaches the right edge of the screen, and the horizontal scrolling keys are disabled.

To view output from another command simply pipe the output of the command to LIST, for example:

Normally LIST will detect input from a pipe automatically, but if it does not, use /S 2083 to explicitly specify piped input. Your ability to navigate backward through the displayed output (e.g. with **PgUp**) may be limited when viewing a large amount of data through a pipe, due to the way Windows handles piped output.

To view text from the clipboard, use CLIP: as the file to be listed. CLIP: will not return any data unless the clipboard contains text. See Redirection of for more information on CLIP:.

If you print the file which LIST is displaying, the print format will match the display format. If you have switched to hexadecimal or wrapped mode, that mode will be used for the printed output as well. If you print in wrapped mode, long lines will be wrapped at the width of the display. If you print in normal display mode without line wrap, long lines will be wrapped or truncated by the printer, not by LIST. Regardless of the display mode, LIST will bring up a standard Windows print dialog which allows you to print selected text, the current page, or the entire file.

• FTP/HTTP Usage

LIST can display files on FTP servers 3 as well as the contents of HTTP/HTTPS URLs. For example:

```
list ftp://jpsoft.com/index
list http://jpsoft.com/notfound.htm
```

You can also use the <u>IFTP</u> | 255 command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want. For more information, see <u>Using</u> FTP/HTTP Servers 3 and IFTP | 255 | 256 | 257 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258 | 258

NTFS File Streams

LIST supports file streams on NTFS drives. You can list an individual stream by specifying the stream name, for example:

```
list streamfile:s1
```

If no stream name is specified the file's primary data is displayed.

See NTFS File Streams 496 for additional details.

Advanced Features

If you specify a directory name instead of a filename as a parameter, LIST will display each of the files in that directory.

If no filename is specified (and stdin sib is not redirected), LIST will open the common Windows "open file" dialog.

Most of the LIST keystrokes can be reassigned with key mapping 36 directives.

By default, LIST sets tab stops every 8 columns. You can change this behavior with the <u>Tabs Width</u> 51 configuration option.

Options

Select only those files that have the specified attribute(s) set. See Attribute Switches

| 86 | for information on the attributes which can follow /A:. Do not use /A: with @file lists. See @file lists | 90 | for details.

/B[-]n Start at byte *n*. If *n* is preceded by a minus sign –, start *n* bytes from the end of the file. The /B option will only display the file from the offset to the end; you cannot go back to a point before the offset.

Display the file in a separate screen buffer and restore the original buffer upon exiting LIST.

Search for a regular expression [496] in the first *file*. This option is the same as pressing **R**, but it allows you to specify the search text on the command line. The regular expression must be contained in double quotes if it contains spaces, punctuation, or wildcard characters. See also /T.

/H Strip the high bit from each character before displaying. This is useful when displaying files created by some word processors that turn on the high bit for formatting purposes. You can toggle this option on and off from within LIST with the H key or the tool bar.

Only meaningful when used in conjunction with the T 268 "text" option. Directs LIST to interpret characters such as *, ?, [, and] as literal characters instead of wildcard characters. /I affects only the initial search started by T 268, not subsequent searches started from within LIST.

/I"text" Select files by matching text in their descriptions. See <u>Description Ranges</u> for details.

/L[-]n Start at line **n**. If **n** is preceded by a minus sign -, start -**n** lines from the end of the file. The /**L** option only affects the initial page display; it does not prevent you from subsequently scrolling back to the start of the file.

/N Display line numbers. You can toggle the line numbers with the L key.

Only meaningful when used in conjunction with the /T 268 "text" option. Directs LIST to search for text from the end of the file instead of from the beginning of the file. Using this switch can speed up searches for text that is normally near the end of the file, such as a signature. /R affects only the initial search started by /T, not subsequent searches started from within LIST.

Read from standard input rather than a file. This allows you to redirect command output and view it with LIST. Normally, LIST will detect input from a redirected command and adjust automatically. However, you may find circumstances when /S is required. For example, to use LIST to display the output of DIR you could use either of these commands:

```
dir | list
dir | list /s
```

Search for text in the first *file*. This option is the same as pressing **F**, but it allows you to specify the search text on the command line. The text must be contained in double quotes if it contains spaces, punctuation, or wildcard characters. For example, to search for the string **TC** in the file **README.DOC**, you can use this command:

```
list /t"Take Command" readme.doc
```

The search text may include wildcards and extended wildcards. For example, to search for the words *Hello* and *John* on the same line in the file *LETTER.DAT*:

```
list /t"Hello*John" letter.dat
```

When you display multiple files with a single LIST command, /T only initiates a search in the first file. It is ignored for the second and subsequent files. See also: $\frac{1}{268}$ and $\frac{1}{2}$

/U Display a ruler on the second line.

/W Wrap the text at the right edge of the screen. This option is useful when displaying

files that don't have a carriage return at the end of each line. The horizontal scrolling keys do not work when the display is wrapped. You can toggle this option on and off

from within LIST with the W key or the Wrap button on the tool bar.

/X Display the file in hexadecimal (hex) mode. This option is useful when displaying

executable files and other files that contain non-text characters. Each byte of the file is shown as a pair of hex characters. The corresponding text is displayed to the right of each line of hexadecimal data. You can toggle this mode on and off from within

LIST with the X key or the heX button on the tool bar.

You can display spaces rather than periods for non-printable characters by specifying the /XS option. You can also toggle between spaces and periods with

the **S** key while displaying a file in hex mode.

3.13.69 LOADBTM

Purpose: Switch a batch file to or from BTM mode.

Format: LOADBTM [ON | OFF]

Usage:

TCC recognizes three kinds of batch files 130: .CMD, .BAT, and .BTM. Batch files with a .BTM extension will run faster than .BAT or .CMD files, as they are loaded into memory at startup and do not open and close the batch file for each line (as do .BAT and .CMD files).

The LOADBTM command turns BTM mode on and off. It can be used to switch modes in either a . *CMD* or .*BTM* file. If you use LOADBTM with no parameter, it will display the current batch mode: LOADBTM ON or LOADBTM OFF.

Using LOADBTM to repeatedly switch modes within a batch file is not efficient. In most cases the speed gained by running some parts of the file in BTM mode will be more than offset by the speed lost through repeated loading of the file each time BTM mode is invoked.

LOADBTM can only be used within a batch file. It is most often used to convert a .BAT or .CMD file to BTM mode without changing its extension.

3.13.70 LOADMEDIA

Purpose: Close the door of a removable media drive(s)

Format: LOADMEDIA drive ...

Usage:

LOADMEDIA will close the drive door (if the device allows it) of removable media, such as CD-ROMs, DVDs, etc.

See also EJECTMEDIA 2201.

3.13.71 LOG

Purpose: Save a log of commands to a disk file.

Format: LOG [/A /E /H /W file] [ON | OFF | text]

file The name of the file to hold the log.

text An optional message that will be added to the log.

 /A(II) | 270 |
 /H(istory log) | 270 |

 /E(rrors) | 270 |
 /W(rite to) | 271 |

See also: HISTORY 251.

Usage:

The LOG command provides independent controls for two different methods of logging *TCC* activity:

- Command Log 270
- History Log 270.

Command Log

Command logging creates a record of each internal and external command executed either from the command prompt or from a batch file in the format below:

```
[date time][id] command
```

where the **date** and **time** are formatted according to the country code set for your system, **id** is the process ID in hexadecimal format, and **command** is the actual command after any alias or variable expansion.

The LOG command controls the **command log** operation if it does not include the /H 270 option. The default command log filename is **TCCommandLog**.

History Log

History log creates a record of each command executed from the command prompt exactly as it was entered, before aliases and variables are expanded, without any additional information.

The LOG command controls the *history log* operation if it includes the /H 270 option.

Notes

The LOG /H output can be used as the basis for writing batch files. Start LOG /H, then execute the commands that you want the batch file to execute. When you are finished, turn LOG /H off. The resulting file can be turned into a batch file that performs the same commands with little or no editing.

Options:

- /A This option saves all output to the *log all* file. The default filename is *TCLogAll*.
- This option saves all error messages to the *error log*. The default filename is *TCErrorLog*. See also: the <u>Error Logging are configuration option</u>.
- /H This option saves the commands to the *history log*. The default history log name is *TCHistoryLog*. For example, to turn on history logging and write to the file *C:\LOG\HLOG*:

log /h /w c:\log\hlog

/W

This switch specifies a different filename for the LOG output. It also automatically performs a LOG ON command. For example, to turn command logging on and write the log to C:\LOG\LOGFILE:

```
log /w c:\log\logfile
```

Once you select a new file name with the LOG /W or LOG /H /W command, LOG will use that file until you issue another LOG /W or LOG /H /W command, or until you terminate your *TCC* session. Turning LOG or LOG /H off or on does not change the file name.

3.13.72 MD / MKDIR

Purpose: Create a subdirectory.

Format: MD [/N[et] /S] path...

or

MKDIR [/N[et] /S] path...

path The name of one or more directories to create.

/N(o update) 272 /S(ubdirectories) 272

See also: RD 301.

Internet: Can be used with FTP Servers 3.

Usage:

MD and MKDIR are synonyms. You can use either one.

MD creates a subdirectory anywhere in the directory tree. To create a subdirectory from the root, start the *path* with a backslash [\]. For example, this command creates a subdirectory called *MYDIR* in the root directory:

```
md \mydir
```

If no path is given, the new subdirectory is created in the current directory. This example creates a subdirectory called *DIRTWO* in the current directory:

```
md dirtwo
```

To create a directory from the parent of the current directory (that is, to create a sibling of the current directory), start the pathname with two periods and a backslash [...].

Windows limits the maximum length of the subdirectory name. See <u>Directories and Subdirectories</u> 492 for details.

When creating a directory on an LFN drive, you must quote any *path* which contains white space or special characters.

If MD creates one or more directories, they will be added automatically to the <u>extended directory</u> search 3 database unless the **/N** option is specified.

You can create directories on FTP servers. For example:

```
md ftp://ftp.abc.com/data/index
```

Options:

/N

If /N has no additional options, do not update the CD / CDD extended directory search (73) database, JPSTREE.IDX. This is useful when creating a temporary directory which you do not want to appear in the extended search database. /N takes two optional arguments:

- Don't display errors. (Note that a **/Ne** alone will still update the <u>extended</u> directory search 3 database.)
- t Don't update the extended directory search (This is the same as /N with no options.)
- Allows you to create more than one directory at a time. For example, if you need to create the directory *C:\ONE\TWO\THREE* and none of the named directories exist, you can use /S to have MD create all of the necessary subdirectories in a single command (without the /S, this command will fail because the parent directory *C:\ONE\TWO* does not exist):

```
md /s \one\two\three
```

For compatibility with CMD.EXE, **/S** becomes the default if you enable *TCC* extensions with the **/X** switch on the *TCC*startup command line. See Command Line Options of the details on **/X**.

3.13.73 **MEMORY**

Purpose: Display the amount and status of system RAM.

Format: MEMORY

Usage:

MEMORY lists the percentage "memory load" as reported by Windows, the total and available physical RAM, the total and available page file size, the total and available virtual memory, the total and free alias and function space, and the total history space. The memory load is a figure returned by the operating system which gives an overall sense of memory utilization. It is not a precise indicator of system load or memory usage. The total page file figure shows the total number of bytes that can be stored in the file, but may not reflect the actual size of the current file on disk.

3.13.74 MKLINK

Purpose: Create NTFS symbolic, hard, and soft links.

Format: MKLINK [/D /H /J /Q] Link Target

/D 274 Create a directory symbolic link. (The default is to create a file symbolic link.)

TH 273 Create a hard link (like MKLNK).

7J 273 Create a junction.

Don't display results.

Link The new symbolic link name

Target The pathname (full or relative) that the new link refers to.

Usage:

Due to Windows file system restrictions, creating symbolic links with MKLINK requires an NTFS volume and Windows Vista or later.

The file/directory names in *Link* and *Target* can be fully or partially qualified. MKLINK will also copy an existing description to the link.

See also MKLNK 273.

Option:

/D Create a directory symbolic link. (The default is to create a file symbolic link.)

/H Create a hard link instead of a symbolic link.

/J Create a junction rather than a symbolic link.

/Q Don't display the result.

3.13.75 MKLNK

Purpose: Create or delete an NTFS hard or soft link.

Format: Create or update a link:

MKLNK [/A:[[-]rhsadecijopt]] parm1 [parm2]

Delete a link MKLNK /D parm1

parm1 Name of an existing file (hard link 529) or directory (for soft link 534).

parm2 Name of the new directory entry (a file or directory reference) to be created.

/A: 274 (Attribute select)
/D|274 Delete a link

See also MKLINK 272.

File Selection

For hard links, MKLNK supports <u>attribute switches</u> so, extended <u>wildcards</u>, ranges so, multiple file <u>names</u>, and <u>include lists</u> so. Date, time, size, or file exclusion ranges anywhere on the line apply to all **source** files. Use wildcards with caution on LFN volumes; see <u>LFN File Searches</u> for details.

Usage:

Due to operating and file system restrictions, this command requires an NTFS volume.

The file/directory names in *parm1* and *parm2* can be fully or partially qualified, and may contain wildcards (hard links only). MKLINK will also copy an existing description to the link.

If a single argument is specified and it is a junction, MKLNK will display the directory name linked to the junction.

Hard Links

If *parm1* is a file, and *parm2* does not exist, MKLNK will create a hard link 529, as described in the Glossary. If *parm2* exists, MKLNK reports an error.

MKLNK (and the underlying Windows API) may fail if the current directory is on a subst or net use

drive, or a UNC volume.

Soft Links

If *parm1* is a directory, and *parm2* does not exist, MKLNK will create a <u>soft link [534]</u>, also known as a "directory junction" or "reparse point". If *parm2* exists, and it is a <u>soft link [534]</u>, MKLNK updates it.

A soft link is an indirect or symbolic reference (*parm2*) to a directory that physically resides in another location (*parm1*). Note: deleting files from a soft link is equivalent to deleting the files from the original directory.

Note: Other operating systems, such as Linux, may also support "hard links" and "soft links", but the Windows implementation of these concepts may not behave in the same manner even though the names might be similar.

Option:

/A: Select only those files that have the specified attribute(s) set (hard links only). See Attribute Switches or information on the attributes which can follow /A:.

/D Remove an existing hard or soft link. For hard links, if no more links remain **/D** will not delete the file.

3.13.76 MOVE

Purpose: Move files to a new directory and drive.

Format: MOVE [/A:[[-]rhsadecijopt /B /C /D /E /G /H /I"text" /J /L /LD /M /MD /N[dejst] /O /P /Q /R

/S[n] /T /U /V /W /Y /Z] [@file] source... destination

source A file or list of files to move. **destination** The new location for the files.

@file A text file containing the names of the source files to move, one per line

(see @file lists 90 for details).

/A: (Attribute select) 277 /N (Disable) 278 /B (Move after reboot) 277 /O (don't move in

/B (Move after reboot) 277 /O (don't move if target exists) 278 /C(hanged) 277 /P(rompt) 278 /Q(uiet) 278 /Q(uiet) 278

/E (No error messages) 277 /R(eplace) 278

/G (display percent copied) [277] /S(ubdirectory tree) [278]

/H(idden and system) | 277 | /T(otal) | 279 | /I"text" (match description) | 278 | /U(pdate) | 279 | /U(posterior) | 278 | /V(erify) | 279 | /V(ipe) | 279 | /

/LD (create link) 278 /Y (force move of encrypted files) 279

/M(odified files) 278 /Z (overwrite) 279

/MD (Create target directory) 278

Note: MOVE is a complex command. When source and destination are on the same volume and the destination doesn't exist, it's equivalent to a simple REN 305, but when the destination exists or two volumes are involved, it becomes a two-step command: a COPY 1821 to the target followed, if successful, by a DEL 1901 of the source. In this topic, references to "move" may apply to the entire process or only to one of the above steps specifically depending on context.

See also COPY 1821, DEL 1901 and RENAME 3051.

File Selection

Supports attribute switches &, extended wildcards , ranges &, multiple file names &, delayed variable expansion &, and include lists &. Date, time, size, or file exclusion ranges anywhere on the line apply to all source files. Use wildcards with caution on LFN volumes; see LFN File Searches for details.

Internet: Can be used with FTP/TFTP/HTTP/S Servers 937.

Usage:

The MOVE command moves one or more files from one directory to another, whether the directories are on the same drive or not. It has the same effect as copying the files to a new location and then deleting the originals. Like COPY [182] and RENAME [305], MOVE works with single files, multiple files, and sets of files specified with an include list.

The simplest MOVE command moves a single **source** file to a new location and, optionally, gives it a new name. These two examples both move one file from drive *C*: to the root directory on drive *A*:

```
[c:\] move myfile.dat a:\
[c:\] move myfile.dat a:\savefile.dat
```

In both cases, *MYFILE.DAT* is removed from drive *C*: after it has been copied to drive *A*:. If a file called *MYFILE.DAT* in the first example, or *SAVEFILE.DAT* in the second example, already existed on drive *A*:, it would be overwritten. (This demonstrates the difference between MOVE and RENAME. MOVE will move files between drives and will overwrite the destination file if it exists; RENAME will not.)

When you move a single file, the *destination* can be a directory name or a file name. If it is a directory name, and you add a backslash [\] to the end of the name, MOVE will display an error message if the name does not refer to an existing directory. You can use this feature to keep MOVE from treating a mistyped *destination* directory name as a file name, and attempting to move the *source* file to that name.

If you MOVE multiple files, the **destination** must be a directory name. MOVE will move each file into the **destination** directory with its original name. If the **destination** is not a directory, MOVE will display an error message and exit. For example, if *C:\FINANCEWYFILES* is not a directory, this command will display an error; otherwise, the files will be moved to that directory:

```
move *.wks *.txt c:\finance\myfiles
```

The **/D** option can be used for single or multiple file moves; it checks to see whether the **destination** is a directory, and will prompt to see if you want to create the **destination** directory if it doesn't exist.

If MOVE creates one or more destination directories, they will be added automatically to the extended directory search database; see Extended Directory Searches 73 for details.

Be careful when you use MOVE with the <u>SELECT</u> (312) command. If you SELECT multiple files and the **destination** is not a directory (for example, because of a misspelling), MOVE will assume it is a file name. In this case each file will be moved in turn to the **destination** file, overwriting the previous file, and then the original will be erased before the next file is moved. At the end of the command, all of the original files will have been erased and only the last file will exist as the **destination** file.

You can avoid this problem by using square brackets with SELECT instead of parentheses (be sure that you don't allow the command line to get too long — watch the character count in the upper left corner while you're selecting files). MOVE will then receive one list of files to move instead of a series

of individual filenames, and it will detect the error and halt. You can also add a backslash [\] to the end of the *destination* name to ensure that it is the name of a subdirectory (see above).

When you specify a a single subdirectory source and a single subdirectory target, the source directory tree will be moved to a subdirectory of the target directory. If the source is a subdirectory and the target doesn't exist, the target subdirectory will be created and the source tree moved to is. (These are both for compatibility with *CMD.EXE*.)

• FTP Usage:

You can move files to and from Internet URLs (FTP, TFTP and HTTP). For example:

```
move ftp://ftp.abc.com/f1.txt c:\text\
```

Files moved to or from FTP servers are normally transferred in binary mode. To perform an ASCII transfer use the /L switch. File descriptions are not copied when moving files to an Internet URL.

Wildcard characters such as [*] and [?] will be treated as wildcards in FTP URLs, but will be treated as normal characters in HTTP URLs.

Note: The **/G** option (percent moved) may report erratic values during transfer of files larger than 4 Gb (an FTP limitation) and during http downloads.

• NTFS File Streams:

MOVE supports file streams on NTFS drives. You can move an individual stream by specifying the stream name, for example:

```
move streamfile:s1 file2
```

If no stream name is specified the entire file is moved, including all streams. However, if you move a file to a drive or device which does not support streams, only the file's primary data is moved; any additional streams are not processed and their data will be lost.

See NTFS File Streams 496 for additional details.

Advanced Features and Options

MOVE first attempts to rename the file(s), which is the fastest way to move files between subdirectories on the same drive. If that fails, (e.g., because the **destination** is on a different drive or already exists), MOVE will copy the file(s) and then delete the originals.

If MOVE must physically copy the files and delete the originals, rather than renaming them (see above), then some disk space may be freed on the **source** drive. The free space may be the result of moving the files to another drive, or of overwriting a larger **destination** file with a smaller **source** file. MOVE displays the amount of disk space recovered unless the **/Q** option is used (see below). It does so by comparing the amount of free disk space before and after the MOVE command is executed. However, this amount may be incorrect if you are using a deletion tracking system which retains deleted files for later recovery, or if another program performs a file operation while the MOVE command is executing.

When physically copying files, MOVE preserves the hidden, system, and read-only attributes of the **source** files, and sets the archive attribute of the **destination** files. However, if the files can be renamed, and no copying is required, then the **source** file attributes are not changed.

Use caution with the /A: and /H switches (both of which can allow MOVE to process hidden files) when you are physically moving files, and both the **source** and **destination** directories contain file

descriptions. If the **source** file specification matches the description file name (normally *DESCRIPT.ION*), and you tell MOVE to process hidden files, the *DESCRIPT.ION* file itself will be moved, overwriting any existing file descriptions in the **destination** directory. For example, if the *C:\DATA* directory contains file descriptions, this command would overwrite any existing descriptions in the *D:\SAVE* directory:

```
[c:\data] move /h d* d:\save\
```

(If you remove the hidden attribute from the *DESCRIPT.ION* file the same caution applies even if you do not use **/A**: or **/H**, as *DESCRIPT.ION* is then treated like any other file.)

Note: The wildcard expansion process will attempt to allow both CMD.EXE-style "extension" matching (only one extension, at the end of the word) and the advanced *TCC* string matching (allowing things like *.*.abc) when an asterisk is encountered in the **destination** of a MOVE command.

MOVE supports connected web folders. If an HTML file (i.e., with an .htm or .html extension) is copied, MOVE will look for a folder in the same directory with the same name and an extension of ".files". If it is found, the .files directory will be moved to the target directory. You can disable connected web folders by setting the registry key:

HKCU\Software\Microsoft\Windows\CurrentVersion\Explorer\NoFileFolderConnection=0

Options:

- /A: Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. See the cautionary note under Advanced Features and Options above before using /A: when both the source and destination directories contain file descriptions. Do not use /A: with @file lists. See @file lists of for details.
- **/B** If MOVE can't move the file (i.e., access denied), it will schedule it to be moved at the next reboot.
- Move files only if the *destination* file exists and is older than the *source* (see also /U). This option is useful for updating the files in one directory from those in another without moving any newly-created files. Do not use /C with @file lists. See <u>@file lists</u> of for details.
- **/D** Requires that the **destination** be a directory. If the **destination** does not exist, MOVE will prompt to see if you want to create it. If the **destination** exists as a file, MOVE will fail with an "Access denied" error. Use this option to avoid having MOVE accidentally interpret your **destination** name as a file name when it's really a mistyped directory name.
- **/E** Suppress all non-fatal error messages, such as "File Not Found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files and aliases.
- **/G** Displays the percentage of the file moved, the transfer rate (in Kbytes/second), and the estimated time remaining. This is useful when copying large files across networks or via FTP to show whether the move is proceeding.
- /H Move all files, including hidden and system files. See the cautionary note under Advanced Features and Options above before using /H when both source and destination directories contain file descriptions.

- /I"text" Select *source* files by matching text in their descriptions. The text can include wildcards. The search text must be enclosed in double quotes, and must follow the // immediately, with no intervening spaces. You can select all filenames that have a description with // "[?]*", or all filenames that do not have a description with // "[]". Do not use // with @file lists. See @file lists of the details.
- Copy the file in restartable mode. The copy progress is tracked in the destination file in case the move fails. The copy can be restarted by specifying the same source and destination file names.
- /L Perform FTP transfers in ASCII mode, instead of the default binary mode.
- **/LD** When used with /S, if the source is a symbolic or hard link to a directory, MOVE will create the link in the target directory instead of moving the subdirectory tree.
- Move only files that have the archive bit set. The archive bit will remain set after the MOVE. Do not use /M with @file lists. See @file lists 90 for details.
- **/MD** Create the target directory if it doesn't exist. (Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise MOVE cannot tell what you want for the directory and what you want for the filename!)
- /N Do everything except actually move the file(s). This option is most useful for testing what a complex MOVE command will do. /N displays how many files would be moved. /N does not prevent creation of *destination* subdirectories when it is used with /S.

A /N with one of the following arguments has an alternate meaning:

- **d** Skip hidden directories (when used with /S)
- e Don't display errors.
- j Skip junctions (when used with /S)
- **s** Don't display the summary.
- t Don't update the CD / CDD extended directory search (JPSTREE.IDX).
- **/O** Don't move the file(s) unless the target doesn't exist, i.e. do not overwrite an existing target..
- /P Prompt the user to confirm each move. Your options at the prompt are explained in detail under Prompts 1021.
- **/Q** Don't display filenames, the total number of files moved, the percentage moved, or the amount of disk space recovered, if any. When used in combination with the **/P** option above, it will prompt for filenames but will not display the totals. This option is most often used in batch files. See also **/T**.
- /R Prompt for a Y or N response before overwriting an existing *destination* file.
- Move an entire subdirectory tree to another location. MOVE will attempt to create the **destination** directories if they don't exist, and will remove empty subdirectories after the move. When **/D** is used with **/S**, you will be prompted if the first **destination** directory does not exist, but subdirectories below that will be created automatically by MOVE. If MOVE /S creates one or more destination directories, they will be added automatically to the **JPSTREE.IDX** database. If you attempt to use **/S** to move a subdirectory tree into part of itself, MOVE will detect the resulting infinite loop, display an error message, and exit. Do not use **/S** with @file lists. See @file lists of for details.

If you specify a number after the /S, MOVE will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

- **/T** Don't display filenames as they are moved, but display the total number of files deleted and the amount of free disk space recovered, if any.
- Move each **source** file only if it is newer than a matching **destination** file or if a matching **destination** file does not exist (also see **/C**). This option is useful for moving new or changed files from one directory to another. Do not use **/U** with @file lists. See @file lists 90 for details. When used with file systems that have different time resolutions (such as FAT and NTFS), **/U** will attempt to use the "coarsest" resolution of the two.
- Verify each disk write by performing a true byte-by-byte comparison between the source and the newly-created target file. This option may significantly increase the time necessary to complete a MOVE command.
- /W If the MOVE is to a different drive, after the move overwrite the source file with 0's before deleting it (like DEL /W).
- /Y (XP+ Only) Force copy of an encrypted file even when the target will be decrypted (for CMD.EXE compatibility).
- Overwrite read-only destination files. Without this option, MOVE will fail with an "Access denied" error if the destination file has its read-only attribute set. This option allows MOVE to overwrite read-only files without generating any errors.

3.13.77 MSGBOX

Purpose: Display a Windows message box

Format: MSGBOX [/1["text"] /2["text"] /3["text"] /4["text"] /Dn /H /I /M /N /O /Px,y /Q /R /S /Tn /W]

buttontype ["title"] prompt

buttontype One of OK, OKCANCEL, YESNO, YESNOCANCEL, RETRYCANCEL,

ABORTRETRYIGNORE, CANCELTRYCONTINUE, or

CONTINUEABORT

title Text for the title bar of the message box.prompt Text that will appear inside the message box.

/1 (st button) 281 /N (no sound) 281 /2 (nd button) 28h O (topmost window) 281 /3 (rd button) 281 /P (screen coordinates) 281 /4 (th button) 281 /Q(uestion icon) 281 /D(isable temporarily) 281 /R(ight justify buttons) 281 /H(elp button) 281 /S(top icon) 281 /I(nformation icon) 281 /T(imeout) 28 /M (system modal) 281 W(arning icon) 28h

See also: INKEY 257, INPUT 259, QUERYBOX 300, and TASKDIALOG 341.

Usage:

MSGBOX can display one of eight kinds of message boxes and wait for the user's response. You can

use *title* and *prompt* to display any text you wish. *TCC* will automatically size and center the box on the screen. The message box has up to three response buttons (plus an optional Help button), depending on its type, as shown below.

boxtype	button 1	button 2	button 3
ок	OK		
OKCANCEL	OK	Cancel	
YESNO	Yes	No	
YESNOCANCEL	Yes	No	Cancel
RETRYCANCEL	Retry	Cancel	
ABORTRETRYIGNORE	Abort	Retry	Ignore
CANCELTRYCONTINUE	Cancel	Try Again	Continue
CONTINUEABORT	Continue	Abort	

If the standard message box types don't meet your needs, you can create a custom message box with up to four buttons (plus an optional Help button), specifying the text that appears on each button.

The button the user chooses is indicated using the internal variable %_? 3801. Be sure to save the return value in another variable or test it immediately; because the value of %_? 3801 changes with every internal command. The following list shows the value returned for each selection:

response	%_? 380
Yes or OK	10
No	11
Cancel	12
Retry	13
Try Again	14
Continue	15
Ignore	16
Abort	17
Help	18
timeout	20
custom button 1	21
custom button 2	22
custom button 3	23
custom button 4	24

If you define custom buttons, the button type argument will be ignored.

If there is an error in the MSGBOX command itself, $\frac{\%_{-}?}{380}$ will be set as described in its documentation (see $_{-}?$ 380).

For example, to display a Yes or No message box and take action depending on the result, you could use commands like this:

```
msgbox yesno "Copy" Copy all files to A:?
if %_? == 10 copy * a:
```

Since MSGBOX doesn't write to standard output, it disables redirection and piping to allow you to enter the redirection characters (<, >, and |) in your prompt text.

MSGBOX creates a popup dialog box. If you prefer to retrieve input from the command line, see the INKEY 257 and INPUT 259 commands.

Options:

- If there is a text string following the option, set the custom text for the first button. Otherwise, set the first button as the default.
- If there is a text string following the option, set the custom text for the second button. Otherwise, set the second button as the default.
- If there is a text string following the option, set the custom text for the third button. Otherwise, set the third button as the default.
- If there is a text string following the option, set the custom text for the fourth button. Otherwise, set the fourth button as the default.
- **/Dn** Disable the message box buttons for *n* seconds at startup.
- /H Display a help button.
- /I Display an icon consisting of a lower case "i" in a circle in the message box.
- /M The message box is created as a system modal window.
- /N Don't play the default sound.
- **/O** The message box is created as a topmost window.
- **/Px,y** The initial x,y screen coordinates. If you don't use this option, MSGBOX will center its window in the *TCC* tab window.
- /Q Display a question mark icon in the message box.
- /R The buttons will be right-justified (as in XP Explorer).
- /S Display a stop sign icon in the message box.
- /Tn MSGBOX will wait a maximum of n seconds for a response. If the time limit expires,%_? will be set to 20. The time remaining before the window closes will be displayed in the default button.
- **/W** Display an exclamation point icon in the message box.

3.13.78 NETMONITOR

Purpose: Monitor network connection and disconnection

Format: NETMONITOR [/C [name]]

NETMONITOR name CONNECTED | DISCONNECTED n command

name Network name

n Number of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(lear) 282

Usage:

The network name can be either **LAN** (for a local area network), **WAN** (dialup network), or the name of a wireless network. The network name can include wildcards.

The command line will be parsed and expanded before NETMONITOR is executed, so if you want to pass redirection characters or variables to **command** you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

If you don't enter any arguments, NETMONITOR will display the networks it is currently monitoring.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use <u>START 33</u> or <u>DETACH 19</u> in *command* to avoid conflicts.

NETMONITOR creates environment variables when a network is connected that can be queried by *command*. The variable is deleted after *command* is executed.

_netname The name (SSID) of the network

_netcount The number of times the condition has been triggered

Options:

If **name** is specified, remove the monitor for that network. Otherwise, remove all

network monitors.

3.13.79 ON

Purpose: Execute a command in a batch file when a specific condition occurs.

Format: ON BREAK [command]

ON CLOSE [command]
ON ERROR [command]

ON ERRORLEVEL n [command]
ON ERRORMSG [command]
ON LOGOFF [command]
ON SHUTDOWN [command]
ON LBUTTON [command]
ON MBUTTON [command]
ON RBUTTON [command]

command command to execute when the event occurs

Usage:

ON sets a watch that remains in effect for the duration of the current batch file, or until replaced by another ON command. Whenever a **break** or **error** condition occurs after ON has been executed, the corresponding **command** is automatically executed.

Activation of ON BREAK

ON BREAK will execute *command* if the user presses Ctrl-C or Ctrl-Break.

Activation of ON CLOSE

ON CLOSE will execute *command* when *TCC* tab is closed.

Activation of ON ERROR and ON ERRORMSG

ON ERROR or ON ERRORMSG will execute *command* after any critical error, operating system error (such as a disk write error) or internal command error (such as a <u>COPY</u> 182) command that fails to copy any files, or the use of an invalid command option).

ON ERROR executes **command** immediately after the error occurs, without displaying any **TCC** error message (Windows errors may still be displayed).

ON ERRORMSG first displays the appropriate error message, then executes *command*.

If both are specified, ON ERROR will take precedence, and ON ERRORMSG will be ignored.

Activation of ON ERRORLEVEL

ON ERRORLEVEL n will execute **command** when the internal ERRORLEVEL variable is greater than or equal to the integer specified by n. You can also use the IF ERRORLEVEL tests; for example:

ON ERRORLEVEL EQ 37 ...

Activation of ON LOGOFF

ON LOGOFF will execute *command* when the user logs off.

Activation of ON SHUTDOWN

ON SHUTDOWN will execute *command* when the system is being shut down.

Activation of ON LBUTTON

ON LBUTTON will execute *command* when the left mouse button is clicked.

Activation of ON MBUTTON

ON MBUTTON will execute *command* when the middle mouse button is clicked.

Activation of ON RBUTTON

ON RBUTTON will execute *command* when the right mouse button is clicked.

Scope

Each time an ON statement is defined, it defines a new command to be executed for that event, and any prior command is discarded.

ON BREAK or ON ERROR[MSG] without a command restores the TCC default handler.

An ON statement only affects the current batch file. When the batch file containing ON is exited for any reason, whether temporarily (e.g., by a <u>CALL 175</u>) to another batch file) or permanently, the *TCC* default **break** and **error** handlers become effective. A <u>CALL 175</u>) ed batch file may then use ON to define its own handlers. When control returns to the calling batch file, its **break** and **error** handlers that had been in effect at the <u>CALL 175</u>) are reactivated.

Operation

The command can be any command that can be used on a batch file line by itself. Frequently, it is a GOTO 248 or GOSUB 247 command. For example, the following fragment traps any user attempt to

end the batch file by pressing Ctrl-C or Ctrl-Break. It scolds the user for trying to end the batch file and then continues:

```
on break gosub gotabreak
do i = 1 to 1000
    echo %i
enddo
quit
:gotabreak
echo Hey! Stop that!!
return
```

You can use a <u>command group [12]</u> as the command if you want to execute multiple commands, for example:

```
on break (echo Oops, got a break! & quit)
```

ON BREAK, ON ERROR, ON ERRORLEVEL, ON ERRORMSG, ON LBUTTON, ON MBUTTON, and ON RBUTTON assume that you want to continue executing the batch file. After the command is executed, control automatically returns to the command in the batch file immediately after the one that was interrupted by the event. To avoid continuing the batch file after the event at the next command perform one of the following in *command*:

- transfer control with GOTO 2481,
- end the batch file with QUIT 30th or CANCEL 1761
- chain to another batch file (without using CALL 175).

When handling an error condition with ON ERROR[MSG], you may find it useful to use <u>internal</u> variables [372], particularly %_? [380] and %_SYSERR [392], to help determine the cause of the error.

To force **TCC** to ignore break or error, use the REM 3041 command as your command.

Limitations

ON can only be used in batch files.

The ON ERROR[MSG] command will not be invoked if an error occurs while reading or writing redirected input, output, or a pipe.

Caution: If a break or error occurs while the command specified in ON BREAK. ON ERROR, ON ERRORLEVEL, or ON ERRORMSG is executing, the command will be restarted. This means you must use caution either to avoid or to handle any possible errors in the commands invoked by ON, since such errors can cause an infinite loop.

3.13.80 OPTION

Purpose: Modify or display **TCC** configuration.

Formats: Invoking the OPTION dialog: 285

OPTION

Temporarily changing a few options: 285

OPTION //directive=value ...

Temporarily changing a list of options: 285

OPTION @filename

Displaying the current value of an option: 285

OPTION directive

directive Name of a directive to set, modify, or display.

value A new value for that directive.

filename A file containing directives to be immediately activated.

See also: .INI file 26, SETDOS 323

Usage:

Invoking the OPTION Dialog

OPTION without parameters displays a property sheet which allows you to modify most of the configuration options stored in the INI file 26.

When you exit from the property sheet, you can select **Save** to save your changes in the .INI file for use in the current session and all future sessions, or select **Cancel** to discard the changes. See Configuration Dialogs 46 for more information.

In some cases, changes you make in the **Startup** section of the OPTION dialogs will only take effect when you restart **TCC**. Other changes take effect as soon as you exit the dialogs with **Save** or **OK**. However, not all option changes will appear immediately, even if they have taken effect. For example, some color changes will only appear after a **CLS** remaind.

OPTION handles most standard directives. The Key Mapping Directives and Advanced Directives and Control of the Coption of the

OPTION does not preserve inline comments when saving modified settings in the .INI file. To be sure . INI file comments are preserved, put them on separate lines in the file.

Setting Individual Options Temporarily

If you follow the OPTION command with one or more sequences of a double slash mark //, each followed by a new *directive=value*, the new settings will take effect immediately, and will be in effect for the current session only. This example turns off batch file echo and changes the input colors to bright cyan on black:

```
option //BatchEcho=No //InputColors=bri cya on bla
```

Option values may contain white space. However, you cannot enter an option value that contains the // string.

This feature is most useful for testing settings quickly, and in aliases or batch files that depend on certain options being in effect.

Changes made with // are temporary. They will not be saved in the .INI file.

Setting Many Options Temporarily

The command OPTION **@filename** allows you to temporarily modify multiple directive settings. The file specified by **filename** must be in the same format as an .<u>INI file 26</u>. Changes made with **@filename** are temporary. They will not be saved in the .INI file.

Displaying an option value

Specifying an option name alone will display the value of that option; e.g.:

option localHistory

localHistory=Yes

See also: the @OPTION 452 function.

3.13.81 OSD

Purpose: Write floating text to the display

Format: OSD [/C /Font=n /N /POS=top,left /RGB=r,q,b /TIME=n /TOP /BOTTOM /LEFT /RIGHT

/HCENTER /VCENTER /V] text

/C Close the current OSD display
/Font=n The font height (default 18)

/N Don't wait for timeout before returning to the prompt

/POS=top,left Screen coordinates for the top left corner of the text (default 10,10)

/RGB=r,g,b
/TIME=n
/TOP
/BOTTOM
/LEFT
/RIGHT

Text color in RGB format (default 0,255,0)
Time in seconds to display the text (default 10)
Position the text at the top of the display
Position the text at the bottom of the display
Position the text at the left of the display
Position the text at the right of the display

/HCENTER Center the text horizontally
/VCENTER Center the text vertically
/V Display the text vertically
text The text to display

Usage:

OSD displays text on the desktop without a surrounding window, like TV or monitor prompts.

If you want to display multiple lines, insert the LF escape sequence (^N) in your text. For example:

osd /pos=40,50 This is text with Nmultiple lines.

If you specify the /V (vertical display) option, you cannot also display multiple lines of text.

You can combine the window positioning options. For example:

osd /hcenter /vcenter /n Your text here

OSD will strip leading whitespace in *text*. If you want to display the leading whitespace in your *text*, you will need to enclose it in single back quotes.

3.13.82 PATH

Purpose: Display or alter the list of directories that TCC will search for executable files, batch files,

and files with executable extensions that are not in the current directory.

Format: PATH [directory [;directory...]]

directory The full name of a directory to include in the path setting.

See also: ESET 222 and SET 319 (the PATH command is syntactically equivalent to SET PATH).

Usage:

When **TCC** is asked to execute an external command (a .COM, .EXE, .BTM, .BAT, or .CMD file, or an executable extension), it first looks for the file in the current directory. If it fails to find an executable file in the current directory, it will search each of the directories specified in the PATH setting.

TCC first searches the current directory, then the **WINDOWS\SYSTEM32** directory followed by the **\WINDOWS** directory before any directories listed in your search path. (The actual directory names may be different on your system. The command processor will determine the correct names for the "Windows" and "Windows System" directories.) These search procedures conform to the default search sequences used by Windows.

For example, after the following PATH command, **TCC** will search for an executable file in six directories: the current directory, the two Windows directories, the root directory on drive C, then the *BIN* subdirectory on C, and then the *UTIL* subdirectory on C:

```
path c:\;c:\bin;c:\util
```

The list of *directories* to search is stored as an environment string, and can also be set or viewed with SET [319], and edited with ESET [222].

The PATHEXT 369 environment variable, and the related PathExt 47 configuration option, can be used to select the extensions to look for when searching the PATH for an executable file.

If you enter PATH with no parameters, the current path is displayed:

```
[c:\] path
PATH=C:\;C:\BIN;C:\UTIL
```

Entering PATH and a semicolon clears the search path so that only the current directory is searched for executable files. Some applications also use the PATH to search for their files.

If you include an explicit file extension on a command name (for example, WP.EXE), the search will find files with that name and extension in the current directory and every directory in the path. It will not locate other executable files with the same base name (i.e., WP.COM).

If you have an entry in the path which consists of a single period [.], the current directory will not be searched first, but instead will be searched when *TCC* reaches the "." in the path. This allows you to delay the search of the current directory for executable files and files with executable extensions. In rare cases, this feature may not be compatible with applications which use the path to find their files; if you experience a problem, you will have to remove the "." from the path while using any such application.

If you specify an invalid directory in the path, it will be skipped and the search will continue with the next directory in the path.

3.13.83 PAUSE

Purpose: Suspend batch file or alias execution.

Format: PAUSE [text]

text The message to be displayed as a user prompt.

Usage:

A PAUSE command will suspend execution of a batch file or alias, giving you the opportunity to change disks, turn on the printer, etc.

PAUSE waits for any key to be pressed and then continues execution. You can specify the *text* that PAUSE displays while it waits for a keystroke, or let it use the default message:

```
Press any key when ready...
```

For example, the following batch file fragment prompts the user before erasing files:

```
pause Press Ctrl-C to abort, any other key to erase all .LST files erase *.lst
```

If you press **Ctrl-C** or **Ctrl-Break** while PAUSE is waiting for a key, execution of an alias will be terminated, and execution of a batch file will be suspended while you are asked whether to cancel the batch job. In a batch file, you can handle **Ctrl-C** and **Ctrl-Break** yourself with the <u>ON BREAK 2821</u> command.

3.13.84 PDIR

Purpose: Display information about files and subdirectories in user-definable fields. It is a "

programmable DIR" command.

Format: PDIR [ranges] [/A:[attrlist] /D /H /I"text" /K /M /N[dej] /O[[:][order] /P /S[n] /T:t /(...)] [file...]

attrlist Selection attributes (see attribute switches 6 for details)

order Hierarchical list of sort keys

ranges One or more date, description, exclusion, size, time ranges

file One or more files to list

t Timestamp type selection code

/A 290: Attribute select /N 290 Disable options /D 290 colorize /O 291 Order

/H 290 do not Hide . and .. /P 291 Page pause description range /S 291 Subdirectories

"text"

/K 290 show header /T 291 Timestamp type

/M 290 show footer /(...) output fields and format

See also: DIR 1981, ATTRIB 1631, DESCRIBE 1951, and SELECT 3121.

File Selection

Supports <u>attribute switches</u> (extended <u>wildcards</u> (77), <u>ranges</u> (80), <u>multiple file names</u> (87), and <u>include</u> (1sts) (88).

Internet

Can be used with FTP/HTTP Servers 3.

Usage

PDIR is an extremely flexible command allowing you to display information about files and directories from one or more local or remote volume or directories in a wide array of user-defined formats. For a simpler version, see the DIR [198] command.

PDIR and DIR 1981 are related, but they do not have identical switches and they are not intended to produce identical output. PDIR is primarily intended to produce output that will be subsequently parsed by another program (or batch file), or (more rarely) for a special-purpose directory display. Its options and output are geared towards those applications.

The various PDIR displays are controlled through options or switches. The best way to learn how to use the many options available with the PDIR command is to experiment. You will soon know which options you want to use regularly. You can then select those options permanently by using the ALIAS command.

The /(...) option specifies which fields you want to display and how to format them. (You can have multiple /(...) options on a line.) The syntax is:

- a Attributes
- c Compression: Display the compression percentage on NTFS drives with compression enabled.
- **d[...]** Date (you must specify at least one subfield, otherwise the field remains blank)
 - d day (2 digits, leading zero)
 - m month (2 digits, leading zero)
 - y year (4 digits)
- f[...] File or Directory name (case sensitive)
 - P SFN path
 - p LFN path
 - N SFN filename
 - n LFN filename (default)
- i Description
- m MD5 hash value (see the @MD5 450) function)
- **q** File or directory owner (NTFS only)
- r CRC32 hash value (see the @CRC32 [413] function)
- s stream names (NTFS only)
- sp path and stream names as pathname+filename+streamname (NTFS only)
- t[...] Time (you must specify at least one subfield, otherwise the field remains blank)
 - h hours (2 digits, leading zero)
 - m minutes (2 digits, leading zero)
 - **s** seconds (2 digits, leading zero)
 - **d** milliseconds (decimal separator and 3 digits)
- z[...] Size
 - a allocated size (this will usually be more than the physical size unless

the file is compressed.)

the size will be formatted using the thousands separator (default is a

comma)

k|K|m|M|g|G|t|T

(case sensitive) format as kilobytes, megabytes, gigabytes, or terabytes, as used in variable functions (see Memory Size / Disk Space / File Size Units and Report Format (395)). Note that the size will be truncated, not rounded.

@function[*]

call the specified variable function set (internal or user-defined). To specify the current filename, use * as the parameter. For example, pdir /(f @md5[*]) displays the filename and the MD5 hash. Note that the % prefix of the function name is NOT used with the symbolic * parameter. If the parameter of the function is not the symbolic * or it is an "inner" function the % prefix must be doubled, e.g.,

@function1[%%@function2[*1]

"..." Literal string (in quotes). Characters are displayed as is, except that escape characters are converted.

You can also specify a format, independently for each field, by prefixing the field character with its format specification:

where

- specifies left justification instead of the default, right justification;
- i specifies the minimum field width, and
- a specifies the maximum field width.

If the first digit of *i* is **0**, the filed will be padded with zeros instead of spaces.

Example

To display the CRC, the full LFN and the owner of each file:

Options

Options on the command line apply only to the filenames which follow the option, and options at the end of the line apply to the preceding filename only. This allows you to specify different options for different groups of files, yet retains compatibility with the traditional DIR sommand when a single filename is specified.

Most options are used to select the desired files/directories. (This is in contrast to the $\overline{\text{DIR}}$ $\overline{\text{Igs}}$ command.) The special option $\underline{\text{Igs}}$ is used to specify which characteristics of the selected files or directories should be displayed in which sequence and format.

- /A:... Display only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:..
- /D Colorize the directory listing. See DIR 198 for more information on directory colorization.
- **/H** Show the "." and ".." directory names (normally suppressed).
- /I"text" Select filenames by matching text in their descriptions. See Description Ranges of for details.
- **/K** Show the header (disk and directory name) display.
- /M Show the footer (file and byte count totals) display.
- /N Turn off the specified options.

- **d** Skip hidden directories (when used with /S)
- e Don't display errors
- **j** Skip junctions (when used with /S)
- **/O**... The sorting order is applied to the listings of each subdirectory separately. Any combination of the sorting options may be used. If multiple options are specified, the listing will be sorted with the first sort option as the primary key, the next as the secondary key, and so on.
 - n Sort by filename and extension (default). If e is also specified, sort by name only.
 - Reverse the sort order for the next option
 - **a** Sort names and extensions in standard ASCII order, rather than sorting numerically when digits are included in the name or extension.
 - **c** Sort by compression ratio (the least compressed file in the list will be displayed first).
 - **d** Sort by date and time (oldest first); also see /T:acw
 - e Sort by extension
 - g Group subdirectories first, then files
 - i Sort by file description (ignored if /C or /O:c is also used).
 - Sort by owner
 - r Reverse the sort order for all options
 - s Sort by size
 - **u** Unsorted
- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102.
- /S Display file information from the current directory and all of its accessible subdirectories.

If you specify a number after the /S, PDIR will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

/T:type Specifies which single one of the date and time fields below, available on a drive which supports long filenames, should be displayed and used for sorting:

- a Last access date and time (NTFS volumes).
- c Creation date and time.
- w Last write date and time (default).

If /T is not specified, the default is /T:w.

If you append a **u** after the field, DIR will display the file time in UTC.

Note: If more than one time type is specified, the first one specified is used, and all subsequent ones ignored.

Use this option to define the various fields and display formats you wish to use for each selected entry. The fields may be in any order, and may be repeated. If this option is not used, the output format is identical to that of the DIR [198] command.

3.13.85 PLAYAVI

Purpose: Play Windows .AVI (video clip) files.

Format: PLAYAVI [/A /C /S /Vn] filename

filename The file to play

/A(synchronous) 292) /S(ynchronous) 292) /C(enter) 292) /V(olume) 292)

Usage:

PLAYAVI "plays" an .AVI or Windows video clip file.

Note: This command relies on the capabilities of your Windows configurations, including access to the proper codec. See your Windows documentation for details.

By default, PLAYAVI operates in synchronous mode, which means *TCC* waits for the .AVI file to complete and its window to close before continuing with the next command in a batch file or alias, or prompting you for a new command. You can change this default behavior with the /A option.

Options:

- Plays the .AVI file in asynchronous mode. Control returns to the **TCC** prompt immediately for a new command or to execute the next command in the current batch file or alias.
- **/C** Displays the AVI viewer in the middle of the screen. Without this option, the viewer appears in the upper-left corner of the screen.
- /S Plays the .AVI file in synchronous mode (this is the default). *TCC* pauses until the file has finished playing and its window closes.
- **/V** Sets the volume level. The range is 0 (silent) to 100.

3.13.86 PLAYSOUND

Purpose: Play MP3, .WAV, Midi, and other sound files.

Format: PLAYSOUND [/A /M /S /U /Vn] filename

filename The file to play

/A(synchronous) 293 /U(n mute) 293 /V(volume) 293 /S(vnchronous) 293

Usage:

PLAYSOUND "plays" MP3, .WAV, Midi and other types of sound files for which Windows has an appropriate codec installed. It determines the file type automatically from its contents, not its file extension, so it can play sound files which have an unknown file extension.

By default, PLAYSOUND operates in synchronous mode, which means *TCC* waits for the sound file to complete and its window to close before continuing with the next command in a batch file or alias, or prompting you for a new command. You can change this default behavior with the /A 2931 switch, described below.

You can cancel the playing of a synchronous sound file by pressing Ctrl-Break while it is playing.

Options:

/A Plays the sound file in asynchronous mode. Control returns to the *TCC* prompt immediately for a new command or to execute the next command in the current batch file or alias.

/M Mute the volume.

/S Plays the sound file in synchronous mode (this is the default). **TCC** pauses until the file has finished playing and its window closes.

/U Unmute (restore the previous volume level).

N Sets the volume level. The range is 0 (silent) to 100.

3.13.87 PLUGIN

Purpose: Load, unload, or display current plugins

Format: PLUGIN [/B /I plugin /L plugin /P /U plugin]

/B (full pathname) [293] /P(ause) [293] /U(nload) [293] /U(nload) [293]

Usage:

Plugins allow you to write your own internal variables, variable functions, and internal commands, put them in a DLL, and have *TCC* load them at startup. Plugin names will override existing names, so you can extend and/or replace internal variables and commands. When *TCC* starts, it will automatically load any plugins in the default directory (the subdirectory PLUGINS\ in the *TCC* installation directory). The plugins will be loaded before the startup file (TCSTART 22) are executed.

You can also write keystroke plugins that will be called for every keystroke entered at the command line. A keystroke plugin can perform actions when a specific key is entered, or even change the key before passing it back to the command processor.

If no options are specified, PLUGIN will display the currently loaded plugins and their internal variables, variable functions, and commands.

See the Plugin SDK for more information on developing plugins.

Options:

- **/B** Display the full pathnames of the plugins.
- Display information about the specified plugin, including the name, author, author's email and web addresses, description, function list, version and build numbers. The // option supports wildcards.
- Loads the specified plugin. If the filename is *, load all plugins from the default directory (the subdirectory PLUGINS\ in the *TCC* installation directory).
- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102.
- /U Unloads the specified plugin. If the filename is *, unloads all plugins.

3.13.88 POPD

Purpose: Return to the disk drive and directory at the top of the directory stack..

Format: POPD [/X * n]

n The number of directories to pop

/X (exclude) 294

See also: DIRS 2091, PUSHD 2991, @DIRSTACK 4161 and Directory Navigation 711.

Usage:

Each time you use the PUSHD [299] command, it saves the current disk drive and directory on the internal directory stack. POPD restores the most recently saved drive and directory and removes that entry from the stack. You can use these commands together to change directories, perform some work, and return to the starting drive and directory.

Directory changes made with POPD are recorded in the directory history list and can be displayed in the <u>directory history window [118]</u>. Read the section on <u>Directory Navigation [71]</u> for complete details on this and other directory navigation features.

This example saves and changes the current disk drive and directory with PUSHD [299], and then restores it. The current directory is shown in the prompt:

```
[c:\] pushd d:\database\test
[d:\database\test] pushd c:\wordp\memos
[c:\wordp\memos] pushd a:\123
[a:\123] popd
[c:\wordp\memos] popd
[d:\database\test] popd
[c:\]
```

You can use the DIRS command to see the complete list of saved drives and directories (the directory stack).

The POPD command followed by an asterisk [*] clears the directory stack without changing the current drive and directory.

If the directory on the top of the stack is not on the current drive, POPD will switch to the drive and directory on the top of the stack without changing the default directory on the current drive.

Options:

/X Don't save the current directory to the Directory History list.

3.13.89 POSTMSG

Purpose: Post a message to a window

Format: POSTMSG "title" msg wparam lparam

titleThe window titlemsgThe message to sendwParamwParam integerIParamIParam integer value

Usage:

POSTMSG allows you to send a Windows message to any window with a caption.

The *title* may contain wildcards, and POSTMSG will send the message to the first window with a matching title.

See the Windows SDK documentation for a list of possible messages and their parameters.

3.13.90 PRINT

Purpose: Print the specified file(s) using the application associated with each file's extension.

Format: PRINT [/A printer /D printer] filename ...

/A(dd) printer 295 /D(elete) printer 295

Usage:

Except for plain text files, Windows files cannot be printed without sending them to an associated application for interpretation and formatting. Using the extension for each file you want to print, PRINT determines if a Print action has been defined for that file type. If so, it executes the Print action and sends the file to the application for processing.

For example, if you use the command

```
print myletter.doc
```

PRINT looks up the Print command for .DOC files in the registry and, on most computers, will find that it is associated either with WordPad or Word. It will execute the associated program and send it the file along with the necessary command to print the file and then quit.

If PRINT cannot find a Print command for a file, it displays an error message. If there are additional files in the list you gave it to print, it will go on to the next file in the list.

PRINT depends on proper Windows File Associations settings in the registry and proper behavior of the program associated with each file type in order to print the file. If the registry entries or the application associated with a particular file type are not configured correctly, PRINT may not work as expected.

Options:

A Add a connection for the specified printer.

/D Remove the connection to the specified printer.

3.13.91 PRIORITY

Purpose: Display or set process priority, or suspend or resume a process.

Format: PRIORITY [/Q /R /S PID | "title" ABOVE | BELOW | NORMAL | HIGH | IDLE | REALTIME]

ABOVE Above normal priority
BELOW Below normal priority
NORMAL Normal (default) priority

HIGH High priority

IDLE Idle priority (only executes when no higher priority task is scheduled)

REALTIME Realtime priority



/S(uspend) 296

Usage:

You can specify the process either by the PID or by the window title. If you don't specify either a PID or title, PRIORITY will adjust the priority of the current *TCC* process.

If you do not enter any arguments, PRIORITY displays all of the active processes, their current priority, the module names, and the window titles (if any).

Options:

/Q Don't display any suspend / resume messages.

/R Resume the process

/S Suspend the process

3.13.92 PROCESSMONITOR

Purpose: Monitor process start or end

Format: PROCESSMONITOR [/C [name]]

PROCESSMONITOR name STARTED | ENDED n command

namennFull pathname of the process to monitorNumber of repetitions (or FOREVER)

command Command to execute when condition is triggered

/C(lear) 297

Usage:

The process name can include wildcards.

The command line will be parsed and expanded before PROCESSMONITOR is executed, so if you want to pass redirection characters or variables to *command* you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

If you don't enter any arguments, PROCESSMONITOR will display the processes it is currently monitoring.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use START or DETACH of in *command* to avoid conflicts.

PROCESSMONITOR creates three environment variables when a process is STARTED that can be queried by *command*. The variables are deleted after *command* is executed.

_processname The name of the process that was started

_processpid The PID of the process

_processcount The number of times the command has been triggered

For example, if you want to be alerted whenever "myapp" exits:

processmonitor myapp ended forever sendmail bob@abc.com Myapp Myapp just shut down!

Options:

If **name** is specified, remove the monitor for that process name. Otherwise, remove all active process monitors.

3.13.93 PROMPT

Purpose: Change the command line prompt.

Format: PROMPT [text]

text Text to be used as the new command line prompt.

See also: ESET 222 and SET 319 (the PROMPT command is syntactically equivalent to SET PROMPT).

Usage:

You can change and customize the command line prompt at any time. The prompt can include normal text and system information such as the current drive and directory, the time and date, and the amount of memory available. You can create an informal "Hello, Bob!" prompt or a complex prompt full of impressive information.

The prompt *text* can contain special commands in the form \$?, where ? is one of the characters listed below. Unless otherwise specified, those meta characters are case-independent.

- a The ampersand character[&].
- **b** The vertical bar character [].
- **c** The open parenthesis [()].
- d Current date, in the format: Fri 12-28-07 (the month, day, and year are formatted according to your current country settings)
- D Current date, in the format: Fri Dec 28, 2007
- e The ASCII ESC character (decimal 27), necessary for ANSI 10th commands.
- f The close parenthesis [)].
- **q** The > character.
- **h** Backspace over the previous character.
- j Current date in ISO 9601 format (yyyy-mm-dd).
- I The < character.</p>
- **m** Time in hours and minutes using 24-hour format.
- **M** Time in hours and minutes using the default country format.
- n Current drive letter.
- **p** Current drive and directory (lower case).
- P Current drive and directory (upper case on drives which do not support long filenames; directory names shown in mixed case as stored on the disk on LFN drives).
- **q** The = character.
- **r** The numeric exit code of the last external command.
- **s** The space character.
- t Current 24-hour time, in the format hh:mm:ss.
- T Current 12-hour time, in the format hh:mm:ss[a]p).
- **u** The current user.
- v Windows version number, in the format **6.0**.

- W Current directory, in a shortened format. If the current directory is the root or a first-level subdirectory, it is displayed as-is. If it is second level or deeper, the path is truncated (i.e., "c:\...\config"). (This does not work with UNC names.) \$W and \$w behave like \$P and \$p for displaying upper/lower case.
- **xd:** Current directory on drive **d:** in lower case, including the drive letter (uses the actual case of the directory name as stored on the disk for LFN drives.)
- **Xd:** Current directory on drive **d:** in upper case, including the drive letter.
- **z** Current shell nesting level.
- + Display one + character for each directory on the PUSHD [299] directory stack.
- **\$** The **\$** character.
- CR/LF (go to beginning of a new line).

For example, to set the prompt to the current date and time, with a ">" at the end:

```
[c:\] prompt $d $t $g
Thu Sep 30, 2004 10:29:19 >
```

The **TCC** prompt can be set in <u>TCSTART</u> 22 or in any batch file that runs when **TCC** starts.

If you enter PROMPT with no parameters, the prompt will be reset to its default value.

You can include literal text and special characters as well as the value of any environment variable, internal variable (372), or variable function (395) in a prompt. For example, if you want to include the size of the largest free memory block in the command prompt, plus the current drive and directory, you could use this command:

```
[c:\] prompt [(%%@dosmem[K]K) $p]
[(31043K) c:\data]
```

Notice that the @DOSMEM function is shown with two leading percent signs [%]. If you used only one percent sign, the @DOSMEM function would be expanded at once when the PROMPT command was executed, instead of every time the prompt is displayed. As a result, the amount of memory would never change from the value it had when you entered the PROMPT command. You can also use *back quotes* to delay expanding the variable function until the prompt is displayed:

```
prompt `[(%@dosmem[K]K) $p]`
```

You can use this feature along with the <u>@EXEC [424]</u> variable function to create a complex prompt which not only displays information but executes commands. For example, to execute an alias which checks battery status each time the prompt is displayed (enter the alias on one line):

```
alias cbatt `if %_apmlife lt 30 beep 440 4 880 4 440 4 880 4` prompt `%@exec[@cbatt]$p$g`
```

You can include ANSI Total escape sequences in the PROMPT by using the built-in ANSI X3.64 support in **TCC**. This example uses ANSI X3.64 sequences to set a prompt that displays the shell level, date, time and path in color on the top line of the screen (enter the command as one line):

```
prompt e[s=[1;1f]=[41;1;37m]=[K[$z] $d Time: t$h$h$h Path: p[u]=[0;32m]n$g
```

You may find it helpful to define a different prompt in secondary shells, perhaps including \$z in the prompt to display the shell level. To do so, place a PROMPT command in your TCSTART 22 file and use IF, IFF, or SWITCH statements to set the appropriate prompt for different shells.

3.13.94 PUSHD

Purpose: Save the current disk drive and directory, optionally changing to a new drive and directory.

Format: PUSHD [/X path]

path The name of the new default drive and directory.

/X (exclude) 299

See also: DIRS [209], POPD [294], @DIRSTACK [416] and Directory Navigation [71].

Usage:

PUSHD saves the current drive and directory to a "last in, first out" directory stack. The POPD 294 command returns to the last drive and directory that was saved by PUSHD. You can use these commands together to change directories, perform some work, and return to the starting drive and directory. The DIRS 209 command displays the contents of the directory stack.

To save the current drive and directory, without changing directories, use the PUSHD command by itself, with no *path*.

If a *path* is specified as part of the PUSHD command, the current drive and directory are saved and PUSHD changes to the specified drive and directory. If the *path* includes a drive letter, PUSHD changes to the specified directory on the new drive without changing the current directory on the original drive.

This example saves the current directory and changes to C:\WORDP\MEMOS, then returns to the original directory:

```
[c:\] pushd \wordp\memos
[c:\wordp\memos] popd
[c:\]
```

When you use PUSHD to change to a directory on an LFN drive, you must quote the *path* name if it contains white space or special characters.

PUSHD can also change to a network drive and directory specified with a UNC name (see <u>File Systems</u> 49th for details).

If PUSHD cannot change to the directory you have specified it will attempt to search the <u>CDPATH</u> 72 and the <u>extended directory search</u> 3 database. You can also use <u>wildcards</u> 77 in the **path** to force an extended directory search. Read the section on <u>Directory Navigation</u> 71 for complete details on these and other directory navigation features.

Directory changes made with PUSHD are also recorded in the directory history list and can be displayed in the <u>directory history window</u> 118.

The directory stack can hold up to 2047 characters, or about 100 typical entries (depending on the length of the names). If you exceed this limit, the oldest entry is removed before adding a new entry.

Options:

/X Don't save the current directory to the Directory History list.

3.13.95 QUERYBOX

Purpose: Pops up a dialog box to get an input string from the user and save it in an environment

variable.

Format: QUERYBOX [/D /E /Ln /P /POS=top,left /Tn] ["title"] prompt %%varname

title Text for the title bar of the dialog box.prompt Text that will appear inside the dialog box.varname Variable name where the input will be saved.

/D(igits only) | 300 | /P(assword) | 300 | /E(dit existing value) | 300 | /POS (ition) | 300 | /T(imeout) |

See also: INKEY 257, INPUT 259, and MSGBOX 279.

Usage:

QUERYBOX displays a dialog box with a prompt, an optional title, and a string input field. Then it waits for your entry, and places any characters you type into an environment variable. QUERYBOX is normally used in batch files and aliases to get text input.

QUERYBOX is similar to INPUT, except it appears as a popup dialog box. If you prefer to work within the command line window, see the INKEY and INPUT commands.

Standard command line editing keys may be used to edit the input string as it is entered. All characters entered up to, but not including, the carriage return are stored in the variable.

For example, to prompt for a string and store it in the variable NAME:

```
querybox "File Name" Enter a name: %%name
```

If you press **Ctrl-C** or **Ctrl-Break** while QUERYBOX is waiting for input, execution of an alias will be terminated, and execution of a batch file will be suspended while you are asked whether to cancel the batch job. A batch file can handle **Ctrl-C** and **Ctrl-Break** itself with **ON BREAK** [282].

QUERYBOX returns a value of zero in the internal variable %_? 380 after a successful operation, and a non-zero value otherwise (timeout, cancel, etc.). Be sure to save the return value in another variable or test it immediately; because the value of %_? changes with every internal command.

Options:

/D Only accepts numeric values.

/E Allows you to edit an existing value. If there is no existing value for **varname**, QUERYBOX allows you to enter a new value.

/Ln Sets the maximum number of characters which QUERYBOX will accept to n.

/P Tells QUERYBOX to echo asterisks, instead of the characters you type.

/POS Sets the dialog position. (If you don't specify a position, QUERYBOX will center the dialog in the *TCC* window.

/Tn Wait for a maximum of *n* seconds for a response.

3.13.96 QUIT

Purpose: Terminate the current batch file.

Format: QUIT [value]

value The numeric exit code to return to TCC or to the previous batch file.

See also: CANCEL 176 and EXIT 227.

Usage:

QUIT provides a simple way to exit a batch file before reaching the end of the file. If you QUIT a batch file called from another batch file, you will be returned to the previous file at the line following the original CALL.

This example batch file fragment checks to see if the user entered "quit" and exits if true.

```
input Enter your choice : %%option
if "%option" == "quit" quit
```

QUIT only ends the current batch file. To end all batch file processing, use the CANCEL [176] command.

If you specify a *value*, QUIT will set the ERRORLEVEL (395) or exit code to that value. For information on exit codes see the IF (253) command, and the %? (396) variable. Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

You can also use QUIT to terminate an alias. If you QUIT an alias while inside a batch file, QUIT will end both the alias and the batch file and return you to the command prompt or to the calling batch file.

3.13.97 RD / RMDIR

Purpose: Remove one or more subdirectories.

Format: RD [/I"text" /K /N[et] /Q /R /S] [@file] path...

or

@file

RMDIR [/I"text" /K /N[et] /Q /R /S] [@file] path...

path The name of one or more subdirectories to remove.

A text file containing the names of the directories to remove, one per line (see

@file lists 90 for details).

/I (match descriptions) | 302 | /Q(uiet) | 302 | /K (no Recycle Bin) | 302 | /R(ecycle bin) | 302 | /S(ubdirectories) | 302 |

See also: MD 271.

File Selection

Internet: Can be used with FTP Servers 3.

Usage:

RD and RMDIR are synonyms. You can use either one.

RD removes directories from the directory tree. For example, to remove the subdirectory MEMOS from the subdirectory *WP*:

```
rd \wp\memos
```

Before using RD, you must delete all files and subdirectories (and their files) in the *path* you want to remove. Remember to remove hidden and read-only files as well as normal files (you can use DEL /Z 190) to delete hidden and read-only files).

You can use wildcards in the path.

When removing a directory on an LFN drive, you must quote any *path* which contains white space or special characters.

If RD deletes one or more directories, they will be deleted from the extended directory search database.

You cannot remove the root directory, the current directory (.), any directory above the current directory in the directory tree, or any directory in use by another process. RD will delete hidden directories, for compatibility with **CMD.EXE**.

You can remove directories on FTP servers 3. For example:

```
rd ftp://ftp.abc.com/data
```

Options:

- /I"text" Select directories by matching text in their descriptions. The text can include wildcards mad extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]". Do not use /I with @file lists. See @file lists 90 for details.
- When used with the **/S** option, this will physically delete files instead of sending them to the Windows Recycle Bin, even if you have the Delete to Recycle Bin 4 configuration option set.
- **/N** This option takes two possible arguments:
 - e Don't display errors.
 - t Don't update the CD / CDD extended directory search (JPSTREE.IDX).
- /Q When used with the /S option, this will suppress the prompt before deleting the directories.
- /R When used with the /S option, this will send the deleted files to the Windows Recycle Bin.
- This option is included only for compatibility with CMD.EXE, and should be used with EXTREME CARE!! It deletes all files (including hidden and system files) in the named directory and all of its subdirectories, then removes all subdirectories. It can potentially erase all files on a drive with a single command. You cannot use wildcards with the /S option.

Note: Do not use /S with @file lists.

3.13.98 REBOOT

Purpose: Reboot the computer, log off Windows, or shut down.

Format: REBOOT [/H /K /L /M[0|1] /P /R /S /V /W]

 /H(ibernate 303)
 /R(eboot) 303

 /K (lock) 303)
 /S(hutdown) 303

 /L(ogoff) 303)
 /V(erify) 303

 /M(onitor) 303
 /W (standby) 303

 /P(ower off) 303)

Usage:

REBOOT will log off or shut down the operating system, or completely restart your computer. It normally performs a warm reboot, or a a shutdown and restart under Windows.

REBOOT defaults to performing a warm boot, with no prompting. The following example prompts you to verify the reboot, then does a warm boot:

```
reboot /v
```

TCC issues the standard commands to shut down other applications and the Windows before rebooting. Windows may prompt you for additional actions, or even ignore the request altogether depending on which processes are running.

Options:

- **/H** Save everything in memory to your hard disk, and shutdown to save power. The desktop is restored to its original state when the computer is restarted.
- **/K** Lock the workstation. To unlock, the user must log in.
- **L** Log off Windows, but do not reboot. This option is equivalent to selecting Shutdown from the Start menu, then selecting "Close all programs and log on as a different user" in the shutdown dialog.
- /M Switch the display to low power (M0) or shut off the display (M1 -- will not work on all systems). This option will not reboot the computer unless you also include /R.
- **/P** Log off Windows and turn off the computer.
- /R Reboots the system. This is the default, but is required if you specify /M0 or /M1 and also want to reboot.
- Shut down the system, but do not reboot. This is equivalent to selecting Shutdown from the Start menu, then selecting "Shut down the computer" in the shutdown dialog.
- /V Prompt for confirmation (Y or N) before acting.
- **/W** Save power by turning off the monitor and hard disks. When the computer comes out of standby, the desktop is restored to its original state.

3.13.99 RECYCLE

Purpose: Delete files in the recycle bin or display the recycle bin status.

Format: RECYCLE [/D /E /Q /P] [drives ...]

drives Local fixed and removable (non CD-ROM / DVD) drives

 $\frac{D(\text{elete})}{E \text{ (no error messages)}} \sqrt{\frac{P(\text{rompt})}{Q(\text{uiet})}} \sqrt{\frac{Q(\text{uiet})}{Q(\text{uiet})}}$

Usage:

If you don't specify any drives (or paths), RECYCLE will delete (or display) everything in the recycle bin for all local drives.

Options:

/D Empty the recycle bin for the specified drive(s).

/E Suppress all non-fatal error messages, such as "File Not Found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files.

/P Prompt the user to confirm each delete operation.

/Q Don't display the name of the recycle bin(s). This option is most often used in batch files.

3.13.10(REM

Purpose: Put a comment in a batch file.

Format: REM [comment]

comment The text to include in the batch file.

Usage:

The REM command lets you place a remark or comment in a batch file. Batch file comments are useful for documenting the purpose of a batch file and the procedures you have used. For example:

```
rem This batch file provides a
rem menu-based system for accessing
rem word processing utilities.
rem
rem Clear the screen and get selection
cls
```

REM must be followed by a space or tab character, then the comment. Comments can be up to 8,191 characters long. *TCC* will ignore everything on the line following the REM, including quotes, redirection symbols, and other commands (see below for the exception to this rule).

If ECHO is ON, the comment is displayed. Otherwise, it is ignored. If ECHO is ON and you don't want to display the line, preface the REM command with an at sign [@].

You can also place a comment in a batch file by starting the comment line with two colons [::]. In essence this creates a batch file "label" without a valid label name.

You can use REM to create a zero-byte file if you use a redirection symbol immediately after the REM command. For example, to create the zero-byte file *C:\xyz*:

```
rem>xyz
```

(This capability is included for compatibility with and CMD.EXE. A simpler method for creating a zero-byte file with *TCC* is to use **>filename** as a command, with no actual command before the [>] redirection character.)

3.13.10'REN / RENAME

Purpose: Rename files or subdirectories.

Format: REN [/A:[[-][+]rhsadecijopt] /B /E /I"text" /N[et] /P /Q /S /T] [@file] old_name... new_name

or

RENAME [/A:[[-][+]rhsadecijopt] /E /I"text" /N[et] /P /Q /S /T] [@file] old_name...

new_name

old_name Original name of the file(s) or subdirectory.

new_name New name to use, or new path on the same drive.

@file A text file containing the names of the source files to rename, one per

line (see @file lists 90 for details).

/A: (Attribute select) 307
/B (Rename on reboot) 307
/E (No error messages) 307
/Q(uiet) 307
/Q(uiet) 307

/I"text" (match description) 307 /S(ubdirectory) 307

/MD (Create target directory) 307 /T(otal) 307

See also: COPY 182 and MOVE 274.

File Selection:

Supports attribute switches 85, extended wildcards 77, ranges 80, multiple file names 87, delayed variable expansion 89, and include lists 88. Use wildcards with caution on LFN volumes; see LFN File Searches 89 for details.

Internet: Can be used with FTP/HTTP Servers 3 and HTTP/HTTPS servers.

Usage:

REN and RENAME are synonyms. You may use either one.

REN lets you change the name of a file or a subdirectory, or move one or more files to a new subdirectory on the same drive. (If you want to move files to a different drive, use MOVE.)

In its simplest form, you give REN the **old_name** of an existing file or subdirectory and then a **new_name**. The **new_name** must not already exist — you can't give two files the same name (unless they are in different directories). The first example renames the file **MEMO.TXT** to **MEM.TXT**. The second example changes the name of the **\text{WORD}** directory to \text{\text{WP}}:

```
rename memo.txt mem.txt
rename /s \word \wp
```

When you rename files or directories on an LFN drive, you must quote any names which contain white space or special characters.

You can also use REN to rename a group of files that you specify with wildcards, as multiple files, or in an include list. When you do, the **new_name** must use one or more wildcards to show what part of each filename to change. Both of the next two examples change the extensions of multiple files to .SAV:

```
ren config.nt autoexec.nt tcstart.btm *.sav
ren *.txt *.sav
```

REN can move files to a different subdirectory on the same drive. When it is used for this purpose, REN requires one or more filenames for the *old_name* and a directory name for the *new_name*:

```
ren memo.txt \wp\memos\
ren oct.dat nov.dat \data\save\
```

The final backslash in the last two examples is optional. If you use it, you force REN to recognize the last parameter as the name of a directory, not a file. The advantage of this approach is that if you accidentally mistype the directory name, REN will report an error instead of renaming your files in a way that you didn't intend.

REN can also move files to a new directory and change their name at the same time if you specify both a path and file name for *new_name*. In this example, the files are renamed with an extension of .SAV as they are moved to a new directory:

```
ren *.dat \data\save\*.sav
```

If you use REN to rename a directory, the **new_name** must normally be specified explicitly, and cannot contain wildcards. You can override this restriction with **/S**. When you rename a directory the <u>extended</u> directory search additional directory directory search additional directory directory search additional directory di

You can also rename a subdirectory to a new location in the directory tree on the same physical drive (sometimes called "prune and graft"). You must specify the new name explicitly, not just give the path. For example, if the **D:\TCMD** directory contains a subdirectory **TEST**, you can rename TEST to be a subdirectory of the root directory like this:

```
[d:\tcmd] ren TEST \TEST\
```

REN does not change a file's attributes, except to set attribute **A**. The **new_name** file(s) will have the same attributes as **old_name**.

If you have appropriate permissions, you can rename files on FTP, HTTP, and HTTPS servers. For example:

```
ren ftp://ftp.abc.com/file1.txt file2.txt
```

Wildcard characters like [*] and [?] will be treated as wildcards in FTP URLs, but will be treated as normal characters in HTTP URLs.

You can also use the IFTP command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want. For more information, see <u>Using FTP/HTTP Servers</u> and IFTP 255.

Note: The wildcard expansion process will attempt to allow both CMD.EXE-style "extension" matching (assumes only one extension, at the end of the word) and the advanced *TCC* string matching (allowing things like *.*.abc) when an asterisk is encountered in the destination of a REN command.

Options:

Rename only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Do not use /A: with @file lists 90 See @file lists 90 for details.

- **/B** If REN can't rename the file (i.e., access denied), it will schedule it to be renamed at the next reboot.
- /E Suppress all non-fatal error messages, such as "File Not Found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files.
- /I"text" Select files by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]". Do not use /I with @file lists. See @file lists 90 for details.
- **/MD** Create the target directory if it doesn't exist. Note that you *must* either terminate the target directory name with a trailing \ or specify a filename component; otherwise REN cannot tell what you want for the directory and what you want for the filename.
- **/N** Do everything except actually rename the file(s). **/N** displays how many files would be renamed. This option is useful for testing what a REN command will actually do.

A /N with one of the following arguments has an alternate meaning:

- Don't display errors.
- t Don't update the CD / CDD extended directory search (JPSTREE.IDX).
- /P Prompt the user to confirm each rename operation. Your options at the prompt are explained in detail under Page and File Prompts 102.
- **/Q** Don't display filenames or the number of files renamed. When used in combination with the **/P** option above, it will prompt for filenames but will not display the totals. This option is most often used in batch files. See also **/T**.
- Normally, you can rename a subdirectory only if you do not use any wildcards in the **new_name**. This prevents subdirectories from being renamed inadvertently when a group of files is being renamed with wildcards. **/S** will let you rename a subdirectory even when you use wildcards. **/S** does not cause REN to process files in the current directory and all subdirectories as it does in some other file processing commands. To rename files throughout a directory tree, use GLOBAL AEN.
- Don't display filenames as they are renamed, but report the number of files renamed. See also /Q.

3.13.10; RETURN

Purpose: Return from a GOSUB (subroutine) in a batch file.

Format: RETURN [value]

value The numeric exit code to return to TCC

See also: GOSUB 247).

Usage:

TCC allows subroutines in batch files.

A subroutine begins with a label (a colon followed by one or more words) and ends with a RETURN command.

The subroutine is invoked with a GOSUB command from another part of the batch file. When a RETURN command is encountered the subroutine terminates, and execution of the batch file continues on the line following the original GOSUB. If RETURN is encountered without a GOSUB, **TCC** will display a "Missing GOSUB" error message.

You cannot execute a RETURN from inside a DO 210 loop.

The following batch file fragment calls a subroutine which displays the files in the current directory:

```
echo Calling a subroutine
gosub subr1
echo Returned from the subroutine
quit
:subr1
dir /a/w
return
```

If you specify a *value*, RETURN will set the internal exit code to that value. That exit code should be tested immediately upon return from the subroutine and before it is reset by another command. For information on exit codes from internal commands, see the ? 380 variable.

3.13.10@REXEC

Purpose: Remotely execute commands

Format: REXEC [/H host /U name /P password /Rn /Tn] host [/L userid] command ...

command The command to execute

/H(host name) 309 /R(emote port) 309 /L (user ID) 309 /T (firewall type) 309 /U(sername) 309 /U(sername) 309

Usage:

REXEC allows remote execution of commands on any system with the rexec service installed. Press Ctrl-C to disconnect from the other system.

If you don't specify a username, RSHELL will use the current username. You can provide a password on the command line by appending it to the username (i.e., "User:Password"). If you don't provide a password, REXEC will prompt for it.

If you want to do redirection on the remote system, enclose the argument list in double quotes. For example:

REXEC /H host /U user /P password "command | command2"

The double quotes will be removed before passing the commands to the remote system.

Note: Windows does not include the rshell service, so you will need to get one from a third-party and install it on the remote system before executing RSHELL.

Options:

/H Firewall host name

/L User name (ID)

/P Firewall user password

/R Remote port number

/T Firewall type, where **n** is:

0 No firewall (default setting)

1 Connect through a tunneling proxy

2 Connect through a SOCKS4 Proxy

3 Connect through a SOCKS5 Proxy

/U Firewall user name

3.13.104RSHELL

Purpose: Remotely execute commands

Format: RSHELL [/H host /U name /P password /Rn /Tn] host [/L userid] command ...

command The command to execute

 /H(ost name)
 /R(emote port)
 310

 /L (user ID)
 /T (firewall type)
 310

 /P(assword)
 310
 /U(sername)
 310

Usage:

RSHELL allows remote execution of commands on any system with the rshell service installed. Press Ctrl-C to disconnect from the other system.

If you don't specify a username, RSHELL will use the current username.

If you want to do redirection on the remote system, enclose the argument list in double quotes. For example:

RSHELL /H host /U user /P password "command | command2"

The double quotes will be removed before passing the commands to the remote system.

Note: Windows does not include the rshell service, so you will need to get one from a third-party and install it on the remote system before executing RSHELL.

Options:

/H Firewall host name

/L User name

- /P Firewall user password
- /R Remote port number
- /T Firewall type, where *n* is:
 - 0 No firewall (default setting)
 - 1 Connect through a tunneling proxy
 - 2 Connect through a SOCKS4 Proxy
 - 3 Connect through a SOCKS5 Proxy
- /U Firewall user name

3.13.10(SCREEN

Purpose: Position the cursor on the screen and optionally display a message.

Format: SCREEN row column [text]

row The new row location for the cursor **column** The new column location for the cursor

text Optional text to display at the new cursor location

See also: <u>ECHO and ECHOERR</u> 217, <u>ECHOS and ECHOSERR</u> 219, <u>SCRPUT</u> 311, <u>TEXT</u> 345, and VSCRPUT 360.

Usage:

SCREEN allows you to create attractive screen displays in batch files. SCRPUT allows you to specify where a message will appear on the screen. You can use SCREEN to create menus and other similar displays. For example, the following batch file fragment displays a menu:

```
@echo off
cls
screen 3 10 Select a number from 1 to 4:
screen 6 20 1 - Word Processing
screen 7 20 2 - Spreadsheet
screen 8 20 3 - Telecommunications
screen 9 20 4 - Quit
```

SCREEN does not change the screen colors. To display text in specific colors, use SCRPUT (311) or VSCRPUT (360). SCREEN always leaves the cursor at the end of the displayed text.

The **row** and **column** values are zero-based, so on a 25 line by 80 column display, valid **rows** are 0 - 24 and valid **columns** are 0 - 79. SCREEN checks for a valid **row** and **column**, and displays a "Usage" error message if either value is out of range.

In **TCC**, the maximum **row** value is determined by the current height of the **TCC** tab window, and the maximum **column** value is determined by the current virtual screen width (see Resizing the Take Command Window for more information).

You can also specify the **row** and **column** as offsets from the current cursor position. Begin the value with a plus sign [+] to move the cursor down or to the right, or with a minus sign [-] to move the cursor up or to the left. This example prints a string 3 lines above the current position, in absolute column 10:

```
screen -3 10 Hello, World!
```

you specify 999 for the *row*, SCREEN will center the text vertically on the display. If you specify 999 for the *column*, SCREEN will center the text horizontally. This example prints a message at the center of the *TCC* tab window:

```
screen 999 999 Hello, World
```

3.13.10(SCRIPT

Purpose: Run a script using an Active Scripting engine.

Format: SCRIPT [/E engine] [filename ...]

/E(ngine) 311

engine The name of the scripting engine

Usage:

If you don't specify any arguments, SCRIPT will display the installed engines.

See also the @SCRIPT 458 variable function.

TCC has a COM interface to allow the script to call back into TCC. The methods are:

shell.exec("command") - execute the specified command (internal or external)

shell.write("string") - write the string to stdout

shell.writeLn("string") - write the string to stdout with a CR/LF

shell.alert("text") - pop up a message box

Options:

/E If the script doesn't have a recognized extension (i.e., **.vbs**, **.pls**, etc.) you will need to specify the engine SCRIPT should use to execute the script.

3.13.107SCRPUT

Purpose: Position text on the screen and display it in color.

Format: SCRPUT row col [BRIght] fg ON [BRIght] bg text

row Starting rowcol Starting column

fg Foreground character color bg Background character color

text The text to display

See also: <u>ECHO and ECHOERR</u> 217, <u>ECHOS and ECHOSERR</u> 219, <u>SCREEN</u> 310, <u>TEXT</u> 345, and VSCRPUT 360.

Usage:

SCRPUT allows you to create attractive screen displays in batch files. SCRPUT allows you to specify where a message will appear on the screen and what colors will be used to display the message text. You can use SCRPUT to create menu displays, logos, etc.

SCRPUT works like SCREEN, but requires you to specify the display colors. See Colors and Color Names 518 for details.

The **row** and **column** values are zero-based, so on a 25 line by 80 column display, valid **rows** are 0 -24 and valid columns are 0 - 79. The maximum row value is determined by the current height of the TCC tab window. The maximum column value is determined by the current virtual screen width (see Resizing the Take Command Window 68 for more information).

SCRPUT checks for a valid row and column, and displays a "Usage" error message if either value is out of range.

You can also specify the **row** and **column** as offsets from the current cursor position. Begin the value with a plus sign [+] to move down the specified number of rows or to the right the specified number of columns, or with a minus sign [-] to move up or to the left.

If you specify 999 for the *row*, SCRPUT will center the text vertically in the *TCC* tab window. If you specify 999 for the *column*, SCRPUT will center the text horizontally.

SCRPUT does not move the cursor when it displays the *text*.

The following batch file fragment displays part of a menu, in color:

```
cls white on blue
scrput 3 10 bri whi on blu Select an option:
scrput 6 20 bri red on blu 1 - Word Processing
scrput 7 20 bri yel on blu 2 - Spreadsheet
scrput 8 20 bri gre on blu 3 - Communications
scrput 9 20 bri mag on blu 4 - Quit
```

3.13.10(SELECT

Purpose: Interactively select files for a command.

Format: SELECT [/1 /A[[:][-][+]rhsadecijopt] /C /D /E /H /I"text" /J /L /O[:][-]acdeginorsu /T:acw /X

/Z] [command] ... (files...)...

command The command to execute with the selected files.

The files from which to select. File names may be enclosed in either files

parentheses or square brackets. The difference is explained below.

```
/1 One selection only 315
                                     /J(ustify names) 315
/A(ttribute select) 315
                                     /L(ower case) 315
/C(ompression) 315
                                     /O(rder) 315
                                     /T(ime) 316
/D(isable color coding) 315
/E (use upper case) 315
                                     /X (display short names) 316
```

/H(ide dots) 315 /Z (FAT format) 316

/I"text" (match descriptions) 315

File Selection

Supports extended wildcards 777, ranges 801, multiple file names 871, and include lists 881. Ranges must appear immediately after the SELECT keyword.

Internet: Can be used with FTP servers. See Using FTP/HTTP Servers 93.

Usage:

SELECT allows you to select files for internal and external commands by using a "point and shoot" display. You can have SELECT execute a command once for each file you select, or have it create a list of files for a command to work with. The *command* can be an internal command, an alias, an external command, or a batch file.

If you use parentheses around the *files*, SELECT executes the *command* once for each file you have selected. During each execution, one of the selected files is passed to the *command* as a parameter. If you use square brackets around *files*, the SELECTed files are combined into a single list, separated by spaces. The command is then executed once with the entire list presented as part of its command line parameters.

SELECT can also select files on FTP servers. For example:

```
select del (ftp://ftp.domain.com/)
```

You can also use the IFTP command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want. For more information, see <u>Using</u> FTP/HTTP Servers and IFTP [255].

Using the SELECT File List

When you execute the SELECT command, the file list is displayed in a full-window format which includes a top-line status bar and shows the command to be executed, the number of files marked, and the number of Kbytes in those files.

SELECT supports the mouse for selecting and scrolling the list. You can also use the cursor up, cursor down, PgUp, and PgDn keys to scroll through the file list. You can also use character matching to find specific files, just as you can in any popup window while the file list is displayed you can enter any of the following keys to select or unselect files, display files, execute the command, or exit:

space	Select a file, or unselect a marked file
+	Select a file (all products), or unselect a marked file
-	Unselect a marked file
*	Reverse all of the current marks (except those on subdirectories). If no files have been marked you can use * to mark all of the files
1	Unselect all files
Ctrl-L	View the current highlighted file with LIST 264. When you exit from LIST, the SELECT screen will be restored
Enter	Execute the command with the marked files, or with the currently highlighted file if no files have been marked
Esc	Skip the files in the current display and go on to the next file specification inside the parentheses or brackets (if any)
Ctrl-C or Ctrl-Break	Cancel the current SELECT command entirely

On FAT drives the file list is shown in standard FAT directory format, with names at the left and descriptions at the right. On LFN drives the format is similar but more space is allowed for the name, and the description is not shown. In this format long names are truncated if they do not fit in the allowable space. For a short-name format (including descriptions) on long filename drives, use the /X and / or /Z switches.

When displaying descriptions in the short filename format, SELECT adds a right arrow at the end of

the line if the description is too long to fit on the screen. This symbol will alert you to the existence of additional description text. You can use the left and right arrow keys to scroll the description area of the screen horizontally and view the additional text.

Creating SELECT Commands

In the simplest form of SELECT, you merely specify the command and then the list of files from which you will make your selection(s). For example:

```
select copy (*.com *.exe) a:\
```

will let you select from among the .COM files on the current drive, and will then invoke the COPY command to copy each file you select to drive A:. After the .COM files are done, the operations will be repeated for the .EXE files.

If you want to select from a list of all the .COM and .EXE files mixed together, create an include list inside the parentheses by inserting a semicolon:

```
select copy (*.com;*.exe) a:\
```

Finally, if you want the SELECT command to send a single list of files to COPY, instead of invoking COPY once for each file you select, put the file names in square brackets instead of parentheses:

```
select copy [*.com;*.exe] a:\
```

If you use brackets, you have to be sure that the resulting command (the word COPY, the list of files, and the destination drive in this example) does not exceed the <u>command line length limit label.</u> The current line length is displayed by SELECT while you are marking files to help you to stay within that limit.

The parentheses or brackets enclosing the file name(s) can appear anywhere within the command; SELECT assumes that the first set of parentheses or brackets it finds is the one containing the list of files from which you wish to make your selection.

When you use SELECT on an LFN drive, you must quote any file names inside the parentheses which contain white space or special characters. For example, to copy selected files from the **Program Files** "directory to the **E:\SAVE** directory:

```
select copy ("Program Files\*") e:\save\
```

File names passed to the *command* will be quoted automatically if they contain white space or special characters.

The list of files from which you wish to select can be further refined by using date, time, size and file exclusion ranges on. The range(s) must be placed immediately after the word SELECT. If the command is an internal command that supports ranges, an independent range can also be used in the command itself.

You cannot use command grouping to make SELECT execute several commands, because SELECT will assume that the parentheses are marking the list of files from which to select, and will display an error message or give incorrect results if you try to use parentheses for command grouping instead. (You can use a SELECT command inside command grouping parentheses, you just can't use command grouping to specify a group of commands for SELECT to execute.)

Advanced Topics

If you don't specify a command, the selected filename(s) will become the command. For example, this

command defines an alias called UTILS that selects from the executable files in the directory C:\UTIL, and then executes them in the order marked:

```
alias utils select (c:\util\*.com;*.exe;*.btm;*.bat)
```

If you want to use <u>filename completion [113]</u> to enter the filenames inside the parentheses, type a space after the opening parenthesis. Otherwise the command line editor will treat the open parenthesis as the first character of the filename.

With the /I option, you can select files based on their descriptions. SELECT will display files if their description matches the text after the /I switch. The search is not case sensitive. You can use wildcards and extended wild cards as part of the text.

When sorting file names and extensions for the SELECT display, *TCC* normally assumes that sequences of digits should be sorted numerically (for example, the file DRAW2 would come before DRAW03 because 2 is numerically smaller than 03), rather than strictly alphabetically (where DRAW2 would come second because "2" comes after "0"). You can defeat this behavior and force a strict alphabetic sort with the *IO*:a option.

Options:

- /1 Only allow one selection.
- /A[:] Select only those files that have the specified attribute(s) set. See Attribute Switches 6 for information on the attributes which can follow /A:.
- Display per-file and total compression ratios on compressed drives. The compression ratio is displayed instead of the file description. The ratio is left blank for directories and files with a length of 0 bytes, and for files on non-compressed drives. The compression ratios will not be visible on LFN drives unless you use /Z to switch to the short filename format. Only compressed NTFS drives are supported. See DIR /C 1981 for more details on how compression ratios are calculated.
- **/D** Temporarily turn off directory colorization.
- /E Display filenames in upper case.
- **/H** Suppress the display of the "." and ".." directory names.
- /I"text" Display filenames by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]".
- /J Justify (align) filename extensions and display them in the FAT format.
- **/L** Display file and directory names in lower case.
- /O Set the sort order for the files. The order can be any combination of the following options:
 - n Sort by filename (this is the default)
 - Reverse the sort order for the next option.
 - **a** Sort names and extensions in standard ASCII order, rather than sorting numerically when digits are included in the name or extension.
 - **c** Sort by compression ratio (the least compressed file in the list will be

displayed first). For information on supported compression systems see /C above.

- **d** Sort by date and time (oldest first).
- e Sort by extension.
- **g** Group subdirectories together.
- i Sort by the file description (ignored if /C or /O:c is also used).
- o Sort by owner
- r Reverse the sort order for all options.
- **s** Sort by size.
- u Unsorted.

/T:acw Specify which of the date and time fields on an LFN drive should be displayed and used for sorting:

- **a** Last access date and time (access time is not saved on VFAT and FAT32 volumes).
- **c** Creation date and time.
- w Last write date and time (default).
- /X Display short filenames in FAT format (like /Z), on LFN drives.
- Display a directory on an LFN drive in the old-style format, with the filename at the left and the description at the right. Long names will be truncated to 12 characters; if the name is longer than 12 characters, it will be followed by a right arrow.

3.13.10(SENDMAIL

Purpose: Send an email message.

Format.

SENDMAIL [/A file1 [/A file2 ...] /D /Eaddress /H"header: value" /In /M /Pn /R /Sn /V] "address[,address...] [cc:address[,address] bcc:address[,address...]]" subject [text | @msgfile]

file1... The attachment files.

address 317 The destination email address.

subject | 317 | The subject line. text | 316 | The message to send.

msgfile 317 The file containing the message body.

/A 317 file Attachment /M 317 CRAM-MD5 authentication

Delivery Confirmation

Part of Part of Priority

Delivery Confirmation

/E 317 Reply-to address /R 318 Send read receipt

/H 317 Send custom header /Sn Sensitivity

/I 317 n Importance /V 316 Verbose

See also: SNPP 33 and SMPP 330.

Usage:

SENDMAIL sends an email message from *TCC* via SMTP. The text of the message can be entered either on the command line or read from a text file.

Before you can use SENDMAIL, you must either set the <u>SMTP</u> 53 configuration options, or have a default account in the registry. Depending on your system configuration, you may also need to start an

Internet connection before you use SENDMAIL.

A SENDMAIL message has three required parts: an <u>address</u> [317], a <u>subject</u> [317], and <u>message</u> [317]. Optionally it may also have attachments [317].

1. The address field contains one or more standard Internet email addresses:

```
sendmail abc@xyz.com ...
```

If **address** contains white space, the entire address field must be surrounded by quotes. You can specify multiple destinations by separating the addresses with **commas** and enclosing the entire string in quotes (all addresses will appear in the "*To:*" header sent to all recipients). You can add **cc** (**copy**) addresses by prefacing the desired target(s) with **cc:**; and **BCC** (**blind copy**) addresses by prefacing the desired target(s) with **bcc:**. For example:

```
sendmail "bob@bob.com bcc:joe@joe.com" Test Hello!
```

will send the text *Hello!* with subject *Test* to *bob@bob.com* with a blind copy to *joe@joe.com*.

- **2.** The **subject** will appear as the subject line in the message. If it contains white space, it must be surrounded by quotes.
- 3. The *message* may either be entered on the command line, or it may be placed in a text file. To tell SENDMAIL to send the contents of a file as the message text, use @ sign, followed by the filename. You can use the same approach to send the text content of the clipboard (@CLIP:) or the console (@CON:):

```
sendmail abc@xyz.com Party @c:\messages\invitation.txt
sendmail abc@xyz.com Party @clip:
type myfile.txt | sendmail abc@xyz.com Party @con:
```

Options:

/A file Attach file to the email message. The /A switch and the name of the file to attach must appear before address. Any file name that contains spaces or special characters must be quoted. You can send multiple files by repeating the /A switch for each additional file to send. For example:

```
sendmail /a file1 /a "d:\path\My file2" abc@xyz.com ...
```

- **/D** Request Delivery Notification.
- **/E** Set the "reply to" address in the message header.
- /H Set a custom header. The header will be appended to the message headers created from "to", "from", "subject", etc. The headers must of the format "header: value" as specified in RFC 822. You can specify multiple headers with multiple /H arguments.
- **/In** Set the Importance where *n* is:
 - 1 High
 - 2 Normal (default)
 - 3 Low
- /M Use CRAM-MD5 authentication.

/Pn Set the Priority where *n* is:

- 0 Unspecified (default)
- 1 Normal
- 2 Urgent
- 3 Non Urgent
- /R (Read receipt): Send a read receipt.
- /Sn Set the message sensitivity. The values are:
 - 1 Personal
 - 2 Private
 - 3 CompanyConfidential

N Show all the interaction with the server, except the message header and message body text.

3.13.11(SERVICEMONITOR

Purpose: Monitor service start, pause, and / or stop

Format: SERVICEMONITOR [/C [name]]

SERVICEMONITOR name STARTED | PAUSED | STOPPED n command

name Device name

n Number of repetitions (or **FOREVER**)

command Command to execute when condition is triggered

/C(lear) 319

Usage:

The service name can include wildcards.

The command line will be parsed and expanded before SERVICEMONITOR is executed, so if you want to pass redirection characters or variables to **command** you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

If you don't enter any arguments, SERVICEMONITOR will display the services it is currently monitoring.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use START or DETACH of in *command* to avoid conflicts.

SERVICEMONITOR creates several environment variables when a service is started, paused, or stopped that can be queried by *command*. The variables are deleted after *command* is executed.

_servicedisplay Display name used by service control programs to identify the service

_servicename The name of the service in the service control manager database

_servicecount The number of times the command has been triggered

_servicestate The current state of the service. The possible values are:

- 1 The service is stopped
- 2 The service is starting
- 3 The service is stopping
- 4 The service is running
- 5 The service continue is pending
- 6 The service pause is pending
- 7 The service is paused

Options:

If name is specified, remove the monitor for that service. Otherwise, remove all service monitors.

3.13.11'SERVICES

Purpose: Display, stop, or start system services

Format: SERVICES [/P /R /S] [name ...]

/P(ause) [319] /S(top service) [319] /R(un) [319]

Usage:

The *name* is the service name, not the display name. *name* can contain wildcards.

Options:

/P Pause after displaying each page.

/R Run the specified service(s).

/S Stop the specified service(s).

3.13.112SET

Purpose: Display, create, modify, or delete environment variables.

Format: Display mode:

SET [/D /E /P /S /U /V /X] [wildname]

Definition mode:

SET [/A /D /S /U /V /E /R [file...] | name=value | prompt]

Deletion mode:

SET [/D /S /U /V /E] name=

file One or more input files to read variable definitions from.

name The name of the environment variable

value The new value for the variable, separated from name by space[s]

prompt Optional input prompt for the **/P name**= option

wildname Name of variable[s] to be displayed. May contain * wildcard unless

displaying registry variables

/A Arithmetic /S System

32		322	
/D	Default	/U	User
322		323	
<u>/E</u>	Environment, too	<u>/V</u>	Volatile
322		323	
<u>/P</u>	Pause or Prompt	/ <u>X</u>	Override VariableExclude
322		323	370
/R	Read from file(s)		
322	()		

See also: ESET 222 and UNSET 357.

Usage:

Every program and command inherits an <u>environment set</u>, which is a list of pairs of variable *names* and *values*. Each *value* is a non-empty character string (i.e., there must be at least one character in it). Many programs use entries in the environment to modify their own actions. *TCC* itself uses several environment variables.

If you simply type the SET command with no options or parameters, it will display all the names and values of all currently defined variables in the environment. Typically, you will see an entry called **PATH**, an entry called **CMDLINE**, and whatever other environment variables you and your programs have established:

```
[c:\] set
PATH=C:\;C:\UTIL
CMDLINE=C:\TCMD\TCSTART.CMD
```

If you enter only *name*, and there is no variable with that name, SET will display all environment variables whose names begin with *name*. For example, if there is no variable *pa*, the command below will display all variables whose names start with *pa*:

```
set pa
```

The above command is equivalent to the command

```
set pa*
```

If there is only a single parameter and it contains one or more wildcards (sorry, only * available), SET will display all matching environment variables. You cannot use wildcards to display the registry variables (/D 322), /S 322), /U 323), and /V 323).

You can specify variables to exclude from the SET display with the VariableExclude variable. For example, to suppress the display of the processor and user variables:

```
set VariableExclude=proc*;user*
```

(Note that this option doesn't affect the existence of the variables, just whether they're displayed by a SET with no arguments.)

To add a variable to the environment, type SET, a space, the variable name, an equal sign, and the desired value:

```
set mine=c:\finance\myfiles
```

The variable name and the text after the equal sign will be left just as you entered it. However, case is ignored when looking for a variable; for example **MyVar**, **myvar**, and **MYVAR** all refer to the same variable. If the variable already exists, its value will be replaced with the new text that you entered.

Normally you should not put a space on either side of the equal sign. A space before the equal sign will become part of the *name*; a space after the equal sign will become part of the *value*.

Trailing whitespace in the SET command is ignored. To create a variable with trailing whitespace, use a pair of back quotes after the whitespace:

```
set mine=%@repeat[ ,20]``
```

makes mine 20 characters of spaces.

If you use SET to create a variable with the same name as one of the *TCC* internal variables [372], you will disable the internal variable. If you later execute a batch file or alias that depends on that internal variable, it may not operate correctly. Once you delete your variable, the internal variable becomes accessible again.

To display the contents of a variable, type SET plus the variable name:

```
set mine
```

You can edit environment variables with the <u>ESET</u> 222 command. To remove variables from the environment, use <u>UNSET</u> 357, or type SET, followed by the variable name and an equal sign:

```
set mine=
```

The variable's *name* is limited to a maximum of 255 characters. *Name* and *value* together cannot be longer than 8,191 characters.

Note: You cannot use SET to modify GOSUB variables 247).

The size of the environment is set automatically, and increased as necessary as you add variables.

Registry Variables

Windows stores some of its own variables in the registry. This includes Default, System, User, and Volatile variables. Those variables can be manipulated with the SET command's $\frac{D}{322}$, $\frac{S}{322}$, $\frac{D}{322}$, and $\frac{D}{322}$ options respectively. For example, to display the contents of volatile variable *clientname*, use:

```
set /v clientname
```

Note that setting a registry variable using one of the options /D 322, /S 322, /U 323 or /V 323 will not set the variable in the local environment unless you also use the /E 322 option.

User variables are user-specific, and volatile variables are only valid for the current Windows session. Use caution when directly modifying registry variables as they may be essential to various Windows processes and applications.

If the <u>Update Environment on System Change</u> on Guide Change of Configuration option is set, *TCC* will monitor the WM_SETTINGCHANGE message and update the environment from the User, Volatile, and System registry entries. The update is done whenever *TCC* displays the prompt (to prevent the environment from changing in the middle of a command).

Options:

/A Evaluate the arithmetic expression on the right of the equal sign, place the result in the environment, and display it. For example, this command adds 2 and 2, and places the

result in the environment variable VAR:

```
set /a var=2+2
```

/A interprets non numeric strings in *value* as environment variable names whether or not preceded by a percent sign %, and replaces them with their respective *values*. For example, this sequence will set Y to 4:

```
set x=2
set /a y=x+2
```

You can use <u>@EVAL</u> 420 to perform the same task; SET /A is included for compatibility with **CMD.EXE**. Unlike <u>@EVAL</u> 420, use of the >> or << shift operators in SET /A requires disabling their interpretation as redirection symbols by using <u>SETDOS</u> 323 /X-6.

- **/D** Create/modify/delete a **default** variable in the registry (HKU\.DEFAULT\Environment).
- When used together with one of \(\frac{\D}{322} \), \(\frac{\S}{322} \), \(\frac{\D}{323} \), or \(\frac{\D}{323} \), set both the registry variable and the local environment variable.
- When used without a variable name, wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102.

When used with a variable name and an optional prompt string, e.g. set /p *myvar*=Enter value, emulates the **CMD.EXE** behavior of allowing entry of a value for the variable. This is provided for compatibility reasons only. For more flexibility, use the ESET 222 or INPUT command.

Read environment variables from a file. This is much faster than loading variables from a batch file with multiple SET commands. Each entry in the file must fit within the command line length limit for *TCC*. The file is in the same format as the SET display (i.e., name=value), so SET /R can accept as input a file generated by redirecting SET output. For example, the following commands will save the environment variables to a file, and then reload them from that file:

```
set > varlist
set /r varlist
```

You can load variables from multiple files by listing the filenames individually after the /R.

If you are creating a SET /R file by hand, and need to create an entry that spans multiple lines in the file, you can do so by terminating each line (except the last) with an escape character | 1241. However, you cannot use this method to exceed the command line length limit. You can also add comment lines to the file by starting each with a colon :. You can also use other special characters, e.g., redirection and pipe symbols (<>|), without the need for special handling (e.g., escaping). If you reference the value of another variable in value (e.g., x=%path;c:\jpsoft), evaluating that variable (path in the example) is postponed until at some future time a command line evaluates the current variable (x in the example), so that the command echo %x will display the path in effect when echo is executed, regardless of what path may have been when the original SET defined x.

If you do not specify a filename and input is redirected, **SET /R** will read from stdin [535].

Create/modify/delete a **system** variable in the registry (
HKLM\System\CurrentControlSet\Control\Session Manager\Environment
).

/U Create/modify/delete a **user** variable in the registry (HKCU\Environment).

Create/modify/delete a volatile variable in the registry (HKCU\Volatile Environment).

/X Override the **VariableExclude** variable and display all matching variables.

3.13.11(SETDOS

Purpose: Display or set the **TCC** configuration.

Format: SETDOS [/A? /C? /D? /E? /Fn.n /G?? /I[+|-] command /M? /N? /P? /S?:? /V? /X[+|-]n]

/A(NSI) 323 /M(ode for editing) 325 /N(o clobber) 325 /N(o clobber) 325 /N(o clobber) 325 /P(arameter character) 324 /S(hape of cursor) 325 /S(hape of cursor) 325 /V(erbose) 325 /V(erbose) 325

/G (numeric separators) [324] /X (expansion, special characters) [325]

/I(nternal) 324

See also: OPTION 284).

Usage:

SETDOS allows you to customize certain aspects of **TCC** to suit your personal tastes or the configuration of your system.

You can display the value of all SETDOS options by entering the SETDOS command with no parameters.

Most of the SETDOS options can also be changed in the <u>configuration dialogs</u> 46. The name of the corresponding configuration option is listed with each SETDOS option below; if none is listed, that option cannot be set from the configuration dialogs. You can also define the SETDOS options in your **TCSTART** or other startup file (see <u>Automatic Batch Files</u> 22), in aliases, or at the command line.

Note: The functionality of the "/Y" option ("debug", no longer supported) of previous versions has been moved to the BDEBUGGER [166] command.

Inheritance

When a new instance of the command is started, it inherits the SETDOS characteristics set by the most recently started instance of *TCC*.

Options:

[ANSI] This option determines whether ANSI X3.64 support of is enabled. **/A1** enables ANSI X3.64 string processing. The default of **/A0** disables ANSI X3.64 strings. See the ANSI X3.64 Commands Reference of for a list of the ANSI X3.64 sequences supported by **TCC**. See also: the ANSI Colors of configuration option and the ANSI 382 internal variable.

(Command Separator] This option sets the character used for separating multiple commands on the same line. The default value is the ampersand [&]. You cannot use any of the redirection set characters (| > <), or a space, tab, comma, or equal sign as the

command separator. The command separator is saved by <u>SETLOCAL</u> 326 and restored by <u>ENDLOCAL</u> 220. The following example changes the separator character to a tilde [~]:

setdos /c~

[Descriptions and Description Name] This option controls whether file processing commands like COPY [182], DEL [190], MOVE [274], and REN [305] process file descriptions along with the files they belong to. /D1 turns description processing on, which is the default. /D0 turns description processing off. See also: the Enable Descriptions [51] configuration option.

You can also use **/D** to set the name of the hidden file in each directory that contains file descriptions. To do so, follow **/D** with the filename in quotes:

```
setdos /d"files.bbs"
```

Use this option with caution, because changing the name of the description file will make it difficult to transfer file descriptions to another system.

- [Escape Character] This option sets the character used to suppress the normal meaning of the following character. Any character following the escape character will be passed unmodified to the command. The default escape character is a caret [^]. You cannot use any of the redirection characters (| > <) or a space, tab, comma, or equal sign as the escape character. The escape character is saved by SETLOCAL and restored by ENDLOCAL [220]. Certain characters (b, c, e, f, k, n, q, r, s, and t) have special meanings when immediately preceded by the escape character.
- /F [@EVAL maximum and minimum] This option lets you set the default decimal display precision for the @EVAL 420 variable function. The maximum precision is 1,000 digits to the left of the decimal point and 1,000 digits to the right of the decimal point. (You can specify up to 10,000 digits in an @EVAL calculation by using the =x,y option.)

The format for this option is **/Fx.y**, where the x value sets the minimum number of digits to the right of the decimal point and the y value sets the maximum number of digits. You can use **=x,y** instead of **=x.y** if the comma is your decimal separator. Both values can range from 0 to 10. You can specify either or both values: **/F2.5**, **/F2**, and **/F.5** are all valid entries. If **x** is greater than **y**, it is ignored; if only **x** is specified, **y** is set to the same value (e.g. **/F2** is equivalent to **/F2.2**). See the @EVAL Precision [51] configuration option to set the precision when **TCC** starts; see the @EVAL [420] function if you want to set the display precision for a single computation.

[Decimal and thousands separator characters] This option sets the <u>Decimal standard and Thousands separator</u> characters. The format is **/Gxy** where "x" is the new decimal separator and "y" is the new thousands separator. Both characters must be included. The only valid settings are **/G.**, (period is the decimal separator, comma is the thousands separator); **/G**, (the reverse); or **/G0** to remove any custom setting and use the default separators associated with your current country code (this is the default).

The decimal separator is used for <u>@EVAL</u> [420], numeric <u>IF</u> [253] and <u>IFF</u> [254] tests, version numbers, and other similar uses. The thousands separator is used for numeric output, and is skipped when performing calculations in <u>@EVAL</u>.

This option allows you to disable or enable internal commands. To disable a command, precede the command name with a minus [-]. To re-enable a command, precede it with a plus [+]. For example, to disable the internal LIST command to force *TCC* to use an external command:

setdos /i-list

To re-enable all disabled commands use /I*.

- /M [Edit Mode] This option controls the initial line editing mode. To start in overstrike mode at the beginning of each command line, use /M0 (the default). To start in insert mode, use /M1). See also: the Edit Mode 50 configuration option.
- [NoClobber] This option controls output redirection [98]. /N0 means existing files will be overwritten by output redirection (with >) and that appending (with >>) does not require the file to exist already. This is the default. /N1 means existing files may not be overwritten by output redirection, and that when appending the output file must exist. A /N1 setting can be overridden with the [!] character. See also: the Protect Redirected Output File [47] configuration option.
- [Parameter Character] This option sets the character used after a percent sign to specify all or all remaining command line parameters in a <u>batch file 130</u> or <u>alias 154</u>. The default value is the dollar sign [\$]. The parameter character is saved by <u>SETLOCAL 326</u> and restored by <u>ENDLOCAL 220</u>.
- [Insert and Overstrike Cursor] The cursor size is entered as a percentage of the total character height. The default values are 10:100 (a 10% underscore cursor for overstrike mode, and a 100% block cursor for insert mode). Because of the way video drivers remap the cursor shape, you may not get a smooth progression in the cursor size from 1% 100%. (You can disable the cursor by specifying a size of 0:0.)

If either value is -1, **TCC** will not attempt to modify the cursor shape at all. You can retrieve the current cursor shape values with the **%_CI** and **%_CO** internal variables. See also the Overstrike Cursor on and Insert Cursor configuration options.

/V [Batch Echo] This option controls the default for command echoing in batch files.

/V0 disables echoing of batch file commands unless ECHO 217 is explicitly set ON.

/V1, the default setting, enables echoing of batch file commands unless ECHO (217) is explicitly set OFF. See also: the Batch Echo (47) configuration option.

/X[+|-]n (expansion and special characters) This option enables and disables alias and environment variable expansion, and controls whether special characters have their usual meaning or are treated as text. It is most often used in batch files to process text strings which may contain special characters.

The features enabled or disabled by /X are numbered (in hex). All features are enabled when TCC starts, and you can re-enable all features at any time by using /X0. To disable a particular feature, use /X-n, where n is the feature number from the list below. To re-enable the feature, use /X+n. To enable or disable multiple individual features, list their numbers in sequence after the + or - (e.g. /X-345 to disable features 3, 4, and 5).

The features are:

- 1 All alias expansion
- 2 Nested alias expansion only
- All variable expansion (includes environment variables, batch file parameters, variable function evaluation, and alias parameters)
- 4 Nested variable expansion only

- Multiple commands, conditional commands, and piping (affects the command separator, ||, &&, |, and |&)
- 6 Redirection (affects < , >, >&, >&>, etc.)
- 7 Quoting (affects back-quotes [*] and double quotes [*]) and square brackets)
- 8 Escape character
- 9 Include lists 88
- A User-defined functions 242

If nested alias expansion is disabled (/X-2), the first alias of a command is expanded but any aliases it invokes are not expanded. If nested variable expansion is disabled (X-4), each variable is expanded once, but variables containing the names of other variables are not expanded further.

For example, to disable all features except alias expansion while you are processing a text file containing special characters:

```
setdos /x-35678
... [perform text processing here]
setdos /x0
```

A <u>SETLOCAL</u> 3261 command will save the current SETDOS /X values for <u>ENDLOCAL</u> 2201 to restore.

3.13.114SETLOCAL

Purpose: Save a copy of the current disk drive, directory, environment, alias list, and special

characters.

Format: SETLOCAL

See also: ENDLOCAL 220.

Usage:

SETLOCAL is valid only in batch files. It will save :

- · the default disk drive and directory
- the environment,
- · the alias list
- the special character set (command separator, escape character, parameter character, decimal separator, and thousands separator)
- the SETDOS /X 323 setting

After using SETLOCAL, you can change the values of any or all of the above, and later restore the original values with an ENDLOCAL command, or just by exiting the batch file.

SETLOCAL does not save the command history or user functions.

For example, this batch file fragment saves everything, removes all aliases so that user aliases will not affect batch file commands, changes the disk and directory, changes the command separator, runs a program, and then restores the original values:

```
setlocal
unalias *
cdd d:\test
setdos /c~
```

```
program ~ echo Done!
endlocal
```

SETLOCAL and ENDLOCAL may be nested up to 16 levels deep in each batch file. You can also have multiple SETLOCAL / ENDLOCAL pairs within a batch file, and nested batch files can each have their own SETLOCAL / ENDLOCAL pairs.

SETLOCAL does not override the <u>Local Aliases</u> 47 configuration option. Consequently changing aliases inside a SETLOCAL/ENDLOCAL pair affects the definition of aliases of other concurrently executing sessions of *TCC*.

You cannot use SETLOCAL in an alias or at the command line.

An ENDLOCAL is performed automatically at the end of a batch file, or when returning from a "

GOSUB [247] filename". If you invoke one batch file from another without using CALL [175], the first batch file is terminated, and an automatic ENDLOCAL is performed; the second batch file inherits the settings as they were prior to any SETLOCAL.

You can "export" modified variables from inside a SETLOCAL / ENDLOCAL block. See ENDLOCAL 220 for details.

3.13.11!SHIFT

Purpose: Allows the use of more than 512 parameters in a batch file, or iterating through its

parameters. This command can be used only in batch files.

Format: SHIFT [[-]n | /n]

n Number of positions to shift (an unsigned number), or the position of the parameter to be deleted.

Usage:

SHIFT is provided for compatibility with batch files written for CMD.EXE, where it was used to access more than the CMD.EXE limit of 10 parameters. *TCC* supports 4096 parameters (%0 to %4095), so you do not need to use SHIFT for batch files running exclusively under *TCC*.

SHIFT n moves each of the batch file parameters n positions to the left. The default value for n is 1. For example, SHIFT (with no parameters) makes the parameter %1 become to %0, the parameter %2 becomes %1, etc.

SHIFT -n moves parameters to the right, but it is limited to moving them back to their position on entry to the batch file.

This form of SHIFT also affects the special parameters **%n\$**, **%\$** and **%#** (number of command parameters). However, for compatibility with **CMD.EXE**, this form of the SHIFT command does not alter the contents or order of the parameters returned by **%***. See Batch File Parameters 1331 for details.

For example, create a batch file called TEST.BAT:

```
echo %1 %2 %3 %4 shift echo %1 %2 %3 %4 shift 2 echo %1 %2 %3 %4 shift -1 echo %1 %2 %3 %4
```

Executing the command below produces the following results:

```
[c:\] test one two three four five six seven
one two three four
two three four five
four five six seven
three four five six
```

SHIFT /n This form of the command irreversibly deletes parameter %n from the command tail, and shifts all parameters originally to its right 1 position to the left. For example,

```
shift /2
```

leaves parameters %0 and %1 unchanged, and moves the value of %3 to position %2, %4 to %3, etc.

This form of SHIFT also affects the special parameters **%n\$**, **%\$** and **%#** (number of batch file parameters), and unlike the first form, it also affects **%***. See Batch File Parameters [133] for details.

3.13.11(SHORTCUT

Purpose: Create or display a shortcut.

Format: Creation mode 328

SHORTCUT command args dir desc link mode [iconfile [iconoffset [hotkey]]]

Display mode 329 SHORTCUT link

command Command the shortcut executes

args Command line parameters for command

dir Starting directorydesc Description

link Filename of the .LNK or .PIF file.

mode Initial window mode: 1=normal, 2=minimized, 3=maximized

iconfileFile containing the icon to useiconoffsetIcon offset within iconfilehotkeyHotkey to invoke the shortcut

Usage:

Creation Mode

SHORTCUT creates a Windows shortcut file and places it in the specified directory. You can run any Windows shortcut from **TCC**by entering the name of the .LNK file on the command line.

SHORTCUT requires a minimum of 6 parameters. To leave a parameter blank, enter an empty string (2 double quotes "" in its place. Any parameter must be enclosed in double quotes if it includes white space or other special characters.

Command is the full path of the executable file to start, or the data file or folder to open. If it is a data file, its extension must be associated with an executable command (see ASSOC 162) for the shortcut to work.

The **args** parameter lists any command line parameters which you want to include when **command** is executed. For example, if **command** points to a batch file, you might want to include **/c** in **args** so that

TCC exits immediately when the batch file is completed.

The *dir* parameter is the path of the directory to which you want Windows to switch when the command starts. If you don't care which directory is used, you can omit this parameter by entering "" in its place.

Desc provides a description that is stored internally in the shortcut. It is displayed when the cursor is moved to the shortcut. If you omit the description, enter "" in its place.

The *link* parameter is the drive, path, name and extension of the shortcut file you want to create. The drive and path portion is interpreted according to the usual rules - missing elements default to the current defaults, path is relative to the current default unless it starts with \. The file extension must be .LNK, unless you are creating a shortcut to a DOS command, in which case the extension must be .PIF. Note that Windows supports other extensions as well,

Note: If you want the shortcut to appear on the Windows desktop, you should include the full path to one of the desktop directory in the command. In most Windows configurations, that directory can be referenced symbolically as **%userprofile\Desktop**. Some Windows versions also include an **All Users\Desktop** directory.

The **mode** parameter determines how Windows will display the application or folder when you run the shortcut. It must be **1** for a normal window, **2** for a minimized window (normally placed on the taskbar), or **3** for a maximized window.

The two (optional) parameters, *iconfile* and *iconoffset* allow you to specify the icon for the shortcut to use. (By default, SHORTCUT will use the default icon in the executable file.)

The final (optional) parameter *hotkey* specifies the keystroke which will call the shortcut. The keystroke should be entered in the same format as used in KEYSTACK [262]; for example, **Ctrl-Alt-B**.

Display mode

If you provide a single parameter (a link file name), SHORTCUT will display the values for that link.

3.13.117SHRALIAS

Purpose: Retains global command history, directory history, alias and user function lists in memory

when TCC is not running.

Format: SHRALIAS [/U]

/U(nload) 330

Usage:

When you close all **TCC** sessions, the memory for the global command history, global directory history, global alias and global function lists is released. If you want the lists to be retained in memory even when **TCC** is not running, you need to execute SHRALIAS.

The SHRALIAS command starts and initializes SHRALIAS.EXE, a small program which remains active and retains global lists when *TCC* is not running. SHRALIAS.EXE must be stored in the same directory as *TCC* or in a directory on your PATH. You cannot run SHRALIAS.EXE directly, it must be invoked internally by the SHRALIAS command.

Once SHRALIAS has been executed, the global lists will be retained in memory until you use

SHRALIAS /U to unload the lists, or until you shut down your operating system.

If you have an environment variable named SHRALIAS_SAVE_PATH, SHRALIAS will save the alias, history, dirhistory, and function lists to the path specified by SHRALIAS_SAVE_PATH when SHRALIAS exits. The files will be saved in Unicode format as alias.sav, history.sav, dirhistory.sav, and function.sav.

SHRALIAS will not work unless you have at least one copy of *TCC* running with global alias, global function, global command history, or global directory history enabled. If no global list is found, SHRALIAS will display an error.

If you start SHRALIAS from a temporary *TCC* session which exits after starting SHRALIAS, the *TCC* session may terminate and discard the shared lists before SHRALIAS can attach to them. In this case SHRALIAS.EXE will not be loaded. If you experience this problem, add a short delay with the <u>DELAY</u> command after SHRALIAS is loaded and before your session exits.

SHRALIAS will not work in detached sessions (i.e., those started with DETACH 197), or with the AT utility), due to security issues within Windows. Therefore the SHRALIAS command is ignored for detached sessions.

For more information about global histories, function and alias lists, see <u>Local and Global History Lists</u> 108, Local and Global Functions 242, Local and Global Aliases 154.

Option:

/U

Shuts down SHRALIAS.EXE. All global command history, directory history, function and alias lists will be released from memory when the last copy of *TCC* exits unless SHRALIAS is loaded again before that time.

3.13.118SMPP

Purpose: Send simple text (**SMS**) messages, typically to text-enabled cellular phones and similar

devices.

Format: SMPP server username password recipient message

server SMS server name

usernameUser name for the SMS serverpasswordPassword for the SMS server

recipient Phone number or dotted IP of an SMS-enabled device

message The message to send

See also: SENDMAIL 316, SNPP 331.

Usage:

SMPP sends **message** through standard Internet Paging Gateways. Depending on your system configuration, you may need to start an Internet connection before using SMPP. See your service provider for specific requirements.

3.13.11\(\script{SNMP}\)

Purpose: Send SNMP traps

Format: SNMP remotehost trapOID "value" [username password]

remotehost Host name receiving the trap

trapOID OID of the trap **value** Description

usernameUser name for SNMP v3 trappasswordPassword for SNMP v3 trap

Usage:

SNMP normally sends an SNMPv2 trap. If you specify a user name and password it will send an SNMPv3 trap.

The following symbolic names are recognized and translated:

Trap Name	_OID		
coldStart	1.3.6.1.6.3.1.1.5.1		
warmStart	1.3.6.1.6.3.1.1.5.2		
linkDown	1.3.6.1.6.3.1.1.5.3		
linkUp	1.3.6.1.6.3.1.1.5.4		
authenticationFailure	1.3.6.1.6.3.1.1.5.5		
egpNeighborLoss	1.3.6.1.6.3.1.1.5.6		
enterpriseSpecific	1.3.6.1.6.3.1.1.5.7		

3.13.12(SNPP

Purpose: Send messages to alphanumeric pagers.

Format SNPP server pagerid message

server The SNPP server name

pagerid The ID of the pager to receive the message

message The message to send

See also: SENDMAIL 316, SMPP 330.

Usage:

SNPP sends *message* to alphanumeric pagers through standard Internet Paging Gateways. Depending on your system configuration, you may need to start an Internet connection before using SNPP.

3.13.12'START

Purpose: Start a program in another session or window.

Format: START ["title"] [/AFFINITY=n /ABOVENORMAL /BELOWNORMAL /HIGH /LOW

/NORMAL /REALTIME /B /C /K /CM /Dpath /I /FS /INV /MAX /MIN /POS=x,y,width,height

/L /LA /LD /LF /LH /MONITOR=n /RUNAS user password /SEPARATE /SHARED

/SIZE=rows,cols /TAB /WAIT /WIN /PGM] "progname" [command]

title Title to appear on title bar

path Startup directory

prognamecommandProgram name (not the session name)Command to be executed by progname

/ABOVENORMAL	Priority	/LOW 334	Priority
/AFFINITY 333 /BELOWNORMA	Multiple CPUs No new console Priority	/MAX 334 /MIN 334 /MONITOR	Maximized window Minimized window Monitor to use
<u>/C</u> 333	Close when done	/NORMAL	Priority
/D 3331 /FS 3341 /HIGH 3341	Startup directory Full screen window Priority	/PGM 334 /POS 334 /REALTIME	Program name Position of window Priority
/	Inherit environment Invisible window	/RUNAS 334	Run as other user Separate session
<u>/K</u> 334	Keep when done	/SHARED	Shared session
/L 334 /LA 334	Local lists Local aliases	/SIZE 334 /TAB 334	Screen buffer size Start in <i>Take Command</i> tab window
/LD 3341 /LF 3341 /LH 3341	Local directory history Local functions Local history list	/WAIT 3347 /WIN 3347	For session to finish Windowed session

See also: DETACH 197).

Usage:

START is used to begin a new session, and optionally run a program in that session. If you use START with no parameters, it will begin a new *TCC* session. If you add a *command*, START will begin a new session or window and execute that command.

START will return to the *TCC* prompt immediately (or continue a batch file), without waiting for the program to complete, unless you use /WAIT 3341.

If *title* is included, will appear on the task list and **Alt-Tab** displays. instead of the program name, which is the default. *Title* must be enclosed in double quotes, and cannot exceed 127 characters.

START always assumes that the first quoted string on the command line is the *title*. If there is a second quoted string it is assumed to be the *command*. As a result, if the name of the program you are starting contains white space (and must therefore be quoted), and you don't specify a *title*, START will interpret the first quoted string as the *title*, not the *command*. To address this, use the <u>/PGM</u> switch to indicate explicitly that the quoted string is the program name, or include a title before the program name. For example, to start the program *C:\Program Files\Proc.Exe* you could use either of the first two commands below, but the third command would not work:

```
Valid
    start /PGM "C:\Program Files\Proc.Exe"
    start "test" "C:\Program Files\Proc.Exe"
Invalid
    start "C:\Program Files\Proc.Exe"
```

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

START offers a large number of switches to control the session you start. In most cases you need only a few switches to accomplish what you want. The list below summarizes the most commonly used START options, and how you can use them to control the way a session is started.

Window controls: /FS | 334, /MAX | 334, /MIN | 334, and /POS | 334 | allow you to start a character-mode windowed session in full screen mode, a maximized window, a minimized window, or a window with a specified position and size, respectively. /INV | 334 | starts an invisible window. /B | 333 | starts the program in the current console window. The default is /WIN | 334 |, which permits Windows to choose the position and size of the non-maximized window. If you start a graphics mode program, only /MAX | 334 | and /POS | 334 | are effective, and the position and size information associated with /POS | 334 | is ignored. Windows will use the size, but not the position of the same program when last used in RESTORE mode. If you want to control the window size and placement of a graphics mode program, use the ACTIVATE | 152 | command after the window has been opened.

Session priority: The options /ABOVENORMAL 333, /BELOWNORMAL 333, /HIGH 334, /LOW 334, /NORMAL 334 and /REALTIME 334 allow you to select the new session's priority.

Program controls.

If **progname** is in the "App Paths" registry, its associated "Path" value (if it exists) is inserted into the beginning of the PATH [368] in the environment inherited by the program.

If **progname** is the name of a directory instead of an executable program, **TCC** will start your default Windows shell (usually Windows Explorer) in the specified directory.

Progname inherits the environment as it exists when START is executed, unless <u>/I</u> 334 is used to select the default environment.

It *progname* specifies **TCC.EXE**, the options /L 334, /LD 334, /LF 334 and/LH 334 provide control over the use of local or global lists. See details below.

The initial directory for *progname* is the current default directory, unless otherwise specified using the <u>/D</u> 333 option. **WARNING!** If *progname* is a DOS program, this option may not work properly. To avoid such problems, you can change the default directory before START, and restore it afterwards.

If **progname** is a 16-bit Windows application, by default is starts in a shared virtual machine. You may use the /SEPARATE 334 option to force creation of a unique virtual machine.

When *command* is finished, /C 333 closes the session (the default for Windows sessions), while /K 334 keeps it and displays the prompt (the default for character mode sessions).

The Process ID of the detached session or program is returned in the <u>STARTPID</u> (392) internal variable.

Options:

/ABOVENORMAL	Set the priority above normal.
/AFFINITY=n	On multiple processor machines, set the processor affinity for this process.
	Acceptable values are 0 to <i>n</i> -1 (where <i>n</i> is the number of available
	processors)
/BELOWNORMAL	Set the priority below normal.
/B	The program is started without creating a new window or console, i.e. in
	the TCC window. Normally, the application is started in its own window. For
	compatibility with CMD. EXE, /B also disables Ctrl-C processing for the
	program.
/C	Close the session or window when the application ends.
/D	Specifies the startup directory. Include the directory name immediately after
	the /D, with no intervening spaces or punctuation. Due to limitations in the
	way Windows starts DOS programs, /D is ignored when starting DOS
	applications.
	and the second of the second o

/FS Start the console application in full-screen mode. (Not supported in

Windows Vista or later.)

/HIGH Start the window at high priority.

/I Inherit the default (startup) environment, rather than the current

environment.

/INV Start the session or window as invisible. No icon will appear and the

session will only be accessible through the Task Manager or Window List. (Keep session or window at end) The session or window continues after

the application program ends. Use the EXIT 227 command to end the

session.

/K

/L Start **TCC** with local alias, function, history and directory history lists. This

option is equivalent to specifying all of /LA 334, /LD 334, /LF 334, and /LH 334

(below).

/LA Start *TCC* with a local alias list. See ALIAS 154 for information on local and

global alias lists.

/LD Start *TCC* with a local directory history list. See Local and Global History

Lists 108 for information on local and global directory history lists.

/LF Start *TCC* with a local function list. See FUNCTION 242 for information on

local and global function lists.

/LH Start *TCC* with a local history list. See Local and Global History Lists 108 for

information on local and global history lists.

/LOW Start the window at low priority.

/MAX Start the session or window maximized.
/MIN Start the session or window minimized.

/MONITOR=*n* Start the program on the specified monitor (1 to *n*). This will only work with

apps that do not try to position their window at startup, and you cannot

combine this switch with /POS.

/NORMAL Start the window at normal priority.

/PGM The quoted string following this option is the program name. Any additional

text beyond the quoted string is passed to the program as its parameters, so to use other START switches you must place them before **/PGM** which must be the last option for START. You can use **/PGM** to allow START to differentiate between a quoted long filename and a quoted title for the

session.

/POS= Start the window at the specified screen position. The top left corner of the

left,top,width,height screen is 0,0.

/REALTIME Start the window at realtime priority.

/RUNAS Run a command in the context of the specified user. The syntax is:

/RUNAS user@domain password.

If "domain" is not specified, the local database is checked for the username. If you specify * for the password, START will prompt you to enter the password. (Useful when you don't want to put the password in a

batch file.)

/SEPARATE Start a 16-bit Windows application in a separate virtual machine. Normally,

all 16-bit Windows applications are started in the same virtual machine,

see /SHARED 334...

/SHARED: Start a 16-bit Windows application in the shared virtual machine (default).

See also /SEPARATE |334]. Included only for compatibility with CMD.EXE.

/SIZE=rows,columnsSpecifies the screen buffer size. Rows is the number of text rows and

columns is the number of text columns. (This is not the size of the

session's window.)

/TAB Start the command in a new *TCC* tab window.

WAIT Wait for the new session or window to finish before continuing.

/WIN Start the new console session as a window (this is the default.) See also

/FS 334 and /B 333.

3.13.12;SWITCH

Purpose: Select commands to execute in a batch file based on a value.

Format: SWITCH expression

CASE value1 [.OR. value2 [.OR. value3 ...]]

[commands]
CASE value4
[commands]
[DEFAULT
commands]
ENDSWITCH

expression An environment variable, internal variable, variable function, text

string, or a combination of these elements, that is used to select a

group of commands.

value1, value2 A value to test or multiple values connected with .OR.

commandsOne or more commands to execute if the expression matches the

value. If you use multiple commands, they must be separated by command separators or placed on separate lines of a batch file.

See also: IF 253 and IFF 254.

Usage:

SWITCH can only be used in batch files. It allows you to select a command or group of commands to execute based on the possible values of a variable or a combination of variables and text.

The SWITCH command is always followed by an *expression* created from environment variables, internal variables, variable functions, and text strings, and then by a sequence of CASE statements matching the possible *values* of *expression*, an optional DEFAULT statement, and terminated by an ENDSWITCH statement. Each CASE statement and the DEFAULT statement may be followed by one or more *commands*.

TCC evaluates **expression**, and sequentially compares it with the list of **values** in the CASE statements, starting with the first one. Comparison rules are the same ones used for the **EQ** relational operator; see Numerical and String Comparisons for details. If a match is found, the **commands** following the matched CASE statement are executed, and the batch file continues with the commands that follow ENDSWITCH. If there are any matches in subsequent CASE statements, they are ignored.

If during the search for a match the DEFAULT statement is encountered, the *commands*, if any, following it are executed, and the batch file continues with the commands that follow ENDSWITCH. Any CASE statements after the DEFAULT statement are ignored.

SWITCH commands can be nested.

You can exit from all SWITCH / ENDSWITCH processing by using GOTO [248] to a line past the last ENDSWITCH.

Restrictions

Each SWITCH, CASE, DEFAULT and ENDSWITCH statement must be on a separate line, and may not be followed by a command separator. (This is the reason SWITCH cannot be used in aliases.) There is no restriction on grouping and command separator use in the *commands* for a CASE or DEFAULT.

You can link a list of values in a single CASE statement with .OR., but not with .AND. or .XOR..

Examples

The batch file fragment below displays one message if the user presses **A**, another if the user presses **B** or **C**, and a third one if the user presses any other key:

```
inkey Enter a keystroke: %%key
switch %key
case A
    echo It's an A
case B .or. C
    echo It's either B or C
default
    echo It's none of A, B, or C
endswitch
```

In the example above, the value of a single environment variable was used for *expression*. However, you can use other kinds of expressions if necessary. The first SWITCH statement below selects a command to execute based on the length of a variable, and the second bases the action on a quoted text string stored in an environment variable:

```
switch %@len[%var1]
case 0
    echo Missing var1
case 1
    echo Single character
...
endswitch

switch "%string1"
case "This is a test"
    echo Test string
case "The quick brown fox"
    echo It's the fox
...
endswitch
```

3.13.12:SYNC

Purpose: Synchronize two directories

Format: SYNC [/A:... /C /D /E /F /G /J /K /L /M /N[est] /O /P /Q /R /S[n] /T /V /W /X] dir1 dir2

dir1 First directory (and source for a /W)dir2 Second directory (and target for a /W)

```
/A: 337... Attribute switch
                                                      Modified files (not Archived)
                                                /M
                                                 336
/C 336
         Changed source files
                                                /N 336 Disable
/D 336
         Copy encrypted files
                                                /O 336 Only if no target file
/E 336
         No error messages
                                                /P 336 Prompt
/F 336
                                                /Q 336 Quiet
         No empty subdirectories
/G 336
                                                /R 336 Replace
         Display percentage completed
/H 336
                                                /S 336 Subdirectories included
         H(idden included)
/I"text"
         Match description
                                                /T |336 | Totals
```

See also: COPY 182 and MOVE 274.

File Selection

Supports extended wildcards 777 and ranges 801.

Internet: Can be used with FTP servers 93.

Usage:

SYNC will synchronize two directories, copying the updated files from each directory to the other.

Options:

- /A:... Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. See the cautionary note under Advanced Features above before using /A: when both dir1 and dir2 contain file descriptions. Do not use /A: with @file lists. See @file lists 90 for details. Hidden or system files selected by this option overwrite hidden or system files in the target directory.
- Copy files only if the destination file exists and is older than the source file. This option is useful for updating the files in one directory from those in another without copying any files not already in the target directory. Do not use /C with @file lists. See @file lists 90 for details.
- **(Windows XP+ Only)** Force copy of an encrypted file even when the target will be decrypted.
- Suppress all non-fatal error messages, such as **File not found** or **Can't copy file to itself**. Fatal error messages, such as **Drive not ready**, will still be displayed. This option is most useful in batch files and aliases.
- /F When used with /S, SYNC will not create any empty subdirectories.
- Displays the percentage copied, the transfer rate (in Kbytes/second), and the estimated time remaining. Useful when copying large files across a network or via FTP to ensure the copy is proceeding. When /V 1891 is also used, reports percentage verified.
- /H Copy all matching files including those with the hidden and/or system attribute set. See the cautionary note under Advanced Features above before using /H when both dir1 and dir2 contain file descriptions.
- /I" text" Select source files by matching text in their descriptions. See Description Ranges of for details.
- Copy the files in restartable mode. The copy progress is tracked in the destination file in case the copy fails. The copy can be restarted by specifying the same source and destination file names.
- /K (Keep read-only attribute) SYNC normally maintains the hidden and system attributes, sets the archive attribute, and removes the read-only attribute on the target file. /K tells

SYNC to also maintain the read-only attribute on the *destination* file.

- /L Perform FTP transfers in ASCII mode, instead of the default binary mode.
- Copy only those files with the archive attribute set, *i.e.*, those which have been modified since the last backup. The archive attribute of the source file will not be cleared after copying; to clear it use the /X | 189 | switch, or use ATTRIB | 163 |. Do not use /M with @file lists. See @file lists | 90 | for details.
- /N Do everything except actually perform the copy. This option is useful for testing the result of a complex SYNC command. /N displays how many files would be copied. /N does not prevent creation of destination subdirectories when it is used with /S [188].

A /N with one of the following arguments has an alternate meaning:

- **d** Skip hidden directories (when used with /S)
- e Don't display errors.
- j Skip junctions (when used with /S)
- **s** Don't display the summary.
- Don't update the CD / CDD extended directory search (JPSTREE.IDX).
- Ask the user to confirm each source file. Your options at the prompt are explained in detail under Page and File Prompts 102. See also: the /Q 1881 option below.
- Don't display filenames, percentage copied, total number of files copied, etc... When used in combination with the /P last option above, it will prompt for filenames but will not display the totals. This option is most often used in batch files. See also /T last.
- /R Prompt the user before overwriting an existing file. Your options at the prompt are explained in detail under Page and File Prompts 102.
- Copy the subdirectory tree starting with the files in the source directory plus each subdirectory below that. If the destination subdirectories don't exist, SYNC will attempt to create them. If SYNC /S creates one or more destination directories, they will be added automatically to the extended directory search [73] database.

If you attempt to use SYNC /S to copy a subdirectory tree into part of itself, SYNC will detect the resulting infinite loop, display an error message and exit. Do not use /S with **@file** lists. See **@file** lists of for details.

If you specify a number after the /S, SYNC will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

- Turns off the display of filenames, like /Q | 1881, but does display the total number of files copied.
- Verify each disk write by performing a true byte-by-byte comparison between the source and the newly-created target file. This option will significantly increase the time necessary to complete a SYNC command.
- **/W** Delete files in **dir2** that do not exist in **dir1**.
- /X Clear the archive attribute from the source file after a successful copy.

3.13.124TAIL

Purpose: Display the end of the specified file(s).

Format: TAIL [range ... [/] 340 "text"]] [/A: 340 [attrlist] /C 340 nn /F 340 | N+ 340 | N 340 []n /P 340 /Q 340

/V [34] {@file|file}...

file The file or list of files that you want to display.

@file A text file containing the name of a file to display in each line (see @file lists 90)

for details).

/A: (Attribute select) 340 /N(umber of lines) 340 /P(ause) 340

/F(ollow) 340 /Q(uiet) 340 /V(erbose) 341 /N+x (skip x lines before display 340)

See also: HEAD 249, LIST 264, and TYPE 354.

File Selection

Supports extended wildcards 77, ranges 87, multiple file names 87, and include lists 88.

Internet: Can be used with FTP servers [93], including HTTP/HTTPS files, e.g.

```
tail "http://jpsoft.com/notfound.htm"
```

Usage:

The TAIL command displays the last part of a file or files. It is normally only useful for displaying ASCII text files (i.e. alphanumeric characters arranged in lines separated by CR/LF). Executable files (.COM and .EXE) and many data files may be unreadable when displayed with TAIL because they include non-alphanumeric characters or unusual line separators.

You can press Ctrl-S to pause TAIL's display and then any key to continue.

The following example displays the last 15 lines of the files *MEMO1* and *MEMO2*:

```
tail /n15 memo1 memo2
```

To display text from the clipboard use **CLIP**: as the file name. **CLIP**: will not return any data if the clipboard does not contain text. See <u>Highlighting and Copying Text</u> for additional information on **CLIP**:

• FTP Usage

TAIL can also display files on FTP servers 3. For example:

```
tail "ftp://jpsoft.com/index"
```

You can also use the IFTP [255] command to start an FTP session on a server, and then use an abbreviated syntax to specify the files and directories you want.

NTFS File Streams

TAIL supports file streams on NTFS drives. You can type an individual stream by specifying the stream

name, for example:

```
tail streamfile:s1
```

Pipes

TAIL can optionally be used with an input pipe 10th. For example:

```
dir | tail /n2
```

This is not ordinarily feasible in Windows because pipes can't be "rewound", and therefore the pipe has to be written to a temporary memory buffer and the TAIL taken from there. Consequently, this limits the amount you can actually display in TAIL to less than a million bytes when the input is piped.

Examples

```
tail /n 5 xxx displays the last 5 lines of file xxx skip 20 lines, then display 999999 lines of xxx skip 20 lines, then display 1 line of xxx skip 1001 lines, then display 1 line of xxx set x=%@execstr[tail /n+1001 /n 1 xxx] sets \bf x to the contents of the 1002-nd line of xxx set x=%@execstr[tail /n 2 xxx] sets \bf x to the contents of the penultimate line of xxx
```

Options:

/A:[attributelist]

Select only those files that match the specified attribute(s). See Attribute Switches of for details.

/Cnn[*b*/*k*/*m*]

Display *nn* bytes, 512-byte *b*locks, *k*ilobytes, or *m*egabytes, when there is no suffix, for suffix b, suffix k, or suffix m, respectively.

/F Continuously monitor the file and display new lines until the command is interrupted, e.g, using *Ctrl-C* or Ctrl-*Break*..

/I" text"

Select files by a descriptor range 86. See the link for details.

- /N n Display n lines. The default is 10. Space between the option switch /N and the number n is optional. If /N is specified without n, it is equivalent to specifying 0 lines to be displayed, and the command will not generate output, unless /V 34 is also specified.
- /N+x Skip x lines from the beginning of the file, than start displaying lines. If the /N+ option is specified without specifying x, the option is ignored. This option does not affect the number of lines displayed (unless the start line is too close to the end of file)

Example: TAIL /N+5 file will display 10 lines (the default) after skipping 5 lines.

- /P Pause and prompt after displaying each page.
- Do not display a header for each file. This is the default behavior, but an explicit /Q may be needed to override an alias that forces /V [34].

N Display a header for each file.

3.13.12!TASKDIALOG

Purpose: Display a Windows Vista Task Dialog

Format: TASKDIALOG [/I /S /W] buttontype "title" "instruction" [text]

buttontype One or more of OK, CANCEL, YES, NO, RETRY, CANCEL, and/or

CLOSE

title Text for the task dialog title **instruction** Text for the main instruction

text Optional additional text that appears below the main instruction, in a

smaller font

/I(nformation icon) [28] /W(arning icon) [28]

/S(top icon) 281

See also: INKEY 257, INPUT 259, MSGBOX 279 and QUERYBOX 300.

Usage:

TASKDIALOG requires Windows Vista or later.

The button the user chooses is indicated using the internal variable %_? 380. Be sure to save the return value in another variable or test it immediately; because the value of %_? 380 changes with every internal command. The following list shows the value returned for each button:

response	%_? 380
Yes or OK	10
No	11
Cancel or Close	12
Retry	13

If there is an error in the TASKDIALOG command itself, %_? 380 will be set to 2.

For example, to display a Yes / No message box and take action depending on the result, you could use commands like this:

```
taskdialog yes no "Copy" "Copy all files to A:?"
if % ? == 10 copy * a:
```

Since TASKDIALOG doesn't write to standard output, it disables redirection and piping to allow you to enter the redirection characters (<, >, and |) in your prompt text.

TASKDIALOG creates a popup dialog box. If you prefer to retrieve input from the command line, see the INKEY [25] and INPUT [259] commands.

Options:

- /I Display an icon consisting of a lower case "i" in a circle in the message box.
- /S Display a stop sign icon in the message box.
- **/W** Display an exclamation point icon in the message box.

3.13.12(TASKEND

Purpose: End the specified process.

Format: TASKEND [/F] pid | name | "title"

pid The process IDname The process nametitle Window title

/F(orce) 342

See also: TASKLIST 342, _PID 390, _DETACHPID 385, _WINTITLE 3941

Usage:

Windows applications (and Windows itself) run as one or more processes or tasks. You can use the TASKLIST command to display a list of currently-running tasks. TASKEND can be used to end a task.

When you use TASKEND, you must specify the task you want to end by process ID number, by name (usually the name of the executable file that started the task) or by window title. If you use the Window title to specify the task, you must enclose it in double quotes. You can use wild cards and extended wildcards in the window title.

If you use TASKEND without the **/F** option, the effect is much the same as closing a window by clicking the close button. The application is notified of the request to end the task and has an opportunity to save data, prompt whether you mean to shut down, and perform other normal "close" operations.

If you use the **/F** option with TASKEND, the application is shut down abruptly and has no chance to save data. Use of the **/F** option is only recommended for unusual circumstance and advanced users because of the possibility of data loss.

Using this command may require DEBUG privilege.

Option:

/F

Forces the task or application to end immediately, with no opportunity to save data, prompt the user, etc. Use this option with caution; it can possibly lead to system instability and data loss or corruption.

3.13.12TASKLIST

Purpose: Display a processes list

Format: TASKLIST [/O /P] [name]

name Process name or window title

/O(rder by PID) 343 /P(ause) 343

See also: TASKEND 3421.

Usage:

Windows programs run as one or more processes or tasks. You can use the TASKLIST command to display a list of currently-running tasks. TASKLIST displays the process ID number for each running task, the name of the executable program that started the task, and, when available, the window title.

TASKLIST will display a * after the process ID of the current process.

You can limit the output of TASKLIST by specifying the task name that you wish to see. The name can contain wildcards and extended wildcards 77.

Options:

/O Sort the output by Process ID (PID).

/P Wait for a key to be pressed after each screen page before continuing the display.

3.13.12(TCFILTER

Purpose: Display or change the List View filter

Format: TCFILTER [/C] filter

filter A regular expression new filter

/C(lear) 342

See also: _TCFILTER 392

Usage:

TCFILTER allows you to set the filter used by the *Take Command* List View to determine what file and folder names to display. For example, to only display files with a .DOC extension in the List View:

tcfilter *.doc

See Regular Expression Syntax 496 for details on valid regular expressions.

Option:

/C Clear the current filter

3.13.12(TCTOOLBAR

Purpose: Change the tool bar buttons.

Format: TCTOOLBAR [/C /U /R filename] button [, flags, icon, label, command]

button The button number (1 - 50)

flags 0=Start new tab, 1=Send to current tab

icon lcon to display on button

label The button label

command The command to execute or keystrokes to send

Usage:

TCTOOLBAR lets you configure the *Take Command* tab tool bar buttons (you can also use the Configure Tool Bar dialog available from the Options of menu). The changes you make can be temporary or, with the /U option, written to the TCMD.INI file so that they will be loaded the next time

Take Command starts.

There are a maximum of 50 buttons on the tab tool bar. The **button** parameter must be a number from 1 to 50 to select the button you want to work with. If you enter a command like

```
tctoolbar 1
```

the button with that number will be removed from the tool bar. If you want to add or modify a button, you must include the *flags*, *icon* and/or *label*, and *command* parameters.

The *flags* parameter specifies what happens when you click the button. If *flags* is 0, *Take Command* will use *command* to start a new tab. If *flags* is 1, the *command* text (in KEYSTACK 262) format) is sent to the current tab. You can optionally add 2 to the value of *flags* to insert a separator before the button.

The *icon* parameter allows you to specify the name of an icon file (or an executable file if you want to use its default icon). The icon will be displayed to the left of the button label. If you have entered a *label*, the *icon* parameter is optional.

The *label* parameter specifies the text that appears on the button. If the text contains white space or other special characters, it must be enclosed in double quotes. If you have entered an *icon* file, *label* is optional.

The **command** parameter contains the command to start a new tab (if **flags=0**), or the keystrokes to be sent to the current tab in KEYSTACK [262] format (if **flags=1**) when the button is clicked.

Option:

/C Clear all entries from the toolbar.

/R Load the toolbar button definitions from the specified file. /R will **not** clear an existing toolbar; you must use /C for that. The file should be in the same format as the [Buttons] section in TCMD.INI:

Bn=flags,icon,label,command

n - the button number (1 - 50)
flags - 0=start new tab, 1=send keystrokes to current tab
icon - the icon to display on the label (leave empty for no icon)
label - the label to display on the button
command - the command to execute

/U Write the changed button definition to the **TCMD.INI** file so that it will be included the next time *Take Command* starts.

3.13.13(TEE

Purpose: Copy standard input to both standard output and a file.

Format: TEE [/A /D /T] file...

file One or more files that will receive the "tee-d" output.

/A(ppend) 345 /T(ime) 345 /D(ate) 345

See also: Y 364, piping 101 and redirection 981.

Usage:

TEE is normally used to "split" the output of a program so that you can see it on the display and also save it in a file. It can also be used to capture intermediate output before the data is altered by another program or command.

TEE gets its input from standard input (usually the piped output of another command or program), and sends out two copies: one to standard output, the other to the *file(s)* that you specify. TEE is not likely to be useful with programs which do not use standard output, because these programs cannot send output through a pipe.

For example, to search the file *DOC* for any lines containing the string *Take Command*, make a copy of the matching lines in *TC.DAT*, sort the lines, and write them to the output file *TCS.DAT*:

```
ffind /t"Take Command" doc | tee tc.dat | sort > tcs.dat
```

If you are typing at the keyboard to produce the input for TEE, you must enter a **Ctrl-Z** to terminate the input.

See Piping 10th for more information on pipes.

Option:

/A Append to the file(s) rather than overwriting them.

/D Prefix each line with the current date (in yyyy-mm-dd format).

/T Prefix each line with the current time (in hh:mm:ss.ms format).

3.13.13'TEXT

Purpose: Display a block of text in a batch file.

Format: TEXT

. . ENDTEXT

See also: ECHO 217, ECHOS 219, SCREEN 310, SCRPUT 311, and VSCRPUT 360.

Usage:

TEXT can only be used in batch files. Both TEXT and ENDTEXT must be entered as the only commands on their respective lines.

The TEXT command is useful for displaying menus, tables, special characters, or multiline messages. TEXT will display all lines in the batch file between itself and the terminating ENDTEXT. The display starts at the current display position, which allows you to start its display with other text, e.g., from the ECHOS 219 command.

The lines between TEXT and ENDTEXT are not parsed. As a consequence, no environment variable expansion or other processing is performed, and all lines are displayed exactly as they are stored in the batch file, subject only to the choice of font and codepage differences, if any, between the program which created the file and that in effect during its execution. This makes it easy to include special characters, e.g., < | > in the text. However, if the ANSI X3.64 interpretation option is enabled, you

can change screen colors by inserting ANSI X3.64 escape sequences anywhere in the text block. The ENDTEXT command itself will not be displayed.

You can also use the <u>CLS</u> 18th or the <u>COLOR</u> 18th command to set the default screen colors before executing TEXT.

Redirecting TEXT output

To redirect or pipe the entire block of text, use redirection shown in the Examples show

Warning: If the TEXT command is redirected or piped. and the redirection/piping fails, the lines of the batch file following the TEXT command are executed as if they were commands, causing potential harm. The simplest way to avoid trouble this may cause is to use the ON ERROR COMMAND COMMAND

Examples

The following batch file fragment displays a simple menu:

```
@echo off & cls
screen 2 0
text
Enter one of the following:
   1 - Spreadsheet
   2 - Word Processing
   3 - Utilities
   4 - Exit
endtext
inkey /k"1234" Enter your selection: %%key
```

The example below uses TEXT to display or append to a file (specified as the optional parameter of the batch file):

```
@echo off
setlocal
setdos /x-6
set dest=%@if[%# GT 0,>> %1,]
setdos /x+6
set repeat=0
on error (unset dest & goto PROBLEM)
: PROBLEM
iff %repeat GT 1 then
  echo Repeated problems - quitting
 quit
endiff
set repeat=%@inc[%repeat]
text %dest
| Logical Drives |
endtext
subst %dest
echo. %dest
if %_transient eq 1 .and. %# EQ 0 pause
endlocal
```

3.13.137TIME

Purpose: Display or set the current system time.

Format: TIME [/S [server] /T] [hh [:mm:ss]]] [AM | PM]

hh The hour (0 - 23)
 mm The minute (0 - 59)
 ss The second (0 - 59)

/S(erver time) 347 /T (Display only) 347

See also: DATE 189.

Usage:

If you don't enter any parameters, TIME will display the current system time and prompt you for a new time. Press Enter if you don't wish to change the time; otherwise, enter the new time:

```
[c:\] time
Thu Jan 31, 2008 9:30:06
Enter new date (mm-dd-yy):
```

TIME defaults to 24-hour format, but you can optionally enter the time in 12-hour format by appending **a**, **am**, **p**, or **pm** to the time you enter. For example, to enter the time as 9:30 am:

```
time 9:30 am
```

The operating system adds the system time and date to the directory entry for every file you create, modify, or access. If you keep both the time and date accurate, you will have a record of when you last updated each file.

Options:

/S server Sets the date and time from the specified internet time server. If no server is specified, TIME uses the server defined in the <u>Time Server sand</u> configuration option (the default is clock.psu.edu).

Displays the current time but does not prompt you for a new time. You cannot specify a new time on the command line with π . If you do, the new time will be ignored.

3.13.13.TIMER

Purpose: TIMER is a system stopwatch.

Format: TIMER [ON | OFF | /Q /S /1 /2 /3]

ON Force the stopwatch to reset and start

OFF Force the stopwatch to stop

/1 stopwatch #1 (default) /Q quiet
/2 stopwatch #2 /S split
/3 stopwatch #3

348

Usage:

The TIMER command accepts its parameters in any order, and acts on the specified one of three possible timers (system stopwatches) by turning it on or off, or by displaying its current elapsed time. The TIMER command with neither of the keywords **ON** and **OFF** nor the **/S** option toggles the state of the timer.

If you execute TIMER or TIMER /S when the timer is off, or execute TIMER ON at any time, the current time of day is displayed, and the stopwatch starts from :

```
[c:\] timer
Timer 1 on: 12:21:46
```

If you execute TIMER /S when the timer is on, the elapsed time is displayed:

```
[c:\] timer /s
Timer 1 Elapsed time: 0:00:12.06
```

If you execute TIMER when it is on, or execute TIMER OFF, the stopwatch stops, the current time and the elapsed time are displayed, and the elapsed time is reset:

```
[c:\] timer
Timer 1 off: 12:21:58
Elapsed time: 0:00:12.06
```

There are three stopwatches available (1, 2, and 3) so you can time multiple overlapping events. By default, TIMER uses stopwatch #1.

TIMER is particularly useful for timing events in batch files. For example, to time both an entire batch file, and an intermediate section of the same file, you could use commands like this:

```
rem Turn on timer 1
timer
rem Do some work here
rem Turn timer 2 on to time the next section
timer /2
rem Do some more work
echo Intermediate section completed
rem Display time taken in intermediate section
timer /2
rem Do some more work
rem Now display the total time
timer
```

The smallest interval TIMER can measure depends on the operating system you are using, your hardware, and the interaction between the two. However, it should never be more than 60 ms.

You can also retrieve the elapsed time of a timer using the @TIMER[] 463 function.

Options:

- /1 Use timer #1 (the default).
- /2 Use timer #2.
- /3 Use timer #3.

- /Q Don't display any messages.
- /S Display a split time without stopping the timer. To display the current elapsed time but leave the timer running:

```
[c:\] timer /s
Timer 1 elapsed: 0:06:40.63
```

- **ON** Start the timer regardless of its previous state (on or off). Otherwise the TIMER command toggles the timer state (unless /S is used).
- **OFF** Stops the timer.

3.13.134TITLE

Purpose: Change the window title.

Format: TITLE [/P] title

/P(rompt characters) 349

title The new window title.

See also: the TITLEPROMPT [370] variable and the ACTIVATE [152] and WINDOW [362] commands.

Usage:

TITLE changes the text that appears in the caption bar at the top of the *TCC* window. You can also change the window title with the WINDOW command or the ACTIVATE command.

The title text should not be enclosed in quotes unless you want the quotes to appear as part of the actual title.

To change the title of the current window to "Title Test":

```
title Title Test
```

Options:

/P Support the special characters in PROMPT [297].

3.13.13!TOUCH

Purpose: Change a file's time stamps [495], and optionally create a file.

Format: TOUCH [/A:[[-][+]rhsdaecjot] /C [/D[acw][date] /E /F /I""text"" /N /Q /R[:acw]file /Sn /T[acw[u]][hh:mm[:ss[.dd]]] file...

file One or more files whose date and/or time stamps are to be changed.

A 350 Attribute select

C 350 Create file

D 350 Date

/N No action

Q Quiet

Reference file

File Selection:

Supports <u>attribute switches</u> 86, extended <u>wildcards</u> 77, <u>ranges</u> 80, <u>multiple file names</u> 87, subdirectories, catalog files 90, and include lists 88.

Usage:

TOUCH is used to change the date and / or time of a file. You can use it to be sure that particular files are included or excluded from an internal command, backup program, compiler MAKE utility, or other program that selects files based on their time and date stamps, or to set a group of files to the same date and time for consistency.

TOUCH should be used with caution, and in most cases should only be used on files you create. Many programs depend on file dates and times to perform their work properly. In addition, many software manufacturers use file dates and times to signify version numbers. Indiscriminate changes to date and time stamps can lead to confusion or incorrect behavior of other software.

By default, TOUCH affects only files. You must utilize the /A 3501: option to include directories. /A:D will select directories only.

Options:

- /A: Select only those files that have the specified attribute(s) set. See Attribute Switches 6 for information on the attributes which can follow /A:.
- Create *file* (as a zero-byte file) if it does not already exist. You cannot use wildcards with /C, but you can create multiple *files* by listing them individually on the command line.
- /D If neither /R | 35th nor /D | 35th are specified, the current date is used. If the /D | 35th option is specified without date, TOUCH will not modify the date even if /R | 35th is also specified. If the /D | 35th option is followed by date, and /R | 35th is not specified, date is used. The date must not be quoted. If both /R | 35th and /D | 35th with date are specified, the one specified later in the command takes effect.

On an LFN drive, you can specify which of the date fields should be set by appending **a**, **c**, or **w** to the **/D** option:

- a Last access date
- c Creation date
- w Last modification (write) date

If you append a ${\bf u}$ to the date field, TOUCH will set the UTC date rather than the local date.

- **/E** Suppress all non-fatal error messages, such as "File not found." Fatal error messages, such as "Drive not ready," will still be displayed. This option is most useful in batch files.
- /F The file systems normally do not permit changing timestamps of read only files. The /F option forces date and time change of read-only files by temporarily removing the read only attribute.

/I"text" Select files by matching text in their descriptions. See Description Ranges 66 for details.

- /N Display what would occur without actually doing it.
- /Q Do not display normal messages.
- The /R option permits duplication of the timestamp of *ref_file*. For example, if you recompile an old program (e.g., to obtain an intermediate file that has long been deleted) you may want to use the timestamp of the source file that was last changed as the timestamp of the newly built duplicate of the original object file to prevent a "make" from attempting to rebuild everything else in the project as shown in the example:

```
touch /r project.c project.obj
```

Another use could be to synchronize files without rendering the current version inaccessible during the synchronization:

```
touch /c /r c:\jpsoft\tcmd.chm %temp\tcmd.chm
copy /u ftp://jpsoft.com/help/tcmd.chm %temp\tcmd.chm
```

In the above example TOUCH creates an empty file with the timestamp of your already existing help file; COPY [182] updates the empty file if a newer version is available (beware of timestamp synchronization across the Internet!).

On an LFN drive, you can specify which of the date/time fields should be used by appending **a**, **c**, or **w** to the **/R** option:

- Last access date and time (on VFAT volumes access time is always midnight).
- c Creation date and time
- w Last modification (write) date and time
- /S TOUCH all matching files in the specified directory and its subdirectories. Do not use /S with @file lists. See @file lists 90 for details.

If you specify a number after the /S, TOUCH will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.

If neither /R 35th nor /T 35th are specified, the current time is used. If the /T 35th option is specified without time, TOUCH will not modify the time even if /R 35th is also specified. If the /T 35th option is followed by time, and /R 35th is not specified, time is used. (Time must not be quoted). If both /R 35th and /T 35th with time are specified, the one specified later in the command takes effect.

On an LFN drive, you can specify which of the time fields should be set by appending **a**, **c**, or **w** to the **/T** option:

- Last access time (on VFAT volumes access time is always midnight).
- c Creation time
- w Last modification (write) time

If you append a ${\bf u}$ to the time field, TOUCH will set the UTC time rather than the local time.

3.13.13(TRANSIENT

Purpose: Toggle the shell's transient mode

Format: TRANSIENT [on | off]

Usage:

TRANSIENT allows you to change the shell's transient mode (i.e., whether it was started with a /C), so that you can make a transient session permanent (or vice versa).

3.13.137TREE

Purpose: Display a graphical directory tree.

Format: TREE [[/A:[[-]+]rhsadecijopt /A /B /D /F /H /Nj /P /S[n] /T[:a|c|w] /Z] dir...

dir The directory to use as the start of the tree. If one or more directories are specified, TREE will display a tree for each specified directory. If none are specified, the tree for the current working directory is displayed.

/A: (Attribute select) | 352 |/N (disable option) | 353 |/A(SCII) | 352 |/P(ause) | 353 |/B(are) | 353 |/S (file size) | 353 |/D(escriptions) | 353 |/T (ime and date) | 353 |/F(iles) | 353 |/Z (file size) | 353 |/H(idden directories) | 353 |

File Selection:

Supports <u>attribute switches</u> 86, extended <u>wildcards</u> 77, <u>ranges</u> 80 (with **/F**), and <u>multiple file names</u> 87

Usage:

The TREE command displays a graphical representation of the directory tree using standard or extended ASCII characters. For example, to display the directory structure on drive C:

```
[c:\] tree c:\
```

TREE uses the standard line drawing characters in the U.S. English extended ASCII character set. If your system is configured for a different country or language, or if you use a font which does not include these line drawing characters, the connecting lines in the tree display may not appear correctly (or not appear at all) on your screen. To correct the problem, use /A 352, or configure the *TCC* to use a font which can display standard extended ASCII characters.

You can print the display, save it in a file, or view it with LIST 1264 by using standard redirection 1981 symbols. Be sure to review the /A 1352 option before attempting to print the TREE output. The options discussed below specify the amount of information included in the display.

Options:

Display the tree using standard ASCII characters. You can use this option if you want to save the directory tree in a file for further processing or print the tree on a printer which does not support the graphical symbols that TREE normally uses.

/A:[..] Select only those files that match the specified attribute(s). See Attribute Switches 86

for details.

- /B Display the full pathname of each directory, without any of the line-drawing characters.
- **/D** Display file and directory descriptions.
- **/F** Display files as well as directories. If you use this option, the name of each file is displayed beneath the name of the directory in which it resides.
- /H Display hidden as well as normal directories. If you combine /H and /F 353, hidden files are also displayed.
- **/N** Disables the specified options:
 - j Skip junctions (when used with /S 353)
- Wait for a key to be pressed after each screen page before continuing the display. Your options at the prompt are explained in detail under Page and File Prompts 102.
- If you specify a number after the /S, TREE will limit the subdirectory recursion to that number. For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.
- Display the time and date for each directory. If you combine /T and /F 353, the time and date for each file will also be displayed.

By default, the time and date shown will be of the last modification. You can select a specific time and date stamp by using the following variations of π :

```
T:a Last access date and time (access time is not displayed on VFAT and FAT32 volumes).

T:c Creation date and time.
```

/T:w Last modification ("write") date and time (default).

/Z Display the size of each file. This option is only useful when combined with /F 3531.

3.13.13(TRUENAME

Purpose: Find the full, true path and file name for a file

Format: TRUENAME file

See also: The @TRUENAME 464 variable function.

Usage:

Network reassignments, junctions, symbolic links, and the SUBST command can obscure the true name of a file. TRUENAME "sees through" these obstacles and reports the fully qualified name of a file.

The following example uses TRUENAME to get the true pathname for a file:

```
[c:\] subst d: c:\util\test
[c:\] truename d:\test.exe
```

c:\util\test\test.exe

3.13.13TYPE

Purpose: Display the contents of the specified file(s).

Format: TYPE [/A:[[-][+]rhsadecijopt] /l"text" /L /P] [@file] file...

file The file or list of files that you want to display.

@file A text file containing the names of the files to display, one per line (see @file

lists 90 for details).

/A: (Attribute select) | 355 | /L(ine numbers) | 355 | /P(ause) | 355 |

See also: HEAD 249, TAIL 339, LIST 264).

File Selection

Supports <u>attribute switches</u> (86), extended <u>wildcards</u> (77), <u>ranges</u> (80), <u>multiple file names</u> (87), and <u>include</u> (186), and <u>include</u>

Internet: Can be used with FTP and HTTP servers 93, e.g.

```
type "http://jpsoft.com/notfound.htm"
```

Usage:

The TYPE command displays a file. It is normally only useful for displaying text files (i.e. alphanumeric characters arranged in lines separated by CR/LF). Most text files use either ASCII or Unicode.

Executable files (.COM and .EXE) and many data files may be unreadable when displayed with TYPE because they include non-alphanumeric characters or unusual line separators.

To display the files *MEMO1* and *MEMO2*:

```
type /p memo1 memo2
```

You can press **Ctrl-S** to pause TYPE's display and then any key to continue.

To display text from the clipboard use **CLIP**: as the file name. CLIP: will not return any data if the clipboard does not contain text. See Redirection for more information on CLIP:.

You will probably find LIST to be more useful for displaying files on the screen. The TYPE /L command used with redirection street is useful if you want to add line numbers to a file, for example:

```
type /1 myfile > myfile.num
```

NTFS File Streams

TYPE supports file streams on NTFS drives. You can type an individual stream by specifying the stream name, for example:

```
type streamfile:s1
```

See NTFS File Streams 496 for additional details.

Options:

/A: Select only those files that have the specified attribute(s) set. See Attribute Switches for information on the attributes which can follow /A:. Do not use /A: with @file lists. See @file lists | 90 | for details.

/I"text" Select files by matching text in their descriptions. The text can include wildcards and extended wildcards. The search text must be enclosed in double quotes, and must follow the /I immediately, with no intervening spaces. You can select all filenames that have a description with /I"[?]*", or all filenames that do not have a description with /I"[]". Do not use /I with @file lists. See @file lists 90 for details.

/L Display a line number preceding each line of text.

/P Prompt after displaying each page. Your options at the prompt are explained in detail under Page and File Prompts 102.

3.13.14(UNALIAS

Purpose: Remove aliases from the alias list.

Format: UNALIAS [/Q /R file... (alias ...)] alias...

or UNALIAS *

alias One or more aliases to remove from memory.

file One or more files from which to read the aliases to be undefined.

/Q(uiet) 356 /R(ead file) 356

See also: ALIAS 154 and ESET 222.

Usage:

TCC maintains a list of the aliases that you have defined. The UNALIAS command will remove aliases from that list. UNALIAS supports wildcards in the alias name.

For example, to remove the alias DDIR:

unalias ddir

To remove all the aliases:

unalias *

To remove all the aliases that begin with "DD":

unalias dd*

You can delete all matching aliases except for those specified by enclosing the exceptions in parentheses. For example, to remove all aliases beginning with "a" except for *alias1* and *alias2*:

unalias (alias1 alias2) a*

If you keep aliases in a file that can be loaded with the ALIAS /R 154 command, you can remove the

aliases by using the UNALIAS /R command with the same file name:

```
unalias /r alias.lst
```

This is much faster than removing each alias individually in a batch file, and can be more selective than using UNALIAS *. UNALIAS /R accepts all of the alias definition formats you can use in a file for ALIAS /R.

Options:

- Prevents UNALIAS from displaying an error message if one or more of the aliases does not exist. This option is most useful in batch files, for removing a group of aliases when some of the aliases may not have been defined.
- Read the list of aliases to remove from a file. The file format should be the same format as that used by the ALIAS /R ommand. You can use multiple files with one UNALIAS /R command by placing the names on the command line, separated by spaces:

```
unalias /r alias1.lst alias2.lst
```

UNALIAS /R will read from stdin [535] if no filename is present and input is redirected.

3.13.14 UNFUNCTION

Purpose: Remove user-defined functions from the function list.

Format: UNFUNCTION [/Q /R file... (function ...)] function...

or

UNFUNCTION *

function One or more functions to remove from memory.

file One or more files from which to read functions to be undefined.

/Q(uiet) 357 /R(ead file) 357

See also: FUNCTION 242 and ESET 222.

Usage:

TCC maintains a list of the functions that you have defined. The UNFUNCTION command will remove functions from that list. UNFUNCTION supports wildcards in the function name.

To remove the function DDIR:

```
unfunction ddir
```

To remove all the functions:

```
unfunction *
```

To remove all the functions that begin with "DD":

```
unfunction dd*
```

You can delete all matching functions except for those specified by enclosing the exceptions in parentheses. For example, to remove all functions beginning with "f" except for *func1* and *func2*:

unfunction (func1 func2) f*

If you keep functions in a file that can be loaded with the <u>FUNCTION /R [242]</u> command, you can remove the functions by using the UNFUNCTION /R command with the same file name:

```
unfunction /r function.lst
```

This is much faster than removing each function individually in a batch file, and can be more selective than using UNFUNCTION *.

Options:

- **/Q** Prevents UNFUNCTION from displaying an error message if one or more of the functions does not exist. This option is most useful in batch files, for removing a group of functions when some of the functions may not have been defined.
- Read the list of functions to remove from a file. The file format should be the same format as that used by the FUNCTION /R 242 command. You can use multiple files with one UNFUNCTION /R command by placing the names on the command line, separated by spaces:

```
unfunction /r function1.lst function2.lst
```

UNFUNCTION /R will read from stdin 535 if no filename is present and input is redirected.

3.13.14;UNSET

Purpose: Remove variables from the environment or the registry.

Format: UNSET [/D /E /Q /S /U /V /R file... (name ...)] name [name...]}]

or UNSET *

name One or more variables to removed (wildcards accepted except for registry

variables).

file One or more files from which to read variables to be removed.

 /D(efault) | 358 |
 /S(ystem) | 358 |

 /E(nvironment) | 358 |
 /U(ser) | 358 |

 /Q(uiet) | 358 |
 /V(olatile) | 358 |

 /R(ead) | 358 |
 /V(olatile) | 358 |

See also: ESET 222 and SET 319.

Usage:

UNSET removes one or more variables from the environment or from the Windows Registry.

For example, to remove the environment variable CMDLINE:

```
unset cmdline
```

If you use the command UNSET *, all of the environment variables will be deleted:

```
unset *
```

You can delete all matching variables except for those specified by enclosing the exceptions in parentheses. For example, to remove all variables beginning with "v" except for *var1* and *var2*:

```
unset (var1 var2) v*
```

UNSET can be used in a batch file, in conjunction with the <u>SETLOCAL [326]</u> and <u>ENDLOCAL [220]</u> commands, to clear the environment of variables that may cause problems for applications run from that batch file.

For more information on environment variables, see the <u>SET</u> ommand and the general discussion of the environment set.

Note: You cannot use UNSET with GOSUB variables 247).

Use caution when removing environment variables, and especially when using **UNSET** *. Many programs will not work properly without certain environment variables; for example, *TCC* depends on PATH.

Registry Variables: Default, System, User, and Volatile registry variables can be manipulated with the UNSET command's /D | 358), /S | 358), /U | 358) and /V | 358) switches, respectively. To remove the variable from both the registry and from the local environment, use both the /E | 358) switch and the registry variable selection switch together. (You cannot use wildcards for the variable name.) For example, to remove the volatile variable *myvar* from both the registry and the local environment, use:

```
unset /v /e myvar
```

Use caution when directly removing registry variables as they may be essential to various Windows processes and applications.

Options:

- **/D** Delete a default variable from the registry (HKCU\.DEFAULT\Environment).
- When used together with one of /D 3221, /S 3221, /U 3231, or /V 3231, unsets both the registry variable and the local environment variable.
- **/Q** Prevents UNSET from displaying an error message if one or more of the variables do not exist. This option is most useful in batch files, for removing a group of variables when some of the variables may not have been defined.
- Read environment variables to be UNSET from a file. This is much faster than using multiple UNSET commands in a batch file, and can be more selective than **UNSET***. The file format may be the same as that used by the <u>SET [319]</u> /R command (see <u>SET [319]</u> for more details), or it could just be one variable per line, wildcards not processed.

UNSET /R will read from STDIN [535] if no filename is present and input is redirected.

- /S Delete a system variable from the registry (HKLM\System\CurrentControlSet\Control\Session Manager\Environment).
- /U Delete a **user** variable from the registry (HKCU\Environment).
- N Delete a **volatile** variable from the registry (HKCU\Volatile Environment)

3.13.14:USBMONITOR

Purpose: Monitor USB device connection and disconnection

Format: USBMONITOR [/C [name]]

USBMONITOR name CONNECTED | DISCONNECTED n command

name Device name

n Number of repetitions (or **FOREVER**)

command Command to execute when condition is triggered

/C(lear) 359

Usage:

The USB device name can include wildcards. You can use either the device ID or the "friendly" name for the device.

The command line will be parsed and expanded before USBMONITOR is executed, so if you want to pass redirection characters or variables to **command** you will need to protect them (by enclosing in single back quotes, doubling the %'s, or using command grouping).

If you don't enter any arguments, USBMONITOR will display the USB devices it is currently monitoring.

The monitoring runs asynchronously in a separate thread. When the condition is triggered, the command will be executed immediately. This may cause problems if you try to write to the display or access files while the main *TCC* thread is also performing I/O. You may need to use <u>START</u> or <u>DETACH</u> in *command* to avoid conflicts.

USBMONITOR creates two environment variables when a device is connected or disconnected that can be queried by *command*. The variables are deleted after *command* is executed.

usbdeviceid The device ID

_usbname The "friendly" name of the device

_usbcount The number of times the command has been triggered

Options:

/C If name is specified, remove the monitor for that USB device. Otherwise, remove all

USB monitors.

3.13.144VER

Purpose: Display the **TCC** and operating system versions.

Format: VER [/R]

/R(evision) 360

Usage:

Version numbers consist of a one-digit major version number, a separator, and a one- or two-digit minor version number. VER uses the default decimal separator defined by the current country information. The VER command displays version numbers for both *TCC* and Windows:

```
[c:\] ver
Take Command 9.0.80 Windows Vista [Version 6.0.6000]
```

Option:

/R Display the TCC and operating system internal revision level (if any), plus your registered name.

3.13.14\(\text{VERIFY}\)

Purpose: Enable or disable disk write verification or display the verification state.

Format: VERIFY [ON | OFF]

Usage:

Disk write verification cannot actually be enabled under Windows. *TCC* supports VERIFY as a "donothing" command, for compatibility with CMD.EXE. This avoids **unknown command** errors in old batch files which use the VERIFY command. You can set verification for file copying with the COPY /V option.

If used without any parameters, VERIFY will display the state of the verify flag:

```
[c:\] verify
VERIFY is ON
```

3.13.14(VOL

Purpose: Display disk volume label(s).

Format: VOL [d:] ...

d: The drive or drives to search.

Usage:

Each disk may have a volume label, created when the disk is formatted or with the external LABEL command. Also, every disk formatted with Windows has a volume serial number.

The VOL command will display the volume label and, if available, the volume serial number of a disk volume. If the disk doesn't have a volume label, VOL will report that it is "unlabeled." If you don't specify a drive, VOL displays information about the current drive:

```
[c:\] vol
Volume in drive C: is MYHARDDISK
```

If available, the volume serial number will appear after the drive label or name.

To display the disk labels for drives A and B

```
[c:\] vol a: b:
Volume in drive A: is unlabeled
Volume in drive B: is BACKUP_2
```

VOL will also return volume information for UNC names.

See also: @LABEL 446.

3.13.147VSCRPUT

Purpose: Display text vertically in the specified color.

Format: VSCRPUT row col [BRIght] fg ON [BRIght] bg text

row col Starting row
 fg Foreground text color
 bg Background text color
 text The text to display

See also: SCRPUT 311.

Usage:

VSCRPUT writes text vertically on the screen rather than horizontally. It can be used for simple graphs and charts generated by batch files.

Like the SCRPUT command, it uses the colors you specify to write the text. See <u>Colors and Color</u> <u>Names [518]</u> for details about colors and color names, and notes on the use of bright background colors.

The **row** and **column** values are zero-based, so on a 25 line by 80 column window valid rows are 0 - 24 and valid columns are 0 - 79. VSCRPUT checks for a valid **row** and **column**, and displays a "Usage" error message if either value is out of range.

The maximum **row** value is determined by the current height of the **TCC** window. The maximum **column** value is determined by the current virtual screen width (see <u>Resizing the Take Command Window 68</u>) for more information).

You can also specify the *row* and *column* as offsets from the current cursor position. Begin the value with a plus sign [+] to move down the specified number of rows or to the right the specified number of columns before displaying text, or with a minus sign [-] to move up or to the left.

If you specify 999 for the **row**, VSCRPUT will center the text vertically. If you specify 999 for the **column**, VSCRPUT will center the text horizontally.

VSCRPUT does not move the cursor when it displays the text.

The following batch file fragment displays an X and Y axis and labels them:

```
cls bright white on blue
drawhline 20 10 40 1 bright white on blue
drawvline 2 10 19 1 bright white on blue
scrput 21 20 bright red on blue X axis
vscrput 8 9 bright red on blue Y axis
```

3.13.148WHICH

Purpose: Display the command type and what it would execute.

Format: WHICH [/A] command [command ...]

command One or more commands or files.

/A(II) 362

Usage:

WHICH displays information about internal and external commands, Aliases 128 (including keystroke aliases), and files. When a file matches an applicable Executable Extension or Windows File Association of that data will be displayed. The exact information reported depends on the type of command or file you specify. For example:

$[c:\]$ which cdd buildtree notepad test.btm test.exe test.xyz test.doc donothing

```
CDD is an internal command buildtree is an alias : cdd /s notepad is an external: C:\windows\notepad.exe test.btm is a batch file : C:\test.btm test.exe is an external : C:\test.exe test.xyz is an executable extension : C:\path\mybatch.btm C:\test.xyz test.doc is associated with : C:\Program Files\Microsoft Office\OFFICE11\WINWORD.EXE donothing is an unknown command
```

If the command is an abbreviated alias, WHICH will display the full name; i.e.:

```
[c:\] alias opt*ions=*option
[c:\] which opt
opt*ions is an alias : *option
```

WHICH can also recognize Plugin [293] commands, REXX [142] files, EXTPROC [143] files, and associated files.

Note: WHICH does not support wildcard specifications unless you use the /A option. Parameters must be actual commands or actual file names (including variable and function references as in "which "comspec"). If a filename includes white space or special characters, it must be enclosed in double quotes. A file specified without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be on the current PATH be a considered without an explicit path must be a considere

See Executable Files and File Searches 504 for details on the order in which various locations are searched.

```
See also: @SEARCH 458, ASSOC 162, FTYPE 241.
```

Option:

/A Display all matching commands. (Normally WHICH only displays the first match.)

3.13.14\WINDOW

Purpose: Minimize or maximize the current window, restore the default window size, or change the

window title.

Format: WINDOW [MAX | MIN | RESTORE | HIDE | DISABLE | ENABLE | TRAY | TOPMOST |

NOTOPMOST | TOP | BOTTOM | /POS=left,top,width,height | /SIZE=rows,columns |

/TRANS=n | "newtitle"]

newtitleA new title for the windowheightNew height of windowwidthNew width of window

left New position of the left border of windowtop New position of the top border window

rowscolumnsNew height of windowNew width of window

/POS(ition) 363 /SIZE (of screen buffer) 362

See also: ACTIVATE 152 and TITLE 349.

Usage:

WINDOW is used to control the appearance and title of the current (*TCC*) window. Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

If you are running in a *Take Command* tab window, the MAX, MIN, RESTORE, HIDE, TRAY, and /TRANS options will be sent to the main *Take Command* window, not the *TCC* window.

Note: You can specify only one **WINDOW** option at a time. The different options cannot be combined in a single **WINDOW** command. To perform multiple operations you must use multiple **WINDOW** commands.

Options:

Option	_	Take	Description
	_	Command	
/POS=left,top,width,heig ht	X	x	Set the window position and size on the desktop. The values are specified in pixels. <i>Left</i> and <i>top</i> refer to the position of the top left corner of the window relative to the top left corner (0,0) of the screen. The <i>width</i> and <i>height</i> values determine the window size. The window may be so sized and positioned that parts of it are beyond the physical area of the display. The / before the keyword is optional.
/TRANS=n		x	Set the transparency level of the Take Command window. n is an value from 0 (invisible) to 255 (opaque).
newtitle	X	x	Changes the window title. The title text must be enclosed in double quotes. (The quotes will not appear as part of the actual title as displayed.) Setting the title inside a batch file will only change the window title while the batch file is executing.
MAX	Х	X	Expands the window to its maximum size.
MIN	х	x	Reduces the window to an icon.
RESTORE	х	x	Returns the window to its default size and location.
HIDE	x	x	Makes the window invisible. Use RESTORE to make the window visible.
TRAY	х	x	Moves the window to the taskbar tray.
/SIZE=rows,columns	X		Specify the <i>TCC</i> screen buffer size. Due to the design of Windows console sessions, you cannot use /SIZE to reduce the size of the screen buffer; it can only be increased. Does not affect window size.
DISABLE	Х	x	Disable window input (mouse and keyboard)
ENABLE	х	x	Enable window input
TOPMOST		x	Keeps the <i>Take Command</i> window on top of all other windows until it closes, or NOTOPMOST is used.
NOTOPMOST		x	Allows other windows to overlay the Take Command window (this is the normal state for most windows).
TOP		x	Moves the <i>Take Command</i> window to the top of the window order, above all other non-TOPMOST windows.
ВОТТОМ		x	Moves the Take Command window to the bottom of the window order.

3.13.15(WMIQUERY

Purpose: Query the Windows Management Interface

Format: WMIQUERY [/A /B /C /H] namespace "query string" [index]

/A(II instances) 364 /C(lasses) 364 /H(eader) 364

namespace The namespace to query

"query string" WQL query string index Class instance

Usage:

You can use a single period . for *namespace* to default to **root\cimv2**.

For more details on what is available, see the WMI and WQL documentation on MSDN (msdn.microsoft.com), and download the "WMI Code Creator" from Microsoft and browse the available namespaces, classes, and properties.

For example, to guery the *name* property from the *Win32_Processor* class:

wmiquery root\cimv2 "SELECT name FROM Win32_Processor"

To query available classes:

```
wmiquery /A root "select name from __namespace"
```

Options:

- /A Display all class instances starting at "index".
- **/B** Separate class instances with a blank line.
- **IC** Display all the matching class names for the specified namespace. "**query string**" is the filter to apply to the returned values; it can contain wildcards. For example:

```
wmiquery /c . "win32_q*"
```

/H Display a header for class instances.

3.13.15'Y

Purpose: Copy standard input to standard output, and then copy the specified file(s) to standard

output.

Format: Y file ...

file The file or list of files to send to standard output.

See also: TEE 344, piping 101 and redirection 98.

Usage:

The Y command copies input from standard input (usually the keyboard) to standard output (usually

the screen). Once the input ends, the named files are appended to standard output.

For example, to get text from standard input, append the files *MEMO1* and *MEMO2* to it, and send the output to *MEMOS*:

```
y memo1 memo2 > memos
```

The Y command is most useful if you want to add redirected data to the beginning of a file instead of appending it to the end. For example, this command copies the output of DIR, followed by the contents of the file DIREND, to the file DIRALL:

```
dir | y dirend > dirall
```

If you are typing at the keyboard to produce input text for Y, you must enter a **Ctrl-Z** to terminate the input.

When using Y with a pipe you must take into account that the programs on the two ends of the pipe run simultaneously, not sequentially.

See Piping 101 for more information on pipes.

3.14 Variables & Functions

The environment is a collection of information about your system that every program receives. Each entry in the environment consists of a variable name and a string value.

Usage

You can automatically substitute the text for the variable name in any command. To create the substitution, include a percent sign % and the variable name on the command line or in an alias or batch file, e.g., %comspec. If the name of the variable whose value you want to use is an expression, you can enclose the expression in brackets, e.g., %[%n].

You can create, alter, view, and delete environment variables with the <u>SET</u> 319, <u>ESET</u> 222, and <u>UNSET</u> 357 commands.

A few environment variables have special meanings for **TCC** (they are listed in System Variables 367).

TCC also supports two special types of variables:

- Internal variables [372] are similar to environment variables, but are interpreted internally by *TCC*, and are not visible in the environment. They provide information about your system for use in batch files and aliases. Some of them provide access to information that may change even during the execution of a single command or batch file.
- Variable functions are referenced like environment variables, but perform additional actions like file handling, string manipulation and arithmetic calculations. In addition to the variable functions that are internal to *TCC*, you can use the <u>FUNCTION</u> command to create your own. These latter ones are referred to as user defined functions or UDFs.

Note: *TCC* inherits its initial environment from the process which started it. That process might be Explorer or another existing Windows process which launched the current *TCC* session. Note that if the starting process's environment is changed (through registry modifications, for example) while *TCC* is already running, those changes will not be automatically reflected in *TCC*'s current environment. See the SET [319] command for details.

You use the <u>SET [319]</u> command to create a new environment variable. <u>SET [319]</u> can also modify or delete a single environment variable, or display the value of one or more environment variables. <u>ESET [322]</u> allows you to edit an environment variable. <u>UNSET [357]</u> deletes environment variables. For example, you can create a variable named **BACKUP** like this:

```
set BACKUP=*.bak;*.bk
```

If you then type:

```
del %BACKUP
```

it is equivalent to having type the command:

```
del *.bak; *.bk
```

The environment variable names you use this way may contain any alphabetic or numeric characters, the underscore character _, and the dollar sign \$. You can force acceptance of other characters by including the full variable name in square brackets, like this: %[AB##2]. You can also indirectly reference environment variables using square brackets. For example %[%var1] means "the contents of the variable whose name is stored in *VAR1*". A variable referenced with this technique cannot contain more than 8,191 characters.

In addition, *TCC* uses the environment to keep track of the default directory on each drive. Windows only tracks the default directory of the current drive; *TCC* overcomes this limitation by saving the default directory for each drive in the environment, using hidden variable names. Each variable begins with an equal sign followed by the drive letter and a colon (for example, =C:). You cannot view or change these variables with the <u>SET</u> ommand.

The trailing percent sign that was traditionally required for environment variable names is not usually required by **TCC**, which accept any character that cannot be part of a variable name as the terminator. However, the trailing percent can be used to maintain compatibility.

The trailing percent sign is needed if you want to append variable values. The following examples show the possible interactions between variables and literal strings. First, create two environment variables called ONE and TWO this way:

```
set ONE=abcd set TWO=efgh
```

Now the following combinations produce the output text shown:

original	expanded	method
%ONE%TWO	abcdTWO	("%ONE%" + "TWO")
%ONE%TWO%	abcdTW0	("%ONE%" + "TWO%")
%ONE%%TWO	abcdefgh	("%ONE%" + "%TWO")
%ONE%%TWO%	abcdefgh	("%ONE%" + "%TWO%")
%ONE%[TWO]	abcd[TWO]	("%ONE%" + "[TWO]")
%ONE%[TWO]%	abcd[TWO]	("%ONE%" + "[TWO]%")
%[ONE]%TWO	abcdefgh	("%[ONE]" + "%TWO")
%[ONE]%TWO%	abcdefgh	("%[ONE]" + "%TWO%")

If you want to pass a percent sign to a command, or a string which includes a percent sign, you must use two percent signs in a row. Otherwise, the single percent sign will be seen as the beginning of a variable name and will not be passed on to the command. For example, to display the string "We're with you 100%" you would use the command:

```
echo We're with you 100%%
```

You can also use back quotes around the text, rather than a double percent sign. See Parameter Quoting [134] for details.

Environment variables may contain alias names. **TCC** will substitute the variable value for the name, then check for any alias name which may have been included within the value. For example, the following commands would generate a 2-column directory of the .TXT files:

```
alias d2 dir /2
set cmd=d2
%cmd *.txt
```

For compatibility with some peculiar syntax introduced in recent **CMD.EXE** versions, *TCC* supports:

%var:string1=string2%

Substitutes the second string for all instances of the first string in the variable.

in the variable

%var:~x[,y]% Returns the substring starting at the xth character position (base

0) and continuing for y characters. If y is not specified, returns the remainder of the string. If x is negative, starts from the end

of the string.

For string manipulations, we suggest you rely instead on the much more flexible <u>Variable Functions</u> 404

3.14.1 System Variables

The variables below have special meaning for *TCC*:

	Directory navigation search list
	Command line after full expansion
	Directory colorization specification
COMSPEC 368	Command processor specification
	File completion control variable
HISTORYEXCLUSION	List of commands excluded from the command history 106
368	
PATH 368	Executable program location search list
PATHEXT 369	Ordered search list of extensions of executable programs
	Command prompt format specification
RECYCLEEXCLUDE 369	List of files excluded from the recycle bin
TCMD 370	Take Command's pathname
TCMDVER 370	Take Command's version number
TEMP 370	Directory for temporary files
TITLEPROMPT 370	Command processor window title bar specification
TMP 370	Directory for temporary files
TREEEXCLUDE 370	List of directories excluded from JPSTREE.IDX
VARIABLEEXCLUDE 370	Variables to exclude from SET list

3.14.1.1 CDPATH

CDPATH specifies where to search for directories specified in CD 177, CDD 178, and PUSHD 299 commands and in automatic directory changes 76. See the CDPATH feature 72 for details.

This feature is maintained for backwards compatibility, but has largely been replaced by Extended Directory Searches 73.

3.14.1.2 CMDLINE

CMDLINE is set by **TCC** to the fully expanded text of the currently executing command line just before invoking any external command (.COM, .EXE, .BTM, .BAT or .CMD), unless the command line is prefaced with @ to prevent echoing, in which case **CMDLINE** will be removed.

3.14.1.3 COLORDIR

COLORDIR controls directory display colors used by <u>DIR</u> 1981. See <u>Color-Coded Directories</u> 2031 for a complete description of the format of this variable.

3.14.1.4 COMSPEC

Many programs expect the value of **COMSPEC** to contain the full path and name of the current character-mode command processor, e.g.

```
c:\program files\jpsoft\tcmd9\tcc.exe
```

TCC automatically sets COMSPEC to point to TCC.EXE on startup. If you need to run a program from **TCC** which utilizes COMSPEC to locate a command processor to process commands or batch files that are not compatible with **TCC**, you may set COMSPEC to the command processor your program expects before you start it.

3.14.1.5 FILECOMPLETION

FILECOMPLETION specifies the files made available during filename completion for selected commands. See Customizing Filename Completion 115 for a complete description of the format.

3.14.1.6 HISTORYEXCLUDE

HistoryExclude specifies which commands should be excluded from the <u>History List 106</u>. The syntax is:

```
HistoryExclude=cmd1[;cmd2[;cmd3[;...]]]
```

For example, to exclude the <u>DEL</u> 190 and <u>FREE</u> 241 commands, the **Notepad** program and the user-defined alias **MYDIR**:

HistoryExclude=del;free;c:\windows\system32\notepad.exe;mydir

See also: HISTORY 251.

3.14.1.7 PATH

The **PATH** variable specifies the list of directories that *TCC* will search for executable files that aren't in the current directory. **PATH** is used by some application programs to find their own files. See the PATH command for a full description of this variable, which can also be changed or modified with SET 319 and ESET 222.

Note: We strongly recommend that you always leave at least your **WINDOWS** and **SYSTEM32** directories in the **PATH**. The directory where *TCC* resides need not be included in **PATH**.

3.14.1.8 PATHEXT

PATHEXT is expected to contain a list of extensions (including a leading period .), separated by semicolons. For example, to replicate the default extension list used by *TCC*:

```
set pathext=.pif;.com;.exe;.btm;.bat;.cmd;.rex;.rexx
```

If you use a command in a batch file or at the command prompt and all of the following are true:

- the PathExt 47 configuration option is set
- the command is not an alias
- the command is not an internal command
- the command is not a filename with an explicit extension (thus neither an executable extension nor a Windows file association is available)

then *TCC* will search each directory listed in PATH search in turn for a file with its name matching the command and its extension matching one of the extensions in PATHEXT. The 1st directory in PATH searched first, then the 2nd, looking in each for each of the extensions in PATHEXT in the order listed.

Enabling PATHEXT affects only the standard path search. It does not affect searches for files with explicit extensions, which must have either a standard extension (see list above), or one which is either an executable extension [9] or a Windows association.

Caution: If you set the PathExt onfiguration option, and fail to set the PATHEXT variable, path searches without an explicit extension will fail as there will be no extensions for which to search! (Windows XP does define a default value for the PATHEXT variable.)

3.14.1.9 PROMPT

PROMPT defines the command line prompt. It can be set or changed with the PROMPT and ESET commands. See the PROMPT command for details.

See also: TITLEPROMPT 370.

3.14.1.10 RECYCLEEXCLUDE

RECYCLEEXCLUDE specifies files to be excluded from the Recycle Bin.

The syntax is:

```
RecycleExclude=file1[;file2...]
```

file1, file2, ... : file specifications, may include wildcards

For example, to exclude *.lib, *.obj, and *.bak files:

```
RecycleExclude=*.lib;*.obj;*.bak
```

See also: DEL / ERASE 1990 command and the Delete to Recycle Bin 47 configuration option.

3.14.1.11 TEMP

TEMP specifies the directory where *TCC* should store temporary files, unless the <u>TMP</u> (370) variable exists. Many other programs also use TEMP to locate where they should place their temporary files.

3.14.1.12 TCMD

TCMD is the full pathname of the *Take Command* executable. It is only available to the applications running in *Take Command* tab windows.

3.14.1.13 TCMDVER

TCMDVER is the current major version, minor version, and build number of *Take Command*. (For example, "9.00.80".) It is only available to the applications running in *Take Command* tab windows.

3.14.1.14 TITLEPROMPT

TITLEPROMPT can be used to specify the contents of *TCC*'s window title. Modifying its value changes the displayed title immediately. Unsetting it does NOT affect the title. It may contain the special escape-sequences acceptable in PROMPT [297], and all internal variables and functions can be used to generate it.

If you have specified a title for a startup tab in *Take Command*, it will override the **TITLEPROMPT** value.

See also: ACTIVATE 1521, PROMPT [297], TITLE [349] and WINDOW [362].

3.14.1.15 TMP

If **TMP** is defined, it specifies the directory where **TCC** should store temporary files (overriding <u>TEMP</u> 370). Some other programs also use TMP to define where they should place their temporary files.

3.14.1.16 TREEEXCLUDE

TreeExclude specifies which drives and directories to ignore when updating the *JPSTREE.IDX* file. The syntax is:

```
TreeExclude=dir1[;dir2[;dir3[;...]]]
```

Any specified drive/directory and all of its subdirectories will be excluded from *JPSTREE.IDX* update. For example, to exclude everything in **c:\windows**, **d:\temp\temp2**, and everything on drive **g**:

```
TreeExclude=c:\windows;d:\temp\temp2;g:\
```

Setting **TreeExclude** to the base directory of the target of a directory tree copy can speed up the copying considerably.

See also: Extended Directory Searches 73 and CDD 178.

3.14.1.17 VARIABLEEXCLUDE

VariableExclude specifies which environment variables should be excluded from the SET list. The syntax is:

```
VariableExclude=var1[;var2[;var3[;...]]]
```

For example, to exclude the SESSIONNAME, TMP, USERDOMAIN, and USERNAME variables:

SET VariableExclude=sessionname;tmp;userdomain;username

See also: SET 319.

3.14.2 CMD.EXE Compatibility Variables

CMD.EXE has some built-in variables (i.e., which are treated as environment variables but which do not exist in the environment):

CD - the current directory (see also _CWD 384).

CMDCMDLINE - the command line that started the command processor.

CMDEXTVERSION - the command extensions internal version number.

DATE - the current system date (see also _DATE 385)).

RANDOM - a random number between 0 and 32767 (see also @RANDOM 453)).

TIME - the current system time (see also _TIME 393).

TCC supports all of these built-in variables. (In TCC, CMDEXTVERSION will always return 2.)

The variables below are used by some Microsoft command processors, but are ignored by *TCC*. To see their usage by Microsoft and the alternate methods to achieve the same purpose in *TCC*, review:

COPYCMD 37 CMD.EXE default options for COPY 182 command DIRCMD 37 CMD.EXE default options for DIR 198 command

3.14.2.1 COPYCMD variable

The **COPYCMD** variable is used by some versions of CMD.EXE to hold default options for the COPY command. *TCC* does not directly support this variable, i.e, its value has no affect on internal commands. In general, it is more efficient to define several aliases, each including a different combination of options. For example, if you want the COPY command to default to prompting you before overwriting an existing file, you could use this alias:

```
alias COPY=`*copy /r`
```

If you wish to use or create a COPYCMD variable for compatibility with CMD.EXE, you can define an alias to append the contents of that variable to the COPY command:

```
alias COPY=`*copy %copycmd`
```

Now each time the COPY alias is executed, the current value of COPYCMD will modify the execution of the COPY command.

3.14.2.2 DIRCMD variable

The **DIRCMD** variable is used by some versions of CMD.EXE to hold default options for the DIR command. **TCC** does not directly support this variable, i.e, its value has no affect on internal commands. In general, it is more efficient to define several aliases, each including a different combination of options. For example, if you want the DIR command to default to a 2-column display with a vertical sort and a pause at the end of each page, you could use this alias:

```
alias DIR=`*dir /2 /p /v`I
```

If you wish to use or create a DIRCMD variable for compatibility with CMD.EXE, you can define the alias to append the contents of that variable to the DIR command:

```
alias DIR=`*dir %dircmd`
```

Now each time the DIR alias is executed, the current value of DIRCMD will modify the execution of the DIR command.

3.14.2.3 String substitution

For compatibility with some peculiar syntax introduced in recent **CMD.EXE** versions. *TCC* supports:

%var:string1=string2%

Substitutes the second string for all instances of the first string in the variable.

%var:~x[,y]%

Returns the substring starting at the xth character position (base 0) and continuing for v characters. If v is not specified, returns the remainder of the string. If x is negative, starts from the end of the

string.

For string manipulations, we suggest you rely instead on the much more flexible Variable Functions 404

3.14.3 Internal Variables

Internal variables are special variables built into TCC to provide information about your system. They are not stored in the environment, but can be accessed as if they were environment variables in interactive commands, aliases, and batch files.

The values of these variables are stored internally in TCC, and cannot be changed with the SET [319], UNSET 357), ESET 2227 or any other command. The DEFINED status test will always fail, too. You can override any of these variables by defining a new environment variable with the same name. The internal variable can be made available again by unsetting the identically name environment variable. The names of ALL internal variables (except the pseudovariables errorlevel, ?, ??, +, and =) begin with an underscore character to make it easier to distinguish them and to avoid accidentally overriding them.

These internal variables are often used in batch files and aliases to examine system resources and adjust to the current computer settings. You can examine the contents of any internal variable (except %= and %+) from the command line with a command like this:

```
echo %variablename
```

Variables which return a file or directory name from a volume that supports long filenames return it in the same case as it is stored. Returned names are not quoted automatically, you must add the quotes yourself if they are required by the syntax in which you use them.

Some variables return values based on information provided by your operating system. These variables will only return correct information if the operating system provides it. For example, BATTERY 382 will not return accurate results if your operating system and Advanced Power Management drivers do not provide correct information on battery status to TCC.

For a list of internal variables organized by general categories of use, see Internal Variables by Category 376

Examples

You can use internal variables in a wide variety of ways depending on your needs. Here are just a couple of examples. For a more comprehensive set of examples see the *EXAMPLES.BTM* file which came with *TCC*.

Store the current date and time in a file, then save the output of a DIR command in the same file:

```
echo Directory as of %_date %_time > dirsave
dir >> dirsave
```

Use the IFF 254 command to check whether there are enough resources free before running an application:

```
iff %_GDIFREE lt 40 then
    echo Not enough GDI resources!
    quit
else
    d:\mydir\myapp
endiff
```

Call another batch file if today is Monday:

```
if "%_DOW" == "Mon" call c:\cleanup\weekly.bat
```

3.14.3.1 Variables by Name

+ 381	Substitutes the <i>TCC</i> command separator
	Substitutes the <i>TCC</i> escape character
! 380	Last argument of the previous command
? 152	Exit code, last external program
_4ver 38 h	TCC version
_? 380	Exit code, last internal command

_acstatus 381	AC line status
_admin 38f)	1 if an administrator, else 0
_afswcell 38f	OpenAFS workstation cell
_alt 38f)	Alt key depressed: 1, else 0
_ansi 382	ANSI X3.64 status

_batch 382	Batch nesting level
_batchline 382	Line number in current batch file.
_batchname 382	Full path and filename of current batch file.
_batchtype 382	Type of the current batch file
_battery 382	Battery status
_batterylife 382	Remaining battery life, seconds
_batterypercent 382	Remaining battery life, %
_bdebugger 382	Batch debugger active: 1, else 0
_bg 382	Background color at cursor position
	Boot drive letter, without a colon
_build 383	Build number

_capslock 383	CapsLock on: 1, else 0
_cdroms 383	List of the CD-ROM drives
_childpid 383	Process ID of most recent child process
_ci 383	Current text cursor shape in insert mode

	T-
_cmdline 383	Current command line
_cmdproc 383	Command processor name
_cmdspec 383	Full pathname of command processor
_CO 383	Current text cursor shape in overstrike mode
_codepage 383	Current code page number
_column 384	Current cursor column
_columns 384	Virtual screen width
_consolepids 384	Process IDs attached to this console
_country 384	Current country code
_cpu 384	CPU type
_cpuusage 384	CPU time usage (percent)
_ctrl 384	Ctrl key depressed: 1, else 0
_cwd 384	Current drive and directory
_cwds 385	Current drive and directory with trailing \
_cwp 385	Current directory
_cwps 385	Current directory with trailing \
_date 385	Current date
_datetime 385	Current date and time, yyyyMMddhhmmss
_day 385	Current day of the month
_detachpid 385	Process ID of most recent detached process
_disk 385	Current drive
_dname 385	Name of the description file.
dos 385	Operating system type
_dosver 386	Operating system version
dow 386	Current day of the week, English, short
dowf 386	Current day of the week, English, full
dowi 386	Current day of the week as an integer
doy 386	Current day of the year
_drives 386	List of the existing drives
dst 386	Daylight savings time: 1, else 0
dvds 386	List of the DVD drives
	LIGHT OF THE DATE OF THE PERSON OF THE PERSO
echo 386	Echo turned on: 1, else 0
editmode 386	0 if in overstrike mode, 1 if in insert mode
errorlevel 395	Exit code, last external program
_execstr 386	@EXECSTR return code
exit 386	TCC exit return code
expansion 387	SETDOS /X value
_oxpansion ison	02.000// value
fg 387	Foreground color at cursor position
ftperror 387	Last FTP error code
_itperior 307	Last FTF endi code
hdrives 387	List of the fixed drives
_	
_hlogfile 38 ⁷	Current history log file name
_host 387	Host name of local computer.
_hour 387	Current hour
_hwprofile 388	Windows hardware profile if defined
i-llation - A	h.m.
_idleticks 388	Milliseconds since the last user input
_idow 388	Current day of the week, local language, short
_idowf 3881	Current day of the week, local language, full IFTP session active: 1, else 0

irtps lash imonth issh current month name, local language, short imonth issh current month name, local language, short imonth issh current month name, local language, full iminamel ssh implement issodate issh implement		
monthfissh	_iftps 388	IFTPS session active: 1, else 0
impartifiash Current month name, local language, full ininame ss8 Full pathname of the current INI file ip ss8 IP address(es) of local computer.	_imonth 388	Current month name, local language, short
Ininame Isah Full pathname of the current INI file ip sah	imonthf 388	
Paddress(es) of local computer.	ininame 388	
Current date in ISO 9601 format		
Reyboard input character is waiting: 1, else 0 Ialt Issh		
lalt self Last valid drive	_loodato1***1	Surface date in 100 coor format
lalt self Last valid drive	khhit 388	Keyboard input character is waiting: 1 else 0
Last valid drive Left Ctrl key depressed: 1, else 0 Left Ctrl key depressed: 1, else 0 Left Shift Shift Left Shift Shift Left Shift Left Shift Left Shift Left Shift Shift Shift Left Shift Shift Left Shift Shift Shift Left Shift Shift Shift Left Shift Shift Shift Shift Shift Shift Shift Shift Shift Shif		regional input character to waiting. 1, olde c
Last valid drive Left Ctrl key depressed: 1, else 0 Left Ctrl key depressed: 1, else 0 Left Shift Shift Left Shift Shift Left Shift Left Shift Left Shift Left Shift Shift Shift Left Shift Shift Left Shift Shift Shift Left Shift Shift Shift Left Shift Shift Shift Shift Shift Shift Shift Shift Shift Shif	lalt 388	left Alt key denressed: 1 else 0
Left Ctrl key depressed: 1, else 0 Left Shift key depressed: 1, else 0 Left Shift key depressed: 1, else 0		
Current log file name Shift last) Current log file name Left Shift key depressed: 1, else 0		
Left Shift key depressed: 1, else 0		
minute set Current minute Number of monitors monitors set Current month of the year as integer month set Current month of the year, English, full		
monitors seb Number of monitors Current month of the year as integer month seb Current month of the year, English, full	_ISUIII 389	Left Shift key depressed: 1, else 0
monitors seb Number of monitors Current month of the year as integer month seb Current month of the year, English, full	minute and	Comment as in order
monthf अकी Current month of the year as integer monthf अकी Current month of the year, English, full numlock अकी NumLock on: 1, else 0 openafs अकी OpenAFS installed: 1, otherwise 0 osbuild अकी Windows build number parent अकी Name of the parent process pid अकी TCC process ID (numeric) pipe अकी Process ID of parent process ralt अकी Right Alt key depressed: 1, else 0 ready अकी Registered अकी Registered user name row अकी Current cursor row rows अकी Current cursor row Screen height rshift अकी ScrollLock on: 1, else 0 second अकी ScrollLock on: 1, else 0 second अकी ScrollLock on: 1, else 0 second अकी Shell level shell अकी Shell level shell अकी Shell level (old style) shift shift shall Startupd in each shell shall shall Startupd in sol Startupath (asa) STDERR redirected: 1, else 0 stadout (asa) STDERR redirected: 1, else 0 stact (asa) STDERR redirected: 1, else 0		
monthf sss Current month of the year, English, full		
numlock sssh NumLock on: 1, else 0 openafs sssh OpenAFS installed: 1, otherwise 0 osbuild sssh Windows build number parent sssh Name of the parent process pid sssh TCC process ID (numeric) pipe sssh Current process is running in a pipe: 1, else 0 ppid sssh Right Alt key depressed: 1, else 0 ppid sssh Right Alt key depressed: 1, else 0 reatl sssh Right Ctrl key depressed: 1, else 0 ready sssh Registered user name row sssh Current cursor row rows sssh Screen height rshift sssh Right Shift key depressed: 1, else 0 second sssh Current second selected sssh Shell level shell sssh Shell level shell sssh Shell level shrift sssh Shell level shrift sssh Shell level shrift sssh Shell level shrift sssh Startupd Pathname of shortcut that started this process startpath sssh Startupd directory of current shell.		
openafs 390 OpenAFS installed: 1, otherwise 0 osbuild 390 Windows build number parent 390 Name of the parent process pid 390 TCC process ID (numeric) pipe 390 Current process is running in a pipe: 1, else 0 ppid 390 Process ID of parent process Talt 390 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process 1, else 0 Process ID	_monthf 389)	Current month of the year, English, full
openafs 390 OpenAFS installed: 1, otherwise 0 osbuild 390 Windows build number parent 390 Name of the parent process pid 390 TCC process ID (numeric) pipe 390 Current process is running in a pipe: 1, else 0 ppid 390 Process ID of parent process Talt 390 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process Test 1, else 0 Process ID of parent process 1, else 0 Process ID		1
Description	_numlock।३८९)	NumLock on: 1, else 0
Description		
parent 390 Name of the parent process pid 390 TCC process D (numeric) pipe 390 Current process is running in a pipe: 1, else 0 ppid 390 Process D of parent process D of parent process Talt 390 Right Alt key depressed: 1, else 0 ready 390 List of accessible drives registered 390 Registered user name row 390 Current cursor row rows 391 Right Shift key depressed: 1, else 0 Screen height Right Shift key depressed: 1, else 0 Scrolllock 391 Right Shift key depressed: 1, else 0 Second 391 Scrolllock on: 1, else 0 Second 391 Shell level Shell level Shell sold Shell		OpenAFS installed: 1, otherwise 0
Pid 39th Current process ID (numeric)	_osbuild 390	Windows build number
Pid 39th Current process ID (numeric)		
Pid 39th Current process ID (numeric)	_parent 390	Name of the parent process
Current process is running in a pipe: 1, else 0	pid 3901	
Process ID of parent process ralt sed Right Alt key depressed: 1, else 0 rctr sed Right Ctrl key depressed: 1, else 0 ready sed List of accessible drives registered sed Registered user name row sed Current cursor row rows sed Right Shift key depressed: 1, else 0 scrolllock second selected sed selected sed First line of highlighted text shell sed Shell level shell sed Shell level (old style) shift sed Shell level (old style) shift sed Shell level (old style) shortcut sed Shell level (old style) startpath sed Startup directory of current shell startpath sed Startup directory of current shell startpath sed Startup directory of current shell startpath sed Startup directod: 1, else 0 stdout sed Startup directed: 1, else 0 stdout sed se	pipe 390	
Right Alt key depressed: 1, else 0 rctrl sab		
Right Ctrl key depressed: 1, else 0 ready 390 List of accessible drives registered 390 Registered user name row 390 Current cursor row rows 391 Screen height rshift 391 Right Shift key depressed: 1, else 0 second 391 Current second selected 391 First line of highlighted text shell 391 Shell level shells 391 Shell level (old style) shift 391 Shift key depressed: 1, else 0 shortcut 392 Pathname of shortcut that started this process shralias 392 Startup directory of current shell. startpid 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0		<u>'</u>
Right Ctrl key depressed: 1, else 0 ready 390 List of accessible drives registered 390 Registered user name row 390 Current cursor row rows 391 Screen height rshift 391 Right Shift key depressed: 1, else 0 second 391 Current second selected 391 First line of highlighted text shell 391 Shell level shells 391 Shell level (old style) shift 391 Shift key depressed: 1, else 0 shortcut 392 Pathname of shortcut that started this process shralias 392 Startup directory of current shell. startpid 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 starpadard 392 STDERR redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0	ralt 390	Right Alt key depressed: 1, else 0
List of accessible drives registered sep Registered user name row sep Current cursor row rows sep Right Shift key depressed: 1, else 0		
Registered user name row 390 Current cursor row rows 391 Screen height rshift 391 Right Shift key depressed: 1, else 0 second 391 Current second selected 391 First line of highlighted text shell 391 Shell level shells 391 Shell level (old style) shift 391 Shift key depressed: 1, else 0 shortcut 392 Shortcut that started this process shralias 392 Startup directory of current shell. startpid 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0		
Current cursor row rows 39th Screen height rshift 39th Right Shift key depressed: 1, else 0 scrolllock 39th ScrollLock on: 1, else 0 second 39th Current second selected 39th First line of highlighted text shell 39th Shell level shells 39th Shell level (old style) shift 39th Shift key depressed: 1, else 0 shortcut 392th Shift key depressed: 1, else 0 shortcut 392th Shart Shell level (old style) shift 39th Shift key depressed: 1, else 0 shortcut 392th Shift key depressed: 1, else 0 startpath 392th Startup directory of current shell. startpath 392th Startup directory of current STARTed process. stdin 392th STDIN redirected: 1, else 0 stdout 392th STDOUT redirected: 1, else 0 stderr 392th STDERR redirected: 1, else 0 stzn 392th STDERR redirected: 1, else 0		
Screen height Right Shift key depressed: 1, else 0	row 390	
Right Shift key depressed: 1, else 0		
ScrollLock on: 1, else 0		
Selected		right Offit Key depressed. 1, else o
Selected	scrolllock 39h	Scroll ock on: 1 also 0
Selected		· · · · · · · · · · · · · · · · · · ·
Shell level Shell level level Shell level Shell level level level Shell level level level level level le		
Shell level (old style) Shift Shift key depressed: 1, else 0 Shortcut Shift key depressed: 1, else 0 Shortcut Shift key depressed: 1, else 0 Shortcut Shift key depressed: 1, else 0 Startpath Shift key depressed: 1, else 0 Startpath Shift key depressed: 1, else 0 Startpath Shift key depress		
Shift key depressed: 1, else 0 shortcut 392 Pathname of shortcut that started this process shralias 392 SHRALIAS is loaded: 1, else 0 startpath 392 Startup directory of current shell. startpid 392 Process ID of most recent STARTed process. stdin 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time		
Shortcut 392 Pathname of shortcut that started this process		
Shralias 392 SHRALIAS is loaded: 1, else 0 startpath 392 Startup directory of current shell. startpid 392 Process ID of most recent STARTed process. stdin 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time		
startpath 392 startpid 392 stdin 392 STDIN redirected: 1, else 0 stdout 392 STDERR redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time	SNOTTCUT 392	
Startpid 392 Process ID of most recent STARTed process. stdin 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time		
stdin 392 STDIN redirected: 1, else 0 stdout 392 STDOUT redirected: 1, else 0 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time		
stdout 392 stderr 392 STDERR redirected: 1, else 0 stzn 392 Name of time zone for standard time		
_stderr 392 STDERR redirected: 1, else 0 _stzn 392 Name of time zone for standard time		
stzn 392 Name of time zone for standard time		
Lstzo 3927 Offset in minutes from UTC for standard time		
	_stzo 392)	Offset in minutes from UTC for standard time

_syserr 392	Latest Windows error code	
Latest Williams endi code		
tcfilter 392	Current filter in List view window	
tcfolder 393	Selected folder in Folders window	
tctab 393	Running inside Take Command: 1; else 0	
time 393	Current time	
_transient 393	Current process is a transient shell: 1, else 0	
tzn 393	Name of current time zone	
tzo 393	Offset in minutes from UTC for current time zone	
<u>— 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1</u>	1	
_unicode 393	Shell uses unicode for redirected output: 1, else 0	
_utctime 394	Current UTC time	
_utcdate 393	Current UTC date	
_utcdatetime 393	Current UTC date and time	
_utchour 393	Current UTC hour	
_utcisodate 393	Current UTC date in ISO format	
_utcisominute 393	Current UTC minute	
_utcisosecond 393	Current UTC second	
_virtualpc 393	Running inside VirtualPC: 1; else 0	
_vmware 394	Running inside VMWare: 1; else 0	
_vxpixels 394	Virtual screen horizontal size	
_vypixels 394	Virtual screen vertical size	
_windir 394	Minday directory mathematica	
_winfgwindow 394	Windows directory pathname Title of foreground window.	
_winname 394	Name of local computer	
_winsysdir 394	Windows system directory pathname	
_winticks 394	Milliseconds since Windows was started	
_wintitle 394	Current window title	
_winuser 394	Name of current user.	
_winver 394	Windows version number	
_wow64 394	Running inside WOW64: 1; else 0	
_*********	realiting molecularity is a control of the control	
_xpixels 394	xpixels 394 Physical screen horizontal size in pixels	
— T	i ilyaida daraan nanzama aiza iii pixala	
_year 394	Current year	
_ypixels 395	Physical screen vertical size in pixels	
<u></u>	,	

3.14.3.2 Variables by Category

- TCC status 378
- Compatibility 380 Dates and times 379
- Drives and directories 379
- Error codes 380
- Hardware status 377
- Operating system and software status Screen, color, and cursor 378

The list below gives a one-line description of all <u>Internal Variables [372]</u> and a cross reference which selects a separate help topic on that variable. Many variables are simple enough that the one-line

description is probably sufficient, but in most cases you should check for any additional information in the cross referenced explanation if you are not already familiar with a variable. You can also obtain help on any function with a **HELP variablename** command at the prompt. See the <u>HELP 25</u> command for details

Hardware status

_acstatus 381	AC line status
_alt 38f)	Alt key depressed
_battery 382	Battery status
_batterylife 382	Remaining battery life, seconds
_batterypercent 382	Remaining battery life, %
_capslock 383	CapsLock on: 1, otherwise 0
_cpu 384	CPU type
_cpuusage 384	CPU time usage (percent)
_ctrl 384	Ctrl key depressed: 1, otherwise 0
_kbhit 388	A keyboard input character is waiting: 1, otherwise 0
_lalt 388	left Alt key depressed: 1, otherwise 0
_lctrl 389	left Ctrl key depressed: 1, otherwise 0
_lshift 389	left Shift key depressed: 1, otherwise 0
_numlock 389	NumLock on:r 1, otherwise 0
_ralt 390	right Alt key depressed: 1, otherwise 0
_rctrl 390	right Ctrl key depressed: 1, otherwise 0
_rshift 39 ^f 1	right Shift key depressed: 1, otherwise 0
_scrolllock 39h	ScrollLock on: 1, otherwise 0
_shift 391	Shift key depressed: 1, otherwise 0

Operating system and software status

ating system and software status		
! 380	Last argument of previous command	
_admin 381	1 if administrator; else 0	
_ansi 382	ANSI X3.64 status	
_boot 383	Boot drive letter, without a colon	
_codepage 383	Current code page number	
_country 384	Current country code	
_dos 385	Operating system type	
_dosver 386	Operating system version	
_host 387	Host name of local computer.	
_hwprofile 388	Windows hardware profile if defined	
_idleticks 388	Milliseconds since last user input	
_ip 388	IP address(es) of local computer.	
_osbuild 390	Windows build number	
_tctab 393	Running inside Take Command: 1; else 0	
_virtualpc 394	Running inside VirtualPC: 1; else 0	
_vmware 394	Running inside VMWare: 1; else 0	
_windir 394	Windows directory pathname	
_winfgwindow 3947	Title of foreground window.	
_winname 394	Name of local computer	
_winsysdir 394	Windows system directory pathname	
_winticks 394	Milliseconds since Windows was started	
_wintitle 394	Current window title	
_winuser 394	Name of current user.	
_winver 394	Windows version number	
_wow64 394	Running in Windows 64: 1; else 0	

TCC status

C status	
_4ver 381	TCC version
_batch 382	Batch nesting level
_batchline 382	Line number in current batch file.
_batchname 382	Full path and filename of current batch file.
_batchtype 382	Type of the current batch file
_bdebugger 382	Batch debugger active: 1, otherwise 0
_build 383	Build number
_childpid 383	Process ID of most recent child process
_cmdline 383	Current command line
_cmdproc 383	Command processor name
_cmdspec 383	Full pathname of command processor
_detachpid 385	Process ID of most recent detached process
_dname 385	Name of the description file.
_echo 3861	Echo status
_editmode 386	Insert mode: 1; else 0
_exit 386	TCC exit code
_expansion 387	Current expansion mode (SETDOS /X)
_hlogfile 387	Current history log file name
_iftp 388	IFTP session active: 1, otherwise 0
_iftps 388	IFTPS session active: 1, otherwise 0
_ininame 388	Full pathname of the current INI file
_logfile 389	Current log file name
_parent 390	Name of the parent process
_pid 3901	The TCC process ID (numeric)
_pipe 390	Current process is running in a pipe: 1, otherwise 0
_ppid 390	Process ID of parent process
_registered 390	Registered user name
_shell 391	Shell level
_shells 39f	Shell level (old style)
_shortcut 392	Pathname of shortcut that started this process
_shralias 392	SHRALIAS is loaded: 1, otherwise 0
_startpath 392	Startup directory of current shell.
_startpid 392	Process ID of most recent STARTed process.
_stdin 392	STDIN redirected: 1, otherwise 0
_stdout 392	STDOUT redirected: 1, otherwise 0
_stderr 392	STDERR redirected: 1, otherwise 0
_tcfilter 392	Current filter in List view window
_tcfolder 393	Selected folder in Folders window
_transient 393	Current process is a transient shell: 1, otherwise 0
_unicode 393	TC uses unicode for redirected output: 1, otherwise 0

Screen, color, and cursor

	<u> </u>
_bg 382	Background color at cursor position
_ci 383	Current text cursor shape in insert mode
_CO 383	Current text cursor shape in overstrike mode
_column 384	Current cursor column
_columns 384	Virtual screen width
_fg 387	Foreground color at cursor position
_monitor 389	Number of monitors
_row 390	Current cursor row
	Screen height
_selected 39 ¹	(TC) First line of highlighted text

_vxpixels 394	Virtual screen horizontal size
_vypixels 394	Virtual screen vertical size
xpixels 394 Physical screen horizontal size in pixels	
_ypixels 395	Physical screen vertical size in pixels

Drives and directories

_afswcell 381	OpenAFS workstation cell
_cdroms 383	List of CD-ROM drives
_cwd 384	Current drive and directory
_cwds 385	Current drive and directory with trailing \
_cwp 385	Current directory
_cwps 385	Current directory with trailing \
_disk 385	Current drive
_drives 386	List of all available drives
_dvds 386	List of DVD drives
_hdrives 387	List of hard (fixed) drives
_lastdisk 389	Last valid drive
_openafs 390	OpenAFS service installed: 1, otherwise 0
_ready 390	List of ready (accessible) drives

Dates and times

Current date
Current date Current date and time, yyyyMMddhhmmss
Current day of the month
Current day of the week, English, short
Current day of the week, English, short
Current day of the week, English, full Current day of the week as an integer
Current day of the year
Daylight savings time: 1, else 0 Current hour
Current day of the week, local language, short
Current day of the week, local language, full
Current month name, local language, short
Current month name, local language, full
Current date in ISO 9601 format
Current minute
Current month of the year as integer
Current month of the year, English, full
Current second
Name of time zone for standard time
Offset in minutes from UTC for standard time
Current time
Name of current time zone
Offset in minutes from UTC for current time zone
Current UTC time
Current UTC date
Current UTC date and time
Current UTC hour
Current UTC date in ISO format
Current UTC minute
Current UTC second
Current year

Error codes

	Exit code, last external program
_? 380	Exit code, last internal command
errorlevel 395	Exit code, last external program
_execstr 386	Last @EXECSTR return code
_ftperror 387	Last FTP error code
_syserr 392	Latest Windows error code

Compatibility

	,	
	= 381	Substitutes the <i>TCC</i> escape character
ſ	+ 381	Substitutes command separator

3.14.3.3 ! (Variable)

! returns the last argument of the previous command. The command is retrieved from the history list, so this will not work in a batch file -- it's intended for aliases and command line work.

3.14.3.4 ? variable

If an **external** command (i.e., a program) has an **exit code**, its value is stored in the ? variable when the program terminates. Additionally, some **internal** commands, e.g., DIR 1981 - to emulate Microsoft's **CMD.EXE** - also set this variable to the same value they set the variable ? 3801, an action which destroys the code from the last external command.

To insure that you use the **exit code** from the **external** command you want to check, not that of a subsequent internal or external command, it is best to save the value of **?** in another variable immediately on completion of the external command of interest, and use that variable instead. We also strongly recommend that for internal commands you query the _? [380] variable instead.

Not all programs return an exit code. If a program does not explicitly return an exit code, the value of %? is undefined.

Alternate name: ERRORLEVEL 3951.

See also: _? 380

3.14.3.5 _? variable

_? contains the exit code of the last internal command. You must use or save this value immediately, because it is set by every internal command, including the one used to save it.

Result codes:

- 0 command was successful
- 1 a usage error occurred
- another **Take Command** error or an operating system error occurred
- 3 the command was interrupted by Ctrl-C or Ctrl-Break

This variable can also be set in a subroutine by the RETURN 307 command.

Note that in imitation of CMD.EXE some internal commands, e.g., DIR, also set the variables ? | 386) and ERRORLEVEL | 395) to the same value they set this variable. However, you are strongly urged to use this variable.

See also: ? 380

3.14.3.6 = pseudovariable

= is the current <u>Escape character</u> [51]. Use this pseudovariable, instead of the actual escape character, if you want your batch files and aliases to work in other users' environment regardless of how the escape character is defined.

3.14.3.7 + pseudovariable

+ is the current <u>command separator [51]</u>. Use this pseudovariable, instead of the actual command separator, if you want your batch files and aliases to work in other users' environment regardless of how the command separator is defined.

WARNING: %+ should always be surrounded by spaces.

For example, if the command separator is an ampersand [&] (the default in *TCC*) both of the commands below will display "Hello" on one line and "world" on the next. However, if the command separator has been changed the first command will display "Hello & echo world", while the second command will continue to work as intended.

```
echo Hello & echo world echo Hello %+ echo world
```

3.14.3.8 4VER

_4VER returns the current *TCC* version (for example, 9.0). The current <u>Decimal character standard</u> is used to separate the major and minor version numbers.

See also: _BUILD 383.

3.14.3.9 _ACSTATUS

ACSTATUS returns the AC line status.

value	meaning
0	Offline
1	Online
unknown	Unknown

3.14.3.10 ADMIN

_ADMIN returns 1 if the current process is running as an administrator.

3.14.3.11 AFSWCELL

_AFSWCELL returns the OpenAFS workstation cell.

See http://www.openafs.org for more information on OpenAFS.

3.14.3.12 ALT

_ALT returns the status of the *Alt* key:

value	status of selected key
1	at least one Alt key is depressed
0	neither is depressed

3.14.3.13 _ANSI

_ANSI returns 1 if internal support for ANSI Std. X3.64 10th is enabled, 0 if not.

3.14.3.14 BATCH

_BATCH returns the current batch file nesting level. It is **0** if no batch file is currently being processed.

3.14.3.15 BATCHLINE

_BATCHLINE returns the current line number in the current batch file. It is -1 if no batch file is active.

3.14.3.16 BATCHNAME

_BATCHNAME returns the full path and file name of the current batch file. It is an empty string if no batch file is active.

3.14.3.17 BATCHTYPE

_BATCHTYPE returns the file type of the current batch file:

value	meaning
-1	not in a batch file
0	normal
1	compressed
2	encrypted

3.14.3.18 BATTERY

_BATTERY returns the battery charge status:

value	meaning
1	High
2	Low
4	Critical
8	Charging
128	No battery
unknown	Unknown

3.14.3.19 **BATTERYLIFE**

_BATTERYLIFE returns either the number of seconds of battery life remaining, or unknown.

3.14.3.20 BATTERYPERCENT

BATTERYPERCENT returns the percentage of battery charge remaining (0...100), or unknown.

3.14.3.21 BDEBUGGER

_BDEBUGGER returns 1 if the batch debugger is actively debugging a file, or 0 if it is not.

3.14.3.22 BG

_BG returns a string containing the first three characters of the current background screen output color (for example, Bla). See Colors, Color Names and Codes [518] for details.

3.14.3.23 BOOT

_BOOT returns the boot drive letter, without a colon.

3.14.3.24 BUILD

_BUILD returns the internal *TCC* build number.

See also: _4VER 38h.

3.14.3.25 _CAPSLOCK

_CAPSLOCK returns the current state of the *capslock* key:

value	toggled status
1	ON
0	OFF

3.14.3.26 _CDROMS

_CDROMS returns a space-delimited list of the CD-ROM drives on the system.

3.14.3.27 _CHILDPID

_CHILDPID returns the process ID of the most recent child process.

3.14.3.28 CI

_CI returns the insert mode cursor shape, as a percentage (0 to 100).

See also SETDOS /S 323 and the Insert Cursor 50 configuration option.

3.14.3.29 **CMDLINE**

_CMDLINE returns the current command line. (This is most useful in key aliases.) If you specify it on the command line, it returns the contents of the command line with the %_cmdline name removed.

3.14.3.30 CMDPROC

_CMDPROC returns the name of the current command processor (*TCC*). This variable is obsolete.

3.14.3.31 _CMDSPEC

_CMDSPEC returns the full pathname of the command processor.

3.14.3.32 CO

_CO returns the overstrike mode cursor shape, as a percentage (0 to 100).

See also <u>SETDOS /S</u> 323 and the <u>Overstrike Cursor</u> 50 configuration option.

3.14.3.33 _CODEPAGE

_CODEPAGE returns the current Windows code page.

See also CHCP 180.

3.14.3.34 _COLUMN

_COLUMN is the current cursor column. The leftmost column is numbered 0.

See also _COLUMNS 384h, _ROW 390h, and _ROWS 391h.

3.14.3.35 COLUMNS

COLUMNS returns the current number of virtual screen columns (for example, 80).

See Resizing the Take Command Window 68 for additional details on the virtual screen width.

See also _COLUMN 384, _ROW 390, and _ROWS 391.

3.14.3.36 CONSOLEPIDS

_CONSOLEPIDS returns a space-delimited list of the process IDs of all processes attached to this console.

3.14.3.37_COUNTRY

_COUNTRY returns the current country code as reported by the operating system. This code is usually the same as the international dialing code for the country.

3.14.3.38 _CPU

_CPU returns the CPU type:

486 i486

586 Pentium family

etc.

This variable merely queries Windows for the processor type. Compatible AMD or other processors will generally return the value corresponding to the Intel processor they most closely resemble.

This variable is obsolete. To determine the type, revision, stepping level, and other such details for advanced processors, use the @WININFO 467 or @WMI 472 function.

3.14.3.39 _CPUUSAGE

_CPUUSAGE returns the current CPU usage, as a percent (0 to 100).

3.14.3.40 _CTRL

_CTRL returns the status of the Ctrl keys:

value	status of selected key
1	at least one Ctrl key is depressed
0	neither is depressed

3.14.3.41 _CWD

_CWD returns the current working directory, in the format *d:\pathname*. If the current working directory is a root directory, the format is *d:\l*

See also _CWDS 385h, _CWP 385h, _CWPS 385h, @CWD 414h, and @CWDS 414h.

3.14.3.42 _CWDS

_CWDS returns the current working directory in the format d:\pathname\.

See also <u>CWD</u> 384, <u>CWP</u> 385, <u>CWPS</u> 385, <u>@CWD</u> 414, and <u>@CWDS</u> 414.

3.14.3.43 _CWP

_CWP returns the current working directory in the format \(\mathbb{pathname}\) (without the drive letter).

See also _CWD | 3841, _CWDS | 3851, _CWPS | 3851, @CWD | 4141, and @CWDS | 4141.

3.14.3.44 CWPS

_CWPS returns the current working directory in the format **\pathname** (without the drive letter).

See also <u>CWD</u> 384, <u>CWDS</u> 385, <u>CWP</u> 385, <u>@CWD</u> 414, and <u>@CWDS</u> 414.

3.14.3.45 DATE

_DATE returns the current system date, in the format determined by your country settings. The year will be in two-digit format for compatibility unless your country setting is **yyyy-mm-dd**.

See also _ISODATE 388.

3.14.3.46 _ DATETIME

_**DATETIME** returns the current date and time in the format yyyyMMddhhmmss. The date part is the same as _isodate | 3388 | without separators.

3.14.3.47 DAY

_DAY returns the current day of the month (1 to 31).

3.14.3.48 **DETACHPID**

_**DETACHPID** returns the process ID of the most recent process launched by the <u>DETACH</u> 1971 command.

3.14.3.49 DISK

_DISK returns the current disk drive letter, without a colon (for example, **C**).

If the current directory is a UNC, %_disk will return the sharename.

3.14.3.50 DNAME

_DNAME returns the name of the file used to store file descriptions. It can be changed with the Description Filename 51 configuration option, or the SETDOS /D 323 command.

3.14.3.51 DOS

_DOS returns the operating system type. *Take Command* returns a different value depending on the operating system, as follows:

Platform	Take Command
Windows XP	WINXP
Windows 2003	WIN2003
Windows Vista	WINVISTA
Windows 2008	WIN2008

This variable is useful if you have batch files running in more than one environment, and need to take different actions depending on the underlying operating environment or command processor. See also the _WINVER 394 variable.

3.14.3.52 DOSVER

_DOSVER returns the current operating system version. The current <u>Decimal character symbol</u> is used to separate the major and minor version numbers.

3.14.3.53 DOW

_DOW returns the first three characters of the name of the current day of the week (**Mon**, **Tue**, **Wed**, etc.).

3.14.3.54 DOWF

_DOWF returns the full name of the day of the week for the current date (Monday, Tuesday, etc.).

3.14.3.55 DOWI

_DOWI returns the current day of the week as an integer (1 = Sunday, 2 = Monday, etc.).

3.14.3.56 DOY

_DOY returns the current day of the year (1 to 366).

3.14.3.57 DRIVES

_DRIVES returns a space-delimited list of the existing drives in the format:

A: C: D: E:

3.14.3.58 DST

_DST returns 1 if daylight savings time is in effect, or 0 if it is not.

3.14.3.59 DVDS

_DVDS returns a space-delimited list of the DVD drives on the system.

3.14.3.60 ECHO

_ECHO returns the current echo state (0=off, 1=on). There are two ECHO states, one for the command line and one for batch files (see the ECHO 217) command and the Batch Echo 471 configuration option). The value returned by the _ECHO variable reflects the state applicable at the time the variable is queried.

3.14.3.61 _EDITMODE

EDITMODE returns 0 if the line editor is in overstrike mode, or 1 if it is in insert mode.

3.14.3.62 **EXECSTR**

_EXECSTR returns the integer return code of the last @EXECSTR 424 function.

3.14.3.63 **EXIT**

_EXIT returns the reason for exiting *TCC*:

- 0 EXIT command
- 2 CLOSE_EVENT
- 5 LOGOFF_EVENT

6 SHUTDOWN_EVENT

3.14.3.64_EXPANSION

_EXPANSION returns the current expansion mode (i.e., <u>SETDOS /X 323</u>). It returns the string **0** if everything is enabled, or a string of up to 9 characters of the disabled modes.

For example, if you disable nested variable expansion and redirection:

```
setdos /x-46
```

then %_expansion will return 46.

3.14.3.65_FG

_FG returns a string containing the first three letters of the current foreground screen output color (for example, "Whi"). See Colors, Color Names and Codes 518 for details.

3.14.3.66 FTPERROR

_FTPERROR returns the error code of the last error reported by FTP [93]. Some of the possible codes are:

101	You cannot change the remote host at this time
102	The remote host address is invalid
118	Firewall error
141	FTP protocol error
142	Communication error
143	Busy performing current action
144	Local file error
145	Can't open local file for reading
146	No remote file specified while uploading
147	Data interface error
301	Operation interrupted
302	Can't open local file
311	Accept failed for data connection
312	Asynchronous select failed for data connection
11001	Host not found
11002	Non-authoritative 'Host not found'
11003	Non-recoverable errors: FORMERR, REFUSED, NOTIMP
11104	Valid name, no data record (check DNS setup)

3.14.3.67 HDRIVES

_HDRIVES returns a space-delimited list of the hard (fixed) drives on the system.

3.14.3.68_HLOGFILE

_HLOGFILE returns the name of the current history log file (or an empty string if LOG /H is OFF). See LOG [269] for information on history logging.

3.14.3.69 HOST

_HOST returns the host name for the local computer.

3.14.3.70 HOUR

_HOUR returns the current hour (0 - 23).

3.14.3.71 **_HWPROFILE**

_HWPROFILE returns the name of the current Windows hardware profile.

3.14.3.72 **IDLETICKS**

_IDLETICKS returns the number of milliseconds since the last user input.

3.14.3.73 IDOW

_IDOW returns the 3-character abbreviation for the day of the week for the current date, in the current locale language.

3.14.3.74 IDOWF

_IDOWF returns the full name for the day of the week for the current date, in the current locale language.

3.14.3.75 IFTP

_IFTP returns 1 if an IFTP 255 session is active, 0 if it is not.

3.14.3.76 IFTPS

_IFTPS returns 1 if an SSL IFTP 255 session is active, 0 if it is not.

3.14.3.77 **IMONTH**

_IMONTH returns the abbreviated name for the current month, in the current locale language.

3.14.3.78 IMONTHF

_IMONTHF returns the full name for the current month, in the current locale language.

3.14.3.79 ININAME

_ININAME returns the fully qualified pathname of the INI file used by the current shell.

3.14.3.80 IP

_IP returns the IP address of the local computer. If the computer has more than one NIC, _IP returns a space-delimited list of all IP addresses.

3.14.3.81 ISODATE

_ISODATE returns the current system date, in ISO 9601 format (yyyy-mm-dd).

See also _DATE 385 and _DATETIME 385.

3.14.3.82 KBHIT

_KBHIT returns **1** if one or more keystrokes are waiting in the keyboard buffer, or **0** if the keyboard buffer is empty.

3.14.3.83 LALT

_LALT returns the status of the left Alt key:

value	key status

1	depressed
0	not depressed

See also _ALT 381.

3.14.3.84 LASTDISK

_LASTDISK returns the last valid drive letter (without a colon).

3.14.3.85 LCTRL

_LCTRL returns the status of the Left Ctrl key:

value	key status
1	depressed
0	not depressed

See also _CTRL 384).

3.14.3.86 LOGFILE

_LOGFILE returns the name of the current log file (or an empty string if LOG is OFF). See **LOG** [269] for information on logging.

3.14.3.87 LSHIFT

_LSHIFT returns the status of the left shift key:

value	key status
1	depressed
0	not depressed

See also _SHIFT 39h.

3.14.3.88 MINUTE

_MINUTE returns the current minute (0 - 59).

3.14.3.89 **_MONITORS**

_MONITORS returns the number of video displays.

3.14.3.90 MONTH

_MONTH returns the current numeric month of the year (1 to 12).

3.14.3.91 _MONTHF

_MONTHF returns the full name of the current month (January, February, etc.).

3.14.3.92_NUMLOCK

_NUMLOCK reports the current of the *numlock* key:

value	toggled status
1	ON
0	OFF

3.14.3.93 OPENAFS

_OPENAFS returns 1 if the OpenAFS 103 service is active, 0 if it is not.

See http://www.openafs.org for more information on OpenAFS.

3.14.3.94 OSBUILD

OSBUILD returns the Windows build number.

3.14.3.95 PARENT

_PARENT returns the name of the parent process (the process that started *TCC*).

3.14.3.96 PID

_PID returns the current process ID number.

3.14.3.97 PIPE

_PIPE returns 1 if the current process is running inside a pipe, and 0 otherwise.

3.14.3.98 PPID

_PPID returns the process ID number of the parent process.

3.14.3.99 RALT

_RALT returns the status of the right Alt key:

value	key status
1	depressed
0	not depressed

See also _ALT 381.

3.14.3.10(_RCTRL

_RCTRL returns the status of the right Ctrl key:

value	key status
1	depressed
0	not depressed

See also CTRL 384.

3.14.3.10 READY

_READY returns a space-delimited list of the currently ready (accessible) drives in the format :

C: D: E:

3.14.3.10; REGISTERED

_REGISTERED returns the registered name of the user or an empty string if *Take Command* isn't registered.

3.14.3.10; ROW

_ROW returns the current cursor row (for example, **0** for the top of the window).

3.14.3.104_ROWS

_ROWS returns the current number of screen rows in the TCC window (for example, 25).

3.14.3.10:_RSHIFT

_RSHIFT returns the status of the right Shift key:

value key status		
1	depressed	
0	not depressed	

See also <u>SHIFT</u> 391.

3.14.3.10(RUBYTYPE

_RUBYTYPE returns the type of the Ruby VALUE returned by the last @RUBY 458 call.

3.14.3.10 RUBYVALUE

_RUBYVALUE returns the Ruby VALUE returned by the last @RUBY 458 call.

3.14.3.10 SCROLLLOCK

_SCROLLLOCK reports the current state of *scrolllock* mode, which can be toggled using the *scrolllock* key:

value	toggled status
1	ON
0	OFF

3.14.3.10!_SECOND

_SECOND is the current second (0 - 59).

3.14.3.11(_SELECTED

_SELECTED returns the first line of text highlighted in the *TCC* window. If no text has been highlighted, SELECTED returns an empty string.

3.14.3.11 SHELL

_SHELL is the current shell instance identifier, one for each command processor. _SHELL will return 0 for a primary shell, or 1 (or higher) for a shell started by another *TCC* process (either directly or via a pipe).

3.14.3.11;_SHELLS

_SHELLS is the current shell identifier, one for each command processor. _SHELLS duplicates the behavior of _SHELL in older versions (7.01 and earlier) of **4NT** and **Take Command**.

3.14.3.11:_SHIFT

SHIFT is the status the two **Shift** keys:

value status of selected key

•	1	at least one is depressed
	0	neither is depressed

3.14.3.11 SHORTCUT

_SHORTCUT returns the full pathname of the shortcut file that started this process. If the process was not started from a shortcut, _SHORTCUT returns an empty string.

3.14.3.11! SHRALIAS

SHRALIAS returns 1 if SHRALIAS 329 is loaded, 0 if it is not.

3.14.3.11(STARTPATH

_STARTPATH returns the startup directory for the current shell (not necessarily the same as the location of the executable!)

3.14.3.11 STARTPID

_STARTPID returns the process ID of the most recent process launched by the START 3311 command.

3.14.3.11 STDIN

_STDIN returns 1 if STDIN points to the console, or 0 if it has been redirected.

3.14.3.11! STDOUT

STDOUT returns **1** if STDOUT points to the console, or **0** if it has been redirected.

3.14.3.12(STDERR

_STDERR returns 1 if STDERR points to the console, or 0 if it has been redirected.

3.14.3.12 STZN

STZN returns the name of standard time in the current time zone.

```
See also _STZO 392, _TZN 393, and _TZO 393.
```

3.14.3.12; STZO

_STZO returns the offset in minutes from UTC for standard time in the current time zone.

```
See also _STZN 3921, _TZN 3931, and _TZO 3931.
```

3.14.3.12: SYSERR

_SYSERR returns the error code of the last operating system error. You will need a technical or programmer's manual to understand these error values.

See the Windows System Errors table in the Reference section for examples.

3.14.3.12 TCFILTER

_TCFILTER returns the current filter in the *Take Command* List view window if *TCC* is running in a tab window, or an empty string if it is not.

3.14.3.12!_TCFOLDER

_TCFOLDER returns the selected folder in the *Take Command* Folders window if *TCC* is running in a tab window, or an empty string if it is not.

3.14.3.12(_TCTAB

_TCTAB returns 1 if this TCC process is running in a Take Command tab window, or 0 if it is not.

3.14.3.12 TIME

_TIME returns the current system time in the format **hh:mm:ss**. The separator character may vary depending upon your country information.

3.14.3.12_TRANSIENT

_TRANSIENT returns 1 if the current shell is transient (started with a /C, see Command Line Options for details), or 0 otherwise.

3.14.3.12!_TZN

TZN returns the name of the current time zone.

See also _STZN 392, _STZO 392, and _TZO 393.

3.14.3.13(TZO

_TZO returns the offset in minutes from UTC for the current time zone.

See also _STZN 392, _STZO 392, and _TZN 393.

3.14.3.13' UNICODE

_UNICODE returns 1 if the shell is currently using Unicode for redirected output, 0 otherwise.

3.14.3.13; UTCDATE

_UTCDATE returns the current UTC date in the user's default format.

3.14.3.13: UTCDATETIME

UTCDATETIME returns the current date and time in UTC.

3.14.3.13 UTCHOUR

_UTCHOUR returns the current UTC hour.

3.14.3.13! UTCISODATE

_UTCISODATE returns the current UTC date in ISO format (yyyy-mm-dd).

3.14.3.13(_UTCMINUTE

UTCMINUTE returns the current UTC minute.

3.14.3.13 UTCSECOND

UTCSECOND returns the current UTC second.

3.14.3.13\(\text{UTCTIME}\)

UTCTIME returns the current UTC time.

3.14.3.13!_VIRTUALPC

_VIRTUALPC returns 1 if *TCC* is running inside VirtualPC virtual machine.

3.14.3.14(VMWARE

_VMWARE returns 1 if **TCC** is running inside a VMWare virtual machine.

3.14.3.14 VXPIXELS

_VXPIXELS returns the horizontal size of the virtual screen (including multiple monitors) in pixels.

3.14.3.14; VYPIXELS

_VXPIXELS returns the vertical size of the virtual screen (including multiple monitors) in pixels.

3.14.3.14; WINDIR

_WINDIR returns the pathname of the Windows directory.

3.14.3.14 WINFGWINDOW

_WINFGWINDOW returns the title of the foreground window.

3.14.3.14! WINNAME

_WINNAME returns the computer name of the current system.

3.14.3.14(WINSYSDIR

_WINSYSDIR returns the pathname of the Windows system directory.

3.14.3.14; WINTICKS

WINTICKS returns the number of milliseconds since Windows was started.

3.14.3.14 WINUSER

_WINUSER returns the name of the user currently logged on.

3.14.3.14! WINVER

_WINVER returns the current Windows version number. The current Decimal character is used to separate the major and minor version numbers.

3.14.3.15(_WINTITLE

_WINTITLE returns the title of the current window.

3.14.3.15' WOW64

_WOW64 returns 1 if *TCC* is running in the WOW64 environment (64-bit Windows).

3.14.3.15;_XPIXELS

_XPIXELS returns the physical screen horizontal size in pixels.

3.14.3.15:_YEAR

_YEAR returns the current year (1980 to 2099).

3.14.3.15 YPIXELS

_YPIXELS returns the physical screen vertical size in pixels.

3.14.3.15 ERRORLEVEL

ERRORLEVEL is an alternate name (included for compatibility with CMD.EXE) for the __? [380] variable, and is the exit code of the last external command. Many programs return **0** to indicate success and a non-zero value to signal an error. However, not all programs return an exit code. If no explicit exit code is returned, the value of **ERRORLEVEL** is undefined.

WARNING: For compatibility with CMD.EXE, some internal commands, e.g., **DIR**, also set this variable to the same value as the variable _? [380], which destroys the code from the last external command. If you need to preserve the return value of the external command, save the value in a variable immediately upon command completion, and use the saved variable instead. We also strongly recommend that for internal commands you query the _? [380] variable instead.

See also _? 380

3.14.4 Variable Functions

Variable functions are very similar to internal variables, but they take one or more parameters (which can be environment variables or even other variable functions).

Variable functions are useful at the command prompt as well as in <u>aliases [128]</u> and <u>batch files [130]</u> to check on available system resources, manipulate strings and numbers, and work with files and filenames.

The variable functions built into *TCC* are listed in alphabetical order in subsequent topics. You can also obtain help from the command prompt on any function with a HELP @functionname command, or by pressing Ctrl-F1 34 when the cursor is on the function name. See the HELP 251 command for details

Note: The <u>FUNCTION [242]</u> command can be used to create, edit, or display user-defined variable functions, and the <u>UNFUNCTION [356]</u> to delete them.

For a list of Variable Functions organized by general categories of use, see <u>Variable Functions by Category</u> 40h.

Syntax

To have either a user-defined or a built-in variable function evaluated, its name must be preceded by a percent sign % (%@EVAL, %@LEN, etc.). All variable functions must have square brackets [] enclosing their parameter(s), if any. No space is allowed between the function name and the [. The combined parameters of a variable function may not exceed 8,191 characters.

Memory Size / Disk Space / File Size Units and Report Format

Some variable functions, such as QDISKFREE 416, accept an optional parameter **scale code**. These functions return a size of a disk or of an entity on the disk as a multiple of the specified scale factor from the table below. Lower case letters denote a power of 1,000, upper case letters a power of 1,024.

Code	Scale Factor		Code	Scale Factor	Scale Factor	
k	1,000	10**3	K	1,024	2**10	kilobyte
m	1,000,000	10**6	M	1,048,576	2**20	megabyte
g	1,000,000,000	10**9	G	1,073,741,824	2**30	gigabyte
t	1,000,000,000,000	10**12	T	1,099,511,627,776	2**40	terabyte

You can include **commas** (or the <u>thousands separator [51]</u>) in the value returned from a function by appending the letter c to the scale code. For example, to add commas to a b (number of bytes) result, enter bc as the parameter, i.e.:

```
echo %@DISKFREE[C,bc]
```

Notes

- 1) Disk manufacturers use the prefixes adopted from the metric system (kilo, mega, giga, tera) in their original meaning (powers of 1,000), while memory manufacturers and Microsoft use the slightly larger powers of 1,024 (2**10).
- 2) The **scale code** is one of the few instances in which **TCC** is case sensitive.

Date Parameter Format

See the Date Formats 127 topic.

File Name Parameters

Filenames passed as variable function parameters must be enclosed in double quotes if they contain white space or special characters. Several functions also return filenames or parts of filenames. On LFN drives, the strings returned by these functions may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. For example (either of these methods would work):

```
set fname="%@findfirst[pro*]"
echo First PRO file contains:
type %fname
.....
set fname=%@findfirst[pro*]
echo First PRO file contains:
type "%fname"
```

If you don't use the quotes in the SET or TYPE command in this example, TYPE will not interpret white space or special characters in the name properly.

Drive Letter Parameters

In variable functions which take a drive letter as a parameter, like <u>@DISKFREE [416]</u> or <u>@READY [453]</u>, the drive letter must be followed by a colon. The function will not work properly if you use the drive letter without the colon.

Functions Accessing File Handles

The @FILEREAD 429, @FILEWRITE 433, @FILEWRITEB 433, @FILESEEK 431, @FILESEEK 431, and @FILECLOSE 422 functions allow you to access files based on their file handle. These functions must be used only with file handles returned by @FILEOPEN 428, unless otherwise noted under the individual functions. If you use them with any other file handle you may damage files.

File Attributes

Several functions accept a file attribute string to help determine which files to process. The rules for

constructing the attribute string are the same as the ones for Attribute Switches 66 in commands.

Examples

You can use variable functions in a wide variety of ways depending on your needs. Here are a couple of examples to give you an idea of what's possible. For a more comprehensive set of examples, see the file **EXAMPLES.BTM**, which comes with *TCC*.

The command below sets the prompt to show the amount of free memory (see PROMPT (see PROMPT) for details on including variable functions in your prompt):

```
prompt (%%@dosmem[K]K) $p$g
```

Set up a simple command line calculator. The calculator is used with a command such as CALC 3*(4+5):

```
alias calc `echo The answer is: %@eval[%$]`
```

3.14.4.1 Functions by Name

@ABS 407	Absolute value of number
	OpenAFS cell name
	OpenAFS mount point
@AFSPATH 407	Path in OpenAFS: 1, otherwise 0
	OpenAFS symbolic link
	OpenAFS volume ID
	OpenAFS volume name
	Converts an age [520] into date and time
@ALIAS 408	Value of an alias
	Short name for the file.
	Set of ASCII-s for characters in string
@ASSOC 409	File association
@ATTRIB 409	Test or return file attributes
@AVERAGE 410	Average of a list of numbers

@CAPI 410	Call a _cdecl function in a DLL
@CAPS 41h	Capitalize first character of each word
@CDROM 41h	CD-ROM drive: 1, otherwise 0
@CEILING 411	Smallest integer not less than a number
@CHAR 41↑	Character string, given a set of ASCII-s
@CLIP 412	Specified line from clipboard
@CLIPW 412	Write string to the clipboard
@COLOR 412	RGB value of a color
@COMMA 412	Insert commas into a number (thousands separators)
@COMPARE 413	Two files are identical: 1, otherwise 0
@CONSOLE 413	Identify console sessions
@CONVERT 413	Convert value from input base to output base
@COUNT 413	Number of times a character appears in a string
@CRC32 413	File CRC
@CWD 414	Current Working Directory of specified drive
@CWDS 414	Current Working Directory of specified drive, with trailing backslash

@DATE 414	Convert date to number of days	
@DAY 414	Day of month for date	

@DEC 415	Decrement a numeric value by 1
@DECIMAL 415	Decimal portion of a number
@DESCRIPT 415	File description
@DEVICE 416	Character device: 1, otherwise 0
@DIGITS 416	String is all digits: 1, otherwise 0
@DIRSTACK 416	Directory stack entry
@DISKFREE 416	Free disk space
@DISKTOTAL 417	Total disk space
@DISKUSED 417	Used disk space
@DOMAIN 417	Domain name of a computer
@DOW 417	Short name of day of week for date
@DOWF 418	Full name of day of week for date
@DOWI 418	Day of week number for date
@DOY 419	Day of year for date
@DRIVETYPE 419	Type of a drive
@DRIVETYPEEX 419	Type of a drive

	Identify server names on a network	
@ENUMSHARES 420	Identify sharenames on a server	
@ERRTEXT 420	Windows error description	
@EVAL 420	Arithmetic calculations	
@EXEC 424	Execute a command and return its exit code	
@EXECSTR 424	Execute a command and return the first output line	
@EXETYPE 424	Application type	
@EXPAND 425	All names that match filename	
@EXT 425	File extension	

@FIELD 426	Extract a field from a string
@FIELDS 427	Count fields in a string
@FILEAGE 427	File age 520 (date and time)
@FILECLOSE 427	Close a file handle
@FILEDATE 428	File date
@FILENAME 428	File name and extension
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file
@FILEREADB 429	Read bytes from a file
@FILES 430	Number of files matching a wildcard
@FILESEEK 43 h	Move a file handle pointer to specified file position
@FILESEEKL 43h	Move a file handle pointer to a specified line
@FILESIZE 432	Total size of files matching a wildcard
@FILETIME 432	File time
@FILEWRITE 433	Write next line to a file
@FILEWRITEB 433	Write data to a file
@FINDCLOSE 434	Closes the search handle.
@FINDFIRST 434	Find first matching file
@FINDNEXT 435	Find next matching file
@FLOOR 435	Largest integer not larger than a number
@FORMAT 435	Formats data string according to format string
@FORMATN 436	Format a numeric value
@FORMATNC 436	Format a numeric value and insert the thousands separator(s)
@FSTYPE 436	File system type (FAT, NTFS, CDFS, etc.)
@FTYPE 437	Open command string for file type
@FULL 437	Full file name with path
@FUNCTION 437	Definition of a function

@GETDIR 437	Prompt for a directory name.
@GETFILE 438	Prompt for a path and file name.
@GETFOLDER 438	Folder name from tree view.
@GROUP 438	User is member of group: 1, otherwise 0
@HISTORY 439	A line or word from the command history
	,
@IDOW 439	Short local name of day of week for date
@IDOWF 439	Full local name of day of week for date
@IF 439	Evaluates a conditional expression
@INC 440	Increment a numeric value by 1
@INDEX 446	Offset of string2 within string1
@INIREAD 44h	Return an entry from an .INI file
@INIWRITE 44h	Write an entry in an .INI file
@INSERT 442	Inserts string1 into string2
@INODE 442	File Inode (in hex)
@INSTR 443	Extract a substring
@INT 443	Integer part of a number
@IPADDRESS 443	Returns the numeric IP for a host name
@IPNAME 444	Returns the host name for a numeric IP address
@ISALNUM 444	Test for alphanumeric characters
@ISALPHA 444	Test for alphabetic characters
@ISASCII 444	Test for ASCII characters
@ISCNTRL 445	Test for control characters
@ISDIGIT 445	Test for decimal digits
@ISPRINT 445	Test for printable characters
@ISPROC 445	Returns 1 if the process is active; otherwise 0
@ISPUNCT 445	Test for punctuation characters
@ISSPACE 446	Test for white space characters
@ISXDIGIT 446	Test for hexadecimal digits
@JUNCTION 446	Directory referenced by the junction
<u>economicinal</u>	Endotory referenced by the junetion
@LABEL 446	Volume label
@LCS 446	Longest common sequence in two strings
@LEFT 446	Left end of string
@LEN 447	Length of a string
@LFN 44 ⁷)	Long name for a short filename
@LINE 447	Specified line from a file
@LINES 448	Count of lines in a file
@LINKS 448	Number of NTFS hard links for the file
@LOWER 448	Convert string to lower case
@LTRIM 448	Left trim specified characters.
@MAKEAGE 449	Convert date and time to age 520
@MAKEDATE 449	Convert number of days to date
@MAKETIME 449	Convert number of seconds to time
@MAX 450	Largest integer in the list
@MD5 450	MD5 hash of a string or file
@MIN 450 @MONTH 450	Smallest integer in the list
WIVION I H 450	Month for date

@NAME 45h	File name without noth or extension
@NUMERIC 45f	File name without path or extension
WNOWERIC 431	Test if a string is numeric
@OPTION 452	Current configuration option value
@OWNER 452	Return file owner
WOVINER 492	Neturn file Owner
@PATH 452	File path without name
@PERL 452	Evaluate a Perl expression
@PING 453	Response time from a host
@QUOTE 453	Double quote the argument if necessary
	,
@RANDOM 453	Generate a random integer
@READSCR 453	Read characters from the screen
@READY 453	Drive ready: 1, otherwise 0
@REGCREATE 454	Create registry subkey
@REGDELKEY 454	Delete a registry key and its subkeys
@REGEX 454	Match a regular expression
@REGEXINDEX 454	Return the offset of a regular expression match
@REGEXIST 454	Test if a registry key exists
@REGEXSUB 455	Return nth matching regular expression group
@REGQUERY 455	Read value from registry
@REGSET 455	Write value to registry
@REGSETENV 455	Write value to registry and broadcast change.
@REGTYPE 455	Return type of registry variable
@REMOTE 456	Remote (network) drive: 1, otherwise 0
@REMOVABLE 456	Removable drive: 1, otherwise 0
@REPEAT 456	Repeat a character
@REPLACE 456	Replace string1 with string2 in text
@REVERSE 457	Reverse a string
@REXX 457	Value of executing an expression by REXX
@RIGHT 457	Right end of string.
@RTRIM 457	Removes specified trailing characters.
@RUBY 458	Evaluate a Ruby expression
@ CODIDT :- A	L
@SCRIPT 458	Evaluate expression in an active scripting engine.
@SEARCH 458	Path search
@SELECT 458	Menu selection
@SERIAL 459	Serial number of a disk
@SFN 460	Short name for a long filename
@SHA1 460	SHA1 checksum for the file
@SHA256 460	SHA2-256 checksum for the file
@SHA384 466	SHA2-384 checksum for the file
@SHFOLDER 46h	SHA2-512 checksum for the file Get Windows folder locations
@SIMILAR 462	Compare two strings for similarity
@SNAPSHOT 462	Save a window or desktop as a BMP
@STRIP 462	Strips all characters in char from string
@SUBST 463	Substitute a string within another string
@SUBSTR 463	Extract a substring
@SUMMARY 462	Query or set the NTFS SummaryInformation stream
@SYMLINK 463	Target of a symbolic link
WO I WILLIAM 1400	paget of a symbolic link

@TIME 463	Convert a time of day to number of seconds
@TIMER 463	Get split time from timer.
@TRIM 464	Remove blanks from a string
@TRUENAME 464	Find true name of a file
@TRUNCATE 464	Truncate file at current position
WINDINGATE 404	Truncate file at current position
@UNC 464	UNC name of a file
@UNICODE 464	Numeric UNICODE value for a character
@UNIQUE 465	Create file with unique name
@UNQUOTE 465	Remove double quotes from a filename
@UNQUOTES 465	Remove leading and trailing double quotes
@UPPER 465	Convert string to upper case
@VERINFO 465	Executable file version information
@WATTRIB 466	Test or return file attributes
@WILD 466	Compares strings using wildcards
@WINAPI 467	Call a Windows API function
@WINCLASS 467	Title of first window with classname
@WINEXENAME 467	Executable name for window
@WININFO 467	Current system information
@WINMEMORY 468	Windows memory information
@WINMETRICS 468	Windows system metrics
@WINPOS 470	Window position
@WINSTATE 476	Current state of window
@WINSYSTEM 476	Set/get windows system parameters
@WMI 472	Query WMI
@WORD 472	Extract a word from a string
@WORDS 473	Count words in a string
@WORKGROUP 473	Workgroup name of a computer
@XMLCLOSE 473	Close an XML file previously opened by @XMLOPEN
@XMLNODES 473	Return the number of nodes (children) for the specified path in an XML file
@XMLOPEN 474	Open an XML file for use by @XMLXPATH and/or @XMLNODES
@XMLXPATH 474	Return text of XML element
@YEAR 474	Year for date

3.14.4.2 Functions by Category

This list gives a one-line description of all built-in <u>Variable Functions</u> selects a separate help topic on that function where you will find the detailed syntax and description. You can also obtain help on any function with a **HELP** @functionname command at the prompt or by pressing <u>Ctrl-F1</u> when the cursor is on the function name. See the <u>HELP</u> tommand for details

- Dates and times 405
- Drives and devices 402
- File content 402
- File names 403
- File properties 403
- Input dialog boxes 405
- Network properties 405
- Numbers and arithmetic 405
- Strings and characters 404
- System status 402
- Utility 406

Note: many functions have functionality that covers several categories.

System status

@ASSOC 409	File association for the extension
@CLIP 412	Specified line from clipboard
@CLIPW 412	Write string to the clipboard
@CONSOLE 413	Identify console sessions
@ERRTEXT 420	Windows error description
@FTYPE 437	Open command string for the file type
@ISPROC 445	Returns 1 if a process is active; otherwise 0
@READSCR 453	Read characters from the screen
@REGCREATE 454	Create registry subkey
	Delete a registry key and its subkeys
@REGEXIST 454	Test if a registry key exists
@REGQUERY 455	Read value from registry
@REGSET 455	Write value to registry
	Write value to registry and broadcast change.
@REGTYPE 455	Type of registry variable
@WINCLASS 467	Title of first window with classname
	Executable name for window
@WININFO 467	Current system information
	Windows memory information
	Windows system metrics
@WINPOS 470	Window position
@WINSTATE 476	Current state of window
@WINSYSTEM 470	Set/get windows system parameters

Directories, drives and devices

	CD-ROM drive: 1, otherwise 0
	Current Working Directory of specified drive
	Current Working Directory of specified drive, with trailing backslash
	Character device: 1, otherwise 0
	Free disk space
	Total disk space
	Used disk space
	Type of drive (hard drive, CD-ROM, etc.)
	Type of drive (hard drive, CD-ROM, etc.)
	File system type (FAT, NTFS, CDFS, etc.)
	Directory referenced by the junction
	Volume label
	Drive ready: 1, otherwise 0
	Remote (network) drive: 1, otherwise 0
	Removable drive: 1, otherwise 0
	Serial number of a disk
	Windows folder locations
@SYMLINK 463	Target of a symbolic link

File content

@COMPARE 413	Compare two files
@CRC32 413	File CRC
@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle

@FILEREAD 429	Read next line from a file
	Read bytes from a file
	Move a file handle pointer
	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file
	Write data to a file handle
@INIREAD 44h	Return an entry from an .INI file
@INIWRITE 44h	Write an entry in an .INI file
@INODE 442	Inode value for a file
@LINE 447	Specified line from a file
@LINES 448	Count lines in a file
	Number of NTFS hard links for a file
	MD5 hash of a string or file
@SHA1 460	SHA1 checksum for a file
@SHA256 460	SHA2-256 checksum for a file
@SHA384 460	SHA2-384 checksum for a file
@SHA512 460	SHA2-512 checksum for a file
	NTFS SummaryInformation stream for a file
@TRUNCATE 464	Truncate file at current position
@VERINFO 465	Executable file version information

File names

	Short name for the file.
	All names that match filename
	File extension
	File name and extension
	Full file name with path
	Long name for a short filename
	File name without path or extension
	File path without name
	Double quote a filename
	Short name for a long filename
	Path search
	True name of a file
	UNC name of a file
	Create file with unique name
	Remove double quotes from a filename
@UNQUOTES 465	Remove leading and trailing double quotes

File properties

@ATTRIB 409	Test or return file attributes
@DESCRIPT 415	File description
	Application type
	File age 520 (date and time)
	File date
	Number of files matching a wildcard
	Total size of files matching a wildcard
	File time
@FINDCLOSE 434	Closes the search handle.
	Find first matching file
@FINDNEXT 435	Find next matching file
@INODE 442	Inode value for a file

@LINKS 448	Number of NTFS hard links for a file
@OWNER 452	File owner
@SEARCH 458	Path search
@SUMMARY 462	NTFS SummaryInformation stream for a file
@TRUENAME 464	True name for a file
@UNIQUE 465	Create file with unique name
@VERINFO 465	Executable file version information
@WATTRIB 466	Test or return file attributes

Strings and characters

@ASCII 409	List of ASCII-s for characters in string
@CAPS 41 A	Capitalize first character of each word
@CHAR 41A	Character string, given a set of ASCII-s
@COUNT 413	Counts occurrences of a character in a string
@EXECSTR 424	Execute a command and return its first output line
@FIELD 426	Extract a field from a string
@FIELDS 427	Count fields in a string
@FORMAT 435	Formats data string according to format string
@INDEX 440	Offset of string2 within string1
@INSERT 442	Insert string1 into string2
@INSTR 443	Extract a substring
@ISALNUM 444	Test for alphanumeric characters
@ISALPHA 444	Test for alphabetic characters
@ISASCII 444	Test for ASCII characters
@ISCNTRL 445	Test for control characters
@ISDIGIT 445	Test for decimal digits
@ISPRINT 445	Test for printable characters
@ISPUNCT 445	Test for punctuation characters
@ISSPACE 446	Test for white space characters
@ISXDIGIT 446	Test for hexadecimal digits
@LCS 446	Longest common sequence in two strings
@LEFT 446	Left end of string
@LEN 447	Length of a string
@LOWER 448	Convert string to lower case
@LTRIM 448	Trims specified leading characters.
@MD5 450	MD5 hash of a string or file
@REGEX 454	Return a Regular Expression test
@REGEXINDEX 454	Return the offset of a regular expression match
@REGEXSUB 455	Return the nth matching group of a regular expression test
@REPEAT 456	Repeat a character
@REPLACE 456	Replace string1 with string2 in text
@REVERSE 457	Reverse a string
@RIGHT 457	Right end of string
@RTRIM 457	Trims specified trailing characters.
@SIMILAR 462	Test similarity between two strings
@STRIP 462	Strips all characters in char from string
@SUBST 463	Substitute a string within another string
@SUBSTR 463	Older version of @INSTR 443 to extract a substring
@TRIM 464	Remove blanks from a string
@UNICODE 464	List of UNICODEs for characters in string
@UPPER 465	Convert string to upper case
@WILD 466	Compares strings using wildcards

@WORD 472	Extract a word from a string
@WORDS 473	Count words in a string

Numbers and arithmetic

	Absolute value of n	
	Average of a list	
	Smallest integer not less than n	
	Insert commas (thousands separators) into a numeric string	
	Convert value from input base to output base	
	Decrement a numeric value by 1	
	Decimal fraction portion of a number	
@DIGITS 416	Tests if string is all digits	
	Arithmetic calculations	
	Format a numeric value	
	Format a numeric value and insert thousands separators	
	Largest integer not larger than n	
	Increment a numeric value by 1	
	Integer part of a number	
	Largest integer in the list	
	Smallest integer in the list	
@NUMERIC 45h	Test if a string is numeric	
@RANDOM 453	Generate a random integer	

Dates and times

@AGEDATE 408	Converts an age 520 into date and time	
	Day of month for date	
	Convert date to number of days	
	Short name of day of week for date	
@DOWF 418	Full name of day of week	
	Day of week as integer	
	Day of year for date	
	Short localized name of day of week for date	
@IDOWF 439	Full localized name of day of week for date	
@MAKEAGE 449	Convert date and time to age 520	
	Convert number of days to date	
	Convert number of seconds to time	
	Month in specified date	
@TIME 463	Convert time to number of seconds	
@YEAR 474	Year for date	

Input dialog boxes

@GETDIR 437	Prompt for a directory name.	
@GETFILE 438	Prompt for a path and file name.	
@GETFOLDER 438	Folder name from tree view.	
@SELECT 458	Menu selection	

Network properties

@AFSCELL 407	OpenAFS cell name for a path	
@AFSMOUNT 407	OpenAFS mount point for a path	
@AFSPATH 407	Path is in OpenAFS: 1, otherwise 0	

@AFSSYMLINK 407	OpenAFS symbolic link for a path	
	OpenAFS volume ID for a path	
	OpenAFS volume name for a path	
	Domain name of a computer	
	Identify server names on a network	
	Identify sharenames on a server	
	User is member of group: 1, otherwise 0	
	The numeric IP for a host name	
@IPNAME 444	The host name for a numeric IP	
	Response time from a host	
@WORKGROUP 473	Workgroup name of a computer	

Utility

@ALIAS 408	Value of an alias
@CAPI 410	Call a cdecl function in a DLL
@CLIP 412	Specified line from clipboard
@CLIPW 412	Write string to the clipboard
@COLOR 412	RGB value of a color
@DIRSTACK 416	Display directory stack entry
@ERRTEXT 420	Windows error description
@EXEC 424	Execute a command, returns its exit code
@EXECSTR 424	Execute a command, returns its first output line
@FUNCTION 437	Definition of a function
@HISTORY 439	A line or word from the command history
@ F 439	Value dependent on a conditional expression
@OPTION 452	Current configuration option value
@PERL 452	Evaluate a Perl expression
@READSCR 453	Read characters from the screen
@REXX 457	Evaluate a REXX 142 expression
@RUBY 458	Evaluate a Ruby expression
@SCRIPT 458	Evaluate expression in active scripting engine
@SELECT 458	Menu selection
@SNAPSHOT 462	Save a window or the desktop to a BMP
@TIMER 463	Get split time from timer.
@WINAPI 467	Call a Windows API function
@WMI 472	Query WMI
@XMLCLOSE 473	Close an XML file previously opened by @XMLOPEN
@XMLNODES 473	Return the number of nodes (children) for the specified path in an XML
	file
@XMLOPEN 474	Open an XML file for use by @XMLXPATH and/or @XMLNODES
@XMLXPATH 474	Return text of XML element

3.14.4.3 Date Display Formats

All functions which *return* a date accept an **optional code** to specify the desired format of the date value:

Code	Date Format	Description
0 or none	see below	system default
1	mm/dd/yy	USA
2	dd/mm/yy	European
3	yy/mm/dd	Japanese

4 yyyy-mm-dd 5	O 9601
--------------------	--------

Field Order

For codes 1...4 the field order is as shown above. For code 0 the field order will also be one of those shown above. *TCC* determines which field is reported first by Windows in a short date, and selects the order from the table above with the same first field. All other aspects of the Windows short date format are ignored,

Field Width

Month and day are always 2 digits. Year is 2 digits for codes 1, 2 and 3, and 4 digits for code 4. For code 0 the year is 4 digits if it is the first field returned, and 2 digits if it is the last one.

Field Separator

Code **4** (ISO 9601) uses a hyphen as the separator character. For the other formats, the default Windows date separator is returned.

Setting the Windows Date Formats

The details below apply to Windows XP, but other versions of Windows are similar.

Start → Settings → Control Panel → Regional and Language Options → Customize → Date display the desired menu. The two relevant fields are Short Date Format and Date Separator.

3.14.4.4 @ABS

@ABS[*n*]: Returns the absolute value of the number *n*.

Examples:

```
echo %@abs[-1]
echo %@abs[123]
```

3.14.4.5 @AFSCELL

@AFSCELL[path]: Returns the OpenAFS 103 cell name for the path.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.6 @AFSMOUNT

@AFSMOUNT[path]: Returns the OpenAFS 1031 mount point for the pathname.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.7 @AFSPATH

@AFSPATH[path]: Returns 1 if the path is in the OpenAFS 103 file system.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.8 @AFSSYMLINK

@AFSSYMLINK[path]: Returns the OpenAFS 103 symbolic link for the path.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.9 @AFSVOLID

@AFSVOLID[path]: Returns the OpenAFS 103 volume ID for the path.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.10 @AFSVOLNAME

@AFSVOLNAME[path]: Returns the OpenAFS 103 volume name for the path.

See http://www.openafs.org for more information on OpenAFS.

3.14.4.11 @AGEDATE

@AGEDATE[n[,d]]: Converts an age n into a date and time pair, formatted according to the current country settings, or as explicitly specified by n (see Date Display Formats n). The time is separated from the date by a comma, and is always in 24-hour format, displayed with 1 ms precision, as the examples show. The conversion does not take leap seconds into account.

Example:

```
for /1 %n in (1,1,4) echo %n %@agedate[127551146920835000,%n]

1 03-12-05,15:24:52.083
2 12-03-05,15:24:52.083
3 05-03-12,15:24:52.083
4 2005-03-12,15:24:52.083
```

See also: Time Stamps 495), @FILEAGE 427 and @MAKEAGE 449.

3.14.4.12 @ALIAS

@ALIAS[name]: Returns the contents of the specified alias as a string, or a null string if the alias doesn't exist.

When manipulating strings returned by @ALIAS you may need to disable certain special characters with <u>SETDOS [323]</u> /X. Otherwise, command separators, redirection characters, and other similar characters in the alias may be interpreted as part of the current command, rather than part of a simple text string.

Examples:

```
alias xyz=d:\path\myprog.exe -options
echo %@alias[xyz]
```

3.14.4.13 @ALTNAME

@ALTNAME[filename]: Returns the alternate (short, "8.3" FAT-format) name for the specified file. If the *filename* is already in 8.3 format, returns the filename. If the file does not exist, returns an empty string. If *filename* contains a \, @ALTNAME returns the SFN string of the full path.

Examples:

```
echo %@altname["Long Name.exe"]
echo %@altname["C:\Program Files\Microsoft Office"]
echo %@altname["%CommonProgramFiles"]
```

3.14.4.14 @ASCII

@**ASCII**[string]: Returns the space separated list of ASCII values of the characters in **string**. You can use the <u>Escape character</u> before a special character, e.g., a quote or greater than (>) sign, to include it in **string**.

Note: The @UNICODE 464 function will generally return more useful values.

Examples:

function	value
%@ascii[a]	97
%@ascii[A]	65
%@ascii[%=`]	96
%@ascii[abc]	97 98 99

See also: ASCII, Key Codes and Key Names 510).

3.14.4.15 @ASSOC

@ASSOC[.ext]: Returns the file association for the specified extension.

Example:

echo %@assoc[.doc]

3.14.4.16 @ATTRIB

@ATTRIB[filename[,-rhsadecijlopt[,p]]]: If you do not specify any attributes, @ATTRIB returns the attributes of the specified file in the format RHSADECIJNOPT, rather than 0 or 1. If two or more parameters are specified, @ATTRIB returns a 1 if the specified file has the matching attribute(s); otherwise it returns a 0.

The basic attributes for FAT volumes are:

- N Normal (no attributes set)
- R Read-only
- A Archive
- H Hidden
- **S** System
- **D** Directory

In addition, NTFS volumes allow display of the following extended attributes:

- **E** Encrypted
- **C** Compressed
- I Not content-indexed
- J Junction or symbolic link
- L Junction or symbolic link
- **N** Normal
- Offline
- P Sparse file
- T Temporary

The extended attributes are displayed when @ATTRIB is invoked with a single parameter, but they are suppressed when used for file selection (two or more parameters). To select files based on the

extended attributes, see @WATTRIB 4661.

Attributes which are not set will be replaced with an underscore. For example, if *SECURE.DAT* has the read-only, hidden, and archive attributes set, **@ATTRIB[SECURE.DAT]** would return RH_A_____. If the file does not exist, @ATTRIB returns an empty string.

The attributes (other than **N**) can be combined (for example %@ATTRIB[MYFILE,HS]). Normally @ATTRIB will only return **1** if all of the attributes match. However, if a final <code>,p</code> is included (partial match), then @ATTRIB will return **1** if any of the attributes match. For example, **%@ATTRIB[MYFILE,HS,p]** will return **1** if *MYFILE* has the hidden, system, or both attributes. Without <code>,p</code> the function will return **1** only if *MYFILE* has both attributes.

Filename must be in quotes if it contains white space or special characters.

See also: Attributes Switches 86.

Examples:

```
echo %@attrib["C:\Program Files\My Program\myfile.exe",rhs,p]
echo Attributes for myfile.exe: %@attrib[myfile.exe]
```

3.14.4.17 @AVERAGE

@AVERAGE[...]: Returns the average of a list of numbers. The average is returned as a double; you can adjust the decimal precision by running the result through @EVAL 420 (or @INT 443).

3.14.4.18 @CAPI

@CAPI[module,function[,integer | PING=n | PLONG=n | PDWORD=n | NULL | BUFFER | "string"] : Returns the result of calling a function with a _cdecl type in a DLL.

module - name of the DLL containing the function

function - function name (case sensitive)

integer - an integer value to pass to the function

PINT - a pointer to the integer *n*

PLONG - a pointer to the long integer *n*

PDWORD - a pointer to the DWORD *n*

NULL - a null pointer (0)

BUFFER - @CAPI will pass an address for an internal buffer for the API to return a Unicode string value.

aBUFFER - @CAPI will pass an address for an internal buffer for the API to return an ASCII string value.

"string" - text argument (this must be enclosed in double quotes). If the argument is preceded by an 'a' (i.e., a"Argument") then it is converted from Unicode to ASCII before calling the API. (Some Windows APIs only accept ASCII arguments.)

@CAPI supports a maximum of 8 arguments. The return value is either a string value returned by the API (if BUFFER or aBUFFER is specified), or the integer value returned by the API. The function must

be defined as _cdecl. If @CAPI can't find the specified function, it will append a "W" (for the Unicode version) to the function name and try again.

See also @WINAPI 467.

3.14.4.19 @CAPS

@CAPS[["xxx"],text]: Capitalizes the first letter of each word in the string (words that do not start with a letter remain unchanged). The optional first parameter, xxx, specifies the separators that you wish to use. The list must be enclosed in double quotes. If you want to use a double quote as a separator, prefix it with the Escape Character 124.

Examples:

```
echo %@caps[" ",i love take command]
echo %@caps[",",peter,paul,mary]
echo %@caps[" ^"","sacrebleu!", he said]
```

3.14.4.20 @CDROM

@CDROM[d:]: Returns **1** if the drive is an optical drive (CD-ROM, CD-RW, DVD, etc) or **0** otherwise. The drive letter must be followed by a colon.

Examples:

```
echo %@cdrom[C:]
echo %@cdrom[%_disk:]
```

3.14.4.21 @CEILING

@CEILING[n]: Returns the value of the smallest integer that is not less than *n*. @CEILING will perform an implicit @EVAL 420 on its argument, so you can enter an arithmetic expression.

Examples:

```
echo %@ceiling[3.14]
echo %@ceiling[-3.14]
echo %@ceiling[0]
echo %@ceiling[123*37.36]
```

See also: @FLOOR 435).

3.14.4.22 @CHAR

@CHAR[n]: Returns the character corresponding to a Unicode numeric value. If the parameter is a set of numeric values, CHAR returns a string. For example %@CHAR[65] returns A; %@CHAR[65 66 67] returns ABC.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Note: Not all characters are printable. High ASCII characters (128-255) and Unicode characters may vary depending on the font used.

Examples:

```
echo %@char[65]
echo %@char[65 97 66 98 67 99]
```

3.14.4.23 @CLIP

@CLIP[*n*]: Returns line *n* from the Windows text clipboard. The first line is numbered 0. The string ****EOC**** is returned for all line numbers beyond the end of the clipboard.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Examples:

```
echo %@clip[0]
if "%@clip[2]" eq "**EOC**" echo No more data in the clipboard
```

3.14.4.24 @CLIPW

@CLIPW[string]: Writes the **string** to the Windows text clipboard. Returns **0** if the operation was successful.

Examples:

```
if "%@clipw[save this line]" eq "0" echo Saved to the clipboard
```

3.14.4.25 @COLOR

@COLOR[r,g,b]: Displays the Windows color common dialog and returns the RGB value for the selected color as a string in the form r,g,b (e.g. 0,128,64). To specify the initially selected color, use the r (red), g (green) and b (blue) parameters. If no parameters are provided, the initial selection will be black (0,0,0). The parameters are optional, but if one is used all three must be used.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Examples:

```
@color[]
@color[155,0,0]
```

3.14.4.26 @COMMA

@COMMA[n]: Returns the number with commas (or the appropriate Thousands character or your current country setting) inserted where appropriate.

Note: Some <u>variable functions and careful separators if you add a **c** to their scale parameter.</u>

```
echo %@comma[12345678]
echo %@comma[0.12345678]
echo %@comma[%_xpixels]
```

See also: @CONVERT [413], @FORMAT [435], @FORMATN [436].

3.14.4.27 @COMPARE

@COMPARE[file1,file2]: Returns 1 if the two files are identical, or 0 if they differ. **@COMPARE** supports FTP filenames, but cannot compare two FTP files at the same time.

3.14.4.28 @CONSOLE

@CONSOLE[*title*]: Returns **1** if the specified window title belongs to a console window; **0** if it does not . The *title* may include wildcards 77.

3.14.4.29 @CONVERT

@CONVERT[*input*, *output*, *value*]: Returns a numeric string *value* converted from one number base (*input*) to another (*output*). Valid bases range from 2 to 36. The *value* can be between 0 and 2**64-1. No error is returned if *value* is outside that range.

Examples:

```
echo binary 1010101 is decimal %@convert[2,10,1010101] echo decimal 20 is hex %@convert[10,16,20] echo hexadecimal FF is octal %@convert[16,8,FF] echo this year is %@convert[10,2,%_year] in binary
```

See also: @COMMA 412, @FORMAT 435, @FORMATN 436.

3.14.4.30 @COUNT

@COUNT[c,string]: Returns the number of times the character c appears in string.

Examples:

```
echo %@count[a,Another function example]
```

3.14.4.31 @CRC32

@CRC32[filename]: Returns the CRC32 value (using the same algorithm as PKZIP or WINZIP) of the file specified by *filename*, or -1 if the file does not exist or cannot be opened.

```
See also: @SHA256 460, @SHA384 460, @SHA512 460, and @MD5 450...
```

```
echo %@crc32["C:\My Files\Myprog.exe"]
echo %@crc32["%comspec"]
```

3.14.4.32 @CWD

@CWD[*d:***]** : Returns the current working directory of the specified disk drive in the format *d:\pathname*. If the current working directory is the root directory, the format is *d:\l.* The drive letter must be followed by a colon.

Examples:

```
echo %@cwd[C:]
echo %@cwd[%_disk:]
See also: @CWDS 4141.
```

3.14.4.33 @CWDS

@CWDS[d:]: Returns the current working directory of the specified disk drive in the format d:\pathname\lambda. The drive letter must be followed by a colon.

Examples:

```
echo %@cwds[C:]
echo %@cwds[%_disk:]
See also: @CWD414.
```

3.14.4.34 @DATE

@**DATE**[date[,format]]: Returns the number of days since January 1, 1980 for the specified date. See date formats 127 for information on acceptable date formats. **Date** must be between 1980-01-01 and 2099-12-31 (inclusive).

@DATE accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@date[01-01-2008]
echo %@date[%_date]
```

3.14.4.35 @DAY

@DAY[date[,format]]: Returns the numeric day of the month for the specified date. See date formats for information on acceptable date formats.

@DAY accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)

- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@day[01-01-1980]
echo %@day[%_date]
```

3.14.4.36 @DEC

@DEC[string] : Returns :

- -1 if **string** is empty
- otherwise the same value as @EVAL 420 [string 1]

If **string** is the name of an environment variable, its value is used whether or not it is preceded by a percent sign % without modifying the value of the variable. To actually decrement the value of the variable **var** use:

```
set var=%@dec[%var]
```

3.14.4.37 @DECIMAL

@**DECIMAL**[number]: Returns the portion of **number** to the right of the <u>Decimal character</u> [51] as an integer numeric string. Trailing zeros are used to pad to the <u>Minimum Precision</u> [51] specified for @EVAL [420]. For example:

```
%@decimal[%@eval[1/2]]
```

is 5 if minimum width is 0, and 50000 if minimum width is 5.

@DECIMAL will perform an implicit @EVAL on its argument, so you can enter an arithmetic expression (including the @EVAL =min,max format string following the argument).

Examples:

function	value
%@decimal[1234]	0
%@decimal[1.234]	234
%@decimal[12.34]	34

3.14.4.38 @DESCRIPT

@DESCRIPT[filename]: Returns the file description for the specified filename (see DESCRIBE 195)).

The *filename* must be in quotes if it contains white space or special characters.

```
echo %@descript["D:\My Path\Myfile.exe"]
echo %@descript["%comspec"]
```

3.14.4.39 @DEVICE

@DEVICE[name]: Returns 1 if the specified name is a character device (such as a serial port), or 0 if not.

Examples:

```
echo %@device[lpt1]
echo %@device[com1]
echo %@device[com5]
echo %@device[clip]
```

3.14.4.40 @DIGITS

@**DIGITS**[*n*]: Returns **1** if the string is composed of decimal digits only, otherwise it returns **0**. The <u>Decimal character [51]</u>, the <u>Thousands character [51]</u>, and the sign characters (+ or -) are not digits, and if they are present in the string @DIGITS will return **0**.

Examples:

```
echo %@digits[12345]
echo %@digits[-12345]
echo %@digits[1.2345]
```

3.14.4.41 @DIRSTACK

@DIRSTACK[n]: Returns the name of the nth entry in the directory stack. The oldest is number 0. If no n parameter is specified, returns the total number of entries in the stack. The directory stack is set by calls to $\frac{\text{PUSHD}}{\text{POPD}}$ $\frac{\text{POPD}}{\text{POPD}}$

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

```
See also: DIRS 2009, POPD 2904, PUSHD 2909 and Directory Navigation 711.
```

Examples:

```
echo %@dirstack[0]
echo %@dirstack[2]
echo %@dirstack[]
```

3.14.4.42 @DISKFREE

@DISKFREE[d:[,scale[c]]]: Returns the amount of free disk space on the specified drive. If you're specifying a drive, the drive letter must be followed by a colon. Optionally, you can specify a directory or UNC name, and **@DISKFREE** will display the free disk space on the drive referenced by that name (which may be different from the drive if the directory is a link to a directory on another drive).

The optional second parameter specifies the reporting scale (see Memory Size / Disk Space / File Size Units and Report Format [395]). If the scale specification is suffixed with **c** the result will be formatted using the thousands separator [51].

@DISKFREE supports OpenAFS 103 names.

```
See also: @DISKTOTAL 417 and @DISKUSED 417.

Examples:

echo %@diskfree[c:]
echo %@diskfree[% disk:,Kc]
```

3.14.4.43 @DISKTOTAL

@DISKTOTAL[d:[,scale[c]]]: Returns the total disk space on the specified drive. If you're specifying a drive, the drive letter must be followed by a colon. Optionally, you can specify a directory or UNC name, and @DISKTOTAL will display the total disk space on the drive referenced by that name (which may be different from the drive if the directory is a link to a directory on another drive).

The optional second parameter specifies the reporting scale (see Memory Size / Disk Space / File Size Units and Report Format [395]). If the scale specification is suffixed with **c** the result will be formatted using the thousands separator [51].

```
@DISKTOTAL supports OpenAFS 103 names.

See also: @DISKFREE 416 and @DISKUSED 417.
```

Examples:

```
echo %@disktotal[c:]
echo %@disktotal[%_disk:,Kc]
```

3.14.4.44 @DISKUSED

@DISKUSED[d:[,scale[c]]]: Returns the amount of disk space in use on the specified drive. If you're specifying a drive, the drive letter must be followed by a colon. Optionally, you can specify a directory or UNC name, and **@DISKUSED** will display the disk space in use on the drive referenced by that name (which may be different from the drive if the directory is a link to a directory on another drive).

The optional second parameter specifies the reporting scale (see Memory Size / Disk Space / File Size Units and Report Format [395]). If the scale specification is suffixed with **c** the result will be formatted using the thousands separator [51].

```
@DISKUSED supports OpenAFS 103 names.
```

```
See also: @DISKFREE 416 and @DISKTOTAL 417).
```

Examples:

```
echo %@diskused[c:]
echo %@diskused[%_disk:,Kc]
```

3.14.4.45 @DOMAIN

@DOMAIN[name]: Returns the domain of the computer specified by the DNS or NetBios **name**. If **name** is not specified, returns the domain of the local computer.

3.14.4.46 @DOW

@**DOW**[date[,format]]: Returns the first three characters of the English name of the day of the week for the specified date ("Mon", "Tue", "Wed", etc.). See date formats | 127| for information on acceptable

date formats.

@DOW accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@dow[01-01-1980]
echo %@dow[%_date]
```

See also: @IDOW 439.

3.14.4.47 @DOWF

@**DOWF**[date[,format]]: Returns the full English name of the day of the week for the specified date ("Monday", "Tuesday", etc.). See date formats [127] for information on acceptable parameter formats.

@DOWF accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@dowf[01-01-1980]
echo %@dowf[%_date]
```

See also: @IDOWF 439).

3.14.4.48 @DOWI

@**DOWI**[date[,format]]: Returns an integer representing the day of the week for the specified date (1 = Sunday, 2 = Monday, etc.). See date formats [127] for information on acceptable date formats.

@DOWI accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

```
echo %@dowi[01-01-1980]
echo %@dowi[%_date]
```

3.14.4.49 @DOY

@DOY[date[,format]]: Returns the day of year (1 - 366) for the specified date. See <u>date formats</u> 127) for information on acceptable date formats.

@DOY accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@doy[02-02-2005]
echo %@doy[%_date]
```

3.14.4.50 @DRIVETYPE

@DRIVETYPE[*drive*]: Return the type for the specified drive:

- **0** The drive type cannot be determined
- 1 The root path is invalid (no volume is mounted at the path)
- 2 Removable disk
- 3 Fixed disk
- 4 Remote (network) drive
- 5 CD-ROM
- 6 RAM disk

3.14.4.51 @DRIVETYPEEX

@DRIVETYPEEX[drive]: Return the type for the specified drive:

- **0** The drive type cannot be determined
- 1 The root path is invalid (no volume is mounted at the path)
- 2 Removable disk
- 3 Fixed disk
- 4 Remote (network) drive
- 5 CD-ROM
- 6 RAM disk
- 7 DVD
- 8 Tape

3.14.4.52 @ENUMSERVERS

@ENUMSERVERS[n, server[n, type]]: Enumerate the servers on the network. n is the entry number in the list of servers (the first one is n). **server** is the machine name(s) to match and it may contain n mildcards n. Returns a null string if there are fewer than n matching servers. This function can be repeatedly called, incrementing n each time to enumerate all available server names until it returns a null string.

If *n* is -1, @ENUMSERVERS returns the number of matching servers.

@ENUMSERVERS takes an optional third argument to return only servers of that type. The possible types are:

WORKSTATION - All workstations.

SQLSERVER - Any server running Microsoft SQL Server
DOMAIN - Primary domain controller
DOMAINBACKUP - Backup domain controller
DOMAIN_ENUM - Primary domain
LOCAL - Servers maintained by the browser
AFP - Apple File Protocol servers
TIME - Servers running the Timesource service
PRINTQ - Server sharing print queue
TERMINAL - Terminal Servers
CLUSTER - Server clusters in the domain
VSCLUSTER - Cluster virtual servers in the domain
MASTER - Server running the master browser service

WARNING! Windows may require a significant amount of time before returning data to this function when used on large networks.

Examples:

```
echo %@enumservers[0,\\SERVER]
for %i in (0 1 2) echo %@enumservers[%i,*]
```

3.14.4.53 @ENUMSHARES

@ENUMSHARES[n,\lserver\shares]: Enumerate the share names for the specified server. n is the entry number in the list of shares (the first one is 0). server is the server name, and shares is the sharename(s) to match. Shares may contain wildcards . Returns a null string If there are fewer than n matching shares. This function can be repeatedly called, incrementing n each time to enumerate all available shares until it returns a null string.

If the n is -1, @ENUMSHARES returns the number of matching sharenames.

Examples:

```
echo %@enumshares[0,\\SERVR\DRIVE_C]
for %i in (0 1 2) echo %@enumshares[%i,\\SERVER\DRIVE_*]
```

3.14.4.54 @ERRTEXT

@ERRTEXT[*n*] : Returns the operating system error text for the specified code.

Examples:

```
echo %@errtext[2]
echo %@errtext[255]
echo %@errtext[%_syserr]
```

3.14.4.55 @EVAL

@EVAL[expression[=displayformat]]: Evaluates a mathematical expression and returns its value in the format specified by displayformat or in the default format. Parameter Interpretation 42th below describes what expression may contain. Display precision and output format 42th below explains the result format.

The expression can contain environment variables and other variable functions, and may use any of the operators listed below. @EVAL also supports parentheses (to control evaluation order), commas, hexadecimals and decimal separators. Parentheses can be nested. @EVAL will strip leading and trailing zeros from the result unless you use the output formatting operators.

@EVAL supports very large numbers. The maximum size is 20,000 digits (10,000 digits to the left of the decimal point and 10,000 decimal places). If you want to use more than the default decimal values you'll need to change your @Eval Precision on figuration options or use the "=x.y" format in @EVAL.

- ▶ Parameter Interpretation 421
- Arithmetic operators 42
- Trigonometric and transcendental functions 422
- Order of precedence 423
- Precision of internal calculations 423
- Display precision and output format 423
- Examples 423

Parameter Interpretation

Expression may contain environment and internal variables and variable functions. After all variables and functions have been expanded, it must be composed only of numeric strings and names of functions in <u>Trigonometric and transcendental functions</u> (422), connected by <u>Arithmetic operators</u> (421) and optionally grouped with parentheses.

@EVAL permits you to simplify *expression* by dropping the % percent mark in front of the names of environment variables. You must include % for internal variables and variable functions. @EVAL also permits you to use characters which normally have special meaning for TCC e.g., $& < > ^ |$ without disabling their special meaning or quoting them.

Note: To ensure that **expression** is interpreted correctly, spaces should be placed on both sides of each operator, and parentheses used liberally. For example:

```
%@eval[(20 %% 3) + 4]
%@eval[12 and 65]
```

@EVAL also accepts numbers in the e exponent syntax; i.e. 1575e-2 = 15.75.

Number base

If a string starts with the characters 0x it is interpreted as an integer in hexadecimal notation, and may be up to 16 digits long. Any other numeric string is considered to be a decimal number.

For example:

```
[c:\] echo %@eval[0x10 + 16]
32
```

You can specify hexadecimal output with the special syntax @eval[...=H]. For example:

```
echo %@eval[3*6=H]
```

will output 12 (hex). No leading 0x is included in the output. To convert between decimal and hexadecimal formats, see the @CONVERT [413] function.

Arithmetic operators

Every operator accepts both integer and non-integer parameters, except as noted below.

Operators accepting fractional parameters

- + (with one parameter) sign of numeric parameter (e.g. +3)
- + (with two parameters) addition
- (with one parameter) negation of symbolic parameter (e.g., -%n) or sign of numeric parameter (e.g. -1, +3)
- (with two parameters) subtraction
- * multiplication
- / division
- ** exponentiation

Operators requiring integer parameters

\	integer division (returns the integer part of the quotient)
MOD	modulo (returns the remainder when the first parameter is divided by the second)
%%	same as MOD
SHL	arithmetic left shift of the first parameter, truncated toward zero to an integer, by the number of bits specified by the second parameter
<<	same as SHL
SHR	arithmetic right shift of the first parameter, truncated toward zero to an integer, by the number of bits specified by the second parameter
>>	same as SHR

Operators which truncate parameters to integer

AND	bitwise and (returns 1 for each bit position where the corresponding bits in both parameters are 1)
&	same as AND
OR	bitwise or (returns 1 for each bit position where the corresponding bit in at least one parameter is 1)
1	same as OR
XOR	bitwise exclusive or (returns 1 for each bit position where the corresponding bits of the two parameters are different)
^	same as XOR
~	Unary NOT

Trigonometric and transcendental functions

Expression may include the trigonometric and transcendental functions below. The argument is interpreted as radians.

```
log(x)
          natural logarithm
log10(x) log 10
          exponential
\exp(x)
sin(x)
          sine
asin(x) arcsine
sinh(x) hyperbolic sine
cos(x)
         cosine
acos(x) arccosine
cosh(x) hyperbolic cosine
tan(x)
          tangent
atan(x) arctangent
         hyperbolic tangent
tanh(x)
```

The special string PI is a shortcut for the value 3.14159265358979323846.

Order of precedence

- 1. variables
- 2. expressions in matching parentheses
- 3. functions listed in Trigonometric and transcendental functions 422
- 4. exponentiation
- 5. multiplication, division, and MOD
- 6. addition and subtraction
- 7. AND, OR, XOR, SHL, and SHR

When multiple consecutive expressions of a single precedence level are used, evaluation is left to right.

For example, 3 + 4 * 2 will be interpreted as 3 + 8, not as 7 * 2. To change this order of evaluation, use parentheses to specify the order you want.

Precision of internal calculations

@EVAL supports numbers up to 20,000 digits; it is highly unlikely you'll need greater precision than this!

Display precision and output format

The maximum display precision is 10,000 digits to the left of the decimal point and 10,000 digits to the right. You can alter the default decimal precision with the OPTION 2841 command, the @EVAL Precision 511 configuration options, and with the SETDOS 3231 /F command. You can change the decimal separator with the decimal character 511 configuration option or the SETDOS 3231 /G command.

You can alter the display format for the current instance of @EVAL by specifying displayformat.

Hexadecimal display format specification

If *displayformat* is the letter **H**, output will be hexadecimal. If *displayformat* is **X**, the output will be hexadecimal with a leading **0x**.

Explicit precision specification

If *displayformat* is *i.a*, then:

- *i* must be a number which specifies the minimum decimal precision (the minimum number of decimal places displayed);
- a must be a number which sets the maximum decimal precision.
- the character separating *i* and *a* may be the comma if it is your decimal separator

You may specify either or both parameters i and a. If i > a, or if only i is specified, i is used as both the minimum and maximum precision, e.g. both = 2 and = 2.1 are equivalent to = 2.2.

Expression	Value
<pre>@eval[3 / 6=2.4]</pre>	0.50
<pre>@eval[3 / 6=4.4]</pre>	0.5000
@eval[3 / 7]	0.4285714286

@eval[3 / 7=.4]	0.4286
@eval[3 / 7=2.2]	0.42
@eval[3 / 7=2]	0.42

See also: @DEC 415 and @INC 440.

3.14.4.56 @EXEC

@EXEC[command]: Execute command and return its numeric exit code.

Command can be an alias, internal command, external command, .BTM, .BAT, or .CMD file.

By default, @EXEC returns the result code from **command** (see the ? 380 and ? 380 variables). However, if in **command** you preface the command name with @ then @EXEC returns an empty string.

Example:

```
 PROMPT = \ensuremath{\texttt{@exec}} \ensuremath{\texttt{@color}} \ensuremath{\texttt{15}} \ensuremath{\texttt{on}} \ensuremath{\texttt{%eremovable}} \ensuremath{\texttt{[\&_disk]}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{0,2,4}} \ensuremath{\texttt{\&echos}} \ensuremath{\texttt{[\&_cwd\&]}} \ensuremath{\texttt{\&echos}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{0,2,4}} \ensuremath{\texttt{\&echos}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{on}} \ensuremath{\texttt{0,2,4}} \ensuremath{\texttt{\&echos}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{on}} \ensuremath{\texttt{0,2,4}} \ensuremath{\texttt{\&echos}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{on}} \ensuremath{\texttt{0,2,4}} \ensuremath{\texttt{eq}} \ensuremath{\texttt{
```

See also: @EXECSTR 424).

3.14.4.57 @EXECSTR

@EXECSTR[command]: Runs the specified **command** and returns the first line written to stdout by **command**.

@EXECSTR is useful for retrieving a result from an external utility — for example, if you have an external utility called **NETTIME.EXE** which retrieves the time of day from your network server and writes it to standard output, you could save it in an environment variable using a command like this:

```
set server time=%@execstr[d:\path\nettime.exe]
```

If the same utility returned a result properly formatted for the TIME command, you could also use it to set the time on your system:

```
time %@execstr[d:\path\nettime.exe]
```

@EXECSTR can also be used with internal commands:

```
echo Newest file is: %@execstr[*dir /a:-d /h /o:-t /f]
```

@EXECSTR involves several extensive internal processing stages. You might be able to use more complex command sequences (pipes, command groups, etc.) as its parameter, but always *test* carefully first as the results may not always be what you expect. We recommend that you only use a single command (internal, external, batch file, etc.) parameter.

Note: Remember that only the first line of standard output is returned. Since many internal and external commands start their text output on the second line, @EXECSTR[] may not return any useful information from those commands.

See also: @EXEC 424.

3.14.4.58 @EXETYPE

@EXETYPE[filename]: Returns the application type for an executable file:

Code	Application type
0	Unknown
1	DOS app
2	PIF file
3	Win16
4	Win 3.x VxD
5	OS/2
6	Win32 GUI
7	Win32 console
8	Posix

Examples:

```
echo %@exetype["d:\path\myprog.exe"]
echo %@exetype["%comspec"]
```

3.14.4.59 @EXPAND

@EXPAND[[range...] filename[,[{+|-}]rhsadecijopt]]: Returns (in a single line), the names of all files and directories that are within the specified range[s], AND match filename, AND have the specified attributes. Filename may contain wildcards range[s], and include lists 88. Returns an empty string if no files match. If the file list is longer than the allowed command line length 126, it will be truncated without an error message. Each returned filename which contains white space or other special characters will be delimited by double quotes.

Filename must be in double quotes if it contains white space or special characters.

The *range* and attribute parameters, if included, define properties of the files that will be included in the result as specified in <u>File Selection</u>. Multiple *range* parameters may be included, but not more than one each of <u>description range</u> 86, <u>size range</u> 82, <u>date range</u> 82, and <u>time range</u> 84. *Range* parameters must precede *filename*. <u>Exclusion ranges</u> 85 are not supported.

Examples:

```
echo %@expand[/[s2k,3k] *.txt]
```

all files with extension **txt** in the current directory with size at least 2000 bytes and at most 3000 bytes

```
echo %@expand[*,d]
  all subdirectories
echo %@expand[/[d-365] %windir\w*.exe;w*.dll]
```

all files at most 365 days old in the Windows directory, with extension EXE or DLL, and name beginning with \boldsymbol{W} .

3.14.4.60 @EXT

@EXT[*filename*]: Returns the extension from *filename*, without a leading period. On volumes which support long file names, the extension can be up to 255 characters long. On FAT drives it can be up to 3 characters long. *filename* must be quoted if it contains white space or special characters.

On an LFN drive, the returned extension may contain white space or special characters. To avoid problems which could be caused by these characters, quote the returned extension before you pass it to other commands.

Examples:

```
echo %@ext[%@comspec]
echo %@ext["LFN Names may have.very long extensions"]
```

3.14.4.61 @FIELD

@FIELD[["sep_list",]n,string]: Returns the nth field in string. The first field is numbered n. If n is negative, fields are counted backwards from the end of string. You can specify the rightmost field by setting n to n0.

You can specify a range of fields to return with the syntax:

```
@FIELD[["sep_list",]start[-end | +range],string]
```

Specify an inclusive range with a -. For example:

%@FIELD[2-4,A B C D E F G] will return "C D E". (Note that you cannot use inclusive ranges when starting from the end.)

You can specify a relative range with a +. For example:

```
%@FIELD[2+1,ABCDEFG] will return "CD".
```

The default list of separators for @FIELD 4261, @FIELDS 4271, @WORD 4721 and @WORDS 4731 consists of space, tab, and comma. You can use the optional first parameter, **sep_list**, to specify the separators that you wish to use. If you want to use a double quote as a separator, prefix it with an escape character 511, e.g., %=". Alphabetic characters in **sep_list** are case sensitive. If you do not specify a separator list, @FIELD will skip any leading separators.

@FIELD 4261 and @FIELDS 4271 differ from @WORD 4721 and @WORDS 4731 in how multiple consecutive separators are counted. @WORD 4721 and @WORDS 4731 consider a sequence as a single separator, and ignore separators at either end of string. In contrast, @FIELD 4261 and @FIELDS 4271 count each occurrence of a separator individually, including those at either end of string.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). To use hexadecimal form for a negative \mathbf{n} , remember to use 32-bit 2's complement arithmetic, e.g., $\mathbf{0xFFFFFFFF}$ for -1. There is no hexadecimal form to specify field -0 (the rightmost field).

If string is double quoted, you must specify sep_list.

See also: @WORD 472, @WORDS 473, @FIELDS 427.

function	value
%@field[2,zero,one,two,three]	two
%@field[2,zero,,two,three]	two

<pre>%@field["\",2,C:\Program Files\My Dir\myapp.exe]</pre>	My Dir
<pre>%@field[-2,zero,one,two,three]</pre>	one

3.14.4.62 @FIELDS

@FIELDS[["sep_list",]string]: Returns the number of fields in string.

The default list of separators for @FIELD 4261, @FIELDS 4271, @WORD 4772 and @WORDS 4773 consists of space, tab, and comma. You can use the optional first parameter, **sep_list**, to specify the separators that you wish to use. If you want to use a quote mark as a separator, prefix it with an escape character 511, e.g., %=". Alphabetic characters in **sep_list** are case sensitive. If you do not specify a separator list, @FIELD will skip any leading separators.

@FIELD 4261 and @FIELDS 4271 differ from @WORD 47721 and @WORDS 47731 in how multiple consecutive separators are counted. @WORD 47721 and @WORDS 47731 consider a sequence as a single separator, and ignore separators at either end of string. In contrast, @FIELD 4261 and @FIELDS 4271 count each occurrence of a separator individually, including those at either end of string.

If **string** is double quoted, you must specify **sep_list**.

See also: @WORD 472, @WORDS 473, @FIELD 426.

3.14.4.63 @FILEAGE

@FILEAGE[filename[,a|c|w[u]]] : Returns the date and time of the file as an age [520].

Filename must be in quotes if it contains white space or special characters. The optional second parameter selects which date field is returned for files on a $\frac{VFAT}{536}$ or $\frac{NTFS}{532}$ drive: **a** means the last access date, **c** means the creation date, and **w** means the last modification (write) date. The default is **w**.

If you append a *u* to the second argument, @FILEAGE will display the age in UTC.

Examples:

```
echo %@fileage[d:\path\myfile.ext]
echo %@fileage["%comspec",c]
```

See also: Time Stamps 495), @AGEDATE 408 and @MAKEAGE 449).

3.14.4.64 @FILECLOSE

@FILECLOSE[*n*]: Closes the file whose handle is *n*. Returns **0** if the file was successfully closed, or **-1** if an error occurred.

This function should only be used with file handles returned by <u>@FILEOPEN [428]</u>! If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

See also the related handle-based functions:

@FILEOPEN 428 @FILEREAD 429 @FILESEEK 431 @FILESEEKL 431 Open a file handle Read next line from a file handle Move a file handle pointer Move a file handle pointer to a specified line



Write next line to a file handle Write data to a file handle Truncate the file at the current position of the file handle pointer.

3.14.4.65 @FILEDATE

@FILEDATE[filename[,a|c|w[u,d]]] : Returns the date a file was last modified, in the default country format (mm-dd-yy for the US), or as explicitly specified by the optional third parameter **d** (see <u>Date Display Formats [406]</u>). *Filename* must be in quotes if it contains white space or special characters. The optional second parameter selects which date field is returned for files on an LFN drive: **a** means the last access date, **c** means the creation date, and **w** means the last modification (write) date, which is the default.

If you append a u to the second argument, @FILEDATE will display the date in UTC.

Examples:

```
echo %@filedate["D:\my path\myfile.exe"]
echo %@filedate["comspec",c,4]
```

See Time Stamps 4951, @FILETIME 4321, @FILEAGE 4271.

3.14.4.66 @FILENAME

@FILENAME[*filename*]: Returns the name and extension of a file, without a path.

The *filename* must be in quotes if it contains white space or special characters. On an LFN drive, the returned filename may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands.

Examples:

```
echo %@filename["D:\my path\myfile.exe"]
echo %@filename["comspec"]
```

3.14.4.67 @FILEOPEN

@FILEOPEN[filename,r[ead]]w[rite]]a[ppend][,b|t]]: Opens the file in the specified mode and returns the file handle as an integer. The optional third parameter controls whether the file is opened in binary or text mode. Text mode (the default) should be used to read text using @FILEREAD without a length, and to write text using @FILEWRITE [433]. Binary mode should be used to read binary data with @FILEREAD [429] with a length, and to write binary data with @FILEWRITEB [433]. Returns -1 if the file cannot be opened.

Filename must be in quotes if it contains white space or special characters.

To open a file for both reading and writing, open it in append mode, then use <u>@FILESEEK</u> 43 to position to the start of the file (or any other desired location) before performing additional operations.

@FILEOPEN can also open named pipes. The pipe name must begin with \\.\pipe\. @FILEOPEN first tries to open an existing pipe; if that fails it tries to create a new pipe. Pipes are opened in blocking mode, duplex access, byte-read mode, and are inheritable. For more information on named pipes see your Windows documentation.

@FILEOPEN can open file streams on NTFS drives if the stream name is specified. See NTFS File Streams 496 for additional details on file streams.

You must reference the file exclusively using the returned file handle, and you must close the file using the file handle. This is especially important when you are debugging a batch program which uses @FILEOPEN. If you suspect that file handles have been opened and not closed, you should restart **TCC**.

Examples:

```
set h=%@fileopen["d:\path\myfile.txt",write]
echo writing %@filewrite[%h,this is a test] bytes
echo closing handle #%h: %@fileclose[%h]
```

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEK 431	Move a file handle pointer
@FILESEEKL 43	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle
	pointer.

3.14.4.68 @FILEREAD

@FILEREAD[n[,length]]: Reads data from the file whose handle is **n**. Returns the string **EOF** if you attempt to read past the end of the file. If **length** is not specified, @FILEREAD will read until the next CR or LF (end of line) character. If **length** is specified, @FILEREAD will read **length** bytes regardless of any end of line characters.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN</u> 4281. If you use it with any other number you may damage other files opened by **TCC** (or by the program which started **TCC**).

Beware of characters with special meaning to *Take Command*, such as redirection and piping symbols, within the file. Use SETDOS [323] /X with appropriate codes as needed.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILESEEK 43h	Move a file handle pointer
@FILESEEKL 43	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer.

3.14.4.69 @FILEREADB

@FILEREADB[*n*,*length*]: Reads *n* bytes of data from the file whose handle is *n*. Returns the string **EOF** if you attempt to read past the end of the file. The data will be returned as a string of space-separated numeric digits representing the ASCII value of each character.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN</u> 4281. If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

Beware of characters with special meaning to *TCC*, such as redirection and piping symbols, within the file. Use SETDOS 323 /X with appropriate codes as needed.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILESEEK 43	Move a file handle pointer
@FILESEEKL 431	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer.

3.14.4.70 @FILES

@FILES[[/S[n]] [range...] filename[,[{+|-}]rhsadecijopt]]: Returns the number of files within *range* that match *filename* and have the specified attributes. *Filename* may contain wildcards and include lists 8. Returns 0 if no files match. To check files in multiple directories use @FILES once for each, and add the results with @EVAL 420.

Filename must be in double quotes if it contains white space or special characters.

The *range* and <u>attribute</u> of the files that will be included in the result as specified in <u>File Selection</u>. Multiple *range* parameters may be included, but not more than one each of <u>description range</u> of the files that will be included in the result as specified in <u>File Selection</u>. Multiple *range* parameters may be included, but not more than one each of <u>description range</u> of the files that will be included in the result as specified in <u>File Selection</u>. Multiple *range* parameters may be included, but not more than one each of <u>description range</u> of the files that will be included in the result as specified in <u>File Selection</u>. Multiple <u>range</u> parameters may be included, but not more than one each of <u>description range</u> of the files that will be included in the result as specified in <u>File Selection</u>, date range of the files that will be included in the result as specified in <u>File Selection</u>, date range of the files that will be included in the result as specified in <u>File Selection</u>. Multiple <u>range</u> parameters may be included, but not more than one each of <u>description range</u> of the files that will be included in the result as specified in <u>File Selection</u>. Multiple <u>range</u> of the files that will be included in the result as specified in <u>File Selection</u>. The files that will be included in the result as specified in <u>File Selection</u>. The files that will be included in the result as specified in <u>File Selection</u>. The files that will be included in the result as specified in <u>File Selection</u>. The files that will be included in the result as specified in <u>File Selection</u> parameters as a specified in <u>File Selection</u> parameters.

If you include the optional **/S** argument, @FILES will search the current directory and all of its subdirectories for matching files. If you specify a number after the /S, @FILES will limit the subdirectory recursion to that number. (For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.)

If you are searching for subdirectories (i.e., by specifying "d" in the attribute argument), @FILES will not count the "." and ".." directory entries.

```
echo %@files[/[s2k,3k] *.txt]
number of files with extension txt in the current directory with size at least 2000 bytes and at most 3000 bytes

echo %@files[*,d]
number of subdirectories

echo %@files[/[d-365] %windir\w*.exe;w*.dll]
number of files at most 365 days old in the Windows directory, with extension EXE or DLL, and name beginning with w
```

3.14.4.71 @FILESEEK

@FILESEEK[n,offset,start] Moves the file pointer of the file whose handle is **n** by **offset** bytes from the reference location specified via **start** (see the table below). The return value of @FILESEEK is the offset of the file pointer from the beginning of the file after the specified move. If **offset** is negative, the file pointer is moved from the reference location toward the beginning of the file. If **offset** is positive, the file pointer is moved from the reference location toward the end of the file. If **offset** is 0, the pointer is moved to the reference location.

If the function fails, the return value is -1.

start	reference location	
0	beginning of file	
1	current file pointer	
2	end of file	

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN</u> 4281. If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

Useful special cases

If you set **offset** to **0**:

- @FILESEEK[n,0,0] moves the file pointer to the beginning of file
- @FILESEEK[n,0,1] returns the current location of the file pointer without moving it.
- @FILESEEK[n,0,2] moves the file pointer to the end of file, and returns the current file size.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEKL 43	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer.

3.14.4.72 @FILESEEKL

@FILESEKL[n,line[,1]]: Moves the file pointer to the specified *line* in the open file whose handle is **n**. The first line in the file is numbered **0**. Returns the new position of the pointer, in bytes from the start of the file. The third parameter is optional, and determines the starting point for the seek. If not specified, or set to a value other than **1**, @FILESEEKL starts at the beginning of the file. If set to **1**, @FILESEEKL will start from the current position in the file.

If the function fails, the return value is -1.

@FILESEEKL must read each line of the file up to the target line in order to position the pointer, and can therefore cause significant delays if used in a loop or on a large file.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN</u> 428). If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEK 431	Move a file handle pointer
@FILEWRITE 433	Write next line to a file handle
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer.

3.14.4.73 @FILESIZE

@FILESIZE[[/S[n]] [range...] filename[,[scale[c][,a]]]: Returns the size of a file, or -1 if the file does not exist. If *filename* includes wildcards ref or an include list ship, it returns the combined size of all matching files. The optional third parameter a tells @FILESIZE to return the amount of space allocated for the file(s) on the disk. (Network drives and compressed drives may not always report allocated sizes accurately, depending on the way the network or disk compression software is implemented.)

Filename must be in quotes if it contains white space or special characters.

The second parameter specifies the reporting scale (see Memory Size / Disk Space / File Size Units and Report Format [395]). Adding the letter **c** requests the result be formatted using the thousands separator [51].

The optional *range* parameter defines properties of the files that will be included in the result as specified in <u>File Selection 177</u>. Multiple *range* parameters may be included, but not more than one each of <u>description range 88</u>, <u>size range 82</u>, <u>date range 82</u>, and <u>time range 84</u>. *Range* parameters must precede *filename*. Exclusion ranges 85 are not supported.

If you include the optional /S argument, @FILESIZE will search the current directory and all of its subdirectories for matching files. If you specify a number after the /S, @FILES will limit the subdirectory recursion to that number. (For example, if you have a directory tree "\a\b\c\d\e", /S2 will only affect the "a", "b", and "c" directories.)

Examples:

```
echo %@filesize[d:\path\myfile.ext]
echo %@filesize["%comspec",bc]
echo %@filesize["%comspec",bc,a]
```

3.14.4.74 @FILETIME

@FILETIME[filename[,[a|c|w[u]]][,s]]]: Returns the time of day a file was last modified, in hh:mm format. *Filename* must be in quotes if it contains white space or special characters. The optional second parameter selects which time field is returned for files on an LFN drive: *a* means the last access time, *c* means the creation time, and *w* means the last modification (write) time, which is the default. Times are normally returned with hours and minutes only. To retrieve seconds as well, add *s* as the optional third parameter. On non-NTFS drives, the last access time is always returned as 00:00, and without a seconds field (see Time Stamp [495] for additional details).

If you append a u to the second argument, @FILETIME will display the time in UTC.

Examples:

```
echo %@filetime["D:\my path\myfile.exe"]
echo %@filetime["comspec",c,s]
```

See also: @FILEDATE 428, @FILEAGE 427.

3.14.4.75 @FILEWRITE

@FILEWRITE[n,text]: Writes a line to the file whose handle is **n**. Returns the number of characters written, or **-1** if an error occurred. A CR/LF will be appended to *text*.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN</u> 4281 If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

Beware of characters with special meaning to *TCC*, such as redirection and piping symbols, within the file. Use SETDOS [323] /X with appropriate codes as needed.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEK 43	Move a file handle pointer
@FILESEEKL 431	Move a file handle pointer to a specified line
@FILEWRITEB 433	Write data to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer.

3.14.4.76 @FILEWRITEB

@FILEWRITEB[n,length,string]: Writes the specified number of bytes from the **string** to the file whose handle is **n**. Returns the number of bytes written, or **-1** if an error occurred.

Note: Writes ASCII output when passed a Unicode string. Note that if you're trying to write non-English (>128) characters with @FILEWRITEB, the output will probably not match the input.

If the *length* argument is -1, @FILEWRITEB will read the string argument as a series of ASCII values in decimal or hex to write to the file. For example:

```
echo %@filewriteb[%file,-1,0xe0 0xF2 0xA9]
```

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

This function should only be used with file handles returned by <u>@FILEOPEN!</u> 428 If you use it with any other number you may damage other files opened by *TCC* (or by the program which started *TCC*).

Beware of characters with special meaning to *TCC*, such as redirection and piping symbols, within the file. Use SETDOS [323] /X with appropriate codes as needed.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEK 431	Move a file handle pointer
@FILESEEKL 43	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@TRUNCATE 464	Truncate the file at the current position of the file handle pointer

3.14.4.77 @FINDCLOSE

@FINDCLOSE[filename]: Signals the end of a @FINDFIRST [434] ... @FINDNEXT [435] sequence. You must use this function to release the directory search handle. *Filename* is unnecessary, this function can be simply called as %@FINDCLOSE[] without parameters. @FINDCLOSE returns 0 if a @FINDFIRST [434] ... @FINDNEXT [435] sequence is in effect, a non-zero value otherwise.

Examples:

```
echo %@findfirst[*.exe]
echo %@findclose[]
```

3.14.4.78 @FINDFIRST

@FINDFIRST[[range...] filename[,[+|-]rhsadecijopt]]: Returns the name of the first file that matches filename, which may include wildcards and or an include list 88, and which file has the properties specified in the optional range 80 and attribute 86 parameters.

Filename must be in quotes if it contains white space or special characters.

The *range* and attribute parameters, if included, define properties of the files that will be included in the search as specified in <u>File Selection</u> Multiple *range* parameters may be included, but not more than one each of <u>size range</u> 82, <u>date range</u> 82, and <u>time range</u> 84. *Range* parameters must precede *filename*. Each *range* parameter is of the form

```
/[a...]
```

where \boldsymbol{a} is one of \boldsymbol{d} , \boldsymbol{s} or \boldsymbol{t} , optionally followed by range parameters.

On an LFN drive, the returned filename may contain white space or other special characters. Unlike <a href="MEXPAND[]] [425], no double quotes are added by this function. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under Variable Functions [395] for additional details.

@FINDFIRST[] locates the *first* file matching the requirements. To find more matching files, you must use <u>@FINDNEXT[]</u> [435], and terminate the search with <u>@FINDCLOSE[]</u> [434].

Warning: @FINDFIRST searches may not be nested!

```
%@findfirst[/[d-30] *]
locate files created no more than 30 days ago
%@findfirst[/[s2k,3k] "%windir\*.exe",a]
```

locate files with the extension **exe**, the archive flag set, and at least 2,000 bytes but not more than 3,000 bytes long, in the Windows directory.

3.14.4.79 @FINDNEXT

@FINDNEXT[[filename[,[][-]rhsadecijopt]]]: Returns the name of the next file that matches the filename(s) in the previous @FINDFIRST call. Returns an empty string when no more files match. @FINDNEXT should only be used after a successful call to @FINDFIRST [434].

You do not need to include the *filename* parameter, because it must be the same as the one used in the previous @FINDFIRST call, unless you want to change the file attributes for @FINDNEXT. *Filename*, if used, must be in quotes if it contains white space or special characters.

The attribute parameter, if included, defines the attributes of the files that will be included in the search as specified in Attribute Switches 6.

Range parameters may not be used in this function. The **range** parameters specified in the preceding @FINDFIRST call remain effective.

If you don't need to change the attribute parameters established by the preceding @FINDFIRST, you can simply use this function as %@FINDNEXT[] without parameters.

@FINDFIRST[] locates the first file matching the requirements. To find more matching files, you must use @FINDNEXT[] [435], and terminate the search with @FINDCLOSE[] [434].

Examples:

```
echo %@findfirst[*]
echo %@findnext[]
echo %@findnext[*,d]
echo %@findclose[]
```

3.14.4.80 @FLOOR

@FLOOR[n]: Returns the largest integer that is not greater than n. **@FLOOR** will perform an implicit **@EVAL**[n] on its argument, so you can enter an arithmetic expression.

Examples:

```
echo %@floor[3.14]
echo %@floor[-3.14]
echo %@floor[0]
echo %@floor[123]
```

See also: @CEILING 411.

3.14.4.81 @FORMAT

@FORMAT[format, string]: Reformats **string**, truncating it or padding it with spaces or zeros as necessary. **format** is of the format [-]i.a. If the optional minus sign is present, the result is left justified;

otherwise it is right justified. If *i* is specified, and its first digit is **0**, the padding character will will be **0**, otherwise it will be a space. *i* is the minimum number of characters in the result, *a* is the maximum number of characters. If *a* is less than *i*, it will be ignored.

Examples

function	value
"%@format[7,Hello]"	" Hello"
"%@format[.3,Hello]"	"Hel"
"%@format[4,5]"	" 5"
"%@format[04,5]"	"0005"
"%@format[-04,5]"	"5000"

See also: @COMMA 412, @CONVERT 413, @FORMATN 436.

3.14.4.82 @FORMATN

@FORMATN[[-]width[.precision],value]: Formats a numeric value. Width is a nonnegative integer specifying the minimum number of characters printed. If Width has a leading 0, the number will be left-padded with zeros. If the number of characters in the output value is less than the specified width, blanks are added to the left or the right of the values depending on whether the "-" flag (for left alignment) is specified, until the minimum width is reached. Precision specifies the number of digits after the decimal point. The value is rounded to the appropriate number of digits.

If you don't specify a precision, @FORMATN will default to 16 decimal places, and may not round the number appropriately. (For example, @FORMATN[3,3.4] will produce "3.3999999999999".)

See also: @COMMA 412, @CONVERT 413, @FORMAT 435, @FORMATNC 436).

3.14.4.83 @FORMATNC

@FORMATNC[[-]width[.precision],value] : Formats a numeric value and automatically inserts the thousands separator. *Width* is a nonnegative integer specifying the minimum number of characters printed. If *Width* has a leading 0, the number will be left-padded with zeros. If the number of characters in the output value is less than the specified width, blanks are added to the left or the right of the values depending on whether the "-" flag (for left alignment) is specified, until the minimum width is reached. *Precision* specifies the number of digits after the decimal point. The *value* is rounded to the appropriate number of digits.

See also: @COMMA 4121, @CONVERT 4131, @FORMAT 4361, @FORMATN 4361.

3.14.4.84 @FSTYPE

@FSTYPE[d:]: Returns the file system type for the specified drive or sharename. **@FSTYPE** returns **NTFS** for a drive that uses the Windows NTFS file system. It returns **FAT32** for FAT32 drives, and **FAT** for FAT12, FAT16, and VFAT drives.

You can specify either a drive name or a UNC name.

```
echo %@fstype[c:]
echo %@fstype[%_disk:]
echo %@fstype[\Music\iTunes]
```

3.14.4.85 @FTYPE

@FTYPE[xxx]: Returns the open command string for the specified file type.

Examples:

```
echo %@ftype[PerlScriptFile]
```

See also @ASSOC 409 and FTYPE 241.

3.14.4.86 @FULL

@FULL[filename]: Returns the full path and filename of a file. *Filename* must be in quotes if it contains white space or special characters. On an LFN drive, the returned filename may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under <a href="Variable-Vari

Note: The @FULL function makes no assumption about the existence of a file or directory. The *filename* parameter can be any string and the function will attempt to turn it into a fully qualified "volume + path + name" specification, whether that full reference exists or not.

Examples:

```
echo %@full[xyz.abc]
echo "%@full[.]"
echo "%@full["\Program Files"]"
```

3.14.4.87 @FUNCTION

@FUNCTION[*name*]: Returns the definition of the specified <u>user-defined function [242]</u> **name** as a string, or a null string if the function doesn't exist. When manipulating strings returned by @FUNCTION you may need to disable certain special characters with <u>SETDOS /X [323]</u>. Otherwise, command separators, redirection characters, and other similar punctuation in the function may be interpreted as part of the current command, rather than part of a simple text string.

Example:

```
echo %@function[myfunction]
```

See the FUNCTION 242 command.

3.14.4.88 @GETDIR

@GETDIR[d:\path[,title]]: Pops up a dialog box to select a directory. d:\path specifies the initial directory; if it is not specified, @GETDIR defaults to the current directory. Returns the chosen directory as a string, or an empty string if the user selects "Cancel" or presses Esc.

d:\path must be in quotes if it contains white space or special characters. On an LFN drive, the returned path may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned path before you pass it to other commands. See the notes under Variable Functions 395 for additional details.

@GETDIR accepts an optional second parameter to set the title of the dialog box.

```
cdd %@getdir["C:\program Files"]
%@getdir[]\
```

Note: @GETDIR deals with directories. All directories are folders, but not all folders are directories. To select a symbolic folder, see @GETFOLDER 4381.

3.14.4.89 @GETFILE

@GETFILE[d:\path\filename[,filter[,title]]]: Pops up a dialog box to select a file. d:\path\filename specifies the initial directory and filename shown in the dialog, and may include wildcards. Returns the full path and name of the selected file or an empty string if the user selects "Cancel" or presses Esc. The optional second parameter specifies the file extension to use. You can specify multiple extensions by separating them with semicolons. For example, %@getfile[c:\windows,*.exe;*.btm] lets the user select from .EXE and .BTM files only.

The parameters must be in quotes if they contain white space or special characters. On an LFN drive, the returned filename may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under Variable Functions see for additional details.

@GETFILE accepts an optional third parameter to set the title of the dialog box.

@GETFILE is still maintained for backwards compatibility, but it has been replaced by the more powerful @GETFOLDER. [438]

Examples:

```
echo %@getfile[*]
echo %@getfile["%windir",*.exe;*.com]
```

3.14.4.90 @GETFOLDER

@GETFOLDER[startdir[,title]]: Returns a folder selected from a tree view of available symbolic folders. If you don't specify a start folder, @GETFOLDER starts at **My Computer** or the equivalent symbolic folder in your Windows configuration.

The optional second argument sets the text to display above the tree view.

Examples:

```
echo %@getfolder[]
echo %@getfolder["Control Panel"]
```

Note: @GETFOLDER deals with folders. All directories are folders, but not all folders are directories. To select a directory, see @GETDIR [437].

3.14.4.91 @GROUP

@GROUP[server,group,user]: Returns 1 if **user** is a member of the specified **group**. **server** specifies the DNS or NetBIOS name of the computer on which the function is to execute.

3.14.4.92 @HISTORY

@HISTORY[x[,y]]: Returns a line or word from the <u>command history</u> 1061. (This function will prove most useful in keystroke aliases). x is the line to retrieve (current line = 0), and y is the specific word (first word = 0) desired within that line. If y is omitted, @HISTORY returns the entire line.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

3.14.4.93 @IDOW

@**IDOW**[date[,format]]: Returns the 3-character abbreviation for the day of the week for the specified date, in the current locale language. See date formats 127 for information on date formats.

@IDOW accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@idow[01-01-1980]
echo %@idow[%_date]
```

See also: @DOW 417).

3.14.4.94 @IDOWF

@IDOWF[date[,format]]: Returns the full name for the day of the week for the specified date, in the current locale language. See date formats 127 for information on date formats.

@IDOWF accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@idowf[01-01-2007]
echo %@idowf[%_date]
```

See also: @DOWF 418).

3.14.4.95 @IF

@IF[condition,string1,string2]: Evaluates **condition** according to the rules described in Conditional Expressions of and if **true**, it returns **string1**, otherwise it returns **string2**. Leading and trailing white space in **string1** and **string2** is retained. Either string may be empty or contain white space only. WARNING: Both **string1** and **string2** are evaluated whether or not used. Do not use @IF if evaluating either one of the strings may fail; use the IF or IFF command instead.

Examples

1) The expression

```
%@IF[2 == 2,Correct!,Oops!]
returns Correct!
```

2) The command

```
echo Good %@if[%_hour ge 12,evening,morning]!
```

displays Good morning! in the AM hours and Good evening! in the PM hours.

3) Assuming \mathbf{A} and \mathbf{C} are files in the current directory, but \mathbf{B} is a subdirectory, the command:

3.14.4.96 @INC

@INC[string] returns

- 1 if **string** is empty
- otherwise the same value as @EVAL 420 [string + 1]

If **string** is the name of an environment variable, its value is used whether or not it is preceded by a percent mark % without modifying the value of the variable. To actually increment the value of the variable **var** use

```
set var=%@inc[%var]
```

3.14.4.97 @INDEX

@INDEX[string1,string2[,n]]: Returns the offset of **string2** within **string1**, or **-1** if **string2** is not found or if **string1** is empty. The first or leftmost position in **string1** is numbered **0**. The optional third parameter **n** has three different interpretations:

If n > 0, it specifies that the nth match from left to right is desired.

If n < 0 or it is prefixed with the minus sign -, it specifies that the -nth match from right to left is desired.

If *n*=0, the total number of matches is desired.

When *n* is omitted, the value returned is the offset of the *first* (leftmost) match.

Tips

- searching for a comma :
 - 1. quote **string1** (to prevent the expected comma making it appear as more than one parameter)

- 2. use escape character or its pseudovariable form %= in string2 to escape the comma echo %@index["4NT, Take Command, 4DOS", %=,,2]
- searching for a **double quote**:
 - 1. use escape character 51 or its pseudovariable form %= in string2 to escape the double quote
 - 2. use the special form %=q to represent it in string2: echo %@index[contains a "quoted" word,%=q,0]

See Codes for Escapable Characters 124 for details.

Examples:

In all examples below

- string1: This is a fine help file
- string2: h

n	result	purpose
omitted	1	locate leftmost
0	2	count occurrences
1	1	locate leftmost
2	15	locate second leftmost
3	-1	locate third leftmost
-1	15	locate rightmost
-2	1	locate second rightmost
-3	-1	locate third rightmost

3.14.4.98 @INIREAD

@INIREAD[file,section,entry]: Returns the value of the first matching **entry** from the specified **file**, or an empty string if either **file** or the entry in **file** does not exist. If **file** contains more than one section named **section**, only the first one is searched for **entry**.

File, section, and entry must be in quotes if they contain white space or special characters.

File selection

Both the name and extension of *file* must be specified. This function does not apply a default extension. If *file* does not explicitly include a path, @INIREAD uses *%Windir*, the Windows installation directory. To use the current directory, you must explicitly specify it, e.g., using .\ as the path.

Example

```
%@iniread[c:\tcmd\tcmd32.ini,TakeCommand,history]
```

returns the size of the command history if it is specified in TCMD32.INI.

3.14.4.99 @INIWRITE

@INIWRITE[file, section, entry, string]: Creates, updates, or deletes an entry in the specified file. If file does not exist, it will be created. @INIWRITE returns 0 for success or -1 for failure.

File, section, and *entry* must be in quotes if they contain white space or special characters.

File selection

Both the name and extension of *file* must be specified. This function does not apply a default extension. If *file* does not explicitly include a path, @INIWRITE uses *%Windir*, the Windows installation directory. To use the current directory, you must explicitly specify it, e.g., using • \ as the path.

Action

If **file** does not exist, it will be created. If **string** is empty, **file** will be empty, otherwise a section line and a directive line will be created.

The remaining descriptions relate to the case when *file* exists.

If more than one match for **section** exists in **file**, only the first one is searched for **entry**. If more than one match exists for **section** and **entry**, only the first match is one is affected. Searching starts at the beginning of the file, and stops on the first match.

If **string** is empty, the matching **section** and **entry**, if any, is deleted. If **string** is not empty, and there is a matching **section** and **entry**, it is modified. If **string** is not empty, and there is no matching **section** and **entry**, it is created.

Examples

```
echo %@iniwrite[c:\tcmd\tcmd32.ini,TakeCommand,history,8192]
```

will set the size of the command history to 8,192 bytes.

```
echo %@iniwrite[c:\tcmd\tcmd32.ini,TakeCommand,history,]
```

will remove the *history* entry from the file.

3.14.4.10(@INODE

@INODE[filename]: Returns the inode (in hex) for the specified file.

When files are hard-linked to one another (see MKLNK 273), they share the same inode.

3.14.4.10⁻@INSERT

@INSERT[offset,string1,string2]: Inserts **string1** into **string2** starting at **offset**. The first offset in **string2** is **0**. If **offset** is greater than the length of **string2**, **string1** will be appended to the end of **string2**. If **offset** is negative, its value is used to count backward form the end of **string2** (but not past its beginning). Setting **offset** to **-0** is the same as setting it to **0**, i.e., **string1** will precede **string2** in the result. To include a comma in **string1**, precede it with your <u>escape character</u> of the string of the string

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). To use hexadecimal form for a negative **offset**, remember to use 32-bit 2's complement arithmetic.

function	value
%@insert[1,arm,wing]	warming
%@insert[8,very ,this is useful]	this is very useful

<pre>%@insert[255,%=, very!,this is useful]</pre>	this is useful, very!
<pre>%@insert[-9,very ,this is useful]</pre>	this very is useful
<pre>%@insert[0,abcde,xyz]</pre>	abcdexyz

3.14.4.10:@INSTR

@INSTR[start,[length],string]: Returns a substring, beginning at offset start and continuing for length characters. If length is positive or it is omitted, the offset is measured from the beginning (i.e., left end) of the string. If length is omitted, all of the string beginning at offset start is returned. If length is negative, the offset is measured leftward from the right end of the string, and its length is specified by the value of length without the minus sign. @SUBSTR 463 is an older version of the same function.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). To use hexadecimal form for a negative *length*, remember to use 32-bit 2's complement arithmetic.

Examples:

function	value
=%@instr[8,3,this is useful]=	=use=
=%@instr[8,,this is useful]=	=useful=
=%@instr[8,-4,this is useful]=	=is u=
=%@instr[8,,commas, they don't matter]=	=they don't matter=

3.14.4.10:@INT

@INT[n]: Returns the integer part of the number n. @INT will perform an implicit $\underline{\text{@EVAL}}^{420}$ on its argument, so you can use an arithmetic expression for n.

Examples:

```
echo %@int[1234]
echo %@int[1.234]
echo %@int[12.34]
```

3.14.4.10⁴@IPADDRESS

@IPADDRESS[hostname]: Returns the numeric IP address for the specified hostname. If hostname is omitted, returns the current local IP address. The result is displayed in the standard format nnn.nnn.nnn.nnn. An invalid or unknown hostname will return an error (see @ERRTEXT 420 to decipher the error number if necessary).

See also @IPNAME 444.

```
echo %@ipaddress[jpsoft.com]
echo %@ipaddress[]
```

3.14.4.10!@IPNAME

@IPNAME[numeric_IP]: Returns the host name for the specified numeric_IP address. An IP address 0 returns the name of the current local host (usually the computer name). The IP address can be expressed in the common format nnn.nnn.nnn or as a packed decimal. An invalid or unknown IP address returns an error (see @ERRTEXT 420) to decipher the error number if necessary).

See also: @IPADDRESS 4431.

Example:

```
echo %@ipname[192.220.109.228]
echo %@ipname[3235671524]
echo %@ipaddress[0]
```

3.14.4.10(@ISALNUM

@**ISALNUM**[*string*]: Returns **1** if *string* is entirely composed of alphabetic (a-z, A-Z) and/or numeric (0 - 9) characters; **0** otherwise.

See also: @ISALPHA [444], @ISASCII [444], @ISCNTRL [445], @ISDIGIT [445], @ISPRINT [445], @ISP

Example:

```
echo %@isalnum[123abc]
echo %@isalnum[123 abc]
echo %@isalnum[123.456]
```

3.14.4.10;@ISALPHA

@ISALPHA[string]: Returns 1 if string is entirely composed of alphabetic (a-z, A-Z) characters; 0 otherwise.

See also: @ISALNUM 444), @ISASCII 444), @ISCNTRL 445), @ISDIGIT 445), @ISPRINT 445), @ISPRINT 445), @ISPUNCT 445), @ISSPACE 446), @ISXDIGIT 446).

Example:

```
echo %@isalpha[abc]
echo %@isalpha[ABC]
echo %@isalpha[A B C]
```

3.14.4.10(@ISASCII

@ISASCII[string]: Returns **1** if **string** is entirely composed of 7-bit ASCII characters (0x00 – 0x7F); **0** otherwise.

See also: @ISALNUM 444, @ISALPHA 444, @ISCNTRL 445, @ISDIGIT 445, @ISPRINT 445, @ISPUNCT 445, @ISSPACE 446, @ISXDIGIT 446.

Example:

```
echo %@isascii[abc]
echo %@isascii[abc 123]
echo %@isascii["abc",123]
```

3.14.4.10!@ISCNTRL

@ISCNTRL[string]: Returns 1 if string is entirely composed of ASCII control characters (0x00 – 0x1F or 0x7F); 0 otherwise.

See also: @ISALNUM 444), @ISALPHA 444), @ISASCII 444), @ISDIGIT 445), @ISPRINT 445), @ISPRINT 445), @ISPUNCT 445), @ISSPACE 446), @ISXDIGIT 446).

3.14.4.11(@ISDIGIT

@ISDIGIT[string]: Returns 1 if string is entirely composed of decimal digits (0-9); 0 otherwise.

See also: @ISALNUM 444), @ISALPHA 444), @ISASCII 444), @ISCNTRL 445), @ISPRINT 445), @ISPRINT 445), @ISPRINT 446),

Example:

```
echo %@isdigit[0]
echo %@isdigit[123.456]
echo %@isdigit[-123]
```

3.14.4.11 @ISPRINT

@ISPRINT[string]: Returns 1 if string is entirely composed of printable characters; 0 otherwise.

See also: @ISALNUM 444, @ISALPHA 444, @ISASCII 444, @ISCNTRL 445, @ISDIGIT 445, @ISPUNCT 445, @ISSPACE 446, @ISXDIGIT 446.

3.14.4.11;@ISPROC

@ISPROC[pid]: Returns 1 if the specified process ID is an active process, or 0 if it is not.

3.14.4.11;@ISPUNCT

@ISPUNCT[string]: Returns 1 if **string** is entirely composed of punctuation characters, i.e. printable characters which are not alphanumeric or space; **0** otherwise.

See also: @ISALNUM 444), @ISALPHA 444), @ISASCII 444), @ISCNTRL 445), @ISDIGIT 446), @ISPRINT 446), @ISSPACE 446), @ISXDIGIT 446).

```
echo %@ispunct[.]
echo %@ispunct[+]
echo %@ispunct[:-)]
```

3.14.4.11 @ISSPACE

@ISSPACE[string]: Returns 1 if string is entirely composed of white space characters (0x09 – 0x0D or 0x20); 0 otherwise.

See also: @ISALNUM [444], @ISALPHA [444], @ISASCII [444], @ISCNTRL [445], @ISDIGIT [445], @ISPRINT [445], @ISPUNCT [445], @ISXDIGIT [446].

3.14.4.11:@ISXDIGIT

@ISXDIGIT[string]: Returns 1 if string is entirely composed of hexadecimal digits (0–9,A-F, a-f); 0 otherwise.

See also: @ISALNUM 444, @ISALPHA 444, @ISASCII 444, @ISCNTRL 445, @ISDIGIT 445, @ISPRINT 445, @ISPUNCT 445, @ISSPACE 446.

Example:

```
echo %@isxdigit[0]
echo %@isxdigit[7F]
echo %@isxdigit[0x7F]
```

3.14.4.11(@JUNCTION

@JUNCTION[dir]: Returns the directory referenced by the specified junction.

3.14.4.11;@LABEL

@LABEL[d:]: Returns the volume label of the specified disk drive. The drive letter must be followed by a colon.

Examples:

```
echo %@label[C:]
echo %@label[%_disk:]
```

See also: VOL 3601.

3.14.4.11\@LCS

@LCS[string1,string2]: Returns a pointer to the Longest Common Sequence in string1 and string2.

3.14.4.11!@LEFT

@LEFT[*n*, *string*] : If *n* is positive, it returns the leftmost *n* characters of *string*. If *n* is greater than the length of *string*, it returns the entire *string*. If *n* is negative, it returns *string* after dropping its rightmost *n* characters, unless *-n* is greater than the length of *string*, in which case it returns an empty string.

```
%@LEFT[2,jpsoft] jp
%@LEFT[22,jpsoft] jpso
%@LEFT[-2,jpsoft] jpso
%@LEFT[-22,jpsoft] empty string
```

3.14.4.12(@LEN

@LEN[string]: Returns the length of string.

Examples:

```
echo %@len[this is a test]
echo %@len[%comspec]
```

3.14.4.12⁻@LFN

@LFN[*filename*]: Returns the long filename for a short ("8.3") *filename*. The *filename* may contain any valid filename element including drive letter, path, filename and extension; the entire name including all intermediate paths will be returned in long name format. If *filename* does not refer to an actual file, the results are unpredictable.

On an LFN drive, the returned name may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under Variable Functions [395] for additional details.

Examples:

```
echo %@lfn[xyz.abc]
echo "%@lfn[c:\progra~1]"
```

3.14.4.12;@LINE

@LINE[*filename,n*]: Returns line *n* from the specified file. The first line in the file is numbered 0. ****EOF**** is returned for all line numbers beyond the end of the file.

The *filename* must be in quotes if it contains white space or special characters.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

@LINE works with files having lines of no more than 8,191 characters. Longer lines will not be counted accurately.

The @LINE function must read each line of the file to find the line you request, and will therefore cause significant delays if used in a long loop or on a large file. For a more effective method of processing each line of a file in sequence use the DO 210 command, or @FILEOPEN 428 and a sequence of @FILEREADS. 428

You can retrieve input from standard input if you specify **CON** as the filename. If you are redirecting sinput to @LINE using this feature, you must use command grouping 121 or the redirection will not work

properly (you can pipe of to @LINE without a command group; this restriction applies only to input redirection). For example:

```
(echo %@line[con,0]) < myfile.dat</pre>
```

@LINE can retrieve data from file streams on NTFS drives if the stream name is specified. See NTFS File Streams 496 for additional details on file streams.

Beware of characters with special meaning to *TCC*, such as redirection and piping symbols, within the file. Use SETDOS [323] /X with appropriate codes as needed.

3.14.4.12;@LINES

@LINES[filename]: Returns the line number of the last line in the file, or "-1" if the file is empty. The first line in the file is numbered 0, so (for example) @LINES will return 0 for a file containing one line. To get the actual number of lines, use %@INC[%@LINES[filename]].

The *filename* must be in quotes if it contains white space or special characters.

@LINES works with files having lines of no more than 8,191 characters; longer lines will not be counted accurately. @LINES must read each line of the file in order to count it, and will therefore cause significant delays if used on a large file.

@LINES can count lines in file streams on NTFS drives if the stream name is specified. See NTFS
File Streams 496 for additional details on file streams.

3.14.4.12⁴@LINKS

@LINKS[filename]: Returns the number of hard links for the specified file (NTFS only).

See also MKLNK 273.

3.14.4.12:@LOWER

@LOWER[string]: Returns the **string** converted to lower case.

Examples:

```
echo %@lower[ThiS iSS aTeSt]
echo %@lower[%path]
```

3.14.4.12(@LTRIM

@LTRIM[string1,string2]: - Returns **string2** with all the leading characters in **string1** removed. **String1** must be enclosed in double quotes if it contains any spaces, tabs, or commas.

Examples:

```
echo "%@ltrim[JP,JP Software]"
" Software"
```

3.14.4.12^{*}@MAKEAGE

@MAKEAGE[date[,time[,format]]]: Converts **date** and **time** (if included) to an age 520, a single value in the same format as @FILEAGE 427.

@MAKEAGE accepts an optional third parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

@MAKEAGE can be used to compare the time stamp of a file with a specific date and time, for example:

```
if %@fileage[myfile] lt %@makeage[1/1/85] echo OLD!
```

@AGEDATE 408 is the inverse of this function.

Examples:

```
echo %@makeage[%_date]
echo %@makeage[%_date,%_time]
```

See also: Time Stamps 4951, @FILEAGE 4271, @AGEDATE 4081.

3.14.4.12(@MAKEDATE

@MAKEDATE[*n*[,*d*]]: Returns a date, formatted according to the current country settings, or as explicitly specified by *d* (see <u>Date Display Formats [406]</u>). *n* is interpreted as the number of days since 1980-01-01, and must be in the range **0** to **43829** (corresponding to the date **2099-12-31**). This is function is the inverse of @DATE [414]. The optional second parameter specifies the date format:

- **0** system default
- 1 USA (mm/dd/yy)
- **2** European (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO 9601 (yyyy-mm-dd)

Examples:

```
echo %@makedate[7924]
echo %@makedate[7924,4]
```

3.14.4.12!@MAKETIME

@MAKETIME[n]: Returns a time (formatted using the Time Separator specified in Regional Settings). n is interpreted as the number of seconds since midnight, and must not exceed 86399. This function is the inverse of $\underbrace{\text{@TIME}}_{463}$.

Examples:

```
echo %@maketime[45240]
echo %@maketime[79244]
```

3.14.4.13(@MAX

@MAX[*a,b,c,...*]: Returns the largest in the list of parameters. All parameters must be integers in the range **-2147483647** to **2147483647** and must be separated either by whitespace or by commas.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Example:

```
echo %@max[1,5,2,0,-1]
```

3.14.4.13⁻@MD5

String mode: **@MD5**[s,string] File mode: **@MD5**[f,]filename]

Returns the 32 hexadecimal digit MD5 hash of the character in *string* or of the contents of the file *filename*. The first parameter must be *s* for a string, and any leading or trailing whitespace characters in *string* are included.

Filename may be specified with or without an optional **f**. @MD5 returns **-1** if the file does not exist, or it cannot be read.

Since *Take Command* handles all internal strings as Unicode, @MD5 will return different results for a string and the identical string in an ASCII file.

See also: @SHA256 460, @SHA384 460, @SHA512 460, and @CRC32 413.

3.14.4.13:@MIN

@MIN[*a*,*b*,*c*,...**]** : Returns the smallest in the list of parameters. All parameters must be integers in the range **-2147483647** to **2147483647** and must be separated either by whitespace or by commas.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Example:

```
echo %@min[1,5,2,0,-1]
-1
```

3.14.4.13:@MONTH

@MONTH[*date*[,*format*]]: Returns the month number for the specified date (1-12). See <u>date formats</u> for information on acceptable date formats.

@MONTH accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

Examples:

```
echo %@month[01-01-1980]
echo %@month[%_date]
```

3.14.4.134@NAME

@NAME[filename]: Returns the base name of a file, without the path or extension.

The *filename* must be in quotes if it contains white space or special characters. On an LFN drive, the returned filename may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under Variable Functions set in additional details.

Note: The @NAME function makes no assumption about the existence of a file or directory. Its *filename* parameter can be any string and the function will attempt to extract from it a base name.

Examples:

```
echo %@name[xyz.abc]
echo "%@name[%_comspec]"
```

3.14.4.13!@NUMERIC

@NUMERIC[[+|-]string]: Returns 1 if string is numeric, and 0 otherwise.

To be numeric, the following must be true:

- 1. The first character may be a + or sign,
- 2. The next character must be a decimal digit (0 to 9) or the decimal separator [51].
- 3. The remainder of *string* must be composed entirely of decimal digits (0 to 9), the <u>thousands</u> <u>separator</u> [51], and no more than a single decimal separator, with no thousands separators following the decimal separator.

Examples:

function	value
%@numeric[12345]	1
%@numeric[-12345]	1
%@numeric[.12345]	1
%@numeric[\$12.34]	0
%@numeric[5.00.125]	0
%@numeric[+5.00.125,5]	0
%@numeric[.00.125]	0
%@numeric[-5,.00.125]	0

3.14.4.13(@OPTION

@OPTION[directive]: Returns the current value of the requested configuration option. All directives which can be altered dynamically are supported. If **directive** is not supported, an error is returned.

For configuration directives, the current value returned may not match that stored in the .INI file.

For color directives, the current value is returned as a single number (0-255) combining foreground and background specifications. See Colors, Color Names & Codes 518 for details.

Examples:

```
echo %@option[passiveftp]
echo %@option[stdcolors]
```

3.14.4.13^T@PATH

@PATH[filename]: Returns the path portion of *filename*, if present, including the drive letter and a trailing backslash but not including the base name or extension. If the *filename* parameter doesn't contain path information, you may expand it first with the @FULL [43] function.

The *filename* must be in quotes if it contains white space or special characters. On an LFN or NTFS drive, the returned filename may contain white space or other special characters. To avoid problems which could be caused by these characters, quote the returned name before you pass it to other commands. See the notes under Variable Functions set for additional details.

Note: The @PATH function makes no assumption about the existence of a file or directory. Its *filename* parameter can be any string, and the function will attempt to remove from it a "base name".

Examples:

3.14.4.13(@OWNER

@OWNER[filename]: Returns the owner of the specified file (if any).

3.14.4.13!@PERL

@PERL[expression]: Executes the specified Perl expression (requires Active State Perl 5.8).

3.14.4.14(@PING

@PING[host[,timeout[,packetsize]]]: Returns the response time in milliseconds for the specified host. Host is the IP address or name, timeout is the maximum number of seconds to wait, and packetsize is the size of the data packet sent to the host in the ping request. The timeout defaults to 5 seconds, and packetsize defaults to 64 bytes. The minimum packet size is 8 bytes and the maximum is 2048 bytes.

A negative value indicates an error. If the request times out, @PING returns -1. An unreachable host returns -2. An invalid address returns -3.

Examples:

```
echo %@ping[microsoft.com]
echo %@ping[microsoft.com,10]
echo %@ping[microsoft.com,,16]
echo %@ping[192.168.1.100,2,512]
```

3.14.4.14⁻@QUOTE

@QUOTE[string]: Returns a double quoted argument if it contains any whitespace characters.

3.14.4.14:@RANDOM

@RANDOM[*min, max*]: Returns a pseudo random integer value between *min* and *max*, inclusive. The random number generator is initialized from the system clock the first time it is used after *TCC* starts and will therefore produce a different sequence of numbers each time you use it.

Examples:

```
echo %@random[0,1]
echo %@random[-10,10]
```

3.14.4.14;@READSCR

@READSCR[row,col,length]: Returns the text displayed in the *TCC* window at the specified location. The upper left corner of the window is location 0,0. The *row* and *column* can be specified as an offset from the current cursor location by preceding either value with a [+] or [-]. For example:

```
%@readscr[-2,+2,10]
```

returns 10 characters from the screen, starting 2 rows above and 2 columns to the right of the current cursor position.

3.14.4.14@READY

@READY[d:]: Returns 1 if the specified drive is ready; otherwise returns 0. The drive letter must be followed by a colon.

@READY does not support UNC names.

Examples:

```
echo %@ready[E:]
echo %@ready[%_boot:]
```

3.14.4.14!@REGCREATE

@REGCREATE[*HKEY...\subkey*]: Create a new registry subkey. The parameter starts with the root key, which can be abbreviated:

Full root key	Short
HKEY_CLASSES_ROOT	HKCR
HKEY_CURRENT_USER	HKCU
HKEY_LOCAL_MACHINE	HKLM
HKEY_USERS	HKU
HKEY_CURRENT_CONFIG	HKCC

The remainder of the parameter (after the backslash) specifies the new subkey. The entire name must be quoted if it contains any white space or special characters, for example:

```
@REGCREATE["HKLM\Software\My Company\My Product\User"]
```

REGCREATE will create any intermediate keys necessary. For example,
@REGCREATE[HKCU\key1\key2\key3] will create all three keys (if they do not already exist).

REGCREATE returns 0 if the subkey was created or the Windows error number if an error occurred.

See also: <u>@REGQUERY</u> [455] (read a value), <u>@REGSET</u> [455] (write a value), and <u>@REGSETENV</u> [455] (write and broadcast a value).

3.14.4.14(@REGDELKEY

@REGDELKEY[HKEY...\key]: Deletes the specified key and all of its subkeys. Returns 1 if the key was deleted, 0 otherwise. The expression must be enclosed in double quotes if it contains any separator characters (space, comma, or tab).

Note: use EXTREME caution with this function. It has the potential for causing irreparable damage to your registry and can even prevent Windows from booting!

See @REGCREATE 454 for information on the format of the key name.

3.14.4.14 @REGEX

@REGEX[expression,string]: Returns the number of matching groups in the string. If no groups are specified, it returns 1 if the *expression* was found and 0 if it was not. The expression must be enclosed in double quotes if it contains any separator characters (space, comma, or tab). See Regular Expression Syntax 496 for supported expressions.

3.14.4.14(@REGEXINDEX

@REGEXINDEX[expression,string]: Returns the offset of the first match. The expression must be enclosed in double quotes if it contains any separator characters (space, comma, or tab). See Regular Expression Syntax [496] for supported expressions. (This function is basically a wildcard-enabled @INDEX.)

3.14.4.14!@REGEXIST

@REGEXIST[HKEY...\key]: Returns 1 if the specified key exists, 0 otherwise

The expression must be enclosed in double quotes if it contains any separator characters (space, comma, or tab).

See @REGCREATE [454] for information on the format of the key name.

3.14.4.15(@REGEXSUB

@REGEXSUB[n,expression,string] - returns the "nth" matching group in the string. (If you don't specify a group in *expression*, @REGEXSUB will return an empty string.) The expression must be enclosed in double quotes if it contains any separator characters (space, comma, or tab). See Regular Expression Syntax [496] for supported expressions.

3.14.4.15 @REGQUERY

@REGQUERY[*HKEY...\subkey\value*]: Read a value from the registry. REGQUERY supports keys of type REG_DWORD, REG_QWORD, REG_EXPAND_SZ, REG_SZ, REG_DWORD_LITTLE_ENDIAN, and REG_QWORD_LITTLE_ENDIAN. If the key is of type REG_EXPAND_SZ, the value is returned without further expansion. If the value name does not exist, the function returns **-1**. If the value name is not supplied, REGQUERY returns the unnamed value for the specified key (the first value with a NULL name). To retrieve an unnamed value, add a trailing \ to the name.

Note: Remember to use quotes around any entry containing spaces or commas!

See @REGCREATE 454 (create a subkey) for information on the format of the key name. See also: @REGSET 455 (write a value) and @REGSETENV 455 (write and broadcast a value).

3.14.4.15:@REGSET

@REGSET[HKEY...\subkey\value,type,data]: Write a value to the registry. REGSET supports keys of type REG_DWORD, REG_SZ, REG_EXPAND_SZ, and REG_DWORD_LITTLE_ENDIAN. *Type* is the value type (REG_DWORD, REG_EXPAND_SZ, or REG_SZ). *Data* is the data to set. If this parameter is not supplied, @REGSET will remove the value. REGSET returns 0 if the value was written or the Windows error number if an error occurred.

Note: Remember to use quotes around any entry containing spaces or commas!

See <u>@REGCREATE 454</u> for information on the format of the key name. See also: <u>@REGQUERY 4551</u> (read a value) and <u>@REGSETENV 4551</u> (write and broadcast a value).

3.14.4.15;@REGSETENV

@REGSETENV[HKEY...\subkey\value,type,data]: The same as @REGSET [455], but a broadcast message is sent to all applications when the change is made, so that any application monitoring such messages can respond to the change immediately if it is designed to do so. @REGSETENV returns 0 if the value was written or the Windows error number if an error occurred.

Note: Remember to use quotes around any entry containing spaces or commas!

See <u>@REGCREATE 454</u> for information on the format of the key name. See also: <u>@REGQUERY 4551</u> (read a value) and <u>@REGSET 4551</u> (write a value).

3.14.4.154@REGTYPE

@REGTYPE[HKEY...\key]: Returns the registry variable type. The possible values are:

0 - REG NONE (No value type)

- 1 REG_SZ (Unicode null terminated string)
- 2 REG_EXPAND_SZ (Unicode null terminated string with environment variable references)
- 3 REG_BINARY (Free form binary)
- 4 REG DWORD (32-bit number)
- 5 REG_DWORD_BIG_ENDIAN (32-bit number)
- 6 REG LINK (Symbolic Link)
- 7 REG_MULTI_SZ (Multiple Unicode strings)
- 8 REG_RESOURCE_LIST (Resource list in the resource map)
- 9 REG_FULL_RESOURCE_DESCRIPTOR (Resource list in the hardware description)
- 10 REG RESOURCE REQUIREMENTS LIST
- 11 REG_QWORD (64-bit number)

3.14.4.15!@REMOTE

@REMOTE[*d*:]: Returns **1** if the specified drive is a remote (network) drive; otherwise returns **0**. The drive letter must be followed by a colon.

Examples:

```
echo %@remote[e:]
echo %@remote[% disk]
```

3.14.4.15(@REMOVABLE

@REMOVABLE[d:]: Returns **1** if the specified drive is removable (e.g. floppy disk, removable hard disk, USB storage device, etc.), **0** otherwise. The drive letter must be followed by a colon.

Examples:

```
echo %@removable[e:]
echo %@removable[%_disk]
```

3.14.4.15 @REPEAT

@REPEAT[char,count]: Returns the character **char** repeated **count** times (**count** may not exceed 8,191).

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Examples:

function	value	
%@repeat[%@char[95],10]		
7%@repeat[,7]spaces	7	spaces
%@repeat[x,10]	xxxxxxxxx	

3.14.4.15(@REPLACE

@REPLACE[string1, string2, text]: Replaces all occurrences of **string1** in the **text** string with **string2**. For example, **@replace[w,ch,warming]** returns the string "charming".

The search is case sensitive.

Examples:

```
echo %@replace[\,/,"ftp:\\server\etc"]
echo %@replace[%=,,,A better, command processor]
```

3.14.4.15!@REVERSE

@REVERSE[string]: Reverses the order of the characters in string.

3.14.4.16(@REXX

@REXX[[=]expr]: Calls the REXX interpreter to execute the expression. Returns the numeric code or string result from REXX. Console output from the REXX interpreter is suppressed while executing the expression. Note that **TCC** expands variables and functions before passing **expr** to REXX.

Examples:

```
echo %@rexx[ = 3 * 4 ]
set myprog=d:\path\xyz.exe
echo %@rexx[ address(%@name[%myprog]); return address() ]
```

Note: This function requires that a recognized REXX interpreter be installed and properly configured. See REXX Support [142] for more information on the REXX language.

3.14.4.16⁻@RIGHT

@RIGHT[n, string]: If n is positive, it returns the rightmost n characters of **string**. If n is greater than the length of **string**, it returns the entire **string**. If n is negative, it returns **string** after dropping its leftmost n characters, unless n is greater than the length of **string**, in which case it returns an empty string.

Examples:

function	value
%@RIGHT[2,jpsoft]	ft
%@RIGHT[22,jpsoft]	jpsoft
%@RIGHT[-2,jpsoft]	soft
%@RIGHT[-22,jpsoft]	empty string

3.14.4.16;@RTRIM

@RTRIM[string1,string2]: - Returns string2 with any characters in string1 removed from the right side of string1. String1 must be enclosed in double quotes if it contains any spaces, tabs, or commas.

Examples:

```
echo "%@rtrim[98XP,Windows XP]"
"Windows "
```

3.14.4.16;@RUBY

@RUBY[expression]: Returns the string result of the Ruby expression. Note that the Ruby environment is persistent within a **TCC** tab window, so you can do things like:

```
%@ruby[b = 42]
%@ruby[p b]
```

which will print "42". The value returned by @RUBY is the value returned by the RUBY API rb eval string.

You can query the type of the value returned by the last @RUBY call with the RUBYTYPE 39th internal variable, and the value returned by the last @RUBY call with the RUBYVALUE 39th internal variable.

3.14.4.164@SCRIPT

@SCRIPT[engine, expression]: Returns the integer result of expression in the specified active scripting engine. For example:

%@script[PerlScript,print "This message is from Perl!"]

See also the SCRIPT 311 command.

3.14.4.16!@SEARCH

@SEARCH[program[,path[,n]]]: Searches for **program** using the specified **path**, or, if not specified, the **PATH** environment variable, appending an extension if one isn't specified. (See <u>Executable Files and File Searches searches searches searches searches searches searches search proceeds, and the search of the **WINDOWS** and **WINDOWS\SYSTEM** directories.) Returns the fully expanded name of **program**, including drive, path, base name, and extension, or an empty string if a match is not found. If <u>wildcards</u> are used in the **program**, @SEARCH will search for the first program file that matches the wildcard specification, and returns the drive and path for that file plus the wildcard filename (e.g., E:\UTIL*.COM).</u>

Program and each directory specification in **path** must be in quotes if they contain white space or special characters.

@SEARCH accepts an optional third parameter specifying whether to search the current directory. If \mathbf{n} is 0, @SEARCH will not look for the file in the current directory. If \mathbf{n} is 1 (the default), @SEARCH will look in the current directory before searching the path.

Examples:

```
echo %@search[notepad]
echo %@search[msv*.dll,"d:\my dir\"]
```

3.14.4.16(@SELECT

@SELECT[filename,top,left,bottom,right,title[,1]]: Pops up a selection window with the lines from the specified file, allowing you to display menus or other selection lists from within a batch file. You can move through the selection window with standard popup window navigation keystrokes, including character matching (see Popup Windows for details; to change the navigation keys see Key Mapping directives Popup Windows <a href="Popup Win

Filename must be in quotes if it contains white space or special characters. The file size is limited only by available memory. To select from lines passed through input redirection or a pipe, use **CON**: as **filename**. To select from lines in the Windows clipboard, use **CLIP**: as **filename**.

If you use the optional 7th parameter 1 (immediately after the window title), the list will be sorted alphabetically.

Return value:

- the text of the line the scrollbar is on if you press Enter
- an empty string if you press Esc.

Examples:

```
call @select["d:\path\my menu.txt",5,10,15,40,Select an option] help <math>@word["=",0,\@select[d:\path\tcmd.ini,0,0,10,40,Select a directive]]
```

3.14.4.16 @SERIAL

@SERIAL[*d:*]: Returns the serial number of the specified disk drive (in hex, i.e.: ABCD:0123). The drive letter must be followed by a colon.

Examples:

```
echo %@serial[C:]
echo %@serial[%_disk:]
```

See also: @LABEL 446.

3.14.4.16 @SERVER

@SERVER[*machinename,info*]: Returns information about the specified server *machinename*, where *info* is the type of information you want. The types are:

Name - return the server name

Comment - return the server comment

Version - the OS version (major version + minor version).

Users - the number of users who can attempt to log on the server.

Disconnect - the auto-disconnect time, in minutes.

Hidden - returns 1 if the server is hidden, 0 if it is visible

UserPath - the path to user directories

Type - return the type of the server. This is a combination of the following hex flags (you can use the .AND. operator in IF / IFF to test individual flags):

1	A LAN Manager workstation
2	A LAN Manager server
4	Any server running with Microsoft SQL Server
8	Primary domain controller
0x10	Backup domain controller
0x20	Server running the Timesource service
0x40	Apple File Protocol server
0x80	Novell server

0x100	LAN Manager 2.x domain member
0x200	Server sharing print queue
0x400	Server running dial-in service
0x800	Unix/Linux server
0x1000	Windows Server 2003, Windows XP, Windows 2000, or Windows NT
0x2000	Server running Windows for Workgroups
0x4000	Microsoft File and Print for NetWare
0x8000	Windows server that is not a domain controller
0x10000	Server that can run the browser service
0x20000	Server running a browser service as backup
0x40000	Server running the master browser service
0x80000	Server running the domain master browser
0x40000	Windows 95/98/Me
0x1000000	Server clusters available in the domain
0x2000000	Terminal Server
0x4000000	Cluster virtual servers available in the domain
0x4000000	Servers maintained by the browser
0x8000000	0 Primary domain

3.14.4.16!@SFN

@SFN[*filename*]: Returns the fully expanded short ("8.3") filename for a long *filename*. The *filename* may contain any valid filename element including drive letter, path, filename and extension. The entire name including all intermediate paths will be returned in short name format. If *filename* does not refer to an actual file, the results are unpredictable.

Examples:

```
echo %@sfn["c:\program files\xyz.abc"]
echo %@sfn[%_comspec]
```

3.14.4.17(@SHA1

@SHA1[filename]: Returns the SHA1 checksum of the specified file.

See also @SHA256 4601, @SHA384 4601, @SHA512 4601, @MD5 4501, and @CRC32 4131.

3.14.4.17 @SHA256

@SHA256[filename]: Returns the SHA2-256 checksum of the specified file.

See also @SHA384 460, @SHA512 460, @MD5 450, and @CRC32 413.

3.14.4.17;@SHA384

@SHA384[filename]: Returns the SHA2-384 checksum of the specified file.

See also @SHA256 460, @SHA512 460, @MD5 450, and @CRC32 413.

3.14.4.17;@SHA512

@SHA512[filename]: Returns the SHA2-512 checksum of the specified file.

See also @SHA256 460, @SHA384 460, @MD5 450, and @CRC32 413.

3.14.4.17₄@SHFOLDER

@SHFOLDER[n]: Returns the full pathname for the specified Windows folder (which vary in different versions of Windows and if the user has altered the defaults).

n is a number from 0 to 59 that returns the following values:

- 0 Desktop
- 2 Start Menu\Programs
- 5 My Documents
- 6 <user name>\Favorites
- 7 Start Menu\Programs\Startup
- 8 <user name>\Recent
- 9 <user name>\SendTo
- 11 <user name>\Start Menu
- 13 "My Music" folder
- 14 "My Videos" folder
- 16 <user name>\Desktop
- 19 <user name>\nethood
- 20 windows\fonts
- 21 templates
- 22 All Users\Start Menu
- 23 All Users\Start Menu\Programs
- 24 All Users\Startup
- 25 All Users\Desktop
- 26 <user name>\Application Data
- 27 <user name>\PrintHood
- 28 <user name>\Local Settings\Application Data (non roaming)
- 29 non localized startup
- 30 non localized common startup
- 31 common favorites
- 32 Internet cache
- 33 cookies
- 34 history
- 35 All Users\Application Data
- 36 Windows directory
- 37 Windows system directory
- 38 Program Files
- 39 Program Files\My Pictures
- 40 USĔRPROFILE
- 41 X86 system directory on RISC
- 42 x86 c:\Program Files on RISC
- 43 c:\Program Files\Common
- 44 x86 Program Files\Common on RISC
- 45 All Users\Templates
- 46 All Users\Documents
- 47 All Users\Start Menu\Programs\Administrative Tools
- 48 <user name>\Start Menu\Programs\Administrative Tools
- 53 All Users\My Music
- 54 All Users\My Pictures
- 55 All Users\My Video
- 56 Resource Directory
- 59 USERPROFILE\Local Settings\Application Data\Microsoft\CD Burning

3.14.4.17:@SIMILAR

@SIMILAR[string1,string2]: Returns a value (0 - 100) reflecting the similarity between the two strings. **0** means the two strings have nothing in common; **100** means the strings are identical. Using the longer string as the first parameter usually results in lower similarity values and using the shorter results in higher values.

3.14.4.17(@SNAPSHOT

@SNAPSHOT[*DESKTOP* | *window*[,*n*]]: Save the desktop or a specific window to the clipboard as a BMP. The window argument can be either **DESKTOP** or a window title (which can include wildcards). The optional second argument specifies whether you want only the client area (0) or the entire window (1) to be saved. Returns **0** if successful.

3.14.4.17^{*}@STRIP

@STRIP[chars,string]: Removes the characters in **chars** from the **string** and returns the result. For example:

```
%@STRIP[AaEe,All Good Men]
```

returns "11 Good Mn".

The test is case sensitive.

To include a comma in the *chars* string, enclose the entire first parameter in quotes. @STRIP will remove the quotes before processing the *string*.

3.14.4.17(@SUMMARY

@SUMMARY[*file,property*[,*value*]]: Read or set NTFS SummaryInformation data for the specified file. If it is a compound file, @SUMMARY will retrieve the data from the compound file object; otherwise @SUMMARY will retrieve the data from the SummaryInformation stream attached to the file. The valid SummaryInformation fields are:

Title

Subject

Author

Keywords

Comments

Template

LastAuthor

Revision Number

Edit Time

Last printed

Created

Last Saved

Page Count

Word Count Char Count

AppName

Note that most files won't have any of these fields; the ones that do will usually only have some, not all.

To set SummaryInformation data, specify the value in the optional third parameter. For example, to set the **Title**:

@summary[foo.txt,Title,This is the Foo File]

3.14.4.17!@SUBSTR

@SUBSTR[string,start,length]: An older version of @INSTR 443. If the *length* is omitted, it will default to the remainder of *string*. If *string* includes commas, it must be quoted with double quotes ["] or back-quotes [`], or each comma must be preceded by an Escape character 124 The quotes count in calculating the position of the substring. @INSTR, which has *string* as its last parameter, does not have this restriction.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Examples:

```
echo %@substr[this is useful,8]
echo %@substr[this is useful,8,-2]
echo %@substr["commas, they DO matter",9]
echo %@substr[commas%=, they DO matter,9]
```

See also: @INSTR 4431.

3.14.4.18(@SUBST

@SUBST[n, string1, string2]: Substitutes **string1** starting at position **n** in **string2**.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

3.14.4.18⁻@SYMLINK

@SYMLINK[link]: Returns the target referenced by the specified symbolic link.

3.14.4.18:@TIME

@TIME[hh:mm:ss]: Returns the number of seconds since midnight for the specified time. The time must be in 24-hour format. "am" and "pm" are ignored. Any non-numeric character, except a right bracket] can be used to separate the hour, minute and second subfields.

Examples:

```
echo %@time[12:34:56]
echo %@time[% time]
```

3.14.4.18:@TIMER

@TIMER[n[,precision]]: Returns the current split time for a stopwatch started with the TIMER T1 command. The value of T2 specifies the timer to read and can be 1, 2, or 3.

@TIMER accepts an optional second argument to return the timer split as a floating-point numeric value suitable for arithmetic. The possible values are:

- s split time in seconds (2 digit decimal precision)
- m split time in minutes (4 digit decimal precision)
- h split time in hours (5 digit decimal precision)

3.14.4.18⁴@TRIM

@TRIM[string]: Returns the string with the leading and trailing white space (space and tab characters) removed.

3.14.4.18!@TRUENAME

@TRUENAME[filename]: Returns the true, fully-expanded name for a file. **@TRUENAME** will "see through" junctions, symbolic links, a SUBST or network mapping. Wildcards cannot be used in the filename.

Note: The @TRUENAME function makes no assumption about the existence of a file or directory. Its *filename* parameter can be any string and the function will attempt to turn it into a fully qualified "volume + path + name" specification, whether that full reference exists or not.

filename must be in quotes if it contains white space or special characters.

3.14.4.18(@TRUNCATE

@TRUNCATE[handle]: Truncate the file opened for write access by @FILEOPEN 4281 at the current position of the file pointer, where handle is the value returned by @FILEOPEN 4281.

See also the related handle-based functions:

@FILECLOSE 427	Close a file handle
@FILEOPEN 428	Open a file handle
@FILEREAD 429	Read next line from a file handle
@FILESEEK 431	Move a file handle pointer
@FILESEEKL 431	Move a file handle pointer to a specified line
@FILEWRITE 433	Write next line to a file handle
@FILEWRITE B 433	Write data to a file handle

3.14.4.187@UNC

@UNC[filename]: Returns the UNC name for the specified file (or an error if the file has no UNC, e.g., a local file).

3.14.4.18(@UNICODE

@UNICODE[string]: Returns the space separated list of the Unicode values of the characters in **string**. You can use the <u>Escape character</u> before a special character (i.e., a quote or greater than (>) sign) in **string**.

See also: @ASCII 409.

Examples:

function	value
%@unicode[a]	97
%@unicode[A]	65
%@unicode[%=`]	96
%@unicode[abc]	97 98 99

3.14.4.18!@UNIQUE

@UNIQUE[path[,prefix]]: Creates a zero-length file with a unique name in the specified directory, and returns its the full name and path. If no **path** is specified, the file will be created in the current directory. The file name will be FAT-compatible regardless of the type of drive on which the file is created. This function allows you to create a temporary file without overwriting an existing file.

The *path* must be in quotes if it contains white space or special characters.

If **prefix** is specified, @UNIQUE will use the first three characters as the first three characters of the unique filename.

Because the file is created, if the <u>Protect Redirected Output File</u> (47) configuration option is set, you must use the style >! redirection to avoid errors.

Rapid, repeated, consecutive invocations of @UNIQUE may occasionally return a non-unique file name (the same name twice, for example), due to a long-standing timing bug in Windows. If you experience this problem you may need to use DELAY [194], DELAY /M, or BEEP [173] (with a frequency less than 20 Hz) to provide a short delay between invocations. You may also be able to work around the problem by performing some disk I/O activity between invocations, as this can force physical creation of the file on the disk before @UNIQUE is invoked again.

3.14.4.19(@UNQUOTE

@UNQUOTE[string]: Returns the argument with all double guotes removed.

3.14.4.19⁻@UNQUOTES

@UNQUOTES[string]: Returns the argument with leading and trailing double guotes removed.

3.14.4.19:@UPPER

@UPPER[string]: Returns string converted to upper case.

3.14.4.19;@VERINFO

@VERINFO[filename[,info[,language]]]: Returns the version information for the specified file. The optional second parameter specifies the desired information and defaults to **FileVersion**. The optional third parameter specifies the language/codepage pair (in hex). If that parameter is omitted, the code page for the default user language is assumed. If the requested information field is not provided in the specified file, returns a null string.

For example, **TCMD.EXE** returns values for:

CompanyName
FileDescription
FileVersion
InternalName
LegalCopyright
LegalTrademarks
OriginalFilename

ProductName ProductVersion Build

To return CompanyName:

echo %@verinfo[tcmd.exe,companyname,040904E4]

Note: Most, but not all, executables under Windows contain a **FileVersion** field. The number, names and contents of the specific information fields and language/codepage pairs provided within a given application can potentially be anything the programmer decided to use.

3.14.4.19⁴@WATTRIB

@WATTRIB[*filename*[,-attributes[,p]]]: This function is similar to <u>@ATTRIB</u>[409], but supports file selection based on the following extended attributes available on NTFS volumes.

- **E** Encrypted
- **N** Normal
- **T** Temporary
- P Sparse file
- J Junction or symbolic links
- L Junction or symbolic links
- **C** Compressed
- O Offline
- I Not content-indexed

See also: Attributes Switches 86 and the ATTRIB 163 command.

3.14.4.19!@WILD

@WILD[string1,string2]: Compares two strings and returns 1 if they match or 0 if they don't match. This function determines whether or not string1 matches the pattern specified in string2, which may contain wildcards or extended wildcards . No wildcards are permitted in string1. The test is not case sensitive.

Examples

The examples below assume that the **PATH** variable contains:

c:\windows;c:\windows\system32;"c:\program files\util";d:\jpsoft

string1	string2	match condition	result
%path	*\UTIL*	string \util anywhere	1
%path	*C	string ending with c	0
%path	*t	string ending with t	1
%path	C *	string starting with c	1
%path	t*	string starting with t	0
%path	*C*	string containing c	1
%path	*t*	string containing t	1
%path	*b*	string containing b	0
xyz	?	one character long string	0
х	?	one character long string	1

%path	leading c , followed by any one character, followed by 0 or more characters	1
%path	leading c, followed by zero or more characters, followed by any one character	1

3.14.4.19(@WINAPI

@WINAPI[module,function[,integer | PINT=n | PLONG=n | PDWORD=n | NULL | BUFFER | "string"] : Returns the result of calling a Windows API function. The arguments are:

module - name of the DLL containing the function

function - function name (case sensitive)

integer - an integer value to pass to the function

PINT - a pointer to the integer *n*

PLONG - a pointer to the long integer *n*

PDWORD - a pointer to the DWORD *n*

NULL - a null pointer (0)

BUFFER - @WINAPI will pass an address for an internal buffer for the API to return a Unicode string value.

aBUFFER - @WINAPI will pass an address for an internal buffer for the API to return an ASCII string value.

"string" - text argument (this must be enclosed in double quotes). If the argument is preceded by an 'a' (i.e., a"Argument") then it is converted from Unicode to ASCII before calling the API. (Some Windows APIs only accept ASCII arguments.)

@WINAPI supports a maximum of 8 arguments. The return value is either a string value returned by the API (if BUFFER or aBUFFER is specified), or the integer value returned by the API. The function must be defined as WINAPI (__stdcall). If @WINAPI can't find the specified function, it will append a "W" (for the Unicode version) to the function name and try again.

See also @CAPI 410.

3.14.4.19 @WINCLASS

@WINCLASS[classname]: Returns the window title of the first window with the specified class name, or an empty string if no windows match.

3.14.4.19(@WINEXENAME

@WINEXENAME[*title*]: Returns the executable name for the first window matching *title* (which can include wildcards), or an empty string if none.

3.14.4.19!@WININFO

@WININFO[*n*]: Returns information about the current system. *n* is a number specifying what information to return:

n	Information returned
1	Processor architecture
	0 INTEL
	1 MIPS
	2 ALPHA
	3 PPC
	4 SHX
	5 ARM
	6 IA64
	7 ALPHA64
2	Processor bit mask (set of configured processors)
3	Number of processors
4	Type of processor
	586 Pentium:
5	Processor level
6	Processor revision
7	page size, bytes
8	virtual memory allocation granularity, bytes

3.14.4.20(@WINMEMORY

@WINMEMORY[*n*]: Returns the requested Windows memory information. All values except memory load are returned in bytes. *n* is a number specifying what to return:

n	Information returned
0	Memory load, %
1	Total physical RAM
2	Available physical RAM
3	Total that can be stored in the page file
4	Available page file
5	Total virtual memory for process
6	Total free virtual memory for process

3.14.4.20 @WINMETRICS

@WINMETRICS[n]: Returns the requested Windows system metric. All screen dimension metrics are returned in pixels. n is a number determining which metric to return.

Note: This function provides direct access to the **GetSystemMetrics** API. Not all available parameters are listed here and your Windows configuration may support additional parameters. See your Windows technical documentation for details.

n	Information returned
0	Width of screen
1	Height of screen
2	Width of arrow bitmap on horizontal scroll bar
3	Height of arrow bitmap on horizontal scroll bar
4	Height of title bar
5	Width of window border
6	Height of window border

7	Width of dialog box border		
8	Height of dialog box border		
9	Height of thumb box on vertical scroll bar		
10	Width of thumb box on horizontal scroll bar		
11	Width of icon		
12	Height of icon		
13	Width of cursor		
14	Height of cursor		
15	Height of cursor Height of single line menu bar		
16	Width of client area for full-screen window		
17	Height of client area for full-screen window		
18	Height of Kanji window		
19	Mouse present flag		
19	0 no		
	1 yes		
20	Height of arrow bitmap on vertical scroll bar		
21	Width of arrow bitmap on vertical scroll bar		
22	Debug version of Windows		
	0 no		
	1 yes		
23	Left and right mouse buttons swapped		
-0	0 no		
	1 yes		
28	Minimum width of a window		
29	Minimum height of a window		
30	Width of bitmaps in title bar		
31	Height of bitmaps in title bar		
32	Width of window frame that can be sized		
33	Height of window frame that can be sized		
34	Minimum tracking width of window		
35	Minimum tracking height of window		
41	Is Pen Windows installed?		
	0 no		
	1 yes		
42	Is DBCS version of USER.EXE installed?		
	0 no		
	1 yes		
43	Number of buttons on mouse		
70	Windows will display visual info in place of audible info		
	0 no		
	1 yes		
73	Computer has a slow processor		
	0 no		
	1 yes		
74	Is Windows set up for Arabic/Hebrew?		
	0 no		
75	1 yes		
75	Mouse has a wheel		
	0 no		
76	1 yes Coordinate of left side of virtual screen		
76	Coordinate of left side of virtual screen		
77	Coordinate of top of virtual screen		

78	Width in pixels of virtual screen		
79	Height in pixels of virtual screen		
80	Number of monitors on desktop		

3.14.4.20:@WINPOS

@WINPOS[title]: Returns the screen coordinates of the window with the specified title, in the format "top,left,bottom,right".

3.14.4.20:@WINSTATE

@WINSTATE[*title*]: Returns the window state of the first window matching *title* (which can include wildcards 77). The return values are:

Value	Window state	
0	Hidden	
1	Normal	
2	Minimized	
3	Maximized	

3.14.4.20₄@WINSYSTEM

@WINSYSTEM[n],v]: Sets or returns the value of the requested Windows system-wide parameters.

To retrieve a parameter, the format is **@winsystem[n]** where **n** is the appropriate **GET** number from the table below.

To set a parameter, the format is @winsystem[n,v] where n is the appropriate **SET** number from the table below and v is the desired new value for that parameter.

Where the selection is a state, the legal values are **0** for off/disabled, and **1** for on/enabled.

Where the selection is a width or height, the values are in pixels.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits).

Note: This function provides direct access to the **SystemParametersInfo** API. Not all available parameters are listed here. See your Windows technical documentation for details, and use with caution.

GET	SET	Parameter to GET or SET
1	2	Beep state
5	6	Border width
10	11	Keyboard repeat speed (0 to 31)
13	13	Width of an icon cell
14	15	Screen saver time-out (seconds)
16	17	Screen saver state
22	23	Keyboard repeat delay setting (0-3).
24	24	Height of an icon cell

25	26	Icon title wrapping state	
27	28	Icon title wrapping state Pop-up menu alignment	
37	38	Full-window dragging state	
56	57	Show Sounds accessibility flag	
68	69	Keyboard preference state (0=mouse, 1=keyboard)	
70	71	Screen reviewer utility state	
74	75	Font smoothing feature state	
79	81	Time-out for the low-power phase of screen saving (seconds)	
80	82	Time-out value for the power-off phase of screen saving (seconds)	
83	85	Low-power phase of screen saving state	
84	86	Power-off phase of screen saving state	
89	90	Locale identifier for the system default input language.	
93	94	Mouse Trails feature state. (0 or 1= disabled, >1= number of cursors in the trail)	
95	95	Snap-to-default-button feature state	
98	99	Width of the mouse pointer WM_MOUSEHOVER message trigger rectangle	
100	101	Height of the mouse pointer WM_MOUSEHOVER message trigger rectangle	
102	103	Time in the hover rectangle for the mouse pointer to trigger a	
102	100	WM_MOUSEHOVER message (milliseconds)	
104	105	Number of lines to scroll when the mouse wheel is rotated	
106	107	Time that the system waits before displaying a shortcut menu when the mouse	
		cursor is over a submenu item (milliseconds)	
110	111	IME status window state - per user (0=invisible, 1=visible)	
112	113	Current mouse speed (1 to 20).	
4096	4097	Active window tracking state	
4098	4099	Menu animation feature state.	
4100	4101	Combo box animation state.	
4102	4103	List box smooth-scrolling effect state.	
4104	4105	Gradient effect for window title bars.	
4106	4107	Menu access keys underline state.	
4108	4109	Active window tracking Z-order state.	
4110	4111	Hot-tracking state.	
4114	4115	Menu fade animation state.	
4116	4117	Selection fade effect state.	
4118		ToolTip animation state.	
4120	4121	Type of ToolTip animation (1 for fade, 0 for slide)	
4122	4123	Cursor shadow state.	
4124	4125	State of the Mouse Sonar feature	
4126	4127	Mouse clicklock state	
4128	4129	Mouse vanish feature state	
4130	4131	Whether native User menus have flat menu appearance.	
4132	4133	Drop shadow effect state.	
4158	4159	State of all UI effects.	
8192	8193	Time following user input during which the system will not allow applications to force themselves into the foreground (milliseconds)	
8194	8195	Active window tracking delay (milliseconds)	
8196	8197	The number of times SetForegroundWindow will flash the taskbar button when rejecting a foreground switch request.	
8198	8199	Caret width in edit controls	

8200	8201	Time delay before the primary mouse button is locked.
8202	8203	Type of font smoothing (32769=standard anti-aliasing, 32770=ClearType).
8204	8205	Contrast value used in ClearType smoothing (1000-2200)
8206	8207	Width of the left and right edges of the focus rectangle
8208	8209	Height of the top and bottom edges of the focus rectangle

<u>• </u>		
GET	SET	Parameter to GET or SET

3.14.4.20!@WMI

@WMI[namespace, "wql search"[,enum]]: Returns the result of the WMI query.

The optional **enum** parameter specifies the property instance to return for classes that return multiple properties. You can omit the **enum** parameter if you're querying a single property and instance.

For details on what information is available, see the WMI and WQL documentation on MSDN (msdn.microsoft.com).

See also WMIQUERY 364).

Examples:

%@wmi[root\cimv2,"SELECT name FROM Win32_Processor"]

%@wmi[root\cimv2,"SELECT name, state FROM Win32_service",4]

3.14.4.20(@WORD

@WORD[["sep_list",]n,string]: Returns the nth word in string. The first (leftmost) word is numbered 0. If n is negative, words are counted backwards from the end of string, and the absolute value of n is used. You can specify the rightmost word by setting n to -0.

You can specify a range of words to return with the syntax:

@WORD[["sep_list",]start[-end | +range],string]

Specify an inclusive range with a -. For example:

%@word[2-4,A B C D E F G] will return "C D E". (Note that you cannot use inclusive ranges when starting from the end.)

You can specify a relative range with a +. For example:

%@word[2+1,A B C D E F G] will return "C D".

The default list of separators for <u>@FIELD</u> 426, <u>@FIELDS</u> 427, <u>@WORD</u> 472 and <u>@WORDS</u> 473 consists of space, tab, and comma. You can use the optional first parameter, sep_list, to specify the separators that you wish to use. If you want to use a quote mark as a separator, prefix it with an <u>Escape character</u> 124. Alphabetic characters in sep_list are case sensitive.

@FIELD 426 and @FIELDS 427 differ from @WORD 472 and @WORDS 473 in how multiple consecutive separators are counted. @WORD 472 and @WORDS 473 consider a sequence as a single separator, and ignore separators at either end of string. In contrast, @FIELD 426 and @FIELDS 427 count each occurrence of a separator individually, including those at either end of string.

Numeric input may be entered in either decimal format (series of digits 0-9) or in hexadecimal format ("0x" followed by a sequence of 0-F hex digits). To use hexadecimal form for a negative n, remember to use 32-bit 2's complement arithmetic, e.g., 0xFFFFFFF for -1.

If **string** is double quoted, you must specify **sep_list**.

See also: @WORDS 473, @FIELD 426, @FIELDS 427.

Examples:

function	value
%@WORD[2,NOW, , , IS THE TIME]	THE
%@WORD[-0,NOW IS THE TIME]	TIME
%@WORD[-2,NOW IS THE TIME]	IS
%@WORD["=",1,2 + 2=4]	4

3.14.4.20 @WORDS

@WORDS[["sep_list",]string]: Returns the number of words in string.

The default list of separators for <u>@FIELD</u> [426], <u>@FIELDS</u> [427], <u>@WORD</u> [472] and <u>@WORDS</u> [473] consists of space, tab, and comma. You can use the optional first parameter, **sep_list**, to specify the separators that you wish to use. If you want to use a quote mark as a separator, prefix it with an <u>Escape character</u> [124]. Alphabetic characters in **sep_list** are case sensitive.

@FIELD 426 and @FIELDS 427 differ from @WORD 472 and @WORDS 473 in how multiple consecutive separators are counted. @WORD 472 and @WORDS 473 consider a sequence as a single separator, and ignore separators at either end of **string**. In contrast, @FIELD 426 and @FIELDS 427 count each occurrence of a separator individually, including those at either end of **string**.

If **string** is double quoted, you must specify **sep_list**.

See also: @WORD 472, @FIELD 426, @FIELDS 427.

3.14.4.20(@WORKGROUP

@WORKGROUP[name]: Returns the workgroup of the computer specified by the DNS or NetBios name. If name is not specified, @WORKGROUP returns the workgroup of the local computer.

3.14.4.20!@XMLCLOSE

@XMLCLOSE[]: Close an XML file previously opened by @XMLOPEN 4741.

For more details on XML support, see XML in Take Command 5021.

3.14.4.21(@XMLNODES

@XMLNODES[["filename"],path]: Return the number of nodes (children) for the specified path in an XML file. The arguments are:

filename - name of XML file **path** - one or more element accessors separated by a /.

If you don't specify a filename (which *must* be in double quotes), @XMLXPATH will use the XML file previously opened by @XMLOPEN 474.

For more details on XML support, see XML in Take Command 5021.

3.14.4.21 @XMLOPEN

@XMLOPEN[filename] - open an XML file for use by @XMLXPATH 474] and/or @XMLNODES. 473]

For more details on XML support, see XML in Take Command 5021.

3.14.4.21:@XMLXPATH

@XMLXPATH[["filename"],path]: XML XPath query. (See the XML XPath docs for details on XPath syntax.) The arguments are:

```
filename - name of XML file path - one or more element accessors separated by a /.
```

If you don't specify a filename (which *must* be in double quotes), @XMLXPATH will use the XML file previously opened by @XMLOPEN 474.

For more details on XML support, see XML in Take Command [502].

3.14.4.21;@YEAR

@YEAR[date[,format]]: Returns the year for the specified date. See date formats 127 for valid formats.

@YEAR accepts an optional second parameter specifying the date format:

- 0 default
- 1 USA (mm/dd/yy)
- 2 Europe (dd/mm/yy)
- 3 Japan (yy/mm/dd)
- 4 ISO (yyyy/mm/dd)

4 Troubleshooting

- Registration 474
- ▶ Troubleshooting Service and Support 475
- Supported Platforms 477
- Help File 477
- ▶ Error Messages 478

4.1 Registration

There are no separate **trial** and **registered** versions of *Take Command.* Without registration, a trial version is fully functional for 30 days of use.

At any time you can apply your current personal registration information to a trial version in order to turn it into a registered product. Use the command VER /R 359 from the prompt to verify the status of the copy you are currently running. (You can also view the Help/About 61) menu entry.)

When you purchase a new or upgrade copy of *Take Command*, you will receive an email with your name and registration key. Start *Take Command*, click on the **Options** menu entry and then

Configure Take Command. Select the **Register** tab and enter the registration information exactly as you received it in the email. Remember to save your registration key in a safe place in case you need to reinstall. If you have lost your registration key, you can request a replacement by contacting JP Software at support@jpsoft.com, or at one of the addresses listed at the start of this file.

4.2 Troubleshooting, Service & Support

If you need help with *Take Command*, we encourage you to review our documentation and then contact us for assistance if required.

If you need help with sales, ordering, or shipments (including defective disks or other materials which were shipped to you), or with registration codes, please contact our Sales and Customer Service department. See Contacting JP Software [47] for our email address, mail address, and telephone numbers. Note that Sales and Customer service staff cannot assist you with technical problems and conversely Technical Support representatives cannot answer your sales or registration questions.

If you need technical support for *Take Command*, review the <u>Technical Support [475]</u> information section, which tells you what we need to know to provide you with accurate and timely support, then contact us via one of the methods described there. In most instances, our Online Support Forum is the fastest and most efficient way to address your technical questions and concerns.

4.2.1 Technical Support

Support Plans

Standard, no-charge support is available electronically through our Support Forum [475] (see below). We also offer a paid support option which includes automatic upgrades and support by private email or telephone. For complete details on all support options, including plans currently offered and support terms and conditions, see our web site at http://jpsoft.com/.

Before you contact Technical Support, please review the What Information do we need? 476 section which outlines the basic data we need to best address your questions and concerns.

Online Support

The primary venue for Technical Support is via our free online Support Forum, where our support personnel can read and respond to your messages, and other users can participate in and benefit from the exchange. The Forum is a lively community frequented by a number of experienced and helpful users. JP Software representatives read every Forum message and respond as promptly as reasonably possible whenever appropriate.

If you have any kind of Internet access, even if only email, chances are you can use the Forum which we make accessible as a mailing list, a news group, and a set of web pages. Forum members must provide a valid email address and a full name to be able to post, but you do need not need to join or provide any information to simply visit or search the Forum. For complete details and direct access links see the support area of our web site at http://jpsoft.com/.

A number of other support resources are available from our web site, including documentation files, technical tips and discussions, other technical information, and links to other sites. We update this information regularly, and we encourage you to check the Technical Support area of the web site to see if the information there will address any questions you have.

If you are unable to gain access to the forum, or you need to include confidential information in your support request, contact us via email at support@jpsoft.com and we will assist you in resolving the problem with forum access, or assist you with your request privately if appropriate. Please do not use

that address for standard support questions which can be posted on the forum.

If you are a paid support customer you should use the online Support Forum for routine questions. To create a private support incident refer to the materials sent to you with your subscription for contact information, or email priority_support@jpsoft.com and include your support ID (mail to this address may not be answered if it does not include a valid support ID).

Note that for security and "anti-spam" reasons, the support address filters out all non-text data (including screen shots and others) and such prohibited material will probably be lost before it ever reaches us. Technical support messages should be sent as standard ASCII text. Please do not transmit attached files, binary files, screen images, or any file over 10K bytes in size to any of our electronic technical support addresses unless asked to do so by our support staff. We will be unable to respond to (and may not even receive) messages that do not met these basic criteria.

What Information do we need?

Before contacting us for support, please check this help file and other documentation for answers to your question. If you can't find what you need, try the Index. If you're having trouble getting *Take Command* to run properly, review the information on Error Messages 4781, and look through the Support Forum for any last-minute information.

If you need help with sales, ordering, shipments, registration keys, or other similar non-technical issues please contact our Sales and Customer Service department. Technical Support will not be able to assist you with those matters. Conversely, Customer Service is not equipped to answer your technical questions. See Contacting JP Software [477] for our addresses.

Regardless of how you contact us for support, we can do a much better job of assisting you if you can give us some basic information, separate from your interpretations of or conclusions about the problem. Remember that we know NOTHING about your system or configuration unless you tell us, and we can't always make accurate guesses if you don't. The first four items listed below are essential for us to be able to understand and assist you with your problem:

- What environment are you working in? This includes the operating system version you are using, the version of the JP Software product involved, and related information such as network connections and the name and version number of any other software which appears to be involved in the problem. Use the VER /R soft command to determine the *Take Command* version and operating system version. This item is essential! Every question posted on the Forum should include a brief identification such as "Take Command 9.0.88 under XP+SP2" or something similar.
- What exactly did you do? A concise description of what steps you must take to make the problem appear is much more useful than a long analysis of what might be happening. In most cases, posting the exact command line(s) giving you trouble is the simplest approach.
- What did you expect to happen? Tell us the result you expected from the command or operation in question, so that we understand what you are trying to do. Something that seems "obvious" to you might not be so to others. For example, tell us "I was expecting the file name to be in upper case" or a similar brief explanation.
- What actually happened? At what point did the failure occur? If you saw an error message
 or other important or unusual information on the screen, what exactly did it say? Don't simply
 tell us "it didn't work". For example, if you were expecting output from a command and saw
 none, at least tell us that much.
- Briefly, what techniques did you use to try to resolve the problem? What results did you
 get? One technique that tends to solve many problems is to review the help for the command
 or feature in question and try it with the documented exact correct syntax, as opposed to some

undocumented alternative.

- If the problem seems related to startup and configuration issues, what are the contents of any startup files you use (such as TCSTART 22 or TCEXIT 22, and the .INI file), any batch files they call, and any alias or environment variable files they load?
- Can you repeat the problem or does it occur randomly? If it's random, does it seem related to the programs you're using when the problem occurs? Random or occasional problems are very difficult to diagnose. Do your best to determine some sort of pattern or sequence of events that triggers the problem. If you can't reproduce it, chances are we won't be able to either. Note that mysterious unexplainable problems often permanently disappear after simply reloading the program or even rebooting the system.
- If t*Take Command* experiences an unrecoverable failure, it will attempt to send the relevant memory locations and other useful data to the Windows Error Reporting (WER) site.

4.2.2 Contacting JP Software

You can contact JP Software at the following addresses and numbers. Our normal business hours are 9:00 AM to 5:00 PM weekdays, Eastern US time (except holidays).

Address: JP Software Inc.

P.O. Box 328

Chestertown, MD 21620

USA

Phone: 800-595-8197

Fax: 800-595-8197 (rings through to fax)

Online: Web site: http://jpsoft.com/

FTP site: ftp://jpsoft.com

Sales / Customer Service: support@jpsoft.com

Technical Support: Standard (no-charge) support: Available via our online Support Forum,

accessible from the support area of our web site.

See Technical Support [475] for additional details, and for information on paid support options.

Note: Our server implements anti-spam measures. Please make sure you are using the correct address with appropriate subject line and contents, else we might not receive your email message.

4.3 Supported Platforms

Take Command is a Win32 GUI application.

TCC is a Win32 console (character-mode) application.

Both are designed to run under Windows XP, Windows 2003, Windows Vista, and Windows 2008.

4.4 Help File

The installer for *Take Command* includes *tcmd.chm*, a help file in Window's compiled HTML format. That file includes description and syntax for all commands, variables and functions, as well as reference information to assist you in installing and using *Take Command* and developing batch files,

aliases and functions. *Take Command* uses the default Windows help system to display the contents of **tcmd.chm**. Under most configurations, Windows will remember the last used settings (window size, tab selected, etc.) for that file. Once you've started the help system with F1 34 or the HELP 25 command, you can use standard Windows HTML Viewer (HH.EXE) keystrokes to navigate. For more information, see your Windows documentation.

The help is also available as PDF file. Please check our web site regularly to make sure you have the most recent version of the help files, since they are usually updated more frequently than the programs.

You can request help at the prompt from the **Help** menu, by typing <u>HELP</u> [25th] (or <u>HELP</u> [25th] plus a command name), or by pressing the <u>F1</u> [34th] key at any time when **TCC** is accepting keyboard input at the prompt. If you use the <u>HELP</u> [25th] command by itself you will be taken to an introductory page, but if you follow the command with a topic name (e.g. **help copy**) you will see help on the requested topic if available.

If you type a command name on the line and then press $\underline{\mathsf{F1}}^{34}$, the help system will provide context sensitive help by using the first word on the line as the help topic. For example, if you press $\mathsf{F1}$ after entering each of the command lines shown below you will get the display indicated:

```
[c:\] copy * a: Overview
[c:\] copy * a: Help on the COPY command
[c:\] c:\util\map "The page cannot be displayed"
```

You can use this feature to obtain help directly on any topic, not just on commands. All internal commands, internal variables, variable functions, and key mapping directives have their own topic, allowing you to directly query, for example, **help @eval** (help for the @eval[] function) or **help _disk** (help for the DISK internal variable).

You can also invoke help for the word immediately above (or immediately to the left of) the cursor by pressing the Ctrl-F1 key. This feature is especially useful when you need the syntax for a variable function.

If the topic you seek is not listed, look for a suitable cross reference from the **Index** tab or use the **Search** tab. The topics you use most often can be stored and recalled through the **Favorites** tab.

Quick Syntax Help:

If you just need a quick reminder of an internal command's syntax, type the name of the command at the prompt, followed by a slash and a question mark /? For example:

```
copy /?
```

TCC will display the syntax and the valid options for the command.

4.5 Error Messages

This section lists error messages generated by *Take Command*, and includes a recommended course of action for most errors. If you are unable to resolve the problem after reviewing these help files, contact JP Software for technical support [475].

Error messages relating to files are generally reports of errors returned by Windows. You may find some of these messages (for example, "Access denied") vague enough that they are not always helpful. *Take Command* includes the file name in file error messages, but is often unable to determine a more accurate explanation of these errors. The message shown is the best information available

based on the error codes returned by Windows.

Not all errors potentially reported by Windows can be listed here. See Windows System Errors for examples of system errors returned in the _SYSERR [392] internal variable.

The following list includes most common error messages, in alphabetical order:

Access denied: You tried to write to or erase a read-only file, rename a file or directory to an existing name, create a directory that already exists, remove a read-only directory or a directory with files or subdirectories still in it, or access a file in use by another program in a multitasking system.

Alias loop: An alias refers back to itself either directly or indirectly (*i.e.*, a = b = a), or aliases are nested more than 16 deep. Correct your alias list.

Already debugging a batch file: You are attempting to invoke a nested instance of the Batch File Debugger (BDEBUGGER 166)) while you are already in the debugger.

Already excluded files: You used more than one exclude range in a command. Combine the exclusions into a single range.

Bad disk unit: Generally caused by a disk drive hardware failure.

Batch file missing: *TCC* can't find the batch (.*BTM* or .*CMD*) file it was running. It was either deleted, renamed, moved, or the disk was changed. Correct the problem and rerun the file.

Can't COPY or MOVE file to itself: You cannot COPY or MOVE a file to itself. **TCC** attempts to perform full path and filename expansion before copying to help ensure that files aren't inadvertently destroyed.

Can't create: **TCC** can't create the specified file. The disk may be full or write protected, or the file already exists and is read-only, or the root directory is full.

Can't delete: TCC can't delete the specified file or directory. The disk is probably write protected.

Can't end current process: You attempted to terminate *TCC* with a <u>TASKEND</u> [342] command. TASKEND can only be used to end other processes; to terminate *TCC*, use the EXIT [227] command.

Can't get directory: TCC can't read the directory. The disk drive is probably not ready.

Can't make directory entry: *TCC* can't create the filename in the directory. This is usually caused by a full root directory. Create a subdirectory and move some of the files to it.

Can't open: **TCC** can't open the specified file. Either the file doesn't exist or the disk directory or File Allocation Table is damaged.

Can't query key type: The key name supplied to @REGQUERY refers to a key with a type that @REGQUERY does not support. See @REGQUERY 455 for a list of supported key types.

Can't remove current directory: You attempted to remove the current directory, which Windows does not allow. Change to the parent directory and try again.

CD-ROM door open or **CD-ROM not ready**: The CD-ROM drive door is open, the power is off, or the drive is disconnected. Correct the problem and try again.

CD-ROM not High Sierra or ISO-9660: The CD-ROM is not recognized as a data CD (it may be a music CD). Put the correct CD in the drive and try again.

Clipboard is empty or not text format: You tried to retrieve some text from the Windows clipboard, but there is no text available. Correct the contents of the clipboard and try again.

Clipboard is in use by another program: *Take Command* could not access the Windows clipboard because another program was using it. Wait until the clipboard is available, or complete any pending action in the other program, then try again.

Command line too long: A single command or the entire command line exceeded the maximum allowable length (including during alias, variable, or function expansion). Reduce the complexity of the command or use a batch file. Also check for an alias which refers back to itself either directly or indirectly.

Command only valid in batch file: You have tried to use a batch file command, like DO or GOSUB, from the command line or in an alias. A few commands can only be used in batch files (see the individual commands for details).

Contents lost before copy: COPY was appending files, and found one of the source files is the same as the destination. That source file is skipped, and appending continues with the next file.

Data error: Windows can't read or write properly to the device. On a floppy drive, this error is usually caused by a defective floppy disk, dirty disk drive heads, or a misalignment between the heads on your drive and the drive on which the disk was created. On a hard drive, this error may indicate a drive that is too hot or too cold, or a hardware problem. Retry the operation; if it fails again, correct the hardware or diskette problem.

Directory stack empty: POPD 294 or DIRS 209 can't find any entries in the directory stack.

Disk is write protected: The disk cannot be written to. Check the disk and remove the write-protect tab or close the write- protect window if necessary.

Divide by zero: The command or function you used tried to do a division by zero. If the data causing the problem is from your own input or batch file, change the input to avoid the divide by zero condition. If the data was generated internally by *Take Command*, contact JP Software for assistance.

Drive not ready — **close door**: The removable disk drive door is open. Close the door and try again.

Duplicate redirection: You tried to redirect standard input, standard output, or stand error more than once in the same command. Correct the command and try again.

Error in command line directive: You used the **//iniline** option to place an .INI directive on the startup command line, but the directive is in error. Usually a more specific error message follows, and can be looked up in this list.

Error on line [nnnn] of [filename]: There is an error in your .INI file 26. The following message explains the error in more detail. Correct the line in error and restart **TCC** for your change to take effect.

Error reading: Windows experienced an I/O error when reading from a device. This is usually caused by a bad disk, a device not ready, or a hardware error.

Error writing: Windows experienced an I/O error when writing to a device. This is usually caused by a full disk, a bad disk, a device not ready, or a hardware error.

Exceeded batch nesting limit: You have attempted to nest batch files more than 10 levels deep.

File Allocation Table bad: Windows can't access the FAT on the specified disk. This can be caused by a bad disk, a hardware error, or an unusual software interaction.

File association not found: The ASSOC [162] command could not find a file association for the specified extension in the Windows registry.

File exists: The requested output file already exists, and TCC won't overwrite it.

File not found: TCC couldn't find the specified file. Check the spelling and path name.

File type not found: The FTYPE 24th command could not find the specified file type in the Windows registry.

General failure: This is usually a hardware problem, particularly a disk drive failure or a device not properly connected to a serial or parallel port. Try to correct the problem, or reboot and try again. See also: **Data error** above.

Include file not found: You used the Include directive in the <u>INI file</u> (26), but the file you specified was not found or could not be opened.

Include files nested too deep: You used the Include directive in the .INI file 26, and attempted to nest include files more than three levels deep.

Infinite COPY or MOVE loop: You tried to COPY or MOVE a directory to one of its own subdirectories and used the /S switch, so the command would run forever. Correct the command and try again.

Input and output files must have different names: (BATCOMP 166) You are attempting to compress a file to itself.

Input file is already compressed: (BATCOMP 166) You are attempting to compress a batch file that has already been compressed.

Insufficient disk space: COPY or MOVE ran out of room on the destination drive. Remove some files and retry the operation.

Invalid batch file: The batch file is corrupted, or improperly <u>compressed</u>, and or encrypted. Retry with a new copy of the file.

Invalid character value: You gave an invalid value for a character directive in the .INI file 26.

Invalid choice value: You gave an invalid value for a "choice" directive (one that accepts a choice from a list, like "Yes" or "No") in the INI file 26.

Invalid color: You gave an invalid value for a color directive in the INI file 26.

Invalid count: The character repeat count for KEYSTACK 262 is incorrect.

Invalid date: An invalid date was entered. Check the syntax and reenter.

Invalid directive name: Take Command can't recognize the name of a directive in the INI file 26.

Invalid drive: A bad or non-existent disk drive was specified.

Invalid key name: You tried to make an invalid key substitution in the <u>INI file 26</u>, or you used an invalid key name in a keystroke <u>alias 154</u> or command. Correct the error and retry the operation.

Invalid numeric value: You gave an invalid value for a numeric directive in the INI file 26.

Invalid parameter: *TCC*didn't recognize a parameter. Check the syntax and spelling of the command you entered.

Invalid path: The specified path does not exist. Check the disk specification and/or spelling.

Invalid path or file name: You used an invalid path or filename in a directive in the .INI file 26.

Invalid time: An invalid time was entered. Check the syntax and reenter.

Keystroke substitution table full: *TCC* ran out of room to store keystroke substitutions and the .INI file 26. Reduce the number of key substitutions or contact JP Software or your dealer for assistance.

Label not found: A GOTO 248 or GOSUB 247 referred to a non-existent label. Check your batch file.

Listbox is full: There is no more room in the Find Files / Text dialog's results box. Use a more selective search, or use the FFIND command rather than the dialog.

Missing close paren: A KEYSTACK 262 command is missing a closing parentheses around a character group. Correct the command.

Missing ENDTEXT: A TEXT [345] command is missing a matching ENDTEXT. Check the batch file.

Missing GOSUB: *TCC* cannot perform the <u>RETURN</u> 307 command in a batch file. You tried to do a RETURN without a GOSUB 247, or your batch file has been corrupted.

Missing SETLOCAL: An ENDLOCAL 220 was used without a matching SETLOCAL 326.

No aliases defined: You tried to display aliases but no aliases have been defined.

No closing quote: *TCC*couldn't find a second matching back quote [`] or double-quote ["] on the command line.

No expression: The expression passed to the $\frac{\%@EVAL}{420}$ variable function is empty. Correct the expression and retry the operation.

No shared memory found: The SHRALIAS (329) command could not find any global alias list, history list, or directory history list to retain, because you executed the command from a session with local lists. Start *TCC* with at least one global list, then invoke SHRALIAS.

No SMTP server: SENDMAIL and can't find an SMTP server. Check your INI file or mailer configuration (see SENDMAIL for additional details).

Not a directory: The name passed to RD 301 is not a directory.

Not an alias: The specified alias is not in the alias list.

Not in environment: The specified variable is not in the environment.

Not ready: The specified device can't be accessed.

Not same device: This error usually appears in RENAME [305]. You cannot rename a file to a different

disk drive.

Out of function space: You are attempting to create a <u>User-defined Function [242]</u> that would require more resources than what your system makes available. Shorten the function definition or delete functions you no longer need

Out of memory: *Take Command* or Windows had insufficient memory to execute the last command. Try to free some memory by closing other sessions. If the error persists, contact JP Software for assistance.

Out of paper: Windows detected an out-of-paper condition on one of the printers. Check your printer and add paper if necessary.

Overflow: An arithmetic overflow occurred in the <u>@EVAL</u> [420] variable function. Check the values being passed to @EVAL.

Read error: Windows encountered a disk read error; usually caused by a bad or unformatted disk. See also: **Data error** above.

Sector not found: Disk error, usually caused by a bad or unformatted disk. See also: **Data error** above.

Seek error: Windows can't seek to the proper location on the disk. This is generally caused by a bad disk or drive. See also: **Data error** above.

Sharing violation: You tried to access a file in use by another program in a multitasking system or on a network. Wait for the file to become available, or change your method of operation so that another program does not have the file open while you are trying to use it.

SHRALIAS already loaded: You used the <u>SHRALIAS</u> 329 command to load SHRALIAS.EXE, but it was already loaded. This message is informational and generally does not indicate an error condition.

SHRALIAS not loaded: You used the SHRALIAS /U 3291 command to unload SHRALIAS.EXE, but it was never loaded. This message is informational and may not indicate an error condition.

String area overflow: *TCC* ran out of room to store the text from string directives in the .INI file 26. Reduce the complexity of the .INI file or contact JP Software for assistance.

String too long: You tried to put more than 2038 characters into the KEYSTACK buffer. Reduce the number of characters you are trying to send to the application at one time.

Syntax error: A command or <u>variable function</u> was entered in an improper format. Check the syntax and correct the error.

Too many open files: Windows has run out of file handles.

Unbalanced parentheses: The number of left and right parentheses did not match in an expression passed to the @EVAL [420] variable function. Correct the expression and retry the operation.

UNKNOWN_CMD loop: The <u>UNKNOWN_CMD alias</u> salled itself more than ten times. The alias probably contains an unknown command itself, and is stuck in an infinite loop. Correct the alias.

Unknown command: A command was entered that *TCC* didn't recognize and couldn't find in the current search path. Check the spelling or PATH specification. You can handle unknown commands with the UNKNOWN_CMD alias (see ALIAS 154).

Unknown option name: (OPTION 284) You are attempting to modify or display an invalid or unknown option name.

Unknown process: TASKEND [342] cannot find the process you specified. If you are ending a process using the title you may need to use wildcards to get a match on the title string. Correct the command and try again.

Variable loop: A nested environment variable refers to itself, or variables are nested more than 16 deep. Correct the error and retry the command.

Window title not found: The ACTIVATE [152] command could not find a window with the specified title. Correct the command or open the appropriate window and try again.

Write error: Windows encountered a disk write error; usually caused by a bad or unformatted disk. See also; **Data error** above.

5 Reference Information

- ▶ CMD.EXE Comparison 484
- File Systems and File Name Conventions 490
- Miscellaneous Reference Information 504
- ASCII, Key Codes, and ANSI Commands 510
- Glossary 519
- ► Copyright and Version 537

5.1 CMD.EXE Comparison

THIS TOPIC IS STILL UNDER CONSTRUCTION - COMMENTS WELCOME!

The comparison of commands available is based on the version of **CMD.EXE** included with Windows XP Build 2600 Service Pack 2.

If the CMD.EXE command name matches an internal *TCC* command, the *TCC* command is almost always enhanced.

- ▶ TCC command equivalents in CMD.EXE 484
- ▶ CMD.EXE command equivalents in TCC 487
- Command line editing 488
- Filename completion 489
- Command completion 489
- Redirection 489
- Wildcards 489
- ▶ Built-In Variables 489
- Batch File Structure 489
- ▶ Unique TCC features 489

TCC command equivalent in CMD.EXE

CMD.EXE command (nearest functionality)	CMD.EXE command type
	external

ACTIVATE 152			
ALIAS 154	DOSKEY	external	
ASSOC 162	ASSOC	internal	
ATTRIB 163	ATTRIB	external	
BATCOMP 166	ATTRIB	CATCITICI	
BDEBUGGER 166			
BEEP 173			
BREAK 174	BREAK	internal	
BREAKPOINT 174	BILAN	internal	-
CALL 175	CALL	internal	\dashv
CANCEL 176	CALL	internal	
CD 177)	CD.	intornal	
CDD 178	CD	internal	
CHCP 180	OLIOD	autamal	_
	CHCP	external	
CHDIR 177	CHDIR	internal	
CLS 181	CLS	internal	
COLOR 18 [‡] COPY 18 ²	COLOR	internal	
	COPY	internal	
COPY 182	XCOPY	external	
DATE 189	DATE	internal	
DEL 190	DEL	internal	
DELAY 194			
DESCRIBE 195			
DETACH 197			
DIR 198	DIR	internal	
DIRHISTORY 208			
DIRS 209			
DO 210			
DRAWBOX 214			
DRAWHLINE 215			
DRAWVLINE 216			
ECHO 217	ECHO	internal	
ECHOERR 218			
ECHOS 219			
ECHOSERR 220			
ENDLOCAL 220	ENDLOCAL	internal	
ERASE 190	ERASE	internal	
ESET 222			
EVENTLOG 223			
EXCEPT 225			
EXIT 227	EXIT	internal	
FFIND 227	FIND	external	
FFIND 227	FINDSTR	external	
FOR 234	FOR	internal	
FREE 24			
FTYPE 24h	FTYPE	internal	
FUNCTION 242			
GLOBAL 245			
GOSUB 247	CALL :LABEL	internal	
GOTO 248	GOTO	internal	
HEAD 249			\exists
HELP 25th	HELP	external	
HISTORY 25th	111	Oxtornal	
1110101112011			

	h-	h
IF 253	IF	internal
IFF 254		
IFTP 255		
INKEY 257		
INPUT 259		
KEYBD 261		
KEYS 26th		
KEYSTACK 262		
LIST 264	MORE	external
LOADBTM 269		
LOG 269		
MD 271	MD	internal
MEMORY 272		
MKDIR 27A	MKDIR	internal
MKLNK 273		
MOVE 274	MOVE	internal
MSGBOX 279		
ON 282		
OPTION 284		
OSD 286		
PATH 286	PATH	internal
PAUSE 287	PAUSE	internal
PDIR 288	17.002	intornal
PLAYAVI 2917		
PLAYSOUND 292		
POPD 294)	POPD	internal
PRINT 295	PRINT	external
PRIORITY 295	I IXIIVI	external
PROMPT 297	PROMPT	internal
PUSHD 299	PUSHD	internal
QUERYBOX 300	1 00110	internal
QUIT 30A	GOTO :EOF	
RD 301		into an al
	RD	internal
REBOOT 303		
RECYCLE 304	DEM	
REM 304	REM	internal
REN 305	REN	internal
RENAME 305	RENAME	internal
RETURN 307	GOTO :EOF	
REXEC 308		
RSHELL 309	DIADID	
RMDIR 301	RMDIR	internal
SCREEN 310		
SCRPUT 31F)		
SELECT 312		
SENDMAIL 316		
SET 319	SET	internal
SETDOS 323		
SETLOCAL 326	SETLOCAL	internal
SHIFT 327	SHIFT	internal
SHORTCUT 328		
SHRALIAS 329		
SMPP 330		

SNPP 33		
START 33f	START	internal
SWITCH 335		
SYNC 336		
TAIL 339		
TASKEND 342		
TASKLIST 342		
TEE 344		
TEXT 345		
TIME 347)	TIME	internal
TIMER 347		
TITLE 349	TITLE	internal
TOUCH 349		
TREE 352	TREE	external
TRUENAME 353		
TYPE 354	TYPE	internal
UNALIAS 355		
UNFUNCTION 356		
UNSET 357	SET VARNAME=	internal
VER 359	VER	internal
VERIFY 360	VERIFY	internal
VOL 360)	VOL	internal
VSCRPUT 366		
WHICH 36A		
WINDOW 362		
Y 364		

CMD.EXE command equivalents in TCC

CMD.EXE	CMD.EXE class	TCC command	comparison
command			
ASSOC	internal	ASSOC 162	enhanced
AT	external		
ATTRIB	external	ATTRIB 163	enhanced
BREAK	internal	BREAK 174	enhanced
CACLS	external		
CALL	internal	CALL 175, GOSUB 247	enhanced
CD	internal	CD 177	enhanced
CHCP	external	CHCP 180	identical
CHDIR	internal	CHDIR 177	enhanced
CHKDSK	external		
CHKNTFS	external		
CLS	internal	CLS 18th	enhanced
COLOR	internal	COLOR 18th	enhanced
COMP	external		
COMPACT	external		
CONVERT	external		
COPY	internal	COPY 182	enhanced
DATE	internal	DATE 189	enhanced
DEL	internal	DEL 19ℓ	enhanced
DIR	internal	DIR 1981, PDIR 2881	enhanced
DISKCOMP	external		

DISKCOPY	external		
DOSKEY	external	ALIAS 154	enhanced
ECHO	internal	ECHO 217	identical
ENDLOCAL	internal	ENDLOCAL 220	enhanced
ERASE	internal	ERASE 190	enhanced
EXIT	internal	EXIT 227	enhanced
FC	external		
FIND	external	FFIND 227	enhanced
FINDSTR	external	FFIND 227	enhanced
FOR	internal	FOR 234	enhanced
FORMAT	external		
FTYPE	internal	FTYPE 24	enhanced
GOTO	internal	GOTO 248	enhanced
GRAFTABL	external		
HELP	external	HELP 251	enhanced
IF	internal	F 253	enhanced
LABEL	external		
MD	internal	MD 2717	enhanced
MKDIR	internal	MKDIR 27	enhanced
MODE	external		o manoo a
MORE	external	LIST 264	enhanced
MOVE	internal	MOVE 274	enhanced
PATH	internal	PATH 286	identical
PAUSE	internal	PAUSE 287	enhanced
POPD	internal	POPD 294	enhanced
PRINT	external	PRINT 295	enhanced
PROMPT	internal	PROMPT 297	enhanced
PUSHD	internal	PUSHD 299	enhanced
RD	internal	RD 301	enhanced
RECOVER	external		o manoo a
REM	internal	REM 304	identical
REN	internal	REN 305	enhanced
RENAME	internal	RENAME 305	enhanced
REPLACE	external		
RMDIR	internal	RMDIR 30A	enhanced
SET	internal	SET 319	enhanced
SETLOCAL	internal	SETLOCAL 326	enhanced
SHIFT	internal	SHIFT 327	enhanced
SORT	external		
START	internal	START 33A	enhanced
SUBST	external		
TIME	internal	TIME 347	enhanced
TITLE	internal	TITLE 349	enhanced
TREE	external	TREE 352	enhanced
TYPE	internal	TYPE 354	enhanced
VER	internal	VER 359	enhanced
VERIFY	internal	VERIFY 360	enhanced
VOL	internal	VOL 360	identical
XCOPY	external	COPY 182	enhanced

Command line editing

Filename completion

Command completion

Redirection

Wildcards

CMD.EXE only supports the ? and * wildcards.

Built-In Variables

CMD.EXE has several built-in variables (i.e., which are treated as environment variables but which do not exist in the environment):

CD - current directory

CMDCMDLINE - command line that started CMD

CMDEXTVERSION - the command extensions internal version number

DATE - the current date (in the default short format)

RANDOM - a random number between 0 and 32767

TIME - current time

TCC supports all of these built-in variables. (In TCC, CMDEXTVERSION will always return 2.)

Batch File Structure

Unique Take Command features

Batch debugger

Aliases

Internal functions

User defined functions

File selection

Ranges

Internet access and email

OpenAFS support

ANSI X3.64 support

Directory navigation

Histories and logs

Intersession sharing

Perl, REXX, and Ruby support

5.2 Limits

Length Limits

entity	name	value	all
environment variable	1023	4,095	4,095
alias	1023	4,095	4,095
user defined function	1023	4,095	4,095

command type	before expansion	after expansion
command line	32,767	65,535
command group	32,767	65,535

Nesting Limits

command	depth
CALL 175	32
DO 210	no limit
FOR 234	no limit
GOSUB 247 without parameters	no limit
GOSUB 247 with parameters	22
SETLOCAL 326	16
IFF 254	no limit

Miscellaneous Limits

entity	limit
character count in any function	4,095
number of batch file	4,095
parameters	
number of GOSUB parameters	255
file name	4,095
include list	4,095
single parameter	4,095
global alias list	131,072
global function list	65,536
key substitution table	128
directory stack	2,047

5.3 File Systems & File Name Conventions

You probably have thousands of files stored on your computer's disks. Your operating system is responsible for managing all of these files. In order to do so, it uses a unique name to locate each file in much the same way that the post office assigns a unique address to every residence.

The unique name of any file is composed of a drive letter, a directory path, and a filename. In Windows, each of these parts of the file's name is case insensitive; you can mix upper and lower case letters in any way you wish. (Note that accessing Linux / UNIX FTP servers, the filenames **are** case sensitive.)

The topics below are roughly divided according to the different parts of a file name, and cover the file system structure and naming conventions:

- ▶ Drives and Volumes 491
- File Systems 491
- Directories and Subdirectories 492
- File Names 493
- File Attributes 494
- Time Stamps 495
- NTFS Streams 496

5.3.1 Drives & Volumes

A **drive letter** designates which drive contains the file. In a file's full name, the drive letter is followed by a colon. Drive letters **A:** and **B:** are normally reserved for the floppy disk drives.

Normally, drive **C:** is the first (or only) hard disk drive. Most current operating systems can partition a large hard disk into multiple logical drives or volumes that are usually called **C:**, **D:**, **E:**, etc. Network systems (LANs) give additional drive letters to sections of the network file server drives. In addition, you can access network drives via their **UNC** (universal naming convention) name (*e.g.* \(\lambda\)\(\lambda\)\(\text{tal}\)\(\lambda\)\(\text{tal}\)\(\lambda\)\(\text{tal}\)\(\text

Most systems also include optical drives (i.e. CD-ROM, CD-RW, and/or DVD). The optical drive is also assigned a drive letter (or several letters, for changers), typically using letters beyond that used by the last hard disk in the system, but before any network drives.

For example, on a system with a large hard disk you might have **A**: and **B**: as floppy drives, **C**:, **D**:, and **E**: as parts of the hard disk, **F**: as a CD-ROM drive, **G**: as a DVD drive, and **H**: and **I**: as network drives.

Each volume is formatted under a particular file system; see <u>File Systems [49]</u> for details. Additional information about disk files and directories is available under <u>Directories and Subdirectories</u> [492], <u>File Names [493]</u>, and <u>File Attributes [494]</u>.

5.3.2 File Systems

Take Command uses only documented Windows APIs to access the file systems, so it works with any file system supported by Windows.

Additional information about disk files and directories is available under <u>Drives and Volumes [491]</u>, <u>Directories and Subdirectories [492]</u>, <u>File Names [493]</u>, and <u>File Attributes [494]</u>.

Network File Systems

A network file system allows you to access files stored on another computer on a network, rather than on your own system. *Take Command* supports all network file systems which are compatible with the underlying operating system. The networking software used to access remote systems (such as UNIX, Linux, OS X, etc..) which use different file systems typically emulates one of the common Windows file systems. Those emulations do not always provide a perfect duplicate of some functions (attributes, timestamps, etc.), an issue unrelated to *Take Command*.

File and directory names for network file systems depend on both the "server" software running on the system that has the files on it, and the "client" software running on your computer to connect it to the network. However, they usually follow the rules described here.

Most network software maps unused drive letters on your system to specific locations on the network, and you can then treat the drive as if it were physically part of your local computer.

When you use a network file system, remember that the naming rules for files on the network may not match those on your local system. For example, your local system may support long filenames while the network server or client software does not, or vice versa. *Take Command* will usually handle whatever naming conventions are supported by your network software, as long as the network software accurately reports the types of names it can handle.

In rare cases, *Take Command* may not be able to report correct statistics on network drives (such as the number of bytes free on a drive). This is usually because the network file system does not provide complete or accurate information.

Universal Naming Convention (UNC)

Take Command also allows you to use UNC directory names when changing directories (see Directory Navigation 71) for more details).

OpenAFS

Take Command has built-in support for OpenAFS. The parser will recognize Linux-style AFS names (i.e., /afs/athena/user) and convert them to Windows-compatible names (i.e., \\afs\athena\user). (It will also check for custom AFS mount points, and use that name instead of afs.)

See http://www.openafs.org for more information on OpenAFS.

5.3.3 Directories & Subdirectories

A file system is a method of organizing all of the files on an entire disk or hard disk volume. Directories (or folders) are used to divide the files on a disk into logical groups that are easy to work with. Their purpose is similar to that of file drawers containing groups of hanging folders, hanging folders containing smaller folders, and so on. (The terms directory and folder are not synonymous but often used as such in common Windows terminology. For accuracy, we use **directory** throughout these help files unless other folder types are also specifically applicable.)

Every drive has a root or base directory, and many have one or more subdirectories. Subdirectories can also have subdirectories, extending in a branching tree structure from the root directory. The collection of all directories on a drive is often called the directory tree, and a portion of the tree is sometimes called a subtree. The terms directory and subdirectory are typically used interchangeably to mean a single subdirectory within this tree structure.

Subdirectory names follow the same naming rules as files in each operating system (see <u>File Names</u> [493]).

The drive and subdirectory portions of a file's name are called the file's path. For example, the file name *C:\DIR1\DIR2WYFILE.DAT* says to look for the file *MYFILE.DAT* in the subdirectory *DIR2* which

is part of the subdirectory *DIR1* which is on drive C. The path for *MYFILE.DAT* is *C:\DIR1\DIR2*. The backslashes between subdirectory names are required.

Under **TCC**, the path and filename can be up to 4095 characters, though most Windows applications (including **CMD.EXE** and **Explorer**) have trouble with path and filename lengths exceeding 260 characters. Shorter paths and names are advisable under Windows whenever feasible.

TCCmaintains both a current or default drive for your system as a whole, and a current or default directory for every drive in your system. Whenever a program tries to create or access a file without specifying the file's path, the operating system uses the current drive (if no other drive is specified) and the current directory (if no other directory path is specified).

The root directory is named using the drive letter and a single backslash. For example, **D:** refers to the root directory of drive *D:*. Using a drive letter with no directory name at all refers to the current directory on the specified drive. For example, E:JPSOFT.DOC refers to the file *JPSOFT.DOC* in the current directory on drive **E:**, whereas E:\JPSOFT.DOC refers to the file *JPSOFT.DOC* in the root directory on drive **E**:.

There are also two special subdirectory names that are useful in many situations: a single period by itself [.] means "the current default directory." Two periods together [..] means "the directory which contains the current default directory" (often referred to as the parent directory). These special names can be used wherever a full directory name can be used. *TCC* allows you to use additional periods to specify directories further "up" the tree (see Extended Parent Directory Names [118]).

Additional information about disk files and file systems is available under <u>Drives and Volumes 491</u>, <u>File Systems 491</u>, <u>File Names 493</u>, and <u>File Attributes 494</u>.

5.3.4 File Names

FAT File Names

Under the **FAT** file system, a filename consists of a base name of 1 to 8 characters plus an optional extension composed of a period plus 1 to 3 more characters. FAT filenames with an 8-character name and a 3-character extension are sometimes referred to as short filenames (SFNs) to distinguish them from long file names (LFNs).

You can use alphabetic and numeric characters plus the punctuation marks ! # \$ % & '() - @ ^ _ `{} and ~ in both the base name and the extension of a FAT filename. Because the exclamation point [!], percent sign [%], caret [^], at sign [@], parentheses [()], and back-quote [`] also have other meanings to *TCC*, it is best to avoid using them in filenames. It is also better to use only those characters found in <u>ASCII [51]</u>, because changing font and/or code page may change drastically how they are displayed.

FAT file names are always stored on the disk in upper case, and are displayed in upper or lower case depending on the options you select in *TCC*.

Long File Names

VFAT, FAT32 and **NTFS** allow using long file names with a maximum of 255 characters, including spaces and other characters that are not allowed in a FAT system file name, but excluding some punctuation characters which are allowed in FAT file names. See your operating system documentation for details on the characters allowed. If you use file names which contain semicolons [;], see <u>Wildcards</u> for details on avoiding problems with interpretation of those file names under *TCC*.

LFNs are stored and displayed exactly as you entered them, and are not automatically shifted to upper or lower case. For example, you could create a file called *MYFILE*, *myfile*, or *MyFile*, and each name would be stored in the directory just as you entered it. However, case is ignored when looking for

filenames, so you cannot have two files whose names differ only in case (*i.e.*, the three names given above would all refer to the same file). This behavior is sometimes described as "case-retentive but not case-sensitive" because the case information is retained, but does not affect access to the files. This is in contrast with Linux-style file systems, which are case sensitive, and permit **AA**, **Aa**, **aA**, and **aa** to be four different file names.

A file that has an LFN may have an additional, "FAT-compatible" name, which contains only those characters legal on a FAT volume, and which meets the 8-character name / 3-character extension limits. Programs which cannot handle long names (for example, DOS programs accessing an NTFS drive generally can access files by using their FAT-compatible names. This name is assigned at the time the LFN is created in the specific directory, and to make it unique, it depends on what other SFNs exist in that directory at that instance. Consequently, when copying the file to another directory by its LFN the SFN generated in the target directory may be different from the SFN in the source directory.

When specifying an LFN-compatible file name, which includes spaces or other characters that would either not be allowed in a FAT name, or that may have syntactical significance for *TCC*, you must place double quotes around the name in the command line. For example, suppose you have a file named *LET3* on a FAT volume, and you want to copy it to the *LETTERS* directory on drive F:, an LFN volume, and give it the name *Letter To Sara*. To do so, use either of these commands:

```
copy let3 f:\LETTERS\"Letter To Sara"
copy let3 "f:\LETTERS\Letter To Sara"
```

The LFN file systems do not explicitly define an "extension" for file names which are not FAT-compatible. However, by convention, all characters after the last period in the file name are treated as the extension. For example, the file name "Letter to Sara" has no extension, whereas the name "Letter to Sara" has the extension Sara.

Additional information about disk files and file systems is available under <u>Drives and Volumes [491]</u>, <u>File Systems [494]</u>, <u>Directories and Subdirectories [492]</u>, <u>File Attributes [494]</u>, and <u>Time Stamps [495]</u>.

5.3.5 File Attributes

Each file has attributes, each of which defines a single characteristic of the file that can be either set or reset. Most file processing commands allow you to select files for processing based on their attributes. The basic attributes Archive, Read only, Hidden, System, and Directory are present on all disk volumes. NTFS volumes support additional attributes: Encrypted, Compressed, Normal, Offline, Temporary, Not content-indexed, Sparse, and Junction / Symbolic Link / Reparse point. *Take Command* fully supports these extended attributes as a single characteristic of the file that can be either set or reset.

Archive - set by the operating system when the contents of the file are modified to indicate that it is a candidate to be archived, i.e., to be backed up. The attribute can be reset by any program to indicate that the file's contents have been archived. Most programs which can unset this attribute require that you use the explicit reset option, and default to retaining the status of this attribute. For example, the **TCC** command **COPY** requires the **/X** option to reset this attribute.

Read-only – if this attribute is set, the file can't be changed or erased accidentally. Most programs honor this attribute by default, which helps to protect important files from erasure and damage.

Either of the **Hidden** and **System** attributes, when set, prevent the file from appearing in directory listings and file searches, including those performed by file processing command of *Take Command*, unless explicitly requested.. This both protects such files from accidental modification, and also speeds up user tasks not explicitly intended to process them.

Directory – this attribute is set by the operating system when a subdirectory is created, e.g., by the MKDIR command. The attribute cannot be reset. The operating system restricts all accesses to a directory file to directory manipulation operations.

Volume label – a special attribute of at most one directory entry in the root directory of a disk drive. The entry can be created, modified, or deleted only through the Windows utility LABEL (or equivalent third-party software). *Take Command* does not directly modify the volume label or any of its attributes, and provide read access only through the <u>VOL</u> of command and the <u>@LABEL[]</u> variable function. All other commands ignore this directory entry.

Normal – this pseudo attribute is considered to be set if all other attributes (including the extended attributes available only on an NTFS volumes) are reset. It is not stored by the file system. When Take Command checks file attributes, it considers the Normal attribute as set if each of the other attributes is either reset, or unsupported by the combination of the file system and operating system.

The file attributes can also be accessed with the <u>ATTRIB</u> 1631 and <u>DIR</u> 1981 commands, and by the <u>@ATTRIB</u> 4001 and <u>@WATTRIB</u> 4661 variable functions.

Attributes can be set, reset, and viewed with the <u>ATTRIB</u> of command. The <u>DIR</u> of command also has options to view the attribute status of files, and to view information about normally invisible hidden and system files and directories.

5.3.6 File Time Stamps

Each file has one or more time stamps. They are used by the operating system to record when the file was created, last modified, or last accessed. Most *TCC* file processing commands allow you to select files for processing based on their time stamps.

- Write time is the date and time the file was last written, i.e., when its content was last modified, On FAT volumes this is the only timestamp. In all commands and functions this is the timestamp used unless you specify another. On FAT and VFAT volumes, the resolution is 2 s. NTFS volumes have a 100 nanosecond resolution for the file creation and last write. (UNIX and Linux systems use 1-s resolution.) When a file is copied using the COPY command, even across a network, its write time is not changed. However, different file systems record time with different resolution, so minor changes may occur.
- 2. Creation time is the date and time the current instance of the file was created.
- **3.** Access time is the date, and on NTFS volumes, the time, when the file was last accessed for either reading or writing.

Several *TCC* commands and functions let you specify which set of time and date stamps you want to view or work with on LFN volumes. These commands and functions use the letter

- **c** creation time stamp,
- w last write time stamp, and
- a last access time stamp.

Note that FAT32 and VFAT volumes store the date but not the time of the last access. On these drives the time of last access will always be 00:00.

Time Stamp Resolution

The resolution of time stamps as well as the range of time instances representable vary with file systems. The table below shows some of them.

file system	resolution	earliest time stamp	latest time stamp
FAT/VFAT	2 s	1980-01-01 00:00:00 <i>local</i>	2107-12-31 23:59:58 local
NTFS	100 ns	1601-01-01 00:00:01 <i>UTC</i>	

UNIX/Linux	1 s	1970-01-01 00:00:00 <i>UTC</i>	
------------	-----	--------------------------------	--

NTFS Timestamp Reports

These operating systems report timestamps in local time. However, conversion between UTC and local time is based on the difference between UTC and local time at the time of conversion, instead of that in effect when the file event occurred. Consequently, if daylight saving time is currently in effect, all file events around the year will be reported in DST. conversely, when DST is not in effect, all file events around the year will be reported in standard time. This method has the advantage that differences in event times can be calculated easily. However, the times reported will not be those when the event took place if the state DST at time of event is not the same as at the time of reporting.

The TOUCH 349 command can be used to modify the timestamps of files and directories.

Additional information about disk files and file systems is available under <u>Drives and Volumes [491]</u>, <u>File Systems [491]</u>, <u>Directories and Subdirectories [492]</u>, and File Names [493].

5.3.7 NTFS File Streams

The NTFS file system allows each file to contain multiple "streams" or sets of data. For example a compiler could use streams to store a program's source code, object code, and other data, or a word processing program could use them to store multiple versions of the same document.

Streams are specified by entering a stream name following the file name, for example:

```
myfile.doc:version1
myfile.doc:version2
```

You cannot use wildcards in stream names except when using filename completion 3681.

You can display stream names with the <u>DIR 1980</u> /: option. The file processing commands <u>COPY 182</u>], <u>DEL 190</u>], <u>FFIND 227</u>], <u>LIST 264</u>], <u>MOVE 274</u>] and <u>TYPE 354</u>] support file streams when the stream name is explicitly specified; see the individual commands for additional details. Other file-related commands, such as ATTRIB and TOUCH work with the file as a whole, and not with any particular stream or portion of the file data.

Variable functions which reference file contents, such as <u>@FILEOPEN</u> 428, <u>@LINE</u> 447, and <u>@LINES</u> 448 also accept stream names.

5.4 Regular Expression Syntax

Oniguruma Regular Expressions Version 5.9.0 2007/05/31

This section covers the Ruby regular expression syntax. For information on Perl regular expression syntax, see your Perl documentation or http://www.perl.com/doc/manual/html/pod/perlre.html.

1. Syntax elements

- escape (enable or disable meta character meaning)
 alternation
 group
 character class
- 2. Characters

```
\t
           horizontal tab (0x09)
           vertical tab (0x0B)
۱v
           newline
\n
                        (0x0A)
                       (0x0D)
\r
           return
\b
           back space
                         (80x0)
\f
           form feed
                        (0x0C)
\a
           bell
                     (0x07)
                        (0x1B)
           escape
\e
\nnn
           octal char
                            (encoded byte value)
                                (encoded byte value)
\xHH
           hexadecimal char
\x{7HHHHHHH} wide hexadecimal char (character code point value)
           control char
                             (character code point value)
\cx
                             (character code point value)
\C-x
           control char
                              (character code point value)
\M-x
           meta (x|0x80)
           meta control char
                               (character code point value)
\M-\C-x
(* \b is effective in character class [...] only)
```

3. Character types

```
any character (except newline)
\w
        word character
        Not Unicode:
           alphanumeric, "_" and multibyte char.
        Unicode:
           General_Category -- (Letter|Mark|Number|Connector_Punctuation)
       non word char
\W
\s
        whitespace char
        Not Unicode:
           \t, \n, \v, \f, \r, \x20
        Unicode:
           0009, 000A, 000B, 000C, 000D, 0085(NEL),
           General_Category -- Line_Separator
             -- Paragraph_Separator
             -- Space_Separator
\S
        non whitespace char
\d
        decimal digit char
        Unicode: General_Category -- Decimal_Number
\D
        non decimal digit char
        hexadecimal digit char [0-9a-fA-F]
\h
\H
        non hexadecimal digit char
Character Property
```

```
* \p{property-name}

* \p{^property-name} (negative)

* \P{property-name} (negative)

property-name:

+ works on all encodings
Alnum, Alpha, Blank, Cntrl, Digit, Graph, Lower, Print, Punct, Space, Upper, XDigit, Word, ASCII,
```

4. Quantifier

```
greedy
```

- ? 1 or 0 times
- * 0 or more times
- 1 or more times
- {n,m} at least n but not more than m times
- {n,} at least n times
- {,n} at least 0 but not more than n times ({0,n})
- {n} n times

reluctant

- ?? 1 or 0 times
- *? 0 or more times
- +? 1 or more times

{n,m}? at least n but not more than m times

- {n,}? at least n times
- $\{n\}$? at least 0 but not more than n times (== $\{0,n\}$?)

possessive (greedy and does not backtrack after repeated)

- ?+ 1 or 0 times
- *+ 0 or more times
- ++ 1 or more times

({n,m}+, {n,}+, {n}+ are possessive op. in ONIG_SYNTAX_JAVA only)

ex.
$$a^*+/===/(?>a^*)/$$

5. Anchors

- ^ beginning of the line
- \$ end of the line
- \b word boundary
- \B not word boundary
- VA beginning of string
- \Z end of string, or before newline at the end
- \z end of string
- \G matching start position (*)

6. Character class

```
^... negative class (lowest precedence operator)
```

x-y range from x to y

[...] set (character class in character class)

..&&.. intersection (low precedence at the next of ^)

```
ex. [a-w&&[^c-g]z] ==> ([a-w] AND ([^c-g] OR z)) ==> [abh-w]
```

* If you want to use '[', '-', ']' as a normal character in a character class, you should escape these characters by '\'.

POSIX bracket ([:xxxxx:], negate [:^xxxxx:])

Not Unicode Case:

alnum alphabet or digit char

alpha alphabet

ascii code value: [0 - 127]

blank \t, \x20

cntrl

digit0-9

graph include all of multibyte encoded characters

lower

print include all of multibyte encoded characters

punct

space \t, \n, \v, \f, \r, \x20

upper

word alphanumeric, "_" and multibyte characters

xdigit 0-9, a-f, A-F

Unicode Case:

alnum Letter | Mark | Decimal_Number

alpha Letter | Mark ascii 0000 - 007F

blank Space Separator | 0009

cntrl Control | Format | Unassigned | Private_Use | Surrogate

digit Decimal_Number

graph [[:^space:]] && ^Control && ^Unassigned && ^Surrogate

lower Lowercase_Letter print [[:graph:]] | [[:space:]]

punct Connector_Punctuation | Dash_Punctuation | Close_Punctuation | Final_Punctuation | Initial_Punctuation | Open_Punctuation

space Space_Separator | Line_Separator | Paragraph_Separator | 0009 | 000A |

word Letter | Mark | Decimal_Number | Connector_Punctuation xdigit 0030 - 0039 | 0041 - 0046 | 0061 - 0066 (0-9, a-f, A-F)

7. Extended groups

(?#...) comment

(?imx-imx) option on/off

i: ignore case

m: multi-line (dot(.) match newline)

x: extended form

(?imx-imx:subexp) option on/off for subexp

(?:subexp) not captured group captured group

(?=subexp) look-ahead

(?!subexp) negative look-ahead

(?<=subexp) look-behind

(?<!subexp) negative look-behind

Subexp of look-behind must be fixed character length. But different

character length is allowed in top level alternatives only. ex. (?<=a|bc) is OK. (?<=aaa(?:b|cd)) is not allowed.

In negative-look-behind, captured group isn't allowed, but shy group(?:) is

allowed.

(?>subexp) atomic group

don't backtrack in subexp.

(?<name>subexp) define named group

(All characters of the name must be a word character. And first character

must not be a digit or upper case)

Not only a name but a number is assigned like a captured group.

Assigning the same name as two or more subexps is allowed. In this case,

a subexp call can not be performed although the back reference is

possible.

8. Back reference

\n back reference by group number (n >= 1)

\k<name> back reference by group name back reference by group name

In the back reference by the multiplex definition name, a subexp with a large number is referred to preferentially. (When not matched, a group of the small number is referred to.)

* Back reference by group number is forbidden if named group is defined in the pattern and ONIG OPTION CAPTURE GROUP is not set.

Back reference with nest level

\k<name+n> n: 0, 1, 2, ... \k<name-n> n: 0, 1, 2, ... n: 0, 1, 2, ...

Destinate relative nest level from back reference position.

ex 1.

 $\A(?<a>|.|(?:(?.)\g<a>k<b+0>))\z/.match("reer")$

ex 2.

```
 \begin{split} r &= Regexp.compile(<<'\__REGEXP\__'.strip, Regexp::EXTENDED) \\ (?<element> \g<stag> \g<content>^* \g<etag>) \{0\} \\ (?<stag> < \g<name> \s^* >) \{0\} \\ (?<name> [a-zA-Z_:]+) \{0\} \\ (?<content> [^<&]+ (\g<element> | [^<&]+)^*) \{0\} \\ (?<etag> </ \k<name+1> >) \{0\} \\ \g<element> \\ \_REGEXP\_ \\ p r.match('<foo>f<bar>bbb</bar>f</foo>').captures \\ \end{split}
```

9. Subexp call ("Tanaka Akira special")

```
\g<name> call by group name
\g'name' call by group name
\g<n> call by group number (n >= 1)
\g'n' call by group number (n >= 1)

* left-most recursive call is not allowed.
ex. (?<name>a|\g<name>b) => error
(?<name>a|b\g<name>c) => OK

* Call by group number is forbidden if named group is defined in the pattern and
```

ONIG OPTION CAPTURE GROUP is not set.

- * If the option status of called group is different from calling position then the group's option is effective.
- ex. (?-i:\g<name>)(?i:(?<name>a)){0} match to "A"

10. Captured group

where

Behavior of the no-named group (...) changes with the following conditions. (But named group is not changed.)

```
case 1. /.../ (named group is not used, no option)

(...) is treated as a captured group.

case 2. /.../g (named group is not used, 'g' option)

(...) is treated as a no-captured group (?:...).

case 3. /..(?<name>..)../ (named group is used, no option)

(...) is treated as a no-captured group (?:...).

numbered-backref/call is not allowed.

case 4. /..(?<name>..)../G (named group is used, 'G' option)

(...) is treated as a captured group.

numbered-backref/call is allowed.
```

g: ONIG_OPTION_DONT_CAPTURE_GROUP G: ONIG_OPTION_CAPTURE_GROUP

A-1. Syntax dependent options

+ RUBY

(?m): dot(.) match newline

+ PERL and JAVA

(?s): dot(.) match newline

(?m): ^ match after newline, \$ match before newline

A-2. Original extensions

+ hexadecimal digit char type \h, \H

+ named group (?<name>...)

+ named backref \k<name>

+ subexp call \g<name>, \g<group-num>

A-3. Missing features compared with perl 5.8.0

- + \N{name}
- + \I,\u,\L,\U, \X, \C
- + (?{code})
- + (??{code})
- + (?(condition)yes-pat|no-pat)
- * \Q...\E

This is effective on PERL and JAVA.

5.5 XML in Take Command

TCC provides the ability to open, parse and close XML documents through the use of a subset of the XPath language. The syntax of the language is explained more clearly at the W3C site: http://www.w3schools.com/xpath/xpath_syntax.asp. We support a limited subset of the language explained below. Any functions of the language beyond what are listed below are unsupported, but may work.

The most common use of XML in **TCC** is to parse an XML formatted data file to extract elements for further processing in Take Command.

There are four **TCC** functions that provide XML support –

 @XMLOPEN - open an XML file for use by @XMLXPATH and/or @XMLNODES. The syntax is:

@XMLOPEN[filename]

Example: set a=%@XMLOPEN(bookstore.xls)

@XMLCLOSE - close an XML file previously opened by @XMLOPEN. The syntax is:

@XMLCLOSE[]

Example: set a=%@XMLCLOSE()

 @XMLNODES - return the number of nodes (children) for the specified path in an XML file. The syntax is:

```
@XMLNODES[["filename"],path]
```

Example: set a=%@XMLNODES["bookstore.xls",/bookstore] – returns the number of books in the bookstore file (see example file below)

If you don't specify a filename (which *must* be in double quotes. @XMLNODES will use the XML file previously opened by @XMLOPEN.

4. **@XMLXPATH** - XML XPath query. (See the XML XPath docs for details on XPath syntax.) The syntax is:

```
@XMLXPATH[["filename"],path]
```

Example: echo %@XMLXPATH[/bookstore/book] – lists all the sub-element values for the first book (see example file below)

If you don't specify a filename (which *must* be in double quotes), @XMLXPATH will use the XML file previously opened by @XMLOPEN.

Typical Use of The XML Functions

All discussions in this section refer to the following XML data file.

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<bookstore>
       <book>
          <title lang="jap">Harry Potter</title>
          <price>29.99</price>
       </book>
       <book>
          <title lang="eng">Learning XML</title>
          <price>39.95</price>
       </book>
       <book>
          <title lang="ger">Day Watch</title>
          <price>14.99</price>
       </book>
       <book>
          <title lang="eng">Winston Churchill: An Autobiography</title>
          <price>49.99</price>
       </book>
</bookstore>
```

Each tag in this file is referred to as a node (e.g., bookstore, book, title). The identifiers within a tag are often referred to as an attribute (e.g., lang).

Typically you will use the four commands in the following order:

- 1. Open the file with @XMLOPEN
- 2. Get the number of child nodes (records) to process with @XMLNODES
- 3. Set up a loop from one to the number of records to process the records with @XMLXPATH
- 4. Close the file with @XMLCLOSE

Below is a simple example of batch processing (without error handling J):

This example:

- Opens the bookstore data file,
- Evaluates the number of books in the bookstore as 4(since the only child of bookstore is books),
- · Gets the title and price for each book
- Prints each title and price out
- · Closes the data file.

XPath offers a large number of processing options in addition to the ones above. We have not tested their syntax. If you wish to test additional functionality and report back to us, we will add that information to our documentation.

5.6 Miscellaneous Reference Information

- Executable Files and File Searches 504
- Popup Windows 507
- Windows System Errors 507
- ASCII and Key Names 515
- ANSI X3.64 Command Reference 516
- Colors and Color Names 518

5.6.1 Executable Files & File Searches

When **TCC** can't find a matching internal command name, it tries to find an executable file whose name matches the command name. (Executable files are typically those with a .COM or .EXE extension.)

If **TCC** cannot find an executable program to run, it next looks for a matching batch file had name. **TCC** looks first for a .BTM file, then for a .CMD file, then for a .BAT file, and finally for a .REX, .REXX, .PL, or .RB file (if REXX, Perl, and/or Ruby are enabled).

You can change the list of extensions that are considered "executable", and the order in which they are searched, with the PATHEXT see environment variable, and the related PathExt onfiguration option. PATHEXT is supported for compatibility reasons but should not generally be used as a substitute for executable extensions of the path of the

Note: If the search for an external program or batch file fails, *TCC* checks to see if the command name matches the name of a file with an executable extension of the extension of the extension is found, *TCC* runs the program specified when the association was defined. If no executable extension is found, *TCC* will look for a direct association for the extension in the registry and insert the associated string (usually the name of an application) at the beginning of the command line, then call the Windows CreateProcess API to execute that command. If the CreateProcess call fails, or if no association was found in the registry, *TCC* calls the ShellExec Windows API. *TCC* has no control over

which action the above Windows APIs will take when presented with a file name. If you are concerned about what Windows might do with an "unknown" extension, create a specific executable extension.

TCC first performs this search (for an executable program, a batch file, or a file with an executable extension) in the current directory. If that search fails, they repeat the search in every directory in your search path.

The search path is a list of directories that *TCC* (and some applications) search for executable files. For example, if you wanted *TCC* to search the root directory of the C: drive, the \WINUTIL subdirectory on the C: drive, and the \UTIL directory on the D: drive for executable files, your search path would look like this:

```
PATH=C:\;C:\WINUTIL;D:\UTIL
```

The directory names in the search path are separated by semicolons.

You can create or view the search path with the PATH command. You can use the ESET command to edit the path. Many programs also use the search path to find their own files. The search path is stored in the environment with the name PATH.

Take Command also searches the \text{\text{WINDOWS\SYSTEM32}} directory followed by the \text{\text{\text{WINDOWS}}} directory. (The actual directory names may be different on your system. \text{\text{TCC}} will determine the correct names for the "Windows" and "Windows System" directories and use them.) This part of the search procedure conforms with the traditional search sequences used under each Windows operating system.

Note: If the file is not found on the PATH, *TCC* then checks for a corresponding **App Paths** entry in the Windows registry. **App Paths** entries are created by some applications during the installation process.

Remember, *TCC* always looks for an executable file (or a file with an executable extension or Windows file association) in the current subdirectory, then in the Windows directories if appropriate (see above), then in each directory in the search path, and then in the **App Paths** area of the registry. (You can change the search order so the current directory is not searched first; see the PATH 2861 command for details.)

If you include an extension as part of the command name, **TCC** only searches for a file with that extension. Similarly, if you include a path as part of the command name, **TCC** will look only in the directory you specified, and ignore the usual search of the current directory and the PATH.

If your command name includes a path, the elements must be separated with backslashes (*e.g.* **c:\wp\wp**). If you are accustomed to Linux syntax where forward slashes are used in command paths, and want **TCC** to recognize this approach, you can set the Unix/Linux Paths 47 configuration option.

Once the file is found, **TCC** executes it based on its extension. .EXE and .COM files are executed by passing their names to the operating system. .BTM, .BAT, and (if applicable) .CMD files are executed by **TCC**, which reads each line in the file as a new command. Files with executable extensions are executed by starting the associated application, and passing the name of the file on the command line.

If you specify a file name including extension, and the file exists in the current directory (or you specify a path), but the file does not have an extension known to **TCC** (.EXE, .COM, .BTM, .BAT, .CMD, or an executable extension), then the file name will be passed to Windows to check for file associations defined in the Windows registry. This allows you to execute any file whose extension is known to Windows, simply by typing its name. For example, if you have no executable extension defined for .PSP files, but this is an extension known to Windows, at the prompt you can simply enter a command like this:

[c:\graphics] image1.psp

and *Take Command* will request that Windows start the application for you. See Windows File Associations for additional details on how to control Windows file associations in *TCC*.

The following table sums up the possible search options (the term "standard search" refers to the search of the current directory, the Windows directories, and each directory in the search path):

Command	TCC Search Sequence
WP	Search for any executable file whose base name is WP.
WP.EXE	Search for WP.EXE; will not find files with other extensions.
C:\WP\WP	Looks in the C:\WP directory for any executable file whose base name is WP.
	Does not check the standard search directories.
C:\WP\WP.EXE	Looks only for the file C:\WP\WP.EXE.
LAB.DOC	Search for LAB.DOC, if .DOC is defined as an executable extension. Runs
	the associated application if the file is found. If .DOC is not an executable
	extension, passes the name to Windows to check for a Windows file
	association.
C:\LI\LAB.DOC	Looks only for the file C:\L/\LAB.DOC, and only if .DOC is defined as an
	executable extension. Runs the associated application if the file is found. If
	.DOC is not an executable extension, passes the name to Windows to check
	for a Windows file association.

If **TCC** cannot find an executable file, batch program, or a file with an executable extension or Windows file association in the current directory, a directory in the search path, or the directory you specified in the command, it then looks for an alias called **UNKNOWN_CMD** (see the <u>ALIAS [154]</u> command for details). If you have defined an alias with that name, it is executed (this allows you to control error handling for unknown commands). Otherwise, **TCC** displays an "Unknown command" error message and waits for your next instruction.

See also: the WHICH 361 command.

5.6.1.1 Windows File Associations

Windows includes the ability to associate file extensions with specific applications; this feature is sometimes called "file associations". For example, a graphics program might be associated with files with a *.JPG* extension, while Notepad could be associated with files with a *.TXT* extension.

When you attempt to start an application from the command line or a batch file, *TCC* first searches for an external program file with a standard extension (.COM, .EXE, etc.). It then checks executable extensions. If all of these tests fail, *TCC* passes the command name to Windows to see if Windows can find an association for it.

TCC offers two commands which provide control over file associations. Both should be used with caution to avoid creating errors in the registry or damaging existing file types. The ASSOC 1621 command modifies or displays the associations between extensions and file types in the Windows registry. The FTYPE 2411 command modifies or displays the default command used to "open" a file of a specified type.

Executable extensions defined in *TCC* always take precedence over file associations defined in Windows. For example, if you associate the .*TXT* extension with your own editor using a *TCC* executable extension, and Windows has associated .*TXT* with Notepad, your setting will have priority, and the association with Notepad will be ignored when you invoke a .*TXT* file from within *TCC*.

See also: START 331, ASSOC 162, FTYPE 241, Executable Extensions 91, Executable Files and File Searches 504.

5.6.2 Popup Windows

Several features of *TCC* display popup windows. A popup window may be used to display filenames, recently-executed commands, recently-used directories, the results of an <u>extended directory search</u> 73, or a list created by the <u>SELECT</u> 312 command or the <u>@SELECT</u> 458 internal function.

Popup windows always display a list of choices and a cursor bar. You can move the cursor bar inside the window until you find the choice that you wish to make, then press the **Enter** key to select that item.

Navigation inside any popup window follows the conventions described below. Additional information on each specific type of popup window is provided where that window is discussed in detail.

You can control the position and size with the <u>Pop-Up Windows [49]</u> configuration options. A few popup windows (e.g., the extended directory search window) have separate choices in the configuration dialogs. You can also change the keys used in popup windows with key mapping directives [28].

Once a window is open, you can use these navigation keys to find the selection you wish to make:

Up Arrow	Move the selection bar up one line
Down Arrow	Move the selection bar down one line
Left Arrow	Scroll the display left 1 column, if it is a scrolling display (i.e. if it has a
	horizontal scrollbar)
Right Arrow	Scroll the display right 1 column, if it is a scrolling display (i.e. if it has a
	horizontal scrollbar)
PgUp	Scroll the display up one page
PgDn	Scroll the display down one page
Home	Go to the beginning of the list
End	Go to the end of the list
Esc 31	Close the window without making a selection
Enter 41	Select the current item and close the window
Ctrl-E 40	Edit the current selection
Ctrl-D 40	Delete the current selection

Note: The keystrokes shown above are the defaults values. See Key Mapping Directives on how to assign different keystrokes.

In addition to scrolling through a popup window, you can search the list using character matching. If you press a character, the cursor bar will move to the next entry that begins with that character. If you type multiple characters, the cursor will move to the entry that begins with the search string entered to that point (you can enter a search string up to 32 characters long). If no entry matches the character or string that you have typed, **TCC** beeps and does not move the cursor bar. To reset the search string, press Backspace.

5.6.3 Windows System Errors

This list shows a typical set of error and system messages returned by Windows. The numbers are what might be returned in internal variable <u>SYSERR</u> 392, and the corresponding text is that provided by Microsoft.

Code Error Message

- The operation completed successfully.
- 1 Incorrect function.
- 2 The system cannot find the file specified.
- 3 The system cannot find the path specified.
- 4 The system cannot open the file.
- 5 Access is denied.

- 6 The handle is invalid.
- 7 The storage control blocks were destroyed.
- 8 Not enough storage is available to process this command.
- 9 The storage control block address is invalid.
- 10 The environment is incorrect.
- An attempt was made to load a program with an incorrect format.
- 12 The access code is invalid.
- 13 The data is invalid.
- 14 Not enough storage is available to complete this operation.
- 15 The system cannot find the drive specified.
- 16 The directory cannot be removed.
- 17 The system cannot move the file to a different disk drive.
- 18 There are no more files.
- 19 The media is write protected.
- 20 The system cannot find the device specified.
- 21 The device is not ready.
- 22 The device does not recognize the command.
- 23 Data error (cyclic redundancy check).
- 24 The program issued a command but the command length is incorrect.
- 25 The drive cannot locate a specific area or track on the disk.
- 26 The specified disk or diskette cannot be accessed.
- 27 The drive cannot find the sector requested.
- 28 The printer is out of paper.
- 29 The system cannot write to the specified device.
- 30 The system cannot read from the specified device.
- 31 A device attached to the system is not functioning.
- 32 The process cannot access the file because it is being used by another process.
- 33 The process cannot access the file because another process has locked a portion of the file.
- 36 Too many files opened for sharing.
- 38 Reached the end of the file.
- 39 The disk is full.
- 50 The network request is not supported.
- 51 The remote computer is not available.
- 52 A duplicate name exists on the network.
- 53 The network path was not found.
- 54 The network is busy.
- 55 The specified network resource or device is no longer available.
- 56 The network BIOS command limit has been reached.
- 57 A network adapter hardware error occurred.
- 58 The specified server cannot perform the requested operation.
- 59 An unexpected network error occurred.
- The remote adapter is not compatible.
- 61 The printer queue is full.
- Space to store the file waiting to be printed is not available on the server.
- 63 Your file waiting to be printed was deleted.
- The specified network name is no longer available.
- 65 Network access is denied.
- 66 The network resource type is not correct.
- 67 The network name cannot be found.
- 68 The name limit for the local computer network adapter card was exceeded.
- 69 The network BIOS session limit was exceeded.
- 70 The remote server has been paused or is in the process of being started.
- No more connections can be made to this remote computer at this time because there are already as many connections as the computer can accept.
- 72 The specified printer or disk device has been paused.
- 80 The file exists.
- 82 The directory or file cannot be created.
- 83 Fail on INT 24.

- 84 Storage to process this request is not available.
- 85 The local device name is already in use.
- 86 The specified network password is not correct.
- 87 The parameter is incorrect.
- 88 A write fault occurred on the network.
- 89 The system cannot start another process at this time.
- 100 Cannot create another system semaphore.
- 101 The exclusive semaphore is owned by another process.
- 102 The semaphore is set and cannot be closed.
- 103 The semaphore cannot be set again.
- 104 Cannot request exclusive semaphores at interrupt time.
- 105 The previous ownership of this semaphore has ended.
- 107 The program stopped because an alternate diskette was not inserted.
- 108 The disk is in use or locked by another process.
- 109 The pipe has been ended.
- 110 The system cannot open the device or file specified.
- 111 The file name is too long.
- 112 There is not enough space on the disk.
- 113 No more internal file identifiers available.
- 114 The target internal file identifier is incorrect.
- 117 The IOCTL call made by the application program is not correct.
- 118 The verify-on-write switch parameter value is not correct.
- 119 The system does not support the command requested.
- 120 This function is not supported on this system.
- 121 The semaphore timeout period has expired.
- 122 The data area passed to a system call is too small.
- 123 The filename, directory name, or volume label syntax is incorrect.
- 124 The system call level is not correct.
- 125 The disk has no volume label.
- 126 The specified module could not be found.
- 127 The specified procedure could not be found.
- 128 There are no child processes to wait for.
- 130 Attempt to use a file handle to an open disk partition for an operation other than raw disk I/O.
- 131 An attempt was made to move the file pointer before the beginning of the file.
- 132 The file pointer cannot be set on the specified device or file.
- 133 A JOIN or SUBST command cannot be used for a drive that contains previously joined drives.
- 134 An attempt was made to use a JOIN or SUBST command on a drive that has already been joined.
- 135 An attempt was made to use a JOIN or SUBST command on a drive that has already been substituted.
- 136 The system tried to delete the JOIN of a drive that is not joined.
- 137 The system tried to delete the substitution of a drive that is not substituted.
- 138 The system tried to join a drive to a directory on a joined drive.
- 139 The system tried to substitute a drive to a directory on a substituted drive.
- 140 The system tried to join a drive to a directory on a substituted drive.
- 141 The system tried to SUBST a drive to a directory on a joined drive.
- 142 The system cannot perform a JOIN or SUBST at this time.
- 143 The system cannot join or substitute a drive to or for a directory on the same drive.
- 144 The directory is not a subdirectory of the root directory.
- 145 The directory is not empty.
- 146 The path specified is being used in a substitute.
- 147 Not enough resources are available to process this command.
- 148 The path specified cannot be used at this time.
- 149 An attempt was made to join or substitute a drive for which a directory on the drive is the target of a previous substitute.
- 150 System trace information was not specified in your CONFIG.SYS file, or tracing is disallowed.
- 151 The number of specified semaphore events for DosMuxSemWait is not correct.
- 152 DosMuxSemWait did not execute; too many semaphores are already set.

- 153 The DosMuxSemWait list is not correct.
- 154 The volume label you entered exceeds the label character limit of the target file system.
- 155 Cannot create another thread.
- 156 The recipient process has refused the signal.
- 157 The segment is already discarded and cannot be locked.
- 158 The segment is already unlocked.
- 159 The address for the thread ID is not correct.
- 160 The argument string passed to DosExecPgm is not correct.
- 161 The specified path is invalid.
- 162 A signal is already pending.
- 164 No more threads can be created in the system.
- 167 Unable to lock a region of a file.
- 170 The requested resource is in use.
- 173 A lock request was not outstanding for the supplied cancel region.
- 174 The file system does not support atomic changes to the lock type.
- 180 The system detected a segment number that was not correct.
- 183 Cannot create a file when that file already exists.
- 186 The flag passed is not correct.
- 187 The specified system semaphore name was not found.
- 196 The operating system cannot run this application program.
- 197 The operating system is not presently configured to run this application.
- 199 The operating system cannot run this application program.
- 200 The code segment cannot be greater than or equal to 64K.
- 203 The system could not find the environment option that was entered.
- 205 No process in the command subtree has a signal handler.
- 206 The filename or extension is too long.
- 207 The ring 2 stack is in use.
- 208 The global filename characters, * or ?, are entered incorrectly or too many global filename characters are specified.
- 209 The signal being posted is not correct.
- 210 The signal handler cannot be set.
- 212 The segment is locked and cannot be reallocated.
- 214 Too many dynamic-link modules are attached to this program or dynamic-link module.
- 215 Cannot nest calls to LoadModule.
- 230 The pipe state is invalid.
- 231 All pipe instances are busy.
- 232 The pipe is being closed.
- 233 No process is on the other end of the pipe.
- 234 More data is available.
- 240 The session was canceled.
- 254 The specified extended attribute name was invalid.
- 255 The extended attributes are inconsistent.

CAUTION: This is a <u>large</u> topic (>650 KB). The remainder of this list has been omitted in the PDF version of this file. Consider viewing the copy in your local help file (tcmd.chm) instead!

d.

5.7 ASCII and Key Names

For ASCII codes and key names see:

- ▶ ASCII Table 511
- ▶ Keys & Key Names 515

The remainder of this section gives a explanation of the ASCII character sets and key names. For more information on **TCC**'s ANSI X3.64 string support see ANSI X3.64 Commands Reference 516. If you are troubleshooting a keyboard or character display problem, be sure to read all of the explanation below before referring to the tables.

The translation of a key you type on the keyboard to a displayed character on the screen depends on several related aspects of character handling. A complete discussion of these topics is well beyond the scope of this document. However, a basic picture of the steps in the keystroke and character translation process will help you understand how characters are processed in your system, and why they occasionally may not come out the way you expect.

Internally, computers use numbers to represent the keys you press and the characters displayed on the screen. To display the text that you type, your computer and operating system require five pieces of information:

- 1. The numeric key code for the physical key you pressed (determined by your keyboard hardware);
- 2. The specific character that key code represents based on your current keyboard layout or country setting;
- 3. The character set currently in use on your system (see below);
- 4. The international code page in use for that character set; and
- 5. The display font used to display the character.

If the key codes produced by your keyboard, the code page, and the font you choose are not fully compatible, the characters displayed on the screen will not match what you type. The differences are likely to appear in line-drawing characters, "international" (non-English) characters, and special symbols, but not in commonly-used U.S. English alphabetic, numeric, or punctuation characters.

The control codes can be entered on most keyboards by pressing the **Ctrl** key plus another character, or by pressing the special keys **Tab**, **Enter**, **Backspace**, and **Esc**.

See your operating system documentation for more information about character sets, code pages, and country and language support. Refer to your operating system and/or font documentation for details on the full character set available in any particular font.

The tables in this section are based on U.S. English conventions. Your system may differ if it is configured for a different country or language. See your operating system documentation for more information about country and language support.

Note: You may also be able to use the **Alt + keypad** approach to generate ASCII values. See "Command Line Editing 104" for additional information.

5.7.1 ASCII Tables

These tables show the 128-character ASCII set for U.S. English systems. Most of the characters in code range 32..126 (the only codes for which ASCII specifies displayable symbols) will be the same on non-U.S. systems. The symbols associated with all other codes vary from font to font, as well as from country to country.

For more details on ASCII, character sets, and key codes, see the general information topic on ASCII, Key Codes, and ANSI X3.64 Commands 510.

- Control Characters 0 31, 127 512
- Printing Characters 32 47 512
- Printing Characters 48 63 513

- Printing Characters 64 79 513
- Printing Characters 80 95 514
- Printing Characters 96 111 514
- Printing Characters 112 126 514

Control Characters 0 - 31, 127

ASCII (Dec)	ASCII (Hex)	Ctrl + Key	Acronym	Name
0	00	@	NUL	null
1	01	Α	SOH	start of header
2	02	В	STX	start text
3	03	С	ETX	end text
4	04	D	EOT	end of transmission
5	05	Е	ENQ	enquiry
6	06	F	ACK	acknowledge
7	07	G	BEL	bell
8	08	Н	BS	backspace
9	09	ı	HT	horizontal tab
10	0A	J	LF	linefeed
11	0B	K	VT	vertical tab
12	0C	L	FF	form feed
13	0D	М	CR	carriage return
14	0E	N	SO	shift out
15	0F	0	SI	shift in
16	10	Р	DLE	data link escape
17	11	Q	DC1	device control 1
18	12	R	DC2	device control 2
19	13	S	DC3	device control 3
20	14	Т	DC4	device control 4
21	15	U	NAK	negative acknowledge
21	16	V	SYN	synchronize
23	17	W	ETB	end text block
24	18	Х	CAN	cancel
25	19	Υ	EM	end of medium
26	1A	Z	SUB	substitute
27	1B	[ESC	escape
28	1C	\	FS	field separator
29	1D]	GR	group separator
30	1E	۸	RS	record separator
31	1F	_	US	unit separator
127	7F	n/a	DEL	delete

Printing Characters 32 - 47

Dec	Hex	Char	Special character name
032	20	Space	space
033	21	!	exclamation mark

034	22	"	quote mark
035	23	#	number sign
036	24	\$	dollar (currency) sign
037	25	%	percent mark
038	26	&	ampersand
039	27	'	apostrophe
040	28	(left parenthesis
041	29)	right parenthesis
042	2A	*	asterisk
043	2B	+	plus sign
044	2C	,	comma
045	2D	-	hyphen (minus sign)
046	2E		period
047	2F	/	slash

Printing Characters 48 - 63

Dec	Hex	Char	Special character name
048	30	0	
049	31	1	
050	32	2	
051	33	3	
052	34	4	
053	35	5	
054	36	6	
055	37	7	
056	38	8	
057	39	9	
058	3A	:	colon
059	3B	;	semicolon
060	3C	<	less than sign
061	3D	=	equal sign
062	3E	>	greater than sign
063	3F	?	question mark

Printing Characters 64 - 79

Dec	Hex	Char	Special character name
064	40	@	at sign
065	41	Α	
066	42	В	
067	43	С	
068	44	D	
069	45	E	
070	46	F	
071	47	G	
072	48	Н	
073	49	I	

074 075 076 077	4A	J	
075	4B	K	
076	4C	L	
077	4D	М	
078	4E	Ν	
079	4F	0	

Printing Characters 80 - 95

Dec	Hex	Char	Special character name
080	50	Р	
081	51	Q	
082	52	R	
083	53	S	
084	54	Т	
085	55	U	
086	56	V	
087	57	W	
088	58	Χ	
089	59	Υ	
090	5A	Z	
091	5B	[left bracket
092	5C	\	backslash
093	5D]	right bracket
094	5E	^	caret
095	5F		underscore

Printing Characters 96 - 111

Dec	Hex	Char	Special character name
096	60	,	accent grave (back tick or back quote)
097	61	а	
098	62	b	
099	63	С	
100	64	d	
101	65	е	
102	66	f	
103	67	g	
104	68	h	
105	69	i	
106	6A	j	
106	6B	k	
108	6C	I	
109	6D	m	
110	6E	n	
111	6F	0	

Printing Characters 112 - 126

Dec	Hex	Char	Special character name
112	70	р	
113	71	q	
114	72	r	
115	73	s	
116	74	t	
117	75	u	
118	76	V	
119	77	w	
120	78	х	
121	79	у	
122	7A	Z	
123	7B	{	left brace
124	7C		vertical bar
125	7D	}	right brace
126	7E	~	tilde

5.7.2 Key Names

Key names are used by *Take Command* in tab toolbar 62 buttons, and in *TCC* to define keystroke aliases 154, in key mapping directives 28, and in the <u>KEYSTACK</u> 262 command. The format of a key name is the same in all four cases:

[Prefix-]Keyname

The valid prefix and keyname combinations are shown in the table below. Names of keys must be spelled exactly as shown, except for case. Note that you cannot specify a punctuation key.

Prefix	Valid for keynames
none	A-Z, 0-9, F1-F12, Tab, Bksp, Enter, Up, Down, Left, Right, PgUp, PgDn, Home, End, Ins,
	Del, Esc
Alt-	A-Z, 0-9, F1-F12, Bksp, and the non-alphanumeric keys `-=[]\;',./
Ctrl-	A-Z, F1-F12, Tab, Bksp, Enter, Up, Down, Left, Right, PgUp, PgDn, Home, End, Ins, Del
Shift-	F1-F12, Tab

The prefix and key name must be separated by a hyphen (-). For example:

Alt-F10 ctrl-bksp

Some keys are intercepted by Windows and are not passed on to *Take Command*. For example, Alt-Tab, Alt-Esc and Ctrl-Esc typically pop up a task list, or are used in switching among multiple tasks. Alt-space brings down a menu to control window size and position, etc. Keys which are intercepted by the operating system (including menu accelerators, i.e. Alt plus another key) generally cannot be assigned to aliases 154 or with key mapping directives 28, because *Take Command* never receives these keystrokes. However, KEYSTACK 262 can send them to Windows (though not to another application).

The above comments are based on common 101/102-key US-style keyboards. Some key combinations might not be available on some keyboards.

5.8 ANSI X3.64 Command Reference

TCC includes support for ANSI Std X3.64, allowing you to manipulate the cursor, screen color, and other display attributes through sequences of special characters embedded in the text displayed on the screen. These sequences are called "ANSI commands". (For a general description of this feature, see ANSI Support 101).) **TCC** cannot provide ANSI X3.64 support to external applications.

TCC supports most common ANSI X3.64 screen commands, but does not provide the complete set of options supported by some operating system's ANSI X3.64 drivers (for example, **TCC** does not support ANSI X3.64 key substitutions; that functionality is already provided with key aliases 128). This section is a quick reference to the ANSI X3.64 commands supported by **TCC**.

ANSI X3.64 support within *TCC* can be enabled or disabled with the <u>ANSI Colors</u> 49 configuration option, or the <u>SETDOS</u> 323 /A command. You can test whether ANSI X3.64 support is enabled with the <u>ANSI 382</u> internal variable.

An ANSI X3.64 command string consists of three parts:

<ESC>
The ASCII character ESC, followed by a left bracket. These two characters must

be present in all ANSI X3.64 strings.

parameters Optional parameters for the command, usually numeric. If there are multiple

parameters, they are separated by semicolons.

command A single-letter command. (Case sensitive!)

For example, to position the cursor to row 7, column 12 the ANSI X3.64 command is:

<ESC>[7;12H

The parameters part of this command is "7;12" and the command part is "H".

To transmit ANSI X3.64 commands to the screen you can use the ECHO 217 command. The ESC character can be generated by inserting it into the string directly (if you are putting the string in a batch file and your editor will insert such a character), or by using the internal "escape" character | 124 (defaults: caret, [^]) followed by a lower-case "e".

For example, the sequence shown above could be transmitted from a batch file with either of these commands (the first uses an ESC character directly, represented below by "ESC"; the second uses ^e):

```
echo <ESC>[7;12H
echo ^e[7;12H
```

You can also include ANSI X3.64 commands in your prompt [297], using \$e to transmit the <ESC> character.

Commands

The internal **TCC** ANSI X3.64 interpreter supports the subset of X3.64 commands below. Variable parameters are shown in lower-case italics, e.g., **row** and **attr**, and must be replaced with the appropriate decimal numeric value when using the commands. The default value for **row**, **rows**, **col**, and **cols** is 1.

<esc>[rowsA</esc>	Cursor up by rows			
<esc>[rowsB</esc>	Cursor down by <i>rows</i>			
<esc>[co/sC</esc>	Cursor right by cols			
<esc>[co/sD</esc>	Cursor left by cols			

<esc>[row;colH</esc>	Set cursor position (top left is row 1, column 1)
<esc>[2J</esc>	Clear whole screen
<esc>[K</esc>	Clear from cursor to end of line
<esc>[row;coff</esc>	Set cursor position, same as "H" command
<esc>[attr1;attr2;m</esc>	Set display attributes; see table of attribute values below
<esc>[s</esc>	Save cursor position (may not be nested)
<esc>[u</esc>	Restore saved cursor position

Display Attributes

The attribute values used for the **m** command are:

- 0 Restore all attributes to default
- **1** Bright (high intensity) foreground color
- 2 Normal intensity foreground color
- 5 Bright (high intensity) background
- 7 Reverse video
- 30..37 Foreground color
- 40..47 Background color

Foreground Code	Background Code	Color	
30	40	Black	
31	41	Red	
32	42	Green	
33	43	Yellow	
34	44	Blue	
35	45	Magenta	
36	46	Cyan	
37	47	White	

Attribute settings are cumulative, and are independent of order (except code **0**, reset to default), and they can be combined into a single command (using the ; concatenation operator), or split into separate commands.

Examples

Set bright red foreground without changing background:

```
echo %=e[31;1m
```

Set the display to bright cyan on blue, and clear the screen:

```
echo %=e[44;36;1m%=e[2J
```

Set up a prompt which saves the cursor position, displays the date and time on the top line in bright white on magenta, and then restores the cursor position and sets the color to bright cyan on blue, and displays the standard prompt:

```
prompt $e[s$e[1;1f$e[45;37;1m$e[K$d $t$e[u$e[44;36;1m$p$g
```

5.9 Colors, Color Names & Codes

You can use color names in several configuration options and in some internal commands. The general form of a color specification is:

where *fg* is the foreground or text color, and *bg* is the background color.

Color Names

Color names as well as the attribute name **BRI**ght may be shortened to their first three letters. The available color names, shown below on approximations of the 8 basic background colors, are: **BLA**ck, **BLUe**, **GREen**, **CYAn**, **RED**, **MAG**enta, **YEL**low, **WHI**te.

	BLU e	GREen	CYA n	RED	MAG enta	YELlow	WHIte
BLA Ck		GREen	CYAn	RED	MAG enta	YELlow	WHIte
BLA Ck	BLUe	GRE	CYAn	RED	MAG enta	YELlow	WHIte
BLA ck	BLU e	GREen	CYA	RED	MAG enta	YELlow	WHIte
BLA Ck		GREen	CYAn		MAG enta	YELlow	WHIte
BLA ck	BLUe	GREen	CYAn	RED	MAG	YELlow	WHIte
BLA Ck	BLUe	GREen	CYAn	RED	MAGenta	YEL	WHIte
BLA Ck	BLU e	GREen	CYAn	RED	MAG enta	YELlow	WHI

Note: The colors (if any) represented by your viewer in the above table do not necessarily match the actual rendition provided by your display hardware and drivers at a **TCC** prompt. **BRI**ght backgrounds are generally always enabled under Windows.

Color Codes

You can also specify colors by numeric code (see table below) instead of by name. The numeric form is most useful in potentially long options such as ColorDIR (see), where using color names may take too much space. The codes are decimal numbers, with the codes for bright colors larger than those of the corresponding normal colors by 8.

The COLOR 18th command also supports the CMD.EXE style color specification **bf**, where **b** and **f** are CMD.EXE's codes for background and foreground colors, respectively (shown in the CMD.EXE columns of the table below). The numeric values of these codes are the same as the **TCC** codes, but they are represented in hexadecimal.

ANSI X3.64 color codes are also shown in the table. Note that X3.64 support for the *bright* attribute is restricted to foreground. Note that the color codes are decimal, and the codes for *background* colors are larger than those of the corresponding *foreground* colors by 10.

SCREEN COLOR		TCC name	TCC codes (decimal)		CMD.EXE codes* (hexadecimal)		ANSI X3.64 codes (decimal)	
normal	bright		norm al	<u>bright</u>	normal	bright	foreground	backgroun d
black	gray	BLA ck	0	8	0	8	30	40
blue	blue	BLU e	1	9	1	9	34	44
green	green	GRE en	2	10	2	А	32	42

cyan	cyan	CYA n	3	11	3	В	36	46
red	pink	RED	4	12	4	С	31	41
magenta	magenta	MAG enta	5	13	5	D	35	45
brown	yellow	YELlow	6	14	6	E	33	43
white	white	WHIte	7	15	7	F	37	47

Note: The numeric values of the CMD.EXE and native color codes are identical, the difference is in representation only.

Use one number to substitute for the **[BRIght]** fg portion of the color name, and a second to substitute for the **[BRIght]** bg portion. For example, instead of bright white on red you could use 15 on 4 to save space in a ColorDir specification.

The <u>@OPTION</u> 4521 function returns the value of color configuration options by combining both foreground and background into a single number (0-255) using the following logic:

foreground value + (background value * 16) = code

For example, bright white on red (15 on 4) can be expressed as:

$$15 + (4 * 16) = 79$$

The following batch file translates a combined numeric color code:

```
@echo off
setlocal
function x=`%@if[%1 gt 8,bri ,]%@word[%@eval[%1 %% 8],bla blu gre cya red
   mag yel whi]`
:loop
input /c /d %=nColor code? %%c
if %c gt 255 .or. %c lt 0 quit
set f=%@eval[%c %% 16] & set b=%@eval[%c \ 16]
echos The color code %c is "%f on %b" ("%@x[%f] on %@x[%b]")
goto loop
```

Color Errors

A standard color specification allows sixteen foreground and sixteen background colors. However, most video adapters and monitors do not provide true renditions of certain colors. For example, most users see normal "yellow" as brown, and bright yellow as yellow; many also see normal red as red, and "bright red" as pink. Color errors are often worse when running in windowed mode, because Windows may not map the text-mode colors the way you expect. These problems are inherent in the monitor, video adapter, and driver software, and they cannot be corrected using the *Take Command* color specifications.

6 Glossary

The glossary contains basic definitions for over 200 common terms listed in alphabetical order and is divided into sections by the first letter of each term. Concepts directly relevant to *Take Command* are typically discussed in more detail in other areas of this help file.

Select the glossary section you wish to review:

```
A 5201 B 521 C 5221 D 525 E 526 F 528 G 528 H 529 I 529 J 530 K 530 L 530 M 531 N 531 O 532 P
```

532) Q 533) R 533) S 534) T 535) U 536) V 536) W 536) X 537)

6.1 Glossary - A

Access Date - In the Windows file systems it is the later of the dates on which a file was created or last accessed for reading. The VFAT [538] and NTFS [532] file systems save this file property.

Access Time - In the Windows file systems it is the time of day when the latter of the events of creating the file or last accessing the file for reading occurred. NTFS 532 saves this file property.

Advanced Power Management (APM) - A standardized system used by manufacturers of battery-powered computers to control system power management, including shutdown of unused components or of the entire system based on usage patterns. **APM** can also report the source of system power (AC or battery), the battery status, and the remaining battery life.

Age - A special term used by the *Take Command* documentation to reference one of its methods to represent points in time (epochs). An **age** is the time elapsed since 1601-01-01 00:00:00 (local time) as a multiple of 100 ns.

Alias - A *TCC* feature which allows you to create shorthand name for a command or series of commands. For details see Aliases 128.

Alias Argument - Same as Alias Parameter 520.

Alias Parameter - A numbered variable (e.g. %2) included in an alias definition, allowing a different value to be used in the alias each time it is executed.

Alternate File Name - Same as Short File Name 534.

American National Standards Institute (ANSI) - An organization which sets voluntary standards for a large variety of industrial products from boilers to photographic films, including computer-related systems, and is the U.S.A. representative in ISO | Isis composed of various professional organizations, including EIA and IEEE, many of which also define standards.

AND - A logical combination of two true or false conditions. The result is **true** if and only if both conditions are true, otherwise it is **false**. See the table below.

condition 1	condition 2	result
false	false	false
false	true	false
true	false false	
true	true	true

ANSI - American National Standards Institute 520. The acronym ANSI in software development is often used as a short-hand reference to the standard ANSI X3.64 520

ANSI X3.64 - A standard specifying sequences of characters which control colors on the screen, manipulate the cursor and screen contents, and redefine keys. *TCC* includes support for a selected subset. This support may be enabled or disabled at any time. For more details see ANSI X3.64 Command Reference 516.

Append - Concatenation of one file or string onto the end of another.

APM - See Advanced Power Management 520.

Application - A program run from the command prompt or a batch file. Used broadly to mean any program other than *Take Command* itself; and more narrowly to mean a program with a specific purpose such as a spreadsheet or word processing program, as opposed to a utility.

Archive:

- 1) A file attribute indicating that the file has been modified since the last backup (most backup programs clear this attribute).
- 2) A single file (such as a **.ZIP** file) which contains a number of other files, optionally in compressed form.

Argument - Same as Parameter 532.

ASCII - Acronym for American National Standard Code for Information Interchange, defined in the standard ANSI SED INCITS 4-1986 (R1997) Information Systems - Coded Character Sets - 7-Bit American National Standard Code for Information Interchange (7-Bit ASCII) (formerly ANSI X3.4-1986 (R1997)). This standard specifies a set of 128 characters (control characters and graphics characters such as letters, digits, and symbols) with their coded representation for use in information interchange among information processing systems, communication systems, and associated equipment. See ASCII file SED.

ASCII File - A file containing ASCII text, as opposed to a binary file which may contain numbers, or other information that cannot be sensibly interpreted as text. Often used in place of text file [535].

Attribute - A property, or indication of a property, of a file which may be set (present) or cleared (absent). Most attributes can be changed, but some cannot. The standard modifiable attributes are Read-Only [533], Hidden [529], System [535], and Archive [521]. Unmodifiable attributes include Directory [525] and Volume Label [536].

Automatic Directory Change - A *TCC* feature which allows you to change directories by typing the directory name terminated in a backslash [\] at the command prompt, without first entering a command.

Automatic Programs - Programs automatically executed when *TCC* starts or terminates: <u>TCSTART</u> and TCEXIT 5351. See Automatic Startup and Termination Programs 22 for more details.

6.2 Glossary - B

Base Name - The file name without a drive, path, or extension. For example, in the file name *C:\DIR1\LETTER.DAT* the base name is *LETTER*.

Basic Input Output System (BIOS) - Software which provides basic low-level control of devices required to operate the system, such as the keyboard, floppy disk, and screen. On most systems the BIOS is stored in read-only memory inside the PC.

BAT File - Same as Batch File 521.

Batch File - A <u>text file sash</u> containing a sequence of commands for *TCC* to execute. Batch files are used to save command sequences so that they can be reexecuted at any time, transferred to another system, etc. The extension of a batch file may be *.BAT*, *.CMD*, or *.BTM*.

Batch File Argument - Same as Batch File Parameter 521.

Batch File Parameter - A numbered variable (e.g. %2) used within a batch file sath, allowing a different value to be used at that spot in the file each time it is executed.

Batch Program - A more descriptive name for Batch File 521.

Binary File - A file containing information which does not represent or cannot sensibly be interpreted as text. See also ASCII File [52], text file [535].

BIOS - Basic Input Output System 521..

Block Device - A physical device for input or output, which interchanges data with the computer in large blocks. XXIth Century PCs can perform such transfers of data concurrently with other activities. Examples of block devices include disk, tape, and CD-ROM drives. See also Character Device [523].

Boot - Ungrammatical contraction of Booting 522, shortened from Bootstrapping 522.

Boot Directory - The current directory at the time the system is started, usually the <u>root directory</u> 534 of the boot drive 522.

Boot Drive - The disk drive that the operating system is loaded from during the boot process, usually A: (the floppy disk) or C: (the hard disk), or on some systems a CD or DVD drive. In some diskless workstations it may be a network drive.

Booting - shortened form of Bootstrapping 522.

Bootstrapping - From the book "Baron Munchausen's Narrative of his Marvellous Travels and Campaigns in Russia", by Rudolf Erich Raspe (London, England, 1786), in particular, the story of the Baron's astounding ability to pull himself from the ocean by his own bootstraps. See also Cold Boot, Cold Reboot, Reboot, and Warm Reboot.

Break - A signal sent to a program to tell it to halt what it is doing. The **Ctrl-C** key or **Ctrl-Break** key is used to send this signal. Some external commands abort when they receive a break signal; others return to a previous screen or menu, or abort the current operation.

BTM File - A special type of batch file 52th, unique to JP Software products, which is loaded into a buffer 52th in memory to speed up its execution.

Buffer - An area of memory set aside for temporary storage of information moved between concurrent programs or between programs and external media. For example, disk buffers are used to save information as it is transferred between your program and the disk, and the keyboard buffer holds keystrokes until a program can use them. **TCC** uses many buffers for its internal operations, e.g., to store aliases 128.

6.3 Glossary - C

Carriage Return (CR) - A control character (ASCII 511): 13) specifying that the next character is to be displayed at the leftmost position of the current line. In older mechanical character printing devices the carriage was moved to cause printing in different character positions of the same line. In a PC the CR code is generated by pressing the Enter key on the keyboard, and stored in most text file 535 s at the end of each line. See also ASCII 511, End of Line 520.

CD-ROM File System (CDFS) - The file system which supports CD-ROM / CD-RW drives.

Central Processing Unit (CPU) - The part of the computer which historically performed all logic and most calculations. In PC-compatible systems, the CPU is on a single microprocessor chip. Many high-performance computers, including PCs, have more than one processing unit, often organized in such a way that none qualifies as the "central" processing unit.

Character Code - The code representing a specific character in the computer. See also: ASCII 521, Code Page 523, Unicode 536.

Character Device - A physical device for input or output which must communicate with your computer one character at a time. Examples include the console, communications ports, and printers. See also Block Device [522].

Character Mode - A display mode in which output is displayed one character at a time, and which cannot display graphics or pictures not included in the character font used. Character Mode displays are usually in a fixed font, typically with 80 columns in a line and 25 lines on the screen. Some systems allow you to increase or decrease the number of rows and columns to other fixed sizes. See also Graphic Mode 529.

CMD File - A batch file 521 designed for execution by CMD.EXE or TCC.

CMDLINE - An <u>environment variable seed to extend the command line passed to another program beyond its normal length limits.</u>

Code Page - A setting which tells Windows which character set to use, and how to retrieve and display date, time, and other information in the format appropriate to a particular country or region. See also Country Settings 524.

Cold Boot - The process of starting the computer by turning on its power. See also Boot 221, Cold Reboot 323, Reboot 333, Warm Reboot 336.

Cold Reboot - The process of restarting the computer in a way that physically resets most hardware devices, typically by pressing a reset button, or by emulating it utilizing a special feature of the BIOS 521. See also Boot 522, Cold Boot 523, Reboot 533, Warm Reboot 536.

Command Completion - A *TCC* feature which allows you to recall a previous command by typing the first few letters of the command, then an up-arrow or down-arrow.

Command Echoing - A *TCC* feature which displays commands as they are executed. Echoing can be turned on and off.

Command Grouping - A *TCC* feature which allows you enclose a group of several commands within parentheses, and have them treated as a single command.

Command History - A *TCC* feature which retains the commands you have executed from the command prompt, so that they can be recalled, optionally modified, and reexecuted later.

Command History Window - A pop-up window used by *TCC* to display the <u>command history</u> 523, allowing you to choose a previous command to modify and/or execute.

Command Interpreter - Same as Command Processor 523.

Command Line Expansion - The process *TCC* goes through when it scans a command line and substitutes the appropriate actual values for aliases, alias parameters, batch file parameters, user defined functions, and variables. See also Parsing [532].

Command Processor - A program which interprets commands entered interactively or stored in a file (referred to as a <u>batch file [52]</u> in the environment discussed here), and executes other programs. Also called <u>Command Interpreter [523]</u>.

Command Prompt - A prompt displayed on the screen by TCC when it is ready for another command

to be entered and executed.

Command Recall - See Command History 523.

Command Separator - One or more characters used to separate multiple commands on the same command line. See Multiple Commands 1201.

Command Tail - The contents of the command line after removing the command name. See Separating the command from its command tail

Compound Command - See Multiple Commands 120).

Compression - A feature which compresses data as it is stored in a disk file, and expands it as it is read back, resulting in more efficient use of disk space. This feature may be provided by hardware, software, or a combination of both. The software may, but need not, be part of the operating system.

NTFS [532] provides an attribute to indicate whether or not a file is compressed. Accessing compressed files requires slightly more processor time to perform the compression and expansion, but this is often compensated by the reduced data transfer time.

COMSPEC - An environment variable which defines where to find the character-mode command processor to start a secondary shell.

Condition - short for conditional expression 109).

Conditional Commands - A command processor feature allowing commands to be executed or skipped depending on the results of a previous command. See also: Exit Code [527].

Conditional Expression - See Conditional Expression 1091.

Console - See Character Mode 523.

Console Mode - See Character Mode 523.

Control Character - A character which does not have a printable or displayable representation, but, when encountered in a stream of characters, performs a specific action. In ASCII strip the codes for these characters are in the range [0,31] or it is 127; each character also has a two- or three-character symbol for representing it in plain text. The common PC keyboard for U.S. use has special keys for some, i.e., ESC, CR, BS, HT, DEL. Each control character in ASCII strip can be generated by pressing the Ctrl key simultaneously with another key. For more information see ASCII, Key Codes & ANSI Commands store.

Country Settings - The internal settings which tell the operating system how to interpret keyboard characters which vary from country to country, which character set to use, and how to retrieve and display date, time, and other information in the format appropriate to a particular country or region. See also Code Page[523].

CPU - See Central Processing Unit 522.

CR - See Carriage Return 522

CRC - See Cyclic Redundancy Code 5251.

Critical Error - An error, usually related to a physical or hardware problem with input, output, or network access, which prevents a program from continuing.

Current Directory - The directory in which all file operations of a selected drive will take place unless otherwise specified by an explicit path. The current directory is typically displayed as part of the command prompt. Also called the **Current Working Directory**.

Current Drive - The disk drive on which all file operations will take place unless otherwise specified. The current drive is typically displayed as part of the command prompt.

Current Working Directory - Alternate name for Current Directory 5251.

Cursor - A movable marker on the screen to show where text will be entered when you type at the keyboard, or which object on the screen will be affected when a mouse button is clicked.

Cyclic Redundancy Code (**CRC**) - A sequence of characters, associated with a block of data, which provide a reasonably unique signature, used to detect the possibility of the data being corrupted in storage or transmission.

6.4 Glossary - D

Date Range - A *TCC* feature which allows you to select files based on the date and time they were last modified. For details, see <u>Date Ranges</u> 82.

Date Stamp - Information which may be stored in a file's directory entry to show the dates on which the file was created, last modified, and last accessed for reading. Only the modification date is available in the FAT file system [528]. See also Time Stamp [495].

Default Directory - Same as Current Directory 525).

Default Drive - Same as Current Drive 525).

Deletion Tracking - An operating system or utility software feature designed to allow you to "undelete" or recover files which have recently been deleted. Delete tracking typically works by temporarily retaining the deleted files and / or information about the deleted files in a special area of the disk.

Description - A special feature of *TCC*. A string of characters may be assigned to describe a file, using the <u>DESCRIBE [195]</u> command, typically stored in the file DESCRIPT.ION in the same directory as the file itself.

Destination - In some file processing commands (e.g. <u>COPY [182]</u> or <u>MOVE [274]</u>), the name or directory the files should have after the command is completed. It is generally the last specification on the command line. See also <u>Source [535]</u>.

Detached Process - A program which is detached from the normal means of user input and output, and cannot use the keyboard, mouse, or video display.

Device Driver - A program which allows the operating system to communicate with a device. It must be loaded into memory before the system can access the attached devices. Device drivers are also used to manage memory or for other similar internal functions.

Device - A physical device for input or output such as the console, a communications port, or a printer. Sometimes *device* is used to refer to <u>character devices</u> 523, and excludes <u>block devices</u> 522.

Directive - The name of a configurable *Take Command* or *TCC* option and the value assigned to it. Most directives are set with the OPTION 284 command. See also: initialization file 530.

Directory:

- 1) A portion of a disk, identified by a name and a relationship to other directories in a directory tree structure, with the tree starting at the root directory separates files on the disk into logical groups, but does not represent a physical division of the data on the disk.
- 2) The attribute 52th of the entry for the directory in its parent directory 532th.

Directory History - A *TCC* feature which allows you to recall recently-used directory names in a popup window, and choose one to switch to.

Directory History Window - The name of the pop-up window displaying the Directory History [526].

Directory Junction - same as soft link 534).

Directory Stack - A *TCC* feature, implemented through the PUSHD [299] and POPD [294] commands, which allow you to save the current directory and return to it later. See also Stack [535].

Directory Tree - The branching structure of directories on a disk, starting at the <u>root directory</u> 534. The *root* of the tree is usually considered as the *top* of the structure, so the actual structure can be visualized as an upside-down tree with the root at the top and branches going down.

Domain -in mathematics the set of values for which a function is defined.

Drive Letter - A letter used by some operating systems to designate a specific local disk volume, or part or all of a network server volume. In most cases drive letters range from A - Z, but some network operating systems allow the use of certain other characters as drive letters to support more than 26 disk volumes.

6.5 Glossary - E

Echo - See Command Echoing 5231.

End of Line (EOL) - An indication of the end of line in text file sabs. Many conventions exist to represent EOL in ASCII files. The most common ones use one or two control characters: (1) CR [522], (2) CR followed by LF [530], (3) LF followed by CR, (4) LF. Windows text files normally use (2). UNIX/Linux and their variants use (4), and refer to the LF character as the new line (NL) character.

Environment - A set of variables and their values. Some variables are set before the start of **Take Command**. Others may be set at the command line using the <u>SET</u> of command, or by your batch files. If a variable is defined, it has a value, which is a character string, and is at least 1 character long. A variable can be removed from the environment using the <u>UNSET</u> of command, or by setting its value to an empty string. See also <u>Master Environment</u> and <u>Passed Environment</u>.

Environment Variable - The name of a single entry in the environment [526].

Error Level - A numeric value returned from an external command or, in some cases, from an internal command to indicate its result (*e.g.*, success, failure, response to a question). Not all commands return an error level. Also known as Exit Code [527].

Escape Character -

1) The command processor escape character, used to suppress the normal meaning of, or to give special meaning to the immediately following character. The default **escape character** in *TCC* is the caret (^). This may be modified using the <u>Escape character</u> configuration option or by using the /E option of the <u>SETDOS</u> (323) command.

2) A control character, symbol ESC (ASCII 511): 27).

Escape Sequence - A sequence of text characters which has a special meaning and is not treated as normal text. For example, the character sequence <ESC>]K (where <ESC> represents the ASCII "escape" character, decimal value 27) will cause an ANSI X3.64 driver to clear the screen from the cursor to the end of the current line, rather than simply displaying the string ESC]K on the screen. Similarly, in *Take Command*, the escape sequence ^f on the command line is translated to a form feed, and is not treated as the literal characters ^f.

Executable Extension - A *TCC* feature which allows you to specify the application to be executed when a file with a particular extension is named at the command prompt.

Executable File - A file, usually with the extension .**COM** or .**EXE**, which can be loaded into memory and run as a program.

Exclusive OR or **XOR** - A logical combination of two true or false conditions. If both conditions are false or both conditions are true the result is **false**; if either condition is true and the other is false the result is **true**. See below.

condition 1	condition 2	result
false	false	false
false	true	true
true	false true	
true	true	false

Exit Code - The result code returned by an external command or an internal command. Internal commands return an exit code of 0 if successful, or non-zero if unsuccessful. External commands may, but need not return an exit code. See also Errorlevel 5261.

Expansion:

- 1) Command Line Expansion 523
- 2) The inverse of compression 524.

Extended ASCII Character: A legally invalid phrase, used for a character whose code is in the range 128 to 255, used as part of an extended set of 256 characters. The extension character set may include international language symbols, and box and line drawing characters. What is displayed or what is printed when such a character is used depends on the <u>country setting</u> [524], <u>code page</u> [523], and font.

Extended Directory Search - A *TCC* feature which maintains a directory search database or list, typically including all directories in your system, and allows you to change quickly to any directory in the list based on partial match of the directory you specify in the command.

Extended Key Code - The code for a key on the keyboard which has no representation in the standard ASCII character set, such as a function key, cursor key, or **Alt** plus another key.

Extended Parent Directory Names - A *TCC* feature which allows you to use additional periods in a directory name to represent directories which are successively higher in the directory tree.

Extended Wildcard - A *TCC* feature which extends the wildcard syntax and allows you to use multiple wildcard characters, and character ranges (e.g. [a-f] for the letters A through F). See also Wildcard [537],

Extension - The portion of a file name following the last period. For example, in the file name

C:\DIR1\LETTER.JOHN.DAT the extension is .DAT.

External Command - A program directly executable by the operating system, as distinguished from an internal command [530], which is executed by *TCC*.

EXTPROC - A *TCC* feature which allows you to designate a specific external program to run a particular batch file.

6.6 Glossary - F

FAT - See File Allocation Table 528.

FAT-Compatible File Name - See SFN 534).

FAT File System - The file system used by PC-DOS, MS-DOS, and its emulators based on FAT 528, to store files on diskettes and hard disks; also supported by Windows. Supports a single 2-s resolution timestamp of "last written" (modified). It is subclassified according to the size of word required to represent the largest possible FAT 528 size.

FAT16 File System - Each entry in the FAT 528 is 16 bits long, limiting table size to 65,536 allocation blocks.

FAT32 File System - Each entry in the <u>FAT 528</u> is 32 bits long, limiting table size to 4,294,967,296 allocation blocks, See also VFAT File System 536.

FF - See Form Feed 528.

File Allocation Table (FAT) - A table used by the file system to keep track of disk space usage, allocation, ownership, and file content.

File Attribute - See Attribute 521.

File Description - See Description 525.

File Exclusion Range - A *TCC* feature which allows you to exclude files from processing by internal commands. See File Exclusion Ranges 85.

Filename Completion - A *TCC* feature which allows you to type part of a filename on the command line, and have *TCC* fill in the rest for you.

Font - a set of character shapes in a single style and size.

Form Feed (**FF**)- A control character (ASCII: 12), which typically causes a printer to skip to a new page. The **FF** character is not normally entered from the keyboard, but in many cases it can be generated, if necessary, by holding the **Alt** key, pressing the numeric pad keys **012**, and releasing the **Alt** key, or by the **Ctrl-L** key combination.

Free Memory - Usually, the amount of total memory which is unoccupied and available for applications.

6.7 Glossary - G

Global Aliases - A *TCC* option which allows you to store aliases in a global area accessible to all copies of *TCC*, so that any change made by one copy, even between a <u>SETLOCAL</u> 3261 - <u>ENDLOCAL</u> 2201 command pair, is immediately effective in all other copies. See also <u>Local Aliases</u> 5371.

Global Directory History - A *TCC*option which allows you to store the directory history in a global area accessible to all copies of *TCC*, so that any change made by one copy, even between a SETLOCAL 326 - ENDLOCAL 220 command pair, is immediately effective in all other copies. See also Local Directory History 531.

Global History - A *TCC* option which allows you to store the command history in a global area accessible to all copies of *TCC*, so that any change made by one copy, even between a <u>SETLOCAL</u> 220 command pair, is immediately effective in all other copies. See also <u>Local History</u> 531.

Global User Functions - A *TCC* option which allows you to store user-defined functions in a global area accessible to all copies of *TCC*, so that any change made by one copy, even between a SETLOCAL 326 - ENDLOCAL 220 command pair, is immediately effective in all other copies. See also Local User Functions 531.

Graphics Mode - A display mode in which output is displayed in any one of a range of fonts, typically in resizable windows with a variable number of text rows and columns, and which supports the display of graphics and pictures along with text. See also Character Mode 523.

6.8 Glossary - H

Hard link - NTFS gives you the ability to create hard links, which are multiple directory entries referencing a single file body. Creating a hard link causes the system to create an additional directory entry that points to the same file (unlike a shortcut, which is actually an additional file). Files can have multiple hard links, and therefore a single file can appear in multiple directories, with multiple names in each.

A file with more than one hard link can be accessed by any of its directory entries. Each file on an NTFS volume has at least one hard link (connecting a directory entry to the file body). A file is deleted from the file system only after all its hard links (i.e., directory entries) have been deleted.

When a file with more than one directory entry is modified, the file properties (e.g., size, date stamps, etc.) of only the entry actually used for updating the file are updated instantly.

Hard links must be created on the same NTFS volume as the file.

Hidden - A file attribute indicating that the file should not be displayed with a normal DIR of the command, and should not be made available to programs unless they specifically request access to hidden files. Often combined with the System substitute.

History - See Command History 523.

History Window - See Command History Window 523 and Directory History 5261.

6.9 Glossary - I

IFS - See Installable File System 529.

Installable File System (IFS) - A file system for which device drivers can be loaded when required to support devices such as CD-ROM or network drives, or non-default disk formats. Installable file systems may be loaded at system startup, or loaded and unloaded dynamically while the system is running. They typically appear to *TCC* simply as another drive.

Include List - A method of specifying several files or groups of files in the same directory, for use with

all internal commands which take file names as parameters.

Inheritance - A *TCC* feature which allows one instance of *TCC* to "inherit" the TCMD.INI file data, aliases, user defined functions, environment variables, command history, and directory history from a previous instance. More generally, a system which allows one program to pass information or settings on to another, often to a second instance of the same program.

Initialization Directive - See Directive 525.

Initialization File or **.INI File** - A file which enumerates the initial settings of various command processor options, and which is automatically read by the command processor when it starts. The default initialization file for *Take Command* is **TCMD.INI**. For additional details, see Startup Command and Initialization Files [26].

Insert Mode - When editing text, a mode in which newly typed characters are inserted into the line at the cursor position, rather than overwriting existing characters on the line. See also Overstrike Mode S32.

Internal Command - A command which is part of *TCC*. See also external command 528.

Internal Variables - Special variables created by *TCC* to provide information about your system. Internal variables are evaluated each time they are used, and are not actually stored in the environment. Internal variables are accessed using the same syntax as environment variables.

International Standardization Organization (ISO) - An international body promulgating standards.

ISO - See International Standardisation Organization 530.

6.10 Glossary - J

Junction - same as soft link 534

6.11 Glossary - K

Key Code - The code passed to a program when a key is pressed on the keyboard. Depending on the key that is pressed, and the software handling the keyboard, the code can be an ASCII value, a scan code, or an extended key code.

Key Mapping - A *TCC* feature which allows you to assign new keystrokes for command line functions such as manipulating the command history or completing file names.

Keyboard Buffer - A Windows buffer which holds keystrokes you have typed that have not yet been used by the currently executing program.

Keystroke Alias - An alias assigned to a key so that it can be invoked or recalled with a single keystroke.

6.12 Glossary - L

Label:

1) A location marker in a <u>batch file [521]</u>, with the format :name, allowing <u>CALL [175]</u>, <u>GOTO [248]</u> and <u>GOSUB [247]</u> commands to "jump" to that point in the file.

2) Volume Label [536].

Line Feed (LF) - A control character (ASCII 511): 10) indicating that the next character should be

displayed in the current horizontal position but one line down. It is often used in text files as part of, or as the End of Line [526]. It is not normally entered from the keyboard, but in many cases it can be generated, if necessary, by pressing **Ctrl-J**.

LF - See Line Feed 530.

LFN - See Long File Name 531.

LFN File System - A file system which supports long file names 531. An LFN file system may store both a long and short name for a file. The short name is sometimes called the alternate name. See also Long File Name 531, Short File Name 534, VFAT File System 536, and NTFS 532.

Local Aliases - A *TCC* option which allows you to store aliases in a local area only accessible to the current copy of *TCC* so that a change made in the current copy of *TCC* does not affect other copies, and vice versa. See also Global Aliases 528.

Local Directory History - A *TCC* option which allows you to store the directory history in a local area only accessible to the current copy of *TCC*, so that a change made in the current copy of *TCC* does not affect other copies, and vice versa. See also Global Directory History 529).

Local History - A *TCC* option which allows you to store the command history in a local area only accessible to the current copy of *TCC*, so that a change made in the current copy of *TCC* does not affect other copies, and vice versa. See also Global History 529.

Local User Functions - A *TCC* option which allows you to store user-defined functions in a local area only accessible to the current copy of *TCC*, so that a change made in the current copy of *TCC* does not affect other copies, and vice versa. See also Global User Functions 5291.

Logging - A *TCC* option, implemented via the <u>Log</u> command, which allows you to save a record of the commands you execute.

Long File Name (**LFN**) - A file name which does not conform to FAT file system restrictions, either because it is longer than the 8 character name plus 3 character extension, or because it contains spaces, multiple periods, or other characters not allowed in a FAT file name. See also **Short File Name** [534].

6.13 Glossary - M

Master Environment - The master copy of the environment maintained by Windows.

Modulo - The remainder after an integer division. For example 11 modulo 3 is 2.

Multiple Commands - A *TCC* feature which allows multiple commands to be placed on a line, with each command separated by a <u>command separator [524]</u>.

6.14 Glossary - N

Name - The part of the file name from its beginning up to, but not including, the last period in the file

Network - A system which allows several computers to be connected together to share files, printers, modems, or other resources, and to pass electronic mail or other information between the systems on the network.

Network File System - Software which runs over a network to allow access to files on the server. A network file system may support the same options as the file system used on local drives, or it may be more or less restrictive than the local file system about file names, disk volume capacity, and other similar features.

New Technology File System (NTFS): A file system distributed with Windows which allows longer file names, supports larger drives, and provides better performance than the FAT file system [528].

6.15 Glossary - O

Operating System - A collection of software which provides access to various devices, including file systems and networks, services to other software, and ensures that programs don't interfere with each other while they are running.

Option:

- 1) A parameter for an internal command or application which specifies a particular behavior or setting. For example, the command "DIR /P" might be referred to as "having the /P option set". Alternate name: **switch**.
- 2) A command which allows modifying **TCC** operating characteristics.

Option file - Alternate name for Initialization File 530.

OR - A logical combination of two true or false conditions. If both conditions are false the result is false; if either condition is true the result is true. See the table below.

condition 1	condition 2	result
false	false	false
false	true	true
true	false	true
true	true	true

Overstrike Mode - When editing text, a mode in which newly typed characters overwrite existing characters on the line, rather than being inserted into the line at the cursor position. See also Insert Mode 530.

6.16 Glossary - P

Parameter - Additional information placed after a command or function name. For example, in the command **DIR XYZ**, **XYZ** is a parameter. Also used to refer to an alias parameter or batch file parameter.

Parent Directory - The directory in which a particular subdirectory is cataloged, often seen as the directory above a subdirectory.

Parsing - The process *TCC* performs to analyze the command line, perform alias, function and variable expansion, and find the appropriate internal command or external command to execute. More generally, the process of breaking down a string or message into its individual components in order to process them properly. See

Passed Environment - A copy of the environment created before running an application, so that any changes made by the application will not affect the environment of the application's parent.

Path:

- 1) A specification of all the directories required to locate a file. For example, the path for C:\WPFILES\MYDIR\MEMO.TXT is C:\WPFILES\MYDIR\.
- 2) The environment variable PATH (368), which contains a series of path specifications used when searching for external commands and batch files.
- 3) The internal command PATH 286, which redefines the value of the environment variable PATH 368

Pipe - A method for sending the standard output of one command to the standard input of another command, syntactically represented by a vertical bar "|" separating the commands. See also Redirection 98.

Pixel - A single dot on the screen. The color of each pixel can be individually controlled.

Previous Working Directory - The working directory used most recently, just prior to selecting the <u>current working directory</u> [525]. For example, if *C:* *DATA* is the current working directory and you switch to *D:* *UTIL*, *C:* *DATA* becomes the previous working directory.

Primary Shell - The copy of the character-mode command processor which is loaded by the operating system when the system starts or a session opens.

6.17 Glossary - Q

Quote mark - The character " used by English and other natural languages to mark the beginning and end of a block of text copied from another source, and thus not subject to modification. Many programming languages, including **Take Command**, use it in a similar manner to delimit text to be used literally (i.e., exactly as is).

6.18 Glossary - R

RAM - Random Access Memory 533.

RAM Disk - Another name for Virtual Disk 5361.

Random Access Memory (**RAM**) - The physical memory used to store data while a computer is operating. The information in most types of RAM is lost when power is turned off.

Range (file selection) - See <u>Date Range 82</u>, <u>Description Range 86</u>, <u>File Exclusion Range 85</u>, <u>Size Range 82</u>, <u>Time Range 84</u>.

Range - the set of possible values of a function.

Read Only - A file attribute indicating that the file can be read, but not written or deleted by the operating system or *TCC* unless special commands are used.

Read Only Memory (ROM) - Physical memory used to store information which cannot be readily modified.

Reboot - The process of restarting the computer with software, with the keyboard (*e.g.* by pressing Ctrl-Alt-Del), by pressing a reset button, or by turning the power off and back on. See also Boot Cold Reboot sale, and Warm Reboot sale.

Redirection - A method for sending the output from a command to a file, or of providing the input for a command from a file. See also Pipe 533.

Registry - A hierarchically organized data file (or set of files) maintained by Windows to hold system

parameters, hardware and software settings, and other similar information used by the operating system or by other software packages.

Reparse Point - same as soft link 534

REXX - A file and text processing language developed by IBM, and available on many PC and other platforms.

ROM - Read Only Memory 533.

Root Directory - The first directory on a disk, from which all other directories are "descended". The root directory is referenced with a single backslash [\].

6.19 Glossary - S

Search Path - A semicolon-delimited list of directories in which to search for a file.

Secondary Shell - A copy of the command processor which is started by another program, rather than by the operating system.

Section - A part of an <u>Initialization File solution</u> starting with a section name enclosed in brackets, e.g., [primary].

Session - A general term for the individual windows or tasks started by a multitasking system.

Shell - The name used in UNIX/Linux/etc. systems for <u>command processor</u> |523|, from a pictorial representation of the OS being encased by a shell.. Also used to refer to any program which gives access to operating system functions and features through a menu- or mouse-driven system, or which replaces the primary user interface of the operating system.

Short File Name (SFN) - A file name which follows the rules of the FAT file system [528]: a name [531] of 0 ...8 characters and an extension [527] of 0 ...3 characters, each consisting of only alphabetic and numeric characters plus the punctuation marks! # \$ % & '() - @ ^ _ `{} and ~. See also LFN [531].

VFAT file systems consider a file name that contains a lower case character to be a LFN 531, even if it obeys all other rules to a SFN, and assign to it a SFN - the all upper case version of the LFN. NTFS does not assign an SFN to such files.

When you copy an LFN file to another LFN directory by its LFN (using the same name in the target directory), the SFN of the target file may be different from the SFN of the source file.

Size Range - A *TCC* feature which allows you to select files based on their size. For details see <u>Size</u> Ranges 82.

Soft Link - also known as a directory junction or reparse point - is a special file. When created, its content is the name of a directory on any volume. Any reference to the contents of the soft link act on the contents of the directory it references, including deleting of files from the soft link, which deletes the files from the referenced directory.

Soft links can be chained, i.e., a soft link **A** can refer to another soft link **B**. Changing the referenced directory of **B** effectively changes the contents of **A**.

If the directory referenced by a soft link is deleted, references to the soft link's contents fail. If later another directory is created with the same name, the soft link will function again. Similarly, if the reference is to a removable volume, it will reference whatever volume is present at the time of access.

Source - In file processing commands (e.g. COPY or MOVE), the original files before any copying or modification has taken place, *i.e.*, those specified earlier on the command line. See also Destination [525].

Stack - An area of memory used by any program to store temporary data while the program is running; more generally, any such storage area where the last item stored is normally the first one removed.

Standard Error (stderr)- The file or character device where a program displays error messages. It defaults to the screen. It may be redirected 1981 to a file, or piped 1011 to another program.

Standard Input (stdin) - The file or character device whence a program obtains its normal input. It defaults to the keyboard. It may be redirected 1981 to a file, or piped 1011 to another program.

Standard Output (stdout) - The file or character device where a program displays its normal output. It defaults to the screen. It may be redirected shappy from a file, or piped 10th from another program.

Stderr - short for Standard Error 535.

Stdin - short for Standard Input 535.

Stdout - short for Standard Output 535).

Subdirectory - Any directory other than the root directory 5341.

Subtree - See Directory Tree 526.

Switch - Alternate name for Option [532]; also the name of the program control command SWITCH [335].

System - A file attribute indicating that the file belongs to the operating system, and should not be accessed by other programs. Most files with this attribute also has the Hidden 529 attribute.

6.20 Glossary - T

Target: See Destination 525.

TCEXIT: A program which is executed whenever *TCC* exits. See <u>Automatic Startup and Termination</u> <u>Programs</u> 22 for more details.

TCSTART: A program which is executed whenever *TCC* starts. See <u>Automatic Startup and Termination Programs 22</u> for more details.

Text file: A file containing only characters that are either displayable, or which affect the display format (format effectors). The characters of the file are represented by their character codes. **TCC** provides support for two systems of character codes, <u>ASCII</u> [51] and <u>Unicode</u> [536].

Time Range: A *TCC* feature which allows you to select files based on the time they were last modified, created, or accessed. See <u>Time ranges</u> [84] for more details.

Time Stamp: Information stored in a file's directory entry to show the times at which the file was created, last modified, and last accessed. Creation time is not available in the FAT file system; last access time is only available in the NTFS file system. See also Date Stamp [525].

Tree: See Directory Tree 526.

6.21 Glossary - U

UNC - Universal Naming Convention

Universal Naming Convention - A common method for accessing files on a network drive without using a mapped drive letter. Names specified this way are called UNC names, and typically appear as \server\volume\path\filename, where server is the name of the network server where the files reside, volume is the name of a disk volume on that server, and the path\filename portion is a directory name and file name.

UNICODE - A character set standard, designed and maintained by the non-profit Unicode Consortium (http://unicode.org). Windows 2000 introduced an implementation of 16-bit *UNICODE* (65536 potential distinct values) intended to facilitate use of non-English languages. The first two bytes of Unicode text files in NTFS systems contain a signature representing the file encoding.

UDF - User Defined Function.

User Defined Function - A function defined by the user utilizing the <u>FUNCTION [242]</u> command to manipulate strings, dates, and filenames; perform arithmetic; read and write files; and perform other similar functions. UDFs are invoked the same way as <u>Variable functions [395]</u>.

6.22 Glossary - V

Variable - See Alias Parameter 520, Batch File Parameter, Function Parameter, and Environment Variable.

Variable Expansion - The process of scanning a command line and replacing each environment variable name, alias, function, and batch file parameter and function invocation with its value.

Variable Functions - Functions provided by *TCC* to manipulate strings, dates, and filenames; perform arithmetic; read and write files; and perform other similar functions. Variable functions are similar to environment variables or internal variables, but have parameters and can perform actions rather than just returning static information.

VFAT File System - An extension of the FAT file system [528] which supports long filenames [531].

Virtual Disk - A portion of memory, dedicated for this use through special purpose software, accessible by programs as if it were a physical disk drive, and storing data in files in a directory tree. Also called a **RAM Disk**.

Volume - See Disk Drive.

Volume Label - A character string stored on a disk drive or volume used to identify it. Windows uses a special, hidden file name in the disk root directory for this purpose.

6.23 Glossary - W

Warm Reboot - The process of restarting the computer with software, or with the keyboard (e.g. by pressing Ctrl-Alt-Del), typically without physically resetting any hardware devices. See also **Cold Reboot**.

White Space Character - A character used to separate parameters on the command line. The white space characters recognized by *TCC* are the space, tab, and comma.

Wildcard - A character (* or ?) used in a filename to specify the possibility that any single character (?) or sequence of characters (*) can occur at that point in the actual name. See also **Extended Wildcard**.

6.24 Glossary - X

X-3.64 - See ANSI X-3.64 520

XOR - Exclusive OR 537.

7 Copyright & Version

Take Command 9.0 for Microsoft Windows XP / 2003 / Vista / 2008 Software: Copyright © 2008, Rex Conn and JP Software Inc.

All Rights Reserved.

Version 9.0 Help System
Help text: Copyright © 2008 JP Software Inc.
All Rights Reserved.

Language translations by Christian Albaret (French) and Hans-Peter Grözinger (German)

We gratefully acknowledge the contributions of Roger Byrne, Vincent Fatica and our other users.

This help material was last revised on Tuesday, January 29, 2008

Take Command® is a registered trademark of JP Software Inc. JP Software, jpsoft.com, and all JP Software designs and logos are also trademarks of JP Software Inc. Other product and company names are trademarks of their respective owners.

Index

- ! -

! 380

! range exclusion 80

!= inequality test operator 109

- \$ -

\$ metacharacter 297

\$ parameter 133

- & -

& ampersand 126

&& 120

- (-

() parentheses 109, 121

_ * _

* (disable alias) 120

* (wildcard) 77

* parameter 133

_ _ _

.AND. 109

.BAT and 4NT 131

.BAT extension 131

.BTM extension 131

.CMD extension 131

.INI 388

.INI files 24

.OR. 109

.XOR. 109

-?-

? (command) 152

? (variable) 380, 395 ? (wildcard) 77

- @ -

@ at sign 90, 106

@ABS 407

@AFSCELL 407

@AFSMOUNT 407

@AFSPATH 407

@AFSSYMLINK 407

@AFSVOLID 408

@AFSVOLNAME 408

@AGEDATE 408

@ALIAS 408

@ALTNAME 408

@ASCII 409

@ASSOC 162, 241, 409

@ATTRIB 86, 409

@AVERAGE 410

@CAPI 410

@CAPS 411

@CDROM 411

@CEILING 411

@CHAR 411

@CLIP 412

@CLIPW 412

@COLOR 412

@COMMA 412

@COMPARE 413 @CONSOLE 413

@CONVERT 413

© CONVERNIT

@COUNT 413

@CRC32 413

@CWD 414

@CWDS 414

@DATE 414

@DAY 414

@DEC 415

@DECIMAL 415

@DESCRIPT 415

@DEVICE 416

@DIGITS 416

@DIRSTACK 416

@DISKFREE 416

@DISKTOTAL 417

@DISKUSED 417

@DOMAIN 417

@DOW 417		
@DOWF 418		
@DOWI 418		
@DOY 419		
@DRIVETYPE 419		
@DRIVETYPEEX 419		
@ENUMSERVERS 419		
@ENUMSHARES 420		
@ERRTEXT 420		
@EVAL 415, 420, 440		
@EXEC 424		
@EXECSTR 386, 424		
@EXETYPE 424		
@EXPAND 425		
@EXT 425		
@FIELD 426		
@FIELD 420 @FIELDS 427		
@File List 90		
@FILEAGE 427		
@FILECLOSE 427 @FILEDATE 428		
@FILENAME 428		
@FILEOPEN 428		
@FILEREAD 429		
@FILEREADB 429		
@FILES 430		
@FILESEEK 431		
@FILESEEKL 431		
@FILESIZE 432		
@FILETIME 432		
@FILEWRITE 433		
@FILEWRITEB 433		
@FINDCLOSE 434		
@FINDFIRST 434		
@FINDNEXT 435		
@FLOOR 435		
@FORMAT 435		
@FORMATN 436		
@FSTYPE 436		
@FTYPE 162, 241, 437		
@FULL 437		
@FUNCTION 437		
@GETDIR 437		
@GETFILE 438		
@GETFOLDER 438		
@GROUP 417, 438		
@HISTORY 439		
@IDOW 439		

```
@IDOWF 439
@IF 109, 439
@INC 440
@INDEX 440
@INIREAD 441
@INIWRITE 441
@INODE 442
@INSERT
        442
@INSTR 443, 463
@INT 443
@IPADDRESS
           443
@IPNAME 444
@ISALNUM
         444
@ISALPHA 444
@ISASCII 444
@ISCNTRL 445
@ISDIGIT 445
@ISPRINT
         445
@ISPROC
         445
@ISPUNCT
         445
@ISSPACE 446
@ISXDIGIT
         446
@JUNCTION 446
@LABEL 446
@LCS 446
@LEFT 446
@LEN 447
@LFN 447
@LINE 447
@LINES 448
@LINKS 448
@LOWER 448, 465
@LTRIM
       448
@MAKEAGE 449
@MAKEDATE 449
@MAKETIME 449
@MAX 450
@MD5 450
@MIN 450
@MONTH 450
@NAME 451
@NUMERIC 451
@OPTION 452
@OWNER
         452
@PATH 452
@PERL
      142, 452
@PING
      453
@QUOTE 453
```

@READSCR 453 @READY 453 @REGCREATE 454 @REGDELKEY 454 @REGEX 454, 496 @REGEXINDEX 454, 496 @REGEXIST 454 @REGEXSUB 455, 496 @REGQUERY 455 @REGSET 455 @REGSETENV 455 @REGTYPE 455 @REMOTE 456 @REMOVABLE 456 @REPEAT 456 @REPLACE 456 @REVERSE 457 @REXX 142, 457 @RIGHT 457 @RTRIM 457 @RUBY 143, 391, 458 @SCRIPT 458 @SEARCH 458 @SELECT 312, 458 @SERIAL 459 @SERVER 459 @SFN 460 @SHA1 460 @SHA256 460 @SHA384 460 @SHA512 460 @SHFOLDER 461 @SIMILAR 462 @SNAPSHOT 462 @STRIP 462 @SUBST 463 @SUBSTR 443, 463 @SUMMARY 462 @SYMLINK 463 @TIME 463 @TIMER 347, 463 @TRIM 464 @TRUENAME 353, 464 @TRUNCATE 464 @UNC 464 @UNICODE 464 @UNIQUE 465

@RANDOM 453

@UNQUOTE 465 @UNQUOTES 465 @UPPER 465 @VERINFO 465 @WATTRIB 86, 466 @WILD 466 @WINAPI 294, 410, 467 @WINCLASS 467 @WINEXENAME 467 @WININFO 384, 467 @WINMEMORY @WINMETRICS 468 @WINPOS 470 @WINSTATE 470 @WINSYSTEM @WMI 472 @WORD 472 @WORDS 473 @WORKGROUP 473 @XMLCLOSE 473 @XMLNODES 473 @XMLOPEN 474 @XMLXPATH 474 @YEAR 474 [] (wildcard) 77

\ backslash 117

^ caret 124, 126

? 380 _4VER 381 ACSTATUS 381 _ADMIN 381 _AFSWCELL 381 _ALT 381 ANSI 382 _BATCH 382

_BATCHLINE 382	_EXIT 386
_BATCHNAME 382	_EXPANSION 387
_BATCHTYPE 382	_FG 387
_BATTERY 382	_FTPERROR 387
_BATTERYLIFE 382	_HDRIVES 387
_BATTERYPERCENT 382	_HLOGFILE 387
_BDEBUGGER 382	_HOST 387
BG 382	HOUR 387
_BOOT 383	_ _HWPROFILE 388
BUILD 383	IDLETICKS 388
_CAPSLOCK 383	_ _IDOW 388
CDROMS 383, 386	_IDOWF 388
_CHILDPID 383	_ _IFTP
CI 383	IFTPS 388
_CMDLINE 383	_ _IMONTH 388
CMDPROC 383	_IMONTHF 388
CMDSPEC 383	ININAME 388
CO 383	_ IP 388
CODEPAGE 383	ISODATE 388
COLUMN 384	KBHIT 388
_COLUMNS 384	_ _LALT 388
CONSOLEPIDS 384	LASTDISK 389
_COUNTRY 384	_ _LCTRL 389
CPU 384	LOGFILE 389
_CPUUSAGE 384	_ _LSHIFT 389
CTRL 384	MINUTE 389
_CWD 384	_MONITORS 389
_CWDS 385	_MONTH 389
_CWP 385	_MONTHF 389
_CWPS 385	_NUMLOCK 389
_DATE 385	_OPENAFS 390
_DATETIME 385	_OSBUILD 390
_DAY 385	_PARENT 390
_DETACHPID 385	_PID 390
_DISK 385	_PIPE 390
_DNAME 195, 385	_PPID 390
_DOS 385	_RALT 390
_DOSVER 386	_RCTRL 390
_DOW 386	_READY 390
_DOWF 386	_REGISTERED 390
_DOWI 386	_ROW 390
_DOY 386	_ROWS 391
_DRIVES 386	_RSHIFT 391
_DST 386	_RUBYTYPE 391, 458
_DVDS 383, 386	_RUBYVALUE 391, 458
_ECHO 386	_SCROLLLOCK 391
_EDITMODE 386	_SECOND 391
_EXECSTR 386	_SELECTED 391

_SHELL 391 SHELLS 391 _SHIFT 391 _SHORTCUT 392 + plus sign 126, 381 _SHRALIAS 392 _STARTPATH 392 _STARTPID 392 392 _STDERR = equal sign 126, 381 _STDIN 392 == equality test operator 109 STDOUT 392 _STZN 392 STZO 392 _SYSERR 392 _TCFILTER 343, 392 16-bit Applications 66 _TCFOLDER 393 _TCTAB 393 _TIME 393 _TRANSIENT 393 4NT 9.0 3 $_{\mathsf{TZN}}$ 392, 393 4NT.GPF 475 _TZO 392, 393 4NT.INI 24, 388 _UNICODE 393 **4START** 101 393 _UTCDATE _UTCDATETIME 393 - A -UTCHOUR 393 _UTCISODATE 393 _UTCMINUTE **ABOVENORMAL** 331 393 AC line status 381 _UTCSECOND 393 ACTIVATE 152 394 UTCTIME 33 _VIRTUALPC AddFile 394 Administrator _VMWARE 381 394 _VXPIXELS 394 Advanced 45, 51 _VYPIXELS 394 Advanced .INI Directives AFS 103 _WINDIR 394 _WINFGWINDOW 394 Alias 33, 154, 222, 355, 408 Aliases 76, 120, 128, 137, 154, 222, 329, 355 _WINNAME 394 _WINSYSDIR AliasExpand 33 394 Alphabetic 444 _WINTICKS 394 Alphanumeric 444 _WINTITLE 394 Alt Key 381, 388, 390 _WINUSER 394 Alt-255 33, 104 _WINVER 394 _WOW64 394 Alt-Down 104 Alt-End 104 XPIXELS 394 _YEAR 394 Alt-Home 104 Alt-PgDn 104 YPIXELS 395 Alt-PgUp 104 Alt-Up 104 AND 120 ANSI 101, 510, 516, 518 120

ANSI X3.64 status CASE 335 382 App Paths Case Sensitivity 504 127 CD AppendToDir 117 177, 178 Archive 86, 494 CDD 178 Archive attribute CDPATH 72, 367 Argument 133, 134 CD-ROM 411 ASCII 409, 444, 510, 511, 522, 530 Cell Name 407 ASCII Tables 511 **Character Device** 416 **CHCP** ASSOC 162, 241, 409, 506 180 **ATTRIB** 86, 163 CHDIR 177 86, 163, 409, 466, 494 Child Process ID 383 Attributes Automatic directory change ClearKeyMap 41 Clipboard 32, 67, 412 CLOSE 152 - B -CLS 181 CM 331 Background Color 382, 518 CMD.EXE 132, 371, 484 Backspace 29, 104 CMD.EXE variables 372 382 Batch CMDLINE 368 Batch Debugger 139, 166, 174 331 CMSTDIO Batch file name 382 Code Page 180, 383 Batch File Parameter 133 COLOR 181 Batch File Parameters 327 Color Codes 518 Batch Files 128, 130, 131, 132, 133, 135, 137, 139, Color Dialog 412 141, 166, 382 Color Names 518 Batch Line Number 382 Color settings 181 BATCH.BCP 166 COLORDIR 368 BATCOMP 141, 166 Colors 382, 387 Battery 382 Columns 384 Battery charge 382 Command editing 104 **BDEBUGGER** 139, 166, 174 Command groups 121 BEEP 173, 292 Command History 33, 34, 35, 36, 106, 107, 108, BeginLine 29 251, 439 BELOWNORMAL 331 Command Line 50, 103, 104, 126, 383 Bksp 29, 104 Command Line Editing Keys 28, 32 BMP 462 Command names 109 Bookmarks 166 Command parsing 124, 134 383 Boot drive Command processor 383 BOTTOM 152, 362

- C -

BREAK

Build

BREAKPOINT

383

CALL 175 CANCEL 176, 301 Caps Lock 261, 383

137, 174, 282

166, 174

24

19

381

144

381

Command processor exit codes

Command processor options

Command Processor Version

CommandSep 120, 126, 381

135, 144

Command processor path

Commands By Category

Commands By Name

Command separator

CommandEscape
Commands 135

Comparison	Ctrl-Left 32, 104
case insensitive 109	Ctrl-PgUp 34
case sensitive 109	Ctrl-R 30, 104
numeric 109	Ctrl-Right 32, 104
string 109	Ctrl-shift right 104
Compatibility 126	Ctrl-shift-ins 104
Compiled batch files 166	Ctrl-shift-left 104
Compound Character 120	Ctrl-Shift-Tab 33
Compressed 86, 494	Ctrl-Tab 35
Compressed attribute 409	Ctrl-Up 36, 106
Compressed batch file 382	Ctrl-V 32
Compression 141	Ctrl-X 124, 126
Computer Name 394	Ctrl-Y 29, 104
COMSPEC 368	Current command line 383
Conditional commands 120	Current Working Directory 384, 385, 414
Conditional expression 109	Cursor 383
CONFIG.NT 131	Cursor Column 384
Configuration 24, 284, 323	Cursor Position 310, 384
Configuration Dialog 43, 46	Cursor shape 383
Console Window 413	CursorIns 383
Contact 477	CursorOver 383
Context Menus 65	
Control Key 389, 390	- D -
COPY 182, 274, 371	- U -
Copy (directive) 29	Date 189, 347, 388, 414
COPYCMD 371	Date Formats 127, 189, 406, 414
Copying Selected Text 67	Date ranges 80, 82
CopyPrompt 182	DATETIME 210
Copyright 537	Day
Country Code 384	of month 385
CPU 384	of week 386
Create Directory 271	of week (full) 386
Ctrl key 384	of week (integer) 386
Ctrl-A 35, 104, 117	of week (localized) 388
Ctrl-Bksp 30, 104	of year 386
Ctrl-Break 104, 137, 174	Day of Month 414
Ctrl-C 137, 174	Day of Week 417, 418, 439
Ctrl-D 33, 40, 106	Day of Year 419
Ctrl-Down 35, 106	Daylight Savings Time 386
Ctrl-E 34, 40, 106	Debug 41
Ctrl-End 30, 104	Debugger 54
Ctrl-Enter 35, 40, 106	Debugging 139, 166
Ctrl-F 33, 104	DEBUGSTRING 190
Ctrl-F1 34, 104, 251, 477	DEFAULT 335
Ctrl-Home 30, 104	Default Variables 222, 319, 357
Ctrl-K 36, 104, 106	DEFER 190
Ctrl-L 30, 104	DEFINED 109
Ctrll-C 104	DEL 190

Drive 491

Drive Type 419

Del (directive) 30 DELAY 194 - F -Delayed Variable Expansion 89 Delete 104 ECHO 132, 217, 219, 386 DelHistory 33 ECHOERR 218, 220 DELIMS (FOR command) 234 **Echoing** 132 DelToBeginning ECHOS 217, 219 DelToEnd 30 ECHOSERR 218, 220 DelWordLeft 30 Edit Menu 59 DelWordRight 30 Editing 104 **DESCRIBE** 195, 385 Editing keys 104 Description ranges EJECTMEDIA 220 DescriptionName 195, 385 ELSE 253, 254 Descriptions 86 ELSEIFF 254 Desktop 328 323 Enable Desktop Window 462 Encrypted 86, 494 DETACH 197, 385 Encrypted attribute 409 137 Detecting Encrypted batch file 382 Dialog 68, 69 End 31, 104 DIR 198, 288, 371 ENDDO 210 DIRCMD 371 EndHistory 34 Directories 492 **ENDIFF** 254 Directory 86, 117, 271, 494 EndLine 31 **Directory Aliases** 76 ENDLOCAL 220, 326 Directory attribute 409 ENDSWITCH 335 Directory Dialog 437 ENDTEXT 345 Directory History 34, 108, 118, 208 Enter 31, 41, 104 Directory Navigation 71, 73, 76, 209, 294, 299 Environment 222, 319, 357, 365 Directory Searches 72, 73, 177, 178, 370 **Environment Variables** 135 Directory Stack 71, 209, 294, 299, 416 EOL (FOR command) 234 DIREXIST 109 EQ 109 DIRHISTORY 208 EQC 109 209, 294, 299 DIRS EQL 109 DirWinOpen 34 EQU 109 Disable 323 ERASE 190 Disk serial number 459 EraseLine 31 DO 109, 210 Error 282, 392 DO (FOR command) 234 Error Messages 478 DO UNTIL 109 Error Text 420 DO WHILE 109 ERRORLEVEL 109, 282, 380, 395 DOS Applications 66 ERRORMSG 282 Down 30, 35, 106 478, 507 Errors Drag and drop Esc 31 DRAWBOX 214 Escape 33, 381 DRAWHLINE 215, 216 Escape character 124 DRAWVLINE 215, 216 124, 126, 141, 381 EscapeChar

154, 222, 355, 368, 369

223

ESET

EVENTLOG

EVENTMONITOR 224 **EXCEPT** 225 Exclusion ranges Exclusive OR ExecLine 31 Executable extensions 91 Executable Files 504 ExecWait 123 **EXIST** 109 EXIT 227, 386 Exit Code 24, 120, 380 Expand Aliases Extended Directory Searches 177, 178, 299, 370 **Extended Parent Directory Names** 118 **EXTPROC** 143

- F -

F1 34, 104, 251, 477 F10 33 F12 36 F3 106 F6 34 F7 35 F8 36 F9 35 FAT 491 FAT32 491 227 **FFIND** File completion 35, 36 File Dialog 438 File exclusion ranges 85 File Extension 425 File List 90 File Menu 58 File Names 490, 493 File Prompts 102 File Searches 89. 504 File selection 77, 91 File Streams 496 File Systems 490, 491 File Time Stamps 495 FILECOMPLETION 368 FileCompletion directive 115, 116 FILECOMPLETION variable 115, 116 Filename completion 113, 115, 116 117 Filename conversion Filenames 117

FILL 214 FIREWIREMONITOR 232 Folder Dialog 438 Folder Locations Folders 63 FOR 234 Foreground Color 387, 518 Foreground Window 394 FOREVER 210 Format Number 436 Format Text 435 FREE 241 FS 331 FTP 93, 255, 387 FTP.CFG 93 FTPS 93, 255, 387 162, 241, 437, 506 FTYPE **FUNCTION** 242, 356 Functions 365, 395, 397 **Functions Dialog**

- G -

GE 109 General Input Keys 28, 29 **GEQ** 109 GLOBAL 108, 245 Glossary 519, 520, 521, 522, 525, 526, 528, 529, 530, 531, 532, 533, 534, 535, 536, 537 GOSUB 247, 307 GOTO 248, 254 GΤ 109 GTR 109

- H -

Hard Link 272, 273 Hardware Profile 388 **HEAD** 249, 339, 354 HELP 34, 251, 477 Help Menu 61 HelpWord 34, 251, 477 here-document 98 Hidden 86, 494 Hidden attribute 409 HIDE 152, 362 HIGH 331

Highlighting Text 67 HistLogName 269 HistLogOn 269 History 33, 34, 35, 36, 251, 269, 368, 439 History Log File 387 HISTORYEXCLUDE 368 HistWinOpen 34 Home 29, 104 Host name 387 HTTP 92, 93 http://jpsoft.com/ 61 HTTPS 92, 93

- | -

IF 109, 253, 439 IFF 109, 253, 254 IFTP 93, 255, 387, 388 IM 260 Include lists 88 Indirect file 90 INIQuery 42 Initialization 24 Initialization files 24, 26 INKEY 257, 259 Inode 442 INPUT 257, 259, 300 Ins 31 Insert 31, 104, 383 Insert cursor 383 Insert cursor shape 383 Instant Message 260 Internal Commands 144, 147 Internal Variables 372, 373, 376 Internet 53, 92, 255 Introduction 16 INV 331 IΡ 443, 444 IP Address ipworks6.dll 93 ipwssl6.dll 93 ISALIAS 109 ISAPP 109 ISDIR 109 ISFILE 109 **ISFUNCTION** 109 **ISINTERNAL** 109

ISLABEL 109

ISO 9601 127 ISO date 385 ISWINDOW 109 ITERATE 210

- J -

JABBER 260
JavaScript 311
JP Software 477
jphelp.chm 477
JPSTREE.IDX 73, 177, 178, 299, 370
Junction (reparse point) 86, 272, 273, 446, 494
Junction (reparse point) attribute 409

- K -

Key Codes 510
Key Mapping Directives 28, 104, 106, 107, 113
Key Names 515
KEYBD 261
Keyboard 261, 388
Keyboard Shortcuts 64
Keypad 104, 510
KEYS 261, 515
KEYSTACK 102, 262

- L -

Label 360, 446, 494 Language 42 LanguageDLL 42 LastHistory 34 LE 109 LEAVE 210 LEAVEFOR (FOR command) 234 Left 31, 104 Length limits 126 LEQ 109 LFN 35, 89, 117, 493 LFNToggle 35, 117 490 Limits Line Continuation 141 LineToEnd 35 Link 272, 273 LIST 37, 38, 39, 264 LIST Keys 28, 36

List View 63 ListBack 37 ListClipboard 37 ListContinue 37 ListExit ListFind 37 ListFindRegex 38 ListFindRegexReverse 38 ListFindReverse ListHex 38 ListHighBit 38 ListInfo 38 ListNext 38 ListOpen 39 ListPrevious 39 ListPrint 39 39 ListRefresh ListUnicode 39 ListWrap LOADBTM 269 Local 108 LocalAliases 154 LOG 269 Log File 389 Log Off 303 LogErrors 269 109 Logical expression Logical operator 109 LogName 269 LogOn 269 Long File Name 89 Long Filename 117 Longest Common Sequence 446 LOW 331 **Lower Case** 448 LSS 109 LT 109

- M -

MailAddress 316
MailPassword 316
MailPort 316
MailServer 316
MailUser 316
MAX 152, 331, 362
MD 271
MEMORY 272

Menus 58, 59, 60, 61 Message Box 279 Metacharacters MIN 152, 331, 362 Minute 389 MKDIR 271 MKLINK 272 MKLNK 273 388, 389, 450 Month More? 121 Mount Point 407 MOVE 182, 274 **MSAA** 43 MSAAMenu 43 MSGBOX 279 Multiple Commands 120 Multiple filenames 87

- N -

Navigation 370 NE 109 NEQ 109 Nesting Level 382 **Network Drive** 456 NextFile 35 NextHistory 35 Normal 86, 331, 494 Normal attribute 409 NormalEditKey 35 NormalKey NormalListKey NormalPopupKey 40 NOT 109 Not content-indexed 86, 494 Not content-indexed attribute 409 NOTOPMOST 152, 362 NTCMDPROMPT 131 NTFS 491, 496 NTFS Links 448 NTFSDescriptions 195 Num Lock 261 NumLock 389

- O -

Offline 86, 494

Offline attribute 409 137, 282 ON Online Help 477 OpenAFS 103, 381, 390, 407, 408, 491 OPTION 284, 452 Options 43, 44, 45, 47, 49, 50, 51, 53, 54 Options Menu 61 OR 120 OSD 286 Overstrike 31, 383 Overstrike cursor shape 383 Overview

- P -

Page and file prompts 102 Page prompts 102 Parameter 134 Parameter quoting 134 ParameterChar 126, 133 Parameters 109, 133 Parent Directory 118 Parent process 390 Parsing 124, 134 Paste 32, 67 Path 286, 368, 452 PATHEXT 369 PAUSE 287 PDIR 198, 288 Perl 142, 452 PerlScript 311 PGM 331 PgUp 34 453 Ping 97 Pipes Piping 96, 97, 101 Pixels 394, 395 Platforms 477 PLAYAVI 291 PLAYSOUND 173, 292 PLUGIN 293 POPD 209, 294, 299 **PopFile** 35 Popup Window Keys 28, 40 Popup Windows 507 PopupWinDel 40 **PopupWinEdit** PopupWinEditWin 40

PopupWinExec 41 POS 152, 331, 362 POST EXEC POSTMSG 294 PRE_EXEC 154 PRE_INPUT 154 precision 420 PrevFile 36 PrevHistory 36 Primary 26, 391 PRINT 295 PRIORITY 295 Process ID (PID) 197, 342, 383, 385, 390, 392 PROMPT 297, 369 PUSHD 209, 294, 299

- Q -

QUERYBOX 300 QUIT 176, 301 Quotes 465 Quoting 134

- R -

RAM 272 Random 453 Ranges 80, 82, 84, 85, 86 RD 301 Read-only 86, 494 Read-only attribute 409 REALTIME 331 **REBOOT** 303 Recall 106 RECYCLE 304 Recycle Bin 190, 301, 304, 369 RECYCLEEXCLUDE 369 96, 97, 98, 392 Redirection Redirection and Piping 97 Reference 484, 504, 510 Registration 46, 55, 474 Registry 222, 319, 357 Create 454 Delete 454 Exists 454 455 Query Set 455

SERVICES Registry 222, 319, 357 319 Set (broadcast) 222, 319, 357, 368, 369 455 SET Regular Expressions 454, 455, 496 SETDOS 323, 383 Relational expression 109 SETLOCAL 220, 326 Relational operator Setting colors 181 REM 304 Setup 474 Remark 304 SFN 35, 89, 117, 408, 493 Remote Drive 456 SHADOW 214 Removable Drive 456 Shape 383 Removable Media 220 SHARED 331 Remove Directory Sharenames 420 301 274, 305 REN SHEBANG 143 **RENAME** 305 SHIFT 327 RepeatFile 36 Shift Key 389, 391 Resizing Shift right 104 68 RESTORE Shift-left 104 152, 362 36 RETURN 247, 307 Shift-Tab REXEC 308, 309 Short file name 460 Short Filename REXX 142, 457 117 SHORTCUT Riaht 32, 104 328 RMDIR 301 Shortcuts 64, 328 Row 390 SHRALIAS 329.392 Rows Shutdown 303 391 RSHELL 308, 309 SIZE 331, 362 Ruby 143, 391, 458 Size ranges 80, 82 Run Program Dialog SKIP (FOR command) 234 SMPP 330 SMS 330 - S -SNMP 330 SNPP 331 Save Window 462 Soft Link 272, 273 SaveHistory Sparse file 86, 494 Scan Codes 510 Sparse file attribute 409 SCREEN 310, 311 Special Character Compatibility 124, 126 Screen Reader 43 Standard Error 97, 98, 101, 392 Screen resizing 68 Standard Input 97, 98, 101, 392 Screen Size 394, 395 Standard Output 97, 98, 101, 392, 424 SCRIPT 311 START 123, 331, 392 391 ScrLk Starting applications 122 Scroll Lock 261, 391 Startup 17, 47 Scrollback Buffer 66 Startup command 19 SCRPUT 310, 311, 360 Startup Directory 392 Second 391 Startup drive 383 Secondary 26, 391 Startup Options (Take Command) 17 SELECT 312, 458 Startup options (TCC) SENDMAIL 316 Status Bar 64 SEPARATE 331 Status test 109 Servers 419 98, 218, 220 stderr SERVICEMONITOR 318

stdin 98 98, 217, 219 stdout Stopwatch 463 Streams 496 String Processing 139 String substitution 372 Subdirectories 492 Subroutine 247, 307 Substrings 372 Supported Platforms SwapScrollKeys 106 SWITCH 335 **Switches** 91 Symbolic Link 407 symbolic link (reparse point) 463 symbolic links 272 SYNC 336 Syntax Coloring 166 86, 494 System System attribute 409 System Errors 507 System Metrics 468 System Variables 222, 319, 357, 367

- | -

TCMD.INI

24

35 Tab **Tab Configuration** Tab Toolbar Dialog 69 Tab Window 393 Tab Windows 64 Tabs menu 60 249, 339, 354 TAIL Take Command 9.0 **Take Command Dialogs** 68 Take Command Interface 56 Take Command Menus 58 Take Command Tabs Take Command Window **Take Command Windows Configuration** 43 TASKDIALOG 341 **TASKEND** 342 TASKLIST 342 TC Scrollback Buffer Keys 28 TCEXIT 22 TCFILTER 343 TCMD 370

TCMD32.GPF 475 TCMD32.INI 24, 388 TCMDVER 370 TCSTART 22. 101 TCTOOLBAR 343 Technical Support 475 TEE 344, 364 TEMP 370 Temporary 494 Temporary attribute 409 Temporary file **TEXT** 345 **TFTP** 93 THEN 254 189, 347, 393, 463 Time Time ranges 80.84 Time Stamps 495 Time Zone 392, 393 347, 463 TIMER 152, 349, 362, 370, 394 TITLE TITLEPROMPT 370 TMP 370 TOKENS (FOR command) 234 Tool Bar 62, 343 Toolbar Dialog TOP 152, 362 TOPMOST 152, 362 TOUCH 349 TRANS 362 TRANSIENT 352 Transient Shell traps 330 TRAY 362 TREE 352 Tree view 63 TREEEXCLUDE 73, 370 Troubleshooting 474, 475 TRUENAME 353, 464 **TYPE** 339, 354

- U -

UNALIAS 154, 222, 355 UNC 464, 491 UNFUNCTION 242, 356 Unicode 393, 464 Unique File Name 465 UNKNOWN_CMD 154, 355, 504 UNSET 222, 319, 357, 368, 369 UNTIL 210 Up 32, 36, 106 UpdatelNI 43 Updates 55 Upper Case 465 URL 92 USBMONITOR 358 User 394 User Variables 222, 319, 357 Utilities Menu 61

- V -

Variable 397 Variable Expansion 36, 89 Variable Functions 395, 397 Variable Functions by Category 401 Variable name completion 119 VARIABLEEXCLUDE VariableExpand Variables 135, 222, 319, 357, 365, 367, 372, 373, 376 VBScript 311 VER 359 VERIFY 360 Version 359, 381, 386, 390, 465, 537 VFAT 491 Virtual Screen 394 VirtualPC 394 **VMWare** 394 VOL 360 Volatile Variables 222, 319, 357 360, 491 Volume Volume ID 408 Volume Name 408 **VSCRPUT** 311, 360

- W -

WAIT 331
Waiting for applications 123
What's New 3
WHICH 361
WHILE 210
Wildcards 77, 466
WIN 331, 362

Window 152, 362 Class 467 Position 470 State 470 Window Title 394 Windows 49 Windows API 467 Windows Directory 394 Windows File Associations 506 Windows Management Instrumentation 472 Windows Memory 468 Windows Parameters Windows System Directory 394 Windows System Errors 507 Windows System Metrics 468 Windows Version WMIQUERY 364 WordLeft 32 WordRight 32 Workgroup 473

- X -

X3.64 101, 510, 516, 537 XML 502 XOR 537

- Y -

Y 344, 364 Year 394, 474

- Z -

ZOOM 214