The Elements of Linear Algebra Volume One: Livre des Lignes Droites

Theron J Hitchman

Fall 2017

## Contents

To the Student:	V	
The Equation of a Line in the Plane	1 29	
The Equations of a Line in Space		

## CONTENTS

#### To the Student:

So. I am writing this book. (Let's not pretend I am done. You can see the state it is in.) There are dozens (hundreds?) of introductory linear algebra books, so it is pretty reasonable to ask why I am putting in the effort, and in the meantime, causing this much pain. I should explain.

I have taught linear algebra many times and I have liked some books, but never loved one. The closest match for what I wanted to teach is Strang's *Introduction to Linear Algebra*, and I am sure that people who have read that will see some influences here. But my students never seemed to connect with Prof. Strang's enthusiastic, stream-of-consciousness prose. And over time, I found that the things I need to emphasize for my students just don't match with that text, or any other.

In addition, most textbooks assume a certain class structure: lectures accompanied by weekly homework, with some exams. I don't want to run our course that way.

So this book is my solution. It is my attempt to make a thing which matches how I want our class to run.

Here is what you should expect. This book has the basics of linear algebra, done thoroughly. I want this to help you see why some very basic, important things are done the way they are. It is amazing how much of the subject of linear algebra can be done by focusing on small examples, that is, in small dimensions. (We'll learn about dimension later on.) We'll sort out other things through assignments and class discussions.

It is important to read this book actively. If you haven't learned how to read a math text before, there are some key ideas:

#### TO THE STUDENT:

**Time** Mathematics is often technical and tricky. It takes time to absorb. Plan to give yourself lots of time to read and think. And don't be surprised if you have to read some section more than once. (This is not a novel. As much as I see it as a story, it won't sweep you away.)

Examples In the interest of brevity, I have streamlined the exposition. In particular, there are no examples. The point is that you should make your own. This is so important a skill that it is basically a mathematical super-power. Whenever you come across an idea, if you understand it or not, you should make some very explicit examples and consider them carefully.

Questions As part of your active engagement with the text, you will find things that don't quite make sense, yet. This is normal. The mathematician's best approach then is to (1) write down a specific question or two about the confusing bit, and (2) talk to other people about it. You are fortunate that you have an instructor and classmates to talk to. Make lists of questions and try to get them answered!

The real beauty in linear algebra is the tight set of connections between algebra and geometry. I hope you enjoy it.

### The Equation of a Line in the Plane


Let's recall the idea of the plane from classical geometry: the plane is like a flat sheet of drawing paper, which extends indefinitely in all directions without bound. It is the playground for lots of serious considerations from high school: points, lines, circles, triangles, rectangles, and various other doodles live in it. I say in it rather than on it, because all of those objects really have their existence inside the plane. If we were to say "on the plane" then one might think of them as sitting on top of the paper, where a light breeze might move them about. No, those things live inside the plane just as sure as you and I live inside the universe.

And while all of that is evocative and romantic, it doesn't make doing mathematics any easier. Our aim in this first chapter is to do some concrete mathematics: we want to figure out how to describe a single line in the plane very carefully. To do this, we will use tools that René Descartes taught us: coordinates. Better yet, we will use an update of the idea and introduce vectors. Our work has to rely on something, so at some points we will make use of geometry facts you learned in high school. But for all of the points and vectors, angles and dot products, we will go straight to the heart of a single important question:


How can we clearly describe a single line in the plane with an equation?

# THE EQUATION OF A LINE IN THE PLANE POINTS, VECTORS, AND VECTORS

You have likely seen the idea of  $Cartesian\ coordinates$  on the plane before. To be clear, let's set things down carefully. In the plane, we choose a pair of perpendicular lines which meet at a point O. This special point is called the origin. Then, we choose a point X on one of the lines and draw the circle centered at O which passes through X. Note that this circle meets our two lines in two points each, four points total, one of which is the point X. Then, from X, we rotate around the circle by a quarter turn counterclockwise until we hit one of the points on the other line. This new point we will call Y. Are you drawing with me? Here is my picture so far.



We call the line OX the x-axis and the line containing Y the y-axis. Here comes the amazing part: we declare the circle we used to be of unit size, and make the lines OX and OY into number lines! The important part is that the point O should represent 0 on both number lines, and the points X and Y should each represent 1 on their lines. So, instead of marking things with O, X, and Y, we put down marks where X and Y are and label them with 1's, and add little arrows marked with X and Y near the positive "ends" of the lines OX and OY, respectively.



Note that above I have done something a bit silly and let the picture just fall on the paper in an unusual way. I really mean unusual as "not usual." The usual way arranges the lines on the paper to match our expected horizontal (x) and vertical (y) directions. This isn't actually required, but it is what everyone always does. The typical picture looks like Figure 1.




Figure 1: The Standard Cartesian Coordinate System

Now suppose we have some point in the plane, let's call it P. We can describe the location of P relative to our two lines in a simple way. First, we draw a line through P which is parallel to the y-axis and perpendicular to the x-axis. The foot of this perpendicular hits the x-axis at some point A. But this point A

is part of the number line OX, so it has an associated real number, which we will call a. So the point A is instead marked with the label a from this number line.

Similarly, we draw a line through P parallel to the x-axis and perpendicular to the y-axis. The foot of this perpendicular hits the y-axis at some point B, which is part of the number line OY. We denote the number associated to B by b. Again, the point is labeled with the number b from the number line.




Figure 2: A point P and its coordinates (a, b).

So, to identify the point P, we can instead give the pair of numbers a and b. These numbers are called the *coordinates* of P. Of course, the order of the coordinates matters, so we make what we call an *ordered pair* (a,b) to keep things straight, where the x-coordinate comes first, and the y-coordinate comes second. Note that in Figure 2 the x-coordinate a is negative, but the y-coordinate b is postive.

This whole process is reversible, too. If we pick a pair of numbers c and d, in order, then we can find a point in the plane which corresponds, and we can do it unambiguously. Find the spot labeled c on the x-axis number line and construct a line perpendicular to the x-axis through this point. Similarly, find the spot labeled d on the y-axis and construct a line perpendicular to

the y-axis through this point. The two lines you just drew will meet in exactly one point Q, and Q will have coordinates (c, d).

This setup of coordinates on the plane allows us to formalize a wonderful and useful idea from physics, too. Physicists use the concept of a *vector* to describe something (like the wind) which has both magnitude or size (like how fast the air is moving) and direction (which way the air is going). Usually, vectors are drawn as little arrows: the arrow has a direction, and it has a length which represents its magnitude. It is possible to draw vectors which have the same direction but different lengths, and vice versa.

We can use coordinates to describe vectors in the plane, too. Here's how: A physicist's vector v is some arrow in the plane. That arrow has an initial point P, called its tail, and a final point Q, called its head. We can write the coordinates of these points as P = (a, b) and Q = (c, d).




Figure 3: Coordinates for a physicist's vector v.

Then the coordinates of v are taken to be the numbers c-a and d-b, which we interpret how much v acts in the directions parallel to the x-axis and the y-axis, respectively. Note that in Figure 3, the y-coordinate is negative, since b>d.

These coordinates have a hint of algebraic manipulation in them. Those subtractions line up almost like we could write v = (c - a, d - b) = (c, d) - (a, b) = Q - P. But v is a vec-

tor, and if we write it like (c-a,d-b), it looks like the notation for a point. We should not do that because it could get confusing. Furthermore, that "equation" would mean that we are subtracting points and creating a vector, which is also weird. Still, there is something to it. We will return to this idea soon.

For now, let's focus on a bit of ambiguity in the physicist's idea of a vector. Where should that vector be? That is, given the coordinates of a vector in the plane, it is not clear where to draw it! I can slide a vector around the plane, and as long as I keep it parallel to the original, the coordinates won't change. So, unlike with the coordinates of a point, the coordinates of a vector do not uniquely specify the vector.

The mathematician's special fix is this: we simply declare all our vectors to have their initial points, their tails, at the origin O, of our coordinate system. That curtails some of the (admittedly useful) freedom in the physics notion, but it also lets us be more clear.




Figure 4: The physicist's vector vs. the mathematician's vector.

But it pays to keep in mind that the physicists conception of the vector V with coordinates c-a and d-b could be one of many different arrows, while the mathematician's vector v is the arrow from the point O = (0,0) to the point (c-a,d-b).

Now we have circled back around to a muddle. If a mathematician's vector is always based at O, we only need to specify where the head of the vector is...which is just a point. So, how is a vector supposed to be different from a point, again?

This confusion of three different, shifting, partially-overlapping interpretations causes some trouble to the new learner. Professionals tend to pass back and forth between these and use them flexibly to get results. Once you have gotten used to the ideas, you will, too. You should watch out for these instances where the words point and vector get interchanged. If they cause you trouble, remember that we have three different things, which are closely related.

For now, the simplest way to handle things is like this:

- Ignore the physicist's version of the word vector as much as possible.
- A point is a location in the plane, and represented by coordinates in the form of an ordered pair of numbers (a, b).
- A vector is an arrow based at the origin, which can be specified by the coordinates of its head. To keep this separate from the idea of a point, we will write it differently, with the numbers stacked vertically like this:  $\binom{a}{b}$ .
- Always remember that for each point in the plane, there is a unique mathematician's vector which corresponds, and vice versa.

With this in mind, we make our first official definition.

**Definition 1.** A 2-vector is a vertical stack of 2 real numbers, like so:

$$v = \begin{pmatrix} a \\ b \end{pmatrix}$$
.

The collection of all such 2-vectors is called the plane, and written with this notation:  $\mathbb{R}^2$ .

The notation  $\mathbb{R}^2$  is often read "arr-two," and many people use that language interchangeably with "the plane." Also, most of the time we will just say "vector," rather than "2-vector."

# THE EQUATION OF A LINE IN THE PLANE VECTOR ALGEBRA

Let's return to that glimpse of subtraction we saw in Figure 3. We saw there that for points P=(a,b) and Q=(c,d), the vector v from P to Q has coordinates c-a and d-b. This looks almost like we subtracted the points to get Q-P=v. Can we use that? The weird part is that it mixes up points and vectors. So, we will just change viewpoints, and instead think of P and Q as (mathematician's) vectors. To keep things clear, let's introduce new labels.

$$p = \begin{pmatrix} a \\ b \end{pmatrix}, \quad q = \begin{pmatrix} c \\ d \end{pmatrix}$$

If we put these together on the plane with the physicist's vector v from p to q and the mathematician's v we see a wonderful triangle, and an extra vector. So we see a way to talk about subtracting




Figure 5: Subtraction of vectors

vectors: Given two vectors p and q as above, their  $\emph{difference}$  is the vector

$$V = Q - P = \begin{pmatrix} c \\ d \end{pmatrix} - \begin{pmatrix} a \\ b \end{pmatrix} = \begin{pmatrix} c - a \\ d - b \end{pmatrix}.$$

Geometrically, we draw the arrow from p to q and then translate it down so that its tail is at the origin O = (0,0). Of course, the order of p and q in this operation matters. If we switch them, we get an arrow pointing in the opposite direction.

If we can subtract vectors, surely we can add vectors. How would that work? Algebraically, if v = q - p, then we expect q = v + p by rearranging. That would mean

$$q = \begin{pmatrix} c \\ d \end{pmatrix} = v + p = \begin{pmatrix} c - a \\ d - b \end{pmatrix} + \begin{pmatrix} a \\ b \end{pmatrix},$$

which all fits. It looks like addition should be defined coordinateby-coordinate.

**Definition 2** (Addition of Vectors). Let  $p = \binom{a}{b}$  and  $q = \binom{c}{d}$  be two vectors in  $\mathbb{R}^2$ . Their sum is the vector

$$p+q = \begin{pmatrix} a+c \\ b+d \end{pmatrix}.$$

**Theorem 3.** Addition of vectors satisfies the same rules as addition of real numbers:

- when adding more than two vectors, it doesn't matter which operations you do first: (p+q)+r=p+(q+r);
- one can add in either order p + q = q + p;
- the vector o corresponding to the origin O is a "zero" since p + o = o + p = p;
- for each vector p, there is an opposite vector -p so that p + (-p) = o.

Remember that you are supposed to read actively. You can draw all of these pictures and try out all of these things with specific examples that you invent. You should check these by making examples and working out the details. Can you also draw the pictures which go with your examples?

But what about subtracting geometrically? In Figure 5, I have a strong desire to complete the figure by joining the loose end of v to the rest of the figure. If we draw the arrow from the head of v to the head of q, we get this:




Figure 6: Subtraction of vectors

What should the label on the dashed vector in Figure 6 be? Just as the physicist's v and the mathematician's v are parallel, this new vector is parallel to the mathematician's vector p. So the dashed vector must be a physicist's version of p. Then we see q = v + p.

Now we know how to add geometrically: to add two vectors u and v, translate v until its tail is on the head of u, then draw a new vector u + v as the vector from the tail of u to the head of this translated v. It just repurposes the structure of Figure 6.




Figure 7: Geometric Addition of Vectors

This is sometimes called the  $parallelogram\ rule$  for addition of vectors.

There is another useful operation on vectors called *scalar multiplication*. The terminology comes from physics (again) where a *scalar* quantity is just a number, and not a vector. So "scalar multiplication" means to multiply a vector by a scalar.

**Definition 4** (Scalar Multiplication for vectors). Let  $p = \begin{pmatrix} a \\ b \end{pmatrix}$  be a vector in  $\mathbb{R}^2$ , and let  $\lambda$  be a real number. Then the scalar multiple  $\lambda p$  is defined to be

$$\lambda p = \begin{pmatrix} \lambda a \\ \lambda b \end{pmatrix}$$

If you have never seen the symbol  $\lambda$  before, it is an old Greek letter pronounced "lamb-duh." It is traditional to use it in linear algebra in lots of places. Welcome to the  $\lambda$ -club. Oh, there are others, too, like  $\mu$ , which is pronounced "myoo."

Again, this operation has some important similarities to the familiar multiplication of numbers, but because it combines a scalar (a number) with a vector (not a number, exactly) to produce another vector (again, not a number) things are a little different.

**Theorem 5.** Suppose that p and q are vectors, and  $\lambda$  and  $\mu$  are numbers. Scalar multiplication has the following properties:

- Scalar multiplication distributes over vector addition:  $\lambda(p+q) = \lambda p + \lambda q;$
- Scalar multiplication distributes over scalar addition:  $(\lambda + \mu)p = \lambda p + \mu q$ ;
- Scalar multiplication and regular multiplication can be done in either order:  $\lambda(\mu p) = (\lambda \mu)p$ ;
- if  $\lambda = 0$ , then  $\lambda p = 0p = o$  is the zero vector.
- if n is a counting number, then np is the same thing as adding together n copies of p. In particular, 1p = p.

This Theorem, like the last one, just says that a bunch of natural things you expect to happen really do happen. When you study **Modern Algebra**, making lists of these kinds of properties will be really useful. So far, we have collected up the properties that describe a *vector space*.

What is the geometry of scalar multiplication? It corresponds to stretching (or shrinking) a vector, without changing its direction. Let  $\lambda$  be a non-zero number. Since

$$\lambda p = \lambda \begin{pmatrix} a \\ b \end{pmatrix} = \begin{pmatrix} \lambda a \\ \lambda b \end{pmatrix},$$

we see that the ratio of the two coordinates of a vector doesn't change under scalar multiplication. This means that p and  $\lambda p$  point in the same direction. One can see this by considering similar triangles with sides parallel to the x-axis, the y-axis, and p.




Figure 8: Similar triangles and scalar multiplication,  $\lambda > 1$ 

The triangles in Figure 8 are similar: their corresponding horizontal and vertical sides are parallel, and those pairs of sides have a common ratio. We learn that p and  $\lambda p$  lie in the same line.

Now we are getting somewhere! We want to understand lines in the plane, and we have just discovered how scalar multiplication relates to lines which pass through the origin, O.

By the way, this picture helps explain the terminology. The vector  $\lambda p$  is a rescaled version of p. A scalar is a thing which scales vectors.

#### LINES AS PARAMETRIC OBJECTS

We see that for a non-zero vector p, and a non-zero number  $\lambda$ , the vectors p and  $\lambda p$  lie on the same line through the origin, O. But this doesn't depend on which number  $\lambda$  we choose. So if we vary  $\lambda$ , we will get lots of different points on that line. The picture looks something like this one:




Figure 9: The points on a line:  $\lambda p$  for different  $\lambda$ 

This leads us to what is called a parametric description of the line. We think of some variable, say t, as a parameter. (I chose t here so that we think of it as "time.") As we change the value of t, the vectors tp trace out the line which goes through the origin and the point which is the head of the vector p.

**Theorem 6** (parametric lines through the origin). Suppose that P = (a, b) is some point in the plane. The the line which passes through the origin O and the point P consists of the heads of all the vectors

$$tp = t \begin{pmatrix} a \\ b \end{pmatrix},$$

where t varies over all real numbers. That is, this line is the set of the heads of all scalar multiples of the vector p corresponding to P.

This, is fantastic. We can use simple vector algebra to describe

any line through the origin. What about lines that are not through the origin? Suppose we just have two random points P and Q, neither of which is the origin, and we want to describe the line  $\ell$  through P and Q?

Again, let's think of the points on this line  $\ell$  as the heads of mathematics-style vectors. If we put in the vectors p and q which correspond to the points P and Q, we get a good picture like this one.




Figure 10: Working toward a parametric line, part 1

Each point in Figure 10 is the head of a vector from the origin to that point. In particular, the point P is the head of the vector p. So if we add -p to every single one of these vectors, we will move the whole line  $\ell$  in the direction of -p and with the same distance as -p. That will make a new line,  $\ell'$ , and the point which comes from P will land on the origin.

Since q is one of the vectors with its head on the original line, the vector q-p will have its head on the new line. But q-p has its tail at the origin! So, our new line passes through the origin and the head of the vector q-p, and we are in a situation to apply Theorem 6.

By Theorem 6, the line  $\ell'$  is described as all of the points which




Figure 11: Working toward a parametric line, part 2

are heads of vectors of the form t(q-p), where t is a parameter which is allowed to vary over all real numbers. But we get from  $\ell'$  back to  $\ell$  by simply adding the vector p back in. So, our original line  $\ell$ , which goes through the heads of vectors p and q, is described as the set heads of the vectors

$$p + t(q - p),$$

where t is a parameter which is allowed to vary over all real numbers. Now, let's sum up what we have learned.

**Theorem 7** (parametric line). Let P = (a,b) and Q = (c,d) be two points in the plane. The line which passes through these two points can be described as the heads of all vectors of the form

$$p + t(q - p) = \begin{pmatrix} a \\ b \end{pmatrix} + t \begin{pmatrix} c - a \\ d - b \end{pmatrix},$$

where t is a parameter which is allowed to vary over all real numbers.

Note that this theorem actually includes the previous one as a special case. If one of our points happens to be the origin, we simply use P = O, which corresponds to the zero vector, and this description collapses back into the one we found earlier. In either case, the vector v = q - p is called a direction vector for the line.

As a bit of a palate cleanser, let's answer this: Suppose you are given a line described as in the last theorem. How would you sketch it in the plane? The simplest method is to choose two different values of t, use them to generate to points on the line, plot those points, and trace the line through them. Which values of t should you choose? It is often convenient to use t=0 and t=1.

In fact, a parametric description can (perhaps "should") be thought of as describing the motion of a vector or point in the plane. The parameter t should be thought of as time. As the time changes, the location of the vector (or point) in the plane changes. This creates a kind of function, which is sometimes written like so:

$$t \mapsto p + t(q - p)$$

The input time t is some real number, and the corresponding output is the vector p + t(q - p) in  $\mathbb{R}^2$ . For any fixed t, our function gives us the "location of the moving point at time t." You can think of running through all of these different pictures, in sequence, as a movie showing the motion of our vector (or point). Then the line is like a time-lapse photograph which traces out the whole motion.

Note that at time t=0, we have the location  $0 \mapsto p+0(q-p)=p$ , and at time t=1, we get the location  $1 \mapsto p+1(q-p)=q$ . So it makes sense to think of our parametrized line as describing motion "from p to q." And the whole time, the direction of motion is exactly v=q-p: from p to q in the physicist's sense.

#### LENGTHS AND ANGLES IN THE PLANE

What should we mean by the "length" of a vector u in  $\mathbb{R}^2$ ? The most natural thing is to use the notion of the length of the line

segment from the tail to the head — the regular length of the arrow involved. This natural thing is just what we want, but because we wish to generalize it later, it will be best to give it an unusual name: the *norm* of a vector.

How shall we understand it? The key comes from looking upon Figure 8 with new eyes. There we see a vector in  $\mathbb{R}^2$  as the hypotenuse of a right triangle having its legs parallel to the two coordinate axes.




Figure 12: The Norm of a vector

These two legs then have lengths which are equal to our two coordinates, respectively. So we can compute the length of the arrow by the Pythagorean Theorem. Now that we understand what we want, we can make our definition.

**Definition 8** (Norm of a vector). Let  $u = \begin{pmatrix} a \\ b \end{pmatrix}$  be a vector in  $\mathbb{R}^2$ . The norm of u is the number

$$||u|| = \sqrt{a^2 + b^2} \,.$$

It is important to remember that the norm is a number, but never a negative number. Also, the only vector which has norm equal to zero is the zero vector. We shall often have the occasion to use norms of vectors as scalars in forming linear combinations.

As long as we have the concepts of norm and scalar in front of us, let us investigate how those interact. If  $\lambda$  is a scalar, then how

do the norms a vector u and the rescaled  $\lambda u$  compare? Let's write our vector in the form  $u = \begin{pmatrix} a \\ b \end{pmatrix}$ . Then we can do the following straightforward computation:

$$\|\lambda u\| = \|\lambda \begin{pmatrix} a \\ b \end{pmatrix}\| = \|\begin{pmatrix} \lambda a \\ \lambda b \end{pmatrix}\| = \sqrt{(\lambda a)^2 + (\lambda b)^2} = |\lambda| \|u\|$$

This conforms to our basic ideas about scalar multiplication. If we rescale a vector, we are really just changing its length by that factor. (And then there is the worry over the sign of the scalar, because lengths must not be negative.)

In a terrible linguistic collision, the most useful role for the norm of a vector is in the process of normalizing that vector. Beware, mathematics has several words that are overused! Norm, normal, normalize, normalized and other forms of this are a prime example. To normalize a vector u, we multiply it by the scalar  $||u||^{-1}$ , and thus produce a new vector u/||u|| which points in the same direction as u, but has norm equal to 1. This is because we can use our observation just above about how norms interact with scalar multiplication to compute:

$$|||u||^{-1}u|| = ||u||^{-1}||u|| = 1.$$

That last multiplication is just a multiplication of numbers. Note that all of that only makes sense as long as u is not the zero vector. If u is the zero vector, its norm is ||u|| = 0. Since it makes no sense to divide by zero, it is not possible to normalize the zero vector.

Just to make sure all of this stays confusing for learners, mathematicians call a vector with norm equal to 1 a *unit vector*.

To sum up: given a non-zero vector u, it is possible to normalize it, which means to replace it with the vector  $u/\|u\|$ , which is a unit vector.

Now that we are talking about proper geometry with length, can we find a way to measure the angle between two vectors? We can, if we use some trigonometry. We will use the following three facts: 1. Each point on the unit circle can be represented as a point of the form  $(\cos(\alpha), \sin(\alpha))$  for some angle  $\alpha$  between 0 and  $2\pi$ , so the corresponding vector can be written as  $p = \begin{pmatrix} \cos(\alpha) \\ \sin(\alpha) \end{pmatrix}$ .




Figure 13: Trigonometry for points on the unit circle

2. The function  $\theta \mapsto \cos(\theta)$  associates each angle in the interval  $[0, \pi]$  to a unique real number in the interval [-1, 1], and vice versa. For us, this means that it to measure an angle, we can get away with instead finding the cosine of that angle.




Figure 14: Part of the graph of  $y = \cos(\theta)$ 

3. There is an identity on trigonometric functions that helps us deal with the the cosine of a difference of angles: If  $\alpha$  and  $\beta$  are two angles, then

$$\cos(\beta - \alpha) = \cos(\alpha)\cos(\beta) + \sin(\alpha)\sin(\beta).$$

So, let us consider the angle between two vectors, u and v, in  $\mathbb{R}^2$ . First, the angle between these vectors does not depend at all on their lengths. If we change one, or both, of the vectors by rescaling them, that will not change the directions involved, and hence will not change the angle we seek. We can get to a more uniform set up for our task by normalizing u and v. Thus we will instead consider the unit vectors  $u/\|u\|$  and  $v/\|v\|$ , and look for the angle  $\theta$  between them.

Since our vectors are unit vectors, we can represent them with trigonometric functions:

$$\frac{u}{\|u\|} = \begin{pmatrix} \cos(\alpha) \\ \sin(\alpha) \end{pmatrix}, \qquad \frac{v}{\|v\|} = \begin{pmatrix} \cos(\beta) \\ \sin(\beta) \end{pmatrix}.$$

Let's suppose that the angle  $\beta$  that v makes with the x-axis is larger than the angle  $\alpha$  that u makes with the x-axis. Then we want to find the angle  $\theta = \beta - \alpha$ .




Figure 15: Finding the angle between two vectors.

Since cosine is such a nice function on  $[0, \pi]$ , it will do to first try

to find  $\cos(\theta)$ . But then we can simply apply the angle difference formula for cosine to see

$$cos(\theta) = cos(\beta - \alpha) = cos(\alpha)cos(\beta) + sin(\alpha)sin(\beta).$$

This is a great situation. To find  $\cos(\theta)$ , we can just form a funny combination of the components of the vectors  $u/\|u\|$  and  $v/\|v\|$ .

That funny combination takes the form "product of first components plus product of second components." That is familiar! It looks a bit like what happens when we compute a norm, where we have a "square of the first component plus the square of the second component." Motivated by this happy coincidence, we make up a new object to help us organize the similarities:

**Definition 9** (Dot Product). Let  $u = \begin{pmatrix} u_1 \\ u_2 \end{pmatrix}$  and  $v = \begin{pmatrix} v_1 \\ v_2 \end{pmatrix}$  be vectors in  $\mathbb{R}^2$ . The dot product of u and v is the number

$$u \cdot v = u_1 v_1 + u_2 v_2.$$

The dot product is mysterious for new learners. You take this funny combination of the components, and somehow learn all kinds of information about lengths and angles. The dot product has many useful properties, which we gather together now.

**Theorem 10.** Let u, v, and w be vectors in  $\mathbb{R}^2$  and let  $\lambda$  and  $\mu$  be scalars. Then

- The angle  $\theta$  between u and v is given by

$$\theta = \arccos\left(\frac{u \cdot v}{\|u\| \|v\|}\right);$$

- The norm of u is  $||u|| = \sqrt{u \cdot u}$ ;
- The dot product is symmetric:  $u \cdot v = v \cdot u$ ;
- The dot product distributes over linear combinations

$$u \cdot (\lambda v + \mu w) = \lambda (u \cdot v) + \mu (u \cdot w)$$

As our study progresses, we will not have much use for measuring particular angles, but it will be very important to us to understand situations when two vectors make an angle of  $\pi/2$  radians (i.e. 90°, a right angle). It is common to call such vectors perpendicular. It is a fact that  $\cos(\pi/2) = 0$ , so that non-zero vectors u and v make an angle of  $\pi/2$  when

$$0 = \cos(\pi/2) = \frac{u \cdot v}{\|u\| \|v\|}.$$

By clearing out the denominator of this fraction, we see that u and v make an angle of  $\pi/2$  exactly when  $u \cdot v = 0$ . We will generalize this idea eventually, but it is convenient to start using the proper word now.

**Definition 11** (Orthogonal vectors). We say that a pair of non-zero vectors u and v are orthogonal exactly when  $u \cdot v = 0$ .

We have to be a little careful and include the caveat that u and v are nonzero, because of course the dot product of any vector with the zero vector is zero (the number, this time), but it does not feel right to say that the zero vector makes an angle of any type with any other vector.

#### NORMAL VECTORS AND EQUATIONS FOR LINES

Our discussion of the basic geometry of vectors feels like a digression. It has led us away from our main goal, which is to describe lines in the plane. But now we have enough information to circle back<sup>1</sup> and use the dot product and the concept of orthogonality to give a different way of describing lines. As before, we will start with the case of lines through the origin.

Suppose that we are given a vector  $u = \begin{pmatrix} a \\ b \end{pmatrix}$ . What vectors are orthogonal to u? When we try to just sketch this, we get a line through the origin! It looks a lot like Figure 16.

Let's try to be more precise. Suppose we were lucky enough to figure out one single vector  $v_0$  which is orthogonal to u. Then any

<sup>&</sup>lt;sup>1</sup>This is a geometry joke. I am sorry. But not really.




Figure 16: The line of vectors orthogonal to u.

scalar multiple  $tv_0$  of  $v_0$  will also be orthogonal to u, because

$$(tv_0) \cdot u = t(v_0 \cdot u) = t(0) = 0.$$

But the collection of vectors of the form  $tv_0$  is the parametric line through the origin. So, the line we seek is the line through the origin with direction  $v_0$ .

How can we find such a  $v_0$ ? Well, in  $\mathbb{R}^2$ , we can write  $v_0 = \begin{pmatrix} x \\ y \end{pmatrix}$  and then use the orthogonality condition to see that x and y must satisfy

$$0 = u \cdot v_0 = \begin{pmatrix} a \\ b \end{pmatrix} \cdot \begin{pmatrix} x \\ y \end{pmatrix} = ax + by.$$

After a little poking around, one can discover that one solution to the equation ax + by = 0 is x = -b, y = a. So we can choose  $v_0 = \binom{-b}{a}$ . Of course, there are other solutions to this equation (a whole line's worth!), but we just need one and this one is convenient.

If we collect this sequence of observations, we get the following theorem.

**Theorem 12** (Equation for a line through the origin). Let  $u = \begin{pmatrix} a \\ b \end{pmatrix}$  be a non-zero vector. Then the set of vectors orthogonal to u is the line with parametric description

$$t \mapsto t \begin{pmatrix} -b \\ a \end{pmatrix}$$
.

Moreover, we can describe that line by an equation: The line of vectors orthogonal to u consists of the vectors  $X = \begin{pmatrix} x \\ y \end{pmatrix}$  whose coordinates satisfy the equation

$$ax + by = 0.$$

On the other hand, for each line  $\ell$  through the origin with direction vector  $v = \binom{c}{d}$ , the vector  $u = \binom{-d}{c}$  is orthogonal to all of the vectors in the line  $\ell$ . Furthermore, the line  $\ell$  can be represented as the collection of vectors  $X = \binom{x}{y}$  whose coordinates satisfy the equation

$$-dx + cy = 0.$$

**Definition 13** (Normal Vector to a line). A vector which is orthogonal to all of the direction vectors of a line is called a normal vector for that line.

Note that there is a little looseness here in the descriptions. A line has many direction vectors, and also many normal vectors. But there is only so much leeway: all of the direction vectors are scalar multiples of each other, and all of the normal vectors are scalar multiples of each other.

And here we have introduced yet another use for some form of the word "normal." Be aware.

Now that we can write equations to help us describe lines through the origin, we would like to have a similar understanding for lines which do not pass through the origin. First, take any line  $\ell$ . Then  $\ell$  is parallel to a line  $\ell'$  which passes through the origin. Using what we know above, pick out a normal vector  $u = \begin{pmatrix} a \\ b \end{pmatrix}$  to the

line  $\ell'$ . Since  $\ell$  and  $\ell'$  are parallel, u is a normal vector for both. Then, pick out just one vector p which has its head on the line  $\ell$ . (So the corresponding point P lies on  $\ell$ .)

If we let some unknown, generic vector with its head on the line  $\ell$  be represented by the variable vector  $X = \begin{pmatrix} x \\ y \end{pmatrix}$ , we see that the physicist's X - p lies entirely in the line  $\ell$ . Hence the mathematician's X - p is a direction vector for  $\ell$ , and therefore orthogonal to the vector u.




Figure 17: Sorting out the equation of a generic line.

Using the condition for orthogonality, we can derive an equation that the components x and y must satisfy in the following manner. First,

$$0 = u \cdot (X - p) = u \cdot X - u \cdot p;$$

therefore,

$$u \cdot X = u \cdot p$$
.

But  $c = u \cdot p$  is just a number. And we have already learned how to re-express  $u \cdot X$  as ax + by. Rewriting each side of the last displayed equation, we obtain

$$ax + by = c$$
.

That is the form of an equation for a generic line in the plane. This way of writing the equation of a line in the plane is called the

standard form of the equation of a line. There are some important features to track in this form:

- The coefficients a and b of the variables are just the components of the normal vector, but this normal vector is chosen just by looking at a line through the origin. There are a great many lines which are all parallel to the same line through the origin, so they will all have the same set of coefficients.
- Changing which line in that family of parallel lines will involve changing the point P and the corresponding vector p. So even though a and b will not change, the number  $c = u \cdot p$  will be different.
- In each family of parallel lines, the one with right hand side c = 0 is the one through the origin.
- Changing the coefficients a and b results in a different normal vector, and hence a different family of parallel lines.

**Theorem 14** (Equation of a generic line in the plane). Suppose that  $\ell$  is a line in the plane. Let P be a point on the line, with corresponding vector p, and let  $u = \begin{pmatrix} a \\ b \end{pmatrix}$  be a normal vector for  $\ell$ . Set  $c = u \cdot p$ .

Then  $\ell$  is the collection of points at the heads of the vectors  $X = \begin{pmatrix} x \\ y \end{pmatrix}$  which satisfy the equation

$$ax + by = c$$
.

### WORKING WITH LINES DESCRIBED BY EQUATIONS

To make a graph of a line described by an equation, it is easiest to choose two points P and Q which lie on the line, and then draw the line passing through them. In most cases, the most convenient points are the *intercepts* where the line meets the coordinate axes. If the line is ax + by = c, then we can find the x-intercept by setting y = 0 and solving for x = c/a. Hence the point of interest is P = (c/a, 0). Similarly, the y-intercept can be found by setting x = 0. The resulting point will be Q = (0, c/b). Then it is no trouble to plot these two points and draw a line through them.

Now, suppose we have a line described parametrically. We can

find the equation of that line by a process known as "eliminating the parameter." If the parametric form is

$$t \mapsto \begin{pmatrix} p_0 \\ p_1 \end{pmatrix} + t \begin{pmatrix} v_0 \\ v_1 \end{pmatrix},$$

we take apart the two coordinates of the vector to form a pair of parametric equations

$$\begin{cases} x = p_0 + tv_0 \\ y = p_1 + tv_1 \end{cases}$$

Now, we multiply through the first equation by  $-v_1$  and the second equation by  $v_0$ 

$$\begin{cases}
-v_1 x = -v_1 p_0 - t v_0 v_1 \\
v_0 y = v_0 p_1 + t v_0 v_1
\end{cases},$$

and then we add the two equations, thus eliminating the appearance of the parameter t, to obtain

$$-v_1x + v_0y = -v_1p_0 + v_0p_1.$$

This is the equation of the line.

Finally, suppose we have an equation of the line, and we wish to find a parametric representation for it. There is a simple process for doing so, with a neat little trick in the heart of it.

Let our equation be ax + by = c, and assume for simplicity that  $a \neq 0$ . Then, with a little bit of manipulation, we may rewrite the equation as

$$x = \frac{c}{a} - y\frac{b}{a}.$$

The trick is to treat the variable y as if it was our parameter. That is, just declare y=t. That gives us a pair of equations, which we can write as

$$\begin{cases} x = \frac{c}{a} - t\frac{b}{a} \\ y = t \end{cases}.$$

Now, written this way, it is not too hard to translate this into a vector parametric form for the line.

$$\begin{pmatrix} x \\ y \end{pmatrix} = \begin{pmatrix} c/a \\ 0 \end{pmatrix} + t \begin{pmatrix} -b/a \\ 1 \end{pmatrix},$$

or

$$t \mapsto \begin{pmatrix} c/a \\ 0 \end{pmatrix} + t \begin{pmatrix} -b/a \\ 1 \end{pmatrix}.$$

If you like, you can rescale that direction vector, and instead write

$$t \mapsto \begin{pmatrix} c/a \\ 0 \end{pmatrix} + t \begin{pmatrix} -b \\ a \end{pmatrix}.$$

Later it will be important to us that the direction vector  $\binom{-b}{a}$  is a solution to the associated equation ax+by=0.

## The Equations of a Line in Space

Let us now think about the nature of space. Okay, that sounded goofy. I don't mean contemplating planets and nebulae and the enormity of *UY Scuti*. So far, all of our work has been in the plane, which is supposed to represent the ideal of a flat thing which is infinite in extent and "two-dimensional." Our next theater for exploration is a model for the space in which we live. Rather than having two dimensions, it has three, so we can talk about motions which are not just forward and back, and right and left, but also up and down.

Fortunately, much of the hard work we have done understanding vectors in  $\mathbb{R}^2$  carries over quickly. There are ready analogies for point, vector, and dot product, and though the geometry of these gets more interesting, the algebra really doesn't. That will eventually be our lifeline: as the spaces we consider get more exotic, the geometries will get more complicated (and eventually almost impossible to visualize), but the corresponding algebra will always have the same level of complexity. That is why the subject is called "Linear Algebra" rather than "Linear Geometry."

Drawing pictures becomes much more challenging. One option is to study drawing and painting for a few years until representing figures from space on a plane becomes more natural. In fact, there is a strong connection between linear algebra and some of the science behind perspective drawing, which mathematicians call projective geometry. But as that is outside the plan of our current study, we will resort to images made with software.

Again, it will take some work to get there, but we are interested in the following question:

#### THE EQUATIONS OF A LINE IN SPACE

#### How can we clearly describe a single line in space with an equation?

#### Points, Vectors, and the Dot Product in $\mathbb{R}^3$

Just as we worked in the plane with points and vectors (both physicist's and mathematician's vectors) by using coordinates, we can do the same for the space around us. We have the same sort of muddled trichotomy to deal with, which should feel a little less mysterious by now. Anyway, a *point* in space is supposed to be a location; a *(physcist's) vector* is an arrow, having direction and magnitude; and a *(mathematician's) vector* is an arrow whose tail is at a special, pre-selected point called the *origin* and denoted by O.

There are many ways to attempt to set up coordinates in space, but experience has taught us that a good way mimics the set-up from the plane. There, in the plane, we used a pair of perpendicular lines through the origin as our backdrop, which we call *coordinate axes*. In space, we have more room to deal with, so instead we use three planes as reference, and we try to make them as perpendicular as we can.

How do we arrange that? The key fact we need is that when distinct planes meet, they do so along a line. Let's think through



Figure 18: Two planes intersect along a line.

that a little. What does the picture look like near the intersection where two planes meet? A good way to understand it is to look "across the intersection." To this end, turn the picture in front of you until the line of intersection is exactly the "line of sight" pointing directly away from your eye. If you do this correctly, the line should essentially vanish, by collapsing down to a single point in your vision. If you prefer, rather than imagining that you turn the picture, you can imagine moving around in space until you are in the line, and then looking in the correct direction. Either way, you should get the same image: the line of intersection collapses to a point, and the two planes under consideration collapse to lines in your vision, as you are looking at things "edge on."

This picture is now much simpler. We have turned the set-up of two planes which intersect along a line into a picture where two lines meet at a point. What we want is that these two lines should be perpendicular. In fact, they should mimic our usual coordinate axes picture for the plane.

So, now we are ready to set up our coordinate planes and axes for space. First, choose a point O to play the role of the origin. Then, through that point, choose three distinct planes  $\mathcal{P}_1$ ,  $\mathcal{P}_2$ , and  $\mathcal{P}_3$ . Each pair of these planes meets along a line: call the intersection of plane  $\mathcal{P}_i$  with plane  $\mathcal{P}_j$  the line  $\ell_{ij}$ . So, for example,  $\ell_{12}$  is the line along which plane  $\mathcal{P}_1$  meets plane  $\mathcal{P}_2$ .

The important condition we want is this: If you look down the line  $\ell_{ij}$ , then the planes  $\mathcal{P}_i$  and  $p_j$  appear to be a pair of perpendicular lines. We require this to be true for each of the three lines  $\ell_{ij}$  simultaneously.




Figure 19: The Coordinate Planes and Axes

Now we are prepared to give some of these objects their traditional names. The planes  $\mathcal{P}_1$ ,  $\mathcal{P}_2$ , and  $\mathcal{P}_3$  are called the yz-plane, the xz-plane, and the xy-plane, respectively. The line  $\ell_{12}$  is called the z-axis, the line  $\ell_{23}$  is called the x-axis, and the line  $\ell_{13}$  is called the y-axis.

Sometimes, instead of x, y, and z, we may use the variables  $x_1$ ,  $x_2$ , and  $x_3$ . Then all of the names above change accordingly.

Just as in the plane, we can now introduce coordinates for points and vectors. We will just discuss how to do this for points, and you can see how to extend it to both interpretations of vectors in the same manner as before.

Given a point P in space, draw a plane parallel to the yz-plane which passes through P. This plane will meet the x-axis in exactly one point. We treat the x-axis as a number line, so this point has associated to it a number  $P_x$ , which we call the x-coordinate of P. Geometrically, the number  $P_x$  represents the "height" of P above the yz-plane. The words height and above are used in a relative sense, here.

Similarly, we can draw a plane parallel to the xz-plane which passes through P. This plane will intersect the number line of the y-axis, and we call the corresponding number  $P_y$  the y-coordinate of P. Finally, we can draw a plane parallel to the xy-plane through P, which will intersect the z-axis in a point, whose corresponding number  $P_z$  is called the z-coordinate of P. We then take these three numbers and bundle them together and represent the point P by the ordered triple  $P = (P_x, P_y, P_z)$ . Just as before, we will distinguish between points and vectors in our notation, and write vectors as vertical stacks of numbers. Here, such a stack has three parts. Motivated by our work in the plane, we make the following definition.

**Definition 15.** A 3-vector is a vertical stack of three real numbers, like so:

$$v = \begin{pmatrix} v_x \\ v_y \\ v_z \end{pmatrix}.$$

The collection of all such 3-vectors is called 3-space, and written

with this notation:  $\mathbb{R}^3$ .

The notation  $\mathbb{R}^3$  is often read as "arr-three," and many people use that language in place of "three-space." Also, most of the time we will just say "vector" when the context is clear. But it can be helpful to have the extra bit of information in situations where vectors of different sizes are involved.

The algebra of 3-vectors is handled in exactly the same way as the algebra of 2-vectors, except that there is another coordinate to track. All of the geometric connections between points, mathematician's vectors, and physicist's vectors work just as before, but there is "more space" to work with. Most people find visualization in three-space to be much harder than in the plane. This is completely normal, and you should expect to get used to this only if you work at it.

**Definition 16** (Algebra in  $\mathbb{R}^3$ ). Suppose that u and v are 3-vectors, and that  $\lambda$  and  $\mu$  are scalars (real numbers). Then the linear combination of u and v with weights  $\lambda$  and  $\mu$  is defined coordinate-by-coordinate:

$$\lambda u + \mu v = \lambda \begin{pmatrix} u_x \\ u_y \\ u_z \end{pmatrix} + \mu \begin{pmatrix} v_x \\ v_y \\ v_z \end{pmatrix} = \begin{pmatrix} \lambda u_x + \mu v_x \\ \lambda u_y + \mu v_y \\ \lambda u_z + \mu v_z \end{pmatrix}$$

It is, of course, possible to form linear combinations of larger collections of vectors, using the corresponding number of weights. You should also notice that addition of 3-vectors and scalar multiplication for 3-vectors are special cases of linear combination. (How would you do this? Check this statement!) The statements of Theorem 3 and Theorem 5 carry over unchanged to our new setting. The algebra of vectors behaves just as sensibly in  $\mathbb{R}^3$  as in  $\mathbb{R}^2$ , even if the pictures are more challenging.

The geometry of  $\mathbb{R}^3$  can be handled similarly, too, with dot products, norms, and angles.

**Definition 17** (Dot Product, norm, and angles in  $\mathbb{R}^3$ ). Let u and

v be 3-vectors. The dot product of u and v is the real number

$$u \cdot v = \begin{pmatrix} u_x \\ u_y \\ u_z \end{pmatrix} \cdot \begin{pmatrix} v_x \\ v_y \\ v_z \end{pmatrix} = u_x v_x + u_y v_y + u_z v_z,$$

the norm of u is the non-negative real number

$$||u|| = \sqrt{u \cdot u} = \sqrt{u_x^2 + u_y^2 + u_z^2}$$

and the angle between u and v is defined to be

$$\theta = \arccos\left(\frac{u \cdot v}{\|u\| \|v\|}\right).$$

We say two vectors are orthogonal when their dot product is 0. A vector is called a unit vector when its norm is equal to 1.

Again, these behave just as well in  $\mathbb{R}^3$  as in  $\mathbb{R}^2$ . It is possible to "normalize" a non-zero vector u to produce a unit vector  $||u||^{-1}u$ , and the statement of Theorem 10 works in  $\mathbb{R}^3$ .

### PARAMETRIC LINES

Given two points, P and Q, in  $\mathbb{R}^3$ , we can describe the line which passes through those points. This works just as in the case of the plane, using similar triangles for lines through the origin and then picking up those lines and moving them for the general case.

**Theorem 18.** Let P, Q, and R be points in 3-space. Let p, q, and r be the 3-vectors with tails at the origin and heads at P, Q, and R, respectively.

 The line which passes through the origin O and the point R is described parametrically as the heads of all the vectors traced by the function The line which passes through the points P and Q is described parametrically as the heads of all of the vectors traced by the fuction

$$t \mapsto p + t(q - p)$$
.

Note that the second statement collapses into the first if we choose P=O, since then p is the zero vector. In the second statement, things are arranged so that t=0 gives the vector p and t-1 gives the vector q. We think of P as the "base point" and the motion shows travel in the direction of the direction vector q-p. Also, if we are just interested in describing the line, it does not matter which of the points P or Q we consider as base point: switching them just changes the direction vector to p-q=-(q-p), but does not the line as a whole.

## Describing a Plane through the Origin in $\mathbb{R}^3$

In the last chapter, we made productive use of the following question:

What is the set of vectors in  $\mathbb{R}^2$  which are orthogonal to a given vector u?

Our considerations led us an understanding of lines in the plane as objects described as solution sets to a linear equation. With hearts full of hope, we charge off in the same direction here.<sup>2</sup> Perhaps we can find some way to describe lines with equations.

Perhaps we can find some way to describe lines with equations. So, we fix some vector  $u=\begin{pmatrix} a \\ b \\ c \end{pmatrix}$ , and try to figure out the form of those vectors which are orthogonal to u. Suppose that  $v=\begin{pmatrix} x \\ y \\ z \end{pmatrix}$  is some variable vector. We will assume that v is orthogonal to u. This means that

$$0 = u \cdot v = \begin{pmatrix} a \\ b \\ c \end{pmatrix} \cdot \begin{pmatrix} x \\ y \\ z \end{pmatrix} = ax + by + cz.$$

<sup>&</sup>lt;sup>2</sup>This is a geometry joke. I am sorry. But not really.

Thus the set of vectors in  $\mathbb{R}^3$  which are orthogonal to u is exactly the collection of vectors whose coordinates satisfy the linear equation ax + by + cz = 0.

What is that shape, though? We must try to say something about it. To make our discussion easier, let us give it a name. We will call it  $\mathcal{P}$ . In standard mathematical notation, we write

$$\mathcal{P} = \left\{ v = \begin{pmatrix} x \\ y \\ z \end{pmatrix} \middle| ax + by + cz = 0 \right\}.$$

This notation is the way that a mathematician writes a "set," a collection of things. The curly braces tell you that you are using set notation, the stuff before the vertical bar sets up our notation, and the stuff after the vertical bar tells us what conditions describe our set. So, in this case, you should read that displayed equation as

" $\mathcal{P}$  is the set of all 3-vectors v with components x, y, and z such that the equation ax + by + cz = 0 is true."

Our first observation is that this shape contains all the linear combinations of the vectors it has in it. To see this, suppose that  $v_1$  and  $v_2$  are two vectors which are orthogonal to u, and that  $\lambda_1$  and  $\lambda_2$  are two scalars, and consider the linear combination  $\lambda_1 v_1 + \lambda_2 v_2$ . The dot product of this vector with u is

$$u \cdot (\lambda_1 v_1 + \lambda_2 v_2) = \lambda_1 u \cdot v_1 + \lambda_2 u \cdot v_2 = \lambda_1(0) + \lambda_2(0) = 0.$$

Hence, the linear combination  $\lambda_1 v_1 + \lambda_2 v_2$  is also orthogonal to u.

As a special case, the collection of scalar multiples of a single vector is a kind of linear combination,  $\lambda v$ . But the set of multiples of a single vector is a line through the origin in the direction of that vector. This means that our set  $\mathcal{P}$  has to contain all of the lines through pairs O, P, where P is a point in  $\mathcal{P}$ .

Let's sum up some of what we know, so we don't lose track.

**Theorem 19.** Fix a 3-vector u. The set P of all vectors which are orthogonal to u has the following properties:

- If  $u = \begin{pmatrix} a \\ b \\ c \end{pmatrix}$ , then  $\mathcal{P}$  consists of those vectors  $v = \begin{pmatrix} x \\ y \\ z \end{pmatrix}$  whose coordinates satisfy the equation ax + by + cz = 0.
- For each vector p in  $\mathcal{P}$ , the entire line  $t \mapsto tp$  lies in  $\mathcal{P}$ .
- If p and q are vectors in  $\mathcal{P}$ , then any linear combination of p and q also lies in  $\mathcal{P}$ .

This is good, but it does not quite tell us what  $\mathcal{P}$  is, yet. Maybe it is time to just find some examples of vectors which satisfy the defining equation. To make things smoother below, we assume that  $a \neq 0$ . This is not essential, but it will help a little to avoid dividing by 0.

We begin by looking for simple forms. Let's just specify that one of the variables is 0 and see what we get. For example, if we assume x=0, the equation collapses to

$$0 = ax + by + cz = a(0) + by + cz = by + cz.$$

This can be satisfied by choosing y = -c and z = b. So we get the vector

$$v_1 = \begin{pmatrix} 0 \\ -c \\ b \end{pmatrix}.$$

Similarly, we can search for a vector which has y = 0. The defining equation for  $\mathcal{P}$  collapses to ax + cz = 0, which we can solve with x = -c and z = a. This gives us the vector

$$v_2 = \begin{pmatrix} -c \\ 0 \\ a \end{pmatrix}.$$

Since we have searched for, and found, vectors by starting with x = 0 and y = 0, respectively, it makes sense to search for one with z = 0, too. So let's do that. If z = 0, the defining equation collapses to ax + by = 0, which has solution x = -b, y = a. So

we obtain the vector

$$v_3 = \begin{pmatrix} -b \\ a \\ 0 \end{pmatrix}.$$

Given Theorem 19, we know that  $\mathcal{P}$  contains at least the collection of all linear combinations of the three vectors  $v_1$ ,  $v_2$  and  $v_3$ . But note that we do not truly require all three of those vectors! This is because if we pick scalars carefully and form a linear combination of  $v_2$  and  $v_3$ , we obtain

$$bv_2-cv_3+=b\begin{pmatrix} -c\\0\\a\end{pmatrix}-c\begin{pmatrix} -b\\a\\0\end{pmatrix}=\begin{pmatrix} -bc+bc\\-ac\\ab\end{pmatrix}=a\begin{pmatrix} 0\\-c\\b\end{pmatrix}=av_1.$$

This means that  $v_1 = \frac{b}{a}v_2 - \frac{c}{a}v_3$  is already a linear combination of  $v_1$  and  $v_2$ . So we do not need to keep  $v_3$ . It is redundant in our current description. Maybe, just maybe, we are lucky that any vector in  $\mathcal{P}$  is a linear combination of  $v_2$  and  $v_3$ ?

Let's try to approach this from a different direction.<sup>3</sup> We can rewrite the defining equation for  $\mathcal{P}$  in the form

$$x = -\frac{b}{a}y - \frac{c}{a}z.$$

This means that if we know the values of y and z, then the value of x is completely determined. So, really, we only have two independent choices to make. If we choose y=s and z=t to be two numbers, then we have  $x=\frac{-b}{a}s+\frac{-c}{a}t$ . Which means that our vector in  $\mathcal{P}$  has the form

$$\begin{pmatrix} \frac{-b}{a}s + \frac{-c}{a}t \\ s \\ t \end{pmatrix} = s \begin{pmatrix} \frac{-b}{a} \\ 1 \\ 0 \end{pmatrix} + t \begin{pmatrix} \frac{-c}{a} \\ 0 \\ 1 \end{pmatrix} = \frac{s}{a}v_2 + \frac{t}{a}v_3.$$

This is the big result we want, though the shape is not, yet, clear. What we have found is that any vector which has coordi-

<sup>&</sup>lt;sup>3</sup>That is a geometry joke. I am sorry. But not really.

nates which satisfy the equation for  $\mathcal{P}$  must be a linear combination of  $v_2$  and  $v_3$ .

What sort of shape is made up of the linear combinations of two vectors which point in different directions? Well, if we are allowed to move in the direction of one vector, then we generate a line through the origin. Now, from each of the points on this line, we are allowed to move in a different (fixed) direction. That makes a plane! This is the answer we sought: the set  $\mathcal{P}$  is a plane through the origin, the one which contains the vectors  $v_2$  and  $v_3$ .

By the way, we call u the normal vector to the plane  $\mathcal{P}$ .

Again, we should make a summary.

**Theorem 20.** Fix a vector u in 3-space. The set  $\mathcal{P}$  of all vectors orthogonal to u is a plane through the origin.

Moreover, if we write  $u = \begin{pmatrix} a \\ b \end{pmatrix}$ , and assume  $a \neq 0$ , then

- We can describe the plane  $\mathcal{P}$  as the collection of all points

P = (x, y, z) which satisfy the equation

$$ax + by + cz = 0.$$

- We can also describe the plane parametrically as the heads of all of the vectors of the form

$$s \begin{pmatrix} -b/a \\ 1 \\ 0 \end{pmatrix} + t \begin{pmatrix} -c/a \\ 0 \\ 1 \end{pmatrix}.$$

Like before, we view this parametric description as a defining a kind of function.

$$(s,t) \mapsto s \begin{pmatrix} -b/a \\ 1 \\ 0 \end{pmatrix} + t \begin{pmatrix} -c/a \\ 0 \\ 1 \end{pmatrix}.$$

Only this one has two inputs, s and t. The output for any particular choice of s, t is some vector in 3-space. If we make some sort of "multidimensional time lapse photograph," then the heads of all of the vectors we get trace out a plane in 3-space.

So, we set out to see if we could describe a line in 3-space, but we ended up working on describing planes instead. Let's try to finish that up, and we will return to describing lines in a bit.

In Theorem 20, we start with a vector u, and then find two ways to understand the plane  $\mathcal{P}$  through the origin which consists of vectors orthogonal to u. Of the two ways, the equation came first, then the parametric description. And it was the parametric description that helped us realize the object was a plane. Now, let us try to do things in the opposite order.

Suppose that we have a plane  $\mathcal{Q}$  in 3-space which passes through the origin. How can we determine it completely? First note that to determine a line we need two points, but to determine a plane we need three points. Since we already have the origin singled out, consider two more points P and Q. It is important that these three points are distinct, or we will lose the idea of the plane.

First, Q must contain the whole line through P and Q. Thus it must contain all of the points on the line with parametric description

$$t \mapsto p + t(q - p),$$

where p is the vector from O to P, and q is the vector from O to Q. Now, if we fix a particular  $t = t_0$ , we get a point  $X_0$  which lies in Q. This point  $X_0$  is the head of the vector

$$x_0 = p + t_0(q - p) = (1 - t_0)p + t_0q.$$

Since the plane Q contains O and  $X_0$ , it must contain the line through them, which is described parametrically by

$$s \mapsto sx_0 = s(1 - t_0)p + st_0q.$$

Notice that this time we use the variable s as parameter, because we have already used t above and we want to distinguish between the two choices. This is very nice, we have described lots of points on  $\mathcal Q$  as the heads of vectors which are just linear combinations of p and q. For varying choices of s and t, we get may points on  $\mathcal Q$ .




Figure 20: The line PQ and the sweep of lines through O and points X on this line.

A careful look at this situation shows that we have described almost all of the points on  $\mathcal{Q}$ . We have missed those on a single line: the line passing through the origin O which is parallel to the line through P and Q. That is, our exceptions are the multiples of q-p.

Another way to see this is to look at the two scalars involved in our description, s(1-t) and st. There ratio has the form

$$\frac{st}{s(1-t)} = \frac{t}{1-t}.$$

But it is not too hard to plot the function  $t \mapsto t/(1-t)$  and see that it misses the value -1, and only the value -1.




Figure 21: The graph of y = t/(1-t).

This corresponds to missing vectors of the form  $v = \lambda p - \lambda q = \lambda (q - p)$ , which is exactly the line through the origin in the direction q - p.

Anyway, we can patch the plane back together, and add this line back in, by simply allowing any linear combination of the vectors p and q.

**Theorem 21.** Let P and Q be two points in 3-space. If p and q are the vectors with tails at the origin O and heads at P and Q, respectively, then the plane through the three points O, P, and Q is

$$Q = \{v = sp + tq | s \text{ and } t \text{ are real numbers} \}.$$

Now that we have the fact that we can describe a plane through the origin parametrically as the collection of vectors which are linear combinations of two fixed vectors p and q, we want to find a way to turn that information into the equation which describes that plane. There are two readily available methods: (1) we can write out some equations and eliminate the parameters s and t; or, (2) we can find a normal vector to the plane and use that to write down the equation immediately. These two methods should end up in approximately the same place. First, let us try the method of eliminating parameters. We will take a variable vector

 $v = \begin{pmatrix} x \\ y \\ z \end{pmatrix}$ 

which we assume to lie in our plane Q. Our goal is to find an equation satisfied by x, y, and z. In order to make progress, we will need to have more detailed notation for p and q, so we write them out in coordinates as

$$p = \begin{pmatrix} p_1 \\ p_2 \\ p_3 \end{pmatrix}$$
 and  $q = \begin{pmatrix} q_1 \\ q_2 \\ q_3 \end{pmatrix}$ .

Since v is in  $\mathcal{Q}$ , we can write

$$\begin{pmatrix} x \\ y \\ z \end{pmatrix} = s \begin{pmatrix} p_1 \\ p_2 \\ p_3 \end{pmatrix} + t \begin{pmatrix} q_1 \\ q_2 \\ q_3 \end{pmatrix}.$$

We then unbundle this vector equation into three separate equations, one for each coordinate.  $^4$ 

$$\begin{cases} x = p_1 s + q_1 t \\ y = p_2 s + q_2 t \\ z = p_3 s + q_3 t \end{cases}$$

Our first step is to eliminate s using the first two equations. We do this by multiplying the first equation by  $p_2$  and the second by  $-p_1$  and then adding. We obtain

$$p_2x - p_1y = t(p_2q_1 - p_1q_2).$$

Similarly, we will eliminate s by using the second and third equations. We do this by multiplying the second equation by  $p_3$  and

<sup>&</sup>lt;sup>4</sup>We are about to do a computation involving 11 different variables. This looks intimidating, but it isn't so bad. Just stay calm and do it. Choose a particular example and follow along by doing the steps for yourself.

the third by  $-p_2$  and then adding. We obtain

$$p_3y - p_2z = t(p_3q_2 - p_2q_3).$$

This gives us a pair of equations relating x, y, and z to t. We have effectively eliminated s. So, now consider our new system of equations:

$$\begin{cases} p_2x - p_1y = t(p_2q_1 - p_1q_2) \\ p_3y - p_2z = t(p_3q_2 - p_2q_3) \end{cases}$$

It remains to eliminate t from these. The clearest way to do that is to multiply the first equation by  $p_3q_2 - p_2q_3$  and the second equation by  $-(p_2q_1 - p_1q_2)$  and then add. We do this to find

$$(p_3q_2 - p_2q_3)(p_2x - p_1y) - (p_2q_1 - p_1q_2)(p_3y - p_2z) = 0.$$

This is our equation! All of the s's and t's are gone, and we are done. Now, in practice, it is better to have things organized so that like terms are together. If we do a little bit of manipulation and cleaning up, we eventually get this:

$$\{p_2(p_3q_2 - p_2q_3)\} x + \{p_2(p_1q_3 - p_3q_1)\} y + \{p_2(p_2q_1 - p_1q_2)\} z = 0.$$

Note that there is a  $p_2$  multiplied through the whole thing, so we should factor it out and get rid of it. That leaves us with

$$(p_3q_2 - p_2q_3)x + (p_1q_3 - p_3q_1)y + (p_2q_1 - p_1q_2)z = 0.$$

This is the equation of our plane Q, written in a relatively convenient form. We can read off of this expression that a normal vector to Q is

$$n = \begin{pmatrix} p_3 q_2 - p_2 q_3 \\ p_1 q_3 - p_3 q_1 \\ p_2 q_1 - p_1 q_2 \end{pmatrix}.$$

Now let us try the other method. We know that Q is the collection of linear combinations of p and q, and the normal vector to Q

must be orthogonal to every one of those vectors. In particular, the normal vector has to be orthogonal to p and to q. We keep the same notation for components of p and q as above, and introduce notation for n as follows:<sup>5</sup>

$$n = \begin{pmatrix} n_1 \\ n_2 \\ n_3 \end{pmatrix}.$$

The fact that n is orthogonal to both p and q leads us to this pair of equations

$$\begin{cases} p_1 n_1 + p_2 n_2 + p_3 n_3 = 0 \\ q_1 n_1 + q_2 n_2 + q_3 n_3 = 0 \end{cases}.$$

We have to do a similar sort of elimination process here to figure out what the  $n_i$ 's are in terms of the other variables. We are going to do this in a slightly different fashion than the above. It will feel less symmetrical than what we have done before, but it will be very efficient.

Our first step is to multiply the first equation through by  $-q_1/p_1$  and then add it to the second equation. Then we'll take a look at our updated system.

$$\left\{ \begin{array}{cccccccc} p_1 n_1 & + & p_2 n_2 & + & p_3 n_3 & = & 0 \\ & & \left(q_2 - \frac{p_2 q_1}{p_1}\right) n_2 & + & \left(q_3 - \frac{p_3 q_1}{p_1}\right) n_3 & = & 0 \end{array} \right. .$$

Next, we will multiply the second equation by the number

$$\frac{-p_2}{q_2 - \frac{p_2 q_1}{p_1}} = \frac{-p_1 p_2}{p_1 q_2 - p_2 q_1}$$

and add the result back into the first equation. After a lots of

 $<sup>^5</sup>$ We are about to do a computation involving 9 different variables. This looks intimidating, but it isn't so bad. Just stay calm and do it. Choose a particular example and follow along by doing the steps for yourself.

work with fractions, we see that this updates our system to read

$$\begin{cases} p_1 n_1 & + \left(p_3 - \frac{p_1 q_3 - p_3 q_1}{p_1 q_2 - p_2 q_1} p_2\right) n_3 = 0 \\ \left(q_2 - \frac{p_2 q_1}{p_1}\right) n_2 & + \left(q_3 - \frac{p_3 q_1}{p_1}\right) n_3 = 0 \end{cases}.$$

We are certainly not happy with this, yet. To clean up some more, we can work out that  $n_3$  term in the first equation. Then we obtain

$$\begin{cases} p_1 n_1 & + p_1 \frac{p_3 q_2 - p_2 q_3}{p_1 q_2 - p_2 q_1} n_3 = 0 \\ \left(q_2 - \frac{p_2 q_1}{p_1}\right) n_2 + \left(q_3 - \frac{p_3 q_1}{p_1}\right) n_3 = 0 \end{cases}$$

Finally, divide through the second equation by the coefficient of  $n_2$ , and divide through the first equation by  $p_1$  to get rid of a common factor. We now have something that does not look overly scary.

$$\begin{cases} n_1 & + \frac{p_3q_2 - p_2q_3}{p_1q_2 - p_2q_1}n_3 = 0 \\ n_2 & + \frac{p_1q_3 - p_3q_1}{p_1q_2 - p_2q_1}n_3 = 0 \end{cases}.$$

Something wonderful has happened. Note that in each equation, only two of the variables  $n_i$  appear. In fact, if we just choose  $n_3$ , then the equations tell us exactly what  $n_1$  and  $n_2$  should be. We can just write

$$n = \begin{pmatrix} \frac{p_2q_3 - p_3q_2}{p_1q_2 - p_2q_1} n_3\\ \frac{p_3q_1 - p_1q_3}{p_1q_2 - p_2q_1} n_3\\ n_3 \end{pmatrix} = n_3 \begin{pmatrix} \frac{p_2q_3 - p_3q_2}{p_1q_2 - p_2q_1}\\ \frac{p_3q_1 - p_1q_3}{p_1q_2 - p_2q_1}\\ \frac{p_3q_1 - p_1q_3}{p_1q_2 - p_2q_1}\\ 1 \end{pmatrix}$$

This is a good sign. Recall that a plane has many normal vectors. If we find one, we could always just rescale it to get another one. Since our work shows us this property, we should be happy.

But for now, we just want to find any one single normal vector, so we have to make a choice. And it would be good to make a choice that helps simplify all of the messy fractions we have derived. We choose  $n_3 = p_1q_2 - p_2q_1$  so that we can easily clear the

denominator common to the first two coordinates. We substitute this expression in, and we have finally found that our preferred normal  $\operatorname{vector}^6$  is

$$n = \begin{pmatrix} p_2 q_3 - p_3 q_2 \\ p_3 q_1 - p_1 q_3 \\ p_1 q_2 - p_2 q_1 \end{pmatrix}.$$

We deduce that the equation for the plane must be

$$0 = \begin{pmatrix} x \\ y \\ z \end{pmatrix} \cdot \begin{pmatrix} p_2 q_3 - p_3 q_2 \\ p_3 q_1 - p_1 q_3 \\ p_1 q_2 - p_2 q_1 \end{pmatrix},$$

or, more simply,

$$(p_2q_3 - p_3q_2)x + (p_3q_1 - p_1q_3)y + (p_1q_2 - p_2q_1)z = 0.$$

This is our desired result.

We should compare our two versions of the work. Looking carefully, we see that the only differences in the end results are of sign. The normal vectors are the same, up to multiplying by the scalar -1, and the equations are the same up to multiplying through by -1.

After all of that intense computation, it feels like a little bit of a miracle. But the miracle is just that we did things carefully and got through without arithmetic errors.

**Theorem 22.** Let Q be a plane in  $\mathbb{R}^3$  which passes through the origin O and two points  $P = (p_1, p_2, p_3)$  and  $Q = (q_1, q_2, q_3)$ . Then any normal vector to Q is a scalar multiple of the vector

$$n = \begin{pmatrix} p_2 q_3 - p_3 q_2 \\ p_3 q_1 - p_1 q_3 \\ p_1 q_2 - p_2 q_1 \end{pmatrix},$$

and the plane may be described as the set of points which satisfy

<sup>&</sup>lt;sup>6</sup>Some texts call this particular choice of n the  $cross\ product$  of p and q.

the equation

$$(p_2q_3 - p_3q_2)x + (p_3q_1 - p_1q_3)y + (p_1q_2 - p_2q_1)z = 0,$$

or parametrically as the image of

$$(s,t) \mapsto s \begin{pmatrix} p_1 \\ p_2 \\ p_3 \end{pmatrix} + t \begin{pmatrix} q_1 \\ q_2 \\ q_3 \end{pmatrix}.$$

## General Planes in $\mathbb{R}^3$

So far, all of our hard work has led us to a deep understanding of planes in  $\mathbb{R}^3$ , but only those that pass through the origin O. But most of the planes in  $\mathbb{R}^3$  do not contain the origin. We must figure out how to handle those, too.

In the case of lines in the plane, we used a simple method: Given a line not through the origin, find a parallel line through the origin. Describe that line by whatever method you want, and then translate back to get the description you want. We shall use this same method here.

**Definition 23.** Let  $\mathcal{P}$  and  $\mathcal{Q}$  be planes in  $\mathbb{R}^3$ . We say that  $\mathcal{P}$  and  $\mathcal{Q}$  are parallel if they have no points in common.

So, we begin with three points which define a plane  $\mathcal{P}$  in  $\mathbb{R}^3$ . Call them P, Q, and R. As usual, we write p, q, and r for the mathematician's vectors which have their heads at these three points, respectively. Now the physicist's vectors p-r and q-r lie entirely in in  $\mathcal{P}$ . The corresponding mathematician's vectors lie in a plane Q which is parallel to  $\mathcal{P}$ . Also, the new plane Q contains the origin. In fact, these two planes differ exactly by a parallel translation by the vector r: for each vector v with its head in  $\mathcal{P}$ , the corresponding vector v-r lies entirely in Q.

Now, since the plane  $\mathcal{Q}$  passes through the origin, we can give it one of our two types of descriptions, each of which will help us build the corresponding description for the plane  $\mathcal{P}$ . Let us take them in turn, starting with the parametric description.

The plane Q is the collection of vectors formed by linear combinations of p-r and q-r.

$$s(p-r) + t(q-r).$$

Since v - r lies in  $\mathcal{Q}$ , we see that

$$v - r = s(p - r) + t(q - r),$$

or

$$v = r + s(p - r) + t(q - r).$$

Since each of the vectors  $p,\,q,$  and r are known to us, it is straightforward to compute this explicitly. We get the parametric description

$$(s,t) \mapsto r + s(p-r) + t(q-r)$$

Next, let us consider the equation of  $\mathcal{P}$ . The plane  $\mathcal{Q}$  is the set of points w = (x, y, z) which are orthogonal to the normal vector n which is as described in Theorem 22. But v - r is an element of  $\mathcal{Q}$ , so we see that our equation for  $\mathcal{P}$  is just

$$n \cdot (v - r) = 0$$
, or  $n \cdot v = n \cdot r$ .

The trick is that first you must compute n from p-r and q-r. If n has components a, b, and c, we get an equation of the form

$$ax + by + cz = d$$
.

Since the planes  $\mathcal{P}$  and  $\mathcal{Q}$  are parallel, they share the same normal vector. This is apparent in the structure of their equations: the coefficients of the variables represent the normal vector, and they are the same. But the number on the right-hand side, d, depends on exactly which plane you consider in the family of parallel planes with normal vector n.

If we put together all of this work with the things we learned above, we obtain this result.

**Theorem 24.** Let  $\mathcal{P}$  be the plane in  $\mathbb{R}^3$  which contains the points  $R = (r_1, r_2, r_3)$ ,  $P = (p_1, p_2, p_3)$ , and  $Q = (q_1, q_2, q_3)$ . Let p, q, and r be the vectors with their heads at these points, respectively. Then we have the following:

P is parallel to a plane Q which passes through the origin.
 These two planes have a common normal vector

$$n = \begin{pmatrix} a \\ b \\ c \end{pmatrix} := \begin{pmatrix} (p_2 - r_2)(q_3 - r_3) - (p_3 - r_3)(q_2 - r_2) \\ (p_3 - r_3)(q_1 - r_1) - (p_1 - r_1)(q_3 - r_3) \\ (p_1 - r_1)(q_2 - r_2) - (p_2 - r_2)(q_1 - r_1) \end{pmatrix}$$

-  $\mathcal{P}$  has the parametric description

$$(s,t) \mapsto r + s(p-r) + t(q-r).$$

-  $\mathcal{P}$  has the equation

$$ax + by + cz = ar_1 + br_2 + cr_3,$$

where a, b, c are the components of n as above.

It is worth noting that the actual techniques of our earlier work carry over just fine, too. We can pass back and forth between a parametric description of a plane and an equation for that plane.

Suppose you have the equation ax + by + cz = d. To find a parametric description of the plane, do the following.

1. Choose a nonzero coefficient. For simplicity, assume it is  $a \neq 0$ . Then solve for the corresponding variable:

$$x = \frac{d}{a} - \frac{b}{a}y - \frac{c}{a}z.$$

- 2. Choose parameter names, and introduce dummy equations for them. Say y = s and z = t.
- 3. Substitute the new parameters in the equation, and set up

a system of all of the equations you have:

$$\begin{cases} x = \frac{d}{a} - \frac{b}{a}s - \frac{c}{a}t \\ y = s \\ y = t \end{cases}.$$

4. Rewrite the system as a vector equation.

$$\begin{pmatrix} x \\ y \\ z \end{pmatrix} = \begin{pmatrix} \frac{d}{a} \\ 0 \\ 0 \end{pmatrix} + s \begin{pmatrix} -\frac{b}{a} \\ 1 \\ 0 \end{pmatrix} + t \begin{pmatrix} -\frac{c}{a} \\ 0 \\ 1 \end{pmatrix}.$$

In the other direction, suppose that you have a parametric description and want to change it into an equation. The key is to unbundle the parametric description into a system of equations, and then steadily eliminate the variables.

If the system of equations is

$$\begin{cases} x = a + bs + ct \\ y = d + es + ft \\ z = g + hs + it \end{cases}$$

Then we can use the first and second equation to eliminate s, and then the second and third equations to also eliminate s, to get two equations involving only x, y, z, and t, like so:<sup>7</sup>

$$\left\{ \begin{array}{lcll} ex-by&=&\alpha&+&\beta t\\ gy-ez&=&\gamma&+&\delta t \end{array}\right.,$$

Now we can similarly use these two equations to eliminate t and obtain an equation of the form

$$Ax + By + Cz = D$$
.

 $<sup>^7\</sup>mathrm{I}$  ran out of symbols, so here are some new friends. The letters  $\alpha,\beta,\gamma,\delta$  come from an old form of Greek, and are called alpha, beta, gamma, and delta.

# The Equations of a Line in Space Lines in $\mathbb{R}^3$ as Solutions to Systems of Equations

We had a major goal to describe lines in  $\mathbb{R}^3$ , but got distracted by the nature of planes in 3-space.

So, how can we find something like an equation for a line in  $\mathbb{R}^3$ ? We have learned that a single equation relating three variables x, y, and z ends up describing a plane. This means that a single equation can't work!

The key idea is that a line what you get when you intersect two planes. So, to describe a line, we need two equations, not one.

Suppose we are given a line described parametrically.  $t \mapsto p+tv$ . How can we find two equations which will together describe the line? Well, our line has a direction vector v. Choose two vectors  $n_{\mathcal{P}}$  and  $n_{\mathcal{Q}}$  which are orthogonal to v and are not scalar multiples of each other. There are lots and lots of pairs of vectors like this, just pick. It seems like a staggering amount of freedom, but we might as well enjoy it.

Now we consider the plane  $\mathcal{P}$  with equation

$$n_{\mathcal{P}} \cdot \begin{pmatrix} x \\ y \\ z \end{pmatrix} = n_{\mathcal{P}} \cdot p,$$

and the plane Q with equation

$$n_{\mathcal{Q}} \cdot \begin{pmatrix} x \\ y \\ z \end{pmatrix} = n_{\mathcal{Q}} \cdot p.$$

Since the normal vectors  $n_{\mathcal{P}}$  and  $n_{\mathcal{Q}}$  are not scalar multiples of each other, these planes are not parallel. That means these planes intersect along a line. The important thing is that the line of intersection is exactly our line. To see this, we just check that the vectors p + tv satisfy the two equations. It is straightforward to check this directly:

$$n_{\mathcal{P}} \cdot (p + tv) = n_{\mathcal{P}} \cdot p + tn_{\mathcal{P}} \cdot v = n_{\mathcal{P}} \cdot p + 0 = n_{\mathcal{P}} \cdot p,$$

so the vectors p + tv have heads in  $\mathcal{P}$ , and

$$n_{\mathcal{Q}} \cdot (p + tv) = n_{\mathcal{Q}} \cdot p + tn_{\mathcal{Q}} \cdot v = n_{\mathcal{Q}} \cdot p + 0 = n_{\mathcal{Q}} \cdot p,$$

so the vectors p + tv also have heads in Q.

**Theorem 25.** A line in  $\mathbb{R}^3$  can be described as the common solution set for a system of equations representing two planes

Where the two normal vectors

$$n_1 = \begin{pmatrix} a_{11} \\ a_{12} \\ a_{13} \end{pmatrix}, \quad and \quad n_2 = \begin{pmatrix} a_{21} \\ a_{22} \\ a_{23} \end{pmatrix}$$

are both orthogonal to the direction vector v of the line, but are not scalar multiples of each other.

There are many such pairs of planes which have the line as their intersection.

This shows us how we might go from a parametric description to a system of equations. How might we work in the other direction? Suppose we are given a pair of planes described by equations, and we wish to find a parametric description for the line which is their common solution set.

Now the process is exactly that like we used to find a normal vector to a plane through the origin. Just as in the few pages running up to Theorem 22, we have a pair of equations and we want a common solution. The idea is to replace the very general set of equations

$$\left\{ \begin{array}{ccccccc} a_{11}x & + & a_{12}y & + & a_{13}z & = & b_1 \\ a_{21}x & + & a_{22}y & + & a_{23}z & = & b_2 \end{array} \right.$$

with a nicer, equivalent set of equations that looks like this

$$\begin{cases} x & + \alpha z = d_1 \\ y + \beta z = d_2 \end{cases},$$

which we can rewrite in vector form as the parametric description

$$\begin{pmatrix} x \\ y \\ z \end{pmatrix} = \begin{pmatrix} d_1 \\ d_2 \\ 0 \end{pmatrix} + t \begin{pmatrix} -\alpha \\ -\beta \\ 1 \end{pmatrix}.$$

This process is routine to do once learned, but it doesn't always work. There are two kinds of trouble that could happen.

The first is that some pairs of equations represent planes that actually don't intersect. The planes are parallel, and at some point we find an equation that doesn't actually make any sense, like 0 = 1.

The second problem is that some pairs of equations are really the same plane written twice. In this case, the solution set is all of (both of) the planes, not a line. Then the process ends up turning one equation into something trivially true, usually 0=0, and the rest collapses back on our technique for writing the parametric description for the plane.

Both of these situations require that the normal vectors to the planes are scalar multiples of each other, so with a little bit of care, you can learn to look for that before getting started on the time-consuming arithmetic.

**Theorem 26.** There are three cases possible for the shape of the set of simultaneous solutions to a system of 2 equations in three unknowns.

**Generic Case:** The two equations represent a pair of planes which are not parallel. The solution set is a line in  $\mathbb{R}^3$ .

Degenerate Case 1: The two equations are different representations for the same plane. The solution set is that plane.

**Degenerate Case 2:** The two equations represent planes which are distinct, but parallel. There are no solutions because the planes do not intersect.