

1 CORE CAPABILITIES



Microphone recording
Captures any active input endpoint through WASAPI, straight to WAV or MP3.



System audio capture
WASAPI loopback records whatever the playback device is mixing — `--include-output`.



Merge or separate
One mixed file at a chosen mic share (default 65/35), or aligned `_mic` + `_system` tracks.



Microphone gain
`--amplify 0-300` boosts the mic only: 0 = unity, 100 = 2x, 300 = 4x.



Device control
List every capture and playback endpoint; select by ID, list index, or name substring.



Streams to disk
Ring buffer plus a writer loop keep memory bounded at any recording length.




Two ways to stop
Press **Enter**, or run `--stop` elsewhere — a named event, crossing windows and editions.



Live progress
A single in-place status line reports seconds and bytes written on every flush.

2 HOW A RECORDING FLOWS



Every device format — mono, other sample rates, float samples — is converted on the fly to this canonical form, which is what lets the two streams mix reliably.

3 COMMAND REFERENCE

OPTION	ARGUMENT	WHAT IT DOES
-o, --output	<file>	Output path. Required to record; extension corrected to match the format.
-f, --format	wav mp3	Output format. Default mp3.
-i, --include-output	—	Also capture system audio via WASAPI loopback.
--merge	[percent]	Mix both sources into one file; percent is the mic's share (default 65).
--separate	—	Write two aligned files: <code>_mic</code> and <code>_system</code> .
-m, --mic	<id index name>	Microphone to record. Default: system default capture device.
-a, --amplify	<0-300>	Linear gain on the mic stream. Default 0 (unity).
-d, --output-device	<id index name>	Playback device to capture for loopback. Default: system default.
-l, --list-devices	—	List all capture and playback devices, then exit.
-s, --stop	—	Stop a recording started by another instance and finalise its files.
-h, --help	—	Show help and exit. Exit codes: 0 success · 1 error.

TYPICAL INVOCATIONS

```
audior --list-devices
audior --output meeting.mp3
audior --output talk.wav --format wav
audior --output session.mp3 -i --merge --amplify 50
audior --output call.wav -f wav -i --separate
```

4 REQUIREMENTS

SUPPORTED OS

- Windows 10 or Windows 11 — the only supported platforms.
- Uses in-box **WASAPI** and **Media Foundation**; no runtime beyond the Windows C runtime.
- MP3 encoding needs Media Foundation, which is absent on “N” editions without the Media Feature Pack.
- Microphone access must be allowed under Settings → Privacy & Security → Microphone.

TO BUILD THE C EDITION **AUDIOR.EXE**

- MSVC **cl.exe** — Visual Studio 2022, any edition.
- Windows SDK **10.0.19041.0** or later.
- Run **build.bat** from a Developer Command Prompt.
- Compiled as C (/TC). MinGW, Clang-cl and cross-compilation are not supported.

TO RUN THE PS EDITION **AUDIOR.PS1**

- No build step — the C# audio engine is compiled at run time by Add-Type.
- Windows PowerShell only; no external modules.
- If execution policy blocks it: powershell - ExecutionPolicy Bypass -File .\audior.ps1