



CLINICAL PROCEDURES FOR SAFER PATIENT CARE

CONTENTS

Chapter 10. Tubes and Attachments

10.6 Chest Tube Drainage Systems

A **chest tube**, also known as a thoracic catheter, is a sterile tube with a number of drainage holes that is inserted into the pleural space. The pleural space is the space between the parietal and visceral pleura, and is also known as the pleural cavity. A patient may require a chest drainage system any time the negative pressure in the pleural cavity is disrupted, resulting in respiratory distress. Negative pressure is disrupted when air, or fluid and air, enters the pleural space and separates the visceral pleura from the parietal pleura, preventing the lung from collapsing and compressing at the end of exhalation. A small amount of fluid or air may be absorbed by the body without a chest tube. A large amount of fluid or air cannot be absorbed by the body and will require a drainage system (Bauman & Handley, 2011; Perry et al., 2014).

The chest tube is connected to a closed chest drainage system, which allows for air or fluid to be drained, and prevents air or fluid from entering the pleural space. The system is airtight to prevent the inflow of atmospheric pressure. Because the pleural cavity normally has negative pressure, which allows for lung expansion, any tube connected to it must be sealed so that air or liquid cannot enter the space where the tube is inserted (Bauman & Handley, 2011; Rajan, 2013).

The location of the chest tube depends on what is being drained from the pleural cavity. If air is in the pleural space, the chest tube will be inserted above the second intercostal space at the mid-clavical line. If there is fluid in the pleural space, the chest tube is inserted at the fourth to fifth intercostal space, at the mid-axillary line. A chest tube may also be inserted to drain the pericardial sac after open heart surgery, and may be placed directly under the sternum (Perry et al., 2014).

The following are some of the conditions that may require a chest tube drainage system (Bauman & Handley, 2011;

- Pneumothorax
- Hemothorax
- · Spontaneous pneumothorax
- Tension pneumothorax
- Traumatic pneumothorax (stab or gunshot wound)
- Cardiac tamponade (accumulation of blood surrounding the heart after open heart surgery or chest surgery)

A chest tube drainage system must always be placed below the drainage site and secured in an upright position (attached to the floor or an IV pole, as in Figure 10.4) to prevent it from being knocked over.



Figure 10.4 Chest tube drainage system secured to IV pole



Figure 10.5 Chest tube drainage system




Figure 10.6 Chest tube drainage system with labelled parts

A **chest tube drainage system** is a sterile, disposable system that consists of a compartment system that has a one-way valve, with one or multiple chambers, to remove air or fluid and prevent return of the air or fluid back into the patient

manufacturer's directions for setup, monitoring, and use. In general, a traditional chest tube drainage system will have these three chambers:

- 1. Collection chamber: The chest tube connects directly to the collection chamber, which collects drainage from the pleural cavity. The chamber is calibrated to measure the drainage. The outer surface of the chamber has a "write-on" surface to document the date, time, and amount of fluid. This chamber is typically on the far right side of the system (Teleflex Medical Incorporated, 2009).
- 2. Water-seal chamber: This chamber has a one-way valve that allows air to exit the pleural cavity during exhalation but does not allow it to re-enter during inhalation due to the pressure in the chamber. The water-seal chamber must be filled with sterile water and maintained at the 2 cm mark to ensure proper operation, and should be checked regularly. Fill with additional sterile water as required. The water in the water-seal chamber should rise with inhalation and fall with exhalation (this is called *tidaling*), which demonstrates that the chest tube is patent. Continuous bubbling may indicate an air leak, and newer systems have a measurement system for leaks the higher the number, the greater the air leak. The water-seal chamber can also monitor intrathoracic pressure (Teleflex Medical Incorporated, 2009).
- 3. Wet or dry suction control chamber: Not all patients require suction. If a patient is ordered suction, a wet suction system is typically controlled by the level of water in the suction control chamber and is typically set at -20 cm on the suction control chamber for adults. If there is less water, there is less suction. The amount of suction may vary depending on the patient and is controlled by the chest drainage system, not the suction source. Monitor the fluid level to ensure there is gentle bubbling in the chamber. A dry suction system uses a self-controlled regulator that adjusts the amount of suction and responds to air leaks to deliver consistent suction for the patient. If suction is discontinued, the suction port on the chest drainage system must remain unobstructed and open to air to allow air to exit and minimize the development of a tension pneumothorax (Teleflex Medical Incorporated, 2009).

In addition to the three chambers, the drainage system has many safety features to ensure that high negative pressures can be monitored and relieved quickly. To review these safety features and additional information regarding the chambers of a closed chest tube drainage system, visit the <u>Teleflex Medical Incorporated website</u>.

When a patient has a closed chest tube drainage system, it is the health care provider's responsibility to assess the patient and the equipment frequently to ensure the equipment is patent and working effectively. The health care provider should:

- Assess the patient
- Assess the chest tube drainage system for patency and troubleshoot any concerns
- Ensure the safety/emergency equipment is attached to the bed
- Promote lung expansion (deep breathing and coughing exercises, position changes, and ambulation as required)

Checklist 86 reviews the management of a patient with a chest tube drainage system.

CHECKLIST 86: MANAGEMENT OF A CHEST TUBE DRAINAGE SYSTEM (PLEUR-EVAC)

Disclaimer: Always review and follow your hospital policy regarding this specific skill.

Safety considerations:

- A chest tube may be inserted at the bedside, in procedure room, or in the surgical suite. Health care providers often assist physicians in the insertion and removal of a closed chest tube drainage system.
- After initial insertion of a chest tube drainage system, assess the patient every 15 minutes to 1 hour. Once the patient is stable, and depending on the condition of the patient and the amount of drainage, monitoring may be less frequent. If the patient is stable (vital signs within normal limits; drainage amount, colour, or consistency is within normal limits; the patient is not experiencing any respiratory distress or pain), assessment may be completed every 4 hours. Always follow hospital policy for frequency of monitoring a patient with a chest tube.
- Prior to managing a patient with a chest tube, review reason for the chest tube, the location of the chest tube, normal volume of drainage, characteristics of the drainage, date of last dressing change, and any previously recorded air leaks measurements.
- Safety/emergency equipment must always be at the patient's bedside and with the patient at all times during transportation to other departments. Safety equipment includes:
 - Two guarded clamps
 - Sterile water
 - Vaseline gauze (Jelonet)
 - 4 x 4 sterile dressing
 - Waterproof tape
- *Never* clamp a chest tube without a doctor's order or valid reason. The tube must remain unobscured and unclamped to drain air or fluid from the pleural space. There are a few exceptions where a chest tube may be clamped; see special considerations below.
- Chest tube drainage systems are replaced only when the collection chamber is full or the system is contaminated.

STEPS	ADDITIONAL INFORMATION
1. Review the patient chart for the reason for the chest tube and location and insertion date.	Knowing the reason for the chest tube and location informs the health care provider on the type of expected drainage.
2. Perform hand hygiene. identify patient using two identifiers and explain assessment process to patient. Create privacy to assess the patient and drainage system.	Hand hygiene reduces the transmission of microorganisms. Proper identification provides patient safety measures for safe care.

3. Complete respiratory assessment, ensure patient has minimal pain, and measure vital signs. Place patient in semi-Fowler's position for easier breathing.

Patient should be in a semi-Fowler's position, have minimal pain, have *no* respiratory distress, and have *no* evidence of an air leak around the insertion site, and *no* drainage from the insertion site or chest tube equipment.

Frequent assessment of the respiratory status is important if the patient's condition is stable, resolving, or worsening, and ensures that the chest tube is functioning correctly.

Assessment should be every 15 minutes to 1 hour until patient is stable. Increase monitoring if patient's condition worsens.

Chest tubes are painful, as the parietal pleura are very sensitive. Ensure patient has adequate pain relief, especially prior to repositioning, sitting, or ambulation.

4. Assess chest tube insertion site to ensure sterile dressing is dry and intact.

Dressing should remain dry and intact; no drainage holes should be visible in the chest tube.

Check insertion site for subcutaneous emphysema.

Dressing is generally changed 24 hours post-insertion, then every 48 hours. Chest tubes are generally sutured in place.

There should be no fluid leaking from around the site or sounds of air leaks from insertion site.



Chest tube insertion site

5. Maintain a closed system. Ensure all connections are taped and secured according to agency policy.

These measures are important to keep the system intact and prevent accidental tube removal or disruption of the drainage system.

6. Ensure tubing is not kinked or bent under the patient or in Kinked or bent tubing could interfere with the drainage of the the bed rails, or compressed by the bed. pleural fluid. Dependent loops may collect fluid and impede drainage. The long tube may be coiled and secured to a draw sheet with a safety pin (allowing enough tubing so that the patient can move in bed comfortably) to prevent dependent loops. Tubing free from kinks and dependent loops 7. Collection chamber (drainage system) is below the level The drainage system must remain upright for the water-seal of the chest and secured to prevent it from being accidentally chamber to function correctly. knocked over. The chest drainage system must be lower than the chest to facilitate drainage and prevent back flow. Chest drainage system lower than insertion site


8. Periodically check water-seal chamber to ensure water level is to the dotted line (2 cm) — at least once every shift. Add water as necessary.

Adequate water in the water-seal chamber prevents excess suction being placed on the delicate tissue.

Water levels should be checked each shift as the water may evaporate.

9. Check water-seal chamber for tidaling (water moving up and down) with respirations. Gentle bubbling is normal as the lungs expand.

If the water in the water seal does not move up and down with respirations, the system might not be intact or patent. Periodic bubbling in the water-seal chamber is normal and indicates that air that is trapped is being removed. Frequent assessment of the system is required to ensure proper functioning.



Chest tube drainage system with labelled parts

Excessive bubbling may cause unnecessary noise and faster evaporation.

If there is no tidaling, consider 1) an occlusion somewhere between the pleural cavity and the water seal, or 2) a full expansion of the lung, where suction has drawn the lung up against the holes in the chest tubes.

If patient is on positive pressure ventilation, the tidaling will be the opposite: the water will move down with inspiration and up with expiration.

10. Ensure suction control dial is set to ordered level (usually 20 cm).

The amount of suction in the chamber is regulated by the suction control dial, not the suction source.

11. If suction is ordered, a "float" (or equivalent) must be visible clearly in the window.

In wet suction control, gentle bubbling is normal. If there is no bubbling, ensure the connections are tight and turn the suction higher.



Suction pressure set at – 20 cm

12. If suction is *not* ordered, ensure the suction port is left open to air. Suction window will appear blank if suction is not in use or not working.

The suction port must be left open to the air and free of obstruction to prevent a tension pneumonthorax.



Suction port on the top of a chest tube drainage system



Suction control window (white rectangle)

13. In wet suction systems, expect gentle bubbling in the chamber.

Gentle bubbling is normal. Vigorous bubbling is noisy and can be disturbing to the patient. Periodically check the air vent to ensure it is not blocked or occluded.

14. Assess air leak meter to determine progress of patient's internal air level, measured as level 1 to 7. On every shift, document the level of air leak, and if the air leak occurs at rest or with coughing.


Bubbling in the air leak meter indicates an air leak. Measure and monitor.

The source of the leak may be identified by:

- Checking and tightening connections.
- Testing the tube for leaks (see special considerations below). If leak is in the tubing, replace the unit.
- If the leak may be at the insertion site, remove the chest tube dressing and inspect. Has the chest tube been pulled out beyond the chest wall? If you cannot see or hear any obvious leaks at the site, the leak is from the lung.
- Check patient history. Would you expect a patient air leak?

Notify doctor of any new, increased, or unexpected air leaks that are not corrected by the above actions.

To document the air leak, note the numbered column through which the bubbling occurs. If bubbling is present in first three columns of the air leak meter, document "air leak 3."



Air leak meter

15. Check that the clamp is open.

The chest tube should *not* be clamped unless for specific reasons. See special considerations below.



Blue clamp is open

16. Measure date and time, and the amount of drainage, and Drainage that is red and free-flowing indicates a hemorrhage. mark on the outside of the chamber. Record amount and A large amount of drainage, or drainage that changes in characteristics of the drainage on the fluid balance sheet and colour, should be recorded and reported to the primary health patient chart. care provider. Drainage that suddenly decreases may indicate a blood clot or obstruction in the chest tube drainage system. Drainage in collection chamber 17. Encourage frequent position changes as well as deep-Deep-breathing and coughing exercises promote lung expansion and promote fluid drainage. breathing and coughing exercises. 18. The following should be documented and assessed Proper documentation is required to manage a chest tube according to agency policy: drainage system to ensure it is functioning effectively. • Presence of air leaks • Fluctuation of water in water-seal chamber · Amount of suction • Amount of drainage and type • Presence of crepitus (subcutaneous emphysema)

Data source: Bauman & Handley, 2011; BCIT, 2015c; Durai, Hoque, & Davies, 2010; Rajan, 2013; Teleflex Medical Incorporated, 2009

· Breath sounds

• Patient comfort level or pain level

• Appearance of insertion site and/or dressing

Special considerations:

- Do not strip or milk the chest tube: In practice, stripping is used to describe compressing the chest tube with the thumb or forefinger and, with the other hand, using a pulling motion down the remainder of the tube away from the insertion site. *Milking* refers to techniques such as squeezing, kneading, or twisting the tube to create bursts of suction to move clots. Any aggressive manipulation (compressing the tube to dislodge blood clots) can generate extreme pressures in the chest tube. There is no evidence showing the benefit of stripping or milking a chest tube (Bauman & Handley, 2011; Durai et al., 2010; Halm, 2007).
- The *only* exceptions to clamping a chest tube are 1) if the drainage system is being changed, 2) if assessing the system for an air leak 3) if the chest tube becomes disconnected from the chest drainage system the chest tube Previous: 10.5 Tracheostomies

Watch the video <u>Chest tube care & maintenance</u> by <u>Renée Anderson & Wendy McKenzie</u>, Thompson Rivers University.

VIDEO 10.11

Watch the video <u>Dry suction chest drainage system</u> by <u>Renée Anderson & Wendy McKenzie</u>, Thompson Rivers University.

Table 10.3 provides a list of potential complications and interventions related to chest tube drainage systems.

TABLE 10.3 COMPLICATIONS AND INTERVENTIONS RELATED TO CHEST TUBE DRAINAGE SYSTEMS

Complications	Interventions
Potential pneumothorax/respiratory distress	 This is the primary concern for a patient with a chest tube drainage system. Signs and symptoms include decreased SaO₂, increased work of breathing (WOB), diminished breath sounds, decreased chest movement, complaints of chest pain, tachycardia or bradycardia, hypotension. Notify health care provider. Request urgent chest X-ray. Ensure drain system is intact with no leaks or blockages such as kinks or clamps. Apply oxygen and take a set of vital signs.
Air leak	 An air leak may occur from the chest tube insertion site or the drainage system. Do the following to test the system for the site of an air leak: Using a booted (or padded) clamp, begin at the dressing and clamp the drainage tubing momentarily. Look at the water-seal/air leak meter chamber. Keep moving the clamp down the drainage tubing toward the chest drainage system, placing it at 20 to 30 cm intervals. Each time you clamp, check the water-seal/air leak meter chamber. When you place the clamp between the source of the air leak and the water-seal/air leak meter chamber, the bubbling will stop. If bubbling stops the first time you clamp, the air leak must be at the chest tube insertion site or the lung.
Accidental chest tube removal or chest tube falls out	A chest tube falling out is an emergency. Immediately apply pressure to chest tube insertion site and apply sterile gauze or place a sterile Jelonet gauze and dry dressing over insertion site and ensure tight seal. Apply dressing when patient exhales. If patient goes into respiratory distress, call a code. Notify primary health care provider to reinsert new chest tube drainage system.
Accidental disconnection of the drainage system	A chest tube drainage system disconnecting from the chest tube inside the patient is an emergency. Immediately clamp the tube and place the end of chest tube in sterile water or NS. The two ends will need to be swabbed with alcohol and reconnected.
Bleeding at the insertion site	Bleeding may occur after insertion of the chest tube. Apply pressure to site and monitor.
Subcutaneous emphysema	Subcutaneous emphysema is painless tracking of air underneath the subcutaneous tissue. It may be seen in the chest wall, down limbs, around drain sites, or around the head or neck. When the skin is palpated, it feels similar to having tissue paper trapped beneath the skin. Monitor and report to primary health care provider.
Drainage suddenly stops and respiratory distress increases	The chest tube may be clogged by a blood clot or by fluid in a dependent loop. Assess the drainage system and the patient and notify primary health care provider if required.
Sudden increase in bright red drainage	This may indicate an active bleed. Monitor amount of drainage and vital signs, and notify the primary health care provider.
Data source: ATI, 2015c; B	3CIT, 2015c; Perry et al., 2014; Teleflex Medical Incorporated, 2009

allowing the patient to ambulate with ease. It attaches to the chest tube at one end and a drainage bag at the other. The drainage bag allows air and fluid to escape but prevents their re-entering the pleural space. The valve can be worn under clothing. The valve functions in any position, never needs to be clamped, and can be hooked up to suction if required (Gogakos et al., 2015).



Figure 10.7 Heimlich valve



Figure 10.8 Blue end connects to chest tube; other end may be left open to air or attach to a small drainage bag

Critical Thinking Exercises

- 1. What should you do if your patient's chest tube becomes disconnected from the chest tube drainage system?
- 2. When a patient has a chest tube, what emergency supplies must be at the patient's bedside at all times?

LICENSE





Clinical Procedures for Safer Patient Care by Glynda Rees Doyle and Jodie Anita McCutcheon is licensed under a <u>Creative Commons</u>

<u>Attribution 4.0 International License</u>, except where otherwise noted.

SHARE THIS BOOK



Powered by Pressbooks Guides and Tutorials | Contact