The pdfcolparcolumns package

Heiko Oberdiek <oberdiek@uni-freiburg.de>

2008/08/11 v1.2

Abstract

Since version 1.40 pdfTeX supports several color stacks. This package uses them to fix color problems in package $\sf parcolumns$.

Contents

1	Usa	ge	1		
	1.1	Future	2		
2	Implementation				
	2.1	Identification	2		
	2.2	Load packages	2		
		2.2.1 Package parcolumns	2		
		2.2.2 Package pdfcol	2		
		2.2.3 Package infwarerr	2		
	2.3	Color stack macros	2		
	2.4	Patches	3		
		2.4.1 Init stacks	3		
		2.4.2 Switch stack	3		
		2.4.3 Set current stack color	3		
3	Tes	t	5		
4	Installation				
	4.1	Download	5		
	4.2	Bundle installation	6		
	4.3	Package installation	6		
	4.4		6		
	4.5	Some details for the interested	6		
5	Ref	erences	7		
6	His	tory	7		
		7/07/26 v1.0]	7		
		7/09/09 v1.1]	7		
		8/08/11 v1.2]	7		
7	Ind	ov.	7		

1 Usage

\usepackage{pdfcolparcolumns}

The package pdfcolparcolumns loads package parcolums [1]. If color stacks are available then the macros of parcolumns are patched to add support for color stacks.

1.1 Future

Currently package parcolumns does not seem to be maintained. Nevertheless if there will be a new version that adds support for color stacks, then this package may become obsolete.

2 Implementation

2.1 Identification

```
1 \( \*\package \)
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{pdfcolparcolumns}\( \)
4 \[ [2008/08/11 v1.2 Color stacks support for parcolumns (HO)]\( \)
```

2.2 Load packages

2.2.1 Package parcolumns

Currently package parcolumns does not define options. Thus it is just a precaution that the options of package pdfcolparcolumns are passed to package parcolumns.

```
5 \DeclareOption*{%
6  \PassoptionsToPackage{\CurrentOption}{parcolumns}%
7 }
8 \ProcessOptions\relax
9 \RequirePackage{parcolumns}[2004/11/25]
```

2.2.2 Package pdfcol

```
10 \RequirePackage{pdfcol}[2007/09/09]
11 \ifpdfcolAvailable
12 \else
13 \PackageInfo{pdfcolparcolumns}{%
14 Loading aborted, because color stacks are not available%
15 }%
16 \expandafter\endinput
17 \fi
```

2.2.3 Package infwarerr

18 \RequirePackage{infwarerr}[2007/09/09]

2.3 Color stack macros

\pcpc@MaxStack Macro

Macro \pcpc@MaxStack holds the highest number of allocated stacks.

19 \global\chardef\pcpc@MaxStack=\z@

\pcpc@InitStacks

Macro \pcpc@InitStacks takes the number of columns as argument and ensures that there are enough color stacks for all columns.

```
20 \def\pcpc@InitStacks#1{\%}
    \ifnum#1>\pcpc@MaxStack
21
      \begingroup
22
         \count@\pcpc@MaxStack
23
24
         \loop
25
           \advance\count@\@ne
           \pdfcolInitStack{pcpc@\the\count@}%
26
27
         \ifnum#1>\count@
28
         \repeat
29
         \global\chardef\pcpc@MaxStack=\count@
30
       \endgroup
     \fi
31
32 }
```

\pcpc@SwitchStack

```
33 \def\pcpc@SwitchStack#1{%
34 \pdfcolSwitchStack{pcpc@\number#1}%
35 }
\pcpc@SetCurrent

36 \def\pcpc@SetCurrent#1{%
37 \pdfcolSetCurrent{pcpc@\number#1}%
38 }
```

2.4 Patches

Now the color stack macros are patched into the macros of package parcolumns.

2.4.1 Init stacks

\pcpc@InitStacks should go into the definition of environment parcolumns. \pc@alloccolumns is executed there and nowhere else, thus we hook into it.

```
39 \g@addto@macro\pc@alloccolumns{%
40 \pcpc@InitStacks\pc@columncount
41 }
```

2.4.2 Switch stack

\pcpc@SwitchStack should be called by marco \colchunk@. However it is easier to patch \pc@setcolumnwidth that is executed in \colchunk@ only.

```
42 \g@addto@macro\pc@setcolumnwidth{%
43 \pcpc@SwitchStack\pc@columnctr
44 }
```

2.4.3 Set current stack color

\pcccSetCurrent is set at the begin of each line. It must be inserted into \pccplaceboxes. Unhappily there is no easy way. Therefore we check and redefine \pccplaceboxes.

```
45 \begingroup
46
    \left( x_{x}\right) 
47
      \global\let\@tempa\relax
      \count@\z@
48
      \hb@xt@\linewidth{%
49
        \vfuzz30ex %
50
         \vbadness\@M
51
52
         \splittopskip\z@skip
53
         \loop
54
         \ifnum\count@<\pc@columncount
           \advance\count@\@ne
55
56
           \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
57
             \hskip\csname pc@column@width@\number\count@\endcsname
           \else
58
             \expandafter\setbox\expandafter\@tempboxa\expandafter
59
             \vsplit\csname pc@column@\number\count@\endcsname
60
61
                 to \dp\strutbox
             \vbox{%
62
63
               \unvbox\@tempboxa
64
             }%
65
           \fi
66
           \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
67
           \else
             \global\let\@tempa\pc@placeboxes
68
69
           \ifnum\count@<\pc@columncount
70
```

```
\strut
                                             71
                                                                             \hfill
                                             72
                                                                             \ifpc@rulebetween
                                             73
                                                                                   \vrule
                                             74
                                             75
                                                                                   \hfill
                                                                             \fi
                                             76
                                                                        \fi
                                             77
                                             78
                                                                  \repeat
                                                            }%
                                             79
                                                             \ensuremath{\texttt{Qtempa}}
                                             80
                                                       }%
                                             81
                                                        \int x\pc@placeboxes
                                             82
                                             83
                                                             \@PackageWarningNoLine{pdfcolparcolumns}{%
                                             84
                                                                  Command \string\pc@placeboxes\space has changed.\MessageBreak
                                             85
                                             86
                                                                  Supported versions of package 'parcolumns':\MessageBreak
                                             87
                                                                   \space\space 2004/08/05.\MessageBreak
                                                                  The redefinition of \sqrt{\rho}
                                             88
                                                                   \MessageBreak
                                             89
                                             90
                                                                  behave correctly depending on the changes%
                                             91
                                                            }%
                                                       \fi
                                            92
                                            93 \endgroup
\pc@placeboxes
                                             94 \renewcommand*{\pc@placeboxes}{%
                                                        \global\let\@tempa\relax
                                             95
                                                        \count@\z@
                                            96
                                                        \hb@xt@\linewidth{%
                                             97
                                                              \vfuzz30ex %
                                            98
                                                              \vbadness\@M
                                             99
                                                             \splittopskip\z@skip
                                          100
                                          101
                                          102
                                                              \ifnum\count@<\pc@columncount
                                          103
                                                                   \advance\count@\@ne
                                                                   \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
                                          104
                                                                        \hskip\csname pc@column@width@\number\count@\endcsname
                                          105
                                                                   \else
                                          106
                                          107
                                                                        \verb|\expandafter\expandafter| @ tempbox a \verb|\expandafter| | leader a constraint of the constraint of t
                                                                        \vsplit\csname pc@column@\number\count@\endcsname
                                          108
                                          109
                                                                                   to \dp\strutbox
                                          110
                                                                        \vbox{%
                                                                             \pcpc@SetCurrent\count@
                                          111
                                          112
                                                                             \unvbox\@tempboxa
                                                                       }%
                                          113
                                                                  \fi
                                          114
                                                                   \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
                                          115
                                          116
                                                                        \global\let\@tempa\pc@placeboxes
                                          117
                                                                   \fi
                                          118
                                                                   \ifnum\count@<\pc@columncount
                                          119
                                          120
                                                                        \strut
                                                                        \hfill
                                          121
                                          122
                                                                        \ifpc@rulebetween
                                          123
                                                                             \vrule
                                          124
                                                                             \hfill
                                                                       \fi
                                          125
                                                                  \fi
                                          126
                                          127
                                                             \repeat
                                                       }%
                                          128
                                                        \@tempa
                                          129
                                          130 }
```

3 Test

The test file is a modified version of the file that Donald Goodman has posted in comp.text.tex: "Re: xcolor glitches" 1 132 **(*test1)** 133 \NeedsTeXFormat{LaTeX2e} 134 \AtEndDocument{% \typeout{}% 135 136 \typeout{*** \space Check the PDF file manually! \space ***}% 137 138 139 \typeout{}% 140 } 141 \documentclass{article} 142 \usepackage{xcolor} 143 \usepackage{pdfcolparcolumns} 144 145 \newcommand{\instruct}[1]{% \noindent 146 \footnotesize 147 \textcolor{red}{#1}% 148 149 } 150 151 \begin{document} \begin{parcolumns}[colwidths={1=2.3in,2=2.3in},sloppy]{2}% 153 \colchunk[1]{% 154\instruct{Et non dicitur versus} % 155 Fidelium anim\ae\ % \instruct{% 156 sed immediate subiungitur antiphona finalis % 157 beat\ae\ Mari\ae\ Virginis% 158 } % 159 100.% 160 161 \colchunk[2]{% 162 163 \instruct{% 164 And the verse % \textcolor{black}{May the souls of the faithful} % 165 is not said, but the final antiphon of the %166 Blessed Virgin Mary, % 167 \textcolor{black}{100,} % 168

4 Installation

}%

\end{parcolumns}%

}%

173 \end{document}

174 (/test1)

4.1 Download

169

170

171

Package. This package is available on CTAN²:

is immediately joined.%

CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.dtx The source file.

CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.pdf Documentation.

¹Url: http://groups.google.com/group/comp.text.tex/msg/8eda74ed292012bb

²ftp://ftp.ctan.org/tex-archive/

Bundle. All the packages of the bundle 'oberdiek' are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

```
CTAN:install/macros/latex/contrib/oberdiek.tds.zip
```

TDS refers to the standard "A Directory Structure for TEX Files" (CTAN:tds/tds.pdf). Directories with texmf in their name are usually organized this way.

4.2 Bundle installation

Unpacking. Unpack the oberdiek.tds.zip in the TDS tree (also known as texmf tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory TDS:scripts/oberdiek/ for scripts that need further installation steps. Package attachfile2 comes with the Perl script pdfatfi.pl that should be installed in such a way that it can be called as pdfatfi. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

4.3 Package installation

Unpacking. The .dtx file is a self-extracting docstrip archive. The files are extracted by running the .dtx through plain- T_EX :

```
tex pdfcolparcolumns.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as texmf tree):

```
 \begin{array}{lll} pdfcolparcolumns.sty & \rightarrow \ tex/latex/oberdiek/pdfcolparcolumns.sty \\ pdfcolparcolumns.pdf & \rightarrow \ doc/latex/oberdiek/pdfcolparcolumns.pdf \\ test/pdfcolparcolumns-test1.tex & \rightarrow \ doc/latex/oberdiek/test/pdfcolparcolumns-test1.tex \\ pdfcolparcolumns.dtx & \rightarrow \ source/latex/oberdiek/pdfcolparcolumns.dtx \end{array}
```

If you have a docstrip.cfg that configures and enables docstrip's TDS installing feature, then some files can already be in the right place, see the documentation of docstrip.

4.4 Refresh file name databases

If your T_EX distribution (te T_EX , mik T_EX , ...) relies on file name databases, you must refresh these. For example, te T_EX users run texhash or mktexlsr.

4.5 Some details for the interested

Attached source. The PDF documentation on CTAN also includes the .dtx source file. It can be extracted by AcrobatReader 6 or higher. Another option is pdftk, e.g. unpack the file into the current directory:

```
pdftk pdfcolparcolumns.pdf unpack_files output .
```

Unpacking with LATEX. The .dtx chooses its action depending on the format: plain-TeX: Run docstrip and extract the files.

LATEX: Generate the documentation.

If you insist on using LATEX for docstrip (really, docstrip does not need LATEX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdfcolparcolumns.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the .dtx or the .drv to generate the documentation. The process can be configured by the configuration file ltxdoc.cfg. For instance, put this line into this file, if you want to have A4 as paper format:

\PassOptionsToClass{a4paper}{article}

An example follows how to generate the documentation with pdfIATEX:

```
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
```

5 References

- [1] Jonathan Sauer: *The parcolumns package*; 2004/11/25; CTAN:macros/latex/contrib/sauerj/parcolumns.pdf.
- [2] Heiko Oberdiek: The pdfcol package; 2007/09/09;CTAN:macros/latex/contrib/oberdiek/pdfcol.pdf.

6 History

[2007/07/26 v1.0]

• First version, published in the newsgroup comp.text.tex with the name parcolumns-colorstacks: "Re: xcolor glitches" 3

[2007/09/09 v1.1]

- CTAN version, package name renamed to pdfcolparcolumns.
- Uses package pdfcol.
- Documentation added.
- Test file added.

[2008/08/11 v1.2]

- Code is not changed.
- URLs updated.

7 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols

\ 155, 158
Δ
\mathbf{A}
\advance 25, 55, 103
(davance 20, 00, 100
\ae
\AtEndDocument 134

³Url: http://groups.google.com/group/comp.text.tex/msg/56bd897b11bca414

В	P
\begin 151, 152	\PackageInfo 13
	\PassoptionsToPackage 6
C 10.00	\pc@alloccolumns 39
\chardef	\pc@columncount 40, 54, 70, 102, 119
\colchunk 153, 162 \count@ 23, 25, 26, 27, 29, 48, 54,	\pc@columnctr 43
55, 56, 57, 60, 66, 70, 96, 102,	\pc@placeboxes $68, 82, 85, 88, 94$
103, 104, 105, 108, 111, 115, 119	\pc@setcolumnwidth 42
\csname 56, 57, 60, 66, 104, 105, 108, 115	\pcpc@InitStacks 20, 40
\CurrentOption 6	\pcpc@MaxStack <u>19, 21, 23, 29</u>
•	\pcpc@SetCurrent <u>36</u> , 111
D	\pcpc@SwitchStack 33, 43
\DeclareOption 5	\pdfcolInitStack 26
\documentclass 141	\pdfcolSetCurrent
\dp 61, 109	\pdfcolSwitchStack
${f E}$	\ProcessOptions 8
\end 172, 173	\ProvidesPackage3
\endcsname \ldots \ldot	R
. 56, 57, 60, 66, 104, 105, 108, 115	\renewcommand 94
\endinput 16	\repeat 28, 78, 127
•	\RequirePackage 9, 10, 18
\mathbf{F}	(
\footnotesize 147	${f S}$
${f G}$	\setbox 59, 107
\g@addto@macro 39, 42	\space 85, 87, 88, 137
	\splittopskip 52, 100
Н	\strut 71, 120
\hb@xt@ 49, 97	\strutbox 61, 109
\hfill 72, 75, 121, 124	Th.
\hskip 57, 105	T
I	\textcolor 148, 165, 168
\ifnum 21, 27, 54, 70, 102, 119	\the
\ifpc@rulebetween	\typeout 135, 136, 137, 138, 139
\ifpdfcolAvailable 11	\mathbf{U}
\ifvoid 56, 66, 104, 115	\unvbox 63, 112
\ifx 82	\usepackage 142, 143
\instruct 145, 154, 156, 163	(mr.m
	\mathbf{V}
L 40.07	\vbadness 51, 99
\linewidth	\vbox 62, 110
\loop 24, 53, 101	\vfuzz 50, 98
${f M}$	\vrule 74, 123
\MessageBreak 85, 86, 87, 89	\vsplit 60, 108
N	X
\NeedsTeXFormat	\x
\newcommand	,
\noindent 146	${f z}$
\number 34,	\z@ 19, 48, 96
37, 56, 57, 60, 66, 104, 105, 108, 115	\z@skip 52, 100