
SatLim 0.1.0

2-stage clipper / limiter with waveshaping saturator

A 2-stage clipper and limiter with a waveshaping saturator. When you need to nuke it from orbit.


SatLim
SATLIM 0.1
250%
DELTA
BYPASS
Master_Loud
SRC OUT+GR
WAVE HALF
WIN 2s
CEIL +2dB
TUBE
OVERSAMPLE
x1
x2
x4
x8
OUT +0.0dB
SAT -0.4dB
9.2
6
3
6
9
12
6
12
24
36
GR 01.2dB
CLIP 08.0dB
TRU.PK -00.3dB
RMS -07.1dB
L.AHEAD ON
CEILING
-0.5dB
THRESHOLD
-8.0dB
CLIP
60%
RELEASE
40ms
OUT GAIN
+0.0dB
DRIVE
0%
BIAS +0%
ASYM 100%
HP OFF
LP OFF
TONE
OFF
SAT MIX
100%
SAT GAIN
+0.0dB
SatLim v0.1.0

1. The idea

SatLim chews the signal in three steps: a saturator, a hard clipper that bricks the peaks, and a true-peak limiter that catches what the clipper leaves behind.

```
IN > SAT (x1-x8) > lift to the ceiling > CLIP > LIMITER > OUT GAIN > OUT
```

- **THRESHOLD** is the input level that lands on the ceiling. The signal is lifted by `CEILING - THRESHOLD` dB, so lowering the threshold pushes harder into the clipper and limiter.
- **CLIP** clamps the peaks at the ceiling (oversampled) before the limiter sees them. The more clip, the less the limiter has to do, and the more the transients get bricked.
- **LIMITER** catches the remaining inter-sample peaks. With lookahead on it is a true-peak brickwall.
- **OUT GAIN** is after the limiter on purpose. The ceiling is what the limiter holds; the output gain is free, so you can pull the level back for converters that see inter-sample peaks.

2. Layout

Area	What it does
Header	logo (themes), preset bar, window scale, DELTA, BYPASS
Transient scope	the output with what the limiter and the clipper removed, stacked
Scope controls	SRC, WAVE, WIN and CEIL settings under the scope
Saturator (left)	shaper, DRIVE, BIAS, ASYM, HP, LP, TONE, SAT MIX, SAT GAIN and the transfer plot
Meters (middle)	post-saturator level, gain reduction, output level
Right column	OVERSAMPLE, readouts, L.AHEAD, CEILING, THRESHOLD, CLIP, RELEASE, OUT GAIN

3. Limiter section

Control	What it does
CEILING	the level the limiter holds
THRESHOLD	input level that lands on the ceiling; lower is harder
CLIP	0-100 %. 0 = off. Otherwise a hard clamp at the ceiling, driven up to +6 dB into it.
RELEASE	15-80 ms. A shorter release gives a denser, punchier result and more distortion artifacts; a longer one is smoother with less distortion.
L.AHEAD	on: 1.5 ms lookahead with true-peak detection, a brickwall. Off: zero limiter latency, but the gain follows sample peaks, so inter-sample overs can pass.
OUT GAIN	final level, after the limiter
x1 / x2 / x4 / x8	oversampling of the saturator and the clipper (more oversampling, less aliasing, more latency)

Balance THRESHOLD and CLIP. Use THRESHOLD to set how hard the signal hits the ceiling and CLIP to choose how much of that is bricked by the clipper instead of squeezed by the limiter. More clip sounds harder and more distorted; more limiting sounds denser and flatter.

4. Saturator

Control	What it does
Shaper	15 waveshapers, from Tube for warm saturation through Tri Fold for destruction to **Custom**
DRIVE, BIAS, ASYM, HP, LP, TONE, SAT MIX	the same as in SatComp: push, offset, even-order amount, band split, tone, wet/dry
SAT GAIN	level after the saturator. Click the **SAT** readout to auto-match it.

Custom curve. Click the pencil icon to draw your own transfer curve (up to 10 points), with a symmetry tool for odd curves.

5. Scope and meters

The **transient scope** shows the output waveform (UI colour) with two things stacked on top: what the limiter removed (solid accent) and what the clipper removed (hatched accent), up to the peak before clipping. Drag the scope to change its window; **CEIL** sets the ceiling of the view (+10 to -14 dB) so heavy clipping above 0 dBFS stays visible.

Readout	Meaning
GR	limiter gain reduction
CLIP	clipper reduction
TRU.PK	true peak of the output (8x), whether lookahead is on or off. It turns accent only when it clips.
RMS	output level

The **gain reduction meter** splits the same way: the limiter's part solid, the clipper's part hatched under it. **Click** it to cycle its range. The output meter's top block holds the clip lamp; **click** it to reset it and the peak readout.

6. Output and tools

Control	What it does
DELTA	listen to what the clipper and limiter removed
BYPASS	plain bypass: your input at the plug-in's latency, at its own level

7. Recipes

Master-bus loudness. Pick Tube with low drive, a ceiling at -1 dB, THRESHOLD around -4 to -6 dB and a moderate CLIP. Use a release around 40 ms. Pull OUT GAIN down 0.5 dB if you need headroom for the converter.

Crunchy drums. Diode with 30 % drive, x4, lookahead off, a short release and a firmer CLIP. Watch the scope: the hatched part is the clipper doing the work.

Brickwall safety. Keep CLIP at 0, put the ceiling where you want it and use a low threshold only if you want loudness as well as protection.

8. Good to know

- **Latency** is the saturator oversampler plus the clipper oversampler plus the limiter lookahead. It is reported to the host and changes with the x1-x8 setting and L.AHEAD.
- **Presets:** six factory presets ship with the plug-in; yours are saved to `SatLim/Presets` in your application-support folder.
- **Themes:** click the logo for the next scheme, double-click it for dark/light, right-click for the list. **Preferences** has **SCOPE FILL**: solid bars or an outline.
- Double-click any slider to reset it.