



Neo4j Admin and Neo4j CLI

Introduction

neo4j-admin and neo4j are command-line tools for managing and administering a Neo4j DBMS. Both are installed as part of the product and can be executed with a number of commands. The neo4j commands are equivalent to the most important commands in the neo4j-admin server category.

Both neo4j-admin and neo4j commands support the --help option, which prints the command's usage and options, and the --version option, which prints the version of the command. All admin command options can also be provided in a file and passed to the command using the @ prefix. This is useful when the command line becomes too long to manage. For example, neo4j-admin database import full @/path/to/your/<args-filename> mydb . For more information, see Picocli \rightarrow AtFiles \rightarrow official documentation.

NOTE

All admin commands must be invoked with the same user as Neo4j runs as. This guarantees that Neo4j will have full rights to start and work with the database files you use.

The neo4j-admin tool

The neo4j-admin command-line tool is located in the <u>bin</u> directory.

General synopsis

neo4j-admin has the following general synopsis:

neo4j-admin [category] [command] [subcommand]

neo4j-admin commands per category



All administration commands, except for help and version, are organized into the following three categories:

- dbms -DBMS-wide (for single and clustered environments) administration tasks
- server -server-wide administration tasks
- database -database-specific administration tasks
- backup -backup-specific tasks

Table 1. Available commands per category

Category	Command	Description
dbms	set-default-admin	Sets the default admin user when no roles are present.
	set-initial-password	Sets the initial password of the initial admin user (neo4j). For details, see <u>Set an initial password</u> .
	unbind-system-db	Removes and archives the cluster state of the system database so the instance can rebind to a new cluster state of the system database.

Category	Command	Description
server	console	Starts DBMS server in the console.
	get-id	Displays the server ID of an instance. The server ID can be used to specify a server in Cypher commands.
	license	Accept the license agreement. Possible options areaccept-commercial for the commercial oraccept-evaluation for the evaluation license. This command must be run before starting the Neo4j Enterprise Edition. Starting from Neo4j 2025.04, when using an evaluation license, the command prints information about the days remaining in the trial period. If the evaluation license has expired, the command prints a warning with the number of days since the license expired. neo4j-admin server license also logs information about license status in the neo4j.log file on startup.
	memory-recommendation	Prints recommendations for Neo4j heap and page cache memory usage. For details, see <u>Get initial memory recommendations</u> .
	migrate-configuration	Migrates server configuration from the previous major version. For details, see <u>Migrate configurations</u> .
	report	Produces a ZIP/TAR of the most common information needed for remote assessments. For details, see <u>Generate a report about the system</u> .
	restart	Restarts the server daemon.
	start	Starts the server as a daemon.
	status	Gets the status of the server.
	stop	Stops the server daemon.
	unbind	Removes cluster state data from a stopped Neo4j server. For details, see <u>Unbind a server</u> .

Category	Command	Description
	validate-config	Performs configuration validation without starting the server. For details, see <u>Validate configurations</u> .
	windows-service	A command whose subcommands can be used to install, uninstall, and update Neo4j as a Windows service.

Category	Command	Description
database	aggregate-backup Deprecated in 2025.01	Aggregates a chain of backup artifacts into a single artifact. For details, see <u>Aggregate a database backup chain</u> . Replaced by neo4j-admin backup aggregate.
	backup	Performs an online backup from a running Neo4j enterprise server.
	check	Checks the consistency of a database. For details, see <u>Check database consistency</u> .
	сору	Copies a database and optionally applies filters. For details, see <u>Copy a database store</u> .
	dump	Dumps a database into a single-file archive. For details, see <u>Back up an offline database</u> .
	import	Imports a collection of CSV files. For details, see <u>Import</u> .
	info	Prints information about a Neo4j database store. For details, see <u>Display store information</u> .
	load	Loads a database from an archive created with the dump command. For details, see <u>Restore a database dump</u> .
	migrate	Migrates a database from one store format to another or between versions of the same format. For details, see <u>Migrate a database</u> .
	restore	Restores a backed up database. For details, see <u>Restore a database backup</u> .
	upload	Pushes a local database to a Neo4j Aura instance. For details, see <u>Upload to Neo4j Aura</u> .

Category	Command	Description
backup	inspect	Lists the metadata stored in the header of backup files. For details, see <u>Inspect the metadata of a backup file</u> .
	aggregate Introduced in 2025.01	Aggregates a chain of backup artifacts into a single artifact. For details, see <u>Aggregate a database backup chain</u> .

The neo4j tool

The neo4j command-line tool is located in the *bin* directory.

General synopsis

neo4j has the following general synopsis:

neo4j [command]

neo4j commands

The command is an alias for the most important commands in the neo4j-admin server category.

Table 2. Equivalence between **neo4j** and **neo4j-admin** commands

neo4j command	Equivalent neo4j-admin command
neo4j console	neo4j-admin server console
neo4j restart	neo4j-admin server restart
neo4j start	neo4j-admin server start
neo4j status	neo4j-admin server status
neo4j stop	neo4j-admin server stop
neo4j windows-service	neo4j-admin server windows-service

Version command

Version can be obtained by invoking the version command, --version command option, or its short alternative -V, on the root level of both neo4j and neo4j-admin commands. For example, neo4j --version, neo4j-admin -V, neo4j-admin version, or neo4j version.

Help command

Help can be obtained by invoking the help command, --help command option, or its short alternative -h, with both neo4j and neo4j-admin commands. --help and -h options can be invoked on any level, namely root, category, command, and subcommand. For example, neo4j --help, neo4j [command] -h, neo4j-admin [category] --help, or neo4j-admin [category] [command] [subcommand] -h.

The help command can be invoked on any level except the last one, which means command-level for commands that do not have subcommands or subcommand level for commands with subcommands. The help command also accepts a parameter. For example, neo4j help, neo4j-admin help, neo4j-admin [category] help, neo4j-admin help [category], neo4j help [command], or neo4j-admin [category] [command] help [subcommand].

Limitations

Configuration

Administration operations use the configuration specified in the *neo4j.conf* file. Sharing configuration between the DBMS and its administration tasks makes sense as most settings are the same. In some cases, however, it is better to override some settings specified in *neo4j.conf* by configuring the tasks (instead of updating the config settings in the *neo4j.conf* file) because administration tasks generally use fewer resources than the DBMS. For instance, if the page cache

of your DBMS is configured to a very high value in *neo4j.conf*, and you want to override this because the admin tasks like backup do not need so much memory, you provide configuration for the admin tasks instead of updating the page cache setting in the *neo4j.conf* file.

There are several options for overriding settings specified in the *neo4j.conf* file using administration tasks:

- --additional-config option almost all administration commands support the -additional-config option, which you can use to provide a path (full path, local path, or
 symlinks) to a file with additional configuration. The file format should be the same as
 neo4j.conf (or neo4j-admin.conf). The file must be readable by the user running the admin
 command.
- neo4j-admin.conf a configuration file located in the same directory as the neo4j.conf file, which you can use to provide administration-task-specific settings.
- Some commands also support a command-specific configuration file. Such files are also looked for in the same directory as the *neo4j.conf* file. The following table lists command-specific configuration files:

Table 3. Command-specific configuration files

Command	Configuration file
neo4j-admin database backup	neo4j-admin-database-backup.conf
neo4j-admin database check	neo4j-admin-database-check.conf
neo4j-admin database copy	neo4j-admin-database-copy.conf
neo4j-admin database dump	neo4j-admin-database-dump.conf
neo4j-admin database import	neo4j-admin-database-import.conf
neo4j-admin database load	neo4j-admin-database-load.conf
neo4j-admin database migrate	neo4j-admin-database-migrate.conf
neo4j-admin database restore	neo4j-admin-database-restore.conf

All four configuration sources are optional and settings for administration commands are resolved from them with the following descending priority:

- 1. --additional-config option
- 2. command-specific configuration file
- 3. neo4j-admin.conf
- 4. neo4j.conf

NOTE

The commands for launching the DBMS, neo4j start and neo4j console, must be configured only in the neo4j.conf file.

Environment variables

Neo4j Admin can also use the following environment variables:

Environment variable	Description
NE04J_DEBUG	Set to anything to enable debug output.
NEO4J_HOME	Neo4j home directory.
NE04J_CONF	Path to the directory that contains neo4j.conf.
HEAP_SIZE	Set JVM maximum heap size during command execution. Takes a number and a unit, for example, 512m.
JAVA_OPTS	Additional JVM arguments.

If set, HEAP_SIZE and JAVA_OPTS override all relevant settings specified in the configuration file.

Exit codes

When neo4j and neo4j-admin finish as expected, they exit with code 0. A non-zero exit code means something undesired happened during command execution.

Table 4. Exit codes

Exit code	Description
0	Successful execution.

Exit code	Description
1	The command failed to execute.
3	The command failed to execute because the database is not running.
64	The command was invoked with incorrect options/parameters. See the printed usage for details.
70	An exception was thrown, not handled otherwise.

The non-zero exit code can contain further information about the error, for example, see the backup command's exit codes.

Command-line completion

From 5.4 onwards, Neo4j supports command-line completion.

- For Unix-based systems, the tab completion applies to the neo4j and neo4j-admin command line interfaces in terminals such as Bash and ZSH.
- For RPM and DEB packaged installations, the necessary files are automatically installed in bash-completion.
- For tarball installations, the files are located in the *bin/completion/* directory with detailed instructions for manual installation.

Prev

Next

← Generate a report about the system

Cypher Shell →

Contents

Introduction

The neo4j-admin tool

General synopsis

neo4j-admin commands per

category

The neo4j tool

General synopsis

neo4j commands

Version command

Help command

Limitations

Configuration

Environment variables

Exit codes

Command-line completion



Nov 6 2025

The Call for Papers is now open and we want to hear about your graph-related projects. Submit your talks by June 15

Submit your talk

LEARN



Neo4j Community

Site

Neo4j Developer Blog

Neo4j Videos

GraphAcademy

SOCIAL

Twitter

Meetups

Github

Stack Overflow

$\textbf{CONTACT US} \rightarrow$

US: 1-855-636-4532

Sweden +46 171 480 113

UK: +44 20 3868 3223

France: +33 (0) 1 88 46 13

20

Neo4j Labs

Want to Speak?

© 2025 Neo4j, Inc.

Terms | Privacy | Sitemap

Neo4j[®], Neo Technology[®], Cypher[®], Neo4j[®] Bloom[™] and Neo4j[®] Aura[™] are registered trademarks of Neo4j, Inc. All other marks are owned by their respective companies.