z/OS 2.5

MVS Programming: Product Registration





© Copyright International Business Machines Corporation 1997, 2021.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

# **Contents**

Figures	V
About this document	
About this document	
How to use this document	
Where to find more information	
What Java level support is necessary for product registration	
What sava level support is necessary for product registration	······ VII
How to send your comments to IBM	
If you have a technical problem	ix
Summary of changes	xi
Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 5	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,
(V2R5)	x
Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 4 (V2R4)	
Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 3 (V2R3) and its updates	
	_
Chapter 1. Using Registration Services	
Registering a Product	
Using the Register Service	
Using the Deregister Service	
Checking Product Status	చ
Chapter 2 Coding Pegistration Services	5
Chapter 2. Coding Registration Services  Invoking the Services	
Register Service (IFAEDREG)	
Syntax	
Parameters	
Return Codes.	
Deregister Service (IFAEDDRG)	
Syntax	
Parameters	
Return Codes	
Query_Status Service (IFAEDSTA)	
Syntax	
Parameters	
Return Codes.	
List_Status Service (IFAEDLIS)	
Syntax	
ParametersReturn Codes	
IFAEDC	
II ALDC	24
Chapter 3. Examples	31
Registering a product, checking the status of another product, then deregistering the first product	
using assembler	
Obtaining a list of information about products that are registered using assembler	

37
37
37
35
37
<b>4</b> 1
42 43
43
43
44

# **Figures**

1. An Overview of Product Enablement	1
2. IFAEDC from SYS1.SAMPLIB	25
3. Example 1 — Using IFAEDREG, IFAEDSTA and IFAEDDRG	31
4. Example 2 — Using IFAEDLIS	33

# **About this document**

Product registration services allow products to register with MVS<sup>™</sup> when they are running on a particular system. Other products can then use registration services to determine what products are running on a particular system.

Product registration provides an additional function for optional products, or elements, of z/OS. These optional products, which can be either products, product features, or combinations of product and feature, can use registration services to determine, based on a policy the customer sets, whether they are enabled to run on a particular system.

This book describes how to use registration services.

#### Who should use this document

This book is for programmers who design and write, in assembler, C, or Java<sup>™</sup> programs that use registration services. It requires an understanding of how to work with MVS system interfaces.

## How to use this document

This book is one of the set of programming books for MVS. This set describes how to write programs in assembler language or high-level languages, such as C, FORTRAN, and COBOL. For more information about the content of this set of books, see *z/OS Information Roadmap*.

**Note:** If you call the services described in this book from assembler language programs, you must use a high-level assembler.

## Where to find more information

Where necessary, this book references information in other books, using shortened versions of the book title. For complete titles, and order numbers of the books for all products that are part of z/OS, see z/OS Information Roadmap.

# What Java level support is necessary for product registration

The product registration Java support requires that the following Java level or higher be installed:

• IBM® SDK for z/OS Java 2 Technology Edition, Version 1.4 PTF UQ93743, product number 5655-I56.

# How to send your comments to IBM

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

**Important:** If your comment regards a technical question or problem, see instead <u>"If you have a technical</u> problem" on page ix.

Submit your feedback by using the appropriate method for your type of comment or question:

#### Feedback on z/OS function

If your comment or question is about z/OS itself, submit a request through the <u>IBM RFE Community</u> (www.ibm.com/developerworks/rfe/).

#### **Feedback on IBM Documentation function**

If your comment or question is about the IBM Documentation functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Documentation Support at ibmdocs@us.ibm.com.

#### Feedback on the z/OS product documentation and content

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to <a href="mailto:mhvrcfs@us.ibm.com">mhvrcfs@us.ibm.com</a>. We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS MVS Programming: Product Registration, SA38-0698-50
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive authority to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

# If you have a technical problem

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the IBM Support Portal (support.ibm.com).
- Contact your IBM service representative.
- Call IBM technical support.

# **Summary of changes**

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

**Note:** IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under IBM z/OS Product Documentation Update Policy (www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy? OpenDocument).

# Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 5 (V2R5)

This information contains no technical changes for this release.

# Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 4 (V2R4)

This information contains no technical changes for this release.

# Summary of changes for z/OS MVS Programming: Product Registration for Version 2 Release 3 (V2R3) and its updates

This information contains no technical changes for this release.

# **Chapter 1. Using Registration Services**

Product registration provides a common mechanism for products to:

- Register (indicate that they are running) on a particular system
- Determine what products are registered (running) on a particular system

With z/OS, products, such as z/OS features, can use registration services to determine if they are enabled to run on a particular system. <u>z/OS MVS Product Management</u> describes product enablement, which requires that the product be defined appropriately in the enablement policy for the system.

The IFAPRDxx parmlib member contains the enablement policy, which the customer defines for a system.

<u>Figure 1 on page 1</u> shows how the product code, the enablement policy, and MVS registration services fit together to determine whether a product is enabled.




Figure 1. An Overview of Product Enablement

As Figure 1 on page 1 shows, the product code issues the register request to indicate that it is running and check its enablement status. The customer policy in IFAPRDxx defines enablement status for products. When MVS processes the register request, it matches the product name definition in the request with the entries in the enablement policy to determine if the product is enabled on the system, then issues a return code to indicate enablement status. Based on the return code, the product continues to run or ends its processing.

If you are interested in how to enable a product, see:

- <u>z/OS MVS Product Management</u> for information about product enablement and reporting on registered products.
- z/OS MVS Initialization and Tuning Reference for an explanation of how to update IFAPRDxx.
- z/OS Planning for Installation for a description of how to enable z/OS features.

This book, in contrast, describes how to use registration services. It is for the product programmer who needs to know:

- How to use registration services to register a product. See "Registering a Product" on page 2.
- How to use registration services to check product status determine if a product is registered or enabled, or both, on a particular system. See "Checking Product Status" on page 3.

Registration services provide a standard mechanism for determining when a product is running or enabled on a system. Thus, the services are useful for all products with known dependencies on other IBM products or the products of independent software vendors or solution providers.

Examples of using the services appear in Chapter 3, "Examples," on page 31.

# **Registering a Product**

To register a product, issue the Register service. See <u>"Using the Register Service" on page 2</u>. When a product calls the Register service, MVS determines, based on the register request and the enablement policy defined in IFAPRDxx, whether or not the product is enabled to run on the system.

If the Register request type and the policy entry indicate that the product can run on the system, MVS registers the product as one that is running. Other products can then use the Query\_Status and List\_Status services to check whether your product is running. The system and other products assume that a product that is registered is a product that is running on a particular system.

Thus, it is important that, when your product finishes processing, it issue the Deregister service to tell MVS that it is no longer running. See "Using the Deregister Service" on page 2.

## **Using the Register Service**

When a product issues the Register service, the system checks the enablement policy in IFAPRDxx. If the check is successful, MVS issues a return code of 0 and adds the product to its list of registered (running) products.

For the check to be successful, you need to select the type of Register request very carefully, depending on what you want to do:

- To register your product without regard to the enablement policy, select Ifaedreg\_Type\_Required.
   When it processes your request, the system does not check the enablement policy. Use this register request when you are registering only to allow other products:
  - To determine if your product is running.
  - To access information you provide through the Features parameter.
- To register your product and consider it enabled even if there is no entry in the policy, select **Ifaedreg\_Type\_Standard**. This type of request is useful when your product can be enabled without any user change to the policy in IFAPRDxx. With the standard register request, you get return code 4 (indicating that the product is disabled) only when there is a matching statement that explicitly disables the product.
- To register your product and consider it disabled when there is no entry in the policy, select **Ifaedreg\_Type\_NotFoundDisabled**. For the request to be successful, there must be a matching statement in the policy that explicitly enables the product. You get return code 4 when the product is explicitly disabled or when there is no matching statement.

The product definitions in the enablement policy can contain wildcard characters (? and \*), and MVS allows wildcard matching so that a single policy statement can apply to multiple products.

Because of the interaction between the product definition in the register request, the type of register request, and the contents of IFAPRDxx, make sure that your product documentation provides the information users need to update IFAPRDxx, as described in z/OS MVS Initialization and Tuning Reference.

The placement of the Register request in your product code is also important. Most products and separately orderable features would invoke the Register service during initialization. Products or features that have multiple entry points or that allow branch entry must consider registering at each possible point of invocation.

If other products need information about your product, you can use the **Features** parameter to pass the information. Callers of the Query\_Status service can obtain this information, but you need to define its contents and format to enable the callers to interpret the information correctly.

See <u>"Register Service (IFAEDREG)" on page 6</u> for a complete description of the service, including the various types of register request.

# **Using the Deregister Service**

While the system can automatically deregister a product during task or address space termination, it is a good practice to issue the Deregister service when a registered product completes its processing.

Issuing the Deregister service ensures that any status queries that other products issue return correct results. The system considers a registered product to be a running product. If your product stops running but does not deregister, any query of its status will indicate that it is still running.

See "Deregister Service (IFAEDDRG)" on page 13 for a complete description of the service.

# **Checking Product Status**

There are two services you can use to check product status:

- Query\_Status, described in "Query\_Status Service (IFAEDSTA)" on page 15
- List\_Status, described in "List\_Status Service (IFAEDLIS)" on page 19

Which service you need depends on the information your product requires:

- To determine if a specific product is registered and obtain its enablement status (enabled, disabled, or not known), issue the Query\_Status service.
- To obtain information about the registration and enablement status of one or more products, issue the List\_Status service.
- To determine what entry in the enablement policy the system would use to determine the enablement status of a particular product, issue the List\_Status service.

Both services return information in data areas mapped for the assembler language programmer in mapping macro IFAEDIDF and for the C programmer in include file IFAEDC.

Before you issue either service, you need to know how any product you are interested in was defined when it was registered.

If you are using Query\_Status to request the status of a specific product, you might need additional documentation from the product. When a product registers, it can provide information for the system to pass to the caller of Query\_Status. If you are interested in a product that provides this additional information, you need to understand the content and format of the information you will receive.

# **Chapter 2. Coding Registration Services**

There are four registration services:

- Register service registers a product or feature with MVS
- Deregister service deregisters a product, usually done when an element completes processing.
- Query\_Status service checks the status of a specific product
- List\_Status service checks the status of one or more products

These callable services share common invocation characteristics and common processing considerations.

# **Invoking the Services**

The following information describes the environment required, restrictions, register information, performance implications, and abend codes for the registration services.

#### **Environment**

The environment for the callers are:

#### **Minimum authorization:**

Problem state and any PSW key

#### Dispatchable unit mode:

Task

#### **Cross memory mode:**

PASN=HASN=SASN

#### AMODE:

31-bit

#### **ASC** mode:

Primary

#### **Interrupt Status:**

Enabled for I/O and external interrupts

#### Locks

No locks may be held.

#### **Control parameters:**

Control parameters must be in the primary address space.

#### **Programming Requirements**

- If you are coding in assembler, include mapping macro IFAEDIDF. It provides return code equates for the various services and mappings for the output from the Query\_Status service and the List\_Status service. For a description of IFAEDIDF, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- If you are coding in C, include file IFAEDC provides data definitions for the various services. For a description of IFAEDC, see "IFAEDC" on page 24.
- If you are coding in Java, use the methods in the IFAEDJReg class. See <u>"Registering and deregistering a</u> product using Java" on page 34 for more information.

#### Restrictions

- The caller cannot have an established FRR.
- An unauthorized caller of the Register service cannot register if there are already 10 successful registrations (counting all products) made by unauthorized callers from that address space.
- An unauthorized caller cannot deregister a product that was registered by an authorized caller.

• An unauthorized caller cannot deregister a product that was registered from another address space.

#### **Input Register Information**

Before issuing any registration service, the caller does not have to place any information into any register unless using it in register notation for a particular parameter, or using it as a base register.

#### **Output Register Information**

When control returns to the caller, the general purpose registers (GPRs) contain:

#### Register

#### Contents

0-1

Used as work registers by the system

#### 2-13

Unchanged

#### 14-15

Used as work registers by the system

When control returns to the caller, the ARs contain:

#### Register

#### **Contents**

0-1

Used as work registers by the system

#### 2-13

Unchanged

#### 14-15

Used as work registers by the system

Some callers depend on register contents remaining the same before and after issuing a service. If the system changes the contents of register on which the caller depends, the caller must save them before issuing the service, and restore them after the system returns control.

#### **Performance Implications**

These services should not be used in a performance-sensitive environment.

#### **ABEND Codes**

Callers of the registration services might encounter the following ABEND codes:

#### 0C4

**Meaning**: The system cannot properly access a user-provided parameter.

#### **B**78

**Meaning**: The caller was not enabled for I/O and external interrupts.

# **Register Service (IFAEDREG)**

Use the Register service (IFAEDREG) to register a product with MVS. You can register a product or a unique product/feature combination. When you register a product with MVS, you indicate that the registered product is running on the system.

The Register service returns information to the caller and also maintains information that other callers can query to determine if products are registered (running) and enabled on the system.

If the product is an optional z/OS element, feature, or element/feature combination, MVS can also determine whether the element is enabled on this system.

To determine enablement, the system matches the product identified in the call against the policy statements in parmlib member IFAPRDxx.

It is possible, because of wildcard characters (? and \*) in the policy statements, that multiple policy statements might match the given input product. In that case, MVS uses the "best" match to determine whether or not the product is enabled, using the following rules:

- 1. An exact match is better than a wildcard match. There is no differentiation between two wildcard matches.
- 2. The parameters are processed in the following order: Prodowner, ProdID, Prodname, Featurename, Prodvers, Prodrel, and Prodmod. An exact match on a parameter earlier in the list (such as Prodowner) is better than a match on a parameter later in the list (such as Prodname).
- 3. If, after applying the first two rules, more than one match remains, MVS uses the first match of those that remain.

If product code is neither in supervisor state nor running under a system key, it cannot issue more than 10 register requests.

## **Syntax**

```
CALL IFAEDREG,
                                 (Type
                                 .Prodowner
                                 ,Prodname
                                 ,Featurename
                                 ,Prodvers
                                 ,Prodrel
                                 ,Prodmod
                                 ,ProdID
                                 ,Featureslen
                                 ,Features
                                 ,Prodtoken
                                 ,Returncode)
```

In C: the syntax is similar. You can use either of the following techniques to invoke the service:

```
    ifaedreg (Type,...Returncode);
```

When you use this technique, you must link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB.

```
ifaedreg_byaddr (Type,...Returncode);
```

This second technique requires AMODE=31, and, before you issue the CALL, you must verify that the IFAEDREG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

In Assembler: Link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB unless you use either of the following techniques as an alternative to CALL IFAEDREG:

```
1.
     LOAD EP=IFAEDREG
     Save the entry point address
     Put the saved entry point address into R15
     Issue CALL (15),...
         15,X'10'
2.
                                     Get CVT
         15,X'8C'(,15)
15,X'1C0'(,15)
                                    Get ECVT
        15,4(,15)
         15,0(,15)
                                     Get address of IFAEDREG
     CALL (15),(...)
```

Both of these techniques require AMODE=31. If you use the second technique, before you issue the CALL, you must verify that the IFAEDDRG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

**In Java:** Use the methods in the IFAEDJReg class. Prior to invoking your application, the ifaedjreg.jar file must be available on the application's classpath and the registration native library must be available on the application's libpath. See "Registering and deregistering a product using Java" on page 34 for more information.

#### **Parameters**

#### **Type**

Supplied parameter:

Type: IntegerLength: Full word

Type identifies the type of register request. The field must contain a value that represents one or more of the possible types. You add the values to create the full word. Do not specify a type more than once. The possible types, and their meanings, are:

#### Ifaedreg\_Type\_Standard

The system is to register the product, check the enablement policy, and issue a successful return code unless the product is explicitly disabled in the policy. If the product is explicitly disabled, the system does not register the product and does issue return code 4. If you want the service to issue return code 4 (Ifaedreg\_Disabled) when the product is not found in the policy, specify Ifaedreg\_Type\_NotFoundDisabled.

#### Ifaedreg\_Type\_Required

The system is to register the product but not check the enablement policy. Use this option when registering solely for status queries. Because the system does not check the enablement policy, you cannot get return code 4 (Ifaedreg Disabled).

#### Ifaedreg\_Type\_NoReport

The system is to register the product but not report the product in the software registration report or the response to a DISPLAY command (unless the command specifies ALL). You might use this option when registering solely for status queries. Because the system does not check the enablement policy, you cannot get return code 4 (Ifaedreg\_Disabled).

#### Ifaedreg\_Type\_LicensedUnderProd

The system is to register the product/feature combination, but the product/feature combination cannot be ordered separately. The software registration report will differentiate this type of registration from others; a person looking at the report can easily tell that there is no need to check the ordering information for this product/featurename combination.

#### Ifaedreg Type DisabledMessage

The system, if it finds the product to be disabled, is to issue message IFA104I, described in  $\underline{z/OS}$   $\underline{MVS}$   $\underline{System}$   $\underline{MVS}$   $\underline{System}$   $\underline{MS}$   $\underline{System}$   $\underline{MS}$   $\underline{System}$   $\underline{System}$   $\underline{System}$  issues message IFA104I with no console ID specified, and with routing codes 10 (System/Error Maintenance) and 11 (Programmer Information).

#### Ifaedreg\_Type\_NotFoundDisabled

The system, if it does not find the product in the enablement policy, is to treat the product as disabled rather than enabled. That is, if the product is not found, the system does not register the product and does issue return code 4 (Ifaedreg\_Disabled). If you also specify Ifaedreg\_Type\_DisabledMessage, the system issues message IFA104I. For a description of this message, see z/OS MVS System Messages, Vol 8 (IEF-IGD).

#### .Prodowner

Supplied parameter:

Type: EBCDICLength: 16 bytes

Prodowner specifies the name of the product owner (vendor). IBM products, for example, always use IBM CORP or IBM\_CORP.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Prodname

Supplied parameter:

 Type: EBCDIC Length: 16 bytes

Prodname specifies the name of the product.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore ( ), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### .Featurename

Supplied parameter:

 Type: EBCDIC · Length: 16 bytes

Featurename specifies the name of the feature within the product or blanks if there is no feature name.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Prodvers

Supplied parameter:

 Type: EBCDIC · Length: 2 bytes

Prodvers specifies the product version identification or blanks if there is no version identification.

The characters can be upper-case or lower-case alphabetics and numerics. You can use embedded blanks.

The system performs all comparisons in upper case.

If the version identification is less than 2 bytes, left-justify it in the field and pad it on the right with EBCDIC blanks.

#### .Prodrel

Supplied parameter:

 Type: EBCDIC · Length: 2 bytes

Prodrel specifies the product release identification or blanks if there is no release identification.

The characters can be upper-case or lower-case alphabetics and numerics. You can use embedded blanks.

The system performs all comparisons in upper case.

If the release identification is less than 2 bytes, left-justify it in the field and pad it on the right with EBCDIC blanks.

#### ,Prodmod

Supplied parameter:

Type: EBCDICLength: 2 bytes

Prodmod specifies the product modification level or blanks if there is no modification level.

The characters can be upper-case or lower-case alphabetics and numerics. You can use embedded blanks.

The system performs all comparisons in upper case.

If the modification level is less than 2 bytes, left-justify it in the field and pad it on the right with EBCDIC blanks.

#### ,ProdID

Supplied parameter:

Type: EBCDICLength: 8 bytes

ProdID specifies the product identifier. IBM products, for example, use the product's program number.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 8 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Featureslen

Supplied parameter:

Type: IntegerRange: 0-1024Length: Full word

Featureslen specifies the length of the features parameter that follows.

#### ,Features

Supplied parameter:

Type: Character (EBCDIC recommended)

• Length: 1-1024 bytes

Features contains any information that you want the system to pass to the caller of the Query\_Status service. (Featureslen specifies the length of the information.)

If you do not need to pass information to callers of the Query\_Status service, code 0 in the Featureslen parameter. The system then ignores the contents of the Features parameter, but the service syntax requires that you supply a value.

If you do need to pass information to the callers of Query\_Status, using EBCDIC can simplify the parsing requirements for the caller, but you do need to provide a mapping of the information for the caller to use. An alternate approach is to set up self-defining features information (such as

feature1=value1, feature2=value2, . . . ). This approach has the advantage of simplicity, but does use more system (common) storage.

If the product you are registering is already registered, the features information you specify here will replace the features information provided on any previous call, but only for the length provided on the previous call. For example, if the previous call specified a Featureslen of 16, and this call specifies 32, the system uses only the first 16 bytes of features information from this call.

#### ,Prodtoken

Returned parameter:

· Type: Character · Length: 8 bytes

Prodtoken contains the token the system returns to identify this particular registration. Save this token to supply as input to the Deregister service.

#### ,Returncode

Returned parameter:

 Type: Integer · Length: Full word

Returncode contains the return code from the Register service.

#### **Return Codes**

When the Register service returns control to the caller, Returncode contains the return code. To obtain the equates for the return codes:

- If you are coding in assembler, include mapping macro IFAEDIDF. See z/OS MVS Data Areas in the z/OS Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- If you are coding in C, use include file IFAEDC. See "IFAEDC" on page 24.

The following table describes the return codes, shown in decimal.

Return Code (decimal)	Equate Symbol Meaning and Action
00	Equate Symbol: IFAEDREG_SUCCESS
	<b>Meaning</b> : The product/feature combination is enabled and is permitted to execute. Note that, unless you request option Ifaedreg_Type_NotFoundDisabled, you will get this return code when the system does not find a policy statement that matches the product.
	Action: Proceed with normal execution.
04	Equate Symbol: IFAEDREG_DISABLED
	<b>Meaning</b> : The product/feature combination is <b>not</b> enabled; it is explicitly disabled and is not permitted to execute. To get this return code when the system does not find a policy statement that matches the product, you must also request option Ifaedreg_Type_NotFoundDisabled.
	Action:
	Write the appropriate termination message to the terminal or log, unless the operator message issued because you requested Ifaedreg_Type_DisabledMessage provides enough information.
	2. Set a return code to indicate termination for 'not ordered or not permitted to run' condition.
	3. Terminate requestor's use of program.

Return Code (decimal)	Equate Symbol Meaning and Action
08	Equate Symbol: IFAEDREG_NOTAVAILABLE
	Meaning: Environmental error: The Register service is not available on this system.
	Action:
	If this version of the program must execute on a system that provides registration services:
	1. Write the appropriate termination message to the terminal or log.
	Set a return code to indicate termination because registration services are not available on this system.
	3. Terminate requestor's use of program.
	• If this version of the program does not need to execute on a system that provides registration services, take the actions appropriate for the product/feature when you cannot determine if it is enabled.
12	Equate Symbol: IFAEDREG_LIMITEXCEEDED
	<b>Meaning</b> : Environmental error: This request exceeds the limit of 10 register requests by an unauthorized caller in this address space.
	Action: Use the Deregister service to remove unneeded registrations.
16	Equate Symbol: IFAEDREG_NOTTASKMODE
	Meaning: User error: The service was not called in task mode.
	Action: Avoid calling in this environment.
20	Equate Symbol: IFAEDREG_XM
	<b>Meaning</b> : User error: The service was called in cross-memory mode but requires PASN=HASN=SASN.
	Action: Avoid calling in this environment.
24	Equate Symbol: IFAEDREG_BADFEATURESLEN
	Meaning: User error: The Featureslen parameter was not in the range 0-1024.
	Action: Correct the parameter.
28	Equate Symbol: IFAEDREG_NOSTORAGE
	<b>Meaning</b> : Environmental error: The system could not obtain the storage it needed to satisfy the request.
	Action: Contact the system programmer.
32	Equate Symbol: IFAEDREG_BADTYPE
	Meaning: User error: The type parameter did not specify a word formed from any combination of Ifaedreg_Type_Standard, Ifaedreg_Type_Required, Ifaedreg_Type_NoReport, Ifaedreg_Type_LicensedUnderProd, Ifaedreg_Type_DisabledMessage, and Ifaedreg_Type_NotFoundDisabled.
	Action: Correct the parameter.

Return Code (decimal)	Equate Symbol Meaning and Action
36	Equate Symbol: IFAEDREG_LOCKED
	Meaning: User error: The service was called while holding a system lock.
	Action: Avoid calling in this environment.
40	Equate Symbol: IFAEDREG_FRR
	<b>Meaning</b> : User error: The service was called while having a functional recovery routine (FRR) established.
	Action: Avoid calling in this environment.

# **Deregister Service (IFAEDDRG)**

Use the Deregister service (IFAEDDRG) to indicate that a registered product or product/feature combination is ending its processing. When a product registers with MVS, it indicates that it is running on the system. When it ends, the product issues the Deregister service to indicate that it has finished processing.

A product that issues the Register service receives a token that identifies the unique instance of the product. To deregister, the product calls the Deregister service and supplies the token. Note that the system automatically deregisters the product on termination of:

- The cross-memory resource owning task (TCB address in ASCBXTCB) that was active when the register request was done
- The address space that was the home address space when the register request was done.

If the product code is neither in supervisor state nor running under a system key, there are limitations on the use of Deregister:

- 1. You cannot deregister a product that was registered by a caller in supervisor state or running under a system key.
- 2. You can deregister only a product that was registered from your home address space.

## **Syntax**

CALL IFAEDDRG,	(Prodtoken ,Returncode)	

In C: the syntax is similar. You can use either of the following techniques to invoke the service:

```
    ifaeddrg (Type,...Returncode);
```

When you use this technique, you must link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB.

```
ifaeddrg_byaddr (Type,...Returncode);
```

This second technique requires AMODE=31, and, before you issue the CALL, you must verify that the IFAEDDRG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

**In Assembler:** Link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB unless you use either of the following techniques as an alternative to CALL IFAEDDRG:

```
    LOAD EP=IFAEDDRG
        Save the entry point address
        ...
        Put the saved entry point address into R15
        Issue CALL (15),...
        Cet CVT
        L 15,X'10' Get ECVT
        L 15,X'1C0'(,15)
        L 15,X'1C0'(,15)
        L 15,4(,15)
        L 15,4(,15)
        CALL (15),(...)
```

Both of these techniques require AMODE=31. If you use the second technique, before you issue the CALL, you must verify that the IFAEDDRG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

**In Java:** Use the methods in the IFAEDJReg class. Prior to invoking your application, the ifaedjreg.jar file must be available on the application's classpath and the registration native library must be available on the application's libpath. See "Registering and deregistering a product using Java" on page 34 for more information.

#### **Parameters**

#### **Prodtoken**

Supplied parameter:

Type: CharacterLength: 8 bytes

Prodtoken contains the token the system returned when the product issued the Register service.

#### .Returncode

Returned parameter:

Type: IntegerLength: Full word

Returncode contains the return code from the Deregister service.

#### **Return Codes**

When the Deregister service returns control to the caller, Returncode contains the return code. To obtain the equates for the return codes:

- If you are coding in assembler, include mapping macro IFAEDIDF. See *z/OS MVS Data Areas* in the <u>z/OS</u> Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- If you are coding in C, use the include file IFAEDC. See "IFAEDC" on page 24.

The following table describes the return codes, shown in decimal.

Return Code (decimal)	Equate Symbol Meaning and Action
00	Equate Symbol: IFAEDDRG_SUCCESS
	Meaning: The product/feature combination has been deregistered.
	Action: No action is required.

Return Code (decimal)	Equate Symbol Meaning and Action
08	Equate Symbol: IFAEDDRG_NOTAVAILABLE
	Meaning: Environmental error: The Deregister service is not available on this system.
	Action: Avoid calling the Deregister service on this system.
12	Equate Symbol: IFAEDDRG_NOTREGISTERED
	<b>Meaning</b> : User error: The product identified by the Prodtoken parameter was not registered.
	<b>Action</b> : In Prodtoken. provide a correct product token, as returned by the Register service.
16	Equate Symbol: IFAEDDRG_NOTTASKMODE
	Meaning: User error: The service was not called in task mode.
	Action: Avoid calling in this environment.
20	Equate Symbol: IFAEDDRG_XM
	<b>Meaning</b> : User error: The service was called in cross-memory mode but requires PASN=HASN=SASN.
	Action: Avoid calling in this environment.
24	Equate Symbol: IFAEDDRG_NOTAUTH
	<b>Meaning</b> : User error: A caller running in problem state tried to deregister a product that had been registered by an authorized caller (a program running in supervisor state or under a system key).
	Action: Avoid trying to deregister a product registered by an authorized caller.
36	Equate Symbol: IFAEDDRG_LOCKED
	Meaning: User error: The service was called while holding a system lock.
	Action: Avoid calling in this environment.
40	Equate Symbol: IFAEDDRG_FRR
	<b>Meaning</b> : User error: The service was called while having a functional recovery routine (FRR) established.
	Action: Avoid calling in this environment.

# **Query\_Status Service (IFAEDSTA)**

Use the Query\_Status service (IFAEDSTA) to request information about the registration or enablement status of a particular product. The system will indicate, through a combination of return code value and output area content:

- If the product is registered (running)
- · If the product is enabled

When it searches for the product you identify, the system does not use wildcard matching; there is no special treatment for a wildcard character (\* or ?). You can, however, indicate fields that are not important to your search, and the system will try to find the best match it can for the parameters that you provide. If two matches are equivalently good, and one of them contains a registration from the current home address space, then that match is used.

## **Syntax**

```
CALL IFAEDSTA

(Prodowner
,Prodname
,Featurename
,ProdID
,Outputinfo
,Featureslen
,Features
,Returncode)
```

In C: the syntax is similar. You can use either of the following techniques to invoke the service:

```
1. ifaedsta (Type,...Returncode);
```

When you use this technique, you must link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB.

```
2. ifaedsta_byaddr (Type,...Returncode);
```

This second technique requires AMODE=31, and, before you issue the CALL, you must verify that the IFAEDSTA service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

**In Assembler:** Link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB unless you use either of the following techniques as an alternative to CALL IFAEDSTA:

```
    LOAD EP=IFAEDSTA
        Save the entry point address
        ...
        Put the saved entry point address into R15
        Issue CALL (15),...

        C. L 15,X'10' Get CVT
        L 15,X'8C'(,15) Get ECVT
        L 15,X'1C0'(,15)
        L 15,4(,15)
        L 15,8(,15) Get address of IFAEDSTA
        CALL (15),(...)
```

Both of these techniques require AMODE=31. If you use the second technique, before you issue the CALL, you must verify that the IFAEDDRG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

Note: This service is not available in Java.

#### **Parameters**

#### ,Prodowner

Supplied parameter:

Type: EBCDICLength: 16 bytes

Specifies the name of the product owner you are searching for. IBM products always use IBM CORP or IBM\_CORP. If the product owner is not important to your search, set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Prodname

Supplied parameter:

• Type: EBCDIC · Length: 16 bytes

Specifies the name of the product you are searching for. If the product name is not important to your search, set the first character of the field to EBCDIC blank or hexadecimal zeroes.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore ( ), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Featurename

Supplied parameter:

 Type: EBCDIC · Length: 16 bytes

Specifies the name of the feature you are searching for. If the feature name is not important to your search, set the first character of the field to EBCDIC blank or hexadecimal zeroes.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore ( ), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### .ProdID

Supplied parameter:

 Type: EBCDIC · Length: 8 bytes

ProdID specifies the product identifier you are searching for. IBM products use the product's program number as the product identifier. If the product identifier is not important to your search, set the first character of the field to EBCDIC blank or hexadecimal zeroes.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), and period (.). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the name is less than 8 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Outputinfo

Returned parameter:

· Type: Character

· Length: 16

Specifies an output area, mapped by DSECT EDOI (in mapping macro IFAEDIDF) or structure EDOI (in C include file IFAEDC). If the return code is 0, this area contains information about the product you defined.

#### ,Featureslen

Supplied parameter:

Type: IntegerRange: 0-1024Length: Full word

Featureslen specifies the length of the Features parameter that follows.

#### ,Features

Returned parameter:

• Type: Character (EBCDIC recommended)

• Length: 1-1024 bytes

Features contains information provided by the caller of the Register service, and you need documentation from that caller about the length, format, and use of the information.

If the information is larger than the length you specify in Featureslen, the system returns only the information that fits in the area you provide. In that case, bit EdoiNotAllFeaturesReturned and field EdoiNeededFeaturesLen are set in the outputinfo area. You can use the length to call the Query\_Status service again with an expanded area.

If you are not expecting any information from the caller of the Register service, code 0 in the Featureslen parameter. This system will then ignore the Features parameter, but the service syntax requires that you supply a value.

#### ,Returncode

Returned parameter:

Type: IntegerLength: Full word

Returncode contains the return code from the Query\_Status service.

#### **Return Codes**

When the Query\_Status service returns control to the caller, Returncode contains the return code. To obtain the equates for the return codes:

- If you are coding in assembler, include mapping macro IFAEDIDF. See *z/OS MVS Data Areas* in the <u>z/OS Internet library</u> (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- If you are coding in C, use the include file IFAEDC. See "IFAEDC" on page 24.

The following table describes the return codes, shown in decimal.

Return Code (decimal)	Equate Symbol Meaning and Action
00	Equate Symbol: IFAEDSTA_SUCCESS
	<b>Meaning</b> : The product/feature combination is known to be registered or to be enabled or disabled.
	Action: Check the outputinfo area for further information.

Return Code (decimal)	Equate Symbol Meaning and Action
04	Equate Symbol: IFAEDSTA_NOTDEFINED
	<b>Meaning</b> : The product/feature combination is <b>not</b> known to be registered or to be enabled or disabled.
	Action: Check that the operands are correct.
08	Equate Symbol: IFAEDSTA_NOTAVAILABLE
	Meaning: Environmental error: The Status service is not available on this system.
	Action: Avoid calling the Status service on this system.
16	Equate Symbol: IFAEDSTA_NOTTASKMODE
	Meaning: User error: The service was not called in task mode.
	Action: Avoid calling in this environment.
20	Equate Symbol: IFAEDSTA_XM
	<b>Meaning</b> : User error: The service was called in cross-memory mode but requires HASN=PASN=SASN.
	Action: Avoid calling in this environment.
36	Equate Symbol: IFAEDSTA_LOCKED
	Meaning: User error: The service was called while holding a system lock.
	Action: Avoid calling in this environment.
40	Equate Symbol: IFAEDSTA_FRR
	<b>Meaning</b> : User error: The service was called while having a functional recovery routine (FRR) established.
	Action: Avoid calling in this environment.

# **List\_Status Service (IFAEDLIS)**

Use the List\_Status service (IFAEDLIS) to request information about the registration and enablement of one or more products. The system returns information about the products that match the product definition you supply.

You can also use the List\_Status service to determine what, according to the current policy, the enablement state would be for the product you define. You might use this service to determine whether or not registering the product would require a change to the enablement policy in IFAPRDxx.

The system returns the information in the answer area you specify on the List Status request:

- In assembler language, the answer area is mapped by DSECTs EDAAHDR and EDAAE in mapping macro IFAEDIDF.
- In C language, the answer area is mapped by structures EDAAHDR and EDAAE in include file IFAEDC.

EDAAHDR maps information about the request, including the number of entries returned. EDAAE maps each returned entry.

## **Syntax**

```
CALL IFAEDLIS,

(Type
,Prodowner
,Prodname
,Featurename
,ProdID
,Anslen
,Ansarea
,Returncode)
```

In C: the syntax is similar. You can use either of the following techniques to invoke the service:

```
1. ifaedlis (Type,...Returncode);
```

When you use this technique, you must link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB.

```
2. ifaedlis_byaddr (Type,...Returncode);
```

This second technique requires AMODE=31, and, before you issue the CALL, you must verify that the IFAEDLIS service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

**In Assembler:** Link edit your program with a linkage-assist routine (also called a stub) in SYS1.CSSLIB unless you use either of the following techniques as an alternative to CALL IFAEDLIS:

```
    LOAD EP=IFAEDLIS
        Save the entry point address
        ...
        Put the saved entry point address into R15
        Issue CALL (15),...

        C. L 15,X'10' Get CVT
        L 15,X'8C'(,15) Get ECVT
        L 15,X'1CO'(,15)
        L 15,4(,15)
        L 15,12(,15) Get address of IFAEDLIS
        CALL (15),(...)
```

Both of these techniques require AMODE=31. If you use the second technique, before you issue the CALL, you must verify that the IFAEDDRG service is available (in the CVT, both CVTOSEXT and CVTOS390 bits are set on).

Note: This service is not available in Java.

#### **Parameters**

#### **Type**

Supplied parameter:

Type: IntegerLength: Full word

Identifies the type of list request. The field must contain a value that represents a combination of one or more of the possible types. You add the values to create the full word. Do not specify a type more than once. The possible types, and their meanings, are:

#### Ifaedlis\_Type\_Registered

The system is to return data about any matching products that are registered. The number of entries returned appears in field EdaahNumR in the answer area. The address of the first entry appears in field EdaahFirstRAddr, DSECT EDAAE maps each entry. If you specify \* or? in the product definition, the system treats the character as a wildcard character.

#### **Ifaedlis Type State**

The system is to return data about the current policy state (enabled or disabled) of any matching products. The number of entries returned appears in field EdaahNumS. The address of the first entry appears in field EdaahFirstSAddr. DSECT EDAAE maps each entry. If you specify \* or? in the product definition, the system treats the character as a wildcard character.

#### Ifaedlis\_Type\_Status

The system is to return data about the enablement policy entry that would apply if the specified product registered. If there is no matching entry, the system sets Field EdaahStatusAddr in the answer area to 0; otherwise, it contains the address of the entry (mapped by DSECT EDAAE).

**Note:** For this request type, the system does not use wildcard matching when it searches the policy. If you specify \* or? in the product definition, the system does not treat the character as a wildcard character. To indicate that a field is not important, however, you can set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

#### Ifaedlis\_Type\_NoReport

Specify this request type to indicate the system is to return information about all matching entries, including those that registered with Ifaedreg\_Type\_NoReport.

#### ,Prodowner

Supplied parameter:

 Type: EBCDIC · Length: 16 bytes

Specifies the name of the product owner you are searching for. IBM products always use IBM CORP or IBM\_CORP.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), period (.), asterisk (\*), or question mark (?). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the request specifies Ifaedlis\_Type\_Registered or Ifaedlis\_Type\_State, the system treats \* and ? as wildcard characters; it uses wildcard matching. When you specify Ifaedlis Type Status, the system does not use wildcard matching, and \* or? receive no special treatment. If the product owner is not important to your search, set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### .Prodname

Supplied parameter:

• Type: EBCDIC · Length: 16 bytes

Specifies the name of the product you are searching for.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), period (.), asterisk (\*), or question mark (?). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the request specifies Ifaedlis\_Type\_Registered or Ifaedlis\_Type\_State, the system treats \* and? as wildcard characters; it uses wildcard matching. When you specify Ifaedlis\_Type\_Status, the

system does not use wildcard matching, and \* or ? receive no special treatment. If the product name is not important to your search, set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Featurename

Supplied parameter:

Type: EBCDICLength: 16 bytes

Specifies the name of the feature you are searching for.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), period (.), asterisk (\*), or question mark (?). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the request specifies **Ifaedlis\_Type\_Registered** or **Ifaedlis\_Type\_State**, the system treats \* and ? as wildcard characters; it uses wildcard matching. When you specify **Ifaedlis\_Type\_Status**, the system does not use wildcard matching, and \* or ? receive no special treatment. If the feature name is not important to your search, set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

If the name is less than 16 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,ProdID

Supplied parameter:

Type: EBCDICLength: 8 bytes

ProdID specifies the product identifier you are searching for. IBM products, for example, use the product's program number as the product identifier.

The characters can be upper-case or lower-case alphabetics, numerics, national (@, #, \$), underscore (\_), slash (/), hyphen (-), period (.), asterisk (\*), or question mark (?). You can use embedded blanks.

The system translates underscores to blanks for comparison and display, and it performs all comparisons in upper case.

If the request specifies **Ifaedlis\_Type\_Registered** or **Ifaedlis\_Type\_State**, the system treats \* and ? as wildcard characters; it uses wildcard matching. When you specify **Ifaedlis\_Type\_Status**, the system does not use wildcard matching, and \* or ? receive no special treatment. If the product identifier is not important to your search, set the first character of the field to an EBCDIC blank or hexadecimal zeroes.

If the name is less than 8 bytes, left-justify the name in the field and pad it on the right with EBCDIC blanks.

#### ,Anslen

Supplied parameter:

· Type: Integer

Minimum Value: 32Length: Full word

Specifies the length of the answer area parameter that follows. Specify a value of at least 32, the length of the answer area header (DSECT EDAAHDR in macro IFAEDIDF) that the system returns. Add 72 for each entry that you expect the system to return.

#### .Ansarea

Returned parameter:

- · Type: Character
- · Length: Specified on Anslen parameter

The answer area where the system is to place information about the request and the entries that match the product definition. The contents depend on the type of the request:

- If you specified Ifaedlis Type Registered, the answer area consists of a header area and a queue of 0 or more entries. The number of entries is in EDAAHNUMR, and EDAAHFIRSTRADDR points to the first entry. If you did not specify Ifaedlis Type Registered, both fields are 0.
- If you specified Ifaedlis\_Type\_State, the answer area consists of a header area and a queue of 0 or more entries. The number of entries is in EDAAHNUMS, and EDAAHFIRSTSADDR points to the first entry. If you did not specify **Ifaedlis\_Type\_State**, both fields are 0.
- If you specified **Ifaedlis Type Status**, the answer area consists of a header area and a single entry. EDAAHSTATUSADDR points to an entry that defines the policy that would be used to determine whether the product is enabled or disabled. The field is 0 if there is no matching policy entry, and it is always 0 when you did not specify Ifaedlis\_Type\_Status.

If the returned information exceeds the length you specify in Anslen, the system returns only the information that fits in the area you provided. EDAAHTLEN indicates the total length of the information available to be returned. If the length is longer than the length you specified in Anslen, increase Anslen and issue the request again.

#### .Returncode

Returned parameter:

· Type: Integer · Length: Full word

Returncode contains the return code from the List Status service.

#### **Return Codes**

When the List\_Status service returns control to the caller, Returncode contains the return code. To obtain the equates for the return codes:

- If you are coding in assembler, include mapping macro IFAEDIDF. See z/OS MVS Data Areas in the z/OS Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- If you are coding in C, use the include file IFAEDC. See "IFAEDC" on page 24.

The following table describes the return codes, shown in decimal.

Return Code (decimal)	Equate Symbol Meaning and Action
00	Equate Symbol: IFAEDLIS_SUCCESS
	Meaning: The system returned all the requested data.
	Action: No action is required.
04	Equate Symbol: IFAEDLIS_NOTALLDATARETURNED
	<b>Meaning</b> : The answer area was too small. Some of the requested data was not returned.
	Action: Provide a larger answer area and call the service again.

Return Code (decimal)	Equate Symbol Meaning and Action
08	Equate Symbol: IFAEDLIS_NOTAVAILABLE
	Meaning: Environmental error: The IFAEDLIS service is not available on this system.
	Action: Avoid calling the IFAEDLIS service on this system.
12	Equate Symbol: IFAEDLIS_ANSAREATOOSMALL
	<b>Meaning</b> : User error: The answer area length you provided was less than the minimum needed, 32.
	Action: Provide a larger answer area.
16	Equate Symbol: IFAEDSTA_NOTTASKMODE
	Meaning: User error: The service was not called in task mode.
	Action: Avoid calling in this environment.
20	Equate Symbol: IFAEDLIS_XM
	<b>Meaning</b> : User error: The service was called in cross-memory mode but requires PASN=HASN=SASN.
	Action: Avoid calling in this environment.
32	Equate Symbol: IFAEDLIS_BADTYPE
	<b>Meaning</b> : User error: The type parameter did not specify a word formed from any combination of Ifaedlis_Type_Registered, Ifaedlis_Type_State, Ifaedlis_Type_Status, and Ifaedlis_Type_Noreport.
	Action: Correct the parameter.
36	Equate Symbol: IFAEDLIS_LOCKED
	Meaning: User error: The service was called while holding a system lock.
	Action: Avoid calling in this environment.
40	Equate Symbol: IFAEDLIS_FRR
	<b>Meaning</b> : User error: The service was called while having a functional recovery routine (FRR) established.
	Action: Avoid calling in this environment.

# **IFAEDC**

For the C programmer, include file IFAEDC provides equates for return codes and data constants, such as Register service request types. To use IFAEDC, copy the file from SYS1.SAMPLIB to the appropriate local C library. The contents of the file are displayed in Figure 2 on page 25.

```
#ifndef __IFAED
#define __IFAED
/**********************************
   Name: IFAEDC
   Descriptive Name: SMF Product enable/disable services C declares *
 /*01* PROPRIETARY STATEMENT=
 /*
 /*
                                                                      */
 /* LICENSED MATERIALS - PROPERTY OF IBM
 /* THIS MACRO IS "RESTRICTED MATERIALS OF IBM"
/* 5645-001 (C) COPYRIGHT IBM CORP. 1996
 /* SEE COPYRIGHT INSTRUCTIONS
 /* STATUS= HBB6601
 .
/***END_OF_PROPRIETARY_STATEMENT*************************/
 /*01* EXTERNAL CLASSIFICATION: GUPI
 /*01* END OF EXTERNAL CLASSIFICATION:
 /*
   Function:
/*
     IFAEDC defines types, related constants, and function prototypes for the use of SMF Product enable/disable services from the C language
   Usage:
      #include <IFAEDC.H>

    This member should be copied from SAMPLIB to the
appropriate local C library.

    2. The Product enable/disable services do not use a null
        character to terminate strings. The services expect the character operands to be a fixed-length type.
        Use memcpy to move into and from these fields.
    Change Activity:
*$L0=PRDEDSMF, HBB6601, 950601, PDXB: SMF Product enable/disable
```

Figure 2. IFAEDC from SYS1.SAMPLIB

```
/****************************
         Type Definitions for User Specified Parameters
 /* Type for TYPE operand of IFAEDREG
typedef int IfaedType;
                                                               */
/* Type for Product Owner
typedef char IfaedProdOwner??(16??);
/* Type for Product Name
typedef char IfaedProdName??(16??);
/* Type for Feature Name
typedef char IfaedFeatureName??(16??);
/* Type for Product Version
                                                               */
typedef char IfaedProdVers??(2??);
/* Type for Product Release
typedef char IfaedProdRel??(2??);
/* Type for Product Modification level
typedef char IfaedProdMod??(2??);
/* Type for Product ID
typedef char IfaedProdID??(8??);
/* Type for Product Token
```

```
typedef char IfaedProdToken??(8??);
/* Type for Features Length
typedef int IfaedFeaturesLen;
/* Type for Return Code
typedef int IfaedReturnCode;
/************************
          Type Definitions for User Specified Parameters
 /* Type for user supplied EDOI
typedef struct ??<
  struct ??<
int EdoiRegistered : 1;
                                       /* The product is registered
/* The product is not known to
                                                                              */
    int EdoiStatusNotDefined : 1;
                             be enabled or disabled
    int EdoiStatusEnabled : 1;    /* The product is enabled int EdoiNotAllFeaturesReturned : 1;    /* The featureslen
                            area was too small to hold the features
                            provided at registration time. Field
                            EdoiNeededFeaturesLen contains the size
                            provided at registration time.
    int Rsvd0 : 4;
                                         /* Reserved
         ??> EdoiFlags ;
  char Rsvd1??(3??);
                                  /* Reserved
                                                                              */
  int EdoiNeededFeaturesLen; /* The featureslen size provided at
                                      registration time
  struct ??<
    IfaedProdVers EdoiProdVers;
                                          /* The version information
                          provided at registration time
    IfaedProdRel EdoiProdRel;
                                        /* The release information
                          provided at registration time
ProdMod; /* The mod level information
    IfaedProdMod EdoiProdMod;
                          provided at registration time
                                                                              */
          ??> EdoiProdVersRelMod;
                                 /* Reserved
  char Rsvd2??(2??);
??> EDOI;
/* Type for user supplied EDAAHDR
typedef struct ??<
  int EdaahNumR;
                                         /* Number of EDAAE entries which
                      follow indicating registered entries. The first one is pointed to by EdaahFirstRAddr. \rm \star /
  int EdaahNumS;
                                          /* Number of EDAAE entries which
                      follow indicating state entries. The first one
                      is pointed to by EdaahFirstSAddr.
                                          /* Total length of answer area
  int EdaahTLen;
                      needed to contain all the requested information.
                      This includes the area for the records
                      that were returned on this call
  void *EdaahFirstRAddr;
                                         /* Address of first registered
                      entry EDAAE
                                                                              */
  void *EdaahFirstSAddr;
                                          /* Address of first state entry
                      EDAAE
  void *EdaahStatusAddr;
                                          /* Address of the EDAAE that
                      represents the policy entry that would be used to determine if the input product was enabled. 0 if
                      no such policy entry exists.
/* Reserved
  char Rsvd1??(8??);
                                                                              */
??> EDAAHDR;
/* Type for user supplied EDAAE
typedef struct ??<
  void *EdaaeNextAddr;
                                         /* Address of next EDAAE. EdaahNumR
                      (for the registered queue) or EdaahNumS (for the state queue) must be used to determine how far along this chain to go. Not relevant for
                      EdaahStatusAddr.
  struct ??<
                       EdaaeProdOwner; /* Product owner
EdaaeProdName; /* Product name
    IfaedProdOwner
    IfaedProdName
    IfaedFeatureName EdaaeFeatureName; /* Feature name IfaedProdVers EdaaeProdVers; /* Product version
                                        /* Product release
    IfaedProdRel
                       EdaaeProdRel;
                                         /* Product mod level
    IfaedProdMod
                       EdaaeProdMod;
    IfaedProdID
                       EdaaeProdID;
                                         /* Product ID
         ??> EdaaeInfo;
  struct ??<
```

```
int EdaaeStatusNotDefined : 1; /* This will never be on for
                          entries on the state queue. If on, indicates that
                          the state information does not have an entry that
     matches this product. int EdaaeStatusEnabled : 1; /* If on, indicates that the
                          product is considered to be enabled
     int EdaaeNoReport : 1;
                                            /* This will never be on for
                          entries on the state queue. If on, indicates that the product registered with
     Ifaedreg_Type_NoReport.
int EdaaeLicensedUnderProd : 1; /* This will never be on for
                          entries on the state queue. If on, indicates that
                          the product registered with
                          {\tt If aedreg\_Type\_\bar{L}icensed Under Prod.}
     int Rsvd0 : 4;
                                               /* Reserved
                                                                                          */
           ??> EdaaeFlags ;
   char Rsvd1??(1??);
                                      /* Reserved
                                                                                          */
                                      /* Number of concurrent instances of
   int EdaaeNumInstances;
                                           this registration.
                                                                                          */
??> EDAAE;
/***************************
       Fixed Service Parameter and Return Code Defines
 /* Product enable/disable Register Constants
#define Ifaedreg_Type_Standard
#define Ifaedreg_Type_Required 2
#define Ifaedreg_Type_NoReport 4
#define Ifaedreg_Type_LicensedUnderProd 8
#define Ifaedreg_Type_DisabledMessage 16
#define Ifaedreg_Type_NoReport 32
#define Ifaedreg_Type_NotFoundDisabled 32
#define IFAEDREG_TYPE_STANDARD 0
#define IFAEDREG_TYPE_REQUIRED 2
#define IFAEDREG_TYPE_NOREPORT 4
#define IFAEDREG_TYPE_LICENSEDUNDERPROD 8
#define IFAEDREG_TYPE_DISABLEDMESSAGE 16
#define IFAEDREG_TYPE_NOTFOUNDDISABLED 32
/* Product enable/disable Register Return codes
#define Ifaedreg_Success
#define Ifaedreg_Disabled
                                                   4
#define Ifaedreg_NotAvailable
#define Ifaedreg_LimitExceeded
#define Ifaedreg_NotTaskMode
                                                  12
                                                  16
#define Ifaedreg_XM
                                                  20
#define Ifaedreg_BadFeaturesLen
                                                  24
#define Ifaedreg_NoStorage
                                                  28
#define Ifaedreg_BadType
#define Ifaedreg_Locked
                                                  32
#define Ifaedreg_FRR
#define IFAEDREG_SUCCESS
                                                  40
#define IFAEDREG DISABLED
#define IFAEDREG_NOTAVAILABLE #define IFAEDREG_LIMITEXCEEDED
                                                   8
                                                  12
#define IFAEDREG_NOTTASKMODE
                                                  16
#define IFAEDREG_XM
                                                  20
#define IFAEDREG_BADFEATURESLEN
                                                  24
#define IFAEDREG_NOSTORAGE
                                                  28
#define IFAEDREG_BADTYPE
                                                  32
#define IFAEDREG_LOCKED
#define IFAEDREG_FRR
 /* Product enable/disable Deregister Return codes
#define Ifaeddrg_Success
#define Ifaeddrg_NotAvailable
#define Ifaeddrg_NotRegistered
#define Ifaeddrg_NotTaskMode
                                                  12
                                                  16
#define Ifaeddrg_XM
#define Ifaeddrg_NotAuth
#define Ifaeddrg_Locked
                                                  36
#define Ifaeddrg_FRR
#define IFAEDDRG_SUCCESS
                                                  40
                                                   0
#define IFAEDDRG_NOTAVAILABLE
#define IFAEDDRG_NOTREGISTERED #define IFAEDDRG_NOTTASKMODE
                                                  12
                                                  16
#define IFAEDDRG_XM
                                                  20
#define IFAEDDRG NOTAUTH
                                                  24
```

```
#define IFAEDDRG_LOCKED
#define IFAEDDRG_FRR
/* Product enable/disable Status Return codes
                                                                                                            */
#define Ifaedsta_Success
#define Ifaedsta_NotDefined
                                                             4
#define Ifaedsta_NotAvailable
#define Ifaedsta_NotTaskMode
#define Ifaedsta_XM
                                                           16
#define Ifaedsta_Locked
                                                           36
#define Ifaedsta_FRR
                                                           40
#define IFAEDSTA SUCCESS
#define IFAEDSTA_NOTDEFINED #define IFAEDSTA_NOTAVAILABLE
                                                            8
#define IFAEDSTA_NOTTASKMODE
                                                           16
#define IFAEDSTA_XM
                                                           20
#define IFAEDSTA_LOCKED
                                                           36
#define IFAEDSTA_FRR
                                                           40
/* Product enable/disable List Constants
                                                                                                            */
#define Ifaedlis_Type_Registered #define Ifaedlis_Type_State
#define Ifaedlis_Type_Status
#define Ifaedlis_Type_NoReport
#define IFAEDLIS_TYPE_REGISTERED
#define IFAEDLIS_TYPE_STATE
#define IFAEDLIS_TYPE_STATE
#define IFAEDLIS_TYPE_NOREPORT
      Product enable/disable List Return codes
                                                                                                            */
#define Ifaedlis_Success
#define Ifaedlis_NotAllDataReturned
#define Ifaedlis_NotAvailable
#define Ifaedlis_AnsAreaTooSmall
                                                           12
#define Ifaedlis_NotTaskMode
                                                           16
#define Ifaedlis_XM
                                                           20
#define Ifaedlis_BadType
                                                           32
#define Ifaedlis_Locked
#define Ifaedlis_FRR
#define IFAEDLIS_SUCCESS
                                                           40
                                                             0
#define IFAEDLIS_NOTALLDATARETURNED #define IFAEDLIS_NOTAVAILABLE
                                                             4
                                                             8
#define IFAEDLIS_ANSAREATOOSMALL #define IFAEDLIS_NOTTASKMODE
                                                           16
#define IFAEDLIS_XM
                                                           20
#define IFAEDLIS_BADTYPE
                                                           32
#define IFAEDLIS LOCKED
                                                           36
#define IFAEDLIS_FRR
/******************************
                 Function Prototypes for Service Routines
 #ifdef __cplusplus
    extern "OS" ??<</pre>
#else
   #pragma linkage(ifaedreg_calltype,OS)
#pragma linkage(ifaeddrg_calltype,OS)
   #pragma linkage(ifaedsta_calltype,OS)
   #pragma linkage(ifaedlis_calltype,OS)
#endif
typedef void ifaedreg_calltype(
    IfaedType ___TYPE, /* Input - request type
IfaedProdOwner __PRODOWNER, /* Input - product owner
IfaedProdName __PRODNAME, /* Input - product name
IfaedFeatureName __FEATURENAME, /* Input - feature name
IfaedProdVers __PRODNERS, /* Input - product version
IfaedProdRel __PRODREL, /* Input - product release
IfaedProdMod __PRODMOD, /* Input - product modification
IfaedProdID __PRODID, /* Input - product ID
IfaedFeaturesLen FFATURESLEN. /* Input - length of features
    IfaedProdID __PRODID, /* Input - product ID

IfaedFeaturesLen _FEATURESLEN, /* Input - length of features

void *_FEATURES, /* Input - features area

IfaedProdToken *_PRODTOKEN, /* Output - product token

IfaedReturnCode *_RC); /* Output - return code
typedef void_ifaeddrg_calltype(
    IfaedProdToken __PRODTOKEN, /* Input - product token
IfaedReturnCode *_RC); /* Output - return code
```

```
typedef void ifaedsta_calltype(
   IfaedProdOwner __PRODOWNER, /* Input - product owner IfaedProdName __PRODNAME, /* Input - product name IfaedFeatureName __PEATURENAME, /* Input - feature name __PRODID, /* Input - product ID
                                                                                       */
                                                                                       */
                                                                                       */
                         *__EDOI,
                                            /* Output - output information
/* Input - length of features
   EDOI
   IfaedFeaturesLen __FEATURESLEN,
                         *_FEATURES, /* Output - features area
   void
   IfaedReturnCode *__RC);
                                          /* Output - return code
typedef void ifaedlis_calltype(
                         __TYPE, /* Input - request type
__PRODOWNER, /* Input - product owner
__PRODNAME, /* Input - product name
__FEATURENAME, /* Input - feature name
   IfaedType
   IfaedProdOwner
                         PRODUMER, //
   IfaedProdName
   IfaedFeatureName
                                         /* Input - product ID

/* Input - length of answer area

/* Output - answer area

/* Output - return code
                          __PRODID,
   IfaedProdID
                          __ANSLEN,
   int
                         *__ANSAREA,
   void
   IfaedReturnCode *__RC);
extern ifaedreg_calltype ifaedreg;
extern ifaeddrg_calltype ifaeddrg;
extern ifaedsta_calltype ifaedsta;
extern ifaedlis_calltype ifaedlis;
#ifdef __cplusplus
   ??>
#endif
struct IFAED PREDVT ??<
   ifaedreg_calltype* ifaed_regaddr;
   ifaeddrg_calltype* ifaed_drgaddr;
   ifaedsta_calltype* ifaed_staaddr;
ifaedlis_calltype* ifaed_lisaddr;
??>;
struct IFAED_PRED ??<
   unsigned char ifaed_pred_filler1 ??(4??);
struct IFAED_PREDVT * ifaed_predvt;
??>:
#ifndef
            _cplusplus
#define ifaedreg_byaddr(Type, Owner, Name, Fname, Vers, Rel, Mod,
                      Id, Flen, Fptr , Tptr, Rcptr)
 struct IFAED_PSA* ifaed_pagezero = 0;
   ifaed_pagezero->ifaed_cvt->ifaed_cvtecvt->ifaed_ecvtpred->
              ifaed_predvt->ifaed_regaddr
              (Type, Owner, Name, Fname, Vers, Rel, Mod, Id, Flen, Fptr,
               Tptr,Rcptr);
??>;
#define ifaeddrg byaddr(Token, Rcptr)
??<
 struct IFAED_PSA* ifaed_pagezero = 0;
   ifaed_pagezero->ifaed_cvt->ifaed_cvtecvt->ifaed_ecvtpred->
              ifaed_predvt->ifaed_drgaddr
              (Token, Rcptr);
??>
#define ifaedsta_byaddr(Owner, Name, Fname, Id, Eptr, Flen,
                              Fptr, Rcptr)
 struct IFAED_PSA* ifaed_pagezero = 0;
   ifaed_pagezero->ifaed_cvt->ifaed_cvtecvt->ifaed_ecvtpred->
              ifaed_predvt->ifaed_staaddr
              (Owner, Name, Fname, Id, Eptr, Flen, Fptr, Rcptr);
#define ifaedlis_byaddr(Type, Owner, Name, Fname, Id, Alen,
                              Aptr, Rcptr)
struct IFAED_PSA* ifaed_pagezero = 0;
   ifaed_pagezero->ifaed_cvt->ifaed_cvtecvt->ifaed_ecvtpred->
    ifaed_predvt->ifaed_lisaddr
              (Type,Owner,Name,Fname,Id,Alen,Aptr,Rcptr);
??>;
#endif
struct IFAED_ECVT ??<
   unsigned char ifaed_ecvt_filler1 ??(448??);
```

```
unsigned char ifaed_ecvt_filler2 ??(24??);
unsigned char ifaed_ecvtpseq ??( 4??); /* product sequence number */
IfaedProdOwner ifaed_ecvtpown; /* product owner */
IfaedProdName ifaed_ecvtpnam; /* product name
IfaedProdVers ifaed ecvtpver:
    IfaedProdVers ifaed_ecvtpver;
IfaedProdRel ifaed_ecvtprel;
IfaedProdMod ifaed_ecvtpmod;
                                                             /* product release
                                                             /* product mod level
    unsigned char ifaed_ecvt_filler3 ??(26??);
struct IFAED_CVT ??<
    unsigned char ifaed_cvt_filler1 ??(116??);
  struct ??<
     */
     int ifaed_cvtosext : 1; /* If on, CVTOSLVL fields are valid
     int ifaed_cvtdcb_rsvd2 : 3;  /* Not needed
            ??> ifaed_cvtdcb;
    unsigned char ifaed_cvt_filler2 ??(23??);
struct IFAED_ECVT * ifaed_cvtecvt;
unsigned char ifaed_cvt_filler3 ??(1120??);
    unsigned char ifaed_cvtoslv0;
  struct ??<
     int ifaed_cvtoslv1_rsvd1 : 6;  /* Not needed
int ifaed_cvtprded : 1;  /* If on, indicates that the
    product enable/disable services are available
                                                                                                     */
     int ifaed_cvtoslv1_rsvd2 : 1;  /* Not needed
           ??> ifaed_cvtoslv1;
    unsigned char ifaed_cvt_filler4 ??(14??);
??>;
struct IFAED_PSA ??<
    char ifaed_psa_filler??(16??);
struct IFAED_CVT* ifaed_cvt;
/* End of SMF Product Enable/Disable Services Header
#endif
```

## **Chapter 3. Examples**

The following examples show possible uses of the registration services. The examples are written in assembler and Java.

Detailed information about the services appears in Chapter 2, "Coding Registration Services," on page 5.

# Registering a product, checking the status of another product, then deregistering the first product using assembler

Figure 3 on page 31 shows code that registers a product, checks the status of another product, then deregisters the first product and uses the MF parameter of the CALL macro to generate reentrant code.

```
PUBEX1
       CSECT
PUBEX1
       AMODE 31
PUBEX1
       RMODE ANY
            14,12,12(13)
       STM
            12,15
       USING PUBEX1,12
       GETMAIN RU, LV=DYNAREALEN
            14,1
       ST
            13,4(,14)
            14,8(,13)
       LR
            13,14
       USING DYNAREA, 13
DYNAREA DSECT
SAVEAREA DS
PUBEX1
      CSECT
EXAMPLE1 DS
            0H
**************************
* Register a product
**************************
       CALL IFAEDREG, (RTYPE, ROWNER, RNAME,
            RFEATURENAME, RVERSION, RRELEASE
            RMOD, RID, RFEATURESLEN, RFEATURES, PRODTOKEN, RETCODE),
            MF=(E,PL)
* Place code to check return code here
***************************
* Check the status of another product
*************************
       CALL IFAEDSTA, (SOWNER, SNAME, SFEATURENAME,
            SID, SOUTPUTINFO,
            SFEATURESLEN, SFEATURES, RETCODE), MF=(E, PL)
* Place code to check return code here
```

Figure 3. Example 1 — Using IFAEDREG, IFAEDSTA and IFAEDDRG

```
***************************
* Deregister the product
        CALL IFAEDDRG, (PRODTOKEN, RETCODE), MF=(E, PL)
* Place code to check return code here
              ENDEXAMPLE
* Values for REGISTER
               AL4(IFAEDREG_TYPE_STANDARD)
RTYPE
         DC
               CL16'VENDOR X
ROWNER
         DC
RNAME DC CL16'Y_PROD1'
RFEATURENAME DC CL16'
              CL8'1234-567'
         DC
RVERSION DC
              CL2'01'
```

```
RRELEASE DC CL2'01'
RMOD DC CL2'00'
RFEATURESLEN DC AL4(L'RFEATURES)
RFEATURES DC C'FEATURE1, FEATURE20PT=2'
* Values for STATUS
SOWNER DC CL16'VENDOR Y'
SNAME DC CL16'Y_PROD2'
SFEATURENAME DC CL16''
SFEATURENAME DC CL16' SID DC CL8'8888-888' SFEATURESLEN DC AL4(L'SFEATURES)
            IFAEDIDF ,
                                          Return code information
DYNAREA DSECT
RETCODE DS F
PRODTOKEN DS CL8
SOUTPUTINFO DS CL16
SFEATURES DS CL1024
PL CALL ,(,,,,,,,),MF=L Call parm list for 12 parameters
DYNAREALEN EQU *-DYNAREA
PUBEX1 CSECT
ENDEXAMPLE DS 0H
           LR 1,13
                                           Dynamic area address
                    1,13 Dynamic area address
13,4(,13) Previous save area address
            FREEMAIN RU, A=(1), LV=DYNAREALEN
            LM 14,12,12(13)
SLR 15,15
            BR
                     14
                     PUBEX1
```

# Obtaining a list of information about products that are registered using assembler

Figure 4 on page 33 shows code that obtains a list of information about products that are registered, including information about their enablement state and uses the MF parameter of the CALL macro to generate reentrant code..

```
PUBEX2
           CSECT
PUBEX2
           AMODE 31
RMODE ANY
PUBEX2
                  14,12,12(13)
12,15
           STM
           LR
           USING PUBEX2,12
           GETMAIN RU, LV=DYNAREALEN
           LR
                  14,1
                  13,4(,14)
14,8(,13)
13,14
           ST
           LR
           USING DYNAREA, 13
DYNAREA
           DSECT
SAVEAREA DS
                  CL72
PUBEX2
           CSECT
EXAMPLE3 DS
\star Following is an assembler example of getting registration and
* state information about all of the products
           L 2,=AL4(INITEDAA) Initial answer area size ST 2,SIZEEDAA Save it GETMAIN RU,LV=(2) Allocate the answer area
                  1,EDAA@
           ST
                                       Save address of answer area
LAB1
           DS
                  0Η
                  4,EDAA@
                                      Address of answer area
                  IFAEDLIS, (REQ_INFO,
ALL_OWNER, ALL_NAME, ALL_FN, ALL_ID,
SIZEEDAA, (4), LRETCODE), MF=(E, PL)
LRETCODE(4),=AL4(IFAEDLIS_NOTALLDATARETURNED) Warning?
           CALL
           CLC
                                       No, request successful or error
           BNE
                  LAB2
                                       Yes, not enough room
           LR
                                       Save current size
                  2,EDAAHTLEN-EDAAHDR(4) Get required size
           FREEMAIN RU, A=(4), LV=(3) Release old area
                  2, SIZEEDÀA
                                       Save it
           GETMAIN RU, LV=(2)
                                       Allocate new area
                  1,EDAA@
           ST
                                       Save address of answer area
           В
                  LAB1
                                       Retry List operation
LAB2
           DS
           CLC
                  LRETCODE(4),=AL4(IFAEDLIS_SUCCESS) Success?
           BNE
                  LAB3
                                       No, error
```

Figure 4. Example 2 — Using IFAEDLIS

```
*************************
* Process information in answer area when RC=0
*************************
                            EDAAHDR DSECT
        USING EDAAHDR,4
* Process registered entry information
                             Find how many EDAAE registered entries
              5,EDAAHNUMR
        LTR
                             Are there any entries
             LAB4
                             No, check state entries
             6,EDAAHFIRSTRADDR Get first entry
EDAAE,6 EDAAE DSECT
        USING EDAAE,6
LAB5
        DS
             0H
                             EDAAE loop
* Put code to process information contained in EDAAE here
              6, EDAAENEXTADDR Get next EDAAE
        BCT
              5,LAB5
                             Continue while there are more
        DROP 6
* Process state entry information
        DS
LAB4
                             EDAAE loop
              5, EDAAHNUMS
                             Find how many EDAAE state entries
        L
        LTR
              5,5
                             Are there any entries
             LAB10
                             No, done
        ΒZ
              6, EDAAHFIRSTSADDR Get first entry
        USING EDAAE,6
                             EDAAE DSECT
LAB6
                             EDAAE loop
* Put code to process information contained in EDAAE here
```

```
6, EDAAENEXTADDR Get next EDAAE
         DROP
         BCT
               5,LAB6
                                Continue while there are more
         В
               LAB4
                                Skip error case
LAB3
         DS
               ΘН
                               Error return
   Process error case
LAB10
         DS
                               Common path
               2,SIZEEDAA
         L
                                Get size of area
               4,EDAA@
                                Get address of area
         FREEMAIN RU, A=(4), LV=(2) Release area
               ENDEXAMPLE
```

```
INITEDAA EQU
                               Initial size of answer area
DYNAREA DSECT
         DS
EDAA@
                               Address of answer area
SIZEEDAA DS
                               Size of answer area
TEMPSIZE DS
                                Temporary
LRETCODE DS
                               Return code
               ,(,,,,,),MF=L Call parameter list for 8 parameters
РΙ
         CALL
PUBEX2
         CSECT
REQ_INFO DC
               A(IFAEDLIS_TYPE_REGISTERED+IFAEDLIS_TYPE_STATE)
ALL_OWNER DC
               CL16'*'
                               Match all product owners
               CL16'*'
ALL_NAME DC
                               Match all product names
                           Match all reacut
Match all product IDs
ALL_FN
          DC
               CL16'*'
                               Match all feature names
               CL8'*'
ALL_ID
          DC
         IFAEDIDF ,
         DSECT
DYNAREA
DYNAREALEN EQU *-DYNAREA
PUBEX2
        CSEČT
ENDEXAMPLE DS OH
         LR
               1,13
                               Dynamic area address
               13,4(,13)
                               Previous save area address
         FREEMAIN RU, A=(1), LV=DYNAREALEN
         I M
               14,12,12(13)
         SLR
               15,15
               14
         BR
         END
               PUBEX2
```

## Registering and deregistering a product using Java

The IFAEDJReg class provides access to the z/OS product registration and deregistration services through Java. The IFAEDJReg class allows Java programs to use the product registration services by wrapping the system IFAEDREG (register) and IFAEDDRG (deregister) callable services.

A product is identified through various parameters such as product name, product owner, and feature name. These fields are set in the IFAEDJReg object and then the register method can be called.

After a successful registration, a registration token (also referred to as a product token) is returned by the system. This token is used by the deregister method to deregister the product.

The registration or deregistration return code provided by the system is returned by the methods.

The product registration Java support requires that the following Java level or higher be installed:

• IBM SDK for z/OS Java 2 Technology Edition, Version 1.4 PTF UQ93743, product number 5655-I56

To run an application that uses the product registration Java classes, you must add the jar file containing the product registration classes to your path, and add the native library to your libpath.

Note in the examples below, the default installation paths are shown. If you have changed the default by adding a path prefix, modify the commands accordingly.

Add the /usr/include/java\_classes/ifaedjreg.jar file to your application classpath. In the z/OS UNIX System Services shell, this can be done with the command:

```
export CLASSPATH=/usr/include/java_classes/ifaedjreg.jar:$CLASSPATH
```

Add the path to the native library /usr/lib/java\_runtime/libifaedjreg.so to your library path (LIBPATH). In the z/OS Unix System Services shell, this can be done with the command:

```
export LIBPATH=/usr/lib/java_runtime:$LIBPATH
```

The documentation for the using the methods in the Java classes is contained in the Javadoc for the IFAEDJReg class. The Java doc is installed to /usr/include/java\_classes/ifadjregDoc.jar by default.

All of the Javadoc files for product registration have been included in the jar. To view the Javadoc, it is necessary to download the jar file in binary to your workstation, unjar the file to make the individual files accessible, and then use your browser to open the index.html file.

#### Example: Registering a product using Java

The product name "TESTPROD" with product owner "IBM" and product number 9999-999 is to be registered. If the product is disabled, the program will exit. Registration is done using the system service IFAEDREG.

```
IFAEDJReg reg = new IFAEDJReg();
reg.setRegisterType(IFAEDJReg.IFAEDREG_TYPE_STANDARD +
IFAEDJReg.IFAEDREG_TYPE_NOTFOUNDDISABLED);
reg.setProductName("TESTPROD");
reg.setProductOwner("IBM");
reg.setProductID("9999-999");
int rc = reg.register(); // Invoke registration service
if (rc != IFAEDJReg.IFAEDREG_SUCCESS) {
   System.out.println("TESTPROD registration failed due to the return code from IFAEDJReg,
rc="+rc);
   System.exit(1);
}
```

#### **Example: Deregistering a product using Java**

A previously registered product is to be deregistered. The same object that was used during registration is used for the deregistration. Deregistration is done using the system service IFAEDDRG.

```
nt rc = reg.deregister(); // Invoke deregistration service
if (rc != IFAEDJReg.IFAEDDRG_SUCCESS) {
   System.out.println("TESTPROD deregistration failed due to the return code from
        IFAEDJReg, rc="+rc);
   System.exit(2);
}
```

## **Examples**

## **Appendix A. Accessibility**

Accessible publications for this product are offered through IBM Documentation (www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the <u>Contact the z/OS team web page (www.ibm.com/systems/campaignmail/z/zos/contact\_z)</u> or use the following mailing address.

IBM Corporation Attention: MHVRCFS Reader Comments Department H6MA, Building 707 2455 South Road Poughkeepsie, NY 12601-5400 United States

## **Accessibility features**

Accessibility features help users who have physical disabilities such as restricted mobility or limited vision use software products successfully. The accessibility features in z/OS can help users do the following tasks:

- Run assistive technology such as screen readers and screen magnifier software.
- Operate specific or equivalent features by using the keyboard.
- Customize display attributes such as color, contrast, and font size.

## **Consult assistive technologies**

Assistive technology products such as screen readers function with the user interfaces found in z/OS. Consult the product information for the specific assistive technology product that is used to access z/OS interfaces.

## **Keyboard navigation of the user interface**

You can access z/OS user interfaces with TSO/E or ISPF. The following information describes how to use TSO/E and ISPF, including the use of keyboard shortcuts and function keys (PF keys). Each guide includes the default settings for the PF keys.

- z/OS TSO/E Primer
- z/OS TSO/E User's Guide
- z/OS ISPF User's Guide Vol I

## **Dotted decimal syntax diagrams**

Syntax diagrams are provided in dotted decimal format for users who access IBM Documentation with a screen reader. In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line because they are considered a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that the screen reader is set to read out punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1)

are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The \* symbol is placed next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element \*FILE with dotted decimal number 3 is given the format 3 \\* FILE. Format 3\* FILE indicates that syntax element FILE repeats. Format 3\* \\* FILE indicates that syntax element \* FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol to provide information about the syntax elements. For example, the lines  $5.1 \star$ , 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, it indicates a reference that is defined elsewhere. The string that follows the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %0P1 means that you must refer to separate syntax fragment OP1.

The following symbols are used next to the dotted decimal numbers.

#### ? indicates an optional syntax element

The question mark (?) symbol indicates an optional syntax element. A dotted decimal number followed by the question mark symbol (?) indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that the syntax elements NOTIFY and UPDATE are optional. That is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.

#### ! indicates a default syntax element

The exclamation mark (!) symbol indicates a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicate that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the dotted decimal number can specify the ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In the example, if you include the FILE keyword, but do not specify an option, the default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, the default FILE(KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP applies only to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

#### \* indicates an optional syntax element that is repeatable

The asterisk or glyph (\*) symbol indicates a syntax element that can be repeated zero or more times. A dotted decimal number followed by the \* symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line  $5.1 \star$  data area, you know that you can include one data area, more than one data area, or no data area. If you hear the lines  $3 \star$  , 3 HOST, 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

#### Notes:

- 1. If a dotted decimal number has an asterisk (\*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
- 2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you can write HOST STATE, but you cannot write HOST HOST.
- 3. The \* symbol is equivalent to a loopback line in a railroad syntax diagram.

#### + indicates a syntax element that must be included

The plus (+) symbol indicates a syntax element that must be included at least once. A dotted decimal number followed by the + symbol indicates that the syntax element must be included one or more times. That is, it must be included at least once and can be repeated. For example, if you hear the line 6.1+ data area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. Similar to the \* symbol, the + symbol can repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the \* symbol, is equivalent to a loopback line in a railroad syntax diagram.

## **Notices**

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
United States of America

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Site Counsel 2455 South Road Poughkeepsie, NY 12601-5400 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

#### **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

#### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

#### Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

#### **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

## **IBM Online Privacy Statement**

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <a href="mailto:ibm.com">ibm.com</a> /privacy and IBM's Online Privacy Statement at <a href="mailto:ibm.com/privacy/details">ibm.com/privacy/details</a> in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <a href="mailto:ibm.com/software/info/product-privacy">ibm.com/software/info/product-privacy</a>.

## **Policy for unsupported hardware**

Various z/OS elements, such as DFSMSdfp, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

## **Minimum supported hardware**

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: <a href="IBM Lifecycle Support for z/OS">IBM Lifecycle Support for z/OS</a> (www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

#### **Trademarks**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at Copyright and Trademark information (www.ibm.com/legal/copytrade.shtml).

# Index

A	K
accessibility contact IBM <u>37</u> features <u>37</u> assistive technologies <u>37</u>	keyboard navigation <u>37</u> PF keys <u>37</u> shortcut keys <u>37</u>
С	L
checking product status <u>3</u> coding registration services <u>5</u> contact z/OS <u>37</u>	List_Status service example <u>32</u> invoking <u>5</u> using <u>3</u>
D	N
Deregister service example 31 invoking 5	navigation keyboard <u>37</u>
Java example <u>34</u> using 2	0
dynamic enablement 1	overview of product registration <u>1</u>
E	P
enablement, product $\underline{1}$ examples, product registration services $\underline{31}$	product enablement <u>1</u> product registration checking product status 3
F feedback <u>ix</u>	coding the services 5 Deregister service 13 examples 31 List_Status service 19
I IFAEDC include file 18, 19, 24	overview <u>1</u> Query_Status service <u>15</u> Register service <u>6</u>
IFAEDDRG service example 31	Q
Java example 34  IFAEDIDF mapping macro 5, 18, 19  IFAEDLIS service     example 32  IFAEDREG service     example 31	Query_Status service example <u>31</u> invoking <u>5</u> using <u>3</u>
Java example 34 IFAEDSTA service	R
example $31$ IFAPRDxx $1$ , $6$	Register service example <u>31</u> invoking <u>5</u>
J	Jave example <u>34</u> using 2
Java deregistering a product <u>34</u> registering a product <u>34</u>	registration services 1 registration, product 1 request type List_Status service 20 Register service 8

#### S

sending to IBM
reader comments ix
shortcut keys 37
summary of changes
z/OS MVS Programming: Product Registration
xi

#### T

trademarks 44

### U

user interface ISPF <u>37</u> TSO/E <u>37</u>

### Z

z/OS MVS Programming: Product Registration summary of changes <u>xi</u>

# IBW.

Product Number: 5650-ZOS

SA38-0698-50

