z/OS 2.5

UNIX System Services File System Interface Reference





© Copyright International Business Machines Corporation 1996, 2021.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

| Figures | IX |
|-----------------------------------------------------------------------------------------------------------------|------|
| Tables | xi |
| About this document | xiii |
| Who should use this document? | |
| z/OS information | |
| Discussion list | xiv |
| How to send your comments to IBM | xv |
| If you have a technical problem | XV |
| Summary of changes | |
| Summary of changes for z/OS UNIX System Services File System Interface Reference for Version 2 Release 5 (V2R5) | |
| Summary of changes for z/OS UNIX System Services File System Interface Reference for Version 2 Release 4 (V2R4) | |
| Summary of changes for z/OS UNIX System Services for Version 2 Release 3 (V2R3) | |
| Chapter 1. General overview | 1 |
| System structure | |
| Finding more information about sockets | |
| Finding more information about timer units | 2 |
| Chapter 2. Physical file systems | |
| Installing a PFS | |
| Activating and deactivating the PFS | |
| Activation flow for the PFS_Init module | |
| PFS_Init entry interface | |
| Recycling a PFS externally | |
| Considerations for stopping a PFS | |
| Cross-memory considerations | |
| Considerations for writing a PFS in C | |
| Security responsibilities and considerations | |
| Running a PFS in a colony address space | |
| Overview of the PFS interface | |
| Operations summary | |
| LFS/PFS control block structure | |
| Sharing files | |
| LFS-PFS control block integrity | |
| The OSI structure | |
| Waiting and postingLFS-PFS control block serialization | |
| Recovery considerations | |
| PFS interface: File PFS protocols | |
| Mounting file systems | |
| Asynchronous mounting | |
| Resolving pathnames | |
| Unmounting file systems | |
| omnounting me systems | 4 |

| Creating, referring to, and inactivating file vnodes | |
|---------------------------------------------------------|----|
| Creating files | 30 |
| Deleting files | 31 |
| Opening and closing files and first references to files | 31 |
| PFS Open Context and the Open_token | |
| Reading from and writing to files | |
| Reading directories | 35 |
| Getting and setting attributes | |
| Supporting Share Reservations in a PFS | |
| File tags | 41 |
| Using daemon tasks within a PFS | |
| Exporting files to a VFS server | |
| Select | |
| PFS interface: Socket PFS protocols | |
| Activating a domain | |
| Creating, referring to, and closing socket vnodes | |
| Reading and writing | |
| Getting and setting attributes | |
| Select/poll processing | |
| Common INET sockets | |
| SRB-mode callers | |
| Asynchronous I/O processing | |
| Related services Impact on initialization | |
| Waits that are avoided | |
| Related OSI fields | |
| Canceling an operation | |
| Responsibilities for the semantics | |
| Asynchronous I/O flow diagram | |
| Asynchronous I/O flow details | |
| Colony PFS PC | |
| Considerations for Internet Protocol Version 6 (IPv6) | |
| Activating IPv6 on a system | |
| Common INET transport driver index | |
| ioctl used by the XL C/C++ Runtime Library | |
| ioctls used by the prerouter | |
| ioctls used by the resolver | 63 |
| PFS support for multilevel security | 64 |
| PFS support for 64-bit virtual addressing | 66 |
| Levels of support for 64-bit virtual addressing | |
| Indicating support for 64-bit virtual addressing | |
| Minimum 64-bit support | |
| Specific considerations for vnode operations | |
| Expanded 64-bit time values | |
| PFS support for reason code error text | |
| Indicating PFS support for the error text pfsctl call | |
| Passing data on the error text pfsctl call | |
| PFS support for MODIFY OMVS,PFS | |
| PFS support for running in AMODE 64 | 71 |
| Chapter 3. PFS operations descriptions | |
| Environment for PFS operations | |
| C header files | |
| vfs_batsel — Select/poll on a batch of vnodes | |
| vfs_gethost — Get the socket host ID or name | |
| vfs_inactive — Batch inactivate vnodes | |
| vfs mount — Mount a file system | 84 |

| vfs_network — Define a socket domain to the PFS | 88 |
|-------------------------------------------------------------------------------------------------|----------|
| vfs_pfsctl — PFS control | |
| vfs_recovery — Recover resources at end-of-memory | 94 |
| vfs_socket — Create a socket or a socket pair | 97 |
| vfs_statfs — Get the file system status | |
| vfs_sync — Harden all file data for a file system | 103 |
| vfs_unmount — Unmount a file system | 105 |
| vfs_vget — Convert a file identifier to a vnode Token | 108 |
| vn_accept — Accept a socket connection request | 111 |
| vn_access — Check access to a file or directory | |
| vn_anr — Accept a socket connection and read the first block of | data 116 |
| Specific processing notes | 120 |
| Serialization provided by the LFS | 121 |
| Security calls to be made by the LFS | 121 |
| Related services | 121 |
| vn_audit — Audit an action | 121 |
| vn_bind — Bind a name to a socket | 123 |
| vn_cancel — Cancel an asynchronous operation | |
| vn_close — Close a file or socket | |
| vn_connect — Connect to a socket | |
| vn_create — Create a new file | |
| vn_fsync — Harden file data | |
| vn_getattr — Get the attributes of a file | |
| vn_getname — Get the peer or socket name | |
| vn_inactive — Inactivate a vnode | |
| vn_ioctl — I/O control | |
| vn_link — Create a link to a file | |
| vn_listen — Listen on a socket | |
| vn_lockctl — Byte range lock control | |
| vn_lookup — Look up a file or directory | |
| vn_mkdir — Create a directory | |
| vn_open — Open a file | |
| vn_pathconf — Determine configurable path name values | |
| vn_rdwr — Read or write a file | |
| vn_readdir — Read directory entries | |
| vn_readlink — Read a symbolic linkvn readwritev — Read or write using a set of buffers for data | |
| vn_recovery — Recover resources after an abend | |
| vn_remove — Remove a link to a file | |
| vn_rename — Rename a file or directory | |
| vn_rmdir — Remove a directoryvn_rmdir — Remove a directory | |
| vn_select — Select or poll on a vnode | |
| vn_sendtorcvfm — Send to or receive from a socket | |
| vn_setattr — Set the attributes of a file | |
| vn_setpeer — Set a socket's peer address | |
| vn_shutdown — Shut down a socket | |
| vn_sndrcv — Send to or receive from a socket | |
| vn_sockopt — Get or set socket options | |
| vn_srmsg — Send messages to or receive messages from a sock | |
| vn_srx — Send or receive CSM buffers | |
| vn_symlink — Create a symbolic link | |
| vn_trunc — Truncate a file | |
| Chapter 4. VFS servers | 241 |
| Installation | |
| Activation and deactivation | |
| Termination considerations | 242 |
| | |

| Security responsibilities and considerations | 242 |
|----------------------------------------------------------------------------------|-----|
| VFS server considerations for 64-bit addressing | 242 |
| Using the VFS callable services application programming interface | 243 |
| Operations summary | 243 |
| VFS server – LFS control block structure | |
| Registration | 245 |
| Mounting and unmounting | |
| Overview of NFS processing | |
| NFS file handles | |
| Reading and writing | |
| Reading directories | |
| Getting and setting attributes. | |
| Comparing the VFS server and PFS interfaces | |
| Chapter 5. VFS callable services application programming interface | 252 |
| | |
| Syntax conventions for the VFS callable services | |
| Elements of callable services syntax | |
| Other subjects related to callable services | |
| Considerations for servers written in C | |
| v_access (BPX1VAC, BPX4VAC) — Check file accessibility | |
| v_close (BPX1VCL, BPX4VCL) — Close a file | |
| v_create (BPX1VCR, BPX4VCR) — Create a file | |
| v_export (BPX1VEX, BPX4VEX) — Export a file system | |
| v_fstatfs (BPX1VSF, BPX4VSF) — Return file system status | |
| v_get (BPX1VGT, BPX4VGT) — Convert an FID to a vnode Token | |
| v_getattr (BPX1VGA, BPX4VGA) — Get the attributes of a file | |
| v_ioctl (BPX1VIO/BPX4VIO) - Convey a command to a physical file system | |
| v_link (BPX1VLN, BPX4VLN) — Create a link to a file | |
| v_lockctl (BPX1VLO, BPX4VLO) — Lock a file | |
| v_lookup (BPX1VLK, BPX4VLK) — Look up a file or directory | 294 |
| v_mkdir (BPX1VMD, BPX4VMD) — Create a directory | 297 |
| v_open (BPX1VOP, BPX4VOP) — Open or create a file | 301 |
| v_pathconf (BPX1VPC, BPX4VPC) — Get pathconf information for a directory or file | 309 |
| v_rdwr (BPX1VRW, BPX4VRW) — Read from and write to a file | 311 |
| v_readdir (BPX1VRD, BPX4VRD) — Read entries from a directory | 315 |
| v_readlink (BPX1VRA, BPX4VRA) — Read a symbolic link | |
| v_reg (BPX1VRG, BPX4VRG) — Register a process as a server | |
| v_rel (BPX1VRL, BPX4VRL) — Release a vnode token | |
| v_remove (BPX1VRM, BPX4VRM) — Remove a link to a file | |
| v_rename (BPX1VRN, BPX4VRN) — Rename a file or directory | |
| v_rmdir (BPX1VRE, BPX4VRE) — Remove a directory | |
| v_rpn (BPX1VRP, BPX4VRP) — Resolve a path name | |
| v_setattr (BPX1VSA, BPX4VSA) — Set the attributes of a file | |
| v_symlink (BPX1VSY, BPX4VSY) — Create a symbolic link | |
| Chapter 6. OSI services | 255 |
| | |
| Using OSI services from a non-kernel address space | |
| osi_copyin — Move data from a user buffer to a PFS buffer | |
| osi_copyout — Move data from a PFS buffer to a user buffer | |
| osi_copy64 — Move data between user and PFS buffers with 64-bit addresses | |
| osi_ctl — Pass control information to the kernel | |
| osi_getcred — Obtain SAF UIDs, GIDs, and supplementary GIDs | |
| osi_getvnode — Get or return a vnode | |
| osi_kipcget — Query interprocess communications | |
| osi_kmsgctl — Perform message queue control operations | |
| osi_kmsgget — Create or find a message queue | |
| osi_kmsgrcv — Receive from a message queue | 385 |

| osi_kmsgsnd — Send a message to a message queue | |
|------------------------------------------------------------------------------------|-----|
| osi_mountstatus — Report file system status to LFS | |
| osi_post — Post an OSI waiter | |
| osi_sched — Schedule async I/O completion | |
| osi_selpost — Post a process waiting for select | |
| osi_signal — Generate the requested signal event | |
| osi_sleep — Sleep until a resource is available | 402 |
| osi_thread — Fetch and call a module from a colony thread | |
| osi_uiomove — Move data between PFS buffers and buffers defined by a UIO structure | |
| osi_upda — Update async I/O request | |
| osi_wait — Wait for an event to occurosi_wakeup — Wake up OSI sleepers | |
| | |
| Appendix A. System control offsets to callable services | |
| List of offsets | |
| | |
| Appendix B. Mapping macros | 433 |
| Macros mapping parameters | 433 |
| BPXYATTR — Map file attributes for v_ system calls | 433 |
| BPXYNREG — Map interface block to vnode registration | |
| BPXYOSS — Specific information for the Map operating system | |
| BPXYVLOK — Map the interface block for v_lockctl | 445 |
| BPXYVOPN — Map the open parameters structure for v_open | 450 |
| Appendix C. Callable services examples | 453 |
| Reentrant entry linkage | |
| BPX1VCR, BPX4VCR (v_create) | |
| BPX1VSF, BPX4VSF (v_fstatfs) | 454 |
| BPX1VGT, BPX4VGT (v_get) | 454 |
| BPX1VGA, BPX4VGA (v_getattr) | 454 |
| BPX1VIO, BPX4VIO (v_ioctl) | 455 |
| BPX1VLN, BPX4VLN (v_link) | 455 |
| BPX1VLO, BPX4VLO (v_lockctl) | 455 |
| BPX1VLK, BPX4VLK (v_lookup) | 456 |
| BPX1VMD, BPX4VMD (v_mkdir) | |
| BPX1VPC, BPX4VPC (v_pathconf) | |
| BPX1VRW, BPX4VRW (v_rdwr) | |
| BPX1VRD, BPX4VRD (v_readdir) | |
| BPX1VRA, BPX4VRA (v_readlink) | |
| BPX1VRG, BPX4VRG (v_reg) | |
| BPX1VRL, BPX4VRL (v_rel) | |
| BPX1VRM, BPX4VRM (v_remove) | |
| BPX1VRN, BPX4VRN (v_rename) | |
| BPX1VRE, BPX4VRE (v_rmdir) | |
| BPX1VRP, BPX4VRP (v_rpn) | |
| BPX1VSA, BPX4VSA (v_setattr) | |
| BPX1VSY, BPX4VSY (v_symlink) | |
| Reentrant return linkage | 461 |
| Appendix D. Interface structures for C language servers and clients | |
| BPXYVFSI | |
| BPXYPFSI | 484 |
| Appendix E. Assembler and C-language facilities for writing a PFS in C | 517 |
| Assembler replacements for @@XGET and @@XFREE | 517 |
| BPXT4KGT—Get a page of storage | |

| C function | |
|------------------------------------------------|-----|
| Assembler routine | |
| BPXT4KFR—Free a page of storage | |
| C function | |
| Assembler routine | |
| BPXTWAIT—Wait on an ECB list | 520 |
| C function | 520 |
| Assembler routine | 520 |
| BPXTPOST—Post an ECB | 520 |
| C function | 520 |
| Assembler routine | 520 |
| BPXTEPOC—Convert time-of-day to epoch time | 521 |
| C function | |
| Assembler routine | 521 |
| | |
| Appendix F. Accessibility | 523 |
| Accessibility features | 523 |
| Consult assistive technologies | |
| Keyboard navigation of the user interface | 523 |
| Dotted decimal syntax diagrams | 523 |
| | |
| Notices | 527 |
| Terms and conditions for product documentation | 528 |
| IBM Online Privacy Statement | |
| Policy for unsupported hardware | |
| Minimum supported hardware | |
| Trademarks | 530 |
| Acknowledgments | 530 |
| - - | |
| Index | 521 |

Figures

| 1. VFS server and PFS structure | 2 |
|-----------------------------------------------------------------|-----|
| 2. PFS_Init entry parameter list | |
| 3. The LFS/PFS control block structure | 17 |
| 4. Format of BPXYFDUM | 25 |
| 5. Common INET sockets PFS structure | 48 |
| 6. General flow of an asynchronous operation | 58 |
| 7. Input to module and exit using a parameter structure | 409 |
| 8. Input to module and exit without using a parameter structure | 409 |

Tables

| 1. How the PFS_Init routine receives control | 5 |
|-----------------------------------------------------------|-----|
| 2. Pointers to parameters in the PFS_Init entry interface | 6 |
| 3. PFS restart options | 11 |
| 4. TOD and SSE fields with the EXTENDED keyword | 69 |
| 5. List of return codes for vn_anr | 119 |
| 6. List of return codes for vn_bind | 125 |
| 7. List of return codes for vn_readwritev | 186 |
| 8. Error values for the vn_rename operation | 197 |
| 9. Subfunctions for vn_select | 203 |
| 10. Input fields for attribute_structure | 212 |
| 11. List of return codes for vn_srmsg | 229 |
| 12. API functions for VFS callable services | 243 |
| 13. Summary of v_open parameters that vary by open type | 308 |
| 14. Attributes fields for v_setattr | 345 |
| 15. OSI services | 355 |
| 16. System control offsets to callable services | 423 |

About this document

This document describes the interfaces that are used to create physical file system (PFS) and virtual file system (VFS) servers that can operate with z/OS UNIX System Services (z/OS UNIX). PFS and VFS servers might be written to extend the services provided by z/OS UNIX in the areas of device support for a file system or network access to file systems. This document also describes how to use these interfaces.

Chapter 1 is a general overview that shows how the physical file system, logical file system, and virtual file system server interact. Chapters 2 and 3 describe the physical file system interface. Chapters 4 and 5 describe the virtual file system server interface. Chapter 6 describes the Operating System Interface (OSI) callable services.

In the appendixes, you will find information about:

- System control offsets to callable services
- Mapping macros
- Callable services examples
- Interface structures for C language servers and clients
- Assembler and C-language facilities for writing a PFS in C
- · Accessibility features
- Notices
- An index

Related information

You can find more detailed information about sockets and their operations in various publications, including the following ones:

- 4.3BSD UNIX Operating System, by S. J. Leffler et al.
- z/OS XL C/C++ Programming Guide
- z/OS XL C/C++ Runtime Library Reference
- AIX® Version 4.3 Communications Programming Concepts, SC23-4124

You can find detailed information about timer units in z/Architecture Principles of Operation, SA22-7832.

Who should use this document?

This document is intended for a specialized audience: system programmers using C or assembler language to create a physical file system (PFS) or a virtual file system (VFS) server, or to port a PFS or a VFS server to z/OS UNIX. Knowledge of POSIX or UNIX is assumed.

Depending on the complexity of the PFS or VFS server involved, a considerable amount of MVS[™] system programming knowledge might be required. Detailed information about MVS services that might be needed can be found in:

- z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN
- z/OS MVS Programming: Authorized Assembler Services Reference EDT-IXG
- z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU
- z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO
- z/OS MVS Programming: Extended Addressability Guide
- z/OS MVS Programming: Authorized Assembler Services Guide

This document should be used in conjunction with *z/OS UNIX System Services Programming: Assembler Callable Services Reference*. It also supplements information that is contained in IEEE Std 1003.1-1990 and IEEE Std 1003.1a.

z/OS information

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see z/OS Information Roadmap.

To find the complete z/OS library, go to IBM Documentation (www.ibm.com/docs/en/zos).

Discussion list

Customers and IBM® participants also discuss z/OS UNIX on the mvs-oe discussion list. This list is not operated or sponsored by IBM.

To subscribe to the mvs-oe discussion, send a note to:

listserv@vm.marist.edu

Include the following line in the body of the note, substituting your given name and family name as indicated:

subscribe mvs-oe given_name family_name

After you have been subscribed, you will receive further instructions on how to use the mailing list.

How to send your comments to IBM

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

Important: If your comment regards a technical question or problem, see instead <u>"If you have a technical</u> problem" on page xv.

Submit your feedback by using the appropriate method for your type of comment or question:

Feedback on z/OS function

If your comment or question is about z/OS itself, submit a request through the <u>IBM RFE Community</u> (www.ibm.com/developerworks/rfe/).

Feedback on IBM Documentation function

If your comment or question is about the IBM Documentation functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Documentation Support at ibmdocs@us.ibm.com.

Feedback on the z/OS product documentation and content

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to mhvrcfs@us.ibm.com. We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS UNIX System Services File System Interface Reference, SA23-2285-50
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive authority to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

If you have a technical problem

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the IBM Support Portal (support.ibm.com).
- · Contact your IBM service representative.
- Call IBM technical support.

Summary of changes

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

Note: IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under IBM z/OS Product Documentation Update Policy (www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy? OpenDocument).

Summary of changes for z/OS UNIX System Services File System Interface Reference for Version 2 Release 5 (V2R5)

Deleted

The following content is deleted.

• Information about DFS was deleted because DFS/SMB is no longer supported.

Summary of changes for z/OS UNIX System Services File System Interface Reference for Version 2 Release 4 (V2R4)

Changed

January 2021 refresh

- For the osi_ctl service, OSI_TERMINATE enables the PFS to notify the LFS that the PFS is terminating abnormally. See "osi_ctl Pass control information to the kernel" on page 365.
- The specific processing notes for vfs_vet were updated. See "vfs_vget Convert a file identifier to a vnode Token" on page 108.

Prior to the January 2021 refresh

• As part of the zFS to zFS migration support, the BPXYPFSI macro was updated. For more information, see "BPXYPFSI" on page 484.

Summary of changes for z/OS UNIX System Services for Version 2 Release 3 (V2R3)

New

• Support was added for POSIX time values beyond year 2038 and z/OS time-of-day values beyond the year 2040. See "Expanded 64-bit time values" on page 67.

Deleted

Information about the Setup Verification Program (SVP) was deleted.

Chapter 1. General overview

z/OS UNIX System Services (z/OS UNIX) allows you to install virtual file system servers (VFS servers) and physical file systems (PFSs).

A VFS server makes requests for file system services on behalf of a client. A VFS server is similar to a
POSIX program that reads and writes files, except that it uses the lower-level VFS callable services API
instead of the POSIX C-language API.

An example of a VFS server is the Network File System.

• A physical file system (PFS) controls access to data.

PFSs receive and act upon requests to read and write files that they control. The format of these requests is defined by the *PFS interface*.

PFSs include pipes, sockets, and UNIX file systems such as zFS, TFS, and NFS.

Another name for a PFS is an installable file system.

User-written programs use the POSIX API to issue file requests. VFS servers use the VFS callable services API to issue file requests. These requests are routed by the logical file system (LFS) to the appropriate PFS through the PFS interface. See Figure 1 on page 2 for a view of this structure.

This information unit describes these two interfaces and discusses the things you need to know to write a VFS server or a PFS, or to port one to the z/OS UNIX environment. In order to do this, you should be a system programmer who is familiar with POSIX or UNIX.

Porting note

This information unit uses notes like this one to highlight certain points of the implementation that are particularly important to readers who are considering porting an existing UNIX-based program to z/OS UNIX.

z/OS UNIX supports the following types of files:

- · Regular files
- Directories
- Symbolic links
- Character special files (for example, terminals)
- · Pipes (both FIFOs and unnamed)
- Sockets

Character special and unnamed pipe physical file systems cannot be implemented with this interface. Unnamed pipes and socket files cannot be exported by a VFS server.

System structure

The position of the VFS server and the PFS in the structure of z/OS UNIX and the interfaces they use are illustrated in Figure 1 on page 2.




Figure 1. VFS server and PFS structure

- 1. The VFS callable services API is used by VFS servers to call the logical file system.
- 2. The logical file system calls the PFSs through the PFS interface.

Finding more information about sockets

You can find more detailed information about sockets and their operations in various publications, including the following:

- 4.3BSD UNIX Operating System, by S. J. Leffler et al.
- z/OS XL C/C++ Programming Guide
- z/OS XL C/C++ Runtime Library Reference
- AIX Version 4.3 Communications Programming Concepts, SC23-4124

Finding more information about timer units

You can find detailed information about timer units in z/Architecture Principles of Operation, SA22-7832.

Chapter 2. Physical file systems

This topic describes:

- How to install a physical file system (PFS)
- How a PFS is activated and deactivated
- The functions that must be provided by a PFS
- The functions that are provided for it
- · Cross-memory considerations
- · Considerations for writing a PFS in C
- · Security considerations
- Running a PFS in a colony address space
- Considerations for Internet Protocol Version 6 (IPv6)
- PFS support for multilevel security
- PFS support for 64-bit virtual addressing
- · PFS support for reason code error text
- PFS support for MODIFY OMVS,PFS

Installing a PFS

A physical file system (PFS) is packaged as one or more MVS load modules, which must be installed in an APF-authorized load library. The load modules cannot be installed in the z/OS UNIX file system because it is not available when a PFS is loaded.

The PFS must have an initialization routine whose entry point, called *PFS_Init*, is externally known through the system link list or the STEPLIB of the OMVS cataloged procedure. If the PFS runs in a colony address space (see "Running a PFS in a colony address space" on page 13), it must be found through the system link list or a STEPLIB of the colony address space's procedure.

A physical file system is defined to z/OS UNIX through the BPXPRMxx parmlib member you specify when you start the kernel address space (OMVS=xx). The FILESYSTYPE statement defines a single instance of a PFS.

Additional MOUNT, ROOT, SUBFILESYSTYPE, or NETWORK statements activate file system or socket support in the PFS.

```
FILESYSTYPE TYPE(file_system_type)
ENTRYPOINT(PFS_Init)
PARM(parameter_string)
ASNAME(procname)
```

where:

- **TYPE** specifies a 1-to-8-character name that uniquely identifies this PFS. This name is used to route subsequent MOUNT, ROOT, SUBFILESYSTYPE, or NETWORK statements (as well as later MOUNT and PFSCTL syscalls) to the correct PFS.
- **ENTRYPOINT** specifies the name of the PFS's initialization module. The LFS attaches the PFS_Init entry point as an MVS task. This task remains active for as long as the PFS is active. See <u>"Activating and deactivating the PFS" on page 4</u> for a description of initialization processing requirements for this routine.
- **PARM** specifies a PFS-defined parameter text string that can contain any value and be up to 1024 bytes long. The meaning of this string is defined by the individual PFS. The string is passed to the PFS when the PFS_Init routine is attached.

• ASNAME specifies that the PFS is to run outside the kernel in a separate address space.

procname is the name of the procedure to be used when starting this address space, and a logical name for the address space. Each procname generates a different address space when it is first encountered, and each PFS with the same procname shares that address space. These address spaces are logical extensions of the kernel. They are referred to as colony address spaces.

All PFSs are activated automatically when z/OS UNIX is started, based on the FILESYSTYPE and SUBFILESYSTYPE statements in the parmlib member. This is the only way a PFS can be started.

Mounts may also be issued dynamically at a later time through a TSO/E command or a program function call. A mount is not strictly necessary, but it is required if the files that are managed by the PFS are to be visible in the file hierarchy (that is, if they are to be represented by standard pathnames). Support for mount generally implies support for the lookup operation, which is used to resolve a pathname to a file. Pipes and sockets are examples of files that are not in the hierarchy; these PFSs do not use mount.

For a discussion of mount processing, refer to "Mounting file systems" on page 25.

The ROOT statement is a special case of MOUNT. It can be issued only from parmlib, and it defines the system's root file system.

The NETWORK statement does for a sockets PFS what MOUNT does for a data file type of PFS: It activates an address family, or domain, so that subsequent socket() calls are routed to that PFS to service.

For a discussion of network processing, refer to "Activating a domain" on page 43.

Activating and deactivating the PFS

A PFS is started for each FILESYSTYPE statement in the BPXPRMxx parmlib member whenever z/OS UNIX is started. The LFS and PFS exchange information during this initialization phase. Usually the PFS does not terminate.

The same ENTRYPOINT name may be specified on two or more FILESYSTYPE statements with different TYPE operands. This causes the same PFS to be started more than once. It is up to the PFS to allow this or to detect and reject it.

Activation flow for the PFS_Init module

The LFS builds a general file system table (GFS) for each PFS and attaches the PFS's initialization entry point. This creates an independent MVS task, which is expected to follow these general steps:

- 1. Perform any PFS initialization that is necessary.
- 2. Load its VFS and vnode operation service routines and build their respective vector tables.

These are the PFS routines that the LFS calls to get such services as mount, open, read, and write. The VFS and vnode operations vector tables make up the major part of the PFS interface.

This loading may be done by link-editing the operational routines with the PFS_Init routine.

- 3. Save the OSI operations vector table (OSIT) address.
 - The OSI operations vector table contains the addresses of LFS routines that the PFS uses to get certain services, such as those used to create vnodes.
- 4. Pass back to the LFS an 8-byte token that is saved by the LFS and used on all subsequent VFS and vnode operations. This token typically contains the address of the PFS's main anchor block. Its use is optional.
- 5. Exchange miscellaneous items of information between the LFS and PFS. Refer to <u>"The PFSI structure"</u> on page 6 and the PFSI structure in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for details on the specific information that is exchanged.
- 6. Notify the LFS that initialization has finished, by posting the initialization-complete ECB that was supplied.

7. Wait on the termination ECB, which is also supplied by the LFS. This ECB is posted by the LFS when it is time to terminate the PFS.

Each PFS is initialized synchronously and serially during z/OS UNIX initialization, so that no PFS may go into an extended wait during initialization.


Note: The file system is not available this early in z/OS UNIX initialization. If the PFS_Init routine needs configuration or other information from a file, it must use an MVS data set.

PFS_Init entry interface

Table 1 on page 5 shows how the PFS Init routine receives control as the result of an ATTACH in the listed environments.

| Table 1. How the PFS_Init routine receives control | |
|----------------------------------------------------|-------------------------------------------------------------|
| Environment | Control |
| Authorization | Supervisor state, PSW key 0 |
| Dispatchable unit mode | Task |
| Cross memory mode | PASN = HASN |
| AMODE | 31-bit or 64-bit |
| ASC mode | Primary mode |
| Interrupt status | Enabled for interrupts |
| Locks | Unlocked |
| Control parameters | All parameters are addressable in the primary address space |

On entry, register 1 points to a variable-length list of parameter addresses. The high-order bit of the last parameter address is turned on. For information about other entry registers, see ATTACH or ATTACHX in z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN.



The addresses in the parameter list point to the parameters in Table 2 on page 6, each of which is described in Appendix D, "Interface structures for C language servers and clients," on page 465.

| Table 2. Pointers to parameters in the PFS_Init entry interface | |
|-----------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Parameter | Description |
| PFSI | The PFS initialization structure. It contains information that is being passed to the PFS and fields that are to be completed by the PFS during its initialization. See "The PFSI structure" on page 6 for a description of these fields. |
| PFSNAME | An 8-byte field that contains the name of the PFS. This name was specified in either the TYPE parameter of a FILESYSTYPE parmlib statement or the NAME parameter of a SUBFILESYSTYPE parmlib statement. This name is used to identify the PFS for the pfsctl() function and, when applicable, for the v_reg() function. |
| PFSPARM | A variable-length field that contains the text string that is specified in the PARM parameter of the FILESYSTYPE statement. It is a 2-byte field that contains the length of the text string, followed by the string. If this parameter is absent, the length field is zero. |
| OSIT | The OSI service routine vector table, which provides the PFS with the addresses of the LFS service routines it needs to perform some basic functions. |
| | See Chapter 6, "OSI services," on page 355 for a description of the interfaces to, and functions of, each of these OSI routines. |

The PFSI structure

The PFS initialization structure (BPXYPFSI, referred to as the PFSI) contains the following fields (each name is prefixed with the characters pfsi_):

ver

The version number of this PFSI.

ook

An indication that this PFS is running outside the kernel.

alone

An indication that this PFS is the only PFS running in the address space.

new

An indication that this is the first time this PFS has been initialized in the address space.

romntclient

Set on to indicate that the PFS does not support simultaneous R/O mounts from multiple systems; the LFS is responsible for making R/O file systems available for sharing in a sysplex system.

The default value is off. This indicates that the PFS supports sharing of R/O file systems in a sysplex.

rwmntsysplex

Set on to indicate that the PFS does not support simultaneous R/W mounts from multiple systems; the LFS is responsible for making R/W file systems available for sharing in a sysplex system.

The default value is off. This indicates that the PFS supports sharing of R/W file systems in a sysplex.

initcompecb

The ECB that the PFS posts when its initialization is complete.

pfsecb

The ECB that the LFS posts when z/OS UNIX is stopped. The PFS must be waiting on this ECB.

restart

The address of the restart option byte. The PFS sets this byte any time during its processing, to control if and how it is to be restarted if it should terminate.

dumpptr

The address of dump information. This information is used by the PFS to add significant LFS areas to the dumps that are taken by the PFS.

pfsid

The PFS identifier that is used with osi_sleep and osi_wakeup.

asname

The value of the ASNAME parameter of the FILESYSTYPE statement.

ep

The value of the ENTRYPOINT parameter of the FILESYSTYPE statement.

Returned Fields

pfsanchor

The PFS initialization token. This token value is passed back to the PFS on every subsequent call from the LFS as part of the token_structure, which is the first parameter of every call. This field typically contains the address of the PFS's main anchor block.

vfso

The address of the PFS's VFS operation vector table.

vnop

The address of the PFS's vnode operation vector table.

srb

An indication that SRB mode is supported.

asvio

An indication that asynchronous I/O is supported.

usethreads

An indication that the PFS is requesting support for the osi_thread service. This field can be set only by PFSs that are running outside the kernel.

disableLLA

An indication that the LFS should not provide lookup lookaside function for this PFS. If there is not a strict one-to-one correspondence between the spelling of a file name in a directory and the vnode-inode pair that represents the file, the PFS should set this bit. For example, if '/usr/dl/fl,attr=fb' and '/usr/dl/fl' represent the same file in the /usr/dl directory, you must disable the LFS lookup lookaside function. If directories are remote and files may be removed from them remotely, the LFS's LLA cache should also be disabled.

stayalone

An indication that the LFS should not initialize any other PFSs in this address space. This field can be set only by PFSs that are running outside the kernel.

immeddel

An indication that the PFS supports deleting a removed file's data when its open count becomes zero, rather than waiting for vn_inactive to free the space.

cpfs

An indication that the PFS is written in C, and is requesting that the LFS invoke it with pre-initialized C environments.

datoffmove

An indication that the PFS supports DATOFF move for page read operations. For more information, see "Reading from and writing to files" on page 34.

pfstype

The type of the PFS. This identifies the PFS as a local file PFS, a remote file PFS, or a socket PFS.

pipebuf

pathconf() _PC_PIPE_BUF value, if applicable

maxcanon

pathconf() _PC_MAX_CANON value, if applicable

maxinput

pathconf() _PC_MAX_INPUT value, if applicable

chownrstd

pathconf() _PC_CHOWN_RESTRICTED value, if applicable

vdisable

pathconf() _PC_VDISABLE value, if applicable.

Pathconf() values that are not constant for all files supported by the PFS may be reported through the vn_pathconf operation.

compon

The PFS's three-letter component (or module) prefix.

compid

The PFS's five-letter component (or product) ID.

The component prefix and ID are used in dump titles for dumps that are taken by the LFS when there is an abnormal end in the PFS from which it does not recover.

modind

An indication that the PFS is supplying indirect addresses in the VFS and vnode operations vector tables for the various VFS and vnode operations routines.

complow

The low value for the PFS reason code high byte. For more information, see <u>"PFS support for reason code error text"</u> on page 69.

comphigh

The high value for the PFS reason code high byte. For more information, see <u>"PFS support for reason code error text"</u> on page 69.

VFS and vnode operations vector tables

VFS and vnode operations vector tables are allocated and built by the PFS, and their addresses are returned in the PFSI. These tables may not be altered after the PFS posts the initialization-complete ECB.

Vnode operations, such as vn_open and vn_readdir, deal with file system objects. VFS operations, such as vfs_mount and vfs_statfs, deal with whole file systems or with the PFS itself.

The routine that supports each particular operation is loaded into storage by the PFS_Init routine, and the entry-point address is placed into the corresponding vector table entry. If the PFS supports the dynamic service activation capability, it must instead supply indirect addresses (that point to the actual entry-point addresses for each operation routine) in the vector table entries and set the pfsi_modind flag in the PFSI. When the LFS processes a VFS or vnode operation request, it will recognize the flag and use the address supplied in the vector table as an indirect address to locate the target operation routine.

If the PFS does not support a particular operation, the corresponding operation's vector must contain 0. The number of operations that are placed in the table by the PFS, as determined by the returned table's length, may be less than or equal to the number of operations that are supported by the LFS. If this value is less, the LFS treats all remaining operations as not supported, just as though the PFS had supplied 0 for those operation vectors. If the table contains more entries than the LFS expects, it is considered a serious product-level mismatch between the LFS and PFS, and the PFS is terminated.

For more information, see the description of vnoptab and vfsotab structures in <u>Appendix D</u>, "<u>Interface</u> structures for C language servers and clients," on page 465.

Recycling a PFS externally

PFS Recycle can be driven externally by two calls to **pfsctl**. The caller must be a superuser. This is supported for kernel-resident PFSs only; for PFSs that are running in a colony address space, cancel the space to recycle the PFS.

PFS Recycle refreshes the PFS load module after service has been applied. The kernel space does not terminate; the only way to refresh a kernel-resident PFS load module is for the PFS_Init task to exit. The PFS may have its own technique to accomplish this and the PFS. Init task can exit on its own at any time. PFS Recycle restarts the PFS, or the LFS issues a WTOR and waits for a reply before restarting the PFS. Refer to "Considerations for stopping a PFS" on page 10 for details. These pfsctl commands coordinate the PFS's termination with the LFS so that calls into the PFS can be guiesced before the PFS. Init task exits.

PC#RecyclePFS X'8000000C'

PC#RecyclePFS X'8000000C' initiates a PFS recycle by posting the PFS's termination ECB.

- If no argument is passed, or if the argument value is not 1, the LFS returns to the caller immediately after calls to the PFS have quiesced and the PFS has been posted to terminate. The caller and the PFS must coordinate any dependencies that they have on each other after this point, because the PFS may not have terminated when the caller regained control.
- If a fullword argument value of 1 is passed, the LFS waits for the PFS to terminate before returning to the caller.

The Return_value is 0 if the PFS is found.

Before this call the caller or PFS must ensure that:

- All current osi waiters have been osi posted.
 - If the v_reg service has been used to register that the PFS is dependent on the caller's process for osi_post, the LFS osi_posts the osi_waiters, just as it would if the caller's process had terminated.
- All outstanding asyncio has been osi_scheduled.
- · All internal waiters have been posted.
- No new vnode ops will be accepted by the PFS, or that no new ops will be allowed to wait or for asyncio to cue.

Before posting the PFS termination ECB, the LFS ensures that there are no more threads executing code in the PFS layer and it will permit no more VFS or vnode ops to branch into the PFS. The LFS waits for any threads that are still in the PFS layer at the time of the pfsctl call. These could include, for example, threads that were just osi_posted, but whose address space had not been swapped in yet, or that were otherwise not dispatched, so they have not had a chance to return back up to the LFS layer.

A race condition exists between this call and user threads that are branching into the PFS layer at about the same time. The PFS begins to reject these calls and the LFS waits for those rejected threads to exit from the PFS layer.

When the termination ECB is posted, the PFS cleans up and exits the PFS_Init module. This decrements the load module's use count; when that count goes to zero the load module is deleted. This assumes a PFS that was not packaged to reside in LPA.

If the second pfsctl, PC#Restart PFS, is going to be used, the PFS must have left the Restart Option Byte (pfsi_restart) at its default value or reset it to RESTART_WTOR before exiting. In this case, the normal WTOR message is not issued when the PFS terminates, and the second pfsctl takes the place of the operator reply to restart the PFS. Alternatively, the second pfsctl does not have to be used if the PFS sets the Restart Option Byte to RESTART AUTO.

The second pfsctl can also be used without the first if the PFS exits with the Restart Option Byte set to RESTART_PFSCTL(7). This suppresses the WTOR message and causes the LFS to wait for the second pfsctl before restarting the PFS.

PC#RestartPFS X'8000000D'

PC#RestartPFS X'8000000D' restarts the PFS by reattaching the PFS_Init module.

- If no argument is passed, or if the argument value is not 1, the LFS waits for the PFS initialization to complete before returning to the caller.
- If a fullword argument value of 1 is passed, the LFS returns to the caller immediately after posting the internal thread that does the reattach. The caller and the PFS must coordinate between themselves for the restart. This is similar to a startup during IPL.

The Return_value is 0 if the PFS was found and was awaiting this restart. The Return_value is 1 if the PFS was found but was not waiting to be restarted. This would be a normal situation immediately after an IPL, or if the caller did not recycle the PFS. If the PFS is not found the call fails.

This call can be made before the PFS has finished terminating, in which case the LFS proceeds directly to the PFS restart when it does finally terminate.

If all copies of the PFS have been recycled and the PFS load module does not reside in the LPA, the first reattach of the load module brings a fresh copy into storage.

The PFS should run through a more or less normal PFS initialization sequence with respect to the LFS. The regular sequence of returning VFS and vnode operation vectors, posting the LFS ECB, and waiting for the PFS termination ECB must be followed.

On each restart of a PFS, the previously returned value of pfsi_pfsanchor is passed into the new instance of the PFS. The PFS may use a design in which this anchor points to persistent storage so that it can reuse or reclaim resources from a prior instance.

For Socket PESs:

- After the PFS completes its reinitialization, the LFS reissues any vfs_network calls that were originally made to set up for the address family domains that this PFS supports.
- The master socket opens with the normal sequence of events.

For File System PFSs, prior active mounts are reissued.

The PFS does not have to remember anything from one instance to the next with respect to the LFS and the LFS/PFS interfaces.

Considerations for stopping a PFS

Usually, a PFS does not stop. However, an operator can request that a PFS be stopped by issuing a MODIFY OMVS,STOPPFS=**pfsname** command.

In a sysplex environment, the LFS will attempt to move file systems for the stopping PFS that are owned by this system to another system so that the termination of the PFS is nondisruptive. File systems that were mounted with AUTOMOVE(UNMOUNT) will be unmounted. After this, the termination ECB of the PFS will be posted.

The pfsi_stoppfs capability bit indicates whether a PFS supports being stopped in this manner and only the PFS that set the pfsi_stoppfs bit will be stopped. That PFS PFSs does not need its own external operator command for this purpose.

A PFS may define its own external interface for stopping; however, it cannot use the STOP or MODIFY operator commands unless the PFS is running outside of the kernel.

There is nothing to prevent a PFS from terminating, either normally in a manner defined by the PFS, or abnormally. A PFS that is running in an address space outside the kernel terminates if that address space is terminated. If the PFS_Init program task terminates for any reason before the LFS posts the termination ECB, the LFS takes the following actions:

1. All activity to this PFS is halted. Users receive EIO or EMVSERR errors for any reference to a file that is owned by this PFS.

- 2. Every file system that is mounted for this PFS is logically unmounted. The PFS's vfs_umount is not called, because all activity is halted; but otherwise the file system is unmounted as it would be for an UNMOUNT FORCE command.
 - File systems that are owned by other PFSs that are mounted on directories that are owned by the terminating PFS are also unmounted. These PFSs receive vfs_umount force.
- 3. The PFS is restarted or not depending on the setting of the restart option byte (see Table 3 on page 11). The address of this byte is passed to the PFS in the PFSI during initialization. Its value can be adjusted by the PFS any time before it terminates.
- 4. If the PFS was running in an address space outside the kernel, that address space can be stopped and restarted, depending on the setting of the restart option byte.

The following table shows the available PFS restart options.

| Table 3. PFS restart options | |
|------------------------------|-------------------------------------------------------------------------------------------------|
| Option | Action |
| RESTART_NONE | Do not restart. |
| RESTART_AUTO | Automatic restart. |
| RESTART_WTOR | Prompt the operator before restarting. This is the default restart option. |
| RESTART_RCNONE | Stop the address space and do not restart the PFS. |
| RESTART_RCAUTO | Stop the address space and automatically restart the address space and the PFS. |
| RESTART_RCWTOR | Stop the address space and prompt the operator before restarting the address space and the PFS. |

If the PFS is restarted, file systems that were mounted at the time of failure are not automatically remounted, and network statements are not reprocessed. Socket file systems should specify that the PFS is not to be restarted, because NETWORK statements cannot be issued dynamically. Also, if the PFS requests that the colony address space in which it runs be stopped, the ASID for that address space is marked unusable.

When z/OS UNIX or the file system is being shut down by an operator, the LFS issues a PC#ShuttingDownFS vfs pfsctl call to notify the PFS before the LFS starts unmounting file systems. At such time, the PFS can do whatever might be necessary to prepare for an orderly shutdown prior to receiving the unmount requests. This preparation should not inhibit or disrupt file system operations; users may continue using the file system up until the vfs_unmount request is issued.

Note: The entire system might not be shutting down and new mount requests might be received after all existing file systems have been unmounted. The return code from the vfs pfsctl call will be ignored and there is no way for the PFS to stop the shutdown.

Cross-memory considerations

Because all of the VFS and vnode operations can be called in cross-memory mode, a PFS that must invoke MVS functions that cannot run in this mode must attach a worker task, or tasks, to accomplish these functions. A worker task is a subtask that performs non-cross memory work for PFS operations.

See "Using daemon tasks within a PFS" on page 42 for information about some services that make this task easier.

Although the PFS_Init task can be used as a worker task, if this task terminates, the PFS also terminates.

Considerations for writing a PFS in C

A PFS can be written in System Programmer's C. The BPXYPFSI and BPXYVFSI headers define the structures and parameters that are needed for PFSs that are written in C. A PFS that is written in C can avoid the cost of establishing a C environment each time it is invoked for a vnode or VFS function, by requesting that the LFS invoke the PFS with pre-initialized C environments. The PFS requests this at initialization by setting the pfsi_cpfs flag in the PFSI.

The PFS must not do anything that would sever addressability to the stack.

Because the PFS is running in a cross-memory environment, Language Environment[®] and C/C++ run-time library functions are not available. A PFS that needs to invoke these functions must attach a worker task, or tasks, to accomplish these functions.

See "Using daemon tasks within a PFS" on page 42 for information about services that make creating these worker tasks easier.

Some assembler services that may be useful are provided in Appendix E, "Assembler and C-language facilities for writing a PFS in C," on page 517. In particular, BPXFASM must be assembled and link-edited with the PFS modules, to provide the correct @@XGET/@@XFREE routines for their C environment.

Security responsibilities and considerations

z/OS UNIX maintains system security by verifying user identities and file access control information. A PFS is primarily concerned with file access control.

For those functions where POSIX .1 (IEEE Standard 1003.1-1990) specifies that "appropriate privilege" is required, the PFS refers to a bit that is set by the LFS to determine whether the function has appropriate privileges. For more information, see "Appropriate Privileges" in the POSIX standards.

Access control checks are based on information that is stored with each individual file, and are generally carried out on the system where the data resides.

Access control is integrated with the SAF interface to call RACF®, or whichever security product is used at a particular installation.

The basic flow of file security is as follows:

- 1. Security information, such as the owner's UID-GID and the permission bits for a file, is kept in a 64-byte area called the *file security packet* (FSP), which is mapped by IRRPIFSP. The FSP is the security-related section of a file's attributes.
- 2. The FSP is created by a SAF call from the PFS when a file is created. Some of the information is taken from the current security environment, and some of it is passed as parameters.
- 3. The PFS stores the FSP with the attributes of the file.
- 4. When an access check is to be done, the PFS calls SAF with the type of check that is being requested, the audit_structure from the current call, and the file's FSP. SAF passes these to the security product, which extracts user information from the current security environment and compares it against the access control that is stored within the FSP. The audit_structure is used primarily for any auditing that may be necessary.

There are many access and privilege checks defined by the POSIX standards. The detailed description of each vnode operation in <u>Chapter 3</u>, "<u>PFS operations descriptions</u>," on page 73 discusses the access checks that are expected.

- 5. When a file's access control information is changed, such as by chmod(), the PFS calls SAF with the type of change, the new values, the audit_structure from the current call, and the file's current FSP. A new version of the FSP is returned to the PFS, which then replaces the file's old FSP with the new one.
- 6. When a file is deleted, the PFS discards the FSP.

In the flow described previously, the PFS provides some private space within the file attributes for the security product's use, ensures common access checking across all PFSs, allows for the installation of different security products, and lets the security product perform auditing or other non-POSIX processing.

The PFS is ultimately responsible for the following access checks:

- If the PFS controls the storage of its own files, it follows the flow outlined in this topic to create, maintain, and use security information.
- If the PFS is a client getting its data from some remote repository, it sends the request to the remote system, where the access checks are performed using the osi_getcred service.
- If access is not controlled for the type of data that is supported by a particular PFS, the PFS may choose to skip these security procedures.

Some events that occur in the LFS are audited for security purposes by the vn_audit operation. For example, because relative pathnames may be audited during an access check, it is important to audit the working directory so that a full path name can be constructed if necessary. When a user calls chdir() or fchdir(), the LFS invokes vn_audit to record the new working directory. chroot(), which changes the current root, is another call that causes an audit record to be created.

<u>"PFS support for multilevel security" on page 64</u> discusses PFS responsibilities and considerations for multilevel security.

Running a PFS in a colony address space

By default, PFSs are initialized in the kernel address space. An installation may choose to run a PFS in a separate *colony address space* by specifying an ASNAME parameter on its FILESYSTYPE statement. You may want to have a PFS run in a colony address space if:

- The PFS is constrained by kernel address space resources, such as:
 - Storage
 - Data set allocations
 - Lock contention
- The PFS needs to request callable services itself, in order to:
 - Use sockets
 - Make remote procedure calls
 - Obtain POSIX file I/O

When a PFS runs in a colony address space, an extra address space is created, and each PFS operation has a slightly longer path length.

Any PFS can run in a colony address space unchanged. PFSs that are running in colony address spaces can use the osi_thread service, which is not available to PFSs that are running in the kernel address space. Any PFS that uses this service must document to its users that the PFS must be initialized in a colony address space. See "Using daemon tasks within a PFS" on page 42 for more information about the osi_thread service.

The writer of a PFS cannot assume that the PFS will run in the kernel, nor that it will run under the task that calls it.

Overview of the PFS interface

The PFS interface is a set of protocols and calling interfaces between the logical file system (LFS) and the PFSs that are installed on z/OS UNIX. PFSs mount and unmount file systems and perform other file operations.

This topic describes the services provided by the PFS routines that are called by the LFS. The services are described in terms of the requirements the PFS must meet and the expectations of the LFS. Also included are descriptions of the design that are intended to clarify the implementation of a physical file system on z/OS UNIX.

There are two types of PFSs, those that manage files and those that manage sockets:

- 1. File management PFSs deal with objects that have pathnames and that generally follow the semantics of POSIX files.
- 2. Socket PFSs deal with objects that are created by the socket() and accept() functions and that follow socket semantics.

The LFS is called by POSIX programs, non-POSIX z/OS UNIX programs, and VFS servers. In this topic, "the caller" refers to the LFS or any of the programs that call the LFS. When the LFS is mentioned specifically, it is usually to clarify a point of the design.

This interface is a modification of the architecture that is outlined by S. R. Kleiman in the paper "Vnodes: An Architecture for Multiple File System Types in Sun UNIX", which was published in *Proceedings:* Summer Usenix Technical Conference & Exhibition (June 1986).

Porting note

Some operations that are found on some UNIX systems are not called by the z/OS UNIX logical file system, and are not shown in "Operations summary" on page 14. That section includes some functions that are unique to the logical file system.

Operations summary

PFS operations are grouped by category and by applicability to file or socket PFSs.

File PFS (File System Services)

VFS MOUNT

Mount a file system.

VFS UMOUNT

Unmount a file system.

VFS SYNC

Synchronize a file system (synchronize all files).

VFS STATFS

Get general file system attributes.

VFS VGET

Get a vnode from a file ID (FID).

File PFS (Directory Services)

VN CREATE

Create a regular, FIFO, or character special file.

VN LINK

Create a hard link to a file.

VN LOOKUP

Look up a file name in a directory.

VN_MKDIR

Create a directory.

VN READDR

Read a directory.

VN_REMOVE

Remove a file.

VN_RENAME

Rename a file or directory.

VN_RMDIR

Remove a directory.

VN SYMLINK

Create a symbolic or external link.

File PFS (File Services)

VN ACCESS

Perform access check.

VN_CLOSE

Close a file.

VN_FSYNC

Synchronize a file (save data to disk).

VN OPEN

Open a file.

VN_READLINK

Read a symbolic link file or external link file.

VN_TRUNC

Truncate a file.

Any PFS (File Services)

VFS_BATSEL

Select on a set of files or sockets.

VFS PFSCTL

PFS control.

VFS RECOVERY

Recover from an EOM condition for an operation in progress.

VN_AUDIT

Perform security auditing.

VN_GETATTR

Get attributes for a file.

VN INACTIVE

Inactivate a vnode-inode

VN_IOCTL

Control I/O.

VN_PATHCONF

Return configurable limits.

VN_RECOVERY

Recover from an abend for an operation in progress.

VN_READWRITEV

Read or write with multiple buffers.

VN_RDWR

Read or write.

VN_SELECT

Select on a vnode.

VN_SETATTR

Set attributes of a file.

Sockets PFS (address family or domain services)

VFS GETHOST

Get host ID or name.

VFS NETWORK

Activate a domain.

VFS SOCKET

Create socket or socketpair in a domain.

Sockets PFS (Socket Services)

VN ACCEPT

Accept a connection request.

VN_BIND

Bind a socket.

VN CONNECT

Establish a connection.

VN GETNAME

Get the name of the peer or socket.

VN LISTEN

Get ready to accept connection requests.

VN SETPEER

Set a peer.

VN SHUTDOWN

Shut down a socket.

VN SNDRCF

Send or receive.

VN SOCKOPT

Get or set socket options.

VN SNDTORCVFM

Send to or receive from.

VN SRMSG

Send or receive a message.

The VFS-vnode vector tables returned by the PFS after its initialization contain either the direct or indirect addresses (depending on the value of the pfsi_modind flag in the PFSI) of the routines that implement the operations in the preceding list.

LFS/PFS control block structure

In the LFS/PFS model that is used in z/OS UNIX, each active file system object is represented in the LFS and PFS by its own control blocks or structures. These are called the *vnode* and *inode*, respectively. There is a one-to-one relationship between the LFS's vnode and the PFS's inode. They effectively point to each other across the interface, although neither ever directly refers to the other's fields.

There is only one vnode-inode pair for each data object in the system, no matter how many links there are to the object (for file objects), or how many users may be accessing the object. Users who access a vnode through the LFS must be accessing the same data object through the PFS.

Token_structure: A difference between the z/OS UNIX PFS interface and other implementations is that the vnode is not directly addressable by the PFS during a vnode operation. A Token_structure is presented on all calls as a vnode surrogate.

The Token structure contains the following 8-byte PFS tokens:

• Initialization token, returned from the PFS_Init routine during PFS activation. This token usually contains the address of the PFS anchor block.

- Mount token, returned from the vfs_mount or vfs_network operation for the file system that is related to the current call. This token usually contains the address of the PFS mount block.
- File token, originally passed by the PFS to osi_getvnode when the file's vnode-inode pair was created. This token usually contains the address of the PFS file block—that is, the inode.


For a vnode operation, Token_structure contains all three tokens; for a VFS operation, it contains only the initialization and mount tokens.

See the TOKSTR typedef in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of Token_structure.

Porting note

The file token within Token_structure is a copy of the "private data" area in the vnode. If a PFS expects a vnode structure as an input parameter, but does not refer to any vnode fields other than the PFS's private data pointer, the subfields within the program's vnode structure can be rearranged so that the pointer's offset matches that used in Token_structure. In this way, the PFS code that refers to this field will pick up the correct value when it is recompiled, and does not have to be changed.

Token_structure is transient; it lives only for the duration of a single call.



The control block relationships described so far are illustrated in <u>Figure 3 on page 17</u>. Reading from left to right, in the order they are created:

- The GFS-PFS_anchor pair is created at PFS initialization time and exists as long as the PFS does. Pfsa@ represents the PFS token saved by the LFS.
- The VFS-MNT pair is created during a file system mount or socket network activation, and exists until the file system is unmounted, or forever, respectively. Mnt@ represents the PFS token saved by the LFS from that operation.

• The vnode-inode pair is created during lookup and creation operations, which are explained in "Creating, referring to, and inactivating file vnodes" on page 29 and "Creating, referring to, and closing socket vnodes" on page 44.

Each control block contains the other's token for the file object. The Inod@ token of the vnode is placed in Token_structure as input for a call to the PFS, and an inode's Vnod@ token is returned by the PFS from any call that has a vnode as output.

• Token_structure contains all three PFS tokens, and spans the LFS-PFS interface as the first parameter of each call.

Sharing files

The LFS manages user access to the vnodes. For programs that use the open() or socket() function, the LFS allocates file descriptors and manages sharing between processes and threads within a process. For VFS server programs, the LFS allocates vnode tokens, which behave somewhat like file descriptors. All programs, of any type, share the same file hierarchy.

The PFS is not aware of who is using a file or how it is being shared. To the PFS, there is only a vnode-inode pairing, and all file references come through that structure. In effect, the PFS has only one user: the LFS.

The PFS does not generally maintain any state information that would associate a sequence of calls. Successive calls to the PFS may relate to different end users, so every call is self-contained and does not depend on any information saved by the PFS from a previous call.

Files become shared when different end users open the same file, and when additional references to descriptors are created through the fork() and dup() functions.

Because the LFS maintains reference counts in its structures, it knows how many references to a given vnode are active and how many threads are currently making a call to the PFS with each reference. The PFS does not, therefore, have to be aware of how many users are accessing a given vnode-inode pair. The LFS ensures that all activity has ended and that the vnode-inode pair is no longer in use before it invokes vn_inactive to disassociate the vnode and inode.

LFS-PFS control block integrity

To preserve the vnode-inode relationship, the LFS guarantees the following:

- On every operation, the inode, represented by the PFS's token in Token_structure, has not been inactivated.
- When the PFS is called to break the relationship (via vn_inactive at the time that a vnode is being freed), the LFS ensures that there are no other operations in progress against this vnode and, by extension, against the inode.

There are, in fact, no operations in progress against any file that is in the same mounted file system as the file that is being inactivated. This is so that no other operation may be attempting to find or recreate the inode while it is being deleted.

• After a vn_inactive, the PFS does not receive any additional vn_ calls for that inode until the PFS creates a new vnode-inode binding for this same object as a result of a vn_lookup or vfs_vget call.

The OSI structure

The second parameter of every call from the LFS to the PFS is the address of the operating system interface (OSI) structure. This structure contains information that is used by the OSI_operations and MVS-specific information that needs to be passed between the LFS and the PFS. It is mapped by the OSI typedef in Appendix D, "Interface structures for C language servers and clients," on page 465. The fields are described as follows:

Field

Description

Wait-post fields

token

Wait-post token. Set by osi_wait when it is called to set up for a wait. This token is the input to osi_post when it is called to wake up the current thread.

ecb

Address of an event control block (ECB). Set by osi wait when it is called to set up for a wait. This is the ECB that is used by osi wait when it is called to suspend. A program that cannot call osi post can use this ECB with an MVS cross-memory post to wake up the current thread. However, using the MVS cross-memory post for this ECB can result in a system integrity problem.

ascb

Address of the address space control block (ASCB). Set by osi_wait when it is called to set up for a wait. This ASCB address is used, along with the ECB, for an MVS cross-memory post.

SMF accounting fields

diribc

Directory I/O block count that occurred on this operation.

readibc

Read I/O block count that occurred on this operation.

Write I/O block count that occurred on this operation.

bytesrd

The number of bytes that were read on this operation.

byteswr

The number of bytes that were written on this operation.

Miscellaneous fields

rtokptr

Address of the recovery token area. The recovery token area is set and cleared by the PFS on each operation, to provide for abnormal end and end-of-memory recovery. Refer to "Recovery considerations" on page 23 for details.

workarea

Address of a work area for use by the PFS. This area can be used for the dynamic, or automatic, storage necessary to run the current operation. This can save the PFS the overhead of obtaining and freeing stack storage on every call. The workarea is on a doubleword boundary.

workarealen

Length of the workarea. The workarea length is 3KB. This allows 2KB for routines that call the SAF Chk_Owner_Two_Files routine or the osi_uiomove service, each of which requires that a 2-KB work area be passed. The other SAF security routines require a 1-KB work area.

bia

The current thread's process ID (PID). This is the input to osi_signal if it is called to send a signal to the current thread's process.

pfsid

A PFS identifier that is used with osi_sleep and osi_wakeup.

attr

Address of an output file attribute buffer. Whenever this field is nonzero, the PFS should build and return a standard attribute structure for the file operated on at the end of the current operation. This is the same attribute structure that would be returned by vn_getattr.

The buffer is preset with an attribute structure header that contains the available length of the buffer.

Because this buffer may be the same area as an input attribute structure, it should not be modified until the very end of the current operation.

If the PFS does not return the file's attributes when asked, the LFS invokes vn getattr to get them. This results in poorer performance for files that are supported by this PFS.

fsp

Address of an output File Security Packet (FSP). Whenever this field is nonzero, the PFS should return an fsp structure for the file operated on. This is the same fsp structure that would be returned by vn_getattr.

If the PFS does not return the file's FSP when asked, the LFS builds one. For a description of the FSP, refer to "Security responsibilities and considerations" on page 12.

remount

A flag that indicates that the current operation is running during a remount (that is, during UNMOUNT with the REMOUNT option).

NotSigReg

Indicates that the calling process is not registered for signals and so should not be sent any.

Waiting and posting

OSI_Operations are provided to the PFS to wait for internal events and to post the waiting thread when the event occurs.

Three important reasons for using the OSI wait and post services rather than native MVS WAIT and POST are:

- The OSI services allow signals to interrupt a wait.
- Users are not left hanging if z/OS UNIX or the PFS is stopped.
- The PFS is protected from any system integrity exposures that might result from the cross-memory post operation.

There are two kinds of wait, distinguished by whether signals are enabled during the wait:

- The not signal-enabled waits are used to wait for internal serialization or other activities that are independent of external forces likely to take a long time. These waits should generally not be used with human interactions. Examples are: waiting for data to be read from disk, or waiting for an available output buffer from a pool that is shared by all users.
- The *signal-enabled waits* usually correspond to the blocking situations that are defined by POSIX, and often involve waiting for an end user to do something. Examples are: waiting for data to be read or written by another independent program, such as a socket session, or reading input from a terminal.

Signals should be enabled when the end user may need to break out of an indefinite wait.

When a signal-enabled wait is entered, all serialization that was obtained by the LFS is dropped before the wait and reobtained after it. This means that other operations may intrude on an otherwise exclusive operation. The PFS must take this into account if it uses signal-enabled waits. This does not mean that two exclusive operations will actually be running in the PFS for the same vnode-inode at the same time, but that a second operation may run while the first is blocked. When the first is resumed there may have been state changes made by the second. For writes on stream sockets, the default socket option of exclusive write will prevent the dropping of LFS serialization during single-enabled waits.

The WAITX option also allows LFS serialization to be dropped around the wait, independent of whether signals are enabled. See the <u>"LFS-PFS control block serialization" on page 22</u> for details on LFS serialization.

As a consequence of dropping LFS serialization, it is possible for a file system to be unmounted, with the IMMEDIATE or FORCE operands, while a task is waiting. If this happens, the wait service returns with an OSI_UNMOUNTED return code when it is posted, and the PFS must cancel the rest of the operation and return to the LFS with some care. Because it is expected that vfs_umount will have cleaned up all file-system-related resources, the current operation may have to avoid references to internal file system structures that are freed by vfs_umount.

Waits that are signal-enabled or that request the LFS to drop its serialization cannot be used on some vnode and VFS operations. The implementation notes for those operations state this.

The OSI sleep and wakeup functions are similar to wait and post, with these advantages:

- Osi_sleep
 - Does not require a separate setup call
 - Associates a Resource_id and Pfs_id with the sleeping thread
- · Osi_wakeup
 - Wakes up all threads that match Resource_id and Pfs_id

Implementation details: The PFS implementation for waiting and posting involves the steps described in this section. There are two threads involved: the waiting thread and the posting thread.

- 1. The waiting thread is running on behalf of some VFS or vnode operation when it must wait for an event to occur. It calls osi_wait to set up for the wait, performs internal coordination to schedule the eventual wakeup, and calls osi_wait again to actually suspend the thread.
- 2. The posting thread may be an independent PFS task, or it may be running on behalf of some other user's VFS or vnode operation. It determines that a thread is waiting for the resource it is dealing with, and calls osi_post to wake that thread up.
- 3. When the waiting thread wakes up, it checks the return code from osi_wait and reacts accordingly.

| This table lists the PFS implementation for the waiting thread. | | |
|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------|--|
| Waiting thread | Posting thread | |
| Determine that a wait is necessary. | (None) | |
| osi_wait(OSI_SETUPSIG, OSI, RC) | | |
| Create an internal wait structure that is used by the posting thread to recognize that the waiting thread is waiting. | | |
| Save the osi_token in this structure. | | |
| Chain the wait structure where the posting thread will find it. | | |
| osi_wait(OSI_SUSPEND, OSI, RC) | | |
| (None) | When an event occurs, scan the wait structures to see if anyone is waiting for this event. Unchain and free the wait structure. | |
| | osi_post(saved_token, RC) | |
| | If the return code is not zero, the waiting thread did not get this post and you may need to go on to the next waiting thread. | |
| Select on return code: | (None) | |
| When (OSI_POSTED): proceed with what you were going to do. | | |
| When (OSI_SIGNALRCV): a signal has arrived (when using SETUPSIG rather than SETUP). Back out of this operation and return EINTR. | | |
| Otherwise: an abnormal end or unexpected error occurred. Back out of this operation and return EMVSERR. | | |
| – End | | |

Note:

- 1. This example assumes that the PFS has its own serialization around the chaining and unchaining of the wait structure.
- 2. A variation of the steps in this table would be to unchain and free the wait structure on the waiting thread. In this case, the posting thread marks the structure as "posted" so that another event occurrence cannot result in the same structure's being used again. Recovery is more complicated with this approach, though.
- 3. One also has to consider abnormal ends while waiting—for instance, the user might be canceled. In that case, control does not return to the code after the osi_wait. If the PFS supports vn_recovery, or has an ESTAE or FRR active, it gets control there and the situation can be handled as when a signal is received.
- 4. For abnormal ends and any return code other than OSI_POSTED, additional serialization between the waiting thread and the posting thread is necessary. In these cases the waiting thread is ending before, or even while, the posting thread is trying to wake it up.
 - This is why it is important to save a copy of the osi_token from the waiting thread's OSI, rather than just the address of the waiting thread's OSI. The waiting thread's OSI storage could be gone by the time the posting thread tries to refer to it.
- 5. Another consideration is user address space end-of-memory, which abnormally terminates the waiting thread without activating any ESTAE or FRR. In this case, the LFS uses the OSI recovery token to invoke vfs_recovery, which gives the PFS a chance to clean up.

LFS-PFS control block serialization

The LFS serializes use of the vnode-inode pair for each vnode operation. Writing of file data is done under an exclusive latch. Reading of file data is also done under an exclusive latch, unless shared read support has been indicated by the PFS for the file, and the read is via vn_rdwr or vn_readwritev. Shared read can be indicated in the OSI by the PFS upon return from vn_open, vn_close, vn_rdwr, vn_readwritev, vn_setattr, and vn_trunc.

Other read operations, such as vn_readdir, are done under a shared latch.

In particular, to optimize the performance of pathname resolution, only a shared latch is held on the directory that is involved in a vn_lookup operation.

Recommendation: Read operations that are done under a shared latch may require the PFS to update some structures; for example, to mark the access time of a file for update. The PFS is responsible for any additional serialization that is required to maintain integrity of its structures when functions are called with a shared or an exclusive latch. Often the compare and swap instruction is sufficient for this additional serialization. In order to avoid contention problems, the cross-memory local lock (CML) should not be used.

For the operations that refer to more than one vnode (vn_remove, vn_rmdir, vn_link, and vn_rename), exclusive latches are held on all the vnodes that are involved in the operation. This includes vnodes that are not explicitly passed on the interface, such as the file that is being unlinked on vn_remove.

When the PFS enters a signal-enabled wait, or when the WAITX option has been used to drop serialization around the wait, all vnode and file system latches are released before the wait and re-obtained after it. This means that other operations may be invoked from another thread for a given vnode during an exclusive operation that enters a signal-enabled wait, although there would not be two operations running at the same time, because the blocked thread re-obtains exclusive access when it wakes up.

Note: While any operation is active, the PFS never receives a vn_inactive call for that vnode, even if the latches are released. In cases of vn_open or vn_close processing, the LFS does not allow a close against the last active file descriptor while another thread has any operation in progress against it.

Refer to the individual operations for the level of serialization that is provided for each call.

The serialization that is provided can be changed by the PFS when the osi_getvnode service is called to create a vnode. The PFS can specify that no LFS latching be performed. If no LFS latching is specified,

all discussions in this topic about latches held on vnodes do not apply. Other LFS latches are unaffected; sigwait and waitx should still be used to drop other latches, where necessary.

Recovery considerations

There are several recovery situations that must be handled by the PFS.

PFS task or address space termination

As discussed in "Considerations for stopping a PFS" on page 10, if the PFS_Init task terminates for any reason, the LFS terminates the PFS and restarts it based on the current setting of the restart option byte. If the PFS is started in a colony address space and that address space terminates, the PFS_Init task is also terminated by MVS.

User process and thread termination

Two possible situations are discussed: when the process or thread is between calls to the PFS, and when it is running in the PFS code during a PFS interface operation.

In general, when a user process terminates normally or abnormally, the LFS closes all active file descriptors. There is nothing special about these close operations. The PFS receives a normal vn_close if all file descriptors for an open file reference happen to be closed. If forked children have not closed their inherited file descriptors, the PFS does not receive a vn_close and might never know that the user process terminated.

Individual user requests are run on dubbed tasks, but POSIX semantics assign file resources to the process. Consequently, if a user task terminates between calls to the PFS, and its process does not also terminate, the PFS is not notified.

When a VFS server address space terminates, all of its vnode tokens are released and files that were opened for the server are closed. If a reference count for a vnode goes to zero, that vnode is deactivated. If this happens to remove all references to a vnode, that vnode is inactivated after a delay interval. The PFS does not receive any special notification.

PFS abnormal ends

If the user address space or task terminates while actually running in the PFS code for a PFS interface operation, or if the PFS code itself fails, an MVS abnormal end is generated for each affected task. The MVS system then usually runs the FRR and ESTAE recovery exits.

- If the PFS does not have recovery established, the vn_recovery operation is available to allow the PFS to run its recovery processing as an exit from the LFS's ESTAE. See the description of vn_recovery and vfs_recovery that follows this list.
- If the PFS needs its own special recovery, it must establish an FRR or ESTAE on each entry from the LFS.
- If task-level recovery is bypassed by MVS, the end-of-memory (EOM) resource manager established by z/OS UNIX is run. It ensures that the PFS has a last chance to clean up by calling vfs_recovery. See the next topic on vn_recovery and vfs_recovery.

vn_recovery and vfs_recovery are called to permit a PFS to recover resources when a user request ends abnormally, or when the user's address space enters EOM processing while a request to that PFS is active. This works as follows:

- 1. On every VFS and vnode operation, the LFS makes an 8-byte recovery area available to the PFS. This field is in the PFS's primary address space, not in the user's address space. Its address is in the OSI.
- 2. The PFS should set this field soon after entry, or when it has resources that need protection. The field is used for recovery information, or for the address of a recovery structure that is not in the user's address space.
- 3. The PFS clears the field on exit. The LFS also clears the field as soon as the PFS returns, as it has meaning only during a call, and presumably the area it points to is no longer valid. The PFS should

- clear the field so that it cannot be invoked with bad data if the user is canceled after the PFS has returned, but before the LFS can zero out the field.
- 4. If an abnormal end occurs and the LFS ESTAE routine finds this area to be nonzero, the area is passed to the PFS with a call to vn_recovery and cleared after this call.
 - See "vn_recovery Recover resources after an abend" on page 188 for more details.
- 5. If the EOM resource manager for a user address space finds this area to be nonzero, the area is passed to the PFS with a call to vfs_recovery. This can happen only for an abnormal end that bypasses normal ESTAE processing, or when an address space is canceled during ESTAE processing.
 - See "vfs_recovery Recover resources at end-of-memory" on page 94 for more details.
- 6. The PFS uses the information that is stored in the area during vn_recovery or vfs_recovery to clean up whatever was in progress at the time of the interruption.

The PFS can establish its own MVS dynamic resource managers if it must perform special recovery for a user or z/OS UNIX task or address space termination. This is not recommended, however, because severe performance degradation occurs if these resource managers have to be set up and removed on every operation.


Terminating the associated separate address space of the PFS

If a PFS communicates with a separate address space, that is, one unknown to z/OS UNIX, and waits for replies from that address space, users could be left waiting forever if that address space abnormally terminates while it has outstanding responsibilities to post user threads. Usually, the PFS has to remember all users that are waiting in this situation and post them from a recovery resource manager of the separate address space. This can involve extra serialization and overhead during mainline operations.

If, however, the separate address space registers with the v_reg() function, specifying the PFS that is dependent on it, and uses osi_wait and osi_post, the system remembers this information in a task-related area that does not require additional serialization or overhead during mainline operations. When the separate address space terminates, the system scans through all users looking for those in a potential wait for this address space and posts them. Thus the extra overhead is incurred only when the separate address space terminates.

Dumping LFS data

Information that can be used by the PFS to add LFS data areas to dumps taken by the PFS is passed at initialization. Pfsi_dumpptr contains the address of an array of elements, mapped by BPXYFDUM, as shown in the following figure. These can be used to construct entries in a LISTD-type list passed to SDUMPX.



PFS interface: File PFS protocols

Mounting file systems

Mountable file systems are subsets of the file hierarchy that are added and deleted by mount and unmount. Each has its own root and hierarchical directory structure. One such file system serves as the root of the whole file hierarchy, and mounts are done upon the directories of other mounted file systems.

A mount can be issued from the BPXPRMxx parmlib member that is used with the start of z/OS UNIX, by a user through ISHELL, by the TSO/E MOUNT command, by automount, or by a program by using the mount() function. The latter function is restricted to users with appropriate privileges.

Following is the syntax of a MOUNT statement, showing the parameters that are important to this discussion:

```
MOUNT FILESYSTEM(file_system_name) or DDNAME(ddname)
         TYPE(file_system_type)
MOUNTPOINT(pathname)
MODE(READ | RDWR)
PARM(parameter_string)
          SETUID | NOSETUID
```

where:

- FILESYSTEM specifies a 1-to-44-character name, blank padded, by which this file system is to be known. It must be unique among previously mounted file systems. This is also used by some physical file systems as an MVS data set name.
- DDNAME specifies the ddname on an ALLOCATE that is issued from the OMVS cataloged procedure. This is an alternative to the FILESYSTEM parameter for mounts that are issued from the parmlib member only. The real data set name becomes the mounted file system's name.

- TYPE identifies the PFS that supports this mounted file system. This operand must match the TYPE operand that is used on the FILESYSTYPE statement that defined the PFS.
- MOUNTPOINT specifies the path name of the mount point directory within the file hierarchy where this file system is to be mounted. This item is passed to the PFS, but only for informational purposes.
- MODE specifies the type of access that the issuer of MOUNT has to this file system. READ is specified for read-only access, and RDWR is specified for read/write access.
 - The LFS enforces this parameter to prevent operations such as writing and creating files. The PFS must ensure that it does not update access times for read operations, or otherwise change file systems that are mounted read-only.
- PARM specifies a PFS-defined parameter text string. It can contain any value and be up to 1024 bytes long. The meaning of this text string is defined by the individual PFS, and the text is passed to the PFS for it to interpret and process.
- SETUID | NOSETUID specifies whether the SETUID and SETGID mode bits on executables in this file system are to be respected. This is enforced by z/OS UNIX; the information is passed to the PFS for informational purposes only.

For more information about the MOUNT command, see MOUNT - Logically mount a file system in z/OS UNIX System Services Command Reference.

The parameters are passed to the PFS on the vfs_mount operation. The FILESYSTEM or PARM values are used by the PFS to identify the file system object that is being mounted.

During vfs_mount the PFS is expected to:

- 1. Ready the file system for all later processing.
- 2. Save the device number that was assigned to this file system so that it can be output on vn_getattr for any file within this file system. This number corresponds to the st_dev value of POSIX.
- 3. Set output fields, as appropriate, in the MTAB.
- 4. Create an inode that represents the root of the file system.
- 5. Call osi_getvnode to create a vnode. The returned vnode token is saved in the inode.
- 6. Return the vnode token of the root to the LFS.
- 7. Return an 8-byte token that is saved by the LFS and used on all subsequent VFS and vnode operations for this file system. This token is typically the address of the mount block of the PFS. Its use is optional.

Porting note

This differs from some implementations in that vfs_root is not used to extract the vnode of the root of a just-mounted file system.

The root vnode is never explicitly deactivated. If this file system is unmounted, the vfs_umount operation implies vn_inactive for the root vnode-inode pair.

The PFS cannot use a signal-enabled wait or WAITX during MOUNT.

The LFS does not permit two mounts on a single MVS image with the same file system name. If the PFS identifies its mounted objects through the PARM parameter or by some other means, the PFS must permit or reject attempts to mount the same object more than once. If the mounted file system is on DASD, DASD file sharing must be taken into account. If the file system object is on or is using a resource that is shared by multiple systems, the PFS is responsible for managing or denying shared access.

The ROOT statement defines the system root. It is valid only from the parmlib member, and it has the same parameters as MOUNT, except that a MOUNTPOINT is not specified.

Asynchronous mounting

The PFS may choose to complete mounting the file system asynchronously. Because latches are held by the LFS during execution of vfs_mount, it is desirable to perform the mount asynchronously if it cannot be completed immediately (perhaps because of the need to communicate with another system).

Asynchronous mount processing follows this sequence:

- 1. The vfs_mount service is called by the LFS as part of the mount processing described in "Mounting file systems" on page 25.
 - If the PFS decides to complete the mount asynchronously, it must indicate this to the LFS with the AsynchMount flag in the MTAB before returning to the LFS.
 - If the SynchOnly flag in the MTAB is set on, the mount must be completed synchronously. The PFS must either complete it synchronously or reject it, returning EINVAL.
- 2. When the PFS has completed its asynchronous processing, it calls osi mountstatus to indicate to the LFS that the mount can now be completed.
- 3. The LFS then calls vfs mount a second time, from within the OMVS address space. On the second call, AsynchMount in the MTAB is turned on so that the PFS can identify this as the second mount.

The PFS completes the mount actions described in this topic.

After the PFS returns to the LFS from the first call to vfs mount, the LFS may call any vfs operation. In particular, the PFS must be prepared to process vfs unmount and vfs statfs. If the PFS can determine the file attributes on the first call, it can create and return the root vnode on that call. Otherwise, it defers this until the second call. If a vnode is returned on the first call and also on the second call, it must be the same vnode each time. If the mount operation fails during the asynchronous phase, the PFS calls osi_mountstatus and reports the failure on the second vfs_mount call.

Serialization: During each vfs mount, the PFS has exclusive access to the file system that is being mounted, and no access is allowed until the second vfs mount has completed.

Resolving pathnames

LFS processing

Pathname resolution starts from the user's root or working directory. The LFS looks up the first component of the pathname in that directory. This often yields another directory, and the LFS looks up the second component of the name in this new directory. The LFS looks up each successive component of the name in the directory that was returned from the previous lookup, until the end of the pathname is reached.

When the LFS encounters a directory that is a mount point, it switches to the root directory of the file system that was mounted there. The next lookup is done in the mounted file system's root directory, rather than in the directory that was returned from the previous lookup. This is called *crossing mount* points; it is because of these mount points that pathname resolution has to be done one component at a time.

PFS processing

Resolving pathnames and identifying mount points is a function of the LFS. Except for the individual vn_lookup operations that are invoked, the PFS is not involved.

Unmounting file systems

A user can issue an unmount through ISHELL, the TSO/E UNMOUNT command, automount, or a program that is written to use the unmount() function. This function is restricted to users with appropriate privileges.

Here is the syntax of the TSO/E UNMOUNT command, showing the parameters that are important to this discussion:

```
UNMOUNT FILESYSTEM(file_system_name)
NORMAL | DRAIN | RESET | IMMEDIATE | FORCE | REMOUNT(RDWR | READ | SAMEMODE)
```

where:

- FILESYSTEM specifies the name that was used when the file system was mounted.
- NORMAL | DRAIN | RESET | IMMEDIATE | FORCE | REMOUNT(RDWR | READ) specifies the type of unmount to perform.

LFS processing

- NORMAL. The LFS checks to make sure no user is using any of the files in the file system that is to be unmounted, and passes the request to the PFS via vfs_umount. If files in this file system are being accessed, the LFS rejects the unmount request.
- DRAIN. The LFS checks to make sure that no user is accessing any of the files in the file system that is to be unmounted, and passes the request to the PFS via vfs_umount. If files in this file system are being accessed, the LFS waits until all activity has ceased, and then passes the request to the PFS.
- RESET. The LFS cancels a previous unmount drain request. The file system goes back to the normal
 mounted state.
- IMMEDIATE. The LFS stops further user access to the file system that is being unmounted. Any attempt to access files in this file system receives an error return code. The LFS then passes the request to the PFS via vfs_umount.
 - UNMOUNT with IMMEDIATE can be used to override a previous UNMOUNT DRAIN request for a file system.
- FORCE. The LFS stops further user access to the file system that is being unmounted. Any attempt to access files in this file system receives an error return code. The LFS passes the request to the PFS via vfs umount.
 - UNMOUNT with FORCE can be used to unmount a file system even if I/O errors are being received from the underlying device.
 - An IMMEDIATE unmount request must be issued before a FORCE unmount can be requested.
- REMOUNT. The LFS handles this like an IMMEDIATE unmount followed by a mount. User access is suspended while the operations are in progress. vfs_vget is used to establish the vnode/inode bindings so that the remount is not disruptive to the users.

PFS processing

- 1. The PFS processes requests for UNMOUNT with the NORMAL, IMMEDIATE, and FORCE options as follows:
 - NORMAL. Synchronizes all data buffers to disk (if appropriate for this PFS). This saves all data changes to files in the file system that is being unmounted. If an I/O error occurs during this activity, the unmount request fails.
 - IMMEDIATE. Synchronizes all data buffers to disk (if appropriate for this PFS). If an I/O error occurs during this activity, the unmount request fails.
 - FORCE. Synchronizes all data buffers to disk (if appropriate for this PFS). If an I/O error occurs during this activity, the unmount proceeds anyway and data is lost.

The difference between NORMAL and IMMEDIATE is whether the PFS is likely to find itself with any active inodes other than the one belonging to the root. The difference between IMMEDIATE and FORCE is whether the PFS continues if it encounters an I/O error while trying to synchronize data during the unmount.

- 2. The PFS frees any inodes that are still active, including the root inode, which is never explicitly inactivated.
- 3. The PFS reverses the vfs_mount and returns the file system to unready status.

Serialization: The whole file system is serialized under an exclusive latch at the time vfs_umount is called. No other vnode or VFS operations are running, although some may be in the PFS in a blocked state. See "LFS-PFS control block serialization" on page 22 for more about serialization and blocking.

Creating, referring to, and inactivating file vnodes

The PFS creates vnodes by calling osi getvnode, which is one of the OSI services in the OSIT vector table that is passed to the PFS during its initialization. The output of osi_getvnode is actually an 8-byte vnode token, but for the purposes of this discussion the vnode and the vnode token are the same, and the term vnode is used for both.

The first vnode for a mounted file system is created during vfs_mount processing. At this time, the PFS must create a vnode-inode pair to represent the root of the mounted file system and return the vnode token of the root. The LFS never inactivates this first vnode; it is cleaned up as part of vfs umount processing.

Subsequent vnodes within a mounted file system are created by calls to vn lookup, vn create, vn mkdir, or vfs vget. The first three of these routines are passed a previously obtained directory vnode, represented by a token structure, and the name of a file within that directory to find or create.

The vfs vget operation also generates vnodes directly from the file identifier (FID) of a file within a given file system. See "Exporting files to a VFS server" on page 42.

During vn lookup the PFS must:

- 1. Look up the filename in the directory. If the name is not found, vn lookup fails.
- 2. Find or create an inode that represents the named file. This may involve reading the file's control information from a disk when the file has not been referred to for a while.
- 3. For a new inode or one without a vnode (depending on PFS design), call osi getvnode to create a vnode. The PFS's file token is passed to osi_getvnode to be saved in the vnode, and the returned vnode token is saved by the PFS in the inode.
- 4. Return the vnode token from the inode that represents the named file in the specified directory. The file may itself be another directory.

The creation operations of vn create and vn mkdir follow a similar flow. See "Creating files" on page 30 for more information. They are also invoked with a directory vnode and a name, but in these cases the file itself is created if it does not exist. vn lookup may create an inode, but it does not create the file.

The vnode is generally used in subsequent operations, such as vn_rdwr for a file or vn_lookup and vn_create for a directory. A directory vnode may become a mount point, the current root, or the working directory of POSIX processes. None of these references to the vnode involve any processing by the PFS.

Eventually the vnode falls out of use. After all opens have been closed and all other references to the vnode have been released, the LFS marks the vnode for inactivation. If the vnode is not referred to again for some time after it is marked for inactivation, the LFS invokes vn_inactive, or vfs_inactive if the PFS supports batch inactive and actually frees the vnode. The same functions are performed by vfs_inactive and vn inactive; vfs inactive requires only one call to the PFS to performs these functions for multiple vnodes.

During vn inactive the PFS must:

- 1. Disassociate the inode from the vnode.
- 2. Perform any inode cleanup desired.

If the inode's link count is zero, it must be deleted; otherwise it is just deactivated and can be reactivated with vn lookup.

After the call to vn_inactive, or vfs_inactive for multiple vnodes, LFS frees the vnode, unless the PFS reports a problem via a bad return code from the operation.

Porting note: The PFS does not free the vnode. This is a change from some implementations.

In cases in which a file is repeatedly opened and closed by a single process, the deactivation delay helps to avoid the cost of reconstructing the vnode-inode relationship, and whatever other overhead is incurred by a PFS in reactivating a file. In these cases, file caching is done by the LFS and need not be done by the PFS.

Serialization: The vn_lookup service is called with a shared latch held on the directory being searched. The vn_inactive service is called with an exclusive latch on the whole file system that the object belongs to.

The serialization of vn_inactive ensures that no operations are running that could possibly find, or attempt to create, the inode that is being processed by vn_inactive. This is because an exclusive latch is held on the inode's file system during vn_inactive and the LFS does not allow links across file systems, therefore no parent directory of the object that is being inactivated can be referred to while the PFS is trying to inactivate the object.

The PFS must serialize the creation of its own inodes, to ensure that a single file does not have two or more inodes. This is because the same file object may be looked up or created by more than one process concurrently. The PFS must atomically create the vnode-inode pair and associate the inode with the file object, either through a global latch or with a Compare and Swap algorithm.

To help with a Compare and Swap algorithm, a Return an Unused Vnode option is provided on osi_getvnode so that the Compare and Swap loser can free the vnode it had acquired. The vnode obtained from osi_getvnode does not represent anything until the PFS returns it to the LFS from this or another concurrent operation. The instant that the PFS associates a vnode-inode pair with an object, any vn_lookup for the same object that is running on another process must find this same vnode-inode pair.

Creating files

File hierarchy objects are created with the vn_create, vn_mkdir, and vn_symlink calls.

The interface for all these operations includes:

- The object's parent directory vnode, as a token structure
- · The object's name, as a character string
- · An ATTR structure

Serialization: An exclusive latch is held on the parent directory vnode.

PFS processing

During these operations the PFS must:

- 1. Fail the operation if the object already exists—that is, if the name is already in the directory.
- 2. Otherwise, create the object and add an entry to the parent directory.

A unique nonzero *inode number* that corresponds to the st_ino value of POSIX must be assigned to this object. This value only has to be unique within this file system and at this time. It may be reused after the object is deleted. For additional information about reusing file identifiers, see "Exporting files to a VFS server" on page 42.

A directory object should be initialized by the PFS with the "." and ".." entries. For a root, ".." refers to itself, but for any other directory ".." refers to its parent directory. These entries are not strictly required by POSIX.

- 3. Store at least the file's type, major number, and minor number from the passed ATTR structure with the stored attributes of the file. Whenever osi_getvnode is called, the PFS must construct and pass an ATTR structure, as would be returned by vn_getattr, so that the vnode can be built properly.
- 4. Call SAF to create the FSP. The user credentials and ATTR mode bits from the interface and the FSP of the parent directory are passed to SAF, so that it can construct the FSP and do any auditing that is necessary. See "Security responsibilities and considerations" on page 12.
- 5. Store the FSP with the rest of the attributes of the file.

6. For vn_create and vn_mkdir, build an inode-vnode pair, as it would for a vn_lookup of this object, and return the corresponding vnode token.

The PFS is responsible for link counts, which must be initialized here. The *link count* of an object is the number of directory entries within the file system that point to the object. It is reported to a caller via vn_getattr, and changed by vn_link, vn_remove, vn_rmdir, and vn_rename.

Special consideration must be made for the "." and ".." entries when creating directories. "." implies that a directory's initial link count would be two. ".." implies that a directory's parent directory's link count has to be incremented when the child directory is created and decremented when it is deleted.

vn_link creates a new node in the file hierarchy, but it does not create a new object.

The LFS does not allow the creation of links (vn_link) to a directory.

Deleting files

File hierarchy objects are deleted with the vn_remove, vn_rmdir, and vn_rename calls. The vn_rename function causes the deletion of the new_name file when it exists.

The interface for all these operations includes the object's:

- · Parent directory vnode, as a token structure
- · Name, as a character string
- · PFS file token

Serialization: An exclusive latch is obtained for the parent directory vnode and the object's vnode. For vn_rename, an exclusive latch is held on both parent directories, the old object vnode, and the new object vnode, if it exists.

PFS processing

During these operations the PFS must:

- 1. Call SAF's Check Access service to verify that the caller has write permission to the parent directory. If the sticky bit (S_ISVTX) is on in the parent directory's mode, the PFS must call SAF's Check2Owners service to verify that the caller is allowed to delete or rename the object.
- 2. Remove the directory entry for the named object, and update the Change and Modification times for the directory.
- 3. Decrement the link count in the object whose name was removed.
 - If a directory is being removed, it must be empty except for the "." and ".." entries. The parent's link count is also decremented to account for the ".." entry in the removed directory.
- 4. If the object's link count goes to zero, the object itself is deleted later during vn_inactive, but the deletion is recorded for audit purposes now.
 - If the object is a regular file that is not open, the space used by its data must be released now. If a regular file is still open, its data is deleted on the last vn_close. This behavior is required by POSIX.
 - A POSIX-conforming PFS should set the immeddel flag in the PFSI during initialization to let the LFS know that this requirement is in force. Otherwise, the LFS must issue vn_getattr and vn_trunc during unlink() and close() in order to check the link count and free regular file data.
- 5. While an inode's link count and open count both are zero, the PFS may reject subsequent operations, except for vn_readdir, which would return no entries, and vn_inactive.

Opening and closing files and first references to files

POSIX programs read and write files or read directories within an open-close bracket, whereas VFS servers do this directly from the vnodes that they have looked up or created.

The LFS inserts a single open-close bracket around the operations that are issued by a VFS server against regular files. Operations that affect a file's attributes or read a directory may or may not be preceded by

an open, and a PFS has to be prepared for either case. In particular, a file's size may be changed with the truncate() function, which results in a call to vn_setattr without a preceding vn_open.

The PFS must perform two main functions to support reading and writing, both of which tend to be done only once:

- 1. Physically prepare to do the I/O. This may involve getting buffers ready or using lower-layer protocols for a device or access method.
- 2. Perform access checking.

Note that for performance reasons, the fewest number of access checks possible should be done when a particular end user accesses a particular file.

Serialization: Both vn_open and vn_close are invoked under an exclusive vnode latch.

The PFS is expected to do the following:

- During vn_open:
 - 1. Perform access checks. This must be done here for POSIX users.
 - 2. Prepare for I/O, if necessary.
 - 3. Increment an open counter in the inode for regular files.
- During reading or writing:

Perform access checks, if the Check Access bit is on in the UIO.

- During vn_close:
 - 1. Perform any I/O that is necessary, instead of deferring it to the vn_inactive call. Examples include saving the contents of data buffers to disk and updating access times. This allows I/O to be charged back to the end user, whereas I/O that is done during vn_inactive is charged to z/OS UNIX.
 - 2. Decrement the inode's open counter for regular files. If this goes to zero and the file's link count is zero, the file's data blocks are deleted and their space is reclaimed before the return from vn_close.
 - A PFS that reclaims space on the last vn_close of a deleted file should set the immeddel bit in the PFSI during initialization, for best performance. Otherwise, the LFS issues vn_trunc unnecessarily.
 - 3. Perform the minimum amount of other cleanup. It is better to defer cleanup to vn_inactive processing. Even if no one is still referring to a file, which would not be apparent to the PFS, performance is better if the PFS allows LFS file caching to reuse a closed file with minimal overhead.
- During vn_inactive, or vfs_inactive if the PFS supports batch inactive:

Perform final cleanup for the file or directory inode. This operation runs on a z/OS UNIX system task with the containing file system locked, so the PFS should accomplish this cleanup as quickly as possible. Avoid waits and I/O during this cleanup processing.

If this process is followed, the access credentials of POSIX users are checked only during their open () call. A VFS server that maintains state information requests access checking for the first reference by a particular end user to a particular file, but not for subsequent references. A VFS server without this state knowledge must pay the price of access checks on every reference.

The LFS builds and manages the file descriptors that are used by POSIX programs.

The vn_open-vn_close pair has the following characteristics:

- There may be many vn_opens issued for the same file or directory, and any number may be outstanding at a given time.
- The LFS may share a single vn_open with many users, because of forking or VFS server usage. This sharing is not apparent, nor is it of concern, to the PFS.
- For any vn_open that is seen by the PFS, there is a corresponding vn_close. Because there may be many vn_opens active, getting a vn_close does not mean that the file is in any sense no longer in use. The PFS does not get any indication that a particular vn_close is the "last close", so it needs to maintain an "open counter" to control the deletion of data blocks for removed regular files.

• If the PFS needs to maintain an open context for file operations: an 8-byte Open_token can be returned by the PFS from vn_open and the LFS will pass this token back to the PFS on vnode operations that are invoked from within this open context. See <u>"PFS Open Context and the Open_token" on page 33</u> for more information.

PFS Open Context and the Open_token

An 8-byte Open_token can be returned by the PFS from vn_open and the LFS will pass this token back to the PFS on the following vnode operations when they are invoked from within this open context:

```
Vn_rdwr vn_setattr vn_fsync
Vn_readdir vn_getattr vn_lockctl
Vn_readwritev vn_trunc vn_close
```

The token is passed in the OSI structure in the field osi_opentoken. To activate this support, the PFS sets the pfsi_opentokens flag as part of its output from PFS initialization.

Note that there will not always be an Open Token passed on all of these vnode operations. For example, there are both pathname and file descriptor forms of syscalls that generate vn_getattr or vn_setattr, such as stat()/fstat() and chmod()/fchmod(). Pathname operations are not within an open context. The read/write operations can be invoked by programs using the VFS Server v_op interface. These are not part of an open context. An Open Token is always passed on vn_close and vn_trunc if one was returned on the corresponding vn_open.



Attention: If a file system has a PFS that uses Open_tokens, then that file system cannot be remounted.

Sysplex considerations

If the PFS allows the LFS to share its files in a sysplex Shared File System configuration, the following additional considerations apply to cross-system support:

- If an LFS client system leaves the sysplex, all opens that were done at the LFS owner for users at the lost client are closed. These closes must be correlated by the PFS to the open context to which they belong. The following interface is used to accomplish this:
 - On vn_open from the LFS owner to the PFS, the client's sysid will be passed in the osi_otsysid field. This is a 1-byte value that the PFS saves within its open context.
 - If the LFS client system leaves the sysplex, the LFS makes one call to vn_close for each vnode, and on that call it passes the client's sysid in the osi_otsysid field. No other operations run on this vnode at this time.

The PFS should scan through all its open contexts for this file and perform vn_close processing for each one that has a matching client sysid. The difference between this type of vn_close and a regular vn_close that passes a regular Open_token is that the first seven bytes of this Open_token field are zero. The PFS must insure that its Open_tokens use more than just the last byte of the 8-byte token field.

Note: The PFS is also responsible for cleaning up any remaining open contexts on vn_inact of a vnode. These open contexts can persist for a long period of time. To avoid accumulating an indeterminate number of orphaned open contexts in the PFS, this vn_close is done when an LFS client abnormally terminates.

• If an LFS client system is at an earlier release level where the Open_token is not supported, the client does not store or pass back the Open_token. Consequently, all vnode operations from the LFS owner to the PFS for this client will pass a 0 for the Open_token.

Since the Open_token is not usable in this configuration, a flag, osi_otstateless, is passed to the PFS on vn_open to indicate that this is a "stateless" client, and the PFS does not return an Open_token or expect one to be passed to it on future vnode operations. The osi_otstateless flag is also set for vn closes from this client.

• If an LFS server system leaves the sysplex, current vnode references at the remaining client systems are broken, and current users receive RC=EIO for any future file operations.

To summarize, the following information can be passed to the PFS in the osi_opentoken field:

• For vn_open:

0

A non-sysplex open() or a local open() at the LFS owner.

sysid

A remote LFS client open being done at an LFS owner.

sysid & stateless

An open from an LFS client that does not support open tokens is being done at an LFS owner.

For vn_close:

Open_token

A regular vn_close when the Open_token is available.

sysid

A mass vn_close at an LFS owner for all opens from that sysid.

sysid & stateless

A vn_close from an LFS client that does not support open tokens is being done at an LFS owner.

Reading from and writing to files

The PFS is responsible for actually moving data that is to be read or written, and for implementing the semantics that are required by the standards supported by z/OS UNIX.

See also "Opening and closing files and first references to files" on page 31.

vn_rdwr and vn_readwritev are UIO operations, which means that:

- The UIO structure is part of the interface.
- The UIO contains the address, ALET, storage key, and address space ID of the user's buffer or buffers. It has a read/write flag to distinguish direction. For reads, it contains the length of the user's buffer or buffers. For writes, it contains the number of bytes that are to be written.
- The UIO contains the process file size limit for the file. On a write or writev request it is the responsibility of the PFS to determine when this limit has been reached or exceeded. When a write or writev request is unable to write any data without exceeding the file size limit, the PFS must set the bit in the UIO that indicates that the limit was exceeded, and set the errno to EFBIG. The PFS must also be aware of one other special value for the file size limit: If both UIO.u_fssizelimithw and UIO.u_fssizelimitlw are equal to 0, there is no file size limit set for the process.
- It is the responsibility of the PFS to maintain system integrity while moving data between the address spaces. This means that the Move With Source Key and Move With Destination Key machine instructions or the osi_copyin, osi_copyout, and osi_uiomove services must be used.
- The caller maintains file positioning for the PFS, and the current file cursor is in the UIO for every operation. This indicates the position from which the read or write is to start.

When the O_APPEND flag is set on in the open flags parameter for a write operation, the UIO cursor is ignored by the PFS. Writing begins at the end of the file, as it is known by the PFS at the time of the write.

The UIO cursor may reflect the last read/write operation that was seen by the PFS; it may be from a different instance of vn_open; or it may have been changed through seek operations that were issued by the user and that are not seen by the PFS.

The PFS modifies the UIO cursor to reflect the file position after the operation.

The UIO cursor area is 8 bytes long, to support large files. It is the responsibility of the PFS to handle file offsets greater than 2³¹ or to reject them. The 8-byte cursor is a doubleword signed binary integer.

During vn_rdwr and vn_readwritev the PFS must:

- 1. Do access checking, if the UIO check-access bit is on.
- 2. Move the data. During vn rdwr, if the UIO real-page bit is on, use the DATOFF services of MVS to move the data. The ability to refer to real pages is indicated by the PFS during its initialization. If this cannot be supported, the LFS supplies an intermediate virtual page buffer.
- 3. Synchronize the data, if the UIO sync-on-write bit is on, and turn on the sync-done bit to notify the LFS that it was done. Otherwise, the LFS issues vn_fsync explicitly and the whole operation takes a little longer.
- 4. Ensure that the operation does not write beyond the process file size limit. If the starting position is already at or beyond the limit, the PFS must set the limit-exceeded bit in the UIO and return with EFBIG. This check is done in the PFS because of the O_APPEND case, in which it is much more efficient for the PFS to verify the starting position.
- 5. Return the number of bytes that were transferred.
- 6. Modify the UIO cursor to reflect the file position after the operation.

Serialization: The vn_rdwr and vn_readwritev services are invoked with an exclusive latch for both reads and writes. This is to help the PFS implement the POSIX semantics that require atomic operations and immediate visibility to all other processes.

Reading directories

To optimize directory reading, vn readdir is designed to return as many entries as possible on each call. The C run-time library deblocks the entries for POSIX programs, to provide the sequencing that they expect.

Like vn rdwr and vn readwritev, vn readdir is a UIO operation, but the interpretation of the cursor is different. Cursor technique is described in the next topic. See also "Opening and closing files and first references to files" on page 31.

Serialization

Because the LFS obtains a shared latch for the vn_readdir operation, there may be many users reading the same directory at the same time.

The vn_readdir output buffer is mapped by the DIRENT structure, and its format is defined as follows:

- The buffer contains a variable number of variable-length directory entries. Only full entries are placed in the buffer, up to the buffer size specified, and the number of entries is returned on the interface.
- Each directory entry that is returned in the buffer has the following format:
 - 1. 2-byte Entry_length. This length field includes itself.
 - 2. 2-byte Name_length. This is the length of the following Member_name subfield.
 - 3. Member_name. A character field of length Name_length. This name is not null-terminated.
 - 4. File-system-specific data. If Entry length equals Name length plus 4 bytes, this subfield is not present. Whenever this field is present, it must start with the file's inode number, st_ino, in 4 bytes.

To be XPG-conforming, the PFS must include the file's inode number.

This subfield is not part of POSIX, but it is passed through to all programs to use or ignore as they wish. A non-standards-conforming program may take advantage of additional information provided by a specific PFS that it knows about.

• The entries should be packed together. The length fields are not aligned on any particular boundary.

An example of an entry for the name abc and inode number X'1234' is X'000B 0003 818283 00001234'.

Many applications expect entries for "." and ".." to be returned. This is not strictly required for standards conformance.

Successive calls to vn_readdir for a particular end user must proceed through the directory from the point at which the last one left off. A call does not have to account for activity that occurred "behind" its position in the directory, nor worry about items that may be deleted from "in front" of the current position before it was reached.

The PFS does not directly maintain positioning over successive calls to vn_readdir. The 8-byte UIO cursor is used to specify the positioning within the directory.

Not all directories are implemented as simple linear files that hold an array of name entries. Two continuation techniques may be used, and these must both be supported by a PFS. These techniques are the cursor technique and the index technique.:

• With the cursor technique, the cursor that is returned by the PFS in the UIO contains PFS-specific information that locates the next directory entry. The caller is required to preserve the UIO cursor and the entire output buffer from the last vn_readdir, and present both of these on the next vn_readdir.

The PFS may use the cursor as an offset into a simple linear directory file, ignoring the buffer; or it may use it as an offset into the output buffer of the last entry that was returned. The latter approach can be used by a PFS with a tree-structured directory, where the previous entry name is used as a key to search for the next entry. That is, the last returned name, a 1-to-255-byte-long text string, is really the cursor for the caller's position in the directory. To ensure data integrity, you have to use the Move With Source Key instruction or osi_copyin for the entry header, and then again for the name length.

The cursor technique is used by the [for POSIX-conforming functions.

• With the index technique, the index that is set in the UIO by the caller determines which entry to start reading from. To read through the directory, the caller starts at 1 and maintains the index by adding the number of entries returned to the previous index. The caller may jump around in the directory, and there is no requirement that the next index be related to the last vn_readdir.

This technique views the directory as a one-based array, where the first entry has an index of 1, the second entry has an index of 2, and so on.

The index technique is used by the Network File System and by z/OS XL C/C++ for XPG-conforming functions.

If the PFS wants the LFS to convert directory reads that use index technique into cursor technique, the PFS must set the PfsiRddCursor capability bit during its initialization. A PFS might want to do this if its implementation of cursor technique has better performance than index technique. Whenever possible, the LFS will convert to cursor technique. However, a PFS that sets PfsiRddCursor must support the following three requirements:

- 1. If the PFS receives a vn_readdir with FuioRetCursor flag set by the LFS, the PFS must return the cursor entry for each directory entry in new field DirEntCursor.
- 2. The PFS must return the dotdot entry in index 2.
- 3. If a file tag was passed in the Mtab on the vfs_mount, the PFS must save the file tag, and during readdirplus, must return the file tag in the AttrFileTag of every entry that is not a directory or symbolic link and does not already have a file tag.

The UIO contains both the cursor and index fields that are used with these continuation techniques. The interpretation of these two fields is summarized in the following table.

| Index | Cursor | Action |
|-------|--------|-----------------------------------------|
| 0 | 0 | Start reading from the first entry. |
| 0 | М | Use the cursor value to resume reading. |
| N | 0 | Start reading from entry N. |
| N | М | Start reading from entry N. |

Note: 0=zero; N and M are nonzero values.

A nonzero index overrides the cursor. When both are zero or the index is 1, reading starts from the front of the directory.

The general flow for reading a directory is:

- 1. On the first vn_readdir of a sequence, both fields are zero and the PFS starts at the front of the directory. The normal cursor value of the PFS and the number of entries that were placed in the buffer are returned.
- 2. On the next vn_readdir, the caller specifies whether the cursor technique or index technique is being used to proceed through the directory. The PFS positions itself in the directory based on the technique used, reads more entries, and returns its normal updated cursor value and the number of entries that were placed in the buffer.

The PFS must always return an updated cursor value, even if the index technique is being used. Some callers may switch between techniques, as z/OS XL C/C++ does for the seekdir() function.

- 3. In most cases, the caller continues in this way until the directory is exhausted.
- 4. The application can reset the directory stream to the beginning, but this action is not passed through to the PFS. The next vn_readdir simply has both cursor and index values of zero. The application can also begin reading from any desired entry.

Getting and setting attributes

The PFS is responsible for storing file attributes with its files. POSIX users can read these attributes with such functions as stat(), and set various attributes through such functions as chmod(). A VFS server does the same things with $v_getattr()$ and $v_setattr()$.

All of this is passed through to the PFS when the LFS calls the vn_getattr or vn_setattr service with the ATTR structure (BPXYATTR). The ATTR structure is the file attribute interface between the LFS and the PFS. It contains all the fields of the POSIX STAT structure, plus z/OS UNIX extensions that the PFS may support if it can.

A file's attributes are logically split between the security-related and non-security-related attributes. The security-related attributes are kept in the file security packet, IRRPIFSP, or FSP for short. The FSP is stored with the attributes of the file by the PFS, but it is created and changed only through SAF-defined routines. The FSP contains the file's mode bits, UID, and GID; it may also contain other information that is defined by the security product.

The FSP is the file attribute interface between the PFS and SAF. Refer to <u>"Security responsibilities and considerations"</u> on page 12 and "Creating files" on page 30 for more details on SAF and the FSP.

Serialization: The vn_getattr service is invoked with a shared vnode latch, and the vn_setattr service with an exclusive latch.

vn_getattr and vn_setattr do not require vn_open, although the file may be open for read or write at the time of these calls. Reads and writes would not be in progress at the time of the get or set.

All times in the ATTR structure are specified in POSIX format, which is "Seconds Since the Epoch" (00:00:00 January 1, 1970, Coordinated Universal Time). The PFS may keep time values internally in any format, but they must be in POSIX format across the LFS-PFS interface.

The ATTR structure's header is initialized with the ATTR's length before any get or set call.

The vn_getattr protocol is as follows:

- 1. All ATTR fields that are supported by the PFS are returned.
- 2. To account for different release levels, the PFS should zero out the area and set fields it understands only up to the minimum of the input area's length (from the ATTR length subfield) and the PFS's native ATTR length (the one it was compiled with). The input area's ATTR length subfield should be updated to reflect the amount of data that is returned or zeroed out.

A simple way to do this is to construct a local ATTR structure and copy this, truncating it if necessary, to the input ATTR.

The vn_setattr protocol is as follows:

- 1. More than one attribute may be changed on a single vn_setattr call, and each settable field in the ATTR structure is conditionally and individually set. Bit flags are set by the LFS in an ATTR flag area to indicate which fields from the ATTR structure are being set.
 - In general, if a change bit is on, the PFS updates the corresponding file attribute from the value that is passed in the corresponding ATTR field.
 - Security fields. For each security-related field, such as mode, owner, or audit, that is being changed, there is a corresponding SAF routine that the PFS calls to actually make the changes in the FSP. This allows the security product to do permission checks and security auditing, or other necessary security-related processing.
 - **Time fields**. Two bits are defined for each time field. The first bit indicates that a change is to be made, and the second bit indicates whether to use the corresponding ATTR time field's value, or if the current time of day is to be generated and stored by the PFS.

Non-security fields may still have access control defined for them. This means that SAF is called to see if the user has permission to make the change, but the PFS does the change.

- 2. The PFS should ensure that either all changes or no changes are permanently recorded for a single vn_setattr call.
- 3. To account for different release levels, the PFS must not refer to fields beyond the input ATTR's length, as specified in its length subfield.

Note: To optimize performance for VFS servers, several of the vnode operations, such as vn_lookup and vn_rdwr, pass an ATTR structure pointer in the OSI structure and expect an implicit vn_getattr to be performed at the end of the current operation. If the PFS cannot support this, the LFS calls vn_getattr after the operation in question. This flow has poorer performance when accessing files owned by this PFS.

Supporting Share Reservations in a PFS

A file is opened with Share Reservations in order to prevent other programs from later opening the file in ways that conflict with these reservations. Share Reservations are expressed in terms of denying read or write access by using two bits in the open_flags that are passed on vn_open: $0_DENYRD=0\times00020000$ and $0_DENYWRT=0\times00010000$.

If a file is opened with an access intent of read or write that conflicts with an already established Share Reservation, the open is rejected with EBUSY. Conversely, if a file is already opened for an access intent that another open is trying to deny, the later open fails with EBUSY.

See "v_open (BPX1VOP, BPX4VOP) — Open or create a file" on page 301 for information about Share Reservations from the NFS Server's point of view.

A PFS indicates that it supports Share Reservations by setting the pfsi_sharessupported flag as part of its output from PFS initialization. The access and deny modes are always passed to the PFS on vn_open, but when the PFS supports Share Reservations the LFS does not monitor or enforce the reservations.

Types of open operations

This topic contains background information about the various types of open operations.

- The traditional POSIX open() function requests read or write access to a file, and files are shared among all users who independently open them.
- An open/close protocol was added to the NFS architecture in Version 4. The z/OS V4 NFS Server invokes v_open() in support of V4 clients. v_open() can be used to place Share Reservations on a file for Windows work stations.

The distinctions between open() and V4 v_open() are not significant to the PFS. Both are passed on vn_open as type VNOPEN_FILE. When close() or v_close() is issued the resulting vn_close will also be of this type.

• Older V3 clients can use the Network Lock Manager Share function to place Share Reservations on files, but since NLM and NFS are not necessarily integrated on a server the V3 NLM Shares do not inhibit reading and writing. These NLM Shares are advisory locks and only contend with each other at the time

they are obtained. V4 Shares are mandatory locks and they also inhibit any conflicting reading or writing by V3 clients. Because of this difference in enforcement for reads and writes that occur outside of an open context, these NLM Shares are passed to the PFS on vn_open as type VNOPEN_NLM_SHR. When the NLM Unshare is specified a corresponding vn_close is passed to the PFS with this same type.

• V4 NFS clients can reduce the number of flows to a server by sharing opens on that server among its local users. When a file is subsequently opened for more access or with more reservations than the client has so far established on the server, the client must upgrade its open context on the server. Conversely, when the file is closed locally on the client and it no longer needs all of the access rights or reservations it has on the server, it can downgrade its open context on server. These upgrades appear in the PFS as a vn_open and the downgrades appear as a vn_close of the same types as described previously.

These upgrades and downgrades are not necessarily paired. Consequently, when Shares are supported by the PFS there may not be the same number of vn_closes as vn_opens for a given file. See "Close processing" on page 40 for more information. An upgrade of the deny modes appears in the PFS as a vn_open with no access flags turned on, and there should be no SAF Check Access security call made when there is no new access requested.

• The LFS issues Internal Opens in support of file servers such as NFS V3. These servers obtain Vnode Tokens for the files they reference, usually through v_lookup or v_vget, and then proceed to read and write to these files without ever explicitly opening them. The purpose of the Internal Open is to keep the PFS's open counter greater than 0 while the server has an active Vnode Token, so that if the file is removed by the server or by a local user, the file data will not be discarded until after the server has finished and called v_rel(). These Internal Opens do not effect or interact with Share Reservations in any way and so are passed to the PFS as type VNOPEN_INTERNAL. The later reads and writes from this server are outside of an open context and are checked against the corresponding Share Reservations that may inhibit that action. When the Vnode Token is released with v_rel the LFS does an internal close of this same type.

Open processing

The type of open that is being done by vn_open is passed in the ts_sysd1 field. This open can be one of the following:

VNOPEN_FILE

A traditional POSIX open() or NFS V4 v_open(). These actions request access rights and optionally can place share reservations on the file. They contend with any other opens that may already be established for this file. The call can fail due to an existing reservation that denies the access requested, or the call can fail if it attempts to deny an access that is already established. Both conflicts cause the call to be rejected with RC=EBUSY. If the PFS does not support Share Reservations, the LFS uses Rsn=JRShrConflict for the former and Rsn=JRAccessConflict for the later.

This call can be blocking or nonblocking, but the LFS does not allow blocking with share reservations requested. That is, if either O_DENYRD or O_DENYWRT are set then O_NONBLOCK must also be set. When the call is blocking it should wait for any conflicting Share Reservations to be removed. When nonblocking, it should be rejected immediately with RC=EBUSY if there is a conflict. The Share reservations established here inhibit any conflicting reading or writing that occur outside of an open context. See "Considerations for reading and writing and SetAttr" on page 40 for more information.

VNOPEN NLM SHR

This type of open is for a Network Lock Manager Share Reservation. It is not an open in the traditional sense, although there is really no difference to the PFS. SAF/RACF is called for a normal access check . These calls are always nonblocking.

The corresponding vn_close also indicates that it is for a VNOPEN_NLM_SHR, so that the appropriate deny counters can be decremented.

NLM opens contend with all other previous opens, but the reservations established do not inhibit subsequent reads and writes from an NFS V3 client. An NFS client does not have an open context and its reads and writes are allowed to violate NLM Share Reservations, but they are rejected if they

conflict with a V4 Share Reservation. There are two requirements to correctly enforce Reservations with respect to NFS V3 reads and writes:

- The PFS must maintain two pairs of deny counters. These are for (V4_DenyWrt,V4_DenyRd) and (NLM_DenyWrt,NLM_DenyRd).
- For a vn_rdwr operation the LFS must pass the type of client that is doing the read or write. This is done in terms of the type of checking that should be performed by the PFS. See "Considerations for reading and writing and SetAttr" on page 40 for more information.

VNOPEN_INTERNAL

An internal open issued by the LFS. This is for read and write access, or for read-only access if the file system is Read-only. This operation never denies any accesses. This open should bypass all Share checking, and it does not inhibit later Share Reservations. There may be more than one internal vn_open issued for a file. For each internal vn_open there will be a corresponding internal vn_close. These internal opens are done with system credentials.

Close processing

The open_flags passed on vn_close indicate which access and deny counters need to be decremented. These counters can include flags that originated on more than one vn_open. The type of open that is being closed is indicated in the ts_sysd1 field, as follows:

VNOPEN_FILE

Used for POSIX close() and NFS V4 v_close().

VNOPEN_NLM_SHR

Used for a Network Lock Manager UnShare.

VNOPEN_INTERNAL

Used for an internal LFS close that bypasses all Share processing

When Share Reservations are released and a deny counter goes to zero there can be blocked vn_opens that need to be posted.

The total count of vn_opens for any given file can not equal the total count of vn_closes for that file, due to the upgrades and downgrades of a client's open context. For example, the following sequences are possible:

```
vn_open(Read), vn_open(Write), vn_close(Read, Write)
vn_open(Read), vn_open(DenyWrt), vn_close(DenyWrt), vn_open(Write), vn_close(Read,Write)
vn_open(Read,Write), vn_open(Read), vn_close(Write), vn_close(Read), vn_close(Read)
```

The sum of all vn_closes for any one type of access or reservation will equal the sum of all vn_opens that requested that type of access or reservation. For example, in the third sequence, the sum of all vn_opens that specified O_RDONLY equal the sum of all vn_closes with O_RDONLY on.

Considerations for deleting files

When the target of vn_remove – or an old file from a vn_rename – has a Share Reservation on it that denies opening the file for write, the attempt to delete the file is rejected with RC=EBUSY.

When the last link to a file is removed the file's data should not be discarded until the sum of all the (Opens_for_read + Opens_for_write + Internal_Opens) is zero.

Considerations for reading and writing and SetAttr

There are special considerations for vn_rdwr and vn_setattr(FileSizeChange) for clients who perform these operations outside of an open context. From a V3 client these operations are allowed to violate NLM Share Reservations but not V4 reservations. For V4 clients there are several variations in the architecture that include operating outside of an open context and overriding Share Reservations. See "v_rdwr (BPX1VRW, BPX4VRW) — Read from and write to a file " on page 311 for more information about these variations between the clients and the server.

Note that vn_trunc is only called for the ftrunc() function so it always operates within an open context, and the LFS checks that the open was for write. Consequently, there is no share checking required in vn_trunc.

From the PFS's point of view the following types of share checking can be requested on vn_rdwr or vn_setattr(FileSizeChange). They are passed in the ts_sysd1 field of the call:

VNSHRCHK NONE

A read/write/setattr that is within an open context and therefore should be permitted.

VNSHRCHK ADV

A check only against V4 reservations.

VNSHRCHK_MAND

A check against all reservations (V4 and NLM).

When a check is made it corresponds to the action being requested: read versus DenyRd, and write or file size change versus. DenyWrt. When there is a conflict the vn_rdwr or vn_setattr call is rejected with RC=EBUSY.

For a detailed description of the NFS V4 architecture refer to RFC 3530, which can be found at <u>The</u> Internet Engineering Task Force (IETF) (www.ietf.org).

Other considerations

With a read-only file system, Share Reservations should be accepted but do not have to be enforced.

A vfs umount for remount may be rejected if any file within that file system has any share reservations.

Share contention in a sysplex generally has to be resolved at some central file system owner, which leads to the following restrictions when there are various release levels in the sysplex:

- Share reservations should be rejected with RC=EOPNOTSUPP if the file system's owner does not support them.
- Once share reservations have been established, the file system cannot be moved to an owner that does not support reservations. When the file system is moved to an owner that does support reservations, the established reservations should move along with the file system ownership.
- If the owning system crashes and the file system is taken over by a system that does support reservations, those reservations that have been established should be reestablished for the new owner.

If the new owner does not support share reservations, the reservations are lost and the opens that are using them have to be invalidated. This can be done by calling osi_getvnode(OSI_STALEOPENS) for each vnode that has share reservations. Once the opens are marked stale, subsequent attempts to use them are rejected by the LFS with RC=EIO and RSN=JrShrsLost.

File tags

The file tag is a file attribute that identifies the character set of the text data within a file.

It is not expected that the PFS will use file tags, but if the PFS supports its own conversion capability, it may have to take file tags into consideration now that the LFS is also doing conversions. For example, NFS Client will fail vfs_mount if both the LFS TAG() parameter and the NFS PARM(XLATE()) parameter are specified.

The following headers are used by both the PFS interface and the VFS Server functions v_getattr() and v setattr().

Using daemon tasks within a PFS

If the PFS needs to invoke functions that cannot be performed in a cross-memory environment, it must make use of other tasks to perform these functions. To use these daemon tasks the PFS must, at a minimum:

- 1. Attach these tasks and
- 2. Communicate with them

Several services are provided to make this easier. They are:

- · osi kmsgctl
- · osi_kmsgget
- · osi_kmsgrcv
- · osi_kmsgsnd
- · osi_thread

The osi_thread service is available only to PFSs that are running in a colony address space.

The PFS can attach these tasks via the MVS ATTACH service from its initialization task, or it can use the osi_thread service. The osi_thread service attaches a task in the PFS's address space that runs in primary mode. The initial module on this task is a C Main function that fetches the module that is specified by the invoker using the C/C++ fetch() function, and then calls it. When called on this task, or thread, the specified module can perform a single function and return; or it can service work requests by the PFS until the PFS terminates. In the latter case, the osi_thread service is used to attach a PFS daemon task.

When attached, these tasks need to communicate with the PFS functions that are invoked by the LFS. One way these processes can communicate is through message queue functions that are provided by the osi_kmsg services in the previous list. For descriptions of these services, see Chapter 6, "OSI services," on page 355.

Exporting files to a VFS server

For a VFS server to access files that are owned by a PFS on the same system, the following support is necessary in the PFS:

- Its file objects must be visible in the file hierarchy. This is the same as saying that the PFS supports vfs mount and vn lookup.
- Each file must have a unique and persistent file identifier (FID). This is 8 bytes long, and is usually made up from the file's 4-byte st_ino value and a 4-byte uniquifier. The uniquifier must be constructed by the PFS if it reuses file st_ino values, so that the full 8-byte FID is unique and never reused.

The FID must persist over PFS restarts and even full-system IPLs. A VFS server's client may access a file days after it has obtained the FID.

- The FID must be returned in all ATTR structures that are returned.
- The PFS must be able to look up a file by its FID reasonably efficiently. The vfs_vget operation must be supported to convert a FID value to a vnode-inode pairing. This is similar to vn_lookup, except that a FID within a file system is looked up, rather than a name within a directory.
- Access checking on read/write must be supported, as discussed in "Opening and closing files and first references to files" on page 31.
- vn_readdir must not require vn_open and vn_close.
- For better performance, the PFS should support:
 - Implicit vn getattr on any operation that passes a nonzero ATTR pointer in the OSI structure.
 - Sync-on-write, when that bit is on in the UIO. (This eliminates the need for a separate call to fsync.)

Real-page support with DATOFF moves for memory-mapped files.

Porting note

The vn fid operation is not used to convert a vnode to a FID. The combination of returning the FID in the ATTR structure and implicit vn getattr on many operations is much faster for VFS servers.

When a VFS server's client mounts part of the file hierarchy, it really only obtains tokens to a directory and the directory's file system. It is not a mount like that performed for the MOUNT command, and the PFS does not receive a vfs mount or any indication that it occurred. The first call from a VFS server that the PFS would see is likely to be a vfs vget, vn lookup, or vn readdir.

Select

A PFS should consider supporting the vn_select operation if data for a read-type operation may arrive asynchronously when no read has been issued; or if buffers for a write-type operation are rationed and are therefore sometimes not immediately available (require a WAIT).

The LFS answers READY for any select status requested from a PFS that does not support vn_select.

See "Select/poll processing" on page 45 for more details.

PFS interface: Socket PFS protocols

Activating a domain

NETWORK statements in the BPXPRMxx parmlib member that is used to start z/OS UNIX assign socket domains, or address families, to the socket PFSs.

The NETWORK syntax is:

```
NETWORK TYPE(file_system_type)

DOMAINNAME(domain_name)

DOMAINNUMBE(domain_number)
               MAXSOCKETS(number)
```

where:

- TYPE identifies the PFS that supports this domain. This operand must match the TYPE operand that is used on the FILESYSTYPE statement that defined the PFS.
- DOMAINNAME specifies the domain, or address family, name. The AF_UNIX and AF_INET domains are supported by IBM-supplied socket PFSs.
- DOMAINNUMBER specifies the numeric value of the domain that is passed by programs that call socket(). The values that are supported for this field are defined in socket.h.
- MAXSOCKETS specifies the maximum number of currently active sockets that are to be supported.

These parameters are passed to the PFS on the vfs_network operation.

During vfs_network the PFS is expected to:

- 1. Activate support for this domain.
- 2. Optionally return an 8-byte token that is saved by the LFS and used on all subsequent VFS and vnode operations. This token is typically the address of the PFS's domain block.

When a user calls socket(), the first parameter is a domain number. The LFS routes this request to the appropriate PFS with a call to vfs_socket.

The NETWORK statement is analogous to the MOUNT statement that is used by file-oriented PFSs.

For more information about the BPXPRMxx parmlib member, see BPXPRMxx (z/OS UNIX System Services parameters) in z/OS MVS Initialization and Tuning Reference. For a description of the NETWORK statement, see NETWORK statement of BPXPRMxx in z/OS UNIX System Services Planning.

Creating, referring to, and closing socket vnodes

The PFS creates vnodes by calling osi_getvnode, which is one of the OSI services in the OSIT vector table that is passed to the PFS during its initialization.

Sockets are created by user calls to socket() and accept(). The corresponding vnodes are created during vfs_socket and vn_accept, respectively. vfs_socket creates a socket, and if that socket is connected, a stream session is established to another socket that is created by vn_accept. socketpair() generates a special case of the vfs_socket call that creates two connected sockets. This is similar to the pipe() function.

During vfs_socket and vn_accept, the PFS is expected to:

- 1. Set up its socket support and build an inode.
- 2. Call osi_getvnode to create a vnode.
- 3. Return the vnode token that was returned by osi_getvnode.

The LFS builds the file descriptor, which is also called a socket descriptor, that is the output of the socket() and accept() functions.

Sockets do not have a name in the file hierarchy; consequently, they cannot be opened by POSIX users or exported by VFS servers.

The user program makes socket calls on the file descriptor, and the calling parameters are generally passed straight through to the PFS by the LFS.

Socket descriptors can be inherited over fork(), and they can be duplicated with dup(). The LFS manages this sharing; the PFS is not aware of how many active references to a socket there are.

Eventually the program calls close() for its socket descriptors. After all active references to the socket vnode-inode are closed, the LFS calls vn_close. Because sockets cannot be opened like files, the PFS receives only a single vn_close for any socket.

During vn close, the PFS severs the user's socket session.

After the vn_close, the LFS calls vn_inactive for the final cleanup of the vnode-inode relationship.

During vn_inactive, the PFS is expected to:

- 1. Disassociate the inode from the vnode.
- 2. Perform any inode cleanup that is desired.

After the call to vn_inactive, the LFS frees the vnode unless the PFS reports a problem through a bad return code.

Porting note

Because sockets cannot be reused after vn_close, the PFS can combine its close and inactive processing in vn_close, and choose not to support vn_inactive. Nonsupport is not considered a failure of vn_inactive.

Reading and writing

The five variations on read/write—vn_rdwr, vn_readwritev, vn_sndrcv, vn_sndtorcvfm, and vn_srmsg—are all UIO operations, and are described in "Reading from and writing to files" on page 34.

The UIO contains additional fields for the socket-specific buffers that are used on some of these calls.

During these read/write calls, the PFS must:

- 1. Move the data using Move With Source Key or Move With Destination Key, as appropriate. The osi_copyin and osi_copyout services can be used to move data areas between the user and kernel address spaces. The osi_uiomove service can be used to move data areas based on the UIO structure for vn_rdwr and vn_readwritev.
- 2. Return the number of bytes that were transferred.

Serialization: All five operations are called with an exclusive latch for writing. All five operations are called with an exclusive latch for reading, with the exception of vn_rdwr and vn_readwritev, which may be called with a shared latch for reading if the PFS has specified shared read support for the file being read. The LFS defaults to exclusive latching for both reading and writing, to help the PFS implement the POSIX semantics of atomic operations and immediate visibility to all other processes. This latching can be turned off if it is not needed by the PFS. Refer to "LFS-PFS control block serialization" on page 22 for more details.

Getting and setting attributes

Socket descriptors are eligible for fstat(), so sockets can be called for vn getattr. The PFS should consider supporting this operation and returning some information in the ATTR structure. At a minimum, you could return: the file type, permission bits of 777, the current time for the time values, the devno as passed by vfs network, and an inode number for the socket that is unique for this socket at this point in time.

Note: Some programs use fdopen() with a socket descriptor, and this function does an fstat() under the

Generally, a program cannot set any attributes of a socket, so the PFS does not have to support the vn_setattr operation.

Select/poll processing

An application program calls select() or poll() with a list of file descriptors and the events that are to be waited for. The file descriptors can represent files, sockets, pipes, or terminals; they are all referred to as "files" in this discussion. The events that can be waited for are: ready for reading, ready for writing, and exceptional conditions. Because a poll() is converted into a select() call by the time the request reaches the PFS, for this discussion only select will be discussed.

There are two operations that can be called to handle the select request; vfs batsel and vn select. The vfs_batsel operation is useful for a performance boost; it does not have to be supported. If a PFS supports the vfs_batsel operation, a single call is made to that PFS with an array of information about its files. If a single descriptor is requested, or the PFS does not support vfs_batsel, the vn_select operation is called for the owning PFS for each file specified.

The LFS converts the file descriptors into vnodes. If the user has multiple file descriptors in the list that refer to the same file, such as after a dup (), or if a particular PFS owns more than one file that is present in the list, it receives a separate call for each file if the vfs_batsel operation is not supported. Otherwise, a single call is made with multiple array entries for the same file. While one user is waiting in select() for some files, another user may issue select() for some of the same files. The LFS manages the lists and the associations of users to requests. The PFS should just treat each vn_select or vfs_batsel array entry as a completely separate and independent action against the file, and be prepared for more than one select() to be active at a time for a file.

Select processing consists of two phases, called Query and Cancel, which are identified by a parameter on the select call. Each file may be called for both phases or just for Cancel. When a user specifies a timeout value of 0, the LFS skips the Query phase and goes right into the Cancel phase.

The LFS passes a select token to the PFS with each vn_select or vfs_batsel array element call. The select token uniquely identifies a request for both phases, and thus can be used by the PFS to correlate Queries and Cancels. This token is unique to this single instance of vn_select(Query) being called, and is not used again until after the corresponding call to vn_select(Cancel).

There is also a PFS_work_token available on vn_select and in each array element of vfs_batsel that can be set by the PFS to correlate Queries and Cancels.

Note: Only vn_select is mentioned in this discussion. The only difference between vn_select and vfs_batsel is that similar processing must occur within a loop for the array elements of the vfs_batsel request.

Query phase

In the Query phase of select processing, the LFS queries the PFSs by calling vn_select(Query) with the vnode that is represented by each file descriptor.

During vn_select(Query), the PFS must:

- 1. Return status information without taking any other action, if any requested event is immediately available.
- 2. Otherwise, save the select token (16 bytes) and the Select_Options in a select-pending structure that is chained from its inode.

The Query phase ends as soon as any PFS reports immediate status. The remaining PFSs are contacted during the Cancel phase, so the user can receive the most information available at this time.

The LFS may omit recalling the PFS for the Cancel phase if:

- 1. The PFS does not set any of the PFS_work_tokens, and
- 2. For vfs_batsel, status is returned in the array entries.

If the PFS is dependent on being recalled for Cancel whenever it has been recalled for Query, it must set a PFS_work_token to some nonzero value. For optimal performance, the PFS should not have this dependence when it is able to report immediate status to the Query request.

If no PFS reports immediate status, the LFS waits for one of the PFSs to call osi_selpost, or for the time limit to expire.

Event occurrence: Eventually an event occurs asynchronously within a PFS for a given file. The PFS process or thread that handles these events notices that the file has selects pending for it. Examples of such events are: data arriving for a read, buffers freeing up for a write, or sessions terminating for an exceptional condition.

When such an event occurs, the PFS is expected to do the following:

1. Scan through the select-pending structures that are chained from the inode for those that are waiting for this type of status.

The PFS must serialize this with its own processing for Cancel; see "Cancel phase" on page 46.

- 2. For each pending select that is satisfied:
 - a. The PFS removes the select-pending structure, or marks it as "posted". The PFS must ensure that it never calls osi_selpost more than once for a particular vn_select(Query) request or select token.
 - b. The osi selpost routine is called with the select token saved during the Query phase.

The osi_selpost routine uses the select token to find the waiting process and thread and post it.

Note: The identity of the event that occurred is not passed to osi_selpost. This information is picked up by the LFS during the Cancel phase.

Cancel phase

The LFS goes through the Cancel phase by invoking vn_select(Cancel) for each file descriptor when:

- One of the PFS events has occurred and osi_selpost is called
- · Any PFS reported status during the Query phase
- The timeout value expires

Note that if a PFS reported status during the Query phase, the loop that was doing the queries is terminated; therefore, a cancel request may be received by a PFS even though no query was done.

During vn_select(Cancel), the PFS is expected to do the following:

1. Scan the pending-select structures that are chained from the inode for one with a matching select token. If one is found, it is removed so that osi_selpost is not invoked for that select token after the PFS returns from this vn_select(Cancel) call.

Note: It is the PFS's responsibility to serialize the cancellation of a pending select with its asynchronous event handler, which may be attempting to call osi_selpost. It is critical that osi_selpost never be called for a particular select token after the PFS returns to the LFS from a call to vn select(Cancel) for that same select token.

It is not unusual for the PFS not to find a pending select to be canceled, as it could have been already removed by the event handler, or this PFS may not have been queried in the first place.

2. After the PFS ensures that the select is no longer pending, it checks for the requested status and returns this information to the LFS.

The LFS collects status from all of the files and reports it back to the program that called select().

Note: Although it is rare in practice, there is nothing to stop a user from selecting and reading on the same socket from two different processes or threads. Consequently, it is technically possible that an event that is reported by select may no longer be true when the selecting program finally acts on the information. A selecting program may not act on the information, but pass it off to another process to handle. Therefore, reporting back on select does not reserve the data or buffers for the caller; it merely reports the status of the file at that time.

Common INET sockets

Common INET sockets PFS structure


The Common INET layer (CINET) is inserted between the LFS and a sockets PFS to allow multiple AF_INET transports to be used by a single application socket. A sockets PFS can be attached directly to the LFS when it is the only AF_INET transport on the system, or attached through the CINET layer when it is one of several. To be attached to CINET, the PFS must implement the "master socket" and support several additional ioctl command types, as described in this topic. The interface to the PFS is the same in both cases. Once the additional support for CINET is written, the PFS does not have to distinguish between the two cases.

When Common INET is used, the sockets file system is initialized by the SUBFILESYSTYPE statement in the parmlib member, instead of by the FILESYSTYPE statement, which initializes the Common INET support. The operands of the SUBFILESYSTYPE statement are similar to those for the FILESYSTYPE statement.

The general model is that of a sockets PFS that is split into two pieces: a PFS layer that runs in the kernel address space, and additional programming that runs in a separate address space and that actually controls the transport interface to the network. For the purposes of this discussion, the PFS layer piece is called the *transport driver* (or TD) and the separate address space piece is called the *transport provider* (or TP).

The transport driver is started by z/OS UNIX, as a PFS, and communicates with the transport provider through its own internal mechanisms, usually by a space switching program call (PC).

The transport provider (for instance, a TCP/IP stack) is started independently, and communicates with the transport driver through the master socket.



A TD/TP that is structured entirely within the PFS in the kernel address space still has to establish the master socket and pass the minimum ioctl commands to run under the CINET layer.

The master socket

The master socket is used to communicate between the transport provider and both the Common INET layer and its own transport driver. It is used mostly for initialization and, potentially, for later dynamic route updates. If the TP ever has to initiate a message to the TD (for instance, due to an asynchronous configuration update), it can do so over the master socket.

• The master socket is created by the transport provider with the standard socket() C function or the BPX1SOC/BPX4SOC callable service, by specifying AF_INET for the **Domain** and -1 for the **Protocol** parameters.

This builds a session from the TP to the CINET layer.

The TP address space must be defined to RACF as a z/OS UNIX user with a UID of 0.

• The only functions that are used with the master socket are ioctl and close.

Most of the ioctl command codes that are used with z/OS UNIX are nonstandard, so these ioctls must be issued with the w_i octl() C function or the BPX1IOC/BPX4IOC callable service.

The socket can be closed with either close() or BPX1CL0/BPX4CL0.

• The first thing that flows on the master socket must be an SIOCSETRTTD ioctl to connect the socket to a specific transport driver. This ioctl is also known as the left bookend, signifying the start of TD-TP initialization. On the call, the Argument_length should be specified as 8, and Argument should refer to

an 8-byte area in which the TD name is filled in. For more information about the interface to ioctl, refer to "vn_ioctl — I/O control" on page 149.

The vfs_socket request is issued at this point to the specified TD, which builds the normal socket support between the LFS and PFS, but does not propagate this session to the TP.

The SIOCSETRTTD command is then passed on to the TD with an ioctl call.

Note: The TP must know the name of its own TD in order to select it with SIOCSETRTTD. This name was specified with the NAME parameter of the SUBFILESYSTYPE statement that started the TD, and is passed to the TD when it is initialized. There are several ways to make this name known to the TP. It could be a product-specified constant value; the value could be configured into the TP through its externals; the TD could pass the name to the TP if it starts the PC session first; or the TD could store the name with the MVS Named Token Services, where the TP would retrieve it.

• Subsequent ioctls are then sent from the TP to the TD to perform product-specific initialization, as necessary. For instance, these could drive the TD to establish the PC session to the TP. These ioctl calls can specify application-defined commands, or use existing command definitions. The ioctl command values that are used must not conflict with any of the commands that are discussed here, or any that are used by the prerouter.

These commands pass through z/OS UNIX without any interpretation.

Note: If the PFS is designed to run directly attached to the LFS, it has already solved the problems of initialization between the TD and TP. This does not have to change when it is attached through CINET. Only the first and last ioctl commands discussed here are required on the master socket.

• After any product-specific initialization is finished, an IOCC#TCCE loctl command is sent by the TP to notify CINET that this file system is ready for business. This loctl command is also known as the right bookend, signifying the end of TD-TP initialization. For this command, no other specific data is required, so the Argument_length can be zero.

This command is also passed on to the TD.

At this time, the transport is considered to be active. The prerouter gathers configuration information from the transport and applications that had used the SO_EioIfNewTP socket option receive notification that a new transport is available for use. This notification is performed by failing any socket accept or receive type calls with a return code of EIO, after which the application closes that socket and opens a new socket to pick up the new transport.

If the transport is not yet ready to accept new socket requests, the notification phase can be delayed. If the argument length for IOCC#TCCE is four bytes and the argument contains a value of one, this signifies a delay and the SO_EioIfNewTP notification phase is skipped. The transport must later send another IOCC#TCCE ioctl command with a value of two to perform just the notification phase.

• At this point the prerouter will start its conversation with the TD-TP on a separate socket session, see "Common INET prerouting function" on page 50.

Ioctls that flow on the master socket to the TD are never passed through to the TP, because that is where they came from. Some of the ioctl commands are intended only for the Common INET layer, and these are not even passed on to the TD. However, the TD should be coded to ignore the ioctl commands that are intended for the Common INET layer, because when it is connected directly to the LFS it will receive these requests. The TP could also be configured to know how the TD is set up within z/OS UNIX and process accordingly, but this is usually not worth the extra effort and externals.

The master socket is left open for the duration of the transport provider. If this socket is closed, the prerouter assumes that the transport provider has terminated. This socket may also be needed later for dynamic route updates, and it can be used within the TD/TP recovery design. If the TP abnormally terminates, the master socket for it is closed. The TD sees this as a vn_close, at which point it can take whatever recovery actions may be necessary. Thus, a resource manager for the TP and the code to notify the TD are not necessary solely for the purpose of letting the TD know when the TP crashes.

The constants for the various ioctl commands that are used during initialization are defined in BPXYPFSI.

Common INET prerouting function

The Common INET support allows an installation to connect up to 32 different instances of TCP/IP or other AF_INET physical file systems. Application programs that use sockets do not need to change any code to take advantage of the multiple AF_INET file systems.

Supporting multiple AF_INET physical file systems and providing a single file system image to the user means that the Common INET must perform a set of management and distribution functions that govern how a socket behaves with multiple file systems. A fundamental requirement for distributing work across multiple file systems is an understanding of the IP configurations of each file system. The IP configurations are needed to determine which file system should handle a bind() to a particular home IP address, a connect(), a sendto(), and so forth.

When the Common INET processes a socket request that requires it to select only a particular file system based on an input IP address from a user, the Common INET uses its copy of each file system's IP configuration to select the correct file system to process the user's request. Copies of the IP configurations are maintained by the Common INET internally, and are only used for "prerouting" a socket call to the correct file system. The file system that was selected performs all of the official file system functions, such as routing, once the socket request reaches the file system from the Common INET.

Each file system that is connected to the Common INET must provide a copy of its internal IP routing table. An ioctl is issued to each transport provider (TP) as part of the PFS initialization. This allows the Common INET function to query the routing tables for that file system. Once the Common INET prerouter function has successfully retrieved and stored routing information from a particular file system, message BPXF206I is issued to the hardcopy log. Message BPXF206I is also issued whenever a file system refreshes its routing table. For example, IBM's TCP/IP may refresh its routing tables as part of the OBEYFILE command. Message BPXF207I is issued to the hardcopy log whenever the Common INET deletes internal routing information for a file system. When the connection with a specific file system is severed, the Common INET routing information for that file system is deleted.

Limitations of Common INET-attached PFS IP configurations

System programmers and network administrators should be aware of the following information about the common INET prerouting function:

- 1. Two or more file systems may contain home IP addresses on the same network or subnetwork. However, load balancing across file systems is not done. If a user has not done a bind() to a home address, the same file system is selected for each subsequent sendto(), even if there are other transport providers with routes to the same destination.
- 2. Two or more file systems may contain a route to the same destination. Again, load balancing across the file systems is not performed.
- 3. **Route precedence:** The prerouter assigns a route precedence value for each route. The route precedence value is based on the route type reported by the transport provider. The higher the value, the better the route. If there is more than one route to a destination, the route with the best route precedence value will be selected. If there is more than one route to a destination with the best route precedence value, the route with the best route precedence and the best route metric (see item <u>"4" on page 51</u>) will be selected.

In order for route selection based on route precedence to completely work, all TPs connected to the prerouter must report the route type on route-related ioctls (SIOCGRTTABLE and SIOCMSADDRT for IPv4; SIOCGRT6TABLE, SIOCMSADDRT6, and SIOCMSADDRT6V2 for IPv6). For the IPv4 ioctls, the route type is in the Iocn_RtMsgRteType field. For the IPv6 ioctls, the route type is in the IPV6FlgRouteType field. IBM TCP/IP reports the route type on these ioctls. Non-IBM TCP/IP products must adhere to the same route precedence hierarchy as IBM TCP/IP.

If some of the TPs connected to the prerouter supply route types and some do not, routes will be selected as follows when multiple routes exist to the same destination:

• If at least one of the routes to the destination is from a stack that does not supply route types, the best route will be selected by comparing route metric values only.

• Otherwise, the best route will be selected by comparing route precedence values, with route metric values serving as a tie breaker, as described previously.

If none of the TPs connected to the prerouter supply route types and there is more than one route to a destination, the route with the best route metric value will be selected.

Tip: If a TP that does not supply route types is connected to the prerouter, then, when the TP initializes, z/OS UNIX issues message BPXF238I to indicate that the TP does not support route precedence.

- 4. Route metrics: If two or more transports maintain routes to the same destination, metric information may be needed from each transport in order to correctly select the best route. For IBM TCP/IP, this is best accomplished when each stack is running with a dynamic routing daemon (such as OMPROUTE). Statically defined indirect routes (routes to destinations that do not reside on a transport's directlyattached links) do not provide adequate metric information to select the shortest route to a destination network when two or more transports maintain indirect routes to the network.
 - In cases in which two or more file systems maintain routes to the same destination and not all file systems provide metric information, selection of the file system to process a request is unpredictable. Generally, the file systems with metric information are selected because of implementation details.
- 5. If the route selection algorithm cannot select a single best file system based on the values being used to compare their routes to destinations, selection of a file system proceeds as follows:
 - a. If one of the file systems with a route to the destination is the default file system as specified in the BPXPRMxx parmlib member, the default file system is selected.
 - b. Otherwise, the file systems are selected in the order in which they were defined in the BPXPRMxx parmlib member.
- 6. Host-defined routes are always searched before network routes.
- 7. If a file system severs its connection, all routing information for the severed file system is deleted. If the severed file system maintained duplicate home or network routes, these routes are deleted. Subsequent requests for the duplicate routes are routed to the remaining file systems.
- 8. If two transport providers have connections to the same network and two applications that are running on the same MVS start communicating with each other, performance may not be optimal. If for some reason the two applications bind to different transport providers, the external network is used, rather than the Common INET local INET support. Therefore, it is suggested that applications use a method analogous to gethostid() to get the IP address of themselves and bind to the address that is returned from the gethostid(). This method ensures that the default transport provider is selected. The local INET support works only with the default transport provider.

Initializing an AF_INET (IPv4) transport driver

When a transport driver is being initialized, the prerouter is notified of the TD's arrival. The prerouter performs the following functions:

- 1. Opens a socket from the kernel address space. This is not the master socket, but a regular user socket that is initiated through the z/OS UNIX socket interface.
- 2. Issues the SIOCGIFCONF joctl to the TP.
 - If the TP recognizes that the SIOCGIFCONF was sent by the z/OS UNIX prerouter (the prerouter puts 'USS4' in the first four bytes of the buffer), the TP returns the ioctl with Iocn NetConfLength set to -1 (to indicate that no home interface information is being returned). The prerouter will receive information about the IPv4 home interfaces maintained by the file system in the next step.
 - Otherwise, the TP returns the list of home IPv4 interfaces via the ioctl. The prerouter adds the home IP addresses to the home interface table.
- 3. Issues the SIOCGRTTABLE ioctl. This gets the file system IPv4 home, host, and network routing information in a table format. The mapping for this request is found in **ioctl.h**.
 - The TP places the home IP address in the Iocn_ipaddrRtMsgHomeIf field for each route to be returned.

- The TP identifies home routes by setting the Iocn_bRtAttrLocal and Iocn_bRtAttrHost bits on.
- When the TP sets the Iocn_bRtAttrLocal and Iocn_bRtAttrHost bits on in any route, it also sets the Iocn_bRtAttrRtUp bit on if the interface is active, or off if it is inactive.
- 4. Places the routes from the SIOCGRTTABLE in the home, host, and network routing tables managed by the prerouter. Note that the TP can give metrics in hop counts or millisecond delays by setting the appropriate flag in the header of the SIOCGRTTABLE structure. All metrics are converted to hop counts.
- 5. Closes the socket.

The prerouter is now initialized for the transport driver.

Initializing an AF_INET6 (IPv6) transport driver

When the transport driver that is being initialized is IPv6 capable, the prerouter also performs the following functions when it is notified of the TD's arrival:

- 1. Opens a socket from the kernel address space. This is not the master socket, but a regular user socket that is initiated through the z/OS UNIX socket interface.
- 2. Issues the SIOCGHOMEIF6 ioctl to the TP.
 - If the TP recognizes that the SIOCGHOMEIF6 was sent by the z/OS UNIX prerouter (the prerouter puts 'USS6' in the first four bytes of the buffer), the TP returns the ioctl with NchNumEntryRet set to -1 (to indicate that no home interface information is being returned). The prerouter will receive information about the home IPv6 interfaces maintained by the file system in the next step.

A TP that responds to the SIOCGHOMEIF6 ioctl in this manner must use the following ioctls to notify the prerouter of changes to individual IPv6 routes:

- SIOCMSADDRT6V2
- SIOCMSDELRT6V2
- SIOCMSCHGRT6METRICV2
- Otherwise, the TP returns the list of home IPv6 interfaces via the ioctl. The prerouter adds the home IP addresses to the home interface table.

A TP that responds to the SIOCGHOMEIF6 ioctl in this manner must use the following ioctls to notify the prerouter of changes to individual IPv6 routes:

- SIOCMSADDRT6
- SIOCMSDELRT6
- SIOCMSCHGRT6METRIC
- 3. Issues the SIOCGRT6TABLE ioctl. This gets the file system IPv6 home, host, and network routing information in a table format.
 - The TP places the home interface index in the GRT6RtHomeIfIdx field for each route to be returned.
 - The TP identifies home routes by setting the IPV6BitHome and IPV6BitHost bits on.
 - When the TP sets the IPV6BitHome and IPV6BitHost bits on in any route, it also sets the IPV6BitRtUp bit on if the interface is active, or off if it is inactive.
- 4. Places the routes returned from the SIOCGRT6TABLE ioctl in the home, host, and network routing tables managed by the prerouter. (Note that IPv6 metrics are in hop counts.)
- 5. Closes the socket.

The prerouter is now initialized for the transport driver.

Route changes

The prerouter handles BSD-style route changes for the routeD add (SIOCADDRT) and delete (SIOCDELRT) functions. When a route is added, the rt_use field is checked for a nonzero value. If rt_use is nonzero, it

is assumed to be a hop count metric. Metrics can be changed by issuing the SIOMETRIC1RT ioctl or by reissuing the SIOCADDRT ioctl with the rt_use field set to the new metric value.

Route changes can be sent to the prerouter in two ways:

- When processing ioctls for add (SIOCADDRT) and delete (SIOCDELRT) functions from a routing daemon that uses z/OS UNIX sockets, z/OS UNIX automatically passes the ioctls to the prerouter. If the TP did not return a value of -1 for Iocn_NetConfLength on the initial SIOCGIFCONF (as described in "Initializing an AF_INET (IPv4) transport driver" on page 51), the prerouter makes the needed updates.
- If a routing daemon does not use z/OS UNIX sockets (but, instead, uses a different interface to a file system) or the TP returned a value of -1 for Iocn_NetConfLength on the initial SIOCGIFCONF (as described in "Initializing an AF INET (IPv4) transport driver" on page 51), the ioctls for add (SIOCADDRT) and delete (SIOCDELRT) functions must be propagated to z/OS UNIX. To do this, the file system must use the SIOCMSADDRT, SIOCMSDELRT, and SIOMSMETRIC1RT ioctls for IPv4 routes and the SIOCMSADDRT6V2, SIOCMSDELRT6V2, and SIOCMSCHGRT6METRICV2 ioctls for IPv6 routes. These are issued on the master socket (as denoted by the 'MS'). z/OS UNIX needs the master socket or else these functions would be propagated back to the file system and an endless loop would occur.
 - For SIOCMSADDRT and SIOCMSDELRT, the TP identifies home and host routes by setting the Iocn_bRtAttrLocal and Iocn_bRtAttrHost bits on, respectively. If Iocn_bRtAttrLocal is on for any route, the TP also sets the Iocn bRtAttrRtUp bit on if the interface is active. The TP also puts the home IP address associated with the interface in the rt_ifp field for the SIOCMSADDRT, SIOCMSDELRT, and SIOMSMETRIC1RT ioctls. When an IPV4 interface is deleted, the TP also sends a SIOCMSDELRT ioctl to delete the home IP address to the prerouter.
 - For SIOCMSADDRT6V2 and SIOCMSDELRT6V2, the TP identifies home and host routes by setting the IPV6BitHome and IPV6BitHost bits on, respectively. If IPV6BitHome is on for any route, the TP also sets the IPV6BitRtUp bit on if the interface is active. The TP also puts the home interface index in the RT6RtHomeIfIdx field for each route specified with the SIOCMSADDRT6V2, SIOCMSDELRT6V2, and SIOCMSCHGRT6METRICV2 ioctls.

ICMP redirects are handled using the SIOCMSICMPREDIRECT ioctl.

Interface state changes

After the prerouter's routing tables have been built (as described in "Initializing an AF INET (IPv4) transport driver" on page 51 and "Initializing an AF_INET6 (IPv6) transport driver" on page 52), the prerouter can be notified about interface state changes in the following ways:

- For TPs that returned a value of -1 for Iocn NetConfLength on the initial SIOCGIFCONF (or for NchNumEntryRet on the initial SIOCGHOMEIF6) during TD initialization, the prerouter's routing tables will contain both active and inactive routes. The TP can issue the following joctls to change the state of an interface:
 - The SIOCMSMODHOMEIF joctl allows a TP to activate or deactivate an IPv4 home interface. For each entry in the home IP address table, the Iocn bRtAttrRtUp bit indicates the status (active or inactive) of the home interface. SIOCMSMODHOMEIF turns this bit on or off to activate or deactivate the interface. If a home IP address is active, then this means that the home interface and all of the routes associated with that interface are active. Likewise, if a home IP address is inactive, then the home interface and all of the routes associated with that interface are inactive.
 - The SIOCMSMODHOMEIF6 ioctl allows a TP to activate or deactivate an IPv6 home interface. For each entry in the home interface index table, the IPV6BitRtUp bit indicates the status (active or inactive) of the home interface. SIOCMSMODHOMEIF6 turns this bit on or off to activate or deactivate the interface. If an interface is active, then all of the routes associated with that interface are active. Likewise, if an interface is inactive, then all of the routes associated with that interface are inactive.
- Otherwise, for TPs that did not return a value of -1 for Iocn NetConfLength on the initial SIOCGIFCONF (or for NchNumEntryRet on the initial SIOCGHOMEIF6) during TD initialization, the prerouter only adds the active routes to its routing tables. Therefore, the fact that a route exists in the routing tables means that the interface is active. If the state of an interface changes, the prerouter receives an

SIOCMSRBRTTABLE ioctl (for IPv4) or SIOCMSRBRT6TABLE ioctl (for IPv6) from the TP so that it can rebuild its routing tables, as described in "Rebuilding the routing tables" on page 54.

Rebuilding the routing tables

If the file system encounters a situation where it believes that the IPv4 routing information or the IPv4 home IP address information needs to be re-synchronized, it can issue the SIOCMSRBRTTABLE ioctl on the master socket. If the file system encounters a situation where it believes that the IPv6 routing information or the IPv6 home IP address information needs to be re-synchronized, it can issue the SIOCMSRBRT6TABLE ioctl on the master socket. If the IPv6 home IP address information needs to be re-synchronized, SIOCMSRBHOMEIF6 can also be used. These ioctls cause the prerouter to flush the information for the file system and rebuild it from scratch.

When the prerouter receives the SIOCMSRBRTTABLE ioctl (or SIOCMSRBRT6TABLE for IPV6) from the TP, it does the following:

- For SIOCMSRBRTTABLE, if the TP returned a value of -1 for Iocn_NetConfLength on the initial SIOCGIFCONF (as described in "Initializing an AF_INET (IPv4) transport driver" on page 51), the prerouter only issues the SIOCGRTTABLE ioctl to rebuild its home, host, and network routing tables. Otherwise, the prerouter issues both the SIOCGIFCONF ioctl to rebuild its home interface table and the SIOCGRTTABLE ioctl to rebuild its host and network routing tables.
- For SIOCMSRBRT6TABLE, if the TP returned a value of -1 for NchNumEntryRet on the initial SIOCGHOMEIF6 (as described in "Initializing an AF_INET6 (IPv6) transport driver" on page 52), the prerouter only issues the SIOCGRT6TABLE ioctl to rebuild its home, host, and network routing tables. Otherwise, the prerouter issues both the SIOCGHOMEIF6 ioctl to rebuild its home interface table and the SIOCGRT6TABLE ioctl to rebuild its host and network routing tables.

Note: If a user does a socket request during a rebuild, the user may or may not be able to connect with the file system. The routing table is in flux.

SRB-mode callers

z/OS UNIX supports programs that are running on service request block (SRB) dispatchable units, in addition to the more standard task control blocks (TCBs). This affects the PFS, as the resulting vnode operations are also running in SRB mode.

SRB mode is even more restrictive than cross-memory mode. Additional restrictions on the PFS include the following:

• There are no MVS WAITs; instead you have to use SUSPEND/RESUME. This can impact some of the internal functions of the PFS that may not be easy to modify, including task switching, lock managers, and tracing.

Note: The osi_wait/osi_post services transparently support both TCB and SRB-mode callers.

- No TCB is available (Psatold=0). The TCB address is used by some programs to build identifiers, or in other algorithms.
- There is no EOT or ESTAE recovery, although you can use an FRR.

Note: vn_recovery support is still available from the LFS.

• Because SRB callers do not receive POSIX signals, they cannot break out of extended waits, as they can in the EINTR cases.

Signal-enabled osi_waits should still be set up where they are set up now, because this also indicates that the osi wait may be interrupted for process termination.

The following OSI services are enabled for SRB-mode callers:

osi_copyin osi_copyout osi_copy64 osi_getvnode

```
osi_mountstatus
osi_postosi_sched
osi_selpost
osi uiomove
osi_upda
osi wait
osi_wakeup
```

The PFS signifies that it supports SRB-mode callers on the pfsi_srb bit that is returned during PFS initialization. The LFS inhibits SRB-mode calls to PFSs that do not support them.

All sockets-related vnode operations are potentially callable from an SRB, and in the future this may be extended to file-related operations. Therefore, the PFS should be made completely SRB safe.

For more information about SRB-mode programs, see Using a service request block (SRB) in z/OS MVS Programming: Authorized Assembler Services Guide.

Asynchronous I/O processing

An asynchronous capability is provided by z/OS UNIX for socket calls that may block. These include accept, connect, select, poll, and the five pairs of read/write type functions. These services are provided asynchronously to programs through the asyncio callable service. For more information, see asyncio (BPX1AIO, BPX4AIO) — Asynchronous I/O for sockets in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Asynchronous I/O processing between the LFS and PFS is implemented with a two-pass technique using the regular vnode operations, such as vn_accept and vn_rdwr:

- Part 1, which is indicated by a bit in the Osi structure, starts with the beginning of the normal vnode operation and continues up to the point at which the PFS would call osi_wait to block. The PFS returns to the LFS instead of waiting. When the I/O can be completed, the PFS calls the osi sched service at the point at which it would call osi_post for a blocked operation.
- Part 2, which is indicated by another bit in the Osi structure, continues from the point after which osi_wait would have been called through the end of the operation.

These two stages are covered in detail in the "Asynchronous I/O flow details" on page 58.

Related services

Two special osi services are used in asynchronous I/O processing:

- osi_upda, which is called during Part 1 to pass a PFS token to the LFS. Refer to "osi_upda Update async I/O request " on page 414 for specifics.
- osi_sched, which is called to drive Part 2 when the I/O can be completed. Refer to "osi_sched Schedule async I/O completion " on page 396 for specifics.

The vn_cancel service is a special vnode operation that is used to cancel an outstanding request. Refer to "vn cancel — Cancel an asynchronous operation" on page 126 for specifics.

The vnode operations that can be run in two passes are:

```
vn_accept
            vn_rdwr
                            vn_sndtorcvfm
            vn_readwritev
vn_anr
                            vn_srmsg
vn_connect
           vn_sndrcv
```

Impact on initialization

The PFS signifies that it supports asynchronous I/O on the pfsi_asyio bit that is returned during PFS initialization. To support asynchronous I/O, the PFS must also support SRB-mode callers, because Part 2 runs from an SRB, and it must support vn cancel. The LFS inhibits asynchronous calls to PFSs that do not support them.

Waits that are avoided

Asynchronous I/O is intended to avoid long waits only. These are blocking, indeterminate waits that usually depend on something from the network or an end user. Long waits also tend to be conditional, based on the current non-blocking mode. Short internal waits, such as lock waits for serialization, are not avoided. An example is that of a read: you can wait for a lock to look at the inbound queue, but if the queue is empty you cannot wait for the data.

Related OSI fields

The OSI fields that are significant to this discussion are:

- osi_asy1, which signifies Part 1
- osi asy2, which signifies Part 2
- osi_asytok, which holds the LFS's token on entry to Part 1 and the PFS's token on entry to Part 2.
- osi_ok2compimd, which indicates that the PFS may complete the operation immediately, if possible. See "Asynchronous I/O flow details" on page 58 for details.
- osi_compimd, which is returned by the PFS to indicate that it has completed the operation immediately. This is valid only if osi_ok2compimd is on.
- osi_commbuff, which indicates that Part 2 of Async I/O must not occur. Within the PFS, the changes from normal Async I/O flow are:
 - 1. Received data can be copied directly to the user's buffers from the PFS's inbound data handler.
 - 2. osi_sched is called after the data has been copied.
 - 3. The amount of data being returned must be supplied to osi sched.
 - 4. There must be no dependence on Part 2 being called.

Note: The last four fields are meaningful only when osi_asy1 or osi_asy2 are on; they should not be referred to otherwise.

These fields are covered in more detail in Figure 6 on page 58.

Canceling an operation

The LFS attempts to cancel an outstanding operation with vn_cancel. There are two types of vn_cancel: normal and forced.

- A normal vn_cancel only flows to the PFS between Part 1 and Part 2, and is used to get requests off the waiting, or blocking, queues in the PFS. If the request is not currently on a waiting queue, nothing is done. If the request is found, it is removed from the queue and failed with ECANCELED.
- A forced vn_cancel is used during process termination of the original requestor. It can be sent logically at any time, but the PFS will already have abnormally ended and gone through recovery if the request was in Part 1 or Part 2 at the time the process terminated. There is no Part 2 after a vn_cancel force, so the PFS must do any necessary cleanup during the vn_cancel.

Refer to "vn_cancel — Cancel an asynchronous operation" on page 126 for more information.

Responsibilities for the semantics

The semantics for the asyncio function are split between the PFS and the LFS. Some of the features whose support might be ambiguous are discussed here. Refer to aio_suspend (BPX1ASP, BPX4ASP) — Wait for an asynchronous I/O request in z/OS UNIX System Services Programming: Assembler Callable Services Reference while reading this topic.

The LFS must handle the following:

• The aiocb structure. The interface to the PFS is through the regular vnode operations, such as vn_rdwr and vn_sndrcv.


- The returned information. The PFS should return 0 for a successful Part 1, and the normal functional values from Part 2. In particular, the LFS handles the EINPROGRESS return_code.
- Scheduling the SRB and calling the I/O completion notification. This includes calling the user exit, posting an ECB, and sending a signal.
- AioSync. This appears to the PFS as a normal synchronous operation (osi_asy1=osi_asy2=OFF).
- AioOk2CompImd, for accept and connect. The osi_ok2compimd bit is always on in the PFS for vn_accept and vn_connect, so the PFS can always complete these operations immediately without calling osi_upda or osi_sched. osi_compimd should be turned on if the PFS does happen to complete these operations immediately.
- The select and poll functions, which are already asynchronous with respect to the PFS. The PFS continues to call osi selpost for the vfs batsel and vn select operations.

The PFS must handle or contribute to the support of:

- · AioOk2CompImd, for reads (including accept_and_recv) and writes, through support for osi ok2compimd. Even when the PFS is able to complete a read or write type of operation immediately, it must still call osi sched whenever osi ok2compimd=off. See "Asynchronous I/O flow details" on page 58 for details.
- AioCallB4 and deferred buffer allocation, by not requiring the presence of the user's data buffers during Part 1, unless osi_ok2compimd=on; and by passing the length of data that is available to be received to osi_sched.
- The ECANCELED Return_code, by failing a request with that return code when the request has been removed from a waiting queue because of vn_cancel. The race condition between vn_cancel and data arrival can only be resolved by the PFS.

Asynchronous I/O flow diagram

This diagram describes the general flow of an asynchronous operation, noting those parts of the interface that are specific to its asynchronousity, and the significant design points within the PFS that the LFS is dependent on. As it is based on a somewhat generic PFS model, it might not match any specific implementation, and a PFS might have to do some work to accommodate it. PFSs that have an associated separate address space should be able to fit this model. These design points can be met either in the kernel address space or in the associated address space.



Asynchronous I/O flow details

This flow is discussed as an addition to an existing PFS design that already handles synchronous blocking and non-blocking socket operations.

- 1. BPX1AIO/BPX4AIO (asyncio) is called with an Aiocb structure. The Aiocb contains all the information that is needed to do the specific function.
- 2. The LFS builds an Async I/O Request Block (RqBlk). The PFS has signified support via the Pfsi_Asyio PFSinit output bit. The regular vnode operation for the function is invoked in the PFS with:
 - + The osi_asy1 bit turned on to indicate Async I/O Part 1.
 - + The osi_asytok field holding the LFS_AsyTok token.
- 3. Part 1 in the PFS:
 - The PFS builds its own Request Block. The LFS_AsyTok is saved for later use with osi_sched(). The PFS's PFS_AsyTok is passed back to the LFS via osi_upda(). This identifies the request to the PFS in Part 2 and to vn_cancel. Basic preliminary parameter and state checking can be done here.

- The user's read buffers are not referenced during Part 1 unless osi_ok2compimd=ON (see the Variations in this topic). This allows the user to defer read buffer allocation to just before Part 2. The requested length for reads is available, even if the buffers are not.
- The PFS queues the request to await the desired event. This is essentially the same thing that is normally done for blocking requests. Instead of calling osi_wait(), as it would at this point for a blocking request, the PFS returns to the LFS with the Return_value, Return_code, and Reason_code (RRR) from queueing the asynchronous I/O. For a successfully queued request, the Return_value is 0, and any output from the operation is deferred until Part 2. Important PFS structures are preserved as necessary over this return and the subsequent reentry to the PFS for Part 2.

The variations are as follows:

- If the operation fails during Part 1, the normal path is taken and, instead of the request being queued, the failure is returned. This includes both queueing failures and failures of the function that is being requested.
- If the operation can be completed immediately and osi_ok2compimd=ON, the PFS can proceed as it would normally and complete the operation synchronously. osi_compimd is turned ON to tell the LFS that this has happened.
- If osi_ok2compimd=OFF, the PFS must make the call to osi_sched from within this vnode operation, and proceed from Part 2 as if the data were not immediately available. This bit is only OFF for read/write type operations. If the PFS does not need to be recalled for Part 2 (for instance, with a short write), it can skip the call to osi_upda. It is all right to transfer the responsibility for calling osi_sched to some other thread, making the call asynchronously and returning to the LFS, as long as you do not wait for network input.
- 4. The LFS returns to the caller with AioRC=EINPROGRESS; or, if it has failed or completed immediately, cleans up and returns the operation's results.
- 5. The original caller continues. All structures and data buffers must persist throughout the operation.
- 6. Event occurrence in the PFS:
 - At some point data arrives for the socket, or buffers become available, and the request can be completed.
 - The PFS notices, or responds to, this condition as it normally does. Instead of calling osi_post(), as it would at this point for a blocked request, it calls osi_sched() with the saved LFS_AsyTok to drive Part 2.
 - For read type operations, the passed Return_Value contains the length of the data that is available to be read in Part 2. This is an optional performance enhancement that some applications may take advantage of. If the length is not easily known, 0 should be passed.
 - The rest of the action happens on the SRB, because user data cannot generally be moved while it is on the thread that calls osi_post/osi_sched.

The variations are as follows:

- If the request fails asynchronously, the PFS can report this on the call to osi_sched() by passing the failing three R's. There will be no Part 2 if the passed Return_value is -1, so the PFS has to clean everything up from here.
- Alternatively, the PFS can save the results, pass success to osi_sched(), and report the failure from Part 2. This is sometimes more convenient when the event handler is in a separate address space and the PFS has resources to clean up in the kernel address space. The only time osi_sched() fails is if the passed LFS_AsyTok is no longer valid, which may represent a logic error in the PFS. osi_sched() succeeds even after the user has terminated, but the PFS sees vn_cancel instead of Part 2.
- 7. The LFS schedules an SRB into the user's address space and returns to the PFS. The SRB runs asynchronously to the caller of osi_sched().
- 8. The SRB runs in the user's address space, so that the user's data buffers can be referenced from "home" while in cross-memory mode. This also gets the user's address space swapped in if necessary. The LFS is recalled to get into the kernel address space.

- 9. The LFS reconstructs the original vnode request structures. The same vnode operation is invoked in the PFS as for Part 1, with:
 - + The osi_asy2 bit turned on to indicate Async I/O Part 2.
 - + The osi_asytok field holding the PFS_AsyTok value from osi_upda()

The variations are as follows:

If osi_upda was not called during Part 1, the PFS is not called for Part 2.

10. Part 2 in the PFS:

- This is running on an SRB instead of the more usual TCB, and the PFS has to be able to handle this mode
- From the PFS_AsyTok, the PFS is able to pick up from where it left off at the end of Part 1 (3), when it returned to the LFS instead of waiting. Necessary information that is related to the completing operation is obtained in a manner similar to that in which it is obtained after coming back from osi_wait().
- Data is moved between the user's and the PFS's buffers for read/write types of operations; or the operation is completed as appropriate.
- The normal cross-memory environment has been recreated, with the user's buffers in home and the PFS's buffers in primary; or it is otherwise addressable as arranged by the PFS.
- The normal move-with-key instructions are used to protect against unauthorized access to storage. The osi copy services are available.
- For unauthorized callers in a TSO address space, the LFS has stopped the user from running authorized TSO commands while async I/O is outstanding. This avoids an obscure integrity problem, with user key storage being modified from a system SRB.
- The PFS returns to the LFS with the results of the operation and the normal output for this particular vnode operation, such as the vnode_token from vn_accept. The operation is over at this point, as far as the PFS is concerned.

The variations are as follows:

- If the operation fails during Part 2, this is reported back. An earlier failure may have been deferred to Part 2 by the PFS.
- For very large writes, the PFS may not want to commit all of its buffers to one caller. It may instead loop, sending smaller segments and waiting in between for more buffers. If this is the case, the PFS remains in control and does not return from Part 2 until the whole operation is complete, that is, until the remainder of the operation is synchronous and the PFS blocks as necessary, as it normally does in this loop. osi_wait is convenient here, as it accommodates SRB callers. Essentially, osi_sched() is only called when the first set of buffers become available and the effect is to offload the work from the user's task or SRB to a system SRB. The operation is still asynchronous to the user. This ties up the SRB, but it is considered to be a situation of relatively small frequency.
- Because SRBs are not interrupted with signals, osi_waits during Part 2 normally do not return as they do in the EINTR cases. If the user's process terminates, signal-enabled osi_waits return as if they have been signaled.
- 11. On return to the LFS, signals are sent and unauthorized exits are queued to the user's TCB (not shown).
- 12. The LFS returns to the SRB.
- 13. On return to the SRB, authorized exits are called and ECBs are posted. When the user program is notified that the I/O has completed, either on the SRB or user's TCB, it can free the Aiocb and buffers. The operation is over, as far as the LFS is concerned, either at the end of the SRB or after an unauthorized exit has run on the user's TCB.

Colony PFS PC

A PC number is established in colony address spaces that can be used from code running in the kernel to PC into the colony. This could be used by a related PFS that runs in the kernel or by a related file exporter's glue exit.

The PC number is passed to the PFS in the pfsi_pfspc field during initialization. Using this PC involves the following:

- The colony PFS must have a PC routine that will be the target of the PCs. This routine must reside in the colony or in common storage.
- The colony PFS passes the pfsi pfspc PC number and the address of its PC routine to the cooperating code that runs in the kernel or otherwise makes these values known to the kernel code that will use
- The kernel PC caller must place the colony PC routine address in Register 15 and invoke the PC instruction with the pfsi_pfspc value.
- In the colony, the real PC routine that was established by the LFS branches to the address that is in Register 15.
- · The PFS's PC routine is responsible for anything that it may need, and its entry is not much different from that of a real PC routine.

The PC is defined to be entered in the following state:

PSW kev

Authorization

Supervisor state

AR

ASC mode

AMODE

31-bit

Registers on entry: The registers on entry are as follows:

Register

Contents

0-13

As they were in the PC caller

14

A return address that can be used by the PC routine

15

The routine address as set by the PC caller

The routine does not have to save or restore any registers or state information. This is a stacking PC.

The routine must acquire any working storage that it may need in the primary, colony, address space.

The routine must set up an FRR or ESTAE if it needs any recovery to be run in the colony address space. It will be officially running under an ARR (associated recovery routine), but there will be no recovery done by that ARR.

When it has completed, the routine may either issue a PR instruction to return back to the PC caller, or return to the address that was in Register 14 on entry; that is, issue BR 14.

• The PC caller must beware of the colony address space terminating while it is using the PC. If the colony address space terminates before the PC or during the PC routine's execution, the PC caller will abend.

Considerations for Internet Protocol Version 6 (IPv6)

The following should be considered when activating IPv6 on a system.

Activating IPv6 on a system

IPv6 is activated on a system with a second NETWORK statement for DOMAINNAME(AF_INET6) with DOMAINNUMBER(19), which arrives at the PFS as a second vfs_network call. If a PFS supports IPv6, it must support both AF_INET and AF_INET6; there are no IPv6-only stacks.

To indicate support for IPv6, a PFS must:

- 1. Set PfsiIpv6 on during initialization, to indicate that it can receive vfs_network(AF_INET6).
- 2. Return successfully from that call.

An administrator can add the second NETWORK statement for AF_INET6 dynamically with SETOMVS RESET=. The stack is free to reject the vfs_network if it arrives after initialization. Generally, both vfs_network calls are passed to the PFS during z/OS UNIX startup or after a PFS recycles. The vfs_network calls for AF_INET and AF_INET6 may be in any order.

If PfsiIpv6 has not been set, or if the vfs_network for AF_INET6 is not accepted, IPv6 sockets are not opened to that stack. When an application opens an AF_INET6 socket across a Common INET configuration of both IPv6-capable and IPv4-only stacks, an AF_INET socket is opened to the IPv4-only stacks, and a certain amount of address conversion and emulation is performed by CINET for the IPv4-only stack. An IPv6-capable stack must do its own conversions and emulations for any IPv4 partners that it permits on an IPv6 socket.

Common INET transport driver index

In a multi-stack configuration there can be duplication of interface indices. CINET inserts its transport driver index, TdIndex, into the upper halfword of all output interface indices to identify the interfaces uniquely. On input interface indices, the upper halfword is used to select a stack, and is cleared before the information is passed on to the stack. Each stack's TdIndex value is passed to it in PfsiTdIndex, but the stack does not have to do anything with the value.

For more information about the transport driver index, see the discussion of the SIOCGIFNAMEINDEX ioctl command in the usage notes of w_ioctl (BPX1IOC, BPX4IOC) — Control I/O in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

ioctl used by the XL C/C++ Runtime Library

The if_nameindex(), if_nametoindex(), and if_indextoname() functions use the SIOCGIFNAMEINDEX (Get Interface Name/Index Table) ioctl, which returns the Interface Name/Index Table for a PFS. The command and output arguments are defined in the BPXYIOCC macro, and are described in the discussion of the SIOCGIFNAMEINDEX **ioctl** command in w_ioctl (BPX1IOC, BPX4IOC) — Control I/O in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

ioctls used by the prerouter

The dialog between a transport provider and the Common INET prerouter for IPv6 is basically the same as the one for IPv4. The prerouter uses these ioctl commands, which are defined in the BPXYIOCC macro:

| Command | Value | Description |
|--------------------|-------------|---------------------------------------|
| SIOCMSADDRT6 | '8044F604'x | Add an IPv6 route |
| SIOCMSDELRT6 | '8044F605'x | Delete an IPv6 route |
| SIOCMSCHGRT6METRIC | '8044F60A'x | Change an IPv6 route's metric |
| SIOCGRT6TABLE | 'C014F606'x | Get IPv6 network routing table |
| SIOCMSRBRT6TABLE | '8000F607'x | Rebuild IPv6 route tables |
| SIOCGHOMEIF6 | 'C014F608'x | Get IPv6 home interface configuration |
| SIOCMSRBHOMEIF6 | '8000F609'x | Rebuild IPv6 home interface |

| Command | Value | Description |
|----------------------|-------------|------------------------------------------|
| SIOCMSMODHOMEIF6 | '8008F60B'x | Modify IPv6 home interface |
| SIOCMSADDRT6V2 | '8058F60C'x | Add an IPv6 route, version 2 |
| SIOCMSDELRT6V2 | '8058F60D'x | Delete an IPv6 route, version 2 |
| SIOCMSCHGRT6METRICV2 | '8058F60E'x | Change an IPv6 route's metric, version 2 |

The associated argument structures are defined in the BPXYIOC6 macro.

ioctls used by the resolver

The resolver uses two loctl commands to get specific information from a stack. These command codes are defined in BPXYIOCC, and the associated argument structures are described as follows:

SIOCGSRCIPADDR (obtain source IP addresses for an array of IPv6 and IPv4 destination addresses)

SIOCGSRCIPADDR obtains the associated source address (by Source Address Selection algorithm, which is part of RFC 3484 (Default Address Selection)) for each of the IPv6 addresses passed in an array. The label and precedence of each source and destination address are also returned. This information is ultimately used to sort the IPv6 and IPv4 destination addresses, using the algorithm described in the RFC 3484 (Default Address Selection) for destination addresses.

Argument: An array of IPv6 and IPv4 destination addresses, with a total count of the addresses being passed. The IPv4 destination addresses must be passed in as IPv4-mapped IPv6 addresses. The only SisPreferences currently recognized by the z/OS Communications Server IP stack are SisSrcPreferPublic and SisSrcPreferTmp. Upon return from the IOCTL invocation, the array structure is to include a source IP address for each of the array elements associated with the destination address that is being passed. This source address is determined by the stack, using the Source Address Selection algorithm defined in RFC 3484 (Default Address Selection). If a source address cannot be determined for a specific destination IP address (for example, if there is no route to the destination), a null value is placed in the array element's IP source address field (SisSrcIPaddr).

```
DCL 1 SrcIpSelect Based Bdy(Word),
        2 SisHeader,
          3 SisVersion Fixed(8),
                                        /* Version of the IOCTL interface
                                            This should be SrcIpSelect V2*/
                                        /* IPv6_ADDR_PREFERENCES_FLAGS
          3 SisPreferences Bit(8).
                                            byte-4 (see BPXYSOCK)
             /* The following mapping of SisPreferences must
             /* match the mapping of IPv6_ADDR_PREFERENCES_FLAGS
             /* in BPXYSOCK (see BPXYSOCK)
             5 * Bit(2), /* Invalid flags
5 SisSrcPreferNoncga Bit(1), /* IPV6_PREFER_SRC_NONCGA
                                                Prefer non-crypto
             5 SisSrcPreferCga
                                    Bit(1), /* IPV6_PREFER_SRC_CGA
                                                Prefer cryptographic
                                                                            */
             5 SisSrcPreferPublic Bit(1), /* IPV6_PREFER_SRC_PUBLIC
                                                Prefer public addr
             5 SisSrcPreferTmp
                                    Bit(1), /* IPV6_PREFER_SRC_TMP
                                                Prefer temp address
             5 SisSrcPreferCoa
                                    Bit(1), /* IPV6_PREFER_SRC_COA
                                                Prefer care-of addr
                                                                            */
             5 SisSrcPreferHome
                                    Bit(1), /* IPV6_PREFER_SRC_HOME
                                                Prefer home address
          3 SisSrcAddrFlagsIn Bit(8),
                                          /* Source IP address flags
                                           (input to IOCTL)
                                                                            */
             5 SisIgnoreSourceVIPA Bit(1), /* B'1' indicates that
                                           source VIPA should be ignored */
          5 * Bit(7), /*
3 * Char(1), /* Available
3 SisNumEntries Fixed(32), /* Number of destination
                                           addresses for which a source
                                           address must be selected
        2 SisIpAddrs(*),
           B SisDestInfo, /* Destination IPaddr data
4 SisDestIPaddr Char(16), /* Destination IP address. Can
          3 SisDestInfo.
```

```
contain a native IPv6 address,
                                           or a mapped IPv4 address
*/
             5 SisIpV4prefix
                                Char(12), /* IP address prefix
                                                                           */
                                  Char(10), /* Always nulls for IPv6
               7 SisIpV4nulls
                                                mapped addresses
               7 SisIpV4mapped
                                  Char(2), /* IPv6 mapped prefix
                                                                           */
             5 SisV4DestIPaddr Char(4), /* IPv4 address
SisDestLabel Fixed(16), /* Dest IP addr label
                                                                           */
            4 SisDestLabel
            4 SisDestPrecedence Fixed(16), /* Destaddr precedence
                                                                           */
           4 *
                                 Char(4),
          3 SisSrcInfo,
                                         /* Source IP address data
                                                                           */
            4 SisSrcIPaddr Char(16), /* Associated Source IP address
                                          (output from IOCTL)
                                Fixed(16), /* Src IP address label
            4 SisSrcLabel
           4 SisSrcPrecedence Fixed(16), /* Src Ipadr precedence
                                Fixed(32),
            4 SisSrcScopeID
                                          /* Other IOCTL output
          3 SisReturnInfo,
                              Fixed(32), /* Return code from attempt to
           4 SisRetcode
                                          obtain a source address
                                         /* Source IP address flags
            4 SisSrcAddrFlags Bit(8),
                                          (output from IOCTL
             5 SisSrcDeprecated Bit(1), /* B'1' indicates address is
                                          deprecated (only applicable for
                                          native IPv6 addresses
             5 *
                              Bit(7)
                              Char(3); /* Available
           4 *
                                                                           */
DCL SrcIpSelect_V2 Fixed(8) Constant(2);
DCL SrcIpSelect_Version Fixed(8) Constant(2);
```

SIOCGIFVERSION (determine if an IPv4 or IPv6 interface has been configured on a TCP/IP stack)

SIOCGIFVERSION determines if a TCP/IP stack in an INET environment has a configured IPv6 or IPv4 source address. (In this case, the loopback address is not considered to be valid as a configured interface.) This information is needed so that appropriate DNS queries can be made (IPv6 address records (AAAA) vs. IPv4 address records (AA)).

Argument: A four-byte area containing flags that provide the following information:

PFS support for multilevel security

To support multilevel security, a PFS must provide the following capabilities:

· vn link:

If a link is attempted to a character special file, and there is a security label on the file or on the directory for the new link, the vn_link call will fail with EPERM. If the ZCredSeclablActive flag is on, the following checks should be done:

- 1. If zCredSeclablRequired is on and the object has no security label, the zCredROSeclabel should be used as the object security label for all subsequent checks.
- 2. If the directory for the new link has a security label of SYSMULTI, no further security label checking is necessary.
- 3. If the directory for the new link has no security label, or has a security label other than SYSMULTI, a check for equality must be done between the security label of the directory and the security label of the file. If the values are equal, no further security label checking is necessary.

4. If the equality check fails, a dominance check must be made to check that the security label of the directory and the security label of the file are equivalent. The call to check security label equivalence should look like this:

```
RACROUTE REQUEST=DIRAUTH, RSECLABEL=(x), TYPE=EQUALMAC, USERSECLABEL=(y)
```

where x and y are registers that contain the addresses for the security labels.

· vn readdir:

If the ZCredSeclablActive flag is set, the following checks should be done:

- 1. If zCredSeclablRequired is on and the directory has no security label, the zCredROSeclabel should be used as the object security label for all subsequent checks.
- 2. If the directory has a security label of SYSMULTI, a dominance for read should be made between the user's security label and the security label of each entry in the directory. The user's security label is passed in the ZCredSeclabel field. If the security label of the directory entry is SYSMULTI or SYSLOW, the dominance check can be bypassed. If the dominance check fails, the directory entry should be excluded from the output buffer. The dominance check should look like this:

```
RACROUTE REQUEST=DIRAUTH, RSECLABEL=(x), ACCESS=READ, USERSECLABEL=(y)
```

where x and y are registers that contain the addresses for the security labels.

Note:

- 1. The PFS may cache object security labels to avoid rechecking for labels that have already passed the dominance check. A good cache is likely to result in a single check for each unique security label per readdir call.
- 2. No indication will be returned from the PFS if some names were excluded from the output buffer.
- 3. Discrepancy between the apparent number of entries in a directory and the number that can be read is acceptable.
- 4. The LFS will not filter names based on security label when it does a readdir2 for a PFS that does not support security labels. Any PFS that supports security labels must also support readdir2.
- 5. When the index method is used to read a directory, the meaning of the index is not the relative name in the directory, but the relative name that the user can access. For example, if the request is to return entries beginning with entry 10, the PFS must start at the first entry and verify dominance on each name until the 10th name that the user is permitted to see is found, and start returning names that can be seen from that point.

vn readlink:

If the zCredSeclablActive flag is set, the following checks should be done:

- 1. If zCredSeclablRequired is on and the directory has no security label, the zCredROSeclabel should be used as the object security label for all subsequent checks. If this flag is on, and the resulting object security label continues to be null because no value was provided by zCredROSeclabel, vn readlink should return with a failure of EACCES.
- 2. A dominance check should be performed between the user's security label and the security label of the symbolic link. The user's security label is passed in the zCredSeclabel field. If the security label of the directory entry is SYSMULTI or SYSLOW, the dominance check can be bypassed. If the dominance check fails, the vn_readlink should return with a failure of EPERM. The dominance check should look like this:

```
RACROUTE REQUEST=DIRAUTH, RSECLABEL=(x), ACCESS=READ, USERSECLABEL=(y)
```

where x and y are registers that contain the addresses for the security labels.

vn_setattr:

If the AttrSeclabelChg flag is set, a call to the SAF callable service IRRSSB00 should be made to set the security label for the file. The new security label is passed in the zCredSeclabel field, which is passed to SAF. The PFS does not have to access the new or the old security label.

PFS support for 64-bit virtual addressing

The main consideration for 64-bit addressing is the user data buffers, which might require 64-bit addressing in the UIO, IOV, and MSGH structures.

- For a PFS that is running in AMODE 31, other user parameters are copied into the kernel below the 2-gigabyte line, and these copies are passed to the PFS. R1 points to a parameter list of 31-bit addresses, and all calling parameters are below the 2-gigabyte line, although some of these parameters might contain 64-bit addresses of areas that are above the 2-gigabyte line.
- For a PFS that is running in AMODE 64, R1 points to a parameter list of 64-bit addresses, and user parameters might be below or above the 2-gigabyte line.

The data length parameter for read and write-type operations with 64-bit addressing remains 31 bits long.

Levels of support for 64-bit virtual addressing

From the point of view of the LFS, there are three levels of PFS support for 64-bit virtual addressing: None, 64-bit supporting, and 64-bit exploiting.

· None:

The PFS has no understanding of 64-bit addresses. The LFS copies 64-bit addressable user data to an internal 31-bit addressable buffer before it invokes the PFS for write-type operations, and vice versa for reads.

• 64-bit supporting:

The PFS can handle 64-bit user virtual addresses, or it makes use of the OSI services that can. It does not itself use buffers above the 2-gigabyte line or run in AMODE 64, at least not to the knowledge of the LFS.

• 64-bit exploiting:

The PFS supports 64-bit user virtual addresses. It may run in AMODE 64 and have its own data buffers, or even autodata, above the 2-gigabyte line. Some considerations for these PFSs are:

- Unless otherwise specified, the OSI service routines expect to be called in AMODE 31, with a 31-bit parameter list address and 31-bit parameter addresses. The calling interface may have to be manually constructed below the 2-gigabyte line.
- The SAF (RACF) services do not support 64-bit callers or addresses.
- MVS WAIT and POST services do not support ECBs above the 2-gigabyte line.

Recommendation: A PFS should be at least 64-bit supporting, in order to avoid the extra LFS data move that is otherwise required for high user buffers.

Indicating support for 64-bit virtual addressing

A PFS indicates support for 64-bit user virtual addressing during initialization with:

```
pfsi_addr64 Indicates the PFS supports 64-bit user virtual addresses in the UIO, IOV, and MSGH structures. PfsiAddr64 in PL/X.
```

A user indicates 64-bit addressing to the PFS with the following fields and structures:

```
u_addr64 Indicates that this UIO, and any associated IOV and/or MSGH when present, uses 64-bit addresses. FuioAddr64 in PL/X.
u_buff64vaddr A 64-bit field that contains the virtual address of the area being passed. FuioBuff64VAddr in PL/X.
```

The IOV and MSGH structures have corresponding 64-bit formats, IOV64 and MSGH64.

When an application program in AMODE 64 calls a z/OS UNIX service, 64-bit user addressing is assumed and is used by the LFS. This does not necessarily mean that the 64-bit address values are actually greater than 2 gigabytes. Most 64-bit addresses will come from C programs that have been compiled with LP64, which makes all longs and pointers 64 bits by default, regardless of whether the program's heap is above the 2-gigabyte line.

osi_copy64 routine

The OSI routine osi_copy64 ("osi_copy64 — Move data between user and PFS buffers with 64-bit addresses" on page 363) helps a PFS deal with 64-bit addresses. It takes 64-bit virtual addresses and operates in much the same way as osi_copyin and osi_copyout. osi_copy64 is a high-performance routine that does not PC into the kernel. It handles 31- or 64-bit user and PFS buffer addresses for AMODE 31 or AMODE 64 PFS callers.

Minimum 64-bit support

The minimum needed by a PFS to be 64-bit supporting is:

- If the only data moves to or from the user address space are done with osi_uiomove, the PFS just needs to set pfsi_addr64 during initialization.
- If osi_copyin or osi_copyout are used for user buffers, the PFS must check the FuioAddr64 flag at each of these calls, and use osi_copy64 or osi_uiomove whenever this flag is on.
- If the PFS does its own MVCSKs and MVCDKs, it must check the FuioAddr64 flag at each of these locations and handle moves with 64-bit addresses; or call osi_copy64 or osi_uiomove at these points. Doing your own moves is, of course, fastest.

Specific considerations for vnode operations

The following vnode operations contain parameters that may contain 64-bit addresses or point to structures that contain 64-bit addresses. Each of these operations has **Fuio** as an input parameter, which may point to a 64-bit user buffer:

- vn_rdwr
- · vn_readdir
- vn_readlink
- vn_sndrcv
- · vn_sendtorcvfrom
- vn_readwritev—the IO vectors passed may be in an IOV or an IOV64 structure.
- vn_srmsg—the message header passed may be an MSGH or an MSGH64 structure.

Note:

- 1. MSGH64 and IOV64 are always used together.
- 2. Whenever FuioAddr64 is on (and FuioRealPage is off):
 - FuioBuff64Vaddr points to a buffer, an IOV64, or an MSGH64.
 - A MSGH64 always points to an IOV64.

Expanded 64-bit time values

As part of the POSIX standards for 64-bit computing, which is known as LP64 (64-bit Longs and Pointers), the time_t data type for file times is expanded to 64 bits in z/OS V1R6. The current signed 31-bit data type will go negative in 2038. Because the 390 system clock will wrap in 2042, there is an issue for PFSes that store time in STCK format.

The z/Architecture® has a 128-bit STCKE that adds one byte to the left of the current 8-byte format; that is, it has five bytes of "seconds", and goes to about the year 36765. An 8-byte POSIX time value goes far beyond that. A 9-byte time field, or the left 8 bytes of the new STCKE, would hold any real times, and an 8-byte POSIX format field would hold anything that could be set by a user.

z/OS UNIX allows existing external time fields that cannot handle the next epoch to wrap. That is, the initial value for the next epoch is zero and the values in those fields increase positively with time. This starts in the year 2038 for 4-byte signed POSIX times and in the year 2042 for unsigned 8-byte STCK times. Many of these fields will have a separate but corresponding time that will not wrap for these dates; for example, an 8-byte POSIX time or an 8 or 16-byte extended STCKE time.

XL C/C++ Runtime Library support

XL C/C++ Runtime Library supports old 31-bit programs and new LP64 programs with a stat structure that contains 4-byte and 8-byte time fields for all five file time values: the POSIX atime, mtime, ctime; and the z/OS UNIX reference time and create time. The old fields could not be expanded in place without changing the offset of all the following fields; new fields were therefore added to the end. When a C program is compiled without LP64, the stat structure is generated with the POSIX names (such as st_atime) on the 4-byte fields; and when it is compiled with LP64, those names coincide with the new 8-byte fields. The unused fields in each compile have dummy names that would not be referenced by the average C program.

There are two separate runtime libraries, compiled from the same source with and without LP64, so that even the runtime library will not reference both field types at the same time.

PFS support

The kernel supports 31-bit and 64-bit programs with the same routines. The PL/X stat structure, BPXYSTAT, has both fields generated; the new fields have new names. BPXYATTR ("BPXYATTR — Map file attributes for v_ system calls" on page 433) also has five new 8-byte time fields:

```
Char(0),
                                /* +A0--- End of Version 1 --- @D2C*/
3 AttrEndVer1
3 AttrStat4
                                 /* +A0 Fourth part of the stat @DAA*/
   5 AttrLP64 ,
                                /* +A0 LP64 Versions
                                                                 @DAA*/
                       Char(8),
     7 AttrAtime64
                                                                 @DAA*/
                                    /*+A8 Access Time
                       Char(8),
     7 AttrMtime64
                                    /*+B0 Data Mod Time
                                                                 @DAA*/
     7 AttrCtime64
                       Char(8),
                                    /*+B8 Medadata Change Time @DAA*/
     7 AttrCreateTime64 Char(8), /*+CO File Creation Time
                                                                 @DAA*/
                       Char(8),
     7 AttrRefTime64
                                     /*+C8 Reference Time
                                                                 @DAA*/
                       Char(8),
                                     /*+A0 May be AttrIno64
                                                                 @DAA*/
                     Char(16), /* +D0 Reserved (1st consider
   5 *
                                                                 @DAA
                                space at +5C,+8D,+94)
/* +E0 End of Version 2
                                                                 @DAA*/
3 AttrEndVer2 Char(0),
                                                                 @DAA*/
```

The associated 4- and 8-byte fields will usually contain the same values, until some time in the year 2038.

The C ATTR structure in BPXYVFSI exactly matches the PL/X Attr:

```
/* +A0 --- End Ver 1 ---
                                                       @P5A*/
        at atime64[8];
                            /* Large Time Fields
                                                        @P5A*/
char
        at_mtime64[8];
                                                       /*@P5A*/
char
        at_ctime64[8];
char
                                                       /*@P5A*/
        at_createtime64[8];
                                                       /*@P5A*/
char
char
        at_reftime64[8];
                                                       /*@P5A*/
        at_rsvd4[8];
                                                       /*@P5A*/
char
                                                      /*@P5A*/
        at_rsvd5[16];
char
                            /* +E0 --- End Ver 2 ---
                                                        @P5A*/
```

PFSs must return both sets of time fields in all output ATTRs. This includes vn_getattr, any osi_attrs, and ReadDirPlus (part of "v_readdir (BPX1VRD, BPX4VRD) — Read entries from a directory" on page 315). The LFS always passes to the PFSs an ATTR that is large enough to hold the 8-byte times (at least of length Attr#Ver2Len). The **stat()** function is performance-sensitive, because it is called so often by

programs in the field, and it is faster for the PFSs to set the five extra fields than for the LFS to check to see if it has been done, and then copy the 4-byte values to the 8-byte fields.

PFSs that support vn_setattr, or setting times at all, must accept 8-byte time values. The AttrLP64Times bit in BPXYATTR indicates that the time value is being passed in the 8-byte fields. Most of these 8-byte time values will still be less than 2 gigaseconds, but they are being passed by LP64 programs. An LP64 program may try to utime() beyond 2 gigaseconds.

PFSs that use BPXXCTME should use the new syntax for large time values. The BPXXCTME macro converts to and from the extended STCKE TOD format with the optional EXTENDED keyword:

```
?BPXXCTME INPUT(TOD|SSE)
    TOD(8ByteArea|16ByteArea)
    SSE(WordArea|DWordArea)
    MICSEC(WordArea)
    EXTENDED(8<,4>|16<,4>) (optional)
```

INPUT indicates the input field, and TOD is a doubleword-aligned 8- or 16- character field containing the input TOD or the converted value. SSE is a word-aligned 4-byte character field or doubleword-aligned 8-byte character field containing the input SSE or the converted value. Table 4 on page 69 shows the TOD and SSE fields with the EXTENDED keyword:

| Table 4. TOD and SSE fields with the EXTENDED keyword | | |
|-------------------------------------------------------|----------------------------------------|--------------------------|
| EXTENDED | TOD | SSE |
| Keyword is omitted | Bytes 1 through 8 of the STCK format | A 4-byte character field |
| EXTENDED(8) | Bytes 1 through 8 of the STCKE format | An 8-byte field |
| EXTENDED(16) | Bytes 1 through 16 of the STCKE format | An 8-byte field |
| EXTENDED(16,4) | Bytes 1 through 16 of the STCKE format | A 4-byte field |

PFS support for reason code error text

The pfsctl function allows a PFS to provide error text for reason codes that are not supported by the kernel for display by the BPXMTEXT utility. The vfs pfsctl command value is pfsctl errortext (0xc000000b).

During initialization, the PFS declares a range of values for the high byte of the reason codes that it issues. To extract error text for a given reason code, the BPXMTEXT utility calls pfsctl, BPX1PCT. For reason codes not supported by the kernel, the LFS looks for a PFS that supports the high byte value and, if found, the LFS forwards the pfsctl call to that PFS for processing.

Indicating PFS support for the error text pfsctl call

To indicate the range of reason codes that it issues, the PFS returns low and high values in the PFSI structure at the time the PFS initializes. High byte values for PFSs are normally assigned by the LFS. The following fields in the PFSI indicate the low and high values for the range of reason codes:

```
/* low value for the PFS reason code high byte */
pfsi_complow char;
pfsi_comphigh char; /* high value for the PFS reason code high byte */
```

These fields should be set to zero if the PFS does not support the pfsctl errortext command.

Passing data on the error text pfsctl call

As with all pfsctl calls, this is a FUIO type of operation. The PFS should assume that the buffer used to pass the request type and receive the response may reside in the user address space and should handle all data accesses and moves appropriately. No SAF Check Privilege call should be made to check authorization for this call.

The following structure, pfsctl et hdr, maps the header of the pfsctl buffer for this command call:

The following values are supported for the pfsctl_et_xxxx request type:

```
pfsctl_et_desc    0  /* request for the error description */
pfsctl_et_action    1  /* request for the action text */
pfsctl_et_modname    2  /* request for the issuing module information */
```

On entry, the beginning of the buffer is mapped by the pfsctl_et_hdr structure. This is used to indicate the type of data being requested and for which reason code.

On return, the requested text starts at the front of the buffer, overlaying the header. The Return_value from the pfsctl call indicates the number of bytes returned in the buffer. If the buffer is not long enough to hold all of the requested text, the service returns only the amount of data that fits in the buffer and sets the Return_value accordingly. There is no explicit indication that data was truncated. The returned text is assumed to be a simple string of text, not null-terminated, and newline characters are not required unless the text has specific formatting requirements. The BPXMTEXT utility will attempt to flow the text and honor newline characters.

PFS support for MODIFY OMVS, PFS

A PFS can support a vfs_pfsctl with command code PC_MODIFYPFS (0xC000001D). This vfs_pfsctl is sent to the PFS for the following operator command:

```
MODIFY OMVS,PFS=<pfsname>,<command_string>
```

vfs_pfsctl is a FUIO type of operation. The FuioBufferAddr and FuioBufferAlet point to a structure that contains the command string that is specified on the MODIFY command, its length, and the CART and CONSOLE ID from the MODIFY command. With this, a PFS in the OMVS address space can receive and process MODIFY command requests.

- For zFS, see <u>z/OS</u> system commands in *z/OS* File System Administration for examples of MODIFY commands that are supported by zFS.
- For TFS, see Managing the temporary file system (TFS) in z/OS UNIX System Services Planning for examples of MODIFY commands that are supported by TFS.

The following structure maps the header of the pfsctl buffer for this command call:

```
typedef struct s pc modify
              pc_modeye[4]";
                                       /*+00 EBCDIC ID - "MODP"
     char
              pc_modlen;
     short
                                       /*+04 Length of pc_modify struct
     short
              pc_modvers;
                                       /*+06 Version number
                                       /*+08 Console id
/*+0C Command And Response Token
     int
              pc_modconsid;
     char
              pc_modcart[8];
                                       /*+14 length of modify string
              pc_modstringlen;
     int
              pc_modstring[120];
                                       /*+18 modify string
     char
  } PC_MODIFY;
                                                                              /* @ELA*/
```

PFS support for running in AMODE 64

A PFS indicates support for running in AMODE 64 during initialization with:

pfsi amode64 Indicates the PFS runs in AMODE 64. PfsiAmode64 in PL/X

A PFS that supports pfsi_amode64 must also support pfsi_addr64 (must support 64-bit user addresses), and must not set pfsi_cpfs (cannot use HOTC).

For PFSes running in AMODE 64, the LFS will call the PFS with R1 pointing to a parameter list of 64-bit addresses. The parameter list and the parameters can be below or above the 2-gigabyte line.

Osi services have support for AMODE 64 PFSes, with the exception of the following:

- · osi_thread
- osi_copyin
- osi_copyout

Chapter 3. PFS operations descriptions

This topic describes each PFS operation, which are arranged in alphabetic order. The C language prototypes and definitions for these operations can be found in Appendix D, "Interface structures for C language servers and clients," on page 465. Assembler definitions are in Appendix B, "Mapping macros," on page 433.

Environment for PFS operations

Each PFS operation (vfs_ and vn_ functions) operates in the following environment:

Environment at entry

| Operation | Environment |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Authorization: | Supervisor state, PSW key 0 |
| Dispatchable unit mode: | Task or SRB, if the PFS has indicated that it supports SRB-mode callers. You cannot assume that vfs or vn routines receive control under the same dispatchable unit as the requestor of the related callable service. For example, unmount() and sync() do not. |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters are in key 0 storage in the primary address space. |

They are not fetch protected.

Registers at entry

The contents of the registers on entry to this operation are as follows:

| Register | Contents |
|----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 0 | Contains the Vnode or VFS operation number. This number is the index of the operation in the vnop table or the vfso table. This number starts with one for the first operation in each table, and has 0x800 added to the VFS operation numbers so that they can be differentiated from the Vnode operations. For example, for vn_lookup R0 is 8 and for vfs_sync R0 is 0x0803. |
| 1 | Parameter list address. |
| 2-12 | Undefined. |
| 13 | Save area address, of a 136-byte save area. |
| 14 | Return address. |
| 15 | Entry address. |
| AR0-15 | Undefined. |

Environment at exit

Upon return from this operation, the entry environment must be restored.

Registers at exit

Upon return from this operation, the register contents must be as follows:

| Register | Contents |
|-----------|----------------------------------------------|
| 2-13 | Restored from the entry values. |
| 0,1,14,15 | Undefined. |
| AR0-15 | Untouched or restored from the entry values. |

C header files

The C header files that are referred to in this section (such as stat.h) can be found in z/OS XL C/C++ Runtime Library Reference.

vfs_batsel — Select/poll on a batch of vnodes

Function

The vfs_batsel operation monitors activity on a batch of vnodes (multiple vnodes) to see if they are ready for reading or writing, or if they have an exceptional condition pending. The vnodes can be for a socket, pipe, regular, or pseudoterminal file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Reserved_1

Supplied parameter

Type:

Integer

Length:

Fullword

The value 0. This parameter is reserved to maintain consistency with the vn_select operation interface.

Function

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies whether this is a batch-select query or a batch-select cancel request, and whether it is a poll or a select request. The values for this field are defined in the BPXYPFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Function specifies the type of select that is being requested:

- Query (SEL_BATSELQ or SEL_BATPOLLQ): The PFS should perform the following for query:
 - 1. Check each of the files in the Batch-Select_Structure to see if any of the specified events for a file can be satisfied immediately. If so, the BSIC Response fields for those files are updated, and the status for any one of them is returned in the Return_value parameter.
 - 2. If there is no immediate status to report for any file in the Batch-Select_Structure, the PFS records that a select is pending for each of the files and sets up to invoke osi_selpost later, when

one of the selected events has occurred. The PFS returns a value of 0 in Return_value after it has performed its internal processing to set up select pending for each of the files.

The occurrence of an event and the subsequent invocation of osi_selpost happen asynchronously on another thread or MVS task.

- Cancel (SEL_BATSELC or SEL_BATPOLLC): The PFS performs the following for cancel:
 - 1. If there is a pending select recorded for a file with the same SelectToken that was specified on a previous query, it must be canceled in such a way that osi_selpost is not invoked.
 - 2. Check each of the files that are specified in the Batch-Select_Structure to see if any of the specified events can be immediately satisfied. If at least one file has status, that status is returned in the Return_value parameter, and the status for each of the selected files is returned in the BSIC Response fields for those files. If a file does not have status, a 0 is returned in the BSIC Response field for that file. If none of the files have status, 0 is returned in the Return_value parameter.

Batch-Select_Structure

Returned parameter

Type:

BSIC

Length:

Calculated: A BSIC header plus one BSIC entry for each selected file.

An area that contains information about the selected files and events. It specifies which files and events are being selected, a SelectToken for each file, a response area for status, and work area pointers for use by the PFS. This area is mapped by the BSIC typedef in the BPXYPFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). The events that can be selected for select requests are:

- SEL_READ: A read that is issued against this file will not block.
- SEL_WRITE: A write that is issued against this file will not block.
- SEL_XCEPT: An exceptional condition, as defined by the particular PFS, has occurred. This could happen when a socket connection becomes inoperative because of network problems, or when the other end of the socket is closed.

For poll requests, the events that can be selected are documented in other manuals (for instance, z/OS XL C/C++ Runtime Library Reference). The mapping for these fields is defined in the BPXYPFSI header file.

For reading and writing, an error condition that would cause the read or write to fail means that the operation will not block and therefore the file is ready for that operation.

If one or more of the selected events are ready for any of the selected files, the PFS immediately returns the status for one of the files in the Return_value parameter, using the same bit mapping that is used in the BSIC Response field.

Reserved 2

Supplied parameter

Type:

Integer

Length:

Fullword

The value 0. This parameter is reserved, to maintain consistency with the vn_select operation interface.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vfs_batsel service returns the results of the operation, as one of the following:

Return_value Meaning

-1

The operation was not successful. This causes the whole select() or poll() request, as made by the application program, to fail. The Return_code and Reason_code values are passed back to the application program.

0

There is no status for any of the files in the Batch-Select Structure, and the operation was successful.

- For guery (SEL BATSELQ or SEL BATPOLLQ): The PFS is set up to invoke osi selpost when the requested event occurs.
- For cancel (SEL_BATSELC or SEL_BATPOLLC): The PFS has canceled the request to invoke osi_selpost, or it was never set up to do so. The PFS will not invoke osi_selpost after returning from this call.

Greater than 0

Status is being returned in the Batch-Select_Structure. The returned status in this parameter has the same format as the BSIC Response field.

- For query (SEL_BATSELQ or SEL_BATPOLLQ): The operation is complete and the PFS will not invoke osi_selpost for this request.
- For cancel (SEL_BATSELC or SEL_BATPOLLC): The PFS has canceled the request to invoke osi_selpost if it had been recorded.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_batsel operation stores the return code. The vfs_batsel operation returns Return_code only if Return_value is -1.For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_batsel operation stores the reason code. The vfs_batsel operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_batsel processing

The vfs_batsel operation is identical to the vn_select operation, except that a batch of files (multiple files) are selected using the Batch-Select_Structure, instead of only one. For information about vn_select, refer to "Select/poll processing" on page 45.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications mentioned in "Finding more information about sockets" on page 2 for the select function.

Specific processing notes

- On the query request, the PFS should save the BSIC SelectToken for each file passed in the Batch-Select_Structure. This token is used both during the cancel request (to delete the request) and when an event occurs that the LFS should be informed of through the osi_selpost function.
- The PFS can use the BSIC entry workptr field in the Batch-Select_Structure to save information about each file during a query request. It can also use the BSIC header workptr field to save information about the entire query (such as an address where it has stored information about this request) so that it can be found during a cancel request. The data is used to correlate the cancel request with its matching query request. This provides an alternative to scanning the PFS control blocks for matching SelectToken values.

Serialization provided by the LFS

None.

Security calls to be made by the PFS

None.

Related services

• "vn_select — Select or poll on a vnode" on page 201

vfs_gethost — Get the socket host ID or name

Function

The vfs_gethost operation gets the ID or the name of the socket host.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Name_length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of the name. If this value is zero, the request is for the host ID. Otherwise, this is the length of the buffer to hold the name. On return, for host name, this field contains the length of the name plus one for the null.

Name

Returned parameter

Type:

String

Length:

Specified by Name_length

An area that contains the name on return, if the host name was requested. This name must be null-terminated by the PFS.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_gethost operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful (for getting the host name).

Greater than 0

The operation was successful (for getting the host ID) and is the identifier of the current host.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_gethost operation stores the return code. The vfs_gethost operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_gethost operation stores the reason code. The vfs_gethost operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_gethost processing

For more information about the semantics of this operation, refer to the publications mentioned in <u>"Finding more information about sockets" on page 2</u> for the gethostid() and gethostname() functions.

Specific processing notes

The PFS determines whether to get the host name or host ID depending on Name_length. A zero length indicates a gethostid() request.

Serialization provided by the LFS

The vfs_gethost operation is invoked with an exclusive latch held on the domain of the PFS.

Security calls to be made by the PFS

None.

vfs inactive - Batch inactivate vnodes

Function

The vfs_inactive disassociates multiple vnodes from the PFS's related inodes.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token, and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See <u>Chapter 6</u>, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

InactBuffer_structure

Supplied and returned parameter

Type:

IAB

Length:

Calculated: An IAB header plus one IAB entry for each selected vnode.

The InactBuffer_structure contains information about the vfs and the vnodes that are to be made inactive. This area is mapped by the IAB typedef in the BPXYPFSI header file (Appendix D).

This structure contains the following fields:

Server_devno

A fullword that contains the device number of this vfs.

Each **Server_devno** is followed by an array of records containing the following information:

Vnode pointer

A pointer to the vnode.

Pfs_token

An eight-byte area that contains the pfs token for this vnode.

Server Vnode

A pointer to the server's vnode.

Return_Value

A fullword in which the vfs_inactive operation returns the results of the operation for the vnode. A nonzero value indicates that the operation was not successful.

InactBuffer_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that supplies the length of the InactBuffer_structure.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vfs_inactive service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_inactive service stores the return code. The vfs_inactive service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_inactive service should support the following error value:

Return_code

Explanation

EIO

An I/O error occurred while accessing the file.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_inactive service stores the reason code. The vfs_inactive service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_inactive processing

"Creating, referring to, and inactivating file vnodes" on page 29 provides an overview of file inactivate processing.

Specific processing notes

- The Return_value for each vnode that is being made inactive is returned in the InactBuf_structure while the results of the vfs_inactive service is provided in the returned parameters.
- If a transient error, such as an I/O error, is encountered, the Return_value should be set to -1. In this case, the request is retried later.
- If a permanent error that prevents the specified file or directory from being used is encountered, Return_value should be set to zero. In this case, all references to the file or directory are removed from the LFS and the request is not retried. The PFS must not issue a signal-enabled wait during inactivate processing. "Waiting and posting" on page 20 provides an overview of wait and post processing.
- If a file's link count is zero, but its open count is not zero, the PFS should ignore the open count and delete the file's data along with the file. This might happen, for example, when an address space is canceled right after vn_open finishes in the PFS, but before the LFS regains control.

Serialization provided by the LFS

The vfs_inactive operation is invoked with an exclusive latch held on the file system containing the vnode.

Security calls to be made by the PFS

None.

Related services

- "osi_wait Wait for an event to occur" on page 415
- "vn_inactive Inactivate a vnode" on page 147

vfs_mount — Mount a file system

Function

The vfs_mount operation activates a file system and returns the root directory vnode_token.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in <u>Appendix D</u>, "<u>Interface structures for C</u> language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

See <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Mount_table

Supplied and returned parameter

Type:

Structure

Length:

Specified by the MTAB.mtab_hdr.cblen field

An area that is used to pass the file system name, mount options, and PFS-specific parameters to the vfs_mount operation. This area is mapped by the MTAB typedef in the BPXYPFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Vnode token

Returned parameter

Type:

Token

Length:

8 bytes

An area in which the vfs_mount service returns the vnode_token for the root directory of the mounted file system.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_mount service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_mount service stores the return code. The vfs_mount service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_mount operation should support at least the following error value:

Return_code

Explanation

EEXIST

A file system with the same name has already been mounted.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_mount service stores the reason code. The vfs_mount service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_mount processing

"Mounting file systems" on page 25 provides an overview of file system mount processing.

Specific processing notes

• The PFS is responsible for the following fields:

token_structure.ts_mount

The PFS should fill in this field with a token that it can use to locate the PFS structures that are associated with the mounted file system. On subsequent calls for files within this file system, the token_structure value contains the token set here by the PFS.

MTAB.mt_filesys or MTAB.mt_ddname

On entry to the PFS, the field MTAB.mt_filesys contains either the blank padded file system name or nulls. On a successful return, if this field is not nulls and it represents an MVS data set name, the field MTAB.mt_ddname should be filled in by the PFS with the dynamically allocated ddname.

If the field MTAB.mt_filesys is nulls on entry to the PFS, the field MTAB.mt_ddname contains the ddname of an allocated MVS data set for the file system. On a successful return, the field MTAB.mt_filesys should be filled in by the PFS with the MVS data set name that is specified on the DD statement.

MTAB.mt_rwmntclient

The read/write sysplex-awareness of file systems is typically determined by the PfsiRWMntClient (or PfsiRWMntSysplex) that the PFS sets during its initialization. A PfsiRWMntClient (or PfsiRWMntSysplex) of 0 typically indicates that the PFS is sysplex-aware for all read/write mounts, and a PfsiRWMntClient (or PfsiRWMntSysplex) of 1 typically indicates that PFS is sysplex-unaware for all read/write mounts. However, if a PFS wants to mount certain file systems as read/write sysplex-aware and other file systems as read/write sysplex-unaware, it can do this by setting the output MTAB.mt_rwmntclient on the primary owner mount, to indicate the read-write sysplex-awareness of a particular file system. An output MTAB.mt_rwmntclient of 0 indicates read/write sysplex-aware, and an output MTAB.mt_rwmntclient of 1 indicates read/write sysplex-unaware.

The output MTAB.mt_rwmntclient is ignored for network PFSes.

MTAB.mt_disablella

The LLA (lookup lookaside) enablement of file systems is typically determined by the PfsiDisableLLA that the PFS sets during its initialization. The PfsiDisableLLA typically indicates whether LLA is enabled or disabled for all file systems. However, if a PFS wants to disable LLA for certain file systems (those that are read/write sysplex-aware) and enable LLA for other file systems (those that are read/write sysplex-unaware), it can do this by setting MTAB.mt_disablella as output on the primary owner mount. An output MTAB.mt_disablella of

0 indicates that the LFS should enable LLA, and an output MTAB.mt_disablella of 1 indicates that the LFS should disable LLA.

The output MTAB.mt_disablella is ignored for network PFSes.

MTAB.mt_samemode

If MTAB.mt_samemode is set by the LFS on input for an owner mount, then the read/write-awareness and LLA for this file system must not be changed by the PFS. The LFS passes the MTAB.mt_rwmntclient and MTAB.mt_disablella as input to indicate the read/write-awareness and LLA-enablement for the file system. MTAB.mt_samemode is set for certain operations where the read/write sysplex-awareness should not be changed by the PFS, like for the vfs_mount on the owner for a samemode remount. Only PFSes that would set the output MTAB.mt_rwmntclient and/or MTAB.mt_disablella need to check the input MTAB.mt_samemode bit.

If every file in this file system has the same values, the PFS is responsible for filling in the MTAB with the following pathconf values (see the IEEE POSIX 1003.1 specification for further details):

MTAB.mt_linkmax

LINK_MAX

MTAB.mt_namemax

NAME_MAX

MTAB.mt_notrunc

POSIX_NO_TRUNC

MTAB.mt chownrstd

POSIX_CHOWN_RESTRICTED

Alternatively, the PFS may meet this responsibility by supporting vn_pathconf.

- The PFS must not issue a signal-enabled wait under the thread invoking vfs_mount.
- "Waiting and posting" on page 20 provides an overview of wait and post processing.
- If the mount is to be completed asynchronously:
 - The PFS must set MTAB.mt_asynchmount on before returning to the LFS. The LFS in turn sets MTAB.mt_asynchmount on before calling the PFS for the second call to vfs_mount.
 - When the mount operation has completed, the PFS indicates this to the LFS by calling osi_mountstatus.
 - The vnode_token must be returned on at least one of the calls to vfs_mount. However, if the PFS chooses to return a nonzero vnode_token on each call, it must be the same token.
 - If asynchronous mount processing in the PFS fails, the PFS should call osi_mountstatus to drive the second call to vfs_mount. When called by the LFS to complete the mount, the PFS should then return the error to the LFS, which deletes all references to the incompletely mounted file system. No call to vfs_umount results.
 - If MTAB.mt_synchonly is set on in the Mount_table, vfs_mount must either complete the mount synchronously or reject the request, returning EINVAL. MTAB.mt_synchonly is always set on for the system root and for mounts that result from MOUNT statements in BPXPRMxx that specify DDNAME.
 - Vfs operations, such as vfs_umount and vfs_statfs, may need to be handled during an asynchronous mount.
- It is not necessary for the PFS to perform security checking during mount processing, because the LFS has already performed all necessary checking.
- The PFS returns an aggregate name, if it has one, from the vfs_mount operation. If mt_aggnameptr is not zero, it points to mt_aggname, which is a 45-byte area where the PFS can put the aggregate name. If the PFS may run on an earlier release, it should test for mt_hdr.cblen > 0x80 before it tests mt_aggnameptr. If read-only mounts of file systems with the same aggregate name should be function shipped to the owning system rather than locally mounted, mt_aggattachrw should be

turned on. If subsequent recovery of this mount should not attempt to attach the aggregate before issuing the vfs_mount, mt_agghfscomp should be turned on.

Serialization provided by the LFS

The vfs_mount operation is invoked with an exclusive latch held on the file system, to ensure that no other operations are attempted upon the file system being mounted. In addition, the LFS ensures that all vfs_mount and vfs_umount calls are serialized.

Note: However, if the mount is asynchronous, there is a time between the start and the end of the mount in which the latch is not held.

Security calls to be made by the PFS

None.

Related services

- "vfs_unmount Unmount a file system" on page 105
- "vn_pathconf Determine configurable path name values" on page 171
- "osi_getvnode Get or return a vnode" on page 372
- "osi_ctl Pass control information to the kernel" on page 365
- "osi_wait Wait for an event to occur" on page 415

vfs_network — Define a socket domain to the PFS

Function

The vfs_network operation is called as a result of the NETWORK statement in the BPXBPRMxx parmlib member that is used to start z/OS UNIX. It defines information about a socket domain to the PFS that is supporting it.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Network_structure

Supplied parameter

Type:

NETW

Length:

Specified by netw.netw_hdr.cblen

The Network_structure is an area, built during initialization, that contains the information that is included on the NETWORK statement—the socket domain name and number and the maximum number of sockets. This area is mapped by the NETW typedef in the BPXYPFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_network operation returns the results of the operation as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_network operations stores the return code. The vfs_network operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_network operation should support at least the following error values:

Return_code Explanation

EAFNOSUPPORT The address family that was specified in the Network_structure is not supported by this PFS.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_network operation stores the reason code. The vfs_network operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_network processing

For information about the vfs_network call, refer to "Activating a domain" on page 43.

Specific processing notes

The PFS should ensure that it does not do any blocking waits during its processing.

The PFS is responsible for returning two fields set so that they can be used for subsequent processing. These fields are:

NETW.nt_localremote

An indication of whether the communication done by this PFS is local or remote. Turn the bit on to indicate remote communication.

TOKSTR.ts_mount

The 8-byte token that is returned by the PFS and used on all subsequent calls to this PFS. This token is used by the PFS to locate the PFS structures that are associated with this network.

Serialization provided by the LFS

The logical file system ensures that only one vfs_network statement is processed at a time. Further, the PFS does not receive any socket requests specifying this domain until the vfs_network operation completes.

Security calls to be made by the PFS

None.

vfs_pfsctl - PFS control

Function

The vfs_pfsctl operation passes control information to the PFS.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure contains the PFS's initialization token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Command

Supplied parameter

Type:

Integer

Length:

Fullword

The command indicates the function that is to be performed by the PFS.

User_IO_structure

Supplied parameter

Type:

Structure

Length:

Specified by the UIO.u_hdr.cblen field

An area that is to be used by the vfs_pfsctl service to determine the buffer address, length, storage key, and other attributes of the argument that is passed by the caller of pfsctl (BPX1PCT). This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_pfsctl operation returns the results of the operation, as one of the following codes:

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

0 or greater

Can be used by the PFS to return the length of the information that is being returned in a modified argument buffer.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_pfsctl operation stores the return code. The vfs_pfsctl operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_pfsctl operation should support at least the following error values when the situation applies:

EMVSPARM

The command or argument parameters are incorrect.

The address of the argument buffer is incorrect, or the user is not authorized to read or write to that location.

EINTR

The service was interrupted by a signal.

EPERM

Permission was denied. The calling program does not have sufficient authority for the service that was requested.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_pfsctl operation stores the reason code. The vfs_pfsctl operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS product.

Implementation notes

Overview of vfs_pfsctl processing: This function is like vn_ioctl, except that the data is directed to the PFS itself rather than to, or for, a particular file. A program can communicate with the PFS through the pfsctl (BPX1PCT) callable service, which is converted by the LFS into vfs_pfsctl. An example of this would be a program that is provided with a particular PFS product that displays performance statistics for that PFS.

Avoid passing addresses with this service, and instead include all data in the buffer.

Negative command values are reserved for use by the LFS.

Command values of less than 0x40000000 are considered to be authorized functions, and a privilege check is made. See the security calls to be made by the PFS section.

Specific processing notes: The token_structure of this operation contains only the initialization token.

The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u_hdr.cblen

Specifies the length of the user IO structure

UIO.u_buffaddr

Specifies the address of the argument buffer

UIO.u buffalet

Specifies the ALET of the argument buffer

UIO.u count

Specifies the length of the argument buffer

UIO.u asid

Specifies the ASID of the caller

UIO.u key

Specifies the storage key of the argument buffer

Serialization provided by the LFS: None.

Security calls to be made by the PFS: None expected by the LFS.

When the command value is less than 0x40000000, the LFS calls SAF's Check Privilege callable service to determine if the caller has appropriate privileges before it invokes the PFS with vfs_pfsctl. The results of this call are passed to the PFS using the osi_privileged bit.

If the osi_privileged bit is on, the user has appropriate privileges. If the PFS wishes to restrict this function or certain command values, it can check this bit.

In a shared file system environment, if there is an attempt to move z/OS UNIX ownership to a target system that has a local mount to the PFS, on the target system the LFS sends the PFS a vfs_pfsctl with a command code of PC#OwnerOK. This sets UIO.u_buffaddr to the address of an 8-byte area containing the PFS mount token returned on the vfs_mount, identifying the file system, and UIO.u_count to a length of 8. If the PFS supports this vfs_pfsctl and it determines that this system should not be the z/OS UNIX owner of the input file system, the PFS should indicate that it is not valid for this system to assume ownership by returning a Return_value of -1, a Return_code of ENOMOVE, and a unique Reason_code describing the error. This will result in the move failing. For any other output from the vfs_pfsctl, the move will proceed.

Related services

None.

vfs_recovery — Recover resources at end-of-memory

Function

The vfs_recovery operation permits a PFS to recover resources when a user address space enters end-of-memory processing while a request to that PFS is active.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred hdr.cblen.

The Audit structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Recovery area

Supplied parameter

Type:

String

Length:

8 bytes

A copy of the Recovery area that was filled in by the PFS during the operation that was interrupted. This area is mapped by osirtoken in BPXYPFSI (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_recovery operation returns the results of the operation, as one of the following:

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Fullword

A fullword in which the vfs_recovery operation stores the return code. The vfs_recovery operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_recovery operation stores the reason code. The vfs_recovery operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_recovery processing

"Recovery considerations" on page 23 provides an overview of recovery processing, and discusses the flow for vfs_recovery in particular.

Specific processing notes

When an active request to the PFS is interrupted in a situation where normal ESTAE processing is bypassed by MVS, the PFS may have resources, such as storage and locks, that are left in a state that will cause problems for other users.

To allow the PFS a chance to clean up if this should happen, a Recovery_area is passed on every operation, through the osi_rtokptr pointer in the OSI_structure, where the PFS can record its resources or store a pointer to a recovery block. Any information that is stored in this area by the PFS during an operation is passed back to the PFS via the Recovery_area parameter of vfs_recovery if the operation is interrupted by end-of-memory for the user address space.

The OSI Work Area and the Pre-initialized C Environment Stack, if used, are still addressable and left as they were at the time of the abend. These areas can be used to hold a recovery block whose address is placed in the Recovery_area. The vfs_recovery operation is invoked with its own areas like any other operation.

Refer also to "vn_recovery — Recover resources after an abend" on page 188, which is the operation that is invoked during normal ESTAE processing.

There is no EOM recovery for the vfs_recovery operation itself. The operation is invoked with osi_rtokptr pointing to a new recovery area that can be used for standard PFS abend recovery; that is, with vn_recovery.

The PFS is not called if the file system has been unmounted between the original vnode operation and the running of the EOM resource manager. This can only happen if the user was in a signal-enabled wait at the time the address space was terminated. It is expected that the PFS has cleaned up all its file-system-related resources during vfs_umount.

See also the OSI and osirtoken structures in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465.

The state of any file-level objects that might have been involved with the interrupted operation is unknown at the time vfs_recovery is invoked.

vfs_recovery for an EOM event is limited in the amount of time that the operation may process. The current time limit is 3 minutes. If the vfs_recovery operation exceeds this limit, then the EOM task that the vfs_recovery is executing on is detached and a vfs_pfsctl with a command code of PC_THREADUNDUB is issued. The pfsctl data includes the original operation Recovery_area and

associated file system mount token. Refer to the s_pc_undub structure mapping in the BPXYPFSI. No serialization is used for this pfsctl; there can be at most one pfsctl active for each process in EOM. The Recovery_area and file system mount token might not be valid at this point. It is up to the PFS to validate these. Furthermore, the PFS must not enter an unbounded wait for this pfsctl. After the pfsctl completes the original operation OSI Work Area and the Pre-initialized C Environment Stack, if used, are no longer addressable.

Serialization provided by the LFS

The vfs_recovery operation is invoked with a shared latch held on the file system represented by the token_structure.

Any file-level objects that may have been involved with the interrupted operation are not serialized.

Security calls to be made by the PFS

None.

vfs_socket — Create a socket or a socket pair

Function

The vfs_socket operation creates one socket or two related sockets.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping

OSI structure

Supplied and returned parameter

Type:

OSI

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Domain

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains a number that represents the address family the socket is to be created for. The values defined for this field are mapped by **socket.h**.

Type

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains a number that represents the socket type. The values defined for this field are mapped by socket.h.

Protocol

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains a number that represents the protocol to be used with the socket.

Array_dimension

Supplied parameter

Type:

Integer

Fullword

A fullword that specifies the number of Vnode_tokens to get. The allowable values for this field are 1 (for the socket call) and 2 (for the socketpair call).

Vnode token array

Returned parameter

Type:

Token

Length:

16 bytes

A two-element array that contains the one or two Vnode_tokens obtained.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_socket operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs socket operation stores the return code. The vfs socket operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_socket operation should support at least the following error values:

| Return_code | Explanation |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EAFNOSUPPORT | The address family that is specified by Domain is not supported by this PFS. |
| EINVAL | The socket type that was specified is not supported; or the Array_dimension that was specified is incorrect. If the PFS does not support the socketpair() call, an Array_dimension of 2 is incorrect. |
| EPROTONOSUPPORT | The protocol that was specified is not supported. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_socket operation stores the reason code. The vfs_socket operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_socket processing

See <u>"Creating, referring to, and closing socket vnodes" on page 44</u> for general information about sockets.

For more information about the semantics of this operation, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the socket() and socketpair() functions.

Specific processing notes

If the PFS does not support socketpair(), the LFS simulates this function by creating and connecting two separate sockets. This is done in response to a Return_Code of EINVAL when Array_dimension is two.

Serialization provided by the LFS

The vfs_socket operation is invoked with a shared latch held on the domain of the PFS.

Security calls to be made by the PFS

None.

Related services

• "vn_close — Close a file or socket" on page 130

vfs_statfs — Get the file system status

Function

The vfs_statfs operation returns status information about a mounted file system.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Fsattr structure

Supplied and returned parameter

Type:

FSATTR

Length:

Specified by FSATTR.fs_hdr.cblen

An area in which the vfs_statfs operation returns the file system status information. This area is mapped by the FSATTR typedef in the BPXYVFSI header file (see <u>Appendix D, "Interface structures for C language servers and clients,"</u> on page 465).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_statfs operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_statfs operation stores the return code. The vfs_statfs operation returns Return_code only if Return_value is -1.For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_statfs operation stores the reason code. The vfs_statfs operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_statfs processing

The vfs_statfs operation returns information about the status of the file system.

To account for different release levels, the PFS should zero out the FSATTR area and set fields it understands only up to the smaller of:

- the input area's length, from the FSATTR length subfield
- the PFS's native FSATTR length (the one with which it was compiled)

The input area's FSATTR length subfield should be updated to reflect the amount of data that is returned, or zeroed out. The PFS must not refer to fields beyond the input FSATTR's length, as specified in its length subfield.

Specific processing notes

- The value that is returned in FSATTR.fs_hdr.cblen must match the amount of valid data that is returned in the Fsattr_structure.
- When a Return_Value of 0 is returned, the PFS is responsible for returning valid data in at least the following fields in the FSATTR:
 - FSATTR.fs_blocksize
 - FSATTR.fs_totalspace
 - FSATTR.fs_usedspace
 - FSATTR.fs_freespace

- vfs_statfs may be called before the mount process completes for a file system that is being mounted asynchronously. If the PFS is unable to provide valid data, the PFS must return a Return_value of -1, along with a Return_code of EAGAIN.
- Serialization provided by the LFS

The vfs_statfs operation is invoked with a shared latch held on the mounted file system.

• Security calls to be made by the PFS: None.

vfs_sync — Harden all file data for a file system

Function

The vfs_sync operation writes to disk (or otherwise stabilizes) all changed data in a buffer cache for files in a mounted file system.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vfs_sync service returns the results of the operation as one of the following return_values:

-1

The operation was not successful. The Return_code and Reason_Code values must be completed by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_sync service stores the return code. The vfs_sync service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_sync service should support at least the following error values:

Return_code

Explanation

EROFS

The file system is mounted read-only.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_sync service stores the reason code. The vfs_sync service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS product.

Implementation notes

Overview of vfs_sync processing

vfs_sync writes to non-volatile storage (usually disk) all modified data for each file in the mounted file system that is indicated by the mount token in the input token_structure. The PFS can use the synch daemon to synchronize modified data at regular intervals, by specifying the desired interval in the MTAB during the mount operation.

A PFS could perform vfs_sync processing asynchronously, although this is not recommended. The osi_usersync flag in the OSI can be set to indicate to the PFS that the vfs_sync request is the result of a user request, rather than a timer pop. If this bit is set, the PFS must complete vfs_sync processing before it returns from the call.

To allow for timer-driven cleanup, vfs_sync is called for read-only file systems also.

Specific processing notes

Data should be completely hardened before vfs_sync returns to its caller.

Serialization provided by the LFS

The vfs_sync operation is invoked with an exclusive latch held on the mounted file system.

Security calls to be made by the PFS

None.

The osi_quiesce flag in the OSI is set if the vfs_sync is the result of a user quiesce.

Related services

• "vn_fsync — Harden file data" on page 139

vfs_unmount — Unmount a file system

Function

The vfs_unmount operation unmounts a file system and inactivates the root vnode.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Unmount_options

Supplied parameter

Type:

Integer

Length:

Fullword

An area that is used to pass the options that are to be used to unmount the file system that is specified in Token_structure. The values for this parameter are defined in the stat.h header.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_unmount service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_unmount service stores the return code. The vfs_unmount service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_unmount operation should support at least the following error value:

Return_code

Explanation

EIO

An I/O error occurred while the file system was being unmounted.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vfs_unmount service stores the reason code. The vfs_unmount service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vfs_unmount processing

"Unmounting file systems" on page 27 provides an overview of file system unmount processing.

Specific processing notes

The PFS cannot issue a signal-enabled wait during unmount processing. <u>"Waiting and posting" on page</u> 20 provides an overview of wait and post processing.

It is not necessary for the PFS to perform security checking during unmount processing, because the LFS has already performed all necessary checking.

A file system that is being mounted asynchronously may be unmounted before the mount process completes. Consequently, if the PFS returns only the vnode_token on the second call to vfs_mount, vfs_unmount must be capable of successfully unmounting a file system without reference to its inode token.

If vfs_umount is being invoked for a remount (MT_REMOUNT or OSI_REMOUNT), the PFS receives a vfs_mount for the same file system as soon as the vfs_umount completes. This is followed by vfs_vgets to recreate the vnode-inode pairs that were active at the time of the unmount operation. If a file was open at the time of the remount, the vnode's open counter is reestablished through calls to vn_open.

The PFS does not have to do anything special for remount; however, for performance reasons, it may want to maintain some resources at vfs_umount in anticipation of reusing them for the next vfs_mount. Socket or RPC sessions are examples of resources that might be worth maintaining.

If the PFS cannot support remount, it should reject the vfs_umount request. One reason for not supporting remount is that the PFS would not complete the following vfs_mount synchronously.

Serialization provided by the LFS

The vfs_unmount operation is invoked with an exclusive latch held on the file system, to ensure that no other operations are attempted upon the file system that is being unmounted. In addition, the LFS ensures that all mount and unmount operations are serialized.

• Security calls to be made by the PFS: None.

Related services

- "osi_wait Wait for an event to occur" on page 415
- "vfs_mount Mount a file system" on page 84

vfs_vget — Convert a file identifier to a vnode Token

Function

The vfs_vget operation returns a vnode token for the file or directory that is represented by the input file identifier (FID).

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file system (VFS) that is being operated on. It contains the PFS's initialization token and mount token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

File_identifier

Supplied parameter

Type:

FID

Length:

8 bytes

The name of an 8-byte area containing the file identifier of the file or directory for which a vnode token is to be returned. This area is mapped by the FID typedef in the BPXYVFSI header file (see <u>Appendix</u> D, "Interface structures for C language servers and clients," on page 465).

Vnode token

Returned parameter

Type:

Token

Length:

8 bytes

Vnode_token is used to return the vnode token that corresponds to the input FID.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vfs_vget service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. This causes the vfs_vget request to fail. The Return_code and Reason_Code are returned to the caller.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vfs_vget service stores the return code. The vfs_vget service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vfs_vget service should support at least the following error values:

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------|
| ENOENT | The file indicated by the File_identifier does not exist in the mounted file system that is indicated by token_structure |
| EIO | An input/output error occurred while attempting to access data pertaining to the file indicated by the File identifier. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vfs_vget service stores the reason code. The vfs_vget service returns Reason_code only if Return_value is-1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Implementation notes are as follows:

Overview of vfs_vget processing

Given a file identifier as input, vfs_vget returns a vnode token that refers to the file. The file identifier uniquely identifies a file in a particular mounted file system. Its validity persists across mounting and unmounting of the file system, as well as z/OS UNIX re-IPLS. This distinguishes the file identifier from the vnode token, which relates to a file in active use, and whose validity persists only until the token is released via vn_inactive. The FID for a file is created by the PFS and returned in the ATTR structure, which is mapped by typedef ATTR in the BPXYVFSI header file (see) by vn_getattr.

Specific processing notes

An FID uniquifier of zero refers to the node that matches the st_ino value of that FID.

Serialization provided by the LFS

The vfs_vget operation is invoked with a shared latch held on the mounted file system.

Security calls to be made by the PFS

None.

Related services

• "vn getattr — Get the attributes of a file" on page 142

vn_accept — Accept a socket connection request

Function

The vn_accept operation accepts a connection request for a socket server from a socket client. It returns a new socket descriptor.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Sockaddr length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

A fullword that supplies the length of the Sockaddr buffer and returns the length of the Sockaddr structure that is returned.

Sockaddr

Supplied and returned parameter

Type:

SOCK

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. On return, it contains the address that was used for this operation. For an example of this mapping for AF_INET, see **in.h**.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

Vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

An area in which a token that represents the newly created socket is returned.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_accept operation returns the results of the operation, as one of the following:

Return_value Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_accept operation stores the return code. The vn_accept operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_accept operation should support at least the following error values:

| Return_code | Explanation |
|-------------|------------------------------------------------------------------------------------------------------------------|
| EINTR | The request was interrupted by a signal. |
| EINVAL | An incorrect request, such as a socket for which a listen has not been issued (that is, a server), was received. |
| EWOULDBLOCK | The operation would have required a blocking wait, and this socket was marked as nonblocking. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_accept operation stores the reason code. The vn_accept operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_accept processing

- For more information on vn_accept, refer to <u>"Creating, referring to, and closing socket vnodes" on</u> page 44.

For more information on the semantics of this operation for a POSIX-conforming PFS, refer to the publications mentioned in <u>"Finding more information about sockets" on page 2</u> for the accept function.

- The vn_accept service can be used from a multithreaded server, that is, a server with several threads simultaneously calling accept() on the same socket. The PFS must handle queuing for vn_accept requests on the same socket that are waiting to be satisfied. When a connection arrives it is given to one of the waiting vn_accept requestors. All the server threads are expected to be equal; their requests may be satisfied in any order.

Serialization provided by the LFS

The vn_accept operation is invoked with an exclusive latch held on the vnode of the socket.

• Security calls to be made by the PFS: None.

Related services

• "vn_listen — Listen on a socket" on page 156

vn_access — Check access to a file or directory

Function

The vn_access operation checks whether the calling process has the requested access permission to the specified file or directory.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Access_intent

Supplied parameter

Type:

Integer

Length:

Fullword

An input structure passed through to the SAF Check Access callable service by the vn_access operation. The values for this parameter are defined in **unistd.h.**

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_access service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_access service stores the return code. The vn_access service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_access operation should support at least the following error value:

Return_code

Explanation

EACCES

The caller does not have the requested access to the specified file or directory.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_access service stores the reason code. The vn_access service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

· Overview of vn_access processing

"Security responsibilities and considerations" on page 12 provides an overview of file access checking.

For more information on the semantics of this operation for a POSIX-conforming PFS, refer to the access () function in the POSIX.1 standard (IEEE Std 1003.1-1990).

Specific processing notes

The PFS should provide reason codes that distinguish between the SAF reason codes:

- User is not authorized to access the file.
- Input that is not valid.

Serialization provided by the LFS

The vn_access operation is invoked with a shared latch held on the vnode.

· Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to check that the user has the requested access to the file or directory.

vn_anr — Accept a socket connection and read the first block of data

Function

The vn_anr operation accepts a connection request for a socket server from a socket client and reads the first block of data.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

```
vn_anr (Token_structure,
OSI_structure,
Audit_structure,
Anr_addrs
User_IO_structure
Open_flags,
Acp_token,
Return_value,
Return_code,
Reason_code)
```

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more information about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that supplies the bits associated with the socket. The defined values for this field are mapped by fcntl.h.

Acp_token

Supplied and returned parameter

Type:

Token

8 bytes

An area that is used in one of two ways:

- The LFS passes the PFS's token for a reusable socket.
- The LFS passes a value of 0, and the PFS returns the Vnode token for a new accepted socket.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u hdr.cblen.

An area that contains the buffer parameters for the receive operation that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). For more information about how the fields in this structure are processed, see the specific processing notes section in "Implementation notes for vn anr" on page 120.

Anr addrs

Supplied parameter

Type:

struct anr_addrs

Length:

sizeof(anr_addrs)

A structure that describes the remote and local socket addresses. This structure contains the following fields:

Field

Description

Remote_sockaddr_length

A fullword that supplies the length of the Remote_sockaddr buffer that is pointed to by Remote_sockaddr_ptr. On return, this parameter contains the length of the socket address that was put in the Remote_sockaddr buffer.

If the value of Remote_sockaddr_length is 0, the Remote_sockaddr is not to be returned.

Remote sockaddr ptr

A pointer to the Remote_sockaddr buffer. On return, this buffer contains the socket address of the remote socket that has just connected.

Local_sockaddr_length

A fullword that supplies the length of the Local_sockaddr buffer that is pointed to by Local_sockaddr_ptr.

On return, this parameter contains the length of the socket address that was put in the Local_sockaddr buffer.

If this value is 0, the Local_sockaddr is not to be returned.

Local_sockaddr_ptr

A pointer to the Local_sockaddr buffer. On return, this buffer contains the socket address of the new local socket that was just created.

msg_flags

A fullword that supplies the message flags mapped by BPXYMSGF. On return this parameter contains the updated message flags. (For more information, see Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_anr operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was either not successful or, when Return_code is EINTRNODATA, partially successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful; the value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_anr operation stores the return code. The vn_anr operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_anr operation should support at least the return codes that are listed in Table 5 on page 119.

Table 5. List of return codes for vn_anr

| • | · – |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Return_code | Explanation |
| EFAULT | The address of one of the buffers is not in addressable storage. |
| EINTR | A signal arrived before a connection was assigned to this request. |
| EINTRNODATA | A signal arrived after a connection was assigned to this request, but before any data arrived. The connection has been established. The result of this call is equivalent to a successful vn_accept. |
| | This condition does not occur in a PFS that does not assign arrived connections to a vn_anr request until some data has also arrived. |
| EINVAL | An incorrect parameter was specified. |
| EWOULDBLOCK | A new connection has been established but the SO_RCVTIMEO timeout value was reached before any data arrived. The result of this call is equivalent to a successful vn_accept. |
| | This condition does not occur in a PFS that does not assign arrived connections to a vn_Anr request until some data has also arrived. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_anr operation stores the reason code. The vn_anr operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn_anr

Overview of vn_anr processing:

The vn_anr operation is a functional combination of the vn_accept and vn_rdwr operations, in that an inbound connection is accepted to create a new socket and the first block of data is read on that socket. The output is the new connected socket and the data.

The vn_anr operation is generated from an application call to the accept_and_recv callable service (BPX1ANR). The accept_and_recv callable service is designed to work with the send_file service (BPX1SF) to provide an efficient file transfer capability for connection-oriented servers with short connection times and high connection rates. See accept_and_recv (BPX1ANR, BPX4ANR) — Accept a connection and receive the first block of data in z/OS UNIX System Services Programming: Assembler Callable Services Reference for more information.

The vn_anr operation is intended to be used from a multithreaded server, that is, a server with several threads simultaneously calling accept_and_recv() on the same socket. The PFS must handle queuing for vn_anr requests on the same socket that are waiting to be satisfied. When a connection and its first data have arrived, the connection and data are given to one of the waiting vn_anr requesters. All of the server threads are expected to be equal, and their requests may be satisfied in any order. In particular, LIFO order would reduce the serialization necessary to manage the requester queue.

The PFS does not complete the vn_anr operation until the first data has arrived on the new connection or a signal arrives for this thread. The listening socket must be in blocking mode; this requirement is enforced by the LFS.

When socket reuse is supported by the PFS, the Acp_token parameter is used to pass the PFS's token for the socket that is being reused. When reuse is not supported, or when a reusable socket is not supplied by the application, the Acp_token parameter is used to return the vnode token of the new socket that is created. In this case, the input Acp_token is 0, and the output Acp_token is basically the same as the Vnode_token parameter of the vn_accept operation.

Specific processing notes

A PFS that does not support socket reuse does not have to be coded to reject vn_anr requests that attempt to reuse a socket. A reusable socket is one that was closed by a prior write-type operation that specified the REUSE flag. If the PFS does not honor the REUSE flag, it is assumed that the PFS does not support reuse, and the socket is closed in the normal way. Consequently, the Acp_token parameter would be 0 on a subsequent vn_anr request.

Because the vn_anr operation is a combined operation, it can be interrupted between the connection arrival and the data arrival. If the PFS irrevocably associates a new connection to a vn_anr request before any data has arrived and is subsequently interrupted by a signal, it may return the connection via Acp_token, and set a Return_value of -1 and a Return_code of EINTRNODATA. It is strongly recommended that the PFS not assign connections to vn_anr requests until data has arrived, because doing so ties up a server's worker threads while the PFS is waiting for the data to arrive.

If an application uses both accept() and accept_and_recv() calls on the same socket from several threads at the same time, the results are allowed to be unpredictable. Depending on PFS design and timing, the vn_accept and vn_anr calls may be satisfied in any order. Because it is not recommended that connections be assigned to vn_anr requests until the first data has arrived, it is possible that vn_accept requests could consume all arriving connections.

Specific processing notes

The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file).

UIO.u_hdr.cblen

Specifies the length of the UIO.

UIO.u buffadr

Specifies the address of the user's buffer.

UIO.u_count

Specifies the size of the user's buffer. If this value is 0, no read is done, and vn_anr is functionally equivalent to vn_accept. In this case, the rest of the UIO fields should be ignored.

UIO.u_asid

Specifies the ASID of the user.

UIO.u rw

Set to 0, specifying a read request.

UIO.u key

Specifies the storage key of the caller.

The Remote_sockaddr, Local_sockaddr, and data buffer are all optional.

Serialization provided by the LFS

The vn_anr operation is invoked with an exclusive latch held on the listening vnode if latching is requested by this PFS.

Security calls to be made by the LFS

None.

Related services

• "vn_listen — Listen on a socket" on page 156

vn_audit - Audit an action

Function

The vn_audit operation audits the action that is indicated by the audit_structure.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

vn_audit (Token_structure, OSI_structure, Audit_structure, Return_value, Return_code, Reason_code)

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_audit operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Fullword

A fullword in which the vn_audit operation stores the return code. The vn_audit operation returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_audit operation stores the reason code. The vn_audit operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn audit

Overview of vn_audit processing

- The vn_audit operation calls the SAF Audit interface to write an audit record.
- The Audit_structure contains a code that identifies the function that is being audited, defined in IRRPAFC.

Serialization provided by the LFS

The vn_audit operation is invoked with a shared latch held on the vnode of the file.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Audit callable service to write the audit record.

vn_bind — Bind a name to a socket

Function

The vn_bind operation associates a name with a socket.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Sockaddr_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of sockaddr.

Sockaddr

Supplied parameter

Type:

SOCK

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. It contains the address that is to be used for this operation. For an example of this mapping for AF_INET, see in.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_bind operation returns the results of the operation, as one of the following:

Return_value

Meaning

_1

The operation was not successful. The Return_code and Reason_Code values must be completed by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_bind operation stores the return code. The vn_bind operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_bind operation should support at least the following return codes that are listed in <u>Table 6 on</u> page 125

Table 6. List of return codes for vn_bind

| Return_code | Explanation |
|--------------|---------------------------------------------------------|
| EAFNOSUPPORT | The address family that was specified is not supported. |
| EINVAL | The length of the name is either too short or negative. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_bind operation stores the reason code. The vn_bind operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn_bind

Overview of vn_bind processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the bind() function.

Specific processing notes

An unbind flag can be passed in the first word of the system data area of the Token_structure, ts_sysdl. A value of 1 in this word indicates that the socket should be reset to an unbound state, if possible. If the socket can be reset to an unbound state, then a subsequent vn_bind call with a different Sockaddr might be successful. If the socket cannot be unbound, the call should be rejected. All other parameters are the same as on a successful vn_bind call. There is no external application

interface for this function; it is used internally by the Common INET (CINET) layer so that CINET can try to place an application socket back into a state where another call to bind() may succeed after a bind() has succeeded on some transports but failed on others.

A bind with source address selection flag can be passed in the first word of the system data area of the Token_structure, ts_sysd1. A value of 2 in this word indicates that the socket should be bound using the source address selection preferences. (bind2addrsel())

The function specifies the destination IP address. When this function is used, the socket is bound to the "best" source address for the provided destination IP address.

The caller's suggestion of "best" source address is set by using the setsockopt () call with the IPv6 socket option Sock#IPV6_ADDR_PREFERENCES. Port number is irrelevant for bind2addrsel() function.

The return value, return code, and reason code are same as the bind() operation. The external application interface for this function is the BPX1BAS, BPX4BAS, and bind2addrsel() functions. See these functions in z/OS UNIX System Services Programming: Assembler Callable Services Reference for more details.

Serialization provided by the LFS

The vn_bind operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

When a program specifies a port value less than 1024 decimal, the PFS must call SAF's Check Privilege function to verify that the caller has the authority to do so.

vn_cancel — Cancel an asynchronous operation

Function

The vn_cancel operation cancels the wait for an asynchronous operation to complete, or cancels the remaining portion of an operation after the I/O completion has been scheduled.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

VnCan_Flags

Supplied parameter

Type:

String

Length:

4 bytes

Control flags for this cancellation. Refer to the vncanflags structure in BPXYPFSI.

• vncanforce: This flag specifies whether a normal or forced cancellation is being requested:

- 0- Normal Cancel:

Only the wait for completion is being canceled; otherwise the operation is to proceed normally. If the PFS finds the request on a waiting queue, it is to be removed from the queue and completed with a return code of ECANCELED. That is, osi_sched should be called, and the normal flow for a failed request should be followed. Note that if it is the PFS's custom to handle asynchronous failures in Part 2, it may call osi_sched with success and return ECANCELED from the Part 2 call.

If the PFS does not find the request on a waiting queue, it should take no action whatsoever. The request is completing, or has completed, normally and should not be interrupted.

- 1- Forced Cancel and Cleanup:

Part 2 is not run for this operation, usually because the user's process is terminating. The PFS should remove the request from any waiting queues, and discard all buffers and other resources

that were allocated to this request. Regardless of whether the request was found on the waiting queues, the PFS must clean up the request if it is still active.

PFS_AsyTok

Supplied parameter

Type:

String

Length:

8 bytes

A copy of the PFS's Asynchronous I/O Request Token, which identifies the request that is being canceled.

This is the token that was originally passed by the PFS to the LFS via a call to osi_upda during Part 1 of the asynchronous operation. This is also the same token that is passed in osi_asytok on Part 2 of an asynchronous operation to identify the request to the PFS.

LFS_AsyTok

Supplied parameter

Type:

String

Length:

8 bytes

A copy of the LFS's Asynchronous I/O Request Token, which was originally passed to the PFS in the osi_asytok field on Part 1 of the request that is being canceled.

This token has presumably been saved by the PFS in its request structure during Part 1, since it is needed for osi_sched, and can be used to validate the PFS request structure. The PFS's original request structure must be validated on vn_cancel because the original operation might have finished by the time the vn_cancel reaches the PFS, and therefore its request structure might have been already freed or reused for another operation. Once cancel is started for a request, the LFS does not reuse its token until after the cancel has completed.

The PFS may also, of course, perform this validation on its own and ignore the LFS_AsyTok if it is so designed. A request structure could be validated, for instance, with a structure sequence number that is included within the PFS_AsyTok, or by running a chain of active request blocks.

For more information see the processing notes in this topic.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_cancel operation returns the results of the operation, as one of the following:

Return_value

Meaning

0

The request was found.

-1

The request was not found.

Generally, vn_cancel is not called after osi_sched has been called, but there is a race condition between these two acts and so this Return_value is really not very definitive. For more information, see the processing notes.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_cancel operation stores the return code. The vn_cancel operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_cancel operation should support at least the following error value:

Return_code

Explanation

EINVAL

The PFS_AsyTok is not valid.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_cancel operation stores the reason code. The vn_cancel operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_cancel processing

"Asynchronous I/O processing" on page 55 provides an overview of asynchronous I/O, and discusses the flows that are related to vn_cancel.

Specific processing notes

- Vn_cancel is for one specific request only.
- Only requests that originally had OsiAsy1=ON are potentially cancelable.
- The normal cancel only "pushes through" the original request, and does not attempt to abort it if it is not blocked.
- Vn_cancel is not an asynchronous operation in the sense of the OsiAsy1 and OsiAsy2 bits. It is also not normally a blocking operation. If the original request is found on a waiting queue, it may be removed and osi_sched() called, on another thread while vn_cancel returns to the LFS.
- Vn_cancel must contend with situations in which a thread may be calling osi_sched, or an SRB may be running Part 2 of the original request. This can be a problem in either case, if the PFS is about to free up the structures that are related to the original request and the PFS_AsyTok. Hopefully, the original request structure can be validated or not used directly, in order to avoid introducing additional serialization points into the main line path just to deal with a potential cancel. For instance, for a normal cancel, only requests that are found on a waiting chain need be referenced directly, and for cancel force some cleanup may be able to be deferred to vn_close.

Technically, though, because of fork() and inherited descriptors, vn_cancel(Force) might not soon be followed by vn_close. However, it would be rather rare for an application in this position to carry on. The results of the application would be unpredictable because of timing; and at a minimum it would have to expect data loss, since the termination could as easily have occurred on entry to its I/O Completion exit.

Vn_cancel(Force) is a result of process termination; therefore, any requests that were still in the PFS have gone through recovery and generally have been handled, as they would be for any abnormal end situation.

- Part 1 requests run on the user's TCB or SRB, and these are abnormally ended before vn_cancel is issued.
- For process termination in general, new SRBs are not permitted to start Part 2, but old SRBs are allowed to finish. Osi_wait(), though, returns as if interrupted with a signal, in an attempt to keep these SRBs from blocking. If the user address space goes to memterm, nothing is able to run, so Part 2 can be abnormally ended for that reason. If the PFS issues its own MVS suspend during Part 2, it can also be abnormally ended by the system.

Serialization provided by the LFS

The vn_cancel operation is invoked with an exclusive vnode latch.

Additional serialization is provided even when the PFS is not using vnode latching.

- 1. The vn_cancel operation is not invoked while the request it is canceling is still in the PFS during Part 1 of the operation.
- 2. Vn_close is not invoked while vn_cancel is in progress.
- 3. If a user process terminates before osi_upda is called, vn_cancel is not called, since the LFS does not have the PFS's token to pass.
- 4. The LFS serializes vn_cancel with the potentially simultaneously occurring end of Part 2 on the SRB, so the PFS does not have to in any sense "wait" within vn_cancel for Part 2.

Security calls to be made by the PFS

None.

vn_close — Close a file or socket

Function

The vn close operation closes a file or socket.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465</u> for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Bit

Length:

Fullword

A fullword containing the open flags that are associated with this file. These flags are defined by fcntl.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_close operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_close operation stores the return code. The vn_close operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_close operation stores the reason code. The vn_close operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_close processing

See "Opening and closing files and first references to files" on page 31 for a discussion of close processing.

See <u>"Creating, referring to, and closing socket vnodes" on page 44</u> for a discussion of relevant socket processing.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the close() function in the POSIX .1 standard (IEEE Std 1003.1-1990).

Specific processing notes

- 1. The Return_value parameter is preset to -1 before the PFS is called. If the PFS program checks or ends abnormally during the vn_close operation and the abend is percolated back to the LFS, the LFS uses the Return_value to determine what to do next. If the Return_value is still -1, the PFS is recalled with vn_close; otherwise it is not. Therefore, just before the PFS reaches a point at which it would rather not be recalled if it should end abnormally, it should zero out the Return_value.
- 2. If the PFS supports vn_recovery, and vn_recovery returns control information to direct the outcome of the original call, the rule is overridden. That is, vn_close is not recalled if it appears that vn_recovery has handled the problem, regardless of the value of Return_value.
- 3. Although the Return_value, Return_code, and Reason_code values are returned to the caller, the operation always succeeds in that the user's file descriptor is freed and the vnode's open counter is decremented, regardless of the Return_value.
- 4. If vn_inactive is not supported by the PFS, the LFS will free its vnode after the vn_close returns. If vn_inactive is supported, the LFS keeps the vnode for a few minutes and then invokes vn_inactive, at which time the vnode is freed.

For sockets PFSs, the total number of vnodes in use is used to enforce the MAXSOCKETS limit. Thus, for sockets PFSs that use vn_inactive, it is possible for a heavily loaded system to reach its MAXSOCKETS limit—even though not that many sockets are open—because of closed vnodes that have not yet been inactivated.

Refer to "Creating, referring to, and closing socket vnodes" on page 44 for more information about socket close and inactivation.

Serialization provided by the LFS

The vn_close operation is invoked with an exclusive latch held on the vnode of the file. Shared read support for the file that is being closed can be modified in the OSI by the PFS upon returning from the vn_close operation.

Security calls to be made by the PFS

None.

Related services

- "vn_open Open a file" on page 168
- "vfs_socket Create a socket or a socket pair" on page 97

vn_connect - Connect to a socket

Function

The vn_connect operation connects to a socket. The socket can be either a stream socket or a datagram socket. The connection is done for stream sockets by a client; a bind and a listen request must have preceded this request at the server.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Sockaddr_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of sockaddr.

Sockaddr

Supplied parameter

Type:

SOCK

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. It contains the address that is to be used for this operation. For an example of this mapping for AF_INET, see in.h.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_connect operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_connect operation stores the return code. The vn_connect operation returns Return_code only if Return_value is -1.For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_connect operation should support at least the following error values:

| Return_code | Explanation |
|--------------|-----------------------------------------------------------------------------------------------|
| ECONNREFUSED | The connection request was rejected. |
| EINTR | The request was interrupted by a signal. |
| EINVAL | The length of the name specified was too short, or negative. |
| EISCONN | The socket is already connected. |
| ENOAFSUPPORT | The PFS does not support this address family. |
| EOPNOTSUPP | The socket that was specified is a server; a listen has been done. |
| EPROTOTYPE | The request is for an incorrect socket type. |
| EWOULDBLOCK | The operation would have required a blocking wait, and this socket was marked as nonblocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_connect operation stores the reason code. The vn_connect operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_connect processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the connect function.

Specific processing notes

The connect() function performs a different action for each of the following types of initiating sockets:

- If the initiating socket is SOCK_DGRAM, the connect() function establishes the peer address. The peer address identifies the socket to which all datagrams are sent on subsequent send() functions. No connections are made by this connect() function.
- If the initiating socket is SOCK_STREAM, the connect() function attempts to make a connection to the socket that is specified by the Sockaddr parameter.

Serialization provided by the LFS

The vn_connect operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

Related services

- "vn_listen Listen on a socket" on page 156
- "vn_accept Accept a socket connection request" on page 111
- "vn_bind Bind a name to a socket" on page 123

vn_create - Create a new file

Function

The vn_create operation creates a new file using the file type and attributes that are provided by the caller.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Name length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Name. The name is between 1 and 255 bytes long.

Name

Supplied parameter

Type:

String

Length:

Specified by Name_length

An area, of length Name_length, that contains the name of the file that is to be created. This name is not null-terminated.

Attribute_structure

Supplied parameter

Type:

ATTR

Length:

Specified by ATTR.at_hdr.cblen.

An area that is to be used by the vn_create operation to set the attributes of the file that is to be created. This area is mapped by typedef ATTR in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

An area in which the vn_create operation returns the vnode token that is created.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_create operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_create operation stores the return code. The vn_create operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_create operation should support at least the following error values:

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------|
| EACCES | The caller does not have write permission for the parent directory. |
| EEXIST | A file with the same name already exists. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_create operation stores the reason code. The vn_create operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_create processing

"Creating files" on page 30 provides an overview of file creation processing.

Specific processing notes

- The token structure that is passed on input represents the directory in which the file is created.
- The following attribute_structure fields are provided by the LFS:

ATTR.at hdr.cbid

Contains Attr_ID (from the BPXYVFSI header file)

ATTR.at_hdr.cblen

Specifies the length of the attribute_structure

ATTR.at_mode

Specifies the file type and permission bits. See the ATTR typedef in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this field.

The user's file creation mask, umask() value, has already been applied to the permission bits.

ATTR.at_major

Specifies the major number for character-special files. This is provided only when the file type is character-special.

ATTR.at minor

Specifies the minor number for character-special files. This is provided only when the file type is character-special.

• If the file that is named in the Name parameter already exists, the vn_create operation returns a return code of EEXIST, and the output vnode_token is optional.

Serialization provided by the LFS

The vn_create operation is invoked with an exclusive latch held on the vnode of the parent directory.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has write permission to the directory. The PFS is also expected to invoke SAF's Make FSP callable service to create a file security packet.

Related services

- "osi_getvnode Get or return a vnode" on page 372
- "vn_remove Remove a link to a file" on page 191

vn_fsync — Harden file data

Function

The vn fsync operation writes to disk (or otherwise stabilizes) all changed data in a file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for <u>C</u> language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465</u> for the mapping of this structure.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_fsync service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_fsync service stores the return code. The vn_fsync service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_fsync service should support at least the following error value:

Return_code

Explanation

EINVAL

The operation is not possible for the specified file.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_fsync service stores the reason code. The vn_fsync service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_fsync processing

For the file token in the token_structure, vn_fsync must write all modified data that is not yet placed in nonvolatile storage to such a medium.

Specific processing notes

- Data should be completely hardened before vn_fsync returns to its caller.
- For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the fsync() function in the POSIX .1a standard (IEEE Std 1003.1a), draft 7.

Serialization provided by the LFS

The vn_fsync operation is invoked with an exclusive latch held on the vnode of the file.

Security calls to be made by the PFS

None.

Related services

• "vfs_sync — Harden all file data for a file system" on page 103

vn_getattr — Get the attributes of a file

Function

The vn_getattr operation gets the attributes of a file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token.

Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Attribute_structure

Supplied and returned parameter

Type:

ATTR

Length:

Specified by ATTR.at_hdr.cblen.

An area used by the vn_getattr operation to return the file attributes for the file that is specified by the vnode token. Before a call to vn_getattr, Attribute_structure must be initialized with the ID and length fields set correctly and the unused fields set to zero. This area is mapped by typedef ATTR in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vn_getattr service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_getattr service stores the return code. The vn_getattr service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_getattr service stores the reason code. The vn_getattr service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_getattr processing

vn_getattr is used to read file attributes, as described in "Getting and setting attributes" on page 37.

Specific processing notes

- The input attribute_structure length may not match the length that is supported by the PFS. The PFS must return the minimum of:
 - Input ATTR.at_hdr.cblen
 - The attribute_structure length that is supported by this release of the PFS

The returned value in ATTR.at_hdr.cblen must match the size returned.

• Time-related fields that are marked for update must be updated before the attributes are returned.

Serialization provided by the LFS

The vn_getattr operation is invoked with a shared latch held on the vnode of the directory.

Security calls to be made by the PFS

None.

Related services

• "vn_setattr — Set the attributes of a file" on page 210

vn_getname — Get the peer or socket name

Function

The vn_getname operation gets the peer name or the socket name.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

```
vn_getname (Token_structure,
    OSI_structure,
    Audit_structure,
    Name_type,
    Sockaddr_length,
    Sockaddr,
    Return_value,
    Return_code,
    Reason_code)
```

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Name type

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies whether to get the peer name or the socket name. The values for this field are defined in the BPXYPFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Sockaddr length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

A fullword that supplies the length of the Sockaddr buffer, and returns the length of the Sockaddr structure that is returned.

Sockaddr

Supplied and returned parameter

Type:

SOCK

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. On return, it contains the address that was used for this operation. For an example of this mapping for AF_INET, see in.h.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_getname operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_getname operation stores the return code. The vn_getname operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_getname operation should support at least the following error values:

Return_codeExplanationEINVALThe length of the name that was specified is too short.ENOTCONNThe socket is not connected for a getpeername request.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_getname operation stores the reason code. The vn_getname operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_getname processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the getpeername and getsockname functions.

Serialization provided by the LFS

The vn_getname operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None

vn_inactive — Inactivate a vnode

Function

The vn_inactive disassociates a vnode from the PFS's related inode.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vn_inactive service returns the results of the operation, as one of the following:

Return value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_inactive service stores the return code. The vn_inactive service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn inactive service should support the following error value:

Return_code

Explanation

EIO

An I/O error occurred while accessing the file.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_inactive service stores the reason code. The vn_inactive service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_inactive processing

"Creating, referring to, and inactivating file vnodes" on page 29 provides an overview of file inactivate processing.

Specific processing notes

- If a transient error, such as an I/O error, is encountered, the Return_value should be set to -1. In this case, the request is retried later.
- If a permanent error that prevents the specified file or directory from being used is encountered, Return_value should be set to zero. In this case, all references to the file or directory are removed from the LFS and the request is not retried. The PFS must not issue a signal-enabled wait during inactivate processing. "Waiting and posting" on page 20 provides an overview of wait and post processing.
- If a file's link count is zero, but its open count is not zero, the PFS should ignore the open count and delete the file's data along with the file. This may happen, for example, when an address space is canceled right after vn_open finishes in the PFS, but before the LFS regains control.

Serialization provided by the LFS

The vn_inactive operation is invoked with an exclusive latch held on the file system containing the vnode.

Security calls to be made by the PFS

None

Related services

- "osi wait Wait for an event to occur" on page 415
- "vfs_inactive Batch inactivate vnodes" on page 80

vn_ioctl - I/O control

Function

The vn_ioctl operation conveys a command for a file or device driver. The specific commands that are supported are defined by the PFS.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

An area that contains the open options that are associated with the file. These flags are defined in fcntl.h.

Command

Supplied parameter

Type:

Integer

Length:

Fullword

The command indicates the function that is to be performed by the PFS. The values that are defined in ioctl.h are for regular calls. The special values for sockets initialization are defined in BPXYPFSI (see Appendix D, "Interface structures for C language servers and clients," on page 465).

Argument_length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

Argument_length contains the length of the argument.

Argument

Supplied and returned parameter

Type:

Defined by the PFS or the Device Driver

Length:

Specified by Argument_length

Argument is the buffer that is to be processed by the PFS. It may contain input data to be processed, data placed in it by the PFS or device driver, or both.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_ioctl service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_ioctl service stores the return code. The vn_ioctl service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_ioctl service should support at least the following error value:

Return_code

Explanation

ENODEV

The requested function is not supported by the PFS.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_ioctl service stores the reason code. The vn_ioctl service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_ioctl processing

vn_ioctl provides a vehicle by which a PFS may provide functions not described by the POSIX standard.

Specific processing notes

- The PFS could use vn loctl to support unique file operations.
- vn_ioctl could be used to allow direct access to devices that are controlled by the PFS. You should avoid passing addresses with this service (using *argument*), and instead include all data in the buffer.
- The maximum Argument_length that is supported by the LFS is 1024 bytes.
- Refer to "Common INET sockets" on page 47 for information about the commands that a PFS must support in order to be an AF INET socket PFS.
- Open_flags are all zero when vn_ioctl is the result of the w_pioctl (BPX1PIO) function, since the file being operated on has not been opened. The PFS may want to include a special access check in this case.
- For those cases in which user data addresses are passed in the argument, the user's storage key is passed to the PFS. This key should be used with MVCSK/MVCDK or osi_copyin/osi_copyout to reference the user data areas.

The key is passed in the first word of the system data area of the Token_structure, ts_sysd1, with a format of X'PPPP020K', where K is the four-bit key value. When ts_sysd1 is all zeros, keys are not passed.

The first two bytes of ts_sysdl, when byte 3 is X'02', are the first and third bytes of the user's PSW, which are the bytes that contain the user's AMODE and Supervisor State bits.

This information is passed in ts_sysdl for all instances of program ioctl() calls, but some internal uses of vn_ioctl, mostly for FIONBIO, do not do so. These cases do not contain addresses in the argument.

Serialization provided by the LFS

The vn_ioctl operation is invoked with an exclusive latch held on the vnode of the file.

Security calls to be made by the PFS

The PFS may choose to invoke SAF's Check Access callable service to verify that the user has write permission to the file or device.

vn_link — Create a link to a file

Function

The vn_link operation creates a link to the file that is specified by Token_structure in the directory that is specified by Directory_token_structure. The link is a new name that identifies an existing file. The new name does not replace the old one, but provides an additional way to refer to the file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

See "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Link_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Link_name. The name can be between 1 and 255 bytes long.

Link name

Supplied parameter

Type:

String

Length:

Specified by Link_name_length

An area, of length Link_name_length, that contains the new name by which the file is to be known. This name contains no nulls.

Directory_token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKStr.ts_hdr.cblen.

The Directory_token_structure represents the vnode of the directory that is to contain Link_name.

This area is mapped by the TOKSTR typedef in the BPXYPFSI header file (see <u>Appendix D, "Interface</u> structures for C language servers and clients," on page 465) for details.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_link service returns the results of the operation, as one of the following:

Return value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_link service stores the return code. The vn_link service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_link service should support at least the following error values:

| Return_code | Explanation |
|--------------|---------------------------------------------------------------------------|
| EEXIST | A file with the same name already exists. |
| ENAMETOOLONG | The length of Link_name exceeds the length that is supported by this PFS. |
| EROFS | The file system is mounted read-only. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_link service stores the reason code. The vn_link service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_link processing

vn_link must create an entry in the directory that is specified by Directory_token_structure, pointing to the file that is specified by Token_structure.

Specific processing notes

- If the link is created successfully, the operation increments the link count of the file. The link count shows how many links to a file exist. (If the link is not created successfully, the link count is not incremented.)
- The LFS does not permit links to directories.
- If the link is created successfully, the change time of the linked-to file is updated, as are the change and modification times of the directory that contains Link_name, that is, the directory that holds the link.
- For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the link() function in the POSIX.1 standard (IEEE Std 1003.1-1990).

Serialization provided by the LFS

The vn_link operation is invoked with an exclusive latch held on the vnodes of the directory and the

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has **any** access to the file, and has **write** access to the directory.

For a discussion of vn_link processing in a multilevel security environment, see <u>"PFS support for multilevel security"</u> on page 64.

Related services

- "vn_remove Remove a link to a file" on page 191
- "vn_rename Rename a file or directory" on page 194

vn_listen - Listen on a socket

Function

The vn_listen operation identifies the socket as a server and establishes the maximum number of incoming connection requests that can be queued.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Backlog

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies the maximum number of connection requests that can be queued.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_listen operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_listen operation stores the return code. The vn_listen operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_listen operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------|
| EINVAL | Either a bind has not been issued on this socket; a listen was already done; or this socket has been connected. |
| EOPNOTSUPP | Listen is valid only for stream sockets. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_listen operation stores the reason code. The vn_listen operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_listen processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the listen function.

Specific processing notes

None.

Serialization provided by the LFS

The vn listen operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

Related services

• "vn_bind — Bind a name to a socket" on page 123

vn_lockctl — Byte range lock control

Function

The vn_lockctl operation conveys a byte range locking command for a file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

LockCommand

Supplied parameter

Type:

Integer

Length:

Fullword

The command indicates the function that is to be performed by the PFS. The values are the same as for the v_lockctl callable service and are defined in BPXYVFSI. See Appendix D, "Interface structures for C language servers and clients," on page 465.

Vlock_length

Supplied parameter

Type:

Integer

Length:

Fullword

Vlock_length contains the length of the Vlock structure that is passed.

Vlock

Supplied and returned parameter

Type:

Structure

Length:

Specified by Vlock_length

The Vlock structure contains information about the locking request. See <u>"v_lockctl (BPX1VLO, BPX4VLO)</u> — Lock a file" on page 283 for more information.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lockctl service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lockctl operation stores the return code. The vn_lockctl operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_lockctl operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EAGAIN | The Lock command was requested, but the lock conflicts with a lock on an overlapping part of the file that is already set by another locker. |
| EDEADLK | The LockWait command was requested, but the potential for deadlock was detected. |
| EINTR | A LockWait request was interrupted by a signal. |
| EINVAL | Parameter error. |
| ENOSYS | Returned for files that must be locked locally. After this return code is encountered, the current and all subsequent lock requests for this file are sent to the local BRLM. This remains in effect until the file is inactivated. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lockctl operation stores the reason code. The vn_lockctl operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_lockctl processing

For an overview of byte range locking and how applications use it, see $\underline{\text{fcntl}()}$ in z/OS XL C/C++ Runtime Library Reference.

See "v_lockctl (BPX1VLO, BPX4VLO) — Lock a file" on page 283 for details on the Vlock structure and its usage.

Serialization provided by the LFS

The vn_lockctl operation is invoked with a shared latch held on the vnode of the file.

Security calls to be made by the PFS

None

Specific processing notes

- 1. The PFS may support locking for just some of its files. Mt_nolocking can be returned from vfs_mount to turn off vn_lockctl for an entire file system. Vn_lockctl can be turned off for one file by rejecting any vn_lockctl request with RC=ENOSYS. Normal local BRLM locking is done in cases where vn_lockctl is not called.
- 2. Vn_lockctl is called for the following locking operations: VL_LOCK, VL_LOCKWAIT, VL_UNLOCK, VL_QUERY, VL_UNREGLOCKER. These are described in <u>"v_lockctl (BPX1VLO, BPX4VLO) Lock a file"</u> on page 283.
- 3. The object being locked is represented by the Vnode of the operation. The Object ID in the Vlok is usually not filled in.
- 4. Locker Registration: To speed up future locking operations for a process, the PFS can return a token in vl_lockertok that the LFS saves and passes back to the PFS on later vn_lockctl calls from this same process. Vl_lockertok will be zeros unless a prior Locker Token has been saved. A new Locker Token can be returned on vn_lockctl requests that fail; for example, with VL_LOCK when the lock can not be granted. The Locker Token is also passed to the PFS on vn_rdwr, vn_trunc, and vn_settattr (File Size Change) calls when the file involved is one for which vn_lockctl would be called for locking requests. When this process terminates, vn_lockctl is called for the VL_UNREGLOCKER operation so it can clean up any resources that may be associated with the token. There is no file associated with this operation, so the Vnode passed on the call is not significant and will usually be the root vnode of one of the file systems that is mounted on this PFS.
- 5. Object Registration: The object being locked is fundamentally represented by the Vnode of the operation, but if the PFS returns a non-zero value in vl_objtok the LFS will save this value in the Vnode and pass it back to the PFS on all future locking operations for this object. A new Object Token can be returned on vn_lockctl requests that fail; for example, with VL_LOCK when the lock can not be granted. There is no explicit Object unregistration. Any locking related resources for an object are normally cleaned up as part of vn_inact processing.
- 6. The Locker ID passed to vn_lockctl for normal POSIX fcntl() users has the user's Process ID (PID) in the vl_clientpid field. The vl_serverpid and vl_clienttid fields will be zeros. In general, the full 16-byte Locker ID represents the individual entity that is requesting the lock. This Locker ID contends with all other 16-byte Locker ID entities for these locks. Only the first 8-bytes of the Locker ID are used for implicit Locker registration and explicit unregistration. Threads would be considered to be part of the registered process.
- 7. For VL_QUERY, only the POSIX Brlk structure can be returned to the fcntl() caller, so the extended blocker information discussed under "v_lockctl (BPX1VLO, BPX4VLO) Lock a file" on page 283 for the vl_blockinglock field is not used with vn_lockctl. The only information returned about the blocking locker by the LFS for fcntl() is a 1-word Process ID. If the blocking locker is another local POSIX process the PFS should return that PID in the Brlk structure; otherwise the PFS should return the PFS's Colony PID.

vn_lookup — Look up a file or directory

Function

The vn_lookup searches the directory that is represented by token_structure for the file or directory whose name is supplied.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Name length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Name. The name is between 1 and 255 bytes long.

Name

Supplied parameter

Type:

String

Length:

Specified by Name_length

An area, of length Name_length, that contains the name of the file or directory that is to be searched for. This name is not null-terminated.

Vnode token

Returned parameter

Type:

Token

Length:

8 bytes

An area in which the vn_lookup operation returns the vnode token of the file or directory that is supplied in the name parameter.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lookup operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lookup operation stores the return code. The vn_lookup operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_lookup operation should support at least the following error values:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------------------------------------------|
| EACCES | The caller does not have search permission for the parent directory. |
| ENAMETOOLONG | The Name_length that was supplied is greater than the maximum name length that is supported by this PFS. |
| ENOENT | The file or directory does not exist in the parent directory. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_lookup operation stores the reason code. The vn_lookup operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_lookup processing

Lookup processing is described in "Creating, referring to, and inactivating file vnodes" on page 29.

Specific processing notes

- The token structure that is passed on input represents the directory that is searched for the input name
- If the file or directory that is named in the Name parameter does not exist in the parent directory, the vn_lookup operation returns a failing return code, and no vnode_token is returned.

Serialization provided by the LFS

The vn_lookup operation is invoked with a shared latch held on the vnode of the parent directory.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has search permission to the directory.

Related services

"osi_getvnode — Get or return a vnode" on page 372

vn_mkdir - Create a directory

Function

The vn_mkdir operation creates a directory using the attributes that are provided by the caller.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Name length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of the directory name that is to be created. The name can be between 1 and 255 bytes long.

Name

Supplied parameter

Type:

String

Length:

Specified by Name_length

An area, of length Name_length, that contains the name of the directory that is to be created. This name contains no nulls.

File_Attribute_Structure

Supplied parameter

Type:

Structure

Length:

Specified by the ATTR.attr_hdr.cblen field

An area that contains the attributes of the directory that is to be created. This area is mapped by the ATTR typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). For more information about how the fields in this structure are processed, see the specific processing notes section in "Implementation notes for vn_mkdir" on page 167.

Vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

An area in which the vn_mkdir service returns the vnode_token for the new directory.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_mkdir service returns the results of the operation, as one of the following:

Return_value Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_mkdir service stores the return code. The vn_mkdir service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_mkdir service supports the following error values:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------|
| EACCES | The caller does not have write authority for the parent directory. |
| EEXIST | A directory with the same name already exists. |
| ENOENT | The parent directory has been marked for deletion. |
| ENAMETOOLONG | The length of the name is greater than the maximum supported length. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_mkdir service stores the reason code. The vn_mkdir service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn_mkdir

Overview of vn_mkdir processing

"Creating, referring to, and inactivating file vnodes" on page 29 provides an overview of directory creation processing.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the mkdir() function in the POSIX .1 standard (IEEE Std 1003.1-1990).

Specific processing notes

- The token structure that is passed on input represents the parent directory in which the new directory is created.
- The following ATTR fields are provided by the LFS:

Attr.at_hdr.cbid

Contains Attr_ID (from the BPXYVFSI header file)

Attr.attr_hdr.cblen

Specifies the length of the File_Attribute_Structure

ATTR.at mode

Specifies the directory permission bits. See <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465 for the mapping of this field.

• If the directory that is named in the Name parameter already exists, the vn_mkdir service returns a return code of EEXIST, and the output vnode_token is optional.

Serialization provided by the LFS

The vn_mkdir operation is invoked with an exclusive latch held on the vnode of the parent directory.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has write permission to the directory. The PFS is also expected to invoke SAF's Make FSP callable service to create a file security packet.

Related services

- "osi_getvnode Get or return a vnode" on page 372
- "vn_remove Remove a link to a file" on page 191

vn_open - Open a file

Function

The vn_open operation opens a file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Open_flags

Supplied parameter

Type:

Bit

Length:

Fullword

A fullword containing the binary flags that describe how the file is to be opened. These flags are defined by fcntl.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_open operation returns the results of the operation as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_open operation stores the return code. The vn_open operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_open operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------|
| EACCES | The caller does not have permission for the requested (read or write) access. |
| ENOENT | The file does not exist. |
| EROFS | An attempt was made to open a file for write in a read-only file system. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_open operation stores the reason code. The vn_open operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_open processing

See "Opening and closing files and first references to files" on page 31 for a discussion of open processing.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the open() function in the POSIX.1 standard (IEEE Std 1003.1-1990).

Specific processing notes

- The O_RDONLY and O_WRONLY bits in the Open_flags control whether the SAF Check Access callable service is called for a read, write, or read and write access check.
- When the O_EXEC flag is ON in the Open_flags, the SAF Check Access call must be made with a check for execute permission rather than read or write permission. This bit is a z/OS UNIX extension that is defined in Appendix D, "Interface structures for C language servers and clients," on page 465.
- When the O_TRUNC flag is ON in the Open_flags the PFS must truncate the file to zero length.
- The LFS implements the semantics of the O_CREAT and O_EXCL flags.
- The Open_flags will be remembered by the LFS and passed to the PFS on all read/write type operations that are related to this open. The O_APPEND and O_NONBLOCK flags, for instance, are processed by the PFS during those read/write operations from the flags passed to it at that time. The O_SYNC flag is transferred by the LFS to the UIO.u_sync flag for all read/write type operations so that this function can be processed by the PFS the same way for both POSIX and NFS users.

Serialization provided by the LFS

The vn_open operation is invoked with an exclusive latch held on the vnode of the file. Shared read support for the file being opened may be modified in the OSI by the PFS upon returning from the vn_open operation.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to check that the user has permission for the requested (read, write, or execute) access.

Related services

• "vn_close — Close a file or socket" on page 130

vn_pathconf — Determine configurable path name values

Function

The vn_pathconf operation returns the current value of a configurable limit or option that is associated with a file or directory.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Option

Supplied parameter

Type:

Integer

Length:

Fullword

The option parameter contains a value that indicates which configurable limit or option is returned in Return value. These values are defined in unistd.h and are:

| Variable Returned | Description |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| _PC_CHOWN_RESTRICTED | Change ownership function is restricted to a process with appropriate privileges, and to changing the group ID (GID) of a file only to the effective group ID of the process or to one of its supplementary group IDs. |
| _PC_LINK_MAX | Maximum value of a file's link count. |
| _PC_MAX_CANON | Maximum number of bytes in a terminal canonical input line. |
| _PC_MAX_INPUT | Minimum number of bytes for which space is to be available in a terminal input queue; therefore, the maximum number of bytes a portable application may require to be typed as input before it reads them. |
| _PC_NAME_MAX | Maximum number of bytes in a filename (not a string length; count excludes a terminating null). |
| _PC_NO_TRUNC | Path name components longer than 255 bytes generate an error. |
| _PC_PATH_MAX | Maximum number of bytes in a path name (not a string length; count excludes a terminating null). |
| _PC_PIPE_BUF | Maximum number of bytes that can be written atomically when writing to a pipe. |
| _PC_VDISABLE | Terminal special characters that are maintained by the system can be disabled using this character value. |

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vn_pathconf operation returns the current value of the *pathname* variable that corresponds to Name specified, or -1 if not successful.

If the named path name variable does not have a limit for the specified file, Return_value is set to -1 and Return_code and Reason_code remain unchanged.

If _PC_CHOWN_RESTRICTED is specified for Option, and _POSIX_CHOWN_RESTRICTED is active, Return_value is set to 1.

If _PC_CHOWN_RESTRICTED is specified for Option, and _POSIX_CHOWN_RESTRICTED is not active, Return_value is set to 0.

If _PC_NO_TRUNC is specified for Option, and _POSIX_NO_TRUNC is active, Return_value is set to 1.

If _PC_NO_TRUNC is specified for Option, and _POSIX_NO_TRUNC is not active, Return_value is set to 0.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_pathconf operation stores the return code. The vn_pathconf operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_pathconf operation stores the reason code. The vn_pathconf operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Specific processing notes

- If the PFS does not have a limit for the specified option, Return_value is set to -1, but Return_code and Reason_code are unchanged. A Return_value of -1 in this case represents a limit of infinity (or no limit) for the requested option.
- The vn_pathconf operation is not invoked by the LFS if the PATH_MAX option is specified. The LFS value for PATH_MAX, 1023, is returned.
- If the PC_NAME_MAX option is specified, the LFS compares its value to the PFS value, and returns the minimum.

Serialization provided by the LFS

The vn pathconf operation is invoked with a shared latch held on the vnode.

Security calls to be made by the PFS

None.

vn rdwr - Read or write a file

Function

The vn rdwr operation reads data from or writes data to a file or a socket.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Open flags

Supplied parameter

Type:

Structure

Length:

Fullword

An area that contains the options that are to be used when reading from or writing to the file or socket. This area is mapped by fcntl.h. For a description of this header, see .fcntl.h - POSIX functions for file operations in z/OS XL C/C++ Runtime Library Reference.

User_IO_structure

Supplied and returned parameter

Type:

Structure

Length:

Specified by the UIO.u_hdr.cblen field

An area to be used by the vn_rdwr service to determine the buffer address, length, storage key, and other attributes of the read or write request. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). See the description of the vn_readwritev service in "Implementation notes" on page 176 for details on how the fields in this structure are processed.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rdwr service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful; the value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rdwr service stores the return code. The vn_rdwr service returns Return_code only if Return_value is -1.For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_rdwr service should support the following error values:

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| EFAULT | A buffer address that was not valid was passed. |
| EINTR | The request was interrupted by a signal. |
| EACCES | The caller does not have the requested (read or write) access to the file. |
| EFBIG | Writing to the specified file would exceed the file size limit for the process, or the maximum file size that is supported by the physical file system. |
| EIO | An I/O error occurred while the file was being accessed. |
| EWOULDBLOCK | The request was made of a non-blocking descriptor, and a block was needed to satisfy the request. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rdwr service stores the reason code. The vn_rdwr service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_rdwr processing

"Reading from and writing to files" on page 34 provides an overview of file read and write processing.

Specific processing notes

• The following UIO fields are provided by the LFS:

UIO.u hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u_hdr.cblen

Specifies the length of the user_IO_structure

UIO.u_buffaddr

Specifies the address of the caller's input/output buffer

UIO.u_buffalet

Specifies the ALET of the caller's input/output buffer

UIO.u_offseth

Specifies the upper word of a doubleword value that contains the offset into the file. The updated value for this field is returned by the PFS as a result of the vn_rdwr operation.

UIO.u_offset

Specifies the lower word of a doubleword value that contains the offset into the file. The updated value for this field is returned by the PFS as a result of the vn_rdwr operation.

UIO.u_count

Specifies the number of bytes that are to be read or written

UIO.u_asid

Specifies the ASID of the caller

UIO.u rw

Specifies whether the request is a read (0) or a write (1)

UIO.u_key

Specifies the storage key of the caller's input/output buffer

UIO.u_fssizelimithw

Specifies the high word of the file size limit for the process

UIO.u fssizelimitlw

Specifies the low word of the file size limit for the process

UIO.u_sync

Specifies that the file is to be written to disk before the PFS returns. The PFS sets UIO.u_syncd to indicate that this has been done.

UIO.u_chkacc

Specifies that access checking is to be performed

UIO.u_realpage

Specifies that a real storage address is being passed. This flag is used only if the PFS reported during initialization that it supports DATOFF moves.

PFS limit processing

The UIO contains the process file size limit for the file. This is a doubleword value that is contained in UIO.u_fssizelimithw and UIO.u_fssizelimitlw. When a write request is unable to write any data before exceeding the file size limit, the PFS must set the UIO.u_limitex bit on, in addition to setting a Return_code of EFBIG. This includes detecting the special case in which the UIO.u_fssizelimithw is equal to UIO_NONEWFILES, which prohibits the expansion of existing files.

(Note that for vn_setattr, the LFS handles file size limit checking.)

The PFS must also be aware of one other special value for the file size limit. If both UIO.u_fssizelimithw and UIO.u_fssizelimitlw are equal to 0, there is no file size limit set for the process.

Serialization provided by the LFS

The vn_rdwr operation is invoked with an exclusive latch held on the vnode, unless the VnodSharedRead flag indicates that shared read is supported, in which case a shared latch is held on the vnode.

Shared read support for the file that is being read from or written to may be modified in the OSI by the PFS upon returning from the vn_rdwr operation.

Security calls to be made by the PFS

If u_chkacc is on in the user_IO_structure, the PFS is expected to invoke SAF's Check Access callable service to check that the user has permission to read from or write to the file. This check should be based on the access intent that is specified by u_rw.

The PFS is expected to invoke SAF's Clear Setid callable service whenever a write is done to a file with the S_GID or S_UID options. System overhead can be significantly reduced by setting an internal flag in the Inode to indicate that Clear Setid has been called, so that subsequent calls can be avoided. This flag would be cleared whenever the file's mode is changed via vn_setattr. In other words, Clear Setid should only be called once on the first write after the file's mode is changed or its Inode is created in storage.

vn_readdir — Read directory entries

Function

The vn_readdir operation reads entries from the directory that is represented by the input Token_structure, and returns as many entries as will fit in the caller's buffer.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more information about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations"</u> on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

User IO structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). See the specific processing notes in "Implementation notes for vn_readdir" on page 180 for details on how the fields in this structure are processed.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readdir operation returns the results of the operation, as one of the following return codes:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be completed by the PFS when Return_value is -1.

0

The operation was successful, and there are no more directory entries to be read. No entries are returned.

0 or greater

The operation was successful; the value represents the number of directory entries that are returned.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readdir operation stores the return code. The vn_readdir operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see <u>Return</u> codes (errnos) in *z/OS UNIX System Services Messages and Codes*.

The vn_readdir operation must support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------|
| EACCES | The caller does not have search permission for the directory. |
| EFAULT | A buffer address that was specified is not in addressable storage. |
| EINVAL | There was a parameter error, such as an input buffer that is too small for any entries. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readdir operation stores the reason code. The vn_readdir operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS product.

Implementation notes for vn_readdir

Overview of vn_readdir processing

"Reading directories" on page 35 provides an overview of the readdir operation.

Specific processing notes

The token structure that is passed on input represents the directory that is to be read.

The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file).

UIO.u hdr.cblen

Specifies the length of the user_IO_structure.

UIO.u_buffaddr

Specifies the address of the caller's buffer.

UIO.u alet

Specifies the ALET of the caller's buffer.

UIO.u offseth

Specifies the high-order word of the cursor.

UIO.u_offset

Specifies the low-order word of the cursor.

UIO.u count

Specifies the maximum number of bytes that can be written to the caller's buffer.

UIO.u asid

Specifies the ASID of the caller.

UIO.u_key

Specifies the storage key of the caller's buffer.

UIO.u_rdindex

Specifies the readdir index field.

- The following UIO fields must be set by the PFS:
 - UIO.u_offseth
 - UIO.u offset

- The PFS is expected to write directory entries into the caller's buffer. These directory entries are mapped by the DIRENT and DIREXT typedefs in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465).
- For more information about the semantics of this operation for a POSIX-conforming PFS, see the description of readdir (BPX1RDD, BPX4RDD) in readdir (BPX1RDD, BPX4RDD) Read an entry from a directory in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Serialization provided by the LFS

The vn_readdir operation is invoked with a shared latch held on the vnode of the directory.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has read permission to the directory.

For a discussion of vn_link processing in a multilevel security environment, see <u>"PFS support for multilevel security"</u> on page 64.

Related services

• "vn_open — Open a file" on page 168

vn_readlink — Read a symbolic link

Function

The vn_readlink operation reads the symbolic link file that is represented by Token_structure, and returns the contents in the buffer that is described by User_IO_structure.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readlink service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful and represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readlink service stores the return code. The vn_readlink service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see <u>Return</u> codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_readlink service should support at least the following error value:

Return_code Explanation

EFAULT

The buffer address that was specified in the input user_IO_structure is not in addressable storage.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readlink service stores the reason code. The vn_readlink service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_readlink processing

"Reading from and writing to files" on page 34 provides an overview of file read and write processing.

The vn_readlink operation reads a symbolic link file. A symbolic link file contains the pathname or external name that was specified when the symbolic link was created.

Specific processing notes

- The token structure that is passed on input represents the symbolic link that is to be read.
- The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u hdr.cblen

Specifies the length of the user_IO_structure

UIO.u buffaddr

Specifies the address of the caller's buffer

UIO.u_alet

Specifies the ALET of the caller's buffer

UIO.u count

Specifies the maximum number of bytes that can be written to the caller's buffer

UIO.u_asid

Specifies the ASID of the caller

UIO.u key

Specifies the storage key of the caller's buffer

- If the buffer that is supplied to vn_readlink is too small to contain the contents of the symbolic link, the value should be truncated to the length of the buffer (UIO.u_count).
- There is no difference in vn_readlink processing for symbolic and external links.
- Refer to the readlink() function in the POSIX .1a standard (IEEE Std 1003.1a), draft 7, for more information about the semantics of this operation for a POSIX-conforming PFS.

Serialization provided by the LFS

The vn_readlink operation is invoked with a shared latch held on the vnode of the directory.

Security calls to be made by the PFS

For a discussion of vn_link processing in a multilevel security environment, see <u>"PFS support for multilevel security"</u> on page 64.

Related services

"vn_symlink — Create a symbolic link" on page 234

vn_readwritev — Read or write using a set of buffers for data

Function

The vn_readwritev operation reads or writes on a file or socket, using a set of buffers to hold the data that is read or written.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that might be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). For more information about how the fields in this structure are processed, see the section on specific processing notes in "Implementation notes for vn_readwritev" on page 186.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readwritev operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful; the value represents the number of bytes that were transferred.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readwritev operation stores the return code. The vn_readwritev operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_readwritev operation should support at least the return codes listed in Table 7 on page 186

Table 7. List of return codes for vn_readwritev

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Either a negative number of bytes was requested, or this socket has been shut down. |
| EFAULT | A buffer address that was specified is not in addressable storage. |
| EFBIG | Writing to the specified file would exceed the file size limit for the process or the maximum file size that is supported by the physical file system. |
| EWOULDBLOCK | The operation would have required a blocking wait, and this socket was marked as nonblocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_readwritev operation stores the reason code. The vn_readwritev operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn_readwritev

Overview of vn_readwritev processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the readv and writev functions.

Specific processing notes

• The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u_hdr.cblen

Specifies the length of the user_IO_structure

UIO.u buffaddr

Specifies the address of the caller's iov structure. The iov structure is mapped in uio.h.

UIO.u_buffalet

Specifies the ALET of the caller's iov structure

UIO.u offseth

Specifies the upper word of a doubleword value that contains the offset into the file. The updated value for this field is returned by the PFS as a result of the vn_readwritev operation.

UIO.u offset

Specifies the lower word of a doubleword value that contains the offset into the file. The updated value for this field is returned by the PFS as a result of the vn_readwritev operation.

UIO.u_count

Specifies the number of elements in the IOV array

UIO.u_asid

Specifies the ASID of the caller

UIO.u rw

Specifies whether the request is a read (0) or a write (1)

UIO.u key

Specifies the storage key of the caller's buffer

UIO.u iovbufalet

Specifies the ALET of the iov's buffers. All of the iov buffers must use the same ALET.

UIO.u_fssizelimithw

Specifies the high word of the file size limit for the process.

UIO.u fssizelimitlw

Specifies the low word of the file size limit for the process.

Also refer to <u>"Reading from and writing to files" on page 34</u> for details on how reads and writes are done by the file system.

The UIO contains fields that may point to a 64-bit addressable user buffer. When FuioAddr64 is on (and FuioRealPage is off), FuioBuff64Vaddr points to a buffer, an IOV64, or an MSGH64.

PFS Limit Processing

The UIO contains the process file size limit for the file. This is a doubleword value that is contained in UIO.u_fssizelimithw and UIO.u_fssizelimitlw. When a write request is unable to write any data before exceeding the file size limit, the PFS must set the UIO.u_limitex bit on, in addition to setting a Return_code of EFBIG. This includes detecting the special case in which the UIO.u_fssizelimithw is equal to UIO_NONEWFILES, which prohibits the expansion of existing files.

(Note that for vn_setattr, the LFS handles file size limit checking.)

The PFS must also be aware of one other special value for the file size limit. If both UIO.u_fssizelimithw and UIO.u_fssizelimitlw are equal to 0, there is no file size limit set for the process.

Serialization provided by the LFS

The vn_readwritev operation is invoked with an exclusive latch held on the vnode of the file or socket, unless the VnodSharedRead flag indicates that shared read is supported, in which case a shared latch is held on the vnode.

Shared read support for the file that is being read from or written to can be modified in the OSI by the PFS upon returning from the vn_readwritev operation.

Security calls to be made by the PFS

If the check access bit is set and this PFS does access checking, the PFS is expected to invoke SAF's Check Access callable service to verify that the user has permission to read from or write to the file.

The PFS is expected to invoke SAF's Clear Setid callable service whenever a write is done to a file with the S_GID or S_UID options. System overhead can be significantly reduced by setting an internal flag in the Inode to indicate that Clear Setid has been called, so that subsequent calls can be avoided. This flag would be cleared whenever the file's mode was changed via vn_setattr. In other words, Clear Setid should only be called once on the first write after the file's mode is changed or its Inode is created in storage.

vn_recovery — Recover resources after an abend

Function

The vn_recovery operation permits a PFS to recover resources when an abnormal end occurs while a request to that PFS is active.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Recovery_area

Supplied parameter

Type:

String

Length:

8 bytes

A copy of the Recovery_area that was filled in by the PFS during the operation that was interrupted. This area is mapped by OSIRTOKEN (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_recovery operation returns control information to direct the outcome of the recovery processing, as follows:

Return_value

Meaning

VNR NODUMP

Suppress the system dump that is normally taken.

VNR RETSUCCESS

Report success to the user. In this case, the value in the Return_Code parameter is passed back to the user as the return value of the original function.

VNR RETERRNO

Report failure to the user. In this case, the values in the Return_Code and Reason_Code parameters are passed back to the user as the return and reason codes for the original function. The return value that is passed back for the original function is -1.

Dump suppression may be requested with either success or failure reports; that is, with values of VNR_NODUMP+VNR_RETSUCCESS or VNR_NODUMP+VNR_RETERRNO, respectively.

If a Return_value is not returned by the PFS, a system dump is attempted and the original function fails with generic return and reason codes. The Return_values listed in this topic are defined in BPXYPFSI (see Appendix D, "Interface structures for C language servers and clients," on page 465.)

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_recovery operation stores the return code. The vn_recovery operation returns Return_code with the Return_value that was returned, as explained in this topic.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_recovery operation stores the reason code. The vn_recovery operation returns Reason_code with the Return_value that was returned, as explained in this topic.

Implementation notes

Overview of vn recovery processing

"Recovery considerations" on page 23 provides an overview of recovery processing, and discusses the flow for vn_recovery in particular.

When an active request to the PFS is interrupted by an abnormal end, the PFS may have resources, such as storage and locks, that are left in a state that will cause problems for other users. This operation is defined to give the PFS a chance to clean up these resources if an abnormal end should occur.

This operation is designed for a PFS that does not have its own ESTAE or FRR protection. When a PFS has its own recovery, it normally handle abnormal ends before returning or percolating back to the LFS.

Specific processing notes

• An 8-byte Recovery_area is passed on every VFS and vnode operation, through the osi_rtokptr pointer in the OSI_structure, in which the PFS can record its resources or store a pointer to a recovery block. Any information that is stored in this area by the PFS during an operation is passed back to the PFS via the Recovery_area parameter of vn_recovery if the operation is interrupted by an abnormal end.

The SDWA address is also passed to the PFS, for diagnostic purposes. This address is stored 16 bytes after the 8-byte Recovery_area. (Refer to the osirtokenx structure in Appendix D, "Interface structures for C language servers and clients," on page 465.) The PFS must test this address for zero before using it, because the system is not always able to obtain an SDWA during recovery.

- The OSI work area and the preinitialized C Environment Stack (if used) are still addressable, and left as they were at the time of the abnormal end. These areas can be used to hold a recovery block whose address is placed in the Recovery_area. Vn_recovery is invoked with its own separate areas.
- The PFS is not called if the Recovery_area that is pointed to by osi_rtokptr is zero at the time of the abnormal end.

- The PFS is not called if the file system has been unmounted. A file system can be unmounted between the original vnode operation and vn_recovery in the following scenario:
 - 1. An operation goes into a signal enabled wait.
 - 2. The file system is unmounted with the IMMEDIATE operand.
 - 3. The waiting user is canceled.

The PFS is expected to have cleaned up all its file-system-related resources during vfs_umount.

- This Recovery_area is the same one that is used by the vfs_recovery operation for user EOM recovery. The difference between these operations is that if the LFS's ESTAE runs, it calls the PFS with vn_recovery from the same home address space and task that the original operation was invoked from. If the LFS's ESTAE is bypassed by MVS, the LFS's user address space EOM resource manager calls the PFS with vfs_recovery. This call is from a different task and home address space than the original call, and the original home address space no longer exists.
- Vfs_recovery is not called after vn_recovery has been called, unless vn_recovery is interrupted by
 a sudden end-of-memory condition for the user's address space. An example of this would be a
 program check in the PFS that was followed almost immediately by an operator force of the user.
 Another example would be if the PFS's vn_recovery routine were to get into a deadlock or extended
 wait, and the operator had to force the user off.
- Special care must be taken with vn_recovery, because the Token_structure may not always contain a file-level token. This is because vn_recovery is used for abend recovery of all the VFS and vnode operations. If a VFS operation is interrupted, the Token_structure on the vn_recovery call does not contain a file token; and if vfs_pfsctl is interrupted, the Token_structure contains only the PFS's initialization token.
- No recovery of any type is supplied for the vn_recovery operation itself. The operation is invoked with Osi_rtokptr pointing to a new recovery area, but this is only to allow the PFS to use common entry code that may depend on having a valid address in this field.
 - See the OSI and osirtoken structures in Appendix D, "Interface structures for C language servers and clients," on page 465.
- The state of any file system and file objects that may have been involved with the interrupted operation is the same as at the time of the interruption.

Serialization provided by the LFS

The vn_recovery operation is invoked with the same serialization that was held at the time of the abnormal end.

Security calls to be made by the PFS

None.

vn_remove — Remove a link to a file

Function

The vn_remove service removes a link to a file. The input Name can identify a file, a link-name of a file, or a symbolic link.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Name. The name is between 1 and 255 bytes long.

Name

Supplied parameter

Type:

String

Length:

Specified by Name_length

An area, of length Name_length, that contains the name of the link that is to be deleted. This name contains no nulls.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_remove service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_remove service stores the return code. The vn_remove service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_remove service should support at least the following error values:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------------|
| ENAMETOOLONG | The value of Name_length exceeds the length that is supported by this PFS. |
| ENOENT | Name is marked for deletion. |
| EROFS | The file system is mounted read-only. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_remove service stores the reason code. The vn_remove service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_remove processing

"Deleting files" on page 31 provides an overview of file deletion processing.

Specific processing notes

- The system data fields of the Token_structure contain the PFS's file token for the file that is being removed.
- If the name that is specified refers to a symbolic link, the symbolic link file that is named by Name should be deleted.
- If the link name is successfully removed from the directory, and the link count becomes zero, the deletion of the file is recorded for audit purposes. The actual deletion of the file object, and the inode, is done when the vnode is inactivated.

If a regular file is not open when its link count goes to zero, the space that is occupied by its data should be freed for reuse before the return from vn remove.

If a regular file is still open when the link count goes to zero, its contents are not deleted at this point, but remain accessible until the open count goes to zero.

- When the vn_remove service is successful in removing a directory entry and decrementing the link count, even if the link count is not zero, it must return control to the caller with Return_value set to 0. It must update the change and modification times for the parent directory, and the change time for the file itself (unless the file is deleted).
- For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the unlink() function in the POSIX.1 standard (IEEE Std 1003.1-1990).

Serialization provided by the LFS

The vn_remove operation is invoked with an exclusive latch held on the vnode of the file that is to be removed, and on the directory that contains that file name.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has write permission to the directory, and the Audit callable service to record the deletion of the file.

SAF's Check2Owners service is called whenever the sticky bit is on in the parent directory.

Related services

- "vn_create Create a new file" on page 136
- "vn_link Create a link to a file" on page 152
- "vn_rmdir Remove a directory" on page 198
- "vn_symlink Create a symbolic link" on page 234

vn_rename — Rename a file or directory

Function

The vn_rename renames a file or directory.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Name. The name is between 1 and 255 bytes long.

Name

Supplied parameter

Type:

String

Length:

Specified by Name_length

An area, of length Name_length, that contains the file or directory name that is to be renamed. This name is not null-terminated.

New_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of New_name. The name is between 1 and 255 bytes long.

New name

Supplied parameter

Type:

String

Length:

Specified by New_name_length

An area, of length New_name_length, that contains the file or directory name to which the file or directory is to be renamed. This name is not null-terminated.

New token structure

Supplied parameter

Type:

Structure

Length

Specified by the structure's TOKSTR.ts_hdr.cblen field.

New_token_structure represents the vnode of the directory that contains New_name.

Refer to "LFS/PFS control block structure" on page 16 for a discussion of the use of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rename operation returns the results of the operation, as one of the following:

Return_value Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rename operation stores the return code. The vn_rename operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_rename operation should support at least the error values listed in Table 8 on page 197.

Table 8. Error values for the vn_rename operation

| Return_code | Explanation |
|--------------|-----------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The caller does not have write permission for one or both of the parent directories. |
| EBUSY | The New_name could not be deleted, or the named file or directory could not be renamed because the PFS considers it to be in use. |
| EISDIR | An attempt was made to rename a file to a directory. |
| ENAMETOOLONG | The length of one of the names supplied was greater than the maximum supported name length for this PFS. |
| ENOENT | Name was not found. |
| ENOTEMPTY | New_name specified an existing directory that was not empty. |
| ENOTDIR | Token_structure did not represent a directory, or an attempt was made to rename a directory to a file. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rename operation stores the reason code. The vn_rename operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_rename processing

The PFS renames a file or directory that is specified by Name in the directory that is represented by Token_structure to the name that is specified by New_name in the directory that is represented by New_token_structure.

"Deleting files" on page 31 provides an overview of file deletion processing.

Specific processing notes

- The system data fields of the Token_structure contain the PFS's file token for the file that is being renamed. The system data fields of the New_Token_structure contain the PFS's file token for the file that is named by New_name, if it exists.
- If a directory entry does not already exist for New_name, the PFS creates it. If a directory entry for New_name already exists, the file or directory that is represented by this entry is deleted, as described for vn_remove or vn_rmdir, as appropriate.

If New_name is an existing directory that is not empty, the PFS returns a Return_value of -1 and a return code of ENOTEMPTY.

If the rename is successful, the directory entry for the old name is deleted.

- The names that are passed to the PFS cannot be "." or "..".
- For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the rename() function in the POSIX .1 standard (IEEE Std 1003.1-1990).

Serialization provided by the LFS

The PFS is invoked with an exclusive latch for all of the vnodes involved in this operation. These include:

- · The old parent directory
- · The new parent directory
- · The file or directory that is specified by Name
- If it already exists, the file or directory that is specified by New_name

Security calls to be made by the PFS

The PFS is expected to verify that the calling process has write permission for the directories that contain Name and New_name by calling SAF's Check Access callable service. If Name and New_name are themselves directories, the caller does not need write permission to these directories, only to the parent directories.

SAF's Check2Owners service is called whenever the sticky bit is on in the parent directory.

If the file that was previously known by New_name is deleted, invoke SAF's Audit callable service to record the deletion of the file.

Related services

- "vn remove Remove a link to a file" on page 191
- "vn_rmdir Remove a directory" on page 198

vn_rmdir - Remove a directory

Function

The vn_rmdir operation removes a directory. The directory must be empty.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See <u>Chapter 6</u>, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Directory_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Directory_name. The name is between 1 and 255 bytes long.

Directory_name

Supplied parameter

Type:

String

Length:

Specified by Directory_name_length

An area, of length Directory_name_length, that contains the name of the directory that is to be deleted. This name contains no nulls.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rmdir service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rmdir service stores the return code. The vn_rmdir service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_rmdir service should support at least the following error values:

| Return_code | Explanation |
|--------------|--------------------------------------------------------------------------------------|
| ENAMETOOLONG | The value of Directory_name_length exceeds the length that is supported by this PFS. |
| ENOENT | The directory name is marked for deletion. |
| ENOTEMPTY | The directory contains entries other than . and |
| EROFS | The file system is mounted read-only. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_rmdir service stores the reason code. The vn_rmdir service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_rmdir processing

"Deleting files" on page 31 provides an overview of file deletion processing.

Specific processing notes

- The system data fields of the Token_structure contain the PFS's file token for the file that is being removed.
- The directory that is specified by Directory_name must be empty except for the "." and ".." entries.
- If the directory is successfully removed, the change and modification times for the parent directory must be updated.
- The deletion of the directory is recorded for audit purposes now, but the actual deletion of the object and the inode is done when the vnode is inactivated.
- Vn_readdir of a removed directory returns zero entries.
- New files must not be created under a directory that is removed.
- For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the rmdir() function in the POSIX .1 standard (IEEE Std 1003.1-1990).

Serialization provided by the LFS

The vn_rmdir operation is invoked with an exclusive latch held on the vnode of the directory name that is to be removed, and on the directory that contains that directory name.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to verify that the user has write permission to the directory, and invoke the audit callable service to record the deletion of the directory file.

SAF's Check2Owners service is called whenever the sticky bit is on in the parent directory.

Related services

- "vn_remove Remove a link to a file" on page 191
- "vn_mkdir Create a directory" on page 165

vn_select — Select or poll on a vnode

Function

The vn_select operation monitors activity on a vnode to see if it is ready for reading or writing, or if it has an exceptional condition pending. The vnode can be for a socket, a pipe, a regular file, or a pseudoterminal file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Select_token

Supplied and returned parameter

Type:

Token

Length:

16 Bytes

An area that the PFS copies into its own storage and later uses to tell the LFS that a selected event has occurred for this vnode.

This token is unique among all active vn_selects on the system, and can be used to correlate a query request (SEL_QUERY or SEL_POLLQUERY) with its corresponding cancel request (SEL_CANCEL or SEL_POLLCANCEL).

Function

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies whether this is a query or a cancel request, and whether the request is for select or poll. The values for this field are defined in the BPXYPFSI header file (see <u>Appendix</u> <u>D</u>, "Interface structures for C language servers and clients," on page 465). The Function parameter specifies the subfunction that is being requested:

| Table 9. Subfunctions for vn_select | |
|-------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Function | Description |
| SEL_QUERY, SEL_POLLQUERY | The PFS should perform the following: |
| | Check the events that are specified in Select_option to see if any of them can be immediately satisfied. If so, this status is returned in the Return_Value parameter. |
| | 2. If there is no immediate status to report, the PFS records that a select is pending on this file and sets up to invoke osi_selpost later, when one of the selected events has occurred. The PFS returns a value of 0 in Return_Value after it has performed its internal processing to set up for select pending. |
| | The occurrence of the event and the subsequent invocation of osi_selpost happen asynchronously on another thread or MVS task. |

| Table 9. Subfunctions for vn_select (continued) | |
|-------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Function | Description |
| SEL_CANCEL, SEL_POLLCANCEL | The PFS performs the following: |
| | 1. If there is a pending select/poll recorded for a prior query with the same Select_token, it must be canceled in such a way that osi_selpost is not invoked. |
| | 2. Check the events that are specified in Select_option to see if any of them can be immediately satisfied. If so, this status is returned in the Return_Value parameter. |

Select_option

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the bits that describe the options that are requested for this vnode. The values for this field are defined in the BPXYPFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Select_option indicates the conditions or events that are being checked for. If this is a select request, the conditions are:

Option

Description

SEL READ

A read that is issued against this file will not block.

SEL WRITE

A write that is issued against this file will not block.

SEL XCEPT

An exceptional condition, as defined by the particular PFS, has occurred. Typically this could occur because a socket connection has become inoperative because of network problems, or the other end of the socket has been closed.

For reading and writing, an error condition that would cause the read or write to fail means that the operation will not block, and therefore the file is ready for that operation.

If one or more of the selected conditions are ready, the PFS returns the information in the Return_Value parameter immediately, using the same bit mapping to indicate which conditions are ready.

The conditions that can be specified for poll are explained in other documents (for instance, $z/OS\ XL\ C/C++\ Language\ Reference$). The mapping for these fields is defined in the BPXYPFSI header file. (For more information about BPXYPFSI, see "BPXYPFSI" on page 484.)

Pfs_work_token

Supplied or returned parameter

Type:

Token

Length:

Fullword

A fullword that is returned on a query request and passed on a subsequent cancel request. This allows the LFS to store data that the PFS will need on the cancel request, if any is needed.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the vn_select service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. This causes the whole select() or poll() request, as made by the application program, to fail. The Return_code and Reason_Code values are passed back to the application program.

0

There is no status, and the operation was successful.

• For query (SEL_QUERY or SEL_POLLQUERY):

The PFS is set up to invoke osi_selpost when the requested event occurs.

• For cancel (SEL_CANCEL or SEL_POLLCANCEL):

The PFS has canceled the request to invoke osi_selpost, or it has never been set up to do so. The PFS does not invoke osi_selpost after returning from this call.

Greater than 0

There is status being returned in this parameter. The returned status has the same format as the Select_option parameter.

For query (SEL_QUERY or SEL_POLLQUERY):

The operation is complete and the PFS will not invoke osi_selpost for this request.

For cancel (SEL_CANCEL or SEL_POLLCANCEL):

The PFS has canceled the request to invoke osi_selpost if it had been recorded, or it has never been set up to do so.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_select operation stores the return code. The vn_select operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_select operation stores the reason code. The vn_select operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_select processing

For information about vn_select, refer to "Select/poll processing" on page 45.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the select() function.

Specific processing notes

- The PFS should save the Select_token that is passed on the query request. This token is used both during the cancel request (to delete the request), and when an event occurs that the LFS should be informed of through the osi_selpost function.
- The PFS can use the Pfs_work_token parameter on a query request to return data (such as an address where it has stored information about this request), so that it can be found during a cancel request. The data is used to correlate the cancel request with its matching query request. This provides an alternative to scanning the PFS control blocks for a matching Select_token value.
- If the session being selected becomes inoperative, the PFS must fail the operation with a Return_code of EIO. For sockets, this is critical to Common Inet processing so that a stack can be removed from a socket during the internal vn_select that is done to implement blocking reads and accepts. For application select() calls, the LFS will convert EIO from vn_select to ready status for the descriptor so that the application receives the EIO notification on the specific descriptor to which it applies.

Serialization provided by the LFS

The vn_select operation is invoked with an exclusive latch held on the vnode of the file.

Security calls to be made by the PFS

None.

vn_sendtorcvfm — Send to or receive from a socket

Function

The vn_sendtorcvfm operation sends datagrams to or receives datagrams from a socket. The socket can be connected or unconnected.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465). For more information about how the fields in this structure are processed, see the section on specific implementation notes in "Implementation notes" on page 209.

Flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that indicates special processing requests. The defined values for this field are mapped by socket.h.

Sockaddr_length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

A fullword that supplies the length of the Sockaddr buffer and returns the length of the Sockaddr structure that is returned.

Sockaddr

Supplied and returned parameter

Type:

Structure

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. It contains the address that is to be used for this operation. For an example of this mapping for AF_INET, see in.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sendtorcvfm operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful. The value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sendtorcvfm operation stores the return code. The vn_sendtorcvfm operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_sendtorcvfm operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------|
| EFAULT | A buffer address that was specified was not in addressable storage. |
| EINVAL | The length that was specified was incorrect. |
| EWOULDBLOCK | The operation would have required a blocking wait, and this socket was marked as nonblocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sendtorcvfm operation stores the reason code. The vn_sendtorcvfm operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_sendtorcvfm processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the recvfrom() and sendto() functions.

Specific processing notes

The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u hdr.cblen

Specifies the length of the user_IO_structure

UIO.u buffaddr

Specifies the address of the caller's buffer

UIO.u buffalet

Specifies the ALET of the caller's buffer

UIO.u count

Specifies the maximum number of bytes that can be written to the caller's buffer

UIO.u_asid

Specifies the ASID of the caller

UIO.u rw

Specifies whether the request is a read (0) or a write (1)

UIO.u key

Specifies the storage key of the caller's buffer

• The UIO contains fields that may point to a 64-bit addressable user buffer. When FuioAddr64 is on (and FuioRealPage is off), FuioBuff64Vaddr points to a buffer, an IOV64, or an MSGH64.

Serialization provided by the LFS

The vn_sendtorcvfm operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

vn_setattr — Set the attributes of a file

Function

The vn setattr operation sets the attributes of a file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. For more information, see Chapter 6, "OSI services," on page 355.

It also contains MVS-specific information that must be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more information about the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

attribute_structure

Supplied parameter

Type:

ATTR

Length:

Specified by ATTR.at_hdr.cblen.

An area that contains the file attributes that are to be set for the file that is specified by the vnode token. This area is mapped by typedef ATTR in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_setattr operation returns the results of the operation, as one of the following error values:

-1

The operation was not successful. The Return_code and Reason_Code values must be completed by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_setattr operation stores the return code. The vn_setattr operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_setattr operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------|
| EACCES | The caller does not have SAF authority to do these tasks:: |
| | Set the access time or modification time to current time Truncate the file |
| EPERM | The caller does not have SAF authority to do these tasks:: |
| | Change the mode |
| | Change the owner |
| | Change general attribute bits |
| | Set a time field to a value (not the current time) |
| | Set the change time or reference time to the current time |
| | Change the auditing flags |
| | Change the file format |
| | Set the security label; or there is already a security label that is associated with the file |
| EROFS | The file system is mounted read-only. |
| ENOSPC | The file system is out of space. |
| EINVAL | Incorrect input parameter, such as a negative time value, an incorrect mode field, or an incorrect UID-GID. |

Reason_code

Returned parameter

Type:

Integer

Character set:

N/A

Length:

Fullword

A fullword in which the vn_setattr operation stores the reason code. The vn_setattr operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_setattr processing

vn_setattr is used to set file attributes, as described in "Getting and setting attributes" on page 37.

Specific processing notes

| Table 10. Input fields for attribute_structure | | |
|------------------------------------------------|------------------------|---------------------------------------------------------------------------------------------|
| Set flags | Attribute fields input | Description |
| at_modechg | at_mode | Set the mode according to the value in at_mode |
| at_ownchg | at_uid at_gid | Set the owner user ID (UID) and group ID (GID) to the values specified in at_uid and at_gid |

| Table 10. Input fields for attribute_structure (continued) | | |
|------------------------------------------------------------|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| Set flags | Attribute fields input | Description |
| at_setgen | at_genvalue at_genmask | Only the bits corresponding to the bits set ON in the at_genmask are set to the value (ON or OFF) in at_genvalue; other bits are unchanged |
| at_trunc | at_sizeh at_size | Truncate the file size to the number of bytes specified by the doubleword at_sizeh and at_size |
| at_atimechg | at_atime | Set the access time of the file to the value specified in at_atime |
| at_atimechg and at_atimeTOD | None | Set the access time of the file to the current time |
| at_mtimechg | at_mtime | Set the modification time of the file to the value specified in at_mtime |
| at_mtimechg and at_mtimeTOD | None | Set the modification time of the file to the current time |
| at_aauditchg | at_aaudit | Set the security auditor's auditing flags to the value specified in at_aaudit |
| at_uauditchg | at_uaudit | Set the user's auditing flags to the value specified in at_uaudit |
| at_ctimechg | at_ctime | Set the change time of the file to the value specified in at_ctime |
| at_ctimechg and at_ctimeTOD | None | Set the change time of the file to the current time |
| at_reftimechg | at_reftime | Set the reference time of the file to the value specified in at_reftime |
| at_reftimechg and at_refTOD | None | Set the reference time of the file to the current time |
| at_filefmtchg | at_filefmt | Set the file format of the file to the value in at_filefmt |
| at_seclabelchg | at_seclabel | Set the initial security label of the file to the value in at_seclabel |

1. In addition to the attribute fields that are specified according to <u>Table 10 on page 212</u>, the following ATTR header fields are provided by the caller:

ATTR.at_hdr.cbid

Contains ATTR

ATTR.at_hdr.cblen

Specifies the length of attribute_structure.

- 2. Multiple attributes can be changed on a single vn_setattr call. The PFS should ensure that either all supported changes or no changes are permanently recorded for a single vn_setattr call.
- 3. Changing mode (at_modechg = ON):
 - SAF's Change File Mode callable service is called to perform the necessary security checks and to actually make the change to the mode field in the FSP.
 - The at_mode field is mapped by modes.h.

Note:

- a. The file type, which is contained within at_mode, is not changed by the vn_setattr operation.
- b. Files that are open when the vn_setattr service is called retain the access permission they had when the file was opened.
- 4. Changing owner (at_ownchg = ON):
 - SAF's Change Owner and Group callable service is called to perform the necessary security checks and to update the owner or group fields in the FSP.

Note: When the UID or GID value is set to -1, the original value remains unchanged.

- 5. Changing general attribute bits (at_setgen = ON):
 - SAF's Check Access callable service is called for Write access before the PFS changes the file's general attribute bits.
 - For each bit ON in the genmask, the corresponding bit in the file's attributes is set to the value (ON or OFF) from the corresponding genvalue field.
- 6. Truncating a file (at_trunc = ON):
 - SAF's Check Access is called for write access before the PFS changes the file's size.
 - The truncation of a file changes the file size to the doubleword value that is represented by at_sizeh and at_size, beginning from the first byte of the file.
 - If the file is larger than the specified file size, the data from the specified size to the original end of the file is removed. Full blocks are returned to the file system to be used again.
 - If the file is shorter than the specified size, bytes between the old and new lengths are read as zeros.
 - When the file size is changed, the PFS calls SAF's Clear Setid callable service.

Note:

- a. The LFS handles enforcing file size limits for vn_setattr.
- b. The truncate() function requires write permission to the file, whereas ftruncate() requires that the file be open for writing. The LFS handles this difference by calling vn_setattr for the former and vn_trunc for the latter when the file is open for writing.
- 7. Changing time fields (atime, mtime, ctime, and reftime):
 - All time fields in the ATTR are in POSIX format.
 - Each time field is controlled by a pair of bits: the chg bit and the TOD bit, as listed in <u>Table 10 on page 212</u>.
 - The chg bit (for instance, at_atimechg) indicates that the corresponding time field is to be changed.
 - The TOD bit (for instance, at_atimeTOD) indicates whether the change is to an explicitly specified time (bit is off) or to the current time of day (bit is on).
 - For a time change using an explicit time value, the SAF check file owner service is called to verify that the caller is the file owner or has appropriate privileges before the PFS changes the corresponding file time field.
 - To set the time to the current time of day, SAF's Check Access must be called to check for write permission. If the caller does not have write permission, SAF's Check File Owner is called to verify that the caller is the file owner or has appropriate privileges. One of the SAF checks must succeed before the PFS will change the corresponding time field of the file.
- 8. Changing auditor audit flags (at_aauditchg = ON) or user audit flags (at_uauditchg = ON):
 - SAF's Change Audit Options callable service is called to perform the necessary security checks and to update the corresponding audit field in the FSP.
- 9. Changing file format (at_filefmtchg = ON):

- SAF's Check File Owner is called before the PFS saves the new file format value.
- 10. When any attribute field is changed successfully, the file's change time is also updated.
- 11. Changing the security label (ATTSECLABELCHG=ON):
 - For the security label to be changed, the user must have RACF SPECIAL authorization and appropriate privileges, and no security label must currently exist on the file. (For more information about appropriate privileges, see Authorization in z/OS UNIX System Services Programming: Assembler Callable Services Reference.) Only an initial security label can be set. An existing security label cannot be changed. The function successfully sets the security label if the SECLABEL class is active. If the SECLABEL class is not active, the request returns successfully, but the security label is not set.
 - You can invoke the SAF IRRSSB00 callable service to set the security label.

Serialization provided by the LFS

The vn_setattr operation is invoked with an exclusive latch held on the vnode. Shared read support can be modified by the PFS in the OSI upon return from the vn_setattr operation.

Security calls to be made by the PFS

Refer to the previous notes for the security calls that are made for the various file attributes.

Related services

• "vn_getattr — Get the attributes of a file" on page 142

vn_setpeer — Set a socket's peer address

Function

The vn_setpeer operation presets the peer address that is associated with a socket. This causes all datagrams that are sent using the specified socket to be sent to the address that is specified here. Only datagrams that are sent from the specified address are received.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Sockaddr_length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

A fullword that supplies the length of the Sockaddr buffer and returns the length of the Sockaddr structure that is returned.

Sockaddr

Supplied and returned parameter

Type

Structure

Length:

Specified by Sockaddr_length

A structure that varies depending on the address family type. It contains the address that is to be used for this operation. For an example of this mapping for AF_INET, see **in.h**.

Option

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies the option of the vn_setpeer operation to use. These values are mapped by socket.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_setpeer operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_setpeer operation stores the return code. The vn_setpeer operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_setpeer operation should support at least the following error value:

Return_code

Explanation

EINVAL

The address length that was specified is not the size of a valid address for the specified address family.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_setpeer operation stores the reason code. The vn_setpeer operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_setpeer processing

The vn_setpeer call is new for POSIX 1003.12, and is not currently supported by any of the socket PFSs.

Specific processing notes

- Calling setpeer() with the option set to SO_SET causes all datagrams that are sent through this socket to be sent to the address that is specified by sockaddr. Only datagrams that originate from sockaddr are received.
- Calling setpeer() with the option set to SO_SET on the passive end of a virtual circuit before calling listen() or connect() causes an error. Calling connect() and specifying a destination address with setpeer causes an error. Calling setpeer() after a connection is established is an error.
- The result of calling setpeer() with the option set to SO_SET on an endpoint that has already had the destination address preset causes an error if the underlying protocol does not support multiple peer addresses for a given endpoint.

Serialization provided by the LFS

The vn_setpeer operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

Related services

None.

vn_shutdown - Shut down a socket

Function

The vn_shutdown operation shuts down all or part of a duplex socket connection.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

How

Supplied parameter

Type:

Integer

Length:

Fullword

The How parameter explains the condition of the shutdown request. The values that can be specified are:

Value

Condition

SHUT_RD

Shutdown reads from this socket.

SHUT_WR

Shutdown writes to this socket.

SHUT_RDWR

Shutdown reads to and writes from this socket.

These values are defined in socket.h.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_shutdown operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_shutdown operation stores the return code. The vn_shutdown operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_shutdown operation should support at least the following error value:

Return_code

Explanation

EINVAL

The How argument was not valid.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword where the vn_shutdown operation stores the reason code. The vn_shutdown operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Specific processing notes

The How parameter comes directly from the shutdown() system call. The LFS does not check this parameter.

Serialization provided by the LFS

The vn_shutdown operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

Related services

- "vfs_socket Create a socket or a socket pair" on page 97
- "vn_close Close a file or socket" on page 130

vn_sndrcv — Send to or receive from a socket

Function

The vn_sndrcv operation sends datagrams to or receives datagrams from a socket. The socket must be connected.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Open flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). See "Specific processing notes" for details on how the fields in this structure are processed.

Flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that indicates special processing requests. The defined values for this field are mapped by socket.h.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sndrcv operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful. The value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sndrcv operation stores the return code. The vn_sndrcv operation returns Return_code only if Return_value is -1. For a complete list of supported return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_sndrcv operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------|
| EFAULT | A buffer address that was specified is not in addressable storage. |
| EINVAL | An incorrect parameter was specified. |
| EWOULDBLOCK | The operation would have required a blocking wait, and this socket was marked as nonblocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sndrcv operation stores the reason code. The vn_sndrcv operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_sndrcv processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the recv and send functions.

Specific processing notes

The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u hdr.cblen

Specifies the length of the user_IO_structure

UIO.u buffaddr

Specifies the address of the caller's buffer

UIO.u_buffalet

Specifies the ALET of the caller's buffer

UIO.u_count

Specifies the maximum number of bytes that can be written to or read from the caller's buffer

UIO.u_asid

Specifies the ASID of the caller

UIO.u rw

Specifies whether the request is a read (0) or a write (1)

UIO.u key

Specifies the storage key of the caller's buffer

The UIO contains fields that may point to a 64-bit addressable user buffer. When FuioAddr64 is on (and FuioRealPage is off), FuioBuff64Vaddr points to a buffer, an IOV64, or an MSGH64.

Serialization provided by the LFS

The vn_sndrcv operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

vn_sockopt — Get or set socket options

Function

The vn_sockopt operation gets or sets options that are associated with a socket.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Direction

Supplied parameter

Type:

Integer

Length:

Fullword

The Direction parameter specifies whether the socket options are to be set or returned to the requester. The values for this parameter are defined in the BPXYPFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465) and are as follows:

Value

Meaning

GET SOCKOPT

Get the current socket options

SET SOCKOPT

Change the socket options

SET IBMSOCKOPT

Change SetIBMsockopt options

Level

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies the protocol level. This area is mapped by socket.h.

Option

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that specifies the option that is to be set or retrieved. This area is mapped by socket.h.

Option_data_length

Supplied parameter

Type:

Integer

Length:

Fullword

The Option_data_length is a fullword that describes the length of the Option_data parameter.

Option_data

Supplied parameter

Type:

Defined by the Option

Length:

Specified by Option_data_length

For most options, this is either a zero or nonzero, depending on whether the option is disabled or enabled.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sockopt operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sockopt operation stores the return code. The vn_sockopt operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_sockopt operation should support at least the following error value:

Return_code

Explanation

ENOPROTOOPT

The level that was specified is an incorrect protocol.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_sockopt operation stores the reason code. The vn_sockopt operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_sockopt processing

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the getsockopt and setsockopt functions.

Serialization provided by the LFS

The vn_sockopt operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

vn_srmsg — Send messages to or receive messages from a socket

Function

The vn_srmsg operation sends or receives messages on a socket. Message headers are used for the reading or writing operation. The socket can be either connected or unconnected.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on

page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to "Security responsibilities and considerations" on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for the mapping of this structure.

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). For more information about how the fields in this value are processed, see the section on specific processing notes in "Implementation notes for vn_srmsg" on page 230.

Flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that indicates special processing requests. The defined values for this field are mapped by socket.h.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srmsg operation returns the results of the operation, as one of the following return codes:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful. The value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srmsg operation stores the return code. The vn_srmsg operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_srmsg operation should support at the error values that are listed in Table 11 on page 229.

Table 11. List of return codes for vn_srmsg

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------|
| EFAULT | The address of one of the buffers is not in addressable storage. |
| EINVAL | An incorrect parameter was specified. |
| EWOULDBLOCK | A socket that has been defined as nonblocking cannot complete its operation without blocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srmsg operation stores the reason code. The vn_srmsg operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes for vn_srmsg

Overview of vn_srmsg processing

The vn_srmsg call can be used by connected or nonconnected sockets.

For more information about the semantics of this operation for a POSIX-conforming PFS, refer to the publications that are mentioned in <u>"Finding more information about sockets" on page 2</u> for the recvmsg() and sendmsg() functions.

Specific processing notes

• The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file).

UIO.u hdr.cblen

Specifies the length of the user_IO_structure.

UIO.u buffaddr

Specifies the address of the caller's message header.

UIO.u_buffalet

Specifies the ALET of the caller's message header.

UIO.u_count

Specifies the length of the message header.

UIO.u asid

Specifies the ASID of the caller.

UIO.u rw

Specifies whether the request is a read (0) or a write (1)

UIO.u key

Specifies the storage key of the caller's buffer.

UIO.u_iovalet

Specifies the ALET of the io.

UIO.u_iovbufalet

Specifies the ALET of the iov's buffers. All buffers must use the same ALET.

- The UIO contains fields that might point to a 64-bit addressable user buffer. When FuioAddr64 is on (and FuioRealPage is off), FuioBuff64Vaddr points to a buffer, an IOV64, or an MSGH64.
- The message header is defined in socket.h.
- The iov structure is defined in uio.h.

Serialization that is provided by the LFS

The vn_srmsg operation is invoked with an exclusive latch held on the vnode of the socket.

Security calls to be made by the PFS

None.

vn_srx — Send or receive CSM buffers

Function

The vn_srx operation sends or receives data using CSM (Communications Storage Manager) buffers.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients," on page 465 for the mapping of this structure.</u>

Open_flags

Supplied parameter

Type:

Structure

Length:

Fullword

A fullword that contains the bits that are associated with the socket. The defined values for this field are mapped by fcntl.h.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see Appendix D, "Interface structures for C language servers and clients," on page 465). See "Specific processing notes" for information about how the fields in this structure are processed.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srx operation returns the results of the operation, as one of the following values:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0 or greater

The operation was successful. The value represents the number of bytes that were transferred.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srx operation stores the return code. The vn_srx operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_srx operation should support at least the following error values:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------|
| EFAULT | A buffer address that was specified is not in addressable storage. |
| EINVAL | An incorrect parameter was specified. |
| EWOULDBLOCK | A socket that has been defined as nonblocking cannot complete its operation without blocking. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_srx operation stores the reason code. The vn_srx operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_srx processing

The Communications Storage Manager (CSM) provides a facility that allows programs to avoid data moves on a communications session by transferring buffer ownership instead of copying the buffer contents. For more information about CSM, see *z/OS Communications Server: CSM Guide*.

The controlling parameters of the vn_srx operation are passed in a msghdrx structure, which is pointed to from the UIO. Included in the msghdrx is a pointer to an array of structures, each of which points to a data buffer that is obtained from CSM. For more information about the msghdrx structure and the semantics of this operation, see srx_np (BPX1SRX, BPX4SRX) — Send or receive CSM buffers on a socket in socket in <a href="mai

The vn_srx call can be used on either connected or unconnected sockets.

Specific processing notes

• The following UIO fields are provided by the LFS:

UIO.u_hdr.cbid

Contains UIO_ID (from the BPXYVFSI header file)

UIO.u hdr.cblen

Specifies the length of the user_IO_structure

UIO.u_buffaddr

Specifies the address of a primary address space copy of the caller's msghdrx structure

UIO.u_buffalet

Specifies the ALET, 0, of the msghdrx structure

UIO.u_count

Specifies the length of the msghdrx structure that is being passed

UIO.u asid

Specifies the ASID of the caller

UIO.u_rw

Specifies whether the request is a read (0) or a write (1)

UIO.u key

Specifies the storage key of the caller

- The msghdrx structure is defined in bpxysrxh.h.
- The user's msghdrx is copied into the kernel by the LFS, and this copy is passed to the PFS. This kernel msghdrx, with any changes that are made by the PFS, is copied back to the user after the operation.
- The use of Msghdrx_length=0 in BPX1SRX to determine support for this operation is handled by the LFS, and not passed down to the PFS.

Serialization provided by the LFS

The vn_srx operation is invoked with an exclusive latch held on the vnode.

Security calls to be made by the PFS

None.

vn_symlink — Create a symbolic link

Function

The vn_symlink operation creates a symbolic link to a pathname or an external name. A file that is named Link_name, of type "symbolic link", is created within the directory that is represented by Token_structure. The content of the symbolic link file is the path name or external name that is specified in Pathname.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Input parameter format

Parameters

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations" on page 12</u> for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

Pathname length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Pathname. The Pathname can be up to 1023 bytes long.

Pathname

Supplied parameter

Type:

Character string

Length:

Specified by the Pathname_length parameter

An area that contains the path name or external name for which a symbolic link is to be created.

A path name can begin with or without a slash:

- If the path name begins with a slash, it is an absolute path name; the slash refers to the root directory, and the search for the file starts at the root directory.
- If the path name does not begin with a slash, it is a relative path name, and the search for the file starts at the parent directory of the symbolic link file.

A path name contains no nulls.

An external name is the name of an object outside of the hierarchical file system. It may contain nulls.

attribute_structure

Supplied parameter

Type:

ATTR

Length:

Specified by ATTR.at_hdr.cblen.

An area that contains the file attributes that are to be set for the symbolic link being created. This area is mapped by typedef ATTR in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

Link_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

A fullword that contains the length of Link_name. The Link_name can be up to 255 bytes long.

Link_name

Supplied parameter

Type:

Character string

Length:

Specified by Link_name_length parameter

An area that contains the symbolic link that is being created. Link_name contains no nulls.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_symlink service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_symlink service stores the return code. The vn_symlink service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_symlink service should support at least the following error values:

| Return_code | Explanation |
|--------------|--------------------------------------------------------------------------------------------|
| EACCES | The calling process does not have permission to write in the directory that was specified. |
| EEXIST | Link_name already exists. |
| ENAMETOOLONG | Link_name is longer than is supported by the PFS. |
| ENOENT | The parent directory has been marked for deletion. |
| ENOSPC | The file system is out of space. |
| ENOSYS | The PFS does not support storing external links. |
| EROFS | Token_structure specifies a directory on a read-only file system. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_symlink service stores the reason code. The vn_symlink service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_symlink processing

"Creating files" on page 30 provides an overview of symbolic link creation.

Specific processing notes

- The Token_structure that is passed on input represents the directory in which the symbolic link is to be created.
- The following attribute_structure fields are provided by the LFS:

ATTR.at hdr.cbid

Contains Attr_ID (from the BPXYVFSI header file)

ATTR.at_hdr.cbLen

Specifies the length of attribute_structure

ATTR.at genvalue

When ((at_genvalue & S_IFEXTL) == S_IFEXTL) is true, the pathname is an external link.

• An external link is a symbolic link with an extra file attribute bit stored by the PFS. The distinction between a normal symbolic link and an external link is only apparent in the attribute structures that are returned by the PFS for the link file. There is no difference in the way vn_readlink is processed, for example.

If the PFS cannot store this external link bit, it must fail the vn symlink request with ENOSYS.

- If the file that is named in the Name parameter already exists, the vn_symlink operation returns a failing return code.
- Refer to the symlink() function in the POSIX .1a standard (IEEE Std 1003.1a), draft 7, for more information about the semantics of this operation for a POSIX-conforming PFS.

Serialization provided by the LFS

The vn_symlink operation is invoked with an exclusive latch held on the vnode of the directory.

Security calls to be made by the PFS

The PFS is expected to invoke SAF's Check Access callable service to check that the user has write permission to the directory.

Related services

- "vn_readlink Read a symbolic link" on page 181
- "vn_link Create a link to a file" on page 152
- "vn_remove Remove a link to a file" on page 191

vn_trunc — Truncate a file

Function

The vn_trunc operation changes the length of an open file.

Environment on entry and exit

See "Environment for PFS operations" on page 73.

Parameters

Token structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr.cblen.

The Token_structure represents the file (vnode) that is being operated on. It contains the PFS's initialization token, mount token, and the file token. Refer to "LFS/PFS control block structure" on page 16 for a discussion of this structure, and to the TOKSTR typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465 for its mapping.

OSI structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

The OSI_structure contains information that is used by the OSI operations that may be called by the PFS. See Chapter 6, "OSI services," on page 355 for more information.

It also contains MVS-specific information that needs to be passed to the PFS, including SMF accounting fields, a work area, a recovery area, and an optional pointer to an output ATTR structure. For more details on the OSI structure, see "The OSI structure" on page 18.

This area is mapped by the OSI typedef in BPXYPFSI in Appendix D, "Interface structures for C language servers and clients," on page 465.

Audit_structure

Supplied parameter

Type:

CRED

Length:

Specified by CRED.cred_hdr.cblen.

The Audit_structure contains information that is used by the security product for access checks and auditing. It is passed to most SAF routines that are invoked by the PFS.

Refer to <u>"Security responsibilities and considerations"</u> on page 12 for a discussion of security processing, and to the CRED typedef in BPXYPFSI in <u>Appendix D</u>, <u>"Interface structures for C language servers and clients,"</u> on page 465 for the mapping of this structure.

File_length

Supplied parameter

Type:

Integer

Length:

Doubleword

A doubleword that contains the number of bytes to which the file size is to be set. Only positive values are passed by the caller.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_trunc operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_Code values must be filled in by the PFS when Return_value is -1.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_trunc operation stores the return code. The vn_trunc operation returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The vn_trunc operation should support at least the following error value:

Return_code

Explanation

EROFS

The file is on a read-only file system.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the vn_trunc operation stores the reason code. The vn_trunc operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. These reason codes are documented by the PFS.

Implementation notes

Overview of vn_trunc processing

The vn_trunc changes the file size to File_length bytes.

Specific processing notes

- The difference between vn_trunc and vn_setattr(truncate) is that vn_trunc is called for ftruncate(), and therefore does not do a security check. vn_setattr(truncate) is called for truncate() and must do a security check.
- When a file is truncated, all data from File_length to the original end of the file must be removed.

 Full blocks are returned to the file system so that they can be used again, and the file size must be
 - changed to the lesser of File length or the current length of the file.
- When the file is expanded, its length is changed to File_length and unwritten bytes read between the old end-of-file and the new end-of-file are returned as zeros.
- The LFS ensures that the file is a regular file, open for writing if necessary, and that the File_length is not negative.
- When the file size is changed successfully, the PFS calls SAF's Clear Setid callable service.
- The LFS enforces any file size limits that may be in effect.
- Refer to the ftruncate() function in the POSIX .1a standard (IEEE Std 1003.1a), draft 7, for more information about the semantics of this operation for a POSIX-conforming PFS.

Serialization provided by the LFS

The vn trunc operation is invoked with an exclusive latch held on the vnode of the directory.

Security calls to be made by the PFS

Clear Setid.

Related services

• "vn_open - Open a file" on page 168

Chapter 4. VFS servers

A VFS server is a program that registers as a VFS server with z/OS UNIX by calling the v_reg() function. There is no special system definition that is required to become a VFS server.

VFS servers must have appropriate privileges, which are defined as *superuser authority*. For more information about appropriate privileges, see <u>Authorization</u> in <u>z/OS UNIX System Services Programming</u>: Assembler Callable Services Reference. This topic describes:

- How to install a virtual file system (VFS) server.
- · How a VFS server is activated and deactivated.
- The functions that must be provided by a VFS server.
- The functions that are provided for it.
- · Security considerations.

A VFS server is a program that uses the VFS callable services API to access objects in the z/OS UNIX file hierarchy.

This is not to be confused with other types of servers. For example, consider a file transfer program that moves files between z/OS UNIX and a workstation. If this program uses the open(), read(), and write() functions to access the files, it is certainly a "file server", but this type of program it is not discussed in this topic. On the other hand, if this same program uses the $v_get()$ and $v_rdwr()$ functions, it is the type of server that is discussed here. Such a program could be written as a set of LU 6.2 transactions, independent of which interface is used to access the files.

The VFS callable services API is designed to meet the requirements of an NFS-style server, but it is not limited to those applications. The main difference between the POSIX API and the VFS callable services API is that POSIX programs refer to files by path names and VFS servers refer to them by file identifiers (FIDs). VFS servers do their own path name resolution to convert a path name into a FID, and later use the FID to access the file. The FID is designed to be part of the NFS file handle that the Network File System returns to its clients. A file handle always refers to the same file. A path name, on the other hand, might refer to different files over time, because of rename, remove/re-create, or symbolic link changes.

Installation

A VFS server may be installed in the hierarchical file system or in standard MVS load libraries. The choice depends on how the VFS server is activated.

Activation and deactivation

Because any program with appropriate privileges can become a VFS server by calling the v_reg() function, VFS servers can be activated in all the ways that a program can be run on MVS. They may be independent address spaces with their own START cataloged procedure; they can run as batch programs; or they can be shell processes that are run in the background or started through /etc/init. A VFS server can even be a command or program that is invoked directly by a user and run in the foreground of that user's process.

Once a program successfully calls v_reg(), it is registered as a VFS server with z/OS UNIX and dubbed, if it has not already been dubbed. After a server is registered, appropriate privileges are not needed for subsequent v_ functions.

Server registration is not inherited across fork() or spawn().

A VFS server, like any other program, can use the standard file and socket APIs of z/OS UNIX, along with other MVS APIs. The VFS server aspects of the program have to do only with its use of the VFS callable services API.

Termination considerations

There is no service provided to unregister with z/OS UNIX. If and when a VFS server's process terminates, z/OS UNIX removes its registration.

A VFS server can, however, release itself from all z/OS UNIX associations by calling undub (BPX1MPC), which also removes its registration as a VFS server.

When z/OS UNIX removes a VFS server's registration, all of the z/OS UNIX resources that are allocated to that VFS server are freed.

Security responsibilities and considerations

The security structure of z/OS UNIX consists of two parts: the user's identity and the file's access control information. A VFS server is primarily concerned with the user's identity.

As a z/OS UNIX superuser, a VFS server has free access to all z/OS UNIX resources. Consequently, it is the VFS server's responsibility to make sure that everything it does on behalf of a particular end user is done under the authority of that end user.

For a VFS server that is directly invoked by a local user, such as by a command, the simplest thing to do is to require that the invoker be a superuser. If the VFS server runs as a setuid program or is a more traditional client/server type of server, the rest of this topic applies.

It is expected that a VFS server will assume the identity of its end user while making calls to z/OS UNIX services. This consists of several steps:

- 1. End users must be defined to both MVS and z/OS UNIX. They will have both an MVS user ID and a z/OS UNIX UID-GID pair.
- 2. The VFS server must know the MVS user ID of the end user.
- 3. The VFS server invokes SAF services to set up a security environment based on that MVS user ID.
 - RACROUTE REQUEST=VERIFY, ENVIR=CREATE is used to initialize the MVS part of the security environment, and Init_USP is used to add the z/OS UNIX information.
 - For acceptable performance, a VFS server should maintain enough state information so that it could save this security environment for a given end user and not have to re-create it on every request.
- 4. Before calling z/OS UNIX services for an end user, the VFS server updates its address space or task to assume the security environment that was set up by RACROUTE and Init_USP, by storing the ACEE from RACROUTE in the security environment field of the Task Control Block (TCBSENV).

If this is a read or write function, the VFS server must decide whether file access checking is to be performed by the system. If the VFS server maintains enough state information to recognize the first reference by a particular end user to a particular file object, it can limit the overhead of access checking to that first reference. Otherwise, every read or write must be access checked. Other types of calls are unconditionally access-checked if access control is defined for the call.

- After the call, or sequence of calls, for that end user, the VFS server reverts to its own security environment or sets up for the next end user.
- 5. When an end user is finished using the VFS server, the VFS server invokes RACROUTE REQUEST=VERIFY, ENVIR=DELETE to free the security environment.

Access control checks are performed by the PFSs that own the data. These checks are based on information that is associated with each individual file. The VFS server does not control these access checks except for read and write operations.

For more information about these interfaces, see z/OS Security Server RACF Callable Services.

VFS server considerations for 64-bit addressing

For a server that is entirely 31-bit, no changes are required.

For v_op calls in AMODE 31:

- A server may set FuioAddr64 and use 64-bit addressing within the UIO to address its own buffers for the v_rdwr, v_readdir, and v_readlink operations.
- The UIO itself and all the calling parameters must be 31-bit addressable.

For v_op calls in AMODE 64:

- The server must set FuioAddr64 appropriately to indicate whether a 31-bit or a 64-bit buffer address is being passed.
- Register 1 and the parameter list must all be 64-bit addresses; the parameters themselves may be above or below 2 gigabytes.
- BPX1 callers must use the BPX4 entry names.

Using the VFS callable services application programming interface

The VFS callable services API separates a VFS server from the logical file system (LFS) of z/OS UNIX. It is a set of protocols and callable services that deal with accessing objects in the file hierarchy.

This topic describes the services that are provided to a VFS server and the requirements and responsibilities that are placed on a VFS server.

As described in Chapter 1, "General overview," on page 1, a VFS server is just one of many users of the file system. File requests that are made through the various APIs that are supported by z/OS UNIX are routed by the LFS to the PFS that owns or controls the file that is being referred to. The PFS cannot tell what kind of program originated these requests.

Operations summary

The VFS callable services API contains the functions listed in Table 12 on page 243.

| Table 12. API functions for VFS callable services | |
|---------------------------------------------------|---------------------------------------------------|
| Function | Description |
| v_access | Check access permissions |
| v_close | Close a file |
| v_create | Create a regular, FIFO, or character special file |
| v_export | Export a file system |
| v_fstatfs | Get file system attributes |
| v_get | Get a vnode from a file ID (FID) |
| v_getattr | Get attributes for a file |
| v_link | Create a hard link to a file |
| v_lockctl | Control locks |
| v_lookup | Look up a file name |
| v_mkdir | Create a directory |
| v_open | Open or create a file |
| v_rdwr | Read or write to a file |
| v_readdir | Read a directory |
| v_readlink | Read a symbolic link or external link file |
| v_reg | Register a process with the file system |

| Table 12. API functions for VFS callable services (continued) | |
|---------------------------------------------------------------|-------------------------------------------------|
| Function | Description |
| v_rel | Release a vnode |
| v_remove | Remove a file |
| v_rename | Rename a file or directory |
| v_rmdir | Remove a directory |
| v_rpn | Resolve a path name to a file system and a file |
| v_setattr | Set attributes of a file |
| v_symlink | Create a symbolic or external link |

VFS server – LFS control block structure

Files are contained within mounted file systems, and the collection of all the files in all the mounted file systems forms the z/OS UNIX file hierarchy.

The LFS structures for files and file systems are not directly addressable by a VFS server. Consequently, files and file systems are abstracted somewhat on the VFS callable services API.

A file is represented to a VFS server by a vnode token with the following characteristics:

- A vnode token is similar to a POSIX file descriptor, in that it is the main input to all calls that refer to the file.
- Vnode tokens are obtained most often from v_get() and v_lookup(), but also from v_rpn(), v_create(), and v_mkdir()
- Vnode tokens are not inherited across fork().
- Vnode tokens are released with v_rel(). All vnode tokens that are obtained must eventually be released. After v_rel() is called, any subsequent call with the same vnode token fails.
- A single vnode token may be cached by the VFS server and shared among many end users. A single vnode token can be used by several tasks at the same time, but v_rel() is mutually exclusive with all other operations.
- Many different vnode tokens can be obtained for the same file.
- A vnode token that has not been released is always valid for a call in the sense that the VFS server program will not abnormally end from using it.

Files that are deleted are still accessible with existing vnode tokens. This is the same behavior that is expected for POSIX file descriptors that have not been closed. If the underlying real file system is unmounted with IMMEDIATE or FORCE, however, calls that are made with vnode tokens for files in that file system fail with an error code.

A file system is represented to a VFS server by a VFS token with the following characteristics:

- The VFS token represents a virtual file system (VFS). With NFS, for example, this corresponds to a client mount. The directory that is mounted becomes the root of this VFS.
- A VFS is a subset of some real mounted file system. VFS servers do not refer to the mounted file system directly.
- VFS tokens are obtained from v rpn(), and they are never released.
- VFS tokens are used only with the v_get() function, which converts a file ID within a given VFS into a vnode token.
- All VFS tokens for VFSs that are contained within the same real mounted file system are the same.
- VFS tokens remain valid for as long as the underlying real file system is mounted.

After the underlying file system is unmounted, v_get() with the prior VFS token fails with an error code. This remains true even if the real file system is remounted.

Registration

A VFS server must register with z/OS UNIX by calling the $v_reg()$ service.

v_reg() checks that the VFS server has appropriate privileges (is a superuser), and sets up support for the VFS callable services API.

The input to v_reg() is contained in the NREG structure and includes the name by which the VFS server is to be known.

For more information about the information that is passed during registration, see <u>Appendix D, "Interface</u> structures for C language servers and clients," on page 465.

Mounting and unmounting

Servers do not physically mount file systems. NFS-style servers connect to the file hierarchy at the directory that their client has NFS mounted. They also they access only those files that are in these NFS-mounted directories or lower in the hierarchy within the same physically mounted file system.

The Resolve Path Name service, v_rpn(), is called to implement an NFS mount. The input is the directory path name, as sent by the client. The primary output is a VFS token for the file system that the directory belongs to and the file ID (FID) of the directory. These represent a VFS and its root directory. With this information, the VFS server can access any file in the same file system at or under that directory in the hierarchy.

If several directories in the same real file system are mounted by NFS clients, the VFS server receives the same VFS token for each v_rpn() that is issued during those NFS mounts. This fact is not significant to the VFS server, which associates each VFS token that is obtained with the NFS mount that was performed. There should not be any concern for the physical mount structure that underlies the file hierarchy.

The path name that is passed to v_rpn() can be a regular file; in fact, determining whether it is a file or a directory can be the sole objective of the operation. Usually, though, the path name refers to a directory that serves as a base from which other files are accessed. This access involves path name resolution, which is explained in "Resolving the pathname of a file or directory" on page 246.

When a client NFS unmounts the directory, the VFS server can release whatever information it is maintaining about the mount. This includes releasing any cached vnode tokens. The VFS server does not have to inform z/OS UNIX or release the VFS token in any way.

Overview of NFS processing

To understand how the VFS callable services API is used, you need to understand the typical sequence of operations for a network file system (NFS) server.

There are three major interactions between an NFS client and its NFS server:

- 1. Mounting a path name
- 2. Resolving the path name of a file or directory
- 3. Accessing an individual file or directory

Mounting a path name

Initially, an end user at an NFS client mounts the path name of a directory that resides at the VFS server's system onto some mount point directory at the client. These mounts are often done automatically during the initialization of the user's workstation. The VFS server object that is mounted may be a regular file, rather than a directory, in which case information in "Resolving the pathname of a file or directory" on page 246 does not apply. This topic describes only mounting a directory at the VFS server. This directory is referred to as the "initial directory."

The flow for an "NFS mount" is as follows:

- 1. The initial directory path name is sent to the VFS server through the Mount remote procedure call (RPC).
- 2. v_rpn() is called by the VFS server to resolve the path name from the RPC into: a VFS token for the path name object's file system; a vnode token for the object itself; and the file ID (FID) of the object.
- 3. The VFS server builds a structure to represent and remember this mount operation.

A unique "mount key" is constructed and saved in the structure. This may be, for example, an index number into a mount table array or a time stamp. It is used later to find the mount structure.

The VFS token is saved in the mount structure.

- 4. An NFS file handle is constructed from the FID, mount key, and other control information that is specific to this VFS server.
- 5. Either the vnode token of the object is cached, or v_rel() is called to release it.
- 6. The file handle of the object is returned to the client.

After this exchange, the client has a file handle for the initial directory that was mounted. This file handle is saved and associated with the local mount point. All end user references to files at or below the local mount point now refer to files in the VFS server's file hierarchy that are at or below the initial directory.

Resolving the pathname of a file or directory

Subsequently, the client's user refers to a specific file by path name, and the path name is resolved locally, component by component, until an NFS mount point is reached.

The client then continues with the following process:

- 1. The lookup RPC is called with the initial directory file handle, which was saved with the NFS mount point, and the next name component of the path name, which is the name after the mount point name.
- 2. The VFS server uses the mount key from the file handle to find the related mount RPC structure where the VFS token from v_rpn() was saved.
- 3. v_get() is called with that VFS token and the FID from the file handle. This call returns the vnode token for the directory that is represented by the file handle. If the vnode token had been cached, this step could be skipped.
- 4. v_lookup() is called with that directory vnode token and the component name from the RPC. This call returns the named object's vnode token, FID, and attributes.
- 5. An NFS file handle for the named object is constructed from its FID, the mount key, and other control information that is specific to this VFS server.
- 6. v rel() is called to release the directory vnode token.
- 7. v rel() is called to release the named object's vnode token.
- 8. The file handle and attributes of the object are returned to the client.
- 9. At the client the file handle represents the named object that was just looked up. The object's path name is equal to that part of the original path name that has been resolved so far. From the attributes that are returned, the client can tell what type of file the object is:
 - If it is a symbolic link, the readlink RPC is called to retrieve the link's contents.
 - If it is a directory, and there are more name components of the path name to be resolved, the client moves on to the next name component and calls the lookup RPC with that name and the file handle that was just returned.
- 10. The VFS server continues with step <u>"2" on page 246</u>, and this loop continues iteratively through each name component of the remaining path name string.

Note: This processing does not generally cross real mount points at the server. If a particular directory encountered during these lookups has been mounted on, lookups in that directory return files from that directory, not from the directory that was mounted over it. As a consequence, all files that are obtained

from a given initial directory are in the same real mounted file system. This also means that an NFS client's view of the file hierarchy is different from that of a local user. NFS clients can see "underneath" real mount points that are reachable from the directories they have NFS-mounted. This is usually of no consequence, because most mount-point directories are empty. Refer to "v_lookup (BPX1VLK, BPX4VLK) — Look up a file or directory" on page 294 for a way to override this behavior.

After a path name has been fully resolved to the file handle of an object in the VFS server's file hierarchy, the client can use that handle on later RPC requests to perform a specific function against that object. For example:

- If the user program does an open() and read() on a file, the client resolves the open's pathname and uses the file handle to satisfy the read by issuing a read RPC.
- For a mkdir(), the path name is resolved up to the last name component, yielding the file handle of the parent directory in which the new directory is to be defined. The make_dir RPC is then called with this file handle and the last name component of the original path name.
- For a stat(), the path name is resolved to its end, and the file handle is used on a get_attributes RPC.
- The lookups and readlinks that are involved with path name resolution itself are also examples of the use of a file handle for specific operations against the directory that is represented by the handle.

Accessing an individual file or directory

After an object's file handle is available, the flow for a functional request is as follows:

- 1. The functional RPC is called with the object's file handle and other parameters that are specific to this function.
- 2. The VFS server uses the mount key from the file handle to find the related mount RPC structure in which the VFS token from v rpn() was saved.
- 3. v_get() is called with that VFS token and the FID from the file handle. This returns the vnode token for the object that is represented by the file handle.
- 4. The appropriate VFS callable services API function is called to perform the operation that is requested by the RPC. The parameters of the call include the object's vnode token, from step "3" on page 247, and the other parameters that are specific to this function.
- 5. v_rel() is called to release the object's vnode token.
- 6. The data or results of the function are returned to the client.

So long as the client has cached a file handle, the pathname resolution process does not have to be repeated, and files and directories can be immediately accessed by their handle. In particular, this simpler flow would be used for all reads and writes against an open file, since the client can save the file handle with the open structures.

Note:

- 1. If the VFS server keeps enough state information, the v_get()-v_rel() pairs can be skipped by caching the vnode token that is used on a sequence of inbound RPC requests. Because NFS clients do not inform their servers when they are finished with a file handle, a server that is caching vnode tokens must eventually clean them up by calling v_rel(), after an inactivity timeout or with some other reclamation algorithm.
- 2. v_rpn() is the only VFS callable services API function that takes a path name for the file it acts upon.

Capabilities and restrictions for Version 4 NFS server processing in a sysplex environment

Starting with z/OS V1R7, z/OS UNIX supports Version 4 NFS server protocols. This support includes new $v_{open}()$ and $v_{close}()$ callable services, including support for file sharing semantics (share reservations), and enhanced lock control interfaces and functionality (provided by the $v_{lockctl}()$ callable service).

The following capabilities and restrictions apply to Version 4 NFS server processing in a sysplex environment:

- To open a file with share reservations, the file must be owned by a system at the z/OS V1R7 level or higher. The following applies to files that are owned by remote systems:
 - If a file is owned by a remote system that supports share reservations, they will be enforced at the
 owning system for all open requests within the sysplex. At the owning system, an open request from
 a down-level remote system behaves just like a local open request.
 - If a file is owned by a remote system that does not support share reservations, the v_open() fails with return code EOPNOTSUPP, reason code JrNoShrsAtOwner. Move the file system to a sysplex member that supports share reservations.
- A file system that has active share reservations on any of its files can be moved to another system that supports share reservations and those share reservations will move with the files and continue to be enforced at the new owning system.

A file system cannot be moved to a down-level system while there are active share reservations on any file in that file system. Any attempt to do so will fail with return code EINVAL, reason code JrCantMoveShares. Either move the file system to a sysplex member that does support share reservations, stop the NFS client applications that are holding share reservations on the files, or wait for those applications to complete.

- When share reservations exist on files that are owned by a remote system and that system crashes, the following occurs:
 - If the file system is taken over by another system that supports share reservations, the reservations will be reestablished and enforced at the new owning system.
 - If the file system is taken over by another system that does not support share reservations, the share reservations can no longer be enforced. The open tokens for the affected files will be invalidated and subsequent operations with those open tokens will be rejected with return code EIO, reason code JrShrsLost. Move the file system to a sysplex member that supports share reservations; the files can then be reopened as they were before.

Note: You can use the AUTOMOVE parameter on the MOUNT command to restrict such takeovers only to systems that support share reservations.

- When a file system is owned by a remote system that does not support the Version 4 NFS server protocols, the following restrictions apply:
 - Enhanced blocker information is not available when a byte range lock request cannot be granted. In such a case, the output BRLM_Rangelock structure will contain zeros.
 - The new purge locks interfaces are not supported unless the masks map to the old functionality—that is, all clients and threads or all threads at a client. TID subsetting cannot be used.
 - The UnLoadLocks function is not supported.

NFS file handles

The VFS callable services API is designed to be used with NFS, and NFS uses file handles to represent files. Two advantages of NFS file handles over path names are that they are a smaller fixed length (usually 32 bytes long), and that they always refer to the same file object even if that object is renamed or if it is deleted and the path name reused for another object. In the latter case, references to the file handle fail, but this is the desired result.

An NFS file handle contains two pieces of information that are needed to convert the handle back to a file. These are the file system in which the file resides and its identifier (FID) within that file system. The FID values, which are generated by PFSs that own the data, are unique within a file system, persistent, and never reused. File systems, however, do not have a persistent and dedicated identifier that can be used in an NFS file handle.

An NFS client expects file handles to be valid for as long as the corresponding VFS server object exists. To support their validity over system or VFS server restarts, the VFS server must maintain a disk file,

or database, that retains some information about the NFS mounts that have been performed. With this database, the VFS server can create unique and persistent file system identifiers to be placed in the file handles along with the file's FID. This file system identifier is called a "mount key", and the following process makes it unique and persistent:

1. On each mount RPC, a unique "mount key" is generated. This can be, for example, an index into a mount table or a time stamp.

The mount key can be reused after the client issues an unmount RPC. Presumably the client will not be using old file handles from directories that it has unmounted.

The initial directory path name from the RPC and the mount key are saved on disk. The file system name and directory FID are also saved.

A mount structure is built to hold the mount key and VFS token. With the mount key the VFS server is able to find the mount structure and extract the VFS token.

- 2. Each file handle that is constructed contains the file's FID and the mount key for the mount RPC under which the file resides.
- 3. Each time the VFS server is started, it reads the mount file and rebuilds the corresponding mount structures with their saved mount keys.

v_rpn() is called, with the saved path name, to get a new VFS token, which is saved in the new mount structure.

At this point the VFS server has re-created the mount state it had before the system was restarted, and it can field inbound RPCs and process their file handles.

4. With an old file handle the VFS server can find the new mount structure, since the mount key has not changed and the new VFS token is used on the subsequent call to v get().

A mount RPC refers to a specific initial directory, which, when the RPC arrived, was known by the path name that is included with the RPC. That specific directory can be renamed or deleted and the path name reused for another directory. If this happens, the v_rpn() that is issued by a VFS server after it restarts yields the VFS token and FID of a different directory. In this case, the same file handle used by a client before and after the VFS server restart refers to two different objects!

To help detect this situation, v_rpn() returns additional information about the real mounted file system that the initial directory belongs to. This includes the FILESYSTEM name used on the real mount command. By saving this name and the FID of the initial directory, along with the path name and mount key, the VFS server can validate the output of v_rpn() after a restart.

After a restart v_rpn(), the old and new FIDs are compared to catch situations in which the path name has been reused within the same real file system. The old and new FILESYSTEM names are compared in order to catch instances in which the path name was reused across real file systems and happens to refer to an object with the same FID within the new file system. Getting the same FID is not so uncommon; because FIDs are usually generated sequentially, the local root of every real file system, for example, tends to have the same FID.

This scheme requires that the FILESYSTEM name not be reused for another file system, but this is somewhat easier to control. Generally, mount commands are issued only from the BPXPRMxx parmlib member that was used to start z/OS UNIX, or by a small set of people with special authorization. For zFS file systems, also, the FILESYSTEM name is the name of an MVS data set. Controls can be placed over who is able to rename or delete these data sets, and they cannot be renamed or deleted by anyone while they are mounted.

Reading and writing

When reading and writing to files, the VFS server is responsible for maintaining file position and for having access checks performed.

Each call to v rdwr() must specify:

The file offset from which the operation is to start. This differs from the POSIX API, where the LFS
maintains a file cursor.

• Whether security access checks are to be performed. If the VFS server maintains sufficient state information to associate a sequence of reads and writes from the same end user, it can limit these access checks to that end user's first reference, thus improving performance.

Additionally, the VFS server may request a "sync on write", which forces the current write, and all previously written data, to be saved to disk before v_rdwr() returns.

Reading directories

To optimize directory reading, v_readdir() is designed to return as many entries as possible on each call

The VFS server must maintain directory positioning if more than one call must be made to read an entire directory, and this topic describes positioning:

The v readdir() output buffer is mapped by the DIRENT structure, and its format is defined as follows:

- The buffer contains a variable number of variable-length directory entries. Only full entries are placed in the buffer, up to the buffer size specified, and the number of entries is returned on the interface.
- Each directory entry that is returned in the buffer has the following format:
 - 1. 2-byte Entry_length. This length field includes itself.
 - 2. 2-byte Name_length, which is the length of the following Member_name subfield.
 - 3. Member_name. A character field of length Name_length. This name is not null-terminated.
 - 4. File-system-specific data. If (Name_length + 4) = Entry_length, this field is not present. Whenever the field is present, however, it starts with the file's serial number, st_ino, in 4 bytes. This field is not part of POSIX, but it is supported for special-use programs that are dealing with particular file systems that they know about.
- The entries can be packed together, and the length fields are not aligned on any particular boundary.

An example of an entry for the name abc would be X'0007 0003 818283' or X'000B 0003 818283 00001234' with a file serial number of X'1234' also returned.

Entries for "." and ".." may or may not be returned by the PFS that owns the directory.

In order for successive calls to $v_readdir()$ to proceed through a directory from the point at which the last one left off, the VFS server must specify the directory position at which the operation is to start. There are two different ways this can be done:

•

• **Cursor technique**. The cursor that is returned in the UIO contains PFS-specific information that locates the next directory entry. The VFS server is required to preserve the UIO cursor and the entire output buffer from the last v readdir(), and present both of these on the next v readdir().

The PFS may use the cursor as an offset into a simple linear directory file, ignoring the buffer; or it may use it as an offset into the previous output buffer of the last entry returned. The latter approach is used by a PFS with a tree-structured directory, where the previous entry name is used as a key to search for the next entry. That is, the last returned name, a 1-to-255-byte-long text string, is really the "cursor" for the directory position.

• Index technique. The index that is set in the UIO by the VFS server determines which entry to start reading from. To read through a directory, the VFS server starts at one and maintains the index by adding the number of entries that are returned to the previous index. The directory is treated as a one-based array, where the first entry has index 1, the second entry has index 2, and so on.

This technique is slower than the cursor technique, but it is useful when a VFS server does not maintain state information from one call to the next. The index can be passed back to the client, who must return it with the next request to continue reading the same directory for a particular end user.

The UIO contains both the cursor and the index fields that are used with these continuation techniques. The interpretation of these two fields is summarized in the following table:

| The index and | The index and cursor fields are listed, along with the related actions. | |
|---------------|-------------------------------------------------------------------------|-----------------------------------------|
| Index | Cursor | Action |
| 0 | 0 | Start reading from the first entry. |
| 0 | М | Use the cursor value to resume reading. |
| N | 0 | Start reading from entry N. |
| N | М | Start reading from entry N. |

Note: 0=zero; N and M are nonzero values.

A nonzero index overrides the cursor; when both are zero, reading starts from the front of the directory.

The end of the directory stream is indicated in two different ways:

- A Return_value of 0 entries is returned. This happens when the previous v_readdir() exhausted the directory.
- A null name entry is returned as the last entry in the output buffer. A null name entry has an Entry_length of 4 and a Name_length of 0—that is, X'00040000'.

This happens when the current v_readdir() exhausts the directory and there are at least 4 bytes left in the output buffer.

The Move With Destination Key machine instruction or the osi_copyout or osi_uiomove services must be used to write to the user's buffer.

The end of the directory stream is indicated by the PFS in two different ways:

- A Return_value of 0 entries is returned. This must be supported by the PFS for cases in which a vn_readdir is issued and the position is already at the end of the directory.
- A null name entry is returned in the output buffer. A null name entry has an Entry_length of 4 and a Name_length of 0—for example, X'00040000'.

This would be the last entry in the buffer, when the directory end has been encountered on a call and there are at least 4 bytes left in the buffer.

A PFS that supports this indicator helps the caller to run faster. A small directory may be read in only one operation, because the caller can detect that a second call is unnecessary.

Note: POSIX allows open() and read() from a directory, but it only specifies that these operations do not fail with an error. The PFS cannot tell whether a vn_open is from an open() or from an opendir(), but read() results in a vn_rdwr while readdir() results in a vn_readdir. The PFS is free to support vn_rdwr as a traditional UNIX system would, or to just return zero bytes on every operation. The X/Open Portability Guide, Version 4, Issue 2 allows the EISDIR error to be returned for read(). The LFS ensures that only reading is allowed.

Getting and setting attributes

A file's attributes are returned by the v_getattr() function. Many of the other VFS callable services API functions also return file attributes as a performance enhancement, since attributes are often requested in conjunction with those functions.

A file's attributes are changed with the $v_setattr()$ function. A set of "change bits" are used on this interface, and the VFS server specifies exactly which attributes are being updated, along with the new values for those attributes.

Comparing the VFS server and PFS interfaces

Certain traditional VFS or vnode functions are missing from the VFS callable services API. In particular, the set of functions in the VFS callable services API does not match the set of file-related operations in the PFS interface.

Some of these missing functions are not generally used by an NFS-style VFS server, and some of them are implemented in other ways, as explained in the following list.

truncate

A file can be truncated with v_setattr(), specifying the desired file size.

sync

A file can be synchronized, or saved to disk, with v_rdwr(). Specify write, a length of 0, and sync-on-write.

open or close

NFS-style VFS servers do not use these operations. To maintain the performance characteristics of an open-close protocol, the VFS server can limit access checks to an end user's first reference to a particular file.

inactivate

v_rel() is functionally equivalent for a VFS server to the vn_inactive operation for a PFS.

mount or unmount

The v_rpn() function implements an NFS-style mount, and these are not explicitly unmounted.

vfs fid

A file's FID is part of the ATTR structure, so it can be obtained with the v_getattr() function. The ATTR is returned on the operations where a FID would usually be needed, so a VFS server generally does not have to explicitly convert vnodes into FIDs.

vfs root

An NFS-style server does not do real mounts, so it does not need to find the root of a real mounted file system. v_rpn() returns the root of a VFS server's VFS.

check access

A VFS server does not explicitly check to see if its end user has permission to access a file; instead, it assumes the user's identity and makes the file reference under that authority.

Chapter 5. VFS callable services application programming interface

This topic describes the syntax of each of the VFS callable services. The services are arranged in alphabetic order. Sample invocations of each service are in Appendix C, "Callable services examples," on page 453.

Syntax conventions for the VFS callable services

A callable service is a programming interface that uses the CALL macro to access system services. To code a callable service, code the CALL macro followed by the name of the callable service and a parameter list. A syntax diagram for a callable service follows.

```
CALL Service_name,(Parm_1,
Parm_2,

Return_value,
Return_code,
Reason_code)
```

This format does not show the assembler column dependence (columns 1, 10, 16, and 72) or parameter list options (VL and MF). The exact syntax is shown in the examples in Appendix C, "Callable services examples," on page 453.

When you code a callable service:

- You must code all the parameters in the parameter list, because parameters are positional in a callable service interface. That is, the function of each parameter is determined by its position with respect to the other parameters in the list. Omitting a parameter, therefore, assigns the omitted parameter's function to the next parameter in the list.
- You must place values explicitly into all supplied parameters, because callable services do not set defaults.

Elements of callable services syntax

The following paragraphs describe the standard elements that are contained in the callable services reference pages in this information unit.

CALL

CALL is the assembler macro that transfers control and passes a parameter list.

Service_name

The name that assembler understands is the name of a module in the form BPX1xxx, where xxx is a three-character symbol unique to the service. AMODE 64 callers use the form BPX4xxx.

Modules are invoked in one of the following ways:

- A program can load a module first and then branch to the address where it was loaded.
- When you are link-editing a program, you can link to the linkage stub. The program can issue a call.
- You can include in the code the system control offset to the callable service. See Appendix A, "System control offsets to callable services," on page 423 for information about how to use this linkage.

Parm parameters

Parm_1, Parm_2, and so on are placeholders for variables that may be part of a service's syntax.

Return_value

The Return_value parameter is a common parameter for many callable services. It indicates the success or failure of the service. If the callable service fails, it returns -1 in Return_value. For most successful calls to z/OS UNIX services, the return value is set to 0. If the request is not successful, -1 is returned.

Return_code

The Return_code parameter is referred to as the *errno* in the POSIX C interface. The Return_code is returned only if the service fails.

In the callable service description, some of the possible return codes are listed for services that have return codes. The return codes are described in each service if they help describe its function.

Reason codes are listed with the return codes they describe.

For a list of the return codes and their descriptions, see <u>Return codes (errnos)</u> in *z/OS UNIX System Services Messages and Codes*.

Some Return_code values may occur for any callable service: the ones that are unique to z/OS UNIX. They are not always listed under each callable service. For a description of these return codes, see z/OS UNIX System Services Messages and Codes.

Reason_code

The Reason_code parameter usually accompanies the Return_code value when the callable service fails. It further defines the return code. Reason codes do not have a POSIX equivalent.

Reason codes in z/OS UNIX System Services Messages and Codes lists all the reason codes with their descriptions, both alphabetically by name and numerically by value. The value is the lower half of the reason code.

Other subjects related to callable services

See <u>Invocation details for callable services</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference* for a discussion of other subjects related to callable services, such as:

- · How to invoke them
- Their linkage conventions
- · Reentrant versus nonreentrant coding
- · Environmental restrictions
- · Abnormal end conditions
- Authorization

Considerations for servers written in C

The BPXYVFSI header file in Appendix D, "Interface structures for C language servers and clients," on page 465 contains prototypes and linkage macros for all the callable services in this topic. With this header, you can call each service using the v_name that is shown in the title, and you will not have to linkedit your program with the linkage stubs.

This header also contains definitions for all structures, parameters, and constants that are used on the interface.

The calling parameters are the same for C and assembler, but the call format follows C syntax. For example, the call statement for creating a file would look like this:

v_access (BPX1VAC, BPX4VAC) — Check file accessibility

Function

The v_access service verifies that the caller has the requested access permissions to the object that is represented by Vnode_token.

Requirements

| Operation | Environment |
|-----------|-------------|
| | |

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VAC): 31-bit
AMODE (BPX4VAC): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VAC with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file or directory.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Mode

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the permissions to be checked. This area is mapped by the BPXYMODE macro. For information about the BPXYMODE macro, see <u>BPXYMODE — Map the mode constants of the file services</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

The read, write, and execute permissions that are to be checked are set in the Owner permission bits of the Mode (the S_IRUSR, S_IWUSR and S_IXUSR bits).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_access service returns the results of the access check.

When the request is successful, the permission bits that correspond to the caller's allowed access for each of the input mode bits are returned here. This is in the same format as the input Mode parameter, and is therefore a subset of the input Mode bits.

If the request is not successful, -1 is returned.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_access service stores the return code. The v_access service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_access service can return the following value in the Return_code parameter:

Return_code

Explanation

EINVAL

Parameter error; something other than the Owner's permission bits were set.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_access service stores the reason code. The v_access service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. This service is similar to the access() function, but the return of information is handled differently, as follows:

0

Access is denied for all of the bits that were on in the Mode parameter.

Greater then zero

The permissible access is represented by the non-zero bits that are returned here.

-1

The service has failed for some reason other than an access failure.

- 2. The caller's real UID and real GID are used to check for the access that is requested.
- 3. All access is allowed to symbolic link files, regardless of the file's mode setting. This does not imply anything about whether access to the file that is pointed to by the symbolic link would be granted.
- 4. The setting of the AttrLP64times bit in the BPXYATT structure, and not the AMODE of the caller, determines whether 4-byte or 8-byte time fields are used.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321

Characteristics and restrictions

A process must be registered as a server before it can invoke the v_access service; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server "on page 321.

v_close (BPX1VCL, BPX4VCL) — Close a file

Function

Onovotion

The v_close service closes a previous open created by v_open. This frees the open token and removes all state information associated with the v_open.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VCL): | 31-bit |
| AMODE (BPX4VCL): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

```
CALL BPX1VCL,(Vnode_token,
    OSS,
    Open_Token,
    Return_value,
    Return_code,
    Reason_code)
```

AMODE 64 callers use BPX4VCL with the same parameters.

Parameters

Vnode token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file that was previously opened by v_open.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating system specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Open_Token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that holds the open token returned by a prior call to v_open.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_close service returns 0 if the request is successful, or -1 if it is not successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_close service stores the return code. The v_close service returns Return_code only if the Return_value is -1. See z/OS UNIX System Services Messages and Codes for a complete list of possible return code values. The v_open service can return one of the following values in the Return code parameter:

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, the vnode token has been released or one of the token parameters does not contain a valid token value. |
| ESTALE | The open token is stale or already closed. |
| EAGAIN | The open token is currently in use by another thread in this process. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_close service stores the reason code. The v_close service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. The v_close service frees the open token represented by Open_Token and releases all state information associated with it. This includes share reservations and byte range locks associated with the open instance.
- 2. Byte range locks are not associated with open tokens that are created with OPEN_NLM_SHR, so v_close will not release these. They must be explicitly released with the v_lockctl service.
- 3. In accordance with POSIX rules, when v_close releases byte range locks on a file, all locks owned by the open owner are also released—even those obtained by this open owner using other open tokens. Also, for any lock owner who is not the open owner but who is specified on a v_lockctl call using this open token, all of the locks on the file that are owned by that lock owner will be released.
- 4. When v_close releases pending asynchronous byte range locks, the request completion signal will be sent and the lock request will complete with an ECANCELED error.

Note: There is a race condition with the lock request completing normally just before the v_close is issued and, in this case, the lock request will successfully complete but the lock will have been released. This is similar to the case where one thread obtains a byte range lock on a file and another thread closes that file before the first thread has had a chance to use the lock.

- 5. If any other thread is currently issuing a call (such as v_rdwr) using the same open token that v_close is attempting to close, the v_close will fail with an EAGAIN error.
- 6. The v_rel service implicitly calls v_close for any open token that is associated with the vnode token that is being released.

Related services

- "v open (BPX1VOP, BPX4VOP) Open or create a file" on page 301
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_open service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server "on page 321.

v_create (BPX1VCR, BPX4VCR) — Create a file

Function

The v_create service creates a new file in the directory that is represented by Directory_vnode_token. The file can be a regular, FIFO, or character special file. The input Attr is used to define the attributes of the new file. A token that represents the new file is returned in File_vnode_token.

Requirements

| Operation | Environment |
|-------------------------|---------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VCR): | 31-bit |
| AMODE (BPX4VCR): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary |

address space.

Format

AMODE 64 callers use BPX4VCR with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the v_c reate service creates the new file that is named in the Name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the filename that is to be created. The name can be up to 255 bytes long.

Name

Supplied parameter

Type:

Character string

Length:

Specified by Name_length parameter

The name of an area, of length Name_length, that contains the filename that is to be created. It must not contain null characters (X'00').

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_s system calls" on page 433).

Attr

Supplied and returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, that is to be used by the v_create service to set the attributes of the file that is to be created. The attributes of the file that is created are also returned in this area. This area is mapped by the ATTR structure (see <u>"BPXYATTR — Map file attributes for v_system calls"</u> on page 433).

File_vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_create service returns a Vnode_token of the file created.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword where the v_create service returns 0 if the request is successful, or -1 if it is not successful

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_create service stores the return code. The v_create service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_create service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The calling process does not have permission to write in the directory that was specified. |
| EEXIST | The named file exists. |
| EFBIG | The file size limit for the process is set to zero, which means files cannot be created. |
| EINVAL | Parameter error; for example, a supplied area was too small. |
| | The following reason codes can accompany the return code: JRSmallAttr, JRInvalidAttr, JrNoName, JrNullInPath, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENAMETOOLONG | The name is longer than 255 characters. |
| ENFILE | An error occurred while storage was being obtained for a vnode token. |
| ENOTDIR | The supplied token did not represent a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EROFS | The Directory_vnode_token is a file on a read-only file system. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_create service stores the reason code. The v_create service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

1. The following ATTR fields are provided by the caller:

Attr.at hdr.cbid

Contains Attr#ID (from the ATTR structure).

AttrLen

Specifies the length of the ATTR structure.

AttrMode

Specifies the file mode permission bits. For the mapping of this field, see <u>Mapping macros</u> in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

AttrType

Specifies the file type: regular, FIFO, or character special. For the mapping of this field, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

AttrMajorNumber

Specifies the major number for character special files.

AttrMinorNumber

Specifies the minor number for character special files.

AttrCVerSet

Indicates whether the Creation Verifier (AttrCVer) is present.

AttrCVer

Specifies the Creation Verifier for the file. When the AttrCVerSet bit is on and the create is successful, the PFS saves the Creation Verifier, and the server can retrieve it with v_lookup. The Creation Verifier allows the server to determine whether a v_create that returns EEXIST should be considered successful or not. If AttrCVerSet is on, AttrCVer is returned, and the server can compare the file's Creation Verifier with the input Creation Verifier on the v_create. If they are the same, it considers the v_create successful; that is, it is a duplicate of an earlier successful request.

Other fields in the ATTR area should be set to zeros.

- 2. If the file that is named in the Name parameter exists, the v_create service returns a failing return code, and no File_vnode_token is returned.
- 3. Vnode tokens that are returned by the v_create service are not inherited across a fork callable service.
- 4. The caller is responsible for freeing vnode tokens that are returned by the v_create service by calling to the v_rel service when they are no longer needed.
- 5. If the file size limit for the process is set to zero, files cannot be created and file creation fails with EFBIG.
- 6. The value set by umask() for the process does not affect the setting of the mode permission bits.

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_create service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VCR, BPX4VCR (v_create)" on page 453.

v_export (BPX1VEX, BPX4VEX) — Export a file system

Function

The v_export service controls whether a file system is being exported by the server that makes this call. Both local and remote access to this file system are controlled by the server while it is being exported.

Requirements

| Operation | Presentation |
|------------------------|------------------------------------------------------------------------------------|
| Authorization | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode | Task |
| Cross memory mode | PASN = HASN |
| AMODE (BPX1VEX) | 31-bit |
| AMODE (BPX4VEX) | 64-bit |
| ASC mode | Primary mode |
| Interrupt status | Enabled for interrupts |
| Locks | Unlocked |
| Control parameters | All parameters must be addressable by the caller and in the primary address space. |
| | |

Format

```
CALL BPX1VEX, (OSS,

Function,
File_system_name,
VFS_token,
Vnode_token,
Mnte_length,
Mnte,
Attr_length,
Attr,
Vol_Handle,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VEX with the same parameters.

Parameters

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Function

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the function to perform:

- 1. Export the file system. This activates the server's control over the file system.
- 2. Unexport the file system. This deactivates the server's control over the file system.

File_system_name

Supplied parameter

Type

Character string

Length

44 bytes

The name of a 44-character field that identifies the file system that is to be exported or unexported. The name must be left-aligned and padded with blanks.

This is the name that is specified on the mount of the file system. It is an MVS data set name in uppercase letters without surrounding quotation marks.

VFS token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_export service returns the VFS token of the file system.

Vnode_token

Returned parameter

Type

Token

Length

8 bytes

The name of an 8-byte area in which the v_export service returns a vnode token of the root of the file system.

Mnte_length

Supplied parameter

Type

Integer

Length

Fullword

The name of a fullword that contains the length of the area that is to be passed in the Mnte parameter.

The length of this area must be large enough to contain a mount entry header (MnteH) and one mount entry (Mnte). These fields are mapped by the BPXYMNTE macro. For more information about the macro, see Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Mnte

Returned parameter

Type

Structure

Length

Specified by the Mnte_length parameter

The name of an area, of length Mnte_length, in which the v_export service returns information about the file system. This area is mapped by the BPXYMNTE macro. For more information about the macro, see Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Attr_length

Supplied parameter

Type

Integer

Length

Fullword

The name of a fullword that contains the length of the area that is to be passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Returned parameter

Type

Structure

Length

Specified by the Attr_length parameter

The name of an area, of length Attr_length, in which the v_export service returns the file attribute structure for the root. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Vol_Handle

Supplied parameter

Type

Token

Length

16 bytes

The name of a 16-byte area that is to be associated with the exported file system and passed to the exporter exit with each call that is related to this file system.

This parameter is not interpreted by the LFS.

Return_value

Returned parameter

Type

Integer

Length

Fullword

The name of a fullword in which the v_export service returns 0 if the request is successful, or -1 if it is not successful.

Return code

Returned parameter

Type

Integer

Length

Fullword

The name of a fullword in which the v_export service stores the return code. The v_export service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_export service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, the file system that is to be exported or unexported is not mounted or is a sysplex client; or one of the supplied areas was too small. The following reason codes can accompany the return code: JrFileSysNotThere, JrBadEntryCode, JrSmallAttr, JrSmallMnte, JrInvalidOSS, JRCantExpClient. |
| EBUSY | The file system that is to be unexported is not exported by this server. |
| EIO | The file system is being unmounted (JrQuiescing). |
| EAGAIN | The file system has been quiesced (JrQuiesced), or is being asynchronously mounted (JrAsynchMount). |
| EALREADY | The file system that is to be exported is already being exported; or the file system that is to be unexported is not currently exported. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENFILE | An error occurred while storage was being obtained for a vnode token. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a file exporter. |

Reason_code

Returned parameter

Type

Integer

Length

Fullword

The name of a fullword in which the v_export service stores the reason code. The v_export service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of the reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. Vnode tokens that are returned by the v_export service are not inherited across a fork callable service.
- 2. VFS tokens that are returned by the v_export service are inherited across a fork callable service.
- 3. The caller is responsible for freeing the vnode token that is returned by the v_export service, by calling the v_rel() service when it is no longer needed.
- 4. The v_export service is used to gain access to the file system for the server, and is similar to v_rpn() in this respect.

V_export(), though, also activates the server's control over local access through use of the exporter exit that is specified on v_reg(). V_export() acts against a whole mounted file system, while v_rpn() acts against the files underneath arbitrary directories.

- 5. The file system is quiesced before it is exported or unexported, and new requests against the file system are suspended while it is being quiesced. If there is a lot of activity against this file system, the v_export request might take some time to complete, and might cause noticeable pauses for the users.
- 6. The mount point pathname is not returned in the Mnte structure that is returned by v_export.
- 7. On a call to unexport a file system, the VFS_token, Vnode_token, Mnte, Attr, and Vol_Handle parameters are not significant, though they are syntactically required for the call. The Mnte_length and Attr_length fields can be specified as 0, in this case.
- 8. The exporter exit is called during an unexport to notify it about this event.
- 9. When a file system that is mounted with read/write access is shared within a sysplex, it can be exported if it is sysplex-unaware, but only from the sysplex server (owner) system. If it is mounted with read-only access, it can be exported from any system. Any attempts to remount a read-only file system that is exported on a non-owner system will fail. If a read-only file system is exported on the owner and then is remounted with read/write access, the remount will succeed and the file system will become sysplex-unaware after the remount. That is, the non-owner system is function-shipped in read/write mode to the owner system, where it is then exported. This process maintains the integrity of the file system. When the file system is remounted in read-only mode, it becomes sysplex-aware again and all systems will be locally mounted. Once a read-write file system has been exported at the file system sysplex server, it cannot be moved within the sysplex until it is unexported. Attempts to v_export a sysplex client file system are rejected with EINVAL/JRISExported.

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a file exporter before the v_export service is permitted; see <u>"v_reg"</u> (BPX1VRG, BPX4VRG) — Register a process as a server " on page 321.

v_fstatfs (BPX1VSF, BPX4VSF) — Return file system status

Function

The v_fstatfs service returns file system status for the file system that contains the file or directory that is represented by the supplied Vnode_token parameter.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VSF): | 31-bit |
| AMODE (BPX4VSF): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL BPX1VSF,(Vnode_token,
OSS,
FsAttr_length,
FsAttr,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VSF with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents a file or directory that is contained in the file system for which status is being requested.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

FsAttr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the FsAttr parameter. To determine the value of FsAttr_length, use the BPXYSSTF macro. For more information about the BPXYSSTF macro, see BPXYSSTF — Map response structure for file system status in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

FsAttr

Returned parameter

Type:

Structure

Length:

Specified by the FsAttr_length parameter

v fstatfs (BPX1VSF, BPX4VSF)

The name of an area, of length FsAttr_length, in which the v_fstatfs service returns file system status information. This area is mapped by the BPXYSSTF macro. For more information about the BPXYSSTF macro, see BPXYSSTF — Map response structure for file system status in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_fstatfs service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_fstatfs service stores the return code. The v_fstatfs service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_fstatfs service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallFsAttr, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_fstatfs service stores the reason code. The v_fstatfs service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. The supplied FsAttr structure must be at least SSTF#MINLEN (from the BPXYSSTF macro) bytes in length. The length of the structure is SSTF#LENGTH.
- 2. The input FsAttr structure length might not match the length that is supported by the file system. The file system returns the size that represents the amount of valid data in SSTFLEN.

Related services

"v_reg (BPX1VRG, BPX4VRG) — Register a process as a server " on page 321

Characteristics and restrictions

A process must be registered as a server before the v_fstatfs service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VSF, BPX4VSF (v_fstatfs)" on page 454.

v_get (BPX1VGT, BPX4VGT) — Convert an FID to a vnode Token

Function

The v_get service returns a vnode token for the file or directory that is represented by the input FID within the mounted file system that is represented by the input VFS token.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VGT): | 31-bit |
| AMODE (BPX4VGT): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |

Unlocked

address space.

Format

Locks:

Control parameters:

```
CALL BPX1VGT,(VFS_token,
OSS,
FID,
Vnode_token,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VGT with the same parameters.

Parameters

VFS_token

Supplied parameter

Type:

Token

Length:

8 bytes

All parameters must be addressable by the caller and in the primary

The name of an 8-byte area that contains the VFS token for the mounted file system that contains the file or directory that is specified by the FID parameter. This token is obtained from the v_rpn callable service.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

FID

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains the file identifier of the file or directory for which a vnode token is to be returned. The FID for a file is contained in the attribute structure for the file in the AttrFid field; the ATTR structure describes the attribute structure.

Vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_get service returns a vnode token of the file or directory that is supplied in the FID parameter. The token is used to identify the file or directory to other callable services.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_get service returns 0 if the request completes successfully (the file or directory exists), or -1 if the request is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_get service stores the return code. The v_get service returns Return_code only if Return_value is -1. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes. The v_get service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, the VFS token parameter is obsolete. The following reason codes can accompany the return code: JRStaleVFSTok, JRInvalidOSS. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENFILE | An error occurred obtaining storage for a vnode token. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_get service stores the reason code. The v_get service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The FID (file identifier) uniquely identifies a file in a particular mounted file system. For files associated with a physical DASD resource, the FID validly persists across mounting and unmounting of the file system, as well as z/OS UNIX re-IPLS. This distinguishes the FID from the vnode token, which relates to a file in active use, and whose validity persists only until the token is released via the v_rel callable service. Note that automount-managed directories are virtual, and the FID is unique only as long as the directory is being referenced.

A server application uses v_get to convert a FID to a vnode token when it is preparing to use a file because the Vnode token identifies the file to the other VFS callable services.

- 2. The FID for a file is returned in the ATTR structure by such services as v_rpn and v_lookup. For information about the ATTR structure, see <u>"BPXYATTR Map file attributes for v_ system calls" on page 433.</u>
- 3. vnode tokens that are returned by the v_get service are not inherited across a fork callable service.
- 4. The caller is responsible for freeing vnode tokens that are returned by the v_get service by calling to the v_rel service when they are no longer needed.

Related services

- "v_create (BPX1VCR, BPX4VCR) Create a file" on page 260
- "v getattr (BPX1VGA, BPX4VGA) Get the attributes of a file" on page 274
- "v_lookup (BPX1VLK, BPX4VLK) Look up a file or directory" on page 294
- "v_mkdir (BPX1VMD, BPX4VMD) Create a directory" on page 297
- "v_rdwr (BPX1VRW, BPX4VRW) Read from and write to a file " on page 311
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325
- "v_rpn (BPX1VRP, BPX4VRP) Resolve a path name" on page 337
- "v_setattr (BPX1VSA, BPX4VSA) Set the attributes of a file " on page 341

Characteristics and restrictions

A process must be registered as a server before the v_get service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VGT, BPX4VGT (v_get)" on page 454.

v_getattr (BPX1VGA, BPX4VGA) — Get the attributes of a file

Function

The v_getattr service gets the attributes of the file that is represented by Vnode_token.

Requirements

| Operation | Environment |
|-----------|-------------|
|-----------|-------------|

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VGA): 31-bit
AMODE (BPX4VGA): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL BPX1VGA, (Vnode_token,
OSS,
Attr_length,
Attr,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VGA with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Attr. To determine the value of Attr_length, use the BPXYATTR macro (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, in which the v_getattr service returns the file attribute structure for the file that is specified by the vnode token. This area is mapped by the BPXYATTR macro (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_getattr service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_getattr service stores the return code. The v_getattr service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_getattr service can return one of the following values in the Return_code parameter:

Return_code

Explanation

EINVAL

Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS.

Return_code Explanation

EPERM The operation is not permitted. The caller of the service is

not registered as a server.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_getattr service stores the reason code. The v_getattr service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. All time fields in the Attr area are in POSIX format.
- 2. The setting of the AttrLP64times bit in the BPXYATT structure, and not the AMODE of the caller, determines whether 4-byte or 8-byte time fields are used.
- 3. The File Mode field in the Attr area is mapped by the BPXYMODE macro. For more information about the BPXYMODE macro, see <u>BPXYMODE Map the mode constants of the file services</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321

Characteristics and restrictions

A process must be registered as a server before the v_getattr service is permitted; see "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VGA, BPX4VGA (v_getattr)" on page 454.

v_ioctl (BPX1VIO/BPX4VIO) - Convey a command to a physical file system

Function

The v_ioctl callable service conveys a command to a physical file system. The specific action that is specified by the v_ioctl callable service varies by physical file system, and is defined by the physical file system.

Requirements

Operation Environment

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VIO): 31-bit

Operation Environment

AMODE (BPX4VIO): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VIO with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file.

oss

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro. For more information about the BPXYOSS macro, see "BPXYOSS — Specific information for the Map operating system" on page 442.

Command

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the ioctl command that is to be passed to the physical file system. This area is mapped by the BPXYIOCC macro. For more information about the BPXYIOCC macro, see BPXYIOCC — Ioctl command definitions in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Argument_length

Supplied and returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the argument. The length of the argument is specified as an integer value in the range 0-51200.

Argument

Supplied and returned parameter

Type:

Defined by the physical file system

Character set:

No restriction

Length:

Specified by the Argument_length parameter

Specifies the name of a buffer, of length Argument_length, containing the argument to be passed to the physical file system. This buffer is also used for any output.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_ioctl service returns 0 if the request is successful, or -1 if it is not successful. For the getfacl command, return_value contains the FACL length if the request is successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_ioctl service stores the return code. The v_ioctl service returns a Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_ioctl service can return one of the following values in the Return code parameter:

| Return_code | Explanation |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EFAULT | The input argument address or any other parameter is incorrect. The following reason codes can accompany the return code: JrReadUserStorageFailed, JrWriteUserStorageFailed. |
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason code can accompany the return code: JRIOBufLengthInvalid. |
| ENOTDIR | The Vnod_Token passed for the Iocc#GetPathName command is not a directory and a parent directory for this object cannot be determined. |

| Return_code | Explanation |
|-------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| E2BIG | The argument_length passed on a SetfACL or GetfACL request was not large enough to contain even the minimum amount of data. The size that is specified must be large enough to hold a RACL_Edit, followed by an FACL and as many FACL_Entry(s) as needed |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_ioctl service stores the reason code. The v_ioctl service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. For file systems that support access control lists (ACLs), you can use the GetfACL and SetfACL commands. For detailed information about these and other commands, see the Notes section in w_ioctl (BPX1IOC, BPX4IOC) Control I/O in z/OS UNIX System Services Programming: Assembler Callable Services Reference.
- 2. The Iocc#GetPathName command will return the absolute path name of an input directory or file.

An input file must have been recently looked up or created in order for its path name to be generated. if the only reference to this file has been by a server with the vfs_vget function, it will not be possible to construct the path name because an immediate parent directory cannot be determined.

If the input directory resides in a file system that has been covered, by the mounting of another file system on a directory in the path name, the command will fail with ENOENT. The OssXMtPt flag can be used to override this check and return a path name without regard to covered mount points that might be encountered. In this case the path name returned cannot be used as input to functions like v_rpn() and open() because those functions will cross mount points and will either fail to find the directory or will find a different directory with the same path name in a mounted file system.

Related services

- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server " on page 321

Characteristics and restrictions

- 1. A process must be registered as a server before the v_ioctl service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> Register a process as a server " on page 321.
- 2. The argument is limited to 51200 bytes.

Examples

For an example using this callable service, see "BPX1VIO, BPX4VIO (v_ioctl)" on page 455.

v_link (BPX1VLN, BPX4VLN) — Create a link to a file

Function

The v_link service creates a link (Link_name) to the file that is specified by File_vnode_token in the directory that is specified by Directory_vnode_token. The link is a new name that identifies an existing file. The new name does not replace the old one, but provides an additional way to refer to the file. To rename an existing file, see "v_rename (BPX1VRN, BPX4VRN) — Rename a file or directory " on page 330.

Requirements

Operation Environment

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VLN): 31-bit
AMODE (BPX4VLN): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VLN with the same parameters.

Parameters

File_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file to which a link is to be established.

oss

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Link_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Link_name. The name can be up to 255 bytes long.

Link_name

Supplied parameter

Type:

Character string

Length:

Specified by Link_name_length parameter

The name of an area, of length Link_name_length, that contains the name by which the file is to be known. It must not contain null characters (X'00').

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory from which the v_{link} service is to create the link that is supplied in the Link_name parameter.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_link service returns 0 if the request completes successfully, or -1 if the request is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_link service stores the return code. The v_link service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_link service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The process did not have appropriate permissions to create the link. Possible reasons include: |
| | The process had no write permission for the directory that is intended to contain the link. |
| | The process had no permission to access the file that is specified by File_vnode_token. |
| EEXIST | A file, directory, or symbolic link named Link_name already exists. |
| EINVAL | Parameter error; for example, one of the vnode tokens is stale. The following reason codes can accompany the return code: JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS, JRNoName, JRNullInPath. |
| EMLINK | The file that is specified by File_vnode_token already has its maximum number of links. The maximum number is LINK_MAX. The value of LINK_MAX can be determined through pathconf (BPX1PCF) or fpathconf (BPX1FPC). |
| ENAMETOOLONG | Link_name_length exceeds 255 characters. |
| ENOSPC | The directory that is intended to contain the link cannot be extended to contain another entry. |
| ENOTDIR | Directory_vnode_token does not specify a directory. The following reason code can accompany the return code: JRTokNotDir. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server; or the File_vnode_token specifies a directory. The following reason codes can accompany the return code: JRNotRegisteredServer, JRTokDir. |
| EROFS | Creating the link would require writing on a read-only file system. The following reason code can accompany the return code: JRLnkROFileSet. |
| EXDEV | The file that is specified by File_vnode_token and Directory_vnode_token are on different file systems. The following reason code can accompany the return code: JRLnkAcrossFileSets. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_link service stores the reason code. The v_link service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. BPX1VLN creates a link named Link_name to an existing file that is specified by File_vnode_name. This provides an alternate path name for the existing file; the file may be accessed by the old name or the

- new name. The link may be stored under the same directory as the original file, or under a different directory on the same file system.
- 2. If the link is created successfully, the service routine increments the link count of the file. The link count shows how many links to a file exist. (If the link is not created successfully, the link count is not incremented.)
- 3. Links are not allowed to directories.
- 4. If the link is created successfully, the change time of the linked-to file is updated, as are the change and modification times of the directory that contains Link_name (that is, the directory that holds the link).

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325
- "v_remove (BPX1VRM, BPX4VRM) Remove a link to a file " on page 327
- "v_rename (BPX1VRN, BPX4VRN) Rename a file or directory" on page 330

Characteristics and restrictions

A process must be registered as a server before the v_link service is permitted, See <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VLN, BPX4VLN (v_link)" on page 455.

Environment

v_lockctl (BPX1VLO, BPX4VLO) — Lock a file

Function

Operation

The v_lockctl service controls advisory byte-range locks on a file.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VLO): | 31-bit |
| AMODE (BPX4VLO): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

```
CALL BPX1VLO,(OSS,
Command,
Vlock_length,
Vlock,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VLO with the same parameters.

Parameters

oss

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Command

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains one of the integer values that is mapped in the BPXYVLOK macro and indicates the action that is to be performed. For the list of commands, see "BPXYVLOK — Map the interface block for v_lockctl" on page 445.

Vlock_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Vlock. To determine the value of Vlock_length, use the BPXYVLOK macro (see "BPXYVLOK — Map the interface block for v_lockctl" on page 445).

Vlock

Supplied and returned parameter

Type:

Structure

Length:

Specified by the Vlock_length parameter

The name of an area that contains the lock request information. This area is mapped by the BPXYVLOK macro (see "BPXYVLOK — Map the interface block for v_lockctl" on page 445).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lockctl service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lockctl service stores the return code. The v_lockctl service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_lockctl service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EAGAIN | The Lock command was requested, but the lock conflicts with a lock on an overlapping part of the file that is already set by another locker. |
| EDEADLK | The Lockwait command was requested, but the potential for deadlock was detected. The following reason codes can accompany the return code: JRBrlmDeadLockDetected, JRBrlmPromotePending, JRBrlmAlreadyWaiting, JRBrlmUnlockWhileWait. |
| EINTR | A LockWait request was interrupted by a signal. |
| EINVAL | Parameter error. The following reason codes can accompany the return code: JRBadEntryCode, JRInvalidVlok, JRInvalidServerPid, JRNoLockerToken, JRBrlmLockerNotRegistered, JRBrlmBadLType, JRBrlmObjectMissing, JRBrlmInvalidRange, JRBrlmBadL_Whence. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a lock server. |
| ENOENT | The LockCancel command was requested, but an exactly matching lock request was not found on the object's waiting queue. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lockctl service stores the reason code. The v_lockctl service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The v_lockctl service locks out other cooperating lockers from part of a file, so that the locker can read or write to that part of the file without interference from others.

All locks are advisory only. Client and local processes can use locks to inform each other that they want to protect parts of a file, but locks do not prevent I/O on the locked parts. A process that has appropriate permissions on a file can perform whatever I/O it chooses, regardless of the locks that are set. Therefore, file locking is only a convention, and it works only when all processes respect the convention.

2. Registering as a locker (Vlok#RegLocker): Each locker must be registered before it issues any lock requests. On a **Vlok#RegLocker** command, the following Vlock fields are provided by the caller:

VlokID

The Vlok#ID (from the BPXYVLOK macro).

VlokLen

The length of the Vlock structure.

VlokServerPID

The process ID of the lock server. If 0 is specified, the caller's PID is used.

VlokClientPID

A server-generated process ID that uniquely identifies the client within this server PID.

Other fields in the Vlock area should be set to zeros.

The following Vlock field is returned to the caller:

VlokLockerTok

A token to identify the locker on subsequent lock requests.

3. On a **Vlok#Query, Vlok#Lock, Vlok#LockWait, or Vlok#Unlock** command, the following Vlock fields are provided by the caller:

VlokID

The Vlok#ID (from the BPXYVLOK macro).

VlokLen

The length of the Vlock structure.

VlokLockerTok

The locker.

VlokClientTID

The client's thread ID.

VlokObjClass

The file object class. The possible classes are defined in the BPXYVLOK macro; see "BPXYVLOK — Map the interface block for v lockctl" on page 445.

VlokObiID

The file object uniquely within the class. For a zFS file, VlokObjID contains the device number and FID of the file.

VlokObjTok

A token that was returned on the previous lock request for this object. This field is optional, but will improve performance for multiple lock requests.

VlokBrlk

Lock information describing the byte-range. This area is mapped by BPXYBRLK (see note <u>"5" on</u> page 287). The following BPXYBRLK fields must be provided:

| Command | Required fields |
|------------|----------------------------------|
| Vlok#Query | l_type, l_whence, l_start, l_len |
| Vlok#Lock | l_type, l_whence, l_start, l_len |

| Command | Required fields |
|---------------|----------------------------------|
| Vlok#LockWait | l_type, l_whence, l_start, l_len |
| Vlok#Unlock | l_whence, l_start, l_len |

VlokVnToken

(Optional) The vnode token for a UNIX file system object. The use of this optional parameter can improve the performance of any operation that specifies a file system object. Additionally, for the Vlok#UnLoadLocks function, this also indicates that share reservations for the file are to be appended to the unloaded byte range locks (see note "11" on page 290 for more information).

Other fields in the Vlock area should be set to zeros.

The following Vlock fields are returned to the caller:

VlokObjTok

A token to identify the object on a subsequent lock request.

VlokBrlk

On Query, lock information that describes a lock that would prevent the proposed lock from being set.

4. On a Vlok#Lock, Vlok#LockWait, and Vlok#LockAsy command, the caller can pass an open token in the OSS by providing the following field:

OssOpenToken

Contains an open token with which the byte range lock should be associated

For open tokens other than those created with OPEN_NLM_SHR, the lock owner becomes associated with the open token. Thus, when a v_close() is issued using that open token, all byte range locks on this file that were obtained by this lock owner will be released.

- 5. Locking operations are controlled with a structure that is mapped by BPXYBRLK. This structure is needed whether the request is for setting a lock, releasing a lock, or querying a particular byte range for a lock. The following is a description of the BPXYBRLK structure:
 - The l_type field specifies the type of lock that is to be set or queried. (l_type is not used on Unlock.) Valid values for l_type are as follows

Type

Description

F_RDLCK

A read lock. Specified as a halfword integer value of 1, this is also known as a *shared lock*. This type of lock specifies that the locker can read the locked part of the file, and other lockers cannot write on that part of the file in the meantime. A locker can change a held write lock, or any part of it, to a read lock, thereby making it available for other lockers to read. Multiple lockers can have read locks on the same part of a file simultaneously.

F_WRLCK

A write lock. Specified as a halfword integer value of 2, this is also known as an exclusive lock. This type of lock indicates that the locker can write on the locked part of the file, without interference from other lockers. If one locker puts a write lock on part of a file, no other locker can establish a read lock or write lock on that same part of the file. A locker cannot put a write lock on part of a file if there is already a read lock on an overlapping part of the file, unless that locker is the only owner of that overlapping read lock. In such a case, the read lock on the overlapping section is replaced by the write lock that is being requested.

F_UNLCK

Returned on a Query, when there are no locks that would prevent the proposed lock operation from completing successfully. Specified as a halfword integer value of 3.

• The **l_whence field** specifies how the byte-range offset is to be found within the file. The only valid value for **l_whence field** is SEEK_SET, which stands for the start of the file, and is specified as a halfword integer value of 0.

The L_start field identifies the part of the file that is to be locked, unlocked, or queried. The part
of the file that is affected by the lock begins at this offset from the start of the file. For example, if
L_start field is the value 10, a Lock request attempts to set a lock beginning 10 bytes past the start
of the file.

Note: Although you cannot request a byte range that begins or extends beyond the beginning of the file, you can request a byte range that starts or extends beyond the end of the file.

- The **l_len field** gives the size of the locked part of the file, in bytes. The value that is specified for **l_len field** can be negative. If **l_len field** is positive, the area that is affected begins at **l_start** and ends at **l_start** + **l_len-1**. If **l_len** is negative, the area that is affected starts at **l_start+l_len** and ends at **l_start-1**. If **l_len** is zero, the locked part of the file begins at the position that is specified by **l_whence field** and **l_start**, and extends to the end of the file.
- The **l_pid field** identifies the ClientProcessID of the locker that holds the lock found on a Query request, if one was found.
- 6. Obtaining locks (Vlok#Lock and Vlok#LockWait): Locks can be set by specifying a Vlok#Lock as the Command parameter. If the lock cannot be obtained, a return value of -1 is returned, along with an appropriate return code and reason code.

Locks can also be set by specifying Vlok#LockWait as the Command parameter. If the lock cannot be obtained because another process has a lock on all or part of the requested range, the LockWait request waits until the specified range becomes free and the request can be completed.

If a signal interrupts a call to the v_lockctl service while it is waiting in a LockWait operation, the function returns with a return value of -1, and a return code of EINTR.

LockWait operations have the potential for encountering deadlocks. This happens when locker A is waiting for locker B to unlock a region, and B is waiting for A to unlock a different region. If the system detects that a LockWait request might cause a deadlock, the v_lockctl service returns with a return value of -1 and a return code of EDEADLK.

7. Asynchronous locking:

• Obtaining an asynchronous lock (Vlok#LockAsy): The Vlok#LockAsy command parameter is used to request an asynchronous lock. The lock request is either satisfied immediately or is queued for asynchronous completion. The v_lockctl call will not block. The caller should expect to receive the asynchronous lock completion through the sigtimedwait() or sigwaitinfo() interfaces. These provide an event queue for lock completions based on queued signals and is the same as that used with asynchronous I/O completions. The caller can specify the signal number and signal value to pass back on the asynchronous completion.

The Vlock structure is set up just as it would be for the Vlok#LockWait function with the addition of a caller-supplied Aiocb structure that specifies the signal information and holds the results of the completed asynchronous request. The new fields in the Vlock structure for this function are:

VlokAiocbLen

Length of the Aiocb structure

VlokAiocb

Address of the Aiocb structure

The Aiocb must remain valid for the life of an asynchronous request and its use is similar to that for an aio_read call. The following Aiocb fields are provided by the caller:

aio_sigevent.sigev_signo

The signal number

aio sigevent.sigev value

An application-specific data value to be passed with the signal

aio exitdata

An application data area (not touched by the system)

The rest of the Aiocb should be zeroed out.

The following Aiocb fields are returned to the caller:

aio_rv

The return value

aio rc

The return code

aio_rsn

The reason code

The Return value from v lockctl() indicates the outcome of the call, as follows:

+1

The lock will be granted asynchronously.

0

The lock was granted immediately.

-1

The lock request failed as indicated by the accompanying return code and reason code.

When the Return_value from v_lockctl() is +1, the final result of the lock request is determined when the completion signal is pulled from the signal queue using sigtimedwait() or sigwaitinfo(). At that point, the aio_rv field will contain 0 if the lock was granted or -1 (with accompanying values in aio_rc and aio_rsn) if the lock was not granted. Generally, a request will only fail asynchronously if it is canceled.

When the Return_value from v_lockctl() is 0 or -1, the request has immediately succeeded or failed, respectively, and no signal is sent.

As with any asynchronous operation, the request may complete before the v_lockctl() call returns to the caller.

A lock owner may only have one outstanding lock request at a time on any particular range. This includes pending asynchronous requests and blocked synchronous requests. In other words, waiting locks for the same owner cannot intersect. Similarly, unlock requests may not be issued for any range that intersects with a pending lock request from the same lock owner.

• To cancel a specific, outstanding asynchronous lock request, call the v_lockctl service with a command parameter of Vlok#LockCancel and a Vlock structure that contains all the information from the original Vlok#LockAsy request: object, owner, Brlk information, and Aiocb.

You must use the same Aiocb on both the original Vlok#LockAsy request and theVlok#LockCancel request and the Aiocb must not have been modified between the two calls. When the Vlok#LockAsy request returns with a return value of 1, an asynchronous request token is also returned in the Aiocb and that token must be present on any subsequent call to cancel the lock request.

An asynchronous lock request can only be canceled if it is still waiting for the lock to be granted. When a pending request is successfully canceled, the Return_value from $v_lockctl()$ will be 0 and a lock completion signal will be sent with an aio_rc of ECANCELED. When an exact match for the request is not found on the object's waiting queue, the Return_value from $v_lockctl()$ will be -1 and the Return_code will be ENOENT.

There is a race condition between a pending lock being canceled and its being granted, so there is always a chance that the call to cancel the lock request will fail because the successful lock completion signal has already been sent. Note, too, that at the time the v_lockctl call to cancel the lock request returns to the caller, the completion signal (either for the lock being granted or for its being canceled) may still be on the application's signal queue. Therefore, the application must handle the coordination between the caller of the cancel request and the handler of the completion signal.

- Refer to note "16" on page 292 for the effects of a purge request on asynchronous locks.
- If the ownership of a file system is changed within a sysplex environment (for instance, by using the chmount shell command), pending asynchronous locks will be lost. This special situation is indicated by a lock failure of the original request with an aio_rc of EAGAIN and a lower half-word value in aio_rsn of 0x0607 (the value of the JrOwnerMoved reason code). The v_lockctl call must

be issued again to request the asynchronous lock from the new owner. At such time, the lock may be immediately granted or it may again enter a pending state.

- 8. Determining lock status (Vlok#Query): A process can determine locking information about a file by using Vlok#Query as the Command parameter. The VlokBrlk structure should describe a lock operation that the caller would like to perform. When the v_lockctl service returns, the structure is modified to describe the first lock found that would prevent the proposed lock operation from completing successfully.
 - If a lock is found that would prevent the proposed lock from being set, the Query request returns a modified structure whose <code>l_whence</code> value is always SEEK_SET, whose <code>l_start</code> value gives the offset of the locked portion from the beginning of the file, whose <code>l_len</code> value is set to the length of the locked portion of the file, and whose <code>l_pid</code> value is set to the ClientProcessID of the locker that is holding the lock. If there are no locks that would prevent the proposed lock operation from completing successfully, the returned structure is modified to have an <code>l_type</code> of <code>F_UNLCK</code>, but otherwise it remains unchanged.
- 9. Multiple lock requests: A locker can have several locks on a file simultaneously, but can have only one type of lock set on any given byte. Therefore, if a locker sets a new lock on part of a file that it had previously locked, the locker has only one lock on that part of the file, and the lock type is the one that was given by the most recent locking operation.
- 10. Returning blocker information: A request to the v_lockctl service that cannot be granted can return information about the lock that is blocking the request from being granted. The blocking lock shares at least part of the range that was requested and may be from a granted lock range or a waiting lock request. The returned information is in the form of a BRLM_RangeLock structure, defined in IGWLBINT for PL/X and in BPXYVFSI for C.

The caller requests the return of blocker information by specifying in VlokBlockingLock the address of an area in primary storage where the output BRLM_RangeLock may be placed. VlokBlkLockLen specifies the length of this output area. The storage for the output area is assumed to be in the caller's key.

Blocker information can be returned in the following cases:

- A Vlok#Lock or Vlok#LockWait request fails with a return code of EAGAIN or EDEADLK
- A Vlok#Query request finds a blocking lock
- A Vlok#LockAsy request returns with a Return_value of +1

The output BRLM_RangeLock area (or, at a minimum, the server PID in the first word) should be zeroed out before the call to the v_lockctl service. If the contents are changed upon completion of the call, then information about a blocking lock was returned. Note that the blocking lock was blocking this request when the v_lockctl call was issued but is subject to change at any time.

11. Query all locks for an object (Vlok#UnLoadLocks): The Vlok#UnLoadLocks request provides an interface to the BRLM UnloadLocks function and also obtains the share reservations for file system objects.

The information is returned as a chain of BRLM_UnloadLocksList structures, each of which contains control information and an array of (Object, Rangelock) pairs, each of which describe one locked range or share reservation. The storage for the chain of structures is obtained in the caller's primary address space, is in the caller's key, and is owned by the caller's TCB. Each structure in the chain must be freed by the caller using the MVS storage release service. The unloaded lock list segments may be of different lengths so the ull_length field must be used when the storage is released. These structures are defined in IGWLBINT for PL/X and in BPXYVFSI for C.

The following Vlock fields are provided by the caller:

VlokObject

The class and ID of the object

VlokUllSubPool

An MVS storage subpool number for the areas to be obtained. For unauthorized callers, this number must be between 1 and 127.

VlokUllRetWaiters

When set to Vlok#RetWaiters, all locks for the specified objects are returned, including waiting locks, pending asynchronous locks, and held locks. When set to Vlok#RetHeldOnly, only held locks for the specified objects are returned. When set to Vlok#RetAllObj, all the locks for all the objects are returned. Waiting locks are identified by the RlWaiting flag in the BRLM_Rangelock structure.

VlokUllMaskLen and VlokUllInMaskPtr

(Optional) When VlokUllMaskLen is non-zero, it specifies the length of the object mask whose address is passed in VlokUllInMaskPtr. This is a 16-byte mask as defined by VlokObjectMask. The VlokObject and this mask are used together to determine which locks are returned.

The mask is logically ANDed with the object ID of each lock and the result is compared with the VlokObject that is passed. The algorithm is as follows:

```
if ( (LockObject & PassedObjectMask) == VlokObject )
   { The lock will be returned. }
```

For example, to get all the locks for all objects that are files in the UNIX File System with a devno of 8, specify the following. (This example is shown in hexadecimal with blanks inserted for readability.)

```
VlokObject: 00000000 00000008 00000000 000000000
Mask: FFFFFFF FFFFFFF 00000000 00000000
```

VlokUllRetWaiters can be set to Vlok#RetHeldOnly or to Vlok#RetWaiters to further filter what locks are returned. Note that if VlokUllRetWaiters is set to Vlok#RetAllObj, the object mask is ignored and all locks for all objects are returned.

VlokVnToken

(Optional) A vnode token for the VlokObject. Also indicates that the object's share reservations should be appended to the byte range locks that are returned. This must be the same file as identified by the VlokObject.

The following Vlock field is returned to the caller:

VlokUllOutListPtr

The address of the first member of the output chain of BRLM_UnloadLocksList structures, or zero.

Zero or more BRLM_UnloadLocksList structures will be produced by BRLM. For file system objects when a vnode token is supplied, the unloaded locks will be followed by zero or more BRLM_UnloadLocksList structures for the share reservations. Share reservations may be placed in the unused slots of the last BRLM structure. The BRLM_UnloadLocksList structures may have varying numbers of locks returned in their array section so the ull_count field must be used to step through the arrays. The Return_value will contain the total number of locks and share reservations that were returned.

For each byte range lock, the rl_access field will be set to the type of lock: rl_shared, rl_excl, or rl_shr2excl.

For each share reservation, the rl_access field will be set to rl_openmodes. The rl_openacc and rl_opendeny fields will be set to the current Shr_Access and Shr_Deny modes, respectively, for that open. (Refer to "v_open (BPX1VOP, BPX4VOP) — Open or create a file" on page 301 for more information about these modes.)

- 12. Releasing locks (Vlok#Unlock): When an Vlok#Unlock request is made to unlock a byte region of a file, all locks that are held by that locker within the specified region are released. In other words, each byte that is specified on an Unlock request is freed from any lock that is held against it by the requesting locker.
- 13. Locks are not inherited by a child process that is created with the fork service.
- 14. Effects of close and process termination: All locks (those that are owned, pending, or waiting) for a given lock owner on a specific file will be released if any of the owner's open tokens for that file are closed with a v_close call. This includes any open token that was opened by this lock

owner or one that was opened by a different lock owner but was subsequently used by this lock owner on a v_lockctl call. Owned locks are unlocked; pending and waiting locks are canceled. (This does not apply to open tokens created with OPEN_NLM_SHR.)

If the registered server process terminates, all locks that are associated with this process are unlocked or canceled. Since the process is terminating, lock completion signals will not be delivered.

- 15. If the lock server terminates, all locks are released.
- 16. Purging locks (Vlok#Purge): The Vlok#Purge command releases all locks on all files that are held by a locker or a group of lockers. This is primarily a pass through to BRLM. It will purge all types of byte range locks: held locks, waiting locks, or pending asynchronous locks. It does not affect share reservations or open tokens.

The purge interface is implemented using two bit masks that are logically ANDed with the object ID and owner ID, respectively, of each lock before they are compared with the passed arguments. The algorithm is as follows:

```
if ( (PassedObject == (LockObject & PassedObjectMask))
    && (PassedOwner == (LockOwner & PassedOwnerMask)) )
{ The lock will be purged. }
```

This purge function is enhanced and extended from the previously existing v_lockctl purge function. The following Vlock fields are provided by the caller:

VlokObject

The object's 16-byte identifier

VlokServerPID

The process ID of the lock server whose locks are to be released.

VlokClientPID

A server-generated process ID that uniquely identifies the client whose locks are to be released. If binary ones are specified, all locks for all clients of the specified server are released.

VlokClientTID

The client's thread ID for which locks are to be released. If binary ones are specified, all locks for the specified client and server are released.

VlokPgMasks

Points to a pair of 16-byte bit masks for the object and owner, respectively. These are defined as VlokObjectMask and VlokOwnerMask.

VlokPgMaskslen

Specifies the length of the bit mask pair being passed, which is 32

The three subfields of the lock owner ID (VlokServerPID, VlokClientPID, VlokClientTID) are considered to be a single concatenated 16-byte field with respect to the owner mask. Since VlokServerPID is automatically set to the server's PID by the LFS, the first four bytes of the owner mask will be set to all ones so that the server may only purge locks that it has obtained.

Other fields in the Vlock area should be set to zeros.

 Purging locks held on an object by a server: The following Vlock fields are provided by the caller:

VlokObject

The 16-byte identifier of a specific object

VlokObjectMask

All X'FF', for matches on just the specific object

VlokLocker

All zeroes

VlokClientTID

All zeroes

VlokLockerMask

All zeroes, for matches on any owner with the same server PID

• Purging locks held by a client user: The following Vlock fields are provided by the caller:

VlokObject

Zero

VlokObjectMask

All zeroes, for matches on every object

VlokClientPID

The appropriate client PID

VlokClientTID

The appropriate client TID, TID subset (padded with zeroes), or all zeroes

VlokLockerMask

X'FF', left-justified for a length matching the appropriate subset of the 16-byte owner ID, and then padded with X'00'. For instance:

- 16 bytes of X'FF' for exactly one lock owner
- 12 bytes of X'FF' for, perhaps, all processes for a specific user at a specific client
- 8 bytes of X'FF' for all client TIDs for a given client PID
- Effects of purge on asynchronous locks: If a set of locks being purged includes pending asynchronous locks, those lock requests will be canceled.

If a set of asynchronous lock requests are purged, the application will not be able to immediately tell which pending requests have been canceled and which had been granted and then were unlocked. When the call to purge returns to the caller, the lock completion signals will have all been sent but they may still be on the signal queue. The application can coordinate the purge operation with the signal handler after the purge completes by calling sigqueue() with a special signal number or value to flush the queue of these lock completion signals. If only a single thread handles the signal queue, then the appearance of this flush signal will indicate that all of the successful and ECANCELED signals have arrived and have been processed.

17. Each locker should be unregistered when it has finished issuing lock requests. On a Vlok#UnregLocker command, the following Vlock field is provided by the caller:

VlokID

Vlok#ID (from the BPXYVLOK macro)

VlokLen

The length of the Vlock structure

VlokLockerTok

A token to identify the locker to unregister

Other fields in the Vlock area should be set to zeros.

Related services

"v_reg (BPX1VRG, BPX4VRG) — Register a process as a server " on page 321

Characteristics and restrictions

A process must be registered as a lock server before the v_lockctl service is permitted; see <u>"v_reg"</u> (BPX1VRG, BPX4VRG) — Register a process as a server "on page 321.

Examples

For an example using this callable service, see "BPX1VLO, BPX4VLO (v lockctl)" on page 455.

v_lookup (BPX1VLK, BPX4VLK) — Look up a file or directory

Function

The v_lookup service accepts a vnode token that represents a directory and a name that identifies a file. The directory is searched for this file, and if it is found, a vnode token for this file and its file attributes are returned. The file vnode token that is returned must be supplied by the server on all subsequent VFS callable services that are related to this file.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VLK): | 31-bit |
| AMODE (BPX4VLK): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

AMODE 64 callers use BPX4VLK with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the v_lookup service searches for the file that is supplied in the Name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the filename that is to be searched for. The name can be up to 255 bytes long.

Name

Supplied parameter

Type:

Character string

Length:

Specified by Name_length parameter

The name of an area, of length Name_length, that contains the filename to be searched for. It must not contain null characters (X'00').

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, in which the v_lookup service returns the file attribute structure for the file that is supplied in the Name parameter. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

The file attributes information is returned only if the file is found.

File_vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_lookup service returns a vnode token of the file that is supplied in the Name parameter.

v_lookup (BPX1VLK, BPX4VLK)

The token is returned only if the file is found.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lookup service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lookup service stores the return code. The v_lookup service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_lookup service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRNoName, JrNullInPath, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENAMETOOLONG | The name is longer than 255 characters. |
| ENFILE | An error occurred while storage was being obtained for a vnode token. |
| ENOENT | Name was not found. |
| ENOTDIR | The supplied token did not represent a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| ERREMOTE | Object is remote. The following reason code can accompany the return code: JrNoRemote. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_lookup service stores the reason code. The v_lookup service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. Vnode tokens that are returned by the v_lookup service are not inherited across a fork callable service.
- 2. The caller is responsible for freeing vnode tokens that are returned by the v_lookup service, by calling to the v_rel service when they are no longer needed.
- 3. Local mount points are not crossed unless the OssXmtpt flag is set in the input OSS structure. When that flag is on and the name looked up turns out to be a mount point directory, the root directory of the file system that is mounted there is returned instead of the named directory. This is called "crossing down the mount point tree". When the specified name is ".." and the specified directory is a local root, the parent directory of the underlying mount point is returned instead of the parent of the specified directory. This is called "crossing up the mount point tree".
 - In these situations, the OssXmtpt flag is left on and the VFS_Token of the crossed into file system is returned in the AttrCharSetID field of the returned ATTR structure. If a mount point is not encountered, the OssXmtpt flag is turned off.
- 4. When the OssNoRemote flag and the OssXmtpt flag are both set, v_lookup will not allow crossing over into a remote file system. Remote file systems are NFS Client file systems. If a remote file system is encountered, v_lookup will fail with a return code of ERREMOTE.

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_lookup service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example that uses this callable service, see "BPX1VLK, BPX4VLK (v_lookup)" on page 456.

v_mkdir (BPX1VMD, BPX4VMD) — Create a directory

Function

The v_mkdir service creates a new empty directory in the directory that is represented by Directory_vnode_token. The input Attr is used to define the attributes of the new directory. A token that represents the new directory is returned in the New_directory_vnode_token.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VMD): | 31-bit |
| AMODE (BPX4VMD): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VMD with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the v_mkdir service creates the new directory that is named in the Name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the directory name that is to be created. The name can be up to 255 bytes long. It must not contain null characters (X'00').

Name

Supplied parameter

Type:

Character string

Length:

Specified by Name_length parameter

The name of an area, of length Name_length, that contains the directory name that is to be created. It must not contain null characters (X'00').

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Supplied and returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, that is to be used by the v_mkdir service to set the attributes of the directory that is to be created. The attributes of the directory that is created are also returned in this area. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls " on page 433).

New directory vnode token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_mkdir service returns a vnode token of the directory that is created.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_mkdir service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_mkdir service stores the return code. The v_mkdir service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_mkdir service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The calling process does not have permission to update the directory that was specified. |
| EEXIST | The directory named already exists. |
| EFBIG | The file size limit for the process is set to zero, which means directories cannot be created. |
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRInvalidAttr, JrNoName, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENAMETOOLONG | The name is longer than 255 characters. |
| ENFILE | An error occurred while storage was being obtained for a vnode token. |
| ENOTDIR | The supplied token did not represent a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EROFS | Directory_vnode_token specifies a directory on a read-only file system. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_mkdir service stores the reason code. The v_mkdir service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes..

Usage notes

1. The following Attr fields are provided by the caller:

AttrID

Contains Attr#ID (from the ATTR structure).

AttrLen

Specifies the length of the Attr structure.

AttrMode

Specifies directory mode permission bits. See BPXYMODE in <u>Mapping macros</u> in <u>z/OS UNIX System</u> Services Programming: Assembler Callable Services Reference for the mapping of this field.

Other fields should be initialized to zero.

- 2. If the directory that is named in the Name parameter already exists, the v_mkdir service returns a failing return code, and no New_directory_vnode_token is returned.
- 3. Vnode tokens that are returned by the v_mkdir service are not inherited across a fork callable service.
- 4. The caller is responsible for freeing vnode tokens that are returned by the v_mkdir service, by calling to the v_rel service when they are no longer needed.

- 5. If the file size limit for the process is set to zero, directories cannot be created and directory creation fails with EFBIG.
- 6. The value set by umask() for the process does not affect the setting of the mode permission bits.
- 7. The setting of the AttrLP64times bit in the BPXYATT structure, and not the AMODE of the caller, determines whether 4-byte or 8-byte time fields are used.

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_mkdir service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example that uses this callable service, see "BPX1VMD, BPX4VMD (v_mkdir)" on page 456.

v_open (BPX1VOP, BPX4VOP) — Open or create a file

Function

The v_open service opens an existing file or creates and opens a new file. To open an existing file, the file's vnode token is passed. To create a new file, a directory vnode token is passed along with the name of the file to be created in that directory.

The v_open service can also be used to establish share reservations on the file. A file is opened for a particular type of access (reading, writing, or both) and a share reservation can be specified to prohibit any other conflicting access while the file is open. A v_open will fail if an existing share reservation prohibits the desired access or if the file is already open in an access mode that this v_open is trying to prohibit.

An open token is returned which represents the share reservations established by the v_open call. The open token is used on subsequent v_rdwr and v_setattr calls to show that they are being done within a share reservation owned by the caller and with v_lockctl to associate byte range locks with a particular open.

The share reservations made here can be upgraded or downgraded with another call to v_open. They are relinquished with v_close, which removes all state information associated with the v_open.

A file vnode token is returned when a file is opened by name or a new file is created. This token is used on subsequent VFS callable services that are related to this file and the token is eventually released with the v_r el service.

Requirements

Operation Environment

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VOP): 31-bit
AMODE (BPX4VOP): 64-bit

ASC mode: Primary mode

Operation Environment

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VOP with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file being opened or the directory in which a new file is to be created.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating system specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Open_Parms_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the Open_Parms parameter.

Open_Parms

Supplied parameter

Type:

Structure

Length:

Specified by Open_Parms_length parameter

The name of an area that contains additional parameters for this open request. Refer to the usage notes for a description of these parameters. This area is mapped by the BPXYVOPN macro (see "BPXYVOPN — Map the open parameters structure for v_open" on page 450).

FileName_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the FileName parameter. The name can be up to 255 bytes long.

FileName

Supplied parameter

Type:

Character string

Length:

Specified by FileName_length parameter

The name of an area (of length FileName_length) that contains the name of the file to be created. The file name must not contain null characters (X'00').

CreateParm length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the CreateParm parameter.

CreateParm

Supplied parameter

Type:

Structure

Length:

Specified by the CreateParm length parameter

The name of an area whose content depends on the type of create request, as follows:

- For OPEN_CREATE_EXCLUSIVE, an 8-byte creation verifier is passed.
- For OPEN_CREATE_GUARDED and OPEN_CREATE_UNCHECKED, an attr structure is passed which contains the attributes to be assigned to the new file. The set of attributes can include any valid, writable attribute for regular files. Refer to "v_setattr (BPX1VSA, BPX4VSA) Set the attributes of a file "on page 341 for the format of this attr structure and for setting file attributes.

Refer to the usage notes for more information about the three types of file creation.

OutputAttr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the OutputAttr parameter, or 0 if no output attributes are desired.

OutputAttr

Supplied and returned parameter

Type:

Structure

Length:

Specified by the OutputAttr_length parameter

The name of an optional area where the system will return the attributes of the file to be opened. If no output attributes are desired, specify 0 for the preceding OutputAttr_length parameter. See "BPXYATTR — Map file attributes for v_ system calls" on page 433 for a mapping of the file attributes structure.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_open service stores the return code. The v_open service returns Return_code only if the Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_open service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EBUSY | The file is currently open in a way that conflicts with the share reservation that is being requested. The following reason codes can accompany the return code: |
| | JrAccessConflict The file is already open with access that this open is trying to deny. |
| | JrShrConflict This open conflicts with a share reservation that has denied the intended access. |
| EEXIST | The file to be created with the GUARDED or EXCLUSIVE creation protocols already exists. |

Return_code **Explanation EINVAL** Parameter error; for example, a supplied area was too small or the Vnode_token is stale. The following reason codes can accompany the return code: **JrUpgradeSet** The access or share mode of an OPEN_UPGRADE is not a superset of the current value. **JrDowngradeSet** The access or share mode of an OPEN_DOWNGRADE is not a subset of the current value. **JrInvAccess** The access mode is 0 or greater than 3. **EOPNOTSUPP** The socket or file is not a type that supports the requested function. The following reason code can accompany the return code: **JrNoShrsAtOwner** Share reservations are requested but the file is owned by a system that does not support shares. **ESTALE** The open token is not (or is no longer) valid. **EACCES** The user is not authorized either to create a file in this directory or to open the specified existing file. **EROFS** The define or open cannot be done on a read-only file system. **EISDIR** An open request is being attempted on a directory. **EFAULT** A bad parameter address was specified. **EMFILE** The maximum number of vnode tokens or open tokens has been created. The following reason codes can accompany the return code: **JRTokenMax** The maximum number of vnode tokens has been allocated for this process. **JROpenTokMax**

The maximum number of open tokens has been allocated for this process.

ENAMETOOLONG The name is longer than 255 characters.

ENFILE An error occurred in obtaining storage for a vnode token.

ENOTDIR The supplied directory token does not represent a directory.

EPERM The operation is not permitted. The caller of the service is

not registered as a server.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_open service stores the reason code. The v_open service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. An output open token returned by v_open is generally freed by calling v_close. It is also freed if the vnode token with which it is associated is freed by a call to v_rel or if the process terminates.
- 2. The v_close service releases the share reservations made by this and subsequent calls to v_open with this open token. It also releases any byte range locks associated with this open token by v_lockctl.
- 3. An output vnode token returned by v_open is generally freed by calling v_rel. It is also freed if the process terminates.
- 4. Vnode tokens and open tokens returned by the v_open service are not inherited across a call to the fork service.
- 5. All calls to v_open that refer to an existing file may be rejected if the specified access intent or share reservations conflict with the current state of existing opens on that file. See the descriptions of the Shr_Access and Shr_Deny parameters in note "7" on page 306 for more information.
- 6. The total number of open tokens that a process can acquire is limited by the MaxVnTok value that is established when the server registers with v_reg. The limit applies separately to the number of vnode tokens and the number of open tokens, not to the sum of the two.
- 7. The Open_Parms structure contains the following additional parameters:
 - Open_type specifies the type of open being requested. All of the following open types may establish share reservations on the file.
 - OPEN_FILE Open an existing file. The Vnode_token parameter specifies the file to open.
 - OPEN_CREATE_UNCHECKED Create a new file with the unchecked create protocol. The Vnode_token parameter specifies a directory and the FileName parameter specifies the name of the file to create in that directory.
 - OPEN_CREATE_GUARDED Create a new file with the guarded create protocol. The Vnode_token
 parameter specifies a directory and the FileName parameter specifies the name of the file to
 create in that directory.
 - OPEN_CREATE_EXCLUSIVE Create a new file with the exclusive create protocol. The Vnode_token parameter specifies a directory and the FileName parameter specifies the name of the file to create in that directory.
 - OPEN_NLM_SHR Only establish share reservations on a file. The Vnode_token parameter specifies the file. This open type differs from the preceding ones in the following ways:
 - The file is not actually opened to the PFS that manages the file. Normal access checking is still performed for the specified Shr_Access mode. However, because the file is not open to the PFS, file data is not protected from deletion if the file is removed.
 - Byte range locks are not associated with NLM_SHR open tokens and, thus, are not released by a v_close call for this open token. To implement an NLM unshare, call v_close with the open token that was returned by this call to v_open.
 - The share reservations that are established here are only advisory with regard to any read and write operations that are performed without an open token. See "v_rdwr (BPX1VRW, BPX4VRW)" Read from and write to a file " on page 311 for details.
 - OPEN_UPGRADE Upgrade the access intent and share reservations that are associated with a prior open operation. The Vnode_token parameter specifies the file that was opened and the Open_token parameter contains the token that was returned by that open. The Shr_Access and Shr_Deny parameters contain the new settings to be associated with this open token. The new settings consist of the results of applying the upgrade settings to the current settings and, thus, must form a superset of the settings currently in effect for this open token.

- OPEN_DOWNGRADE Downgrade the access intent and share reservations that are associated with a prior open operation. The Vnode_token parameter specifies the file that was opened and the Open_token parameter contains the open token that was returned by that open. The Shr_Access and Shr_Deny parameters contain the new settings to be associated with this open token. The new settings consist of the results of applying the downgrade settings to the current settings and, thus, must form a subset of the settings currently in effect for this open token.
- Open_Owner specifies a structure that contains the (server PID, client PID, thread ID) triplet that
 identifies the individual owner of the share reservations established here. This structure is mapped
 by VlokOwner in the BPXYVLOK macro and by the LOCKOWNER structure in the BPXYVFSI C header.

The first word is reserved and is set by the system to the server's PID.

- Shr_Access specifies the access intent for this open request, as follows:
 - ACC READ Access intent is read
 - ACC_WRITE Access intent is write
 - ACC_BOTH Access intent is read and write

This v_open will be rejected with return code EBUSY, reason code JrShrConflict, if the access intent conflicts with an existing share reservation. A value is required for this parameter (must not be zero).

- Shr_Deny specifies the share reservations for this open request. Share reservations specify the type of access intent that will be prohibited on subsequent open or v_open attempts for this file while this open is in effect. This will also inhibit conflicting read and write operations that are performed without an open token. The following share reservations are valid:
 - DENY_NONE No access is denied.
 - DENY READ Read access is denied. Attempts to open this file for read will be rejected.
 - DENY WRITE Write access is denied. Attempts to open this file for write will be rejected.
 - DENY_BOTH Read and write access is denied. Any attempts to open this file will be rejected.

This v_open will be rejected with return code EBUSY, reason code JrShrConflict, if the file is already open for an access intent that this v_open is trying to deny. Share reservations that attempt to deny reading or writing for files in a read-only file system will be accepted but will not be enforced.

Note: A file system can not be remounted while there are active share reservations on any file in that file system.

- Open_token specifies an 8-byte token that identifies a particular open instance.
 - For OPEN_UPGRADE and OPEN_DOWNGRADE open types, the open token of a prior v_open call is passed by the caller.
 - For all other open types, if the call is successful, the v_open service returns an open token that represents this open on subsequent calls to VFS callable services, in particular v_rdwr and v lockctl.

The open token is put into the OSS of v_rdwr and v_setattr (size change) when those operations are performed within an open context. Read and write operations that are performed within an open context do not need to be validated against the share reservations of other opens. See "v_rdwr (BPX1VRW, BPX4VRW) — Read from and write to a file " on page 311 for details.

- Output_File_vnode_token specifies an 8-byte token that identifies the particular file that was just opened by name. The v_open service returns an output vnode token for successful calls that specify one of the OPEN_CREATE_xxxxx open types. This is the same token as that which would be returned by the v_lookup and v_create services.
- 8. Several v_open parameters are optional or differ in value depending on the setting of the Open_type parameter. Table 13 on page 308 summarizes the parameters that vary by open type.

| Table 13. Summary of v_open parameters that vary by open type | | | | | |
|---------------------------------------------------------------|----------------------------|-----------------------|---------------------------|---------------------|-----------------------------------|
| The open_type | Vnode_token specifies a | FileName required? | CreateParm specifies a | An Open_token is | Output_File_vnode_token returned? |
| OPEN_FILE | File | | | Returned | |
| OPEN_CREATE_UNCHECKED | Directory | Yes | attr structure | Returned | Yes |
| OPEN_CREATE_GUARDED | Directory | Yes | attr structure | Returned | Yes |
| OPEN_CREATE_EXCLUSIVE | Directory | Yes | creation verifier | Returned | Yes |
| OPEN_NLM_SHR | File | | | Returned | |
| OPEN_UPGRADE | File | | | Supplied | |
| OPEN_DOWNGRADE | File | | | Supplied | |

- 9. There are three creation protocols available, as follows:
 - a. OPEN_CREATE_UNCHECKED indicates that the file should be created if a file by that name does not already exist or if encountering an existing regular file by that name is not to be considered an error. The v_open service indicates a successful return value in either case. If the name is in use by something other than a regular file, the v_open call fails with an EEXIST return code.
 - For this type of create, the CreateParm parameter specifies the initial set of attributes for the file. The set of attributes can include any valid, writable attribute for regular files. Refer to "v_setattr (BPX1VSA, BPX4VSA) Set the attributes of a file" on page 341 for the format and protocols for setting file attributes. When an unchecked create encounters an existing file, the attributes specified by CreateParm are ignored, *except* that if a file size of zero is specified, the existing file will be truncated.
 - b. OPEN_CREATE_GUARDED indicates that v_open should fail with an EEXIST return code if it encounters any existing file by the same name. If no object with the same name exists, the request proceeds as described for OPEN_CREATE_UNCHECKED.
 - c. OPEN_CREATE_EXCLUSIVE indicates that the CreateParm parameter contains an 8-byte creation verifier that will be used to ensure the exclusive creation of the file. If the file does not exist, it will be created and the verifier will be stored with the file. No attributes are provided on this call since the PFS may use an attribute of the target object to temporarily store the verifier. The verifier is reliable until the first time v_setattr is called or the file is used in any other way. There is no way to tell if an existing attribute is used (or which one is used) to temporarily store the verifier.

If the file exists, the v_open call fails with an EEXIST return code. The server reacts to an EEXIST failure by calling v_lookup to fetch the attributes of the existing file. If those attributes contain a creation verifier that matches the creation verifier that was passed by the client, then the existing file must have been created by a prior transmission of this create request, so this request is deemed successful. Otherwise, the existing object is something different and the client's request fails.

Related services

- "v_close (BPX1VCL, BPX4VCL) Close a file" on page 257
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_open service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

v_pathconf (BPX1VPC, BPX4VPC) — Get pathconf information for a directory or file

Function

The v_pathconf service accepts a vnode token that represents a file or a directory and returns the current values of options that are associated with that file or directory in the output PCFG structure that is defined in the BPXYPCF macro.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VPC): | 31-bit |
| AMODE (BPX4VPC): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

AMODE 64 callers use BPX4VPC with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory or file for which to obtain pathconf information.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro; see "BPXYOSS — Specific information for the Map operating system" on page 442.

PCFG_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the PCFG parameter.

PCFG

Returned parameter

Type:

Structure

Length:

Specified by the PCFG_length parameter.

The name of an area in which the pathconf information is to be returned. This area is mapped by the BPXYPCF macro.

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the Attr parameter.

Attr

Returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area in which the attributes of the file or directory are to be returned. This area is mapped by the BPXYATTR macro.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_pathconf service returns the length of the output PCFG if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_pathconf service stores the return code. The v_pathconf service returns Return_code only if Return_value is -1. The v_pathconf service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JrInvalidAttr, JRBuffLenInvalid, JrVTokenFreed, JrWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_pathconf service stores the reason code. The v_pathconf service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

The buffer contents that are returned by the v_pathconf service are mapped by the BPXYPCF macro.

Related services

Characteristics and restrictions

A process must be registered as a server before the v_pathconf service is permitted.

Examples

For an example using this callable services, see "BPX1VPC, BPX4VPC (v pathconf)" on page 457.

v rdwr (BPX1VRW, BPX4VRW) — Read from and write to a file

Function

The v_rdwr service accepts a vnode token that represents a file and reads data from or writes data to the file. The number of bytes that are read or written and the file attributes are returned upon completion of the operation.

Requirements

| Operation | Environment |
|-----------|-------------|
| | |

Authorization: Supervisor state or problem state, any PSW key

Operation Environment

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VRW): 31-bit
AMODE (BPX4VRW): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VRW with the same parameters. The FUIO may contain a 64-bit address.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file that is to be read from or written into.

oss

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

UIO

Supplied and returned parameter

Type:

Structure

Length:

Fuio#Len (from the BPXYFUIO macro)

The name of an area that contains the user input and output block. This area is mapped by the BPXYFUIO macro. For more information about the BPXYFUIO macro, see BPXYFUIO — Map file system user I/O block in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, in which the v_rdwr service returns the file attribute structure for the file that is specified by the vnode token. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

The file attributes information is returned only if the read or write operation is successful.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rdwr service returns the number of bytes read or written if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rdwr service stores the return code. The v_rdwr service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_rdwr service can return one of the following values in the Return_code parameter:

Return_code Explanation

EINVAL

Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS, JRRwNotRegFile, JRInvalidFuio, JRBytes2RWZero.

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EFBIG | Writing to the specified file would exceed either the file size limit for the process or the maximum file size that is supported by the physical file system. |
| EACCES | The caller does not have the requested (read or write) access to the file. |
| EIO | An I/O error occurred while reading or writing the file. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EMVSPFSPERM | An internal error occurred in the PFS. Consult Reason_code to determine the exact reason the error occurred. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rdwr service stores the reason code. The v_rdwr service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The following UIO fields are provided to specify the details of the read or write request:

FuioSync

Requests that all data that is associated with the file is to be transferred to the storage device before completion of this write request.

FuioChkAcc

Requests the PFS to perform required access checking before performing the requested read or write operation.

FuioBufferAddr

Contains the address of a buffer that contains the data that is to be read or written.

FuioBuff64Vaddr

Contains the 64-bit virtual address of a buffer that contains the data that is to be read or written.

FuioIBytesRW

Specifies the number of bytes to be read or written.

FuioRWInd

Specifies the operation requested; read or write.

FuioCursor

Specifies the byte offset in the file where the read or write operation is to begin.

FuioRealPage

Specifies that the buffer is a real-storage page and the DATOFF services of MVS must be used to move the data.

FuioInternal

Used internally by the LFS during a call; this field must be zeroed out before each call.

- 2. The FuioAddr64 setting determines whether the pointer to the user buffer is a 64-bit pointer in FuioBuff64Vaddr or a 31-bit pointer in FuioBufferAddr.
- 3. An open token from a prior v_open can passed in the OSS to indicate that this read or write operation is being done within the open context of that token. Consequently, the operation does not have to

be verified against the share reservations that might currently be in effect for this file. If an open token is unavailable to pass on a call, there are three levels of share reservation checking that can be requested:

Oss#NoTokAdvChk

Advisory checking. The operation is validated only against non-NLM share reservations. This corresponds to a read or write from a version 2 or 3 NFS client. These clients do not issue an open request and the NLM share reservations that they make are only advisory with respect to the reads and writes of other version 2 or 3 clients.

Oss#NoTokMandChk

Mandatory checking. The operation is evalidated against all share reservations. This corresponds to a version 4 NFS client read or write with a state of 0 or a write with a state of -1.

Oss#NoTokOverride

No checking. The operation is permitted without any share reservation checking. This is only allowed for read operations and corresponds to a version 4 NFS client read with a state of -1.

In general, version 4 share reservations are enforced against all clients; read and write operations from version 4 clients cannot violate any share reservations. Read and write operations from version 2 and 3 clients are allowed to violate version 2 and 3 share reservations.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321

Characteristics and restrictions

A process must be registered as a server before the v_rdwr service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRW, BPX4VRW (v_rdwr)" on page 457.

v_readdir (BPX1VRD, BPX4VRD) — Read entries from a directory

Function

The v_readdir service accepts a vnode token that represents a directory and returns as many directory entries from this directory as will fit in the caller's buffer.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VRD): | 31-bit |
| AMODE (BPX4VRD): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |
| | |

Format

AMODE 64 callers use BPX4VRD with the same parameters. The FUIO may contain a 64-bit address.

Parameters

Vnode token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory to read directory entries from.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

UIO

Supplied and returned parameter

Type:

Structure

Length:

Fuio#Len (from the BPXYFUIO macro)

The name of an area that contains the user input and output block. This area is mapped by the BPXYFUIO macro. For more information about BPXYFUIO, see <u>BPXYFUIO — Map file system user I/O block in z/OS UNIX System Services Programming: Assembler Callable Services Reference.</u>

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readdir service returns the number of directory entries that were returned if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readdir service stores the return code. The v_readdir service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_readdir service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The calling process does not have permission to read a specified directory. |
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRInvalidFuio, JrBytes2RWZero, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS |
| ENOTDIR | The supplied token did not represent a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readdir service stores the reason code. The v_readdir service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. For an overview of the process of reading from directories, see "Reading directories" on page 250.
- 2. Two protocols are supported for reading through large directories with successive calls:
 - The cursor protocol. The cursor, or offset, that is returned in the UIO by the v_readdir service contains file-system-specific information that locates the next directory entry. The cursor and buffer must be preserved by the caller from one v_readdir call to the next, and reading proceeds based on the cursor.
 - The index protocol. The index that is set in the UIO by the caller determines which entry to start reading from. To read through the directory, the caller starts at one and increments the index by the number of entries that were returned on the previous call.
- 3. The following UIO fields are provided to specify the details of the read directory request:

FuioID

Contains Fuio#ID (from the BPXYFUIO macro).

FuioLen

Contains the length of the UIO structure.

FuioChkAcc

Requests the PFS to perform required access checking before performing the requested readdir operation.

FuioBufferAddr

Contains the address of a buffer where the directory entries are to be returned.

FuioBuff64Vaddr

Contains the 64-bit virtual address of a buffer where the directory entries are to be returned.

FuioIBytesRW

Specifies the maximum number of bytes that can be written to the output buffer.

FuioRDIndex

Specifies the first directory entry that is to be returned when the index protocol is used.

FuioCursor

When the cursor protocol is used, this specifies a value that was returned on the previous v_r eaddir call and that indicates the next entry to be read, or 0 on the first call.

FuioRddPlus

Indicates that the request is for the ReaddirPlus function. The attributes for each entry should be included in the output.

4. The following UIO fields are returned by the v_readdir service:

FuioPSWKey

Is set to the caller's key.

FuioCursor

Is set to the cursor value representing the directory position. This value is used if the next call uses the cursor protocol.

FuioCVerRet

Indicates that the Cookie Verifier (FuioCVer) is being returned.

FuioCVer

When FuioCVerRet is on, this field is set to the Cookie Verifier for the directory that is being read. When a directory is being read with multiple reads, you can use the FuioCVer that is returned to compare each Cookie Verifier with the last one. If the directory has been modified between reads, you can reject the request because the results will not be valid.

- 5. The buffer contents that are returned by the v_readdir service are mapped by the BPXYDIRE macro.
- 6. The FuioAddr64 setting determines whether the pointer to the user buffer is a 64-bit pointer in FuioBuff64Vaddr or a 31-bit pointer in FuioBufferAddr.
- 7. The OssXmtpt flag allows a v_readdir operation to cross mount points when the FuioRddPlus flag is set. Normally, the attributes that are returned with each name are for objects in the same file system as the directory being read. However, some of the objects may be mount point directories. To have the attributes of the mounted root directory returned (instead of the attributes of the mount point), set the OssXmtpt flag in the input OSS structure. When the directory being read is the root of a mounted file system (but not the system root), the attributes for the . . entry will be replaced with the attributes of the parent of the underlying mount point. In such cases, the device number in the Attrdev field in that entry's attributes will differ from the device number of the directory being read and the VFS_Token of the other file system will be returned in the AttrCharSetID field.
- 8. When the OssNoRemote flag and the OssXmtpt flag are both set, v_readdir will not cross over into a remote file system. Remote file systems are NFS Client file systems. If a remote file system is encountered the attributes that are returned will be those of the original object; that is, the mount point rather than the mounted root, and for the . . entry in a root, the root's attributes will be returned.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server " on page 321

Characteristics and restrictions

A process must be registered as a server before the v_readdir service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRD, BPX4VRD (v_readdir)" on page 458.

v_readlink (BPX1VRA, BPX4VRA) — Read a symbolic link

Function

The v_readlink service reads the symbolic link file that is represented by Vnode_token, and returns the contents in the buffer that is described by UIO. The symbolic link file contains the path name or external name that was specified when the symbolic link was defined (see "v_symlink (BPX1VSY, BPX4VSY) — Create a symbolic link" on page 348).

Requirements

Authorization: Supervisor state or problem state, any PSW key

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VRA): 31-bit
AMODE (BPX4VRA): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VRA with the same parameters. The FUIO can contain a 64-bit address.

Parameters

Vnode token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the symbolic link file to read.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

UIO

Supplied and returned parameter

Type:

Structure

Length:

Fuio#Len (from the BPXYFUIO macro)

The name of an area that contains the user input and output block. This area is mapped by the BPXYFUIO macro. For more information about the BPXYFUIO macro, see BPXYFUIO — Map file system user I/O block in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readlink service returns the number of bytes read into the buffer if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readlink service stores the return code. The v_readlink service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_readlink service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRInvalidFuio, JrFileNotSymLink, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_readlink service stores the reason code. The v_readlink service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The following UIO fields are provided by the caller:

FuioID

Contains Fuio#ID (from the BPXYFUIO macro).

FuioLen

Contains the length of the UIO structure.

FuioBufferAddr

Contains the address of a buffer where the link contents are to be returned.

FuioBuff64Vaddr

Contains the 64-bit virtual address of a buffer where the link contents are to be returned.

FuioIBytesRW

Specifies the maximum number of bytes that can be written to the output buffer.

2. The following UIO field is returned by the v_readlink service.:

FuioPSWKey

Is set to the caller's key.

- 3. If the buffer that is supplied to v_readlink is too small to contain the contents of the symbolic link, the value is truncated to the length of the buffer (FuioBytesRW). The length of the symbolic link can be determined from an ATTR structure that is returned on a call to the VFS callable services API (that is, to "v_getattr (BPX1VGA, BPX4VGA) Get the attributes of a file " on page 274). The maximum length is 1023 bytes.
- 4. The FuioAddr64 setting determines whether the pointer to the user buffer is a 64-bit pointer in FuioBuff64Vaddr or a 31-bit pointer in FuioBufferAddr.

Related services

- "v_getattr (BPX1VGA, BPX4VGA) Get the attributes of a file " on page 274
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_symlink (BPX1VSY, BPX4VSY) Create a symbolic link" on page 348

Characteristics and restrictions

A process must be registered as a server before the v_readlink service is permitted; see <u>"v_reg" (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRA, BPX4VRA (v_readlink)" on page 458.

v_reg (BPX1VRG, BPX4VRG) — Register a process as a server

Function

The v_reg service registers a process as a server. A process must be registered by using this service before it can call any other VFS callable services API.

Requirements

| Operation | Environment |
|------------------------|------------------------------------------------|
| Authorization | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode | Task |
| Cross memory mode | PASN = HASN |

Operation Environment

AMODE (BPX1VRG) 31-bit
AMODE (BPX4VRG) 64-bit

ASC mode Primary mode

Interrupt status Enabled for interrupts

Locks Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VRG with the same parameters.

Parameters

Nreg_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the Nreg parameter list area.

Nreg

Supplied and returned parameter

Type:

Structure

Length:

Specified by the Nreg_length parameter

The name of an area that contains the registration parameters. The entries in this area are mapped by BPXYNREG (see "BPXYNREG — Map interface block to vnode registration" on page 440). The following registration parameters must be supplied:

Parameter

Description

ID

Set to Nreg#ID.

Len

Set to Nreg#Len.

Ver

Set to Nreg#Version.

Type

Set to server type:

- NRegSType#FILE for a file server.
- NRegSType#LOCK for a lock server.

NameLen

Set to the length of the supplied server name.

Name

Up to 32 bytes of character string that is used as the name of this server. This name appears in DISPLAY OMVS output.

If the process is to be registered as a server-type file exporter, the following parameters must also be supplied:

ExitName

The name of the program that is to control local access to exported file systems.

InitParm

A parameter that is to be passed to the ExitName program when it is initialized.

Hotc Flag

An indication that the ExitName program should be invoked with a preinitialized C environment (HOTC).

The following registration parameters can be supplied:

No Wait Flag

An indication that server threads should not be suspended during a request that is made to a file system that is quiesced, such as for an HSM backup. The request will fail instead of waiting.

MaxVnTok

An upper bound on the number of vnode tokens and, separately, the number of open tokens that the server is to be allowed to have active at one time.

AllocDevno Flag

Requests that a file system device number, as in AttrDev, be allocated for exclusive use by the server. This number will not be used by the LFS for any mounted file system so the server can use this number as the device number for a non-UNIX file system that it is exporting. On a successful v_reg call, the device number is returned in the **Devno** field of the Nreg structure.

If the process is responsible for posting threads that are waiting within a specific PFS, the process can establish special recovery by specifying the PFS with:

PfsType

The name of the physical file system that is dependent on this process for osi_post. This is the name that was specified when the PFS was defined in the BPXPRMxx parmlib member with either FILESYSTYPE TYPE() or SUBFILESYSTYPE NAME().

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_reg service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_reg service stores the return code. The v_reg service returns the return code only if the return value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The following table lists the possible return code values that can be returned.

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, the server name length that was supplied in the registration parameter list was too long; or the server type that was supplied is not a recognized value. |
| | The JRNameTooLong, JRInvalidNReg, and JRInvalidRegType reason codes can accompany the EINVAL return code. code. |
| EPERM | The operation is not permitted. The caller of the service is not privileged; or the caller is already registered. |

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_reg service stores the reason code. The v_reg service returns the reason code only if the return value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. Registration as a server is not inherited across a fork.
- 2. The **MaxVNTokens** field in the registration parameter list is an input and output parameter. If supplied by the caller, it indicates the value that should be used for this server. If a value of 0 is supplied, or if the value that is supplied exceeds the maximum allowed value, the maximum allowed value is used and returned.
- 3. If the exit program cannot be loaded, the Nreg abend code and abend reason code fields are completed in with the corresponding values that are returned by the system load service.
 - If the exit program fails, v_reg also fails, and the exit's return and reason codes are returned as the corresponding values from v_reg.
- 4. If the server's address space is started before the z/OS UNIX address space, a v_reg that is issued during initialization fails. To account for this, an Event Notification Facility (ENF) signal is issued whenever z/OS UNIX is started. During initialization, a server can set up an ENF Listen for this event and call v_reg. If the v_reg call fails with EMVSNOTUP, the ENF signal is eventually issued, and v_reg can be called again after the server's ENF Listen exit is invoked. The ENF Qualifier Constant is defined in macro BPXYENFO. For more information about the ENF service, see Listening for system events in z/OS MVS Programming: Authorized Assembler Services Guide.
- 5. When a PFS is dependent on a separate address space to call osi_post to wake up threads that are in osi_wait within that PFS, recovery can be established to protect these threads from waiting forever if the separate address space terminates abnormally.

To do this, the separate address space registers and specifies a PfsType name. This creates a process, if one did not exist. When the registered process terminates, the system scans for and wakes up any users that are in osi_wait from within the specified PFS. The PFS's osi_wait call returns with a return code of OSI_POSTERTRM if it is posted for this reason.

This recovery support is process-related. A process is usually the same as the address space, but if the registering task is the only task to use z/OS UNIX services, or if set_dub_default (BPX1SDD/BPX4SDD) has been called to make each task a separate process, this recovery is invoked when the registering task terminates.

If this recovery support is the only reason that the server is registering, use the server type for a file server.

- 6. There is no specific way to unregister. If necessary, the task can call mvsprocclp (BPX1MPC/BPX4MPC) to terminate the process, which also unregisters the server.
- 7. If z/OS UNIX terminates and restarts while the server address space is active, mvsprocclp (BPX1MPC) must be called on each task that used z/OS UNIX services to remove its binding to the old instance of z/OS UNIX before V_reg can be recalled to reregister as a server.

Characteristics and restrictions

In order to register, the caller must have appropriate privileges.

Examples

For an example of this callable service, see "BPX1VRG, BPX4VRG (v_reg)" on page 458.

v_rel (BPX1VRL, BPX4VRL) — Release a vnode token

Function

The v_rel service accepts a Vnode_token value that represents a file or a directory and releases that token.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VRL): | 31-bit |
| AMODE (BPX4VRL): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

```
CALL BPX1VRL,(Vnode_token,
OSS,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VRL with the same parameters.

Parameters

Vnode_token

Supplied parameter

v_rel (BPX1VRL, BPX4VRL)

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that is to be released.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rel service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rel service stores the return code. The v_rel service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_rel service can return one of the following values in the Return code parameter:

Return_code Explanation EINVAL Parameter error; for example, Vnode_token has already been released. The following reason codes can accompany the return code: JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rel service stores the reason code. The v_rel service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. The vnode token is no longer valid and cannot be used for subsequent requests after the v_rel service has successfully processed it.
- 2. All vnode tokens that are obtained from other operations must be released by calling this service.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321

Characteristics and restrictions

A process must be registered as a server before the v_rel service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRL, BPX4VRL (v_rel)" on page 459.

v_remove (BPX1VRM, BPX4VRM) — Remove a link to a file

Function

The v remove service removes a link to a file.

The name of the link is specified as input, along with a Directory_vnode_token value that identifies the directory that contains the name that is to be removed. The name can identify a file, a link name to a file, or a symbolic link.

Requirements

| Operation | Environment |
|----------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VRM): 31-bit
AMODE (BPX4VRM): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VRM with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory from which the v_remove service is to remove the entry that is supplied in the Name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro, see "BPXYOSS — Specific information for the Map operating system" on page 442.

Name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Name. The name can be up to 255 bytes long.

Name

Supplied parameter

Type:

Character string

Length:

Specified by Name_length parameter

The name of an area, of length Name_length, that contains the name that is to be removed. It must not contain null characters (X'00').

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_remove service returns 0 if the request completes successfully, or -1 if the request is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_remove service stores the return code. The v_remove service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_remove service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The process did not have write permission for the directory that contains the name that is to be removed. |
| EAGAIN | The name cannot be removed, because it is temporarily unavailable. The following reason code can accompany the return code: JRInvalidVnode. |
| EBUSY | The file is open by a remote NFS client with a share reservation that conflicts with the requested operation. |
| EINVAL | Parameter error; for example, the vnode token parameter is stale. The following reason codes can accompany the return code: JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS, JRNoName, JRNullInPath. |
| ENAMETOOLONG | Name_length exceeds 255 characters. |
| ENOENT | Name was not found. |
| ENOTDIR | The file that was specified by Directory_vnode_token is not a directory. The following reason code can accompany the return code: JRTokNotDir. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server; or Name specifies a directory. The following reason codes can accompany the return code: JRNotRegisteredServer, JRNotForDir. |
| EROFS | The name that is to be removed is on a read-only file system. The following reason code can accompany the return code: JRReadOnlyFS. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_remove service stores the reason code. The v_remove service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. If the sticky bit is on in the parent directory, the file cannot be deleted.
- 2. If the name that is specified refers to a symbolic link, the symbolic link file that is named by Name is deleted.
- 3. If the v_remove service request is successful and the link count becomes zero, the file is deleted. The contents of the file are discarded, and the space it occupied is freed for reuse. However, if another

- process (or more than one) has the file open, or has a valid vnode token, when the last link is removed, the file contents are not discarded until the last process closes the file or releases the vnode token.
- 4. When the v_remove service is successful in removing a directory entry and decrementing the link count, whether or not the link count becomes zero, it returns control to the caller with Return_value set to 0. It updates the change and modification times for the parent directory, and the change time for the file itself (unless the file is deleted).
- 5. Directories cannot be removed using v_remove. To remove a directory, refer to <u>"v_rmdir (BPX1VRE, BPX4VRE)</u> Remove a directory" on page 334.
- 6. A file may not be removed if it is currently open by a remote NFS client with a share reservation that would prevent the file from being opened for write access.

Related services

- "v_link (BPX1VLN, BPX4VLN) Create a link to a file " on page 280
- "v_lookup (BPX1VLK, BPX4VLK) Look up a file or directory" on page 294
- "v_mkdir (BPX1VMD, BPX4VMD) Create a directory" on page 297
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server " on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325
- "v_remove (BPX1VRM, BPX4VRM) Remove a link to a file " on page 327
- "v_rename (BPX1VRN, BPX4VRN) Rename a file or directory" on page 330
- "v_rmdir (BPX1VRE, BPX4VRE) Remove a directory" on page 334

Characteristics and restrictions

A process must be registered as a server before the v_remove service is permitted. See <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRM, BPX4VRM (v_remove)" on page 459.

v_rename (BPX1VRN, BPX4VRN) — Rename a file or directory

Function

The v_rename service renames a file or a directory that is specified by the Old_name parameter in the directory that is represented by Old_directory_vnode_token to the name that is specified by the New_name parameter in the directory that is represented by New_directory_vnode_token.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VRN): | 31-bit |
| AMODE (BPX4VRN): | 64-bit |
| ASC mode: | Primary mode |

Interrupt status: Enabled for interrupts

Locks: Unlocked

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL BPX1VRN,(Old_directory_vnode_token,
OSS,
Old_name_length,
Old_name,
New_directory_vnode_token,
New_name_length,
New_name,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VRN with the same parameters.

Parameters

Old_directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the file or directory that is to be renamed exists.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating system specific parameters. This area is mapped by the BPXYOSS macro, see "BPXYOSS — Specific information for the Map operating system" on page 442.

Old_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the file or directory name that is to be renamed. The name can be up to 255 bytes long.

Old_name

Supplied parameter

Type:

Character string

Length:

Specified by Old_name_length parameter

The name of an area, of length Old_name_length, that contains the file or directory name that is to be renamed. It must not contain null characters (X'00').

New_directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the renamed file or directory is to exist.

New_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the file or directory name to which the file or directory is to be renamed. The name can be up to 255 bytes long.

New_name

Supplied parameter

Type:

Character string

Length:

Specified by New_name_length parameter

The name of an area, of length New_name_length, that contains the file or directory name to which the file or directory is to be renamed. It must not contain null characters (X'00').

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rename service returns 0 if the request is successful, or -1 if it is not successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rename service stores the return code. The v_rename service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_rename service can return one of the following values in the Return_code parameter:

Return_code Explanation

EACCES The calling process does not have permission to write in a specified directory.

| Return_code | Explanation |
|--------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EAGAIN | One of the files or directories was temporarily unavailable. The following reason code can accompany the return code: JRInvalidVnode. |
| EBUSY | The name that was specified is in use as a mount point or the file is open by a remote NFS client with a share reservation that conflicts with the requested operation. The following reason code can accompany the return code: JRIsFSRoot. |
| EINVAL | Parameter error—for example, attempting to rename a file named "" The following reason codes can accompany the return code: JRDotorDotDot, JrOldPartOfNew, JrNoName, JrNullInPath, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EISDIR | An attempt was made to rename something other than a directory to a directory. |
| ENAMETOOLONG | A name is longer than 255 characters. |
| ENOSPC | The directory that is intended to contain New_name cannot be extended. |
| ENOTDIR | The supplied token did not represent a directory; or an attempt was made to rename a directory to something other than a directory. |
| ENOTEMPTY | New_name specified an existing directory that was not empty. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EROFS | The specified file system is read-only. The following reason code can accompany the return code: JRReadOnlyFS. |
| EXDEV | An attempt was made to rename across file systems. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rename service stores the reason code. The v_rename service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. If the sticky bit is on in the parent directory, special ownership is required to rename the file.
- 2. The v_rename service changes the name of a file or a directory from Old_name to New_name. When renaming completes successfully, the change and modification times for the parent directories of Old_name and New_name are updated.
- 3. For renaming to succeed, the calling process needs write permission for the directory that contains Old_name and the directory that contains New_name. If Old_name and New_name are the names of directories, the caller does not need write permission for the directories themselves.

4. Renaming Files:

- If Old_name and New_name are links that refer to the same file, v_rename returns successfully and does not perform any other action.
- If Old_name is the name of a file, New_name must also name a file, not a directory. If New_name is an existing file, it is unlinked. Then the file that is specified as Old_name is given New_name. The pathname New_name always stays in existence; at the beginning of the operation, New_name refers to its original file, and at the end, it refers to the file that used to be Old_name.
- If Old_name is the name of a file that is currently open by a remote NFS client with a share reservation that would prevent the file from being opened for writing, the file cannot be renamed.

5. Renaming Directories:

If Old_name is the name of a directory, New_name must also name a directory, not a file. If New_name is an existing directory, it must be empty, containing no files or subdirectories. If empty, it is removed, as described in "v_remove (BPX1VRM, BPX4VRM) — Remove a link to a file " on page 327.

New_name cannot be a directory under Old_name; that is, the old directory cannot be part of the pathname prefix of the new one.

Related services

• "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321

Characteristics and restrictions

A process must be registered as a server before the v_rename service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRN, BPX4VRN (v rename)" on page 459.

v_rmdir (BPX1VRE, BPX4VRE) — Remove a directory

Function

The v_rmdir service removes a directory. The directory must be empty.

Directory_name is specified as input, along with a Directory_vnode_token value that identifies the directory that contains the directory that is to be removed.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VRE): | 31-bit |
| AMODE (BPX4VRE): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VRE with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8 byte area that contains a vnode token that represents the directory from which the v_rmdir service is to remove the directory that is supplied in the Directory_name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Directory_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Directory_name. The name can be up to 255 bytes long.

Directory_name

Supplied parameter

Type:

Character string

Length:

Specified by Directory_name_length parameter

The name of an area, of length Directory_name_length, that contains the name of the directory that is to be removed. It must not contain null characters (X'00').

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rmdir service returns 0 if the request completes successfully, or -1 if the request is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rmdir service stores the return code. The v_rmdir service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_rmdir service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The process did not have write permission for the directory that contains the directory that is to be removed. |
| EBUSY | The directory cannot be removed, because it is being used as a mount point. The following reason code can accompany the return code: JRIsFSRoot. |
| EAGAIN | The directory cannot be removed, because it is temporarily unavailable. The following reason code can accompany the return code: JRInvalidVnode. |
| EINVAL | Parameter error; for example, the Vnode_token parameter is obsolete. The following reason codes can accompany the return code: JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS, JRDotOrDotDot, JRNoName, JRNullInPath. |
| ENAMETOOLONG | Directory_name_length exceeds 255 characters. |
| ENOENT | The directory that was specified by Directory_name was not found. |
| ENOTDIR | The file that was specified by Directory_vnode_token is not a directory; or the name that was specified by Directory_name is not a directory. The following reason codes can accompany the return code: JRTokNotDir, JRNotDir. |
| ENOTEMPTY | The directory contains files or subdirectories. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EROFS | The directory that is to be removed is on a read-only file system. The following reason code can accompany the return code: JRReadOnlyFS. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rmdir service stores the reason code. The v_rmdir service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. If the sticky bit is on in the parent directory, the target directory cannot be removed.
- 2. The directory that is specified by Directory_name must be empty.
- 3. If the directory is successfully removed, the change and modification times for the parent directory are updated.
- 4. If any process has the directory open when it is removed, the directory itself is not removed until the last process has closed the directory. New files cannot be created under a directory that is removed, even if the directory is still open.

Related services

- "v_mkdir (BPX1VMD, BPX4VMD) Create a directory" on page 297
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325
- "v_remove (BPX1VRM, BPX4VRM) Remove a link to a file " on page 327

Characteristics and restrictions

A process must be registered as a server before the v_rmdir service is permitted. See <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRE, BPX4VRE (v_rmdir)" on page 460.

v_rpn (BPX1VRP, BPX4VRP) — Resolve a path name

Function

The v_rpn service accepts an absolute path name of a file or a directory and returns a vnode token that represents this file or directory, and the VFS token that represents the mounted file system that contains the file or directory. These tokens must be supplied by the server on any subsequent VFS callable services API that is related to these files, directories, or file systems. The v_rpn service also returns file attribute information for the file or directory, and mount information for the file system.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VRP): | 31-bit |
| AMODE (BPX4VRP): | 64-bit |

v_rpn (BPX1VRP, BPX4VRP))

Operation Environment

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL BPX1VRP, (OSS,
Pathname_length,
Pathname,
VFS_token,
Vnode_token,
Mnte_length,
Mnte,
Attr_length,
Attr,
Return_value,
Return_code,
Reason_code)
```

AMODE 64 callers use BPX4VRP with the same parameters.

Parameters

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Pathname_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the full path name of the file or directory that is to be resolved to a token. The name can be up to 1023 bytes long; each component of the name (between delimiters) can be up to 255 bytes long.

Pathname

Supplied parameter

Type:

Character string

Length:

Specified by Pathname_length parameter

The name of an area, of length Pathname_length, that contains the full name of the file or directory that is to be resolved.

VFS_token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_rpn service returns the VFS token of the file system that contains the file or directory that is supplied in the Pathname parameter.

Vnode_token

Returned parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area in which the v_rpn service returns a vnode token of the file or directory that is supplied in the Pathname parameter.

Mnte_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Mnte parameter.

The length of this area must be large enough to contain a mount entry header (MnteH) and one mount entry (Mnte). These fields are mapped by the BPXYMNTE macro. For more information about the BPXYMNTE macro, see BPXYMNTE — Map response and element structure of w_getmntent in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Mnte

Returned parameter

Type:

Structure

Length:

Specified by the Mnte_length parameter

The name of an area, of length Mnte_length, in which the v_rpn service returns information about the file system that contains the file or directory that is supplied in the Pathname parameter. This area is mapped by the BPXYMNTE macro. For more information about the BPXYMNTE macro, see BPXYMNTE — Map response and element structure of w_getmntent in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the area that is passed in the Attr parameter. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

v_rpn (BPX1VRP, BPX4VRP))

Attr

Returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, in which the v_rpn service returns the file attribute structure for the file or directory that is supplied in the Pathname parameter. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rpn service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rpn service stores the return code. The v_rpn service returns Return_code only if Return_value is -1.For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_rpn service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, the Pathname parameter did not contain an absolute path name; or one of the supplied areas was too small. The following reason codes can accompany the return code: JRNoLeadingSlash, JRSmallAttr, JRSmallMnte, JRInvalidOSS, JRNullInPath. |
| ELOOP | Too many symbolic links were encountered in the path name. |
| EMFILE | The maximum number of vnode tokens have been created. |
| ENAMETOOLONG | The path name or a component in the path name is too long. |
| ENFILE | An error occurred while storage was being obtained for a vnode token. |
| ENOENT | A directory or file that was supplied in the Pathname parameter does not exist; or the Pathname_length parameter is not greater than 0. |
| ENOTDIR | A node in the path name is not a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |

Return_code Explanation

ERREMOTE The object is remote. This return code can be accompanied by reason code JrNoRemote.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_rpn service stores the reason code. The v_rpn service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. Vnode tokens that are returned by the v_rpn service are not inherited across a fork callable service.
- 2. VFS tokens that are returned by the v_rpn service are inherited across a fork callable service.
- 3. The mount point path name is not returned in the Mnte structure that is returned by v_rpn.
- 4. The caller is responsible for freeing the vnode token that is returned by the v_rpn service, by calling to the v_rel service when it is no longer needed.
- 5. When the OssNoRemote flag is, set v_rpn will not cross over into a remote file system, such as the NFS Client file system. If a remote file system is encountered during the resolution of the path name, v_rpn will fail with a return code of ERREMOTE.

Related services

- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_rel (BPX1VRL, BPX4VRL) Release a vnode token" on page 325

Characteristics and restrictions

A process must be registered as a server before the v_rpn service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VRP, BPX4VRP (v_rpn)" on page 460.

v_setattr (BPX1VSA, BPX4VSA) — Set the attributes of a file

Function

The v_setattr service sets the attributes that are associated with the file that is represented by Vnode_token. It can be used to change the mode, owner, access time, modification time, change time, reference time, audit flags, general attribute flags, and file size. It can also be used to set the initial security label for a file or directory.

Requirements

Operation Environment

Authorization: Supervisor state or problem state, any PSW key

Operation Environment

Dispatchable unit mode: Task

Cross memory mode: PASN = HASN

AMODE (BPX1VSA): 31-bit
AMODE (BPX4VSA): 64-bit

ASC mode: Primary mode

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

AMODE 64 callers use BPX4VSA with the same parameters.

Parameters

Vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the file.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Attr. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Supplied and returned parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, that contains the file attributes to be set for the file that is specified by the vnode token. The attributes of the file are also returned in this area, overlaying the input values. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_setattr service returns 0 if the request is successful, or -1 if it is not successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_setattr service stores the return code. The v_setattr service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_setattr service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRInvalidAttr, JRNegativeValueInvalid, JRTrNotRegFile, JRTrNegOffset, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| EACCES | The calling process did not have appropriate permissions. Possible reasons include: |
| | In an attempt to set access time or modification time to current time, the effective UID of the calling process does not match the owner of the file, the process does not have write permission for the file, and the process does not have appropriate privileges. |
| | In an attempt to truncate the file, the calling process does not have write permission for the file. |
| EFBIG | A process attempted to change the size of a file, but the new length that was specified is greater than the maximum file size limit for the process. The following reason code can accompany the return code: JRWriteBeyondLimit. |

| Return_code | Explanation |
|-------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EPERM | The operation is not permitted for one of the following reasons: |
| | The caller of the service is not registered as a server. |
| | In an attempt to change the mode or the file format, the effective UID of the calling process does not match the owner of the file, and the calling process does not have appropriate privileges. |
| | In an attempt to change the owner, the calling process does not have appropriate privileges. |
| | In an attempt to change the general attribute bits, the calling process does not have write permission for the file. |
| | In an attempt to set a time value (not current time), the effective user ID of the calling process does not match the owner of the file, and the calling process does not have appropriate privileges. |
| | In an attempt to set the change time or reference time to currentime, the calling process does not have write permission for the file. |
| | In an attempt to change auditing flags, the effective UID of the calling process does not match the owner of the file, and the calling process does not have appropriate privileges. |
| | In an attempt to change the security auditor's auditing flags, the user does not have auditor authority. |
| | In an attempt to set the security label, one or more of the following conditions applies: |
| | The calling process does not have RACF SPECIAL authorization and appropriate privileges. |
| | The security label that is associated with the file is already set. |
| EROFS | The file is on a read-only file system. The following reason code can accompany the return code: JRReadOnlyFS. |
| ESTALE | On input, the AttrGuardTimeChk bit was on, and the input AttrGuardTime value did not match the Ctime of the file. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_setattr service stores the reason code. The v_setattr service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

| Table 14. Attributes fields fo | r v_setattr | |
|-----------------------------------|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| Set flags | Attribute fields input | Description |
| ATTRCHARSETIDCHG | ATTRCHARSETID | Set the character set ID to the value specified in ATTRCHARSETID |
| ATTRMODECHG | ATTRMODE | Set the mode according to the value in ATTRMODE. |
| AttrOwnerChg | ATTRUID and ATTRGID | Set the owner user ID (UID) and group ID (GID) to the values specified in ATTRUID and ATTRGID. |
| ATTRSETGEN | ATTRGENVALUE ATTRGENMASK | Only the bits corresponding to the bits set ON in the ATTRGENMASK are set to the value (ON or OFF) in ATTRGENVALUE. Other bits will be unchanged. |
| ATTRTRUNC | ATTRSIZE | Truncate the file size to ATTRSIZE bytes. |
| ATTRATIMECHG | ATTRATIME | Set the access time of the file to the value specified in ATTRATIME. |
| ATTRATIMECHG and ATTRATIMETOD | None | Set the access time of the file to the current time. |
| ATTRMTIMECHG | ATTRMTIME | Set the modification time of the file to the value specified in ATTRMTIME. |
| ATTRMTIMECHG and ATTRMTIMETOD | None | Set the modification time of the file to the current time |
| ATTRMAAUDIT | ATTRAUDITORAUDIT | Set the security auditor's auditing flags to the value specified in ATTRAUDITORAUDIT. |
| ATTRMUAUDIT | ATTRUSERAUDIT | Set the user's auditing flags to the value specified in ATTRUSERAUDIT. |
| ATTRCTIMECHG | ATTRCTIME | Set the change time of the file to the value specified in ATTRCTIME. |
| ATTRCTIMECHG and ATTRCTIMETOD | None | Set the change time of the file to the current time. |
| ATTRREFTIMECHG | ATTRREFTIME | Set the reference time of the file to the value specified in ATTRREFTIME. |
| ATTRREFTIMECHG and ATTRREFTIMETOD | None | Set the reference time of the file to the current time. |
| ATTRFILEFMTCHG | ATTRFILEFMT | Set the file format of the file to the value specified in ATTRFILEFMT. |
| ATTRSECLABELCHG | ATTRSECLABEL | Set the initial security label for a file or directory. |

^{1.} Flags in the attributes parameter are set to indicate which attributes should be updated. To set an attribute, turn the corresponding Set Flag on, and set the corresponding attributes field according to Table 14 on page 345. Multiple attributes may be changed at the same time.

The Set Flag field should be cleared before any bits are turned on. It is considered an error if any of the reserved bits in the flag field are turned on.

2. In addition to the attribute fields that are specified according to <u>Table 14 on page 345</u>, the following ATTR header fields must be provided by the caller:

ATTRID

Contains ATTR.

ATTRLEN

Specifies the length of the ATTR structure.

AttrGuardTimeChk

Indicates whether the AttrGuardTime should be checked. If this bit is on, the PFS checks the Ctime of the file against the value that is specified in AttrGuardTime. If they do not match, the request fails with ESTALE.

AttrGuardTime

The time value, in seconds and micro-seconds, to be compared against the file's Ctime if AttrGuardTimeChk is set.

Other fields in the ATTR should be set to 0s.

- 3. Changing mode (ATTRMODECHG = ON):
 - The file mode field in the ATTR area is mapped by the BPXYMODE macro. For more information, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.
 - Files that are open when the v_setattr service is called retain the access permission they had when the file was opened.
 - The effective UID of the calling process must match the file's owner UID, or the caller must have appropriate privileges.
 - Setting the set-group-ID-on-execution permission (in mode) means that when this file is run, through the exec service, the effective GID of the caller is set to the file's owner GID, so that the caller seems to be running under the GID of the file, rather than that of the actual invoker.

The set-group-ID-on-execution permission is set to zero if both of the following are true:

- The caller does not have appropriate privileges.
- The GID of the file's owner does not match the effective GID or one of the supplementary GIDs of the caller.
- Setting the set-user-ID-on-execution permission (in mode) means that when this file is run, the process's effective UID is set to the file's owner UID. This way, the process seems to be running under the UID of the file's owner, rather than that of the actual invoker.
- 4. Changing owner (ATTROWNERCHG = ON):
 - For changing the owner UID of a file, the caller must have appropriate privileges.
 - For changing the owner GID of a file, the caller must have appropriate privileges, or meet all of these conditions:
 - The effective UID of the caller matches the file's owner UID.
 - The Owner_UID value that is specified in the change request matches the file's owner UID.
 - The Group_ID value that is specified in the change request is the effective GID, or one of the supplementary GIDs, of the caller.
 - When owner is changed, the set-user-ID-on-execution and set-group-ID-on-execution permissions of the file mode are automatically turned off.
 - When owner is changed, both UID and GID must be specified as they are to be set. If only one of these values is to be changed, the other must be set to its present value or to -1 in order to remain unchanged.
- 5. Changing general attribute bits (ATTRSETGEN = ON):

- For general attribute bits to be changed, the calling process must have write permission for the file.
- 6. Truncating a file (ATTRTRUNC = ON):
 - The truncation of a file to ATTRSIZE bytes changes the file size to ATTRSIZE, beginning from the first byte of the file. If the file was originally larger than ATTRSIZE bytes, the data from ATTRSIZE to the original end of file is removed. If the file was originally shorter than ATTRSIZE, bytes between the old and new lengths are read as zeros.
 - Full blocks are returned to the file system so that they can be used again. The file offset is not changed.
 - When a file is truncated successfully, it clears the set-user-ID, the set-group-ID, and the save-text (sticky bit) attributes of the file unless the caller has authority to access the root.
 - Changing a file's size is considered to be a write operation and an open token from a prior v_open may be passed in the OSS to indicate that this change is being done within the open context of that token. Consequently, the operation does not have to be verified against the share reservations that may currently be in effect for the file. If no open token is available to pass on the call, there are three levels of share reservation checking that can be requested (see "v_rdwr (BPX1VRW, BPX4VRW) Read from and write to a file " on page 311 for details).

7. Changing times:

- All time fields in the Attr area are in POSIX format.
- For the access time or the modification time to be set explicitly (ATTRATIMECHG = ON or ATTRMTIMECHG = ON), the effective ID must match the file's owner, or the process must have appropriate privileges.
- For the access time or modification time to be set to the current time (ATTRATIMETOD = ON or ATTRMTIMETOD = ON), the effective ID must match the file's owner, the calling process must have write permission for the file, or the process must have appropriate privileges.
- For the change time or the reference time to be set explicitly (ATTRCTIMECHG = ON or ATTRREFTIMECHG = ON), the effective ID must match the file's owner or the process must have appropriate privileges.
- For the change time or reference time to be set to the current time (ATTRCTIMETOD = ON or ATTRREFTIMETOD = ON), the calling process must have write permission for the file.
- When any attribute field is changed successfully, the file's change time is updated as well.
- The setting of the AttrLP64times bit in the BPXYATTR structure, and not the AMODE of the caller, determines whether 4-byte or 8-byte time fields are used. When AttrLP64Times=ON with any of the explicit time changes the new time value is taken from the corresponding AttrATime64, AttrMTime64, AttrCTime64, or AttrRefTime64 field.
- 8. Changing auditor audit flags (ATTRMAAUDIT = ON):
 - For auditor audit flags to be changed, the user must have auditor authority. Users with auditor authority can set the auditor options for any file, even those they do not have path access to or authority to use for other purposes.
 - You can establish auditor authority by running the TSO/E command ALTUSER Auditor.
- 9. Changing user audit flags (ATTRMUAUDIT = ON):
 - For the user audit flags to be changed, the user must have appropriate privileges or be the owner of the file. For more information about appropriate privileges, see <u>Authorization</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.
- 10. Changing file format (ATTRFILEFMTCHG = ON):
 - The effective UID of the calling process must match the file's owner UID or the caller must have appropriate privileges.
- 11. Changing the security label (ATTSECLABELCHG=ON):
 - For the security label to be changed, the user must have RACF SPECIAL authorization and appropriate privileges, and no security label must currently exist on the file. Only an initial security

label can be set. An existing security label cannot be changed. The function will successfully set the security label if the SECLABEL class is active. If the SECLABEL class is not active, the request will return successfully, but the security label will not be set.

12. The tagging of /dev/null, /dev/random, /dev/urandom, /dev/zero is ignored.

Related services

- "v_getattr (BPX1VGA, BPX4VGA) Get the attributes of a file " on page 274
- "v_reg (BPX1VRG, BPX4VRG) Register a process as a server " on page 321

Characteristics and restrictions

- 1. A process must be registered as a server before the v_setattr service is permitted; see <u>"v_reg"</u> (BPX1VRG, BPX4VRG) Register a process as a server " on page 321.
- 2. The ATTREXTLINK flag in the ATTRGENVALUE field of the ATTR cannot be modified with BPX1VSA.
- 3. The general attribute fields (set by ATTRSETGEN, ATTRGENMASK, and ATTRGENVALUE fields) are not intended as a general-use programming interface on v_setattr.
- 4. The security label (ATTRSECLABELCHG) flag requires RACF SPECIAL authorization and appropriate privileges. See <u>Authorization</u> in <u>z/OS UNIX System Services Programming: Assembler Callable Services Reference</u> for information about appropriate privileges.
- 5. The security label (ATTRSECLABELCHG) flag cannot be used to change an existing security label; it can only be used to set an initial security label on a file.

Examples

For an example using this callable service, see "BPX1VSA, BPX4VSA (v_setattr)" on page 460.

v_symlink (BPX1VSY, BPX4VSY) — Create a symbolic link

Function

The v_symlink service creates a symbolic link to a path name or external name. A file whose name is specified in the Link_name parameter, of type "symbolic link", is created within the directory that is represented by Directory_vnode_token. The contents of the symbolic link file is the path name or external name that is specified in Pathname.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | PASN = HASN |
| AMODE (BPX1VSY): | 31-bit |
| AMODE (BPX4VSY): | 64-bit |
| ASC mode: | Primary mode |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

AMODE 64 callers use BPX4VSY with the same parameters.

Parameters

Directory_vnode_token

Supplied parameter

Type:

Token

Length:

8 bytes

The name of an 8-byte area that contains a vnode token that represents the directory in which the v_symlink service creates the new symbolic link file that is named in the Link_name parameter.

OSS

Supplied and returned parameter

Type:

Structure

Length:

OSS#LENGTH (from the BPXYOSS macro)

The name of an area that contains operating-system-specific parameters. This area is mapped by the BPXYOSS macro (see "BPXYOSS — Specific information for the Map operating system" on page 442).

Link_name_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Link_name. The Link_name can be up to 255 bytes long.

Link_name

Supplied parameter

Type:

Character string

Length:

Specified by Link_name_length parameter

The name of a field that contains the symbolic link that is being created. It must not contain null characters (X'00').

Pathname_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Pathname. The Pathname can be up to 1023 bytes long. If the Pathname is not an external name (AttrExtLink = 0), each component of the name (between delimiters) can be up to 255 bytes long.

Pathname

Supplied parameter

Type:

Character string

Length:

Specified by the Pathname_length parameter

The name of a field that contains the path name or external name for which you are creating a symbolic link.

A path name can begin with or without a slash.

- If the path name begins with a slash, it is an absolute path name, the slash refers to the root directory, and the search for the file starts at the root directory.
- If the path name does not begin with a slash, it is a relative path name, and the search for the file starts at the parent directory of the symbolic link file.

A path name must not contain null characters (X'00').

An external name is the name of an object that is outside the hierarchical file system. There are no restrictions on the characters that may be used in an external name.

Attr_length

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of Attr. To determine the value of Attr_length, use the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls" on page 433).

Attr

Supplied parameter

Type:

Structure

Length:

Specified by the Attr_length parameter

The name of an area, of length Attr_length, that is to be used by the v_symlink service to set the attributes of the file that is to be created. This area is mapped by the ATTR structure (see "BPXYATTR — Map file attributes for v_ system calls " on page 433).

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_symlink service returns 0 if the request is successful, or -1 if it is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_symlink service stores the return code. The v_symlink service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The v_symlink service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The calling process does not have permission to write in the directory specified. |
| EEXIST | Link_name already exists. |
| EFBIG | The file size limit for the process is set to zero, prohibiting the creation of symbolic links. |
| EINVAL | Parameter error; for example, a supplied area was too small. The following reason codes can accompany the return code: JRSmallAttr, JRInvalidAttr, JRNoName, JRInvalidSymLinkLen, JRNULLInPath, JRInvalidSymLinkComp, JRVTokenFreed, JRWrongPID, JRStaleVnodeTok, JRInvalidVnodeTok, JRInvalidOSS. |
| ENAMETOOLONG | Link_name is longer than 255 characters. |
| ENOTDIR | The supplied token did not represent a directory. |
| EPERM | The operation is not permitted. The caller of the service is not registered as a server. |
| EROFS | Directory_vnode_token specifies a directory on a read-only file system. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the v_symlink service stores the reason code. The v_symlink service returns a Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The following Attr fields are provided by the caller:

AttrID

Contains Attr#ID (from the ATTR structure)

AttrLen

Specifies the length of the ATTR structure.

AttrExtLink

Specifies whether the Pathname is an external name (1) or a path name in a hierarchical file system (0).

AttrMode

Specifies directory mode permission bits. For the mapping of this field, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

Other fields in the ATTR should be set to zeros.

- 2. Like a hard link (described in "v_link (BPX1VLN, BPX4VLN) Create a link to a file "on page 280), a symbolic link allows a file to have more than one name. The presence of a hard link guarantees the existence of a file, even after the original name has been removed. A symbolic link, however, provides no such assurance; in fact, the file that is identified by Pathname need not exist when the symbolic link is created. In addition, a symbolic link can cross file system boundaries, and can refer to objects that are outside a hierarchical file system.
- 3. When a component of a path name refers to a symbolic link (but not an external symbolic link) rather than to a directory, the path name that is contained in the symbolic link is resolved. When the VFS callable services API, v_rpn, or other z/OS UNIX callable services are being used, a symbolic link in a path name parameter is resolved as follows:
 - If the path name in the symbolic link begins with / (slash), the symbolic link path name is resolved relative to the process root directory.
 - If the path name in the symbolic link does not begin with /, the symbolic link path name is resolved relative to the directory that contains the symbolic link.
 - If the symbolic link is not the last component of the original path name, remaining components of the original path name are resolved from there.
 - When a symbolic link is the last component of a path name, it may or may not be resolved. Resolution depends on the function that is using the path name. For example, a rename request does not have a symbolic link resolved when it appears as the final component of either the new or old path name. However, an open request does have a symbolic link resolved when it appears as the last component.
 - When a slash is the last component of a path name, and it is preceded by a symbolic link, the symbolic link is always resolved.
 - The mode of a symbolic link is ignored during the lookup process. Any files and directories to which a symbolic link refers are checked for access permission.
- 4. The external name that is contained in an external symbolic link is not resolved. Link_name cannot be used as a directory component of a path name.
- 5. If the file size limit for the process is set to zero, symbolic link creation is prohibited and fails with
- 6. The value that is set by umask() for the process does not affect the setting of the mode permission bits.

Related services

- "v getattr (BPX1VGA, BPX4VGA) Get the attributes of a file" on page 274
- "v reg (BPX1VRG, BPX4VRG) Register a process as a server" on page 321
- "v_readlink (BPX1VRA, BPX4VRA) Read a symbolic link" on page 319
- "v_remove (BPX1VRM, BPX4VRM) Remove a link to a file " on page 327
- "v_link (BPX1VLN, BPX4VLN) Create a link to a file " on page 280

Characteristics and restrictions

A process must be registered as a server before the v_symlink service is permitted; see <u>"v_reg (BPX1VRG, BPX4VRG)</u> — Register a process as a server " on page 321.

Examples

For an example using this callable service, see "BPX1VSY, BPX4VSY (v_symlink)" on page 461.

v_symlink (BPX1VSY, BPX4VSY)

Chapter 6. OSI services

The LFS provides several Operating System Interface (OSI) callable services specifically for PFSs.

The addresses of these routines are passed to a PFS during initialization in the OSI operations vector table (OSIT structure). For information about how the OSIT is passed to the PFS during initialization, see "Activating and deactivating the PFS" on page 4. See also Appendix D, "Interface structures for C language servers and clients," on page 465 for more information about C language structures.

Table 15 on page 355 shows the OSI services.

| Table 15. OSI services | | |
|------------------------|--------------------------------------------------------------|--|
| Service | Description | |
| osi_copyin | Copy data to a PFS buffer | |
| osi_copyout | Copy data to a user buffer | |
| osi_copy64 | Move data between user and PFS buffers with 64-bit addresses | |
| osi_ctl | Pass control information to the kernel | |
| osi_getcred | Obtain SAF UIDs, GIDs, and supplementary IDs | |
| osi_getvnode | Get a vnode | |
| osi_kipcget | Query interprocess communications | |
| osi_kmsgctl | Control in-kernel messages | |
| osi_kmsgget | Get a message queue ID | |
| osi_kmsgrcv | Receive an in-kernel message from the queue | |
| osi_kmsgsnd | Send an in-kernel message to the queue | |
| osi_mountstatus | Report file system status | |
| osi_post | General post | |
| osi_sched | Schedule Part 2 of Async I/O | |
| osi_selpost | Select post | |
| osi_signal | Send a signal | |
| osi_sleep | Wait for a resource | |
| osi_thread | Fetch a module from a thread | |
| osi_uiomove | Move data between buffers | |
| osi_upda | Update Async I/O request | |
| osi_wait | General wait | |
| osi_wakeup | Wake a task waiting for a resource | |

This topic describes each of the OSI services, which are arranged in alphabetic order. The OSI services are callable services that are generally called only from within a PFS. Some of these services must be called from the same thread that is making a VFS or vnode call. The information about callable services from Chapter 5, "VFS callable services application programming interface," on page 253 applies here, with a few exceptions:

- The service name is a C-language macro that invokes the particular service based on its address in the OSIT structure.
- The three ways of invoking a module that are listed in <u>Chapter 5</u>, "VFS callable services application programming interface," on page 253 do not apply to these services. They must be called with the saved OSIT structure address, by using the macros listed in Table 15 on page 355.

Assembler language programs must use the OSIT structure offsets for each service. These offsets can be found in the OSIT typedef in Appendix D, "Interface structures for C language servers and clients," on page 465.

Any of the output parameters of a call can be modified by the system, whether the call is successful or not.

Using OSI services from a non-kernel address space

The osi_post, osi_selpost, and osi_wakeup services can be called from a non-kernel address space to wake up a thread that is waiting for some event to occur. Osi_ctl can be used from a non-kernel address space to communicate with a file exporter exit program. The osi_sched service can be called to initiate Part 2 of an asynchronous I/O.

For example, if a PFS establishes its own communication mechanism to another separate address space, there might be times when it needs to wait for a reply from that address space. In these cases the PFS can call osi_wait, while running on the user's thread in either the kernel or the other address space, and a program in that other address space can call osi_post to wake it up. A recovery option is available through the v_reg() function that ensures that these waiting processes are posted if the separate address space should terminate abnormally.

Similarly, if the PFS participates in select() processing and the selected event occurs in another address space, osi selpost can be called from that other address space.

This section does not apply to calls that are made by the PFS while in the kernel or in a colony address space. For these calls, the OSIT table address that is passed during initialization should be used.

To use the OSI services from an independent (non-cross-memory) thread in another address space, or from an end user thread that has PCed from the PFS to another address space, you must perform the following steps from an authorized program that is running in non-cross-memory mode in that other address space:

- 1. Issue an MVS LOAD for the module BPXVOSIT.
- 2. Branch to the address that is returned by LOAD, passing the standard return_value, return_code, and reason code parameters with OS linkage.

The program must be authorized at the time of this branch, so that a PC (Program Call instruction) can be set up between this address space and the kernel.

If return_value is not -1, it will be the address of an OSIT in this address space.

- 3. Save the OSIT address returned from a successful LOAD and branch.
- 4. Do not DELETE the BPXVOSIT load module. All the addresses of the OSI services are within this load module.

The constants and prototype related to doing this are included in <u>Appendix D</u>, "Interface structures for <u>C</u> language servers and clients," on page 465.

From this point on, you can call the OSI services from this address space (via the saved OSIT address) from C or assembler programs the same way a PFS does. The calling program does not have to be authorized at the time of an OSI service call, unless the service specifically requires it.

The following restrictions on using the OSI services from an independent task apply:

• A task in the server process can use the standard IPC message interface to communicate with a PFS that is using the osi_kmsg interface, so osi_getipc and the osi_kmsg services are not intended to be used from an independent task.

- A task in the server process can use the standard kill() function to send a signal; osi_signal should not be used.
- Osi_copyin, osi_copyout, and osi_uiomove should not be used to copy from or to the user address space buffers that were passed on a PFS operation.
- Osi_getvnode, osi_sleep, and osi_thread cannot be used. Osi_wait can be used after some special setup. Refer to the usage notes for osi_wait for details.

The effect of loading and calling BPXVOSIT is tied to the address space. BPXVOSIT cannot be called twice unless z/OS UNIX has terminated and restarted.

If the separate address space is started before the kernel address space, a call to BPXVOSIT that is issued during initialization fails. Generally, a PFS contacts its partner address space during z/OS UNIX initialization, and the load and call can be performed at this time. As an alternative, you can listen for the Event Notification Facility (ENF) Signal, which is issued whenever z/OS UNIX is started. During initialization, an address space can set up an ENF Listen for this event and call BPXVOSIT. If BPXVOSIT fails with EMVSNOTUP, the ENF Signal is eventually issued and BPXVOSIT can be called again after the server's ENF Listen exit is invoked. The ENF Qualifier Constant is defined in macro BPXYENFO.

Invoking OSI services in 31-bit and 64-bit addressing mode

Many OSI services can be invoked in both 31-bit and 64-bit addressing mode. Both Register 1 and the parameter list it points to must correspond to the caller's AMODE. If the parameter itself is identified as an address, it must be 4 byes or 8 bytes, depending on the caller's AMODE, unless otherwise stated.

osi_copyin — Move data from a user buffer to a PFS buffer

Function

The osi_copyin service moves a block of data from a user buffer to a PFS buffer.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state; any PSW key |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

Parameters

Destination_buffer

Supplied parameter

Type:

Char

Length:

Value specified by Move_length.

The name of the buffer in the PFS to which data is copied.

Destination_ALET

Supplied parameter

Type:

Integer

Length:

Fullword

The ALET for the specified Destination_buffer in the PFS.

Source_buffer

Supplied parameter

Type:

Char

Length:

Value specified by Move_length.

The name of the buffer in the user address space from which data is copied.

Source ALET

Supplied parameter

Type:

Integer

Length:

Fullword

The ALET for the specified Source_buffer in the user address space.

Source_key

Supplied parameter

Type:

Integer

Length:

Fullword

The storage key for the Source_buffer in the user address space. The specified key should be in the last 4 bits of the word. The key is typically the same value as the key stored in the UIO field UIO.u_key.

Move_length

Supplied parameter

Type:

Integer

Length:

Fullword

The number of bytes to move.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyin service returns the results of the request, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_code parameters contain the values returned by the service.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyin service stores the return code. The osi_copyin service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

The osi_copyin operation supports the following error value:

Return_code

Explanation

EFAULT

A specified buffer address is not in addressable storage.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyin service stores the reason code. The osi_copyin service returns Return_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

1. The address of the osi_copyin routine is passed to the PFS in the OSIT structure when the PFS is initialized.

2. The storage key for the destination buffer can be any storage key.

Related services

- "osi_uiomove Move data between PFS buffers and buffers defined by a UIO structure" on page 410
- "osi_copyout Move data from a PFS buffer to a user buffer" on page 360
- "osi_copy64 Move data between user and PFS buffers with 64-bit addresses" on page 363

Characteristics and restrictions

This routine must be used only on the dispatchable unit (task or SRB) that made the vnode or VFS call because the service requires the use of the cross-memory environment of the calling dispatchable unit.

osi_copyout — Move data from a PFS buffer to a user buffer

Function

The osi copyout service moves a block of data from a PFS buffer to a user buffer.

Requirements

| Operation | Environment |
|-------------------------|-------------------------------|
| Authorization: | Supervisor state; any PSW key |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Destination_buffer

Supplied parameter

Type:

Char

Length:

Value specified by Move_length.

The name of the buffer in the user address space to which data is copied.

Destination_ALET

Supplied parameter

Type:

Integer

Length:

Fullword

The ALET for the specified Destination_buffer in the user address space.

Source_buffer

Supplied parameter

Type:

Char

Length:

Value specified by Move_length.

The name of the buffer in the PFS from which data is copied.

Source_ALET

Supplied parameter

Type:

Integer

Length:

Fullword

The ALET for the specified Source_buffer in the PFS.

Destination_key

Supplied parameter

Type:

Integer

Length:

Fullword

The storage key for the Destination_buffer in the user address space. The specified key should be in the last 4 bits of the word. The key is typically the same value as the key stored in the UIO field UIO.u_key

Move_length

Supplied parameter

Type:

Integer

Length:

Fullword

The number of bytes to move.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyout service returns the results of the request, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_code parameters contain the values returned by the service.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyout service stores the return code. The osi_copyout service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see <u>Return</u> codes (errnos) in *z/OS UNIX System Services Messages and Codes*.

The osi_copyout operation supports the following error value:

Return_code

Explanation

EFAULT

A buffer address that was specified is not in addressable storage.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_copyout service stores the reason code. The osi_copyout service returns Return_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

- 1. The address of the osi_copyout routine is passed to the PFS in the OSIT structure when the PFS is initialized.
- 2. The storage key for the source buffer can be any storage key.

Related services

- "osi_uiomove Move data between PFS buffers and buffers defined by a UIO structure" on page 410
- "osi_copyin Move data from a user buffer to a PFS buffer" on page 357
- "osi_copy64 Move data between user and PFS buffers with 64-bit addresses" on page 363

Characteristics and restrictions

This routine must be used only on the dispatchable unit (task or SRB) that made the vnode or VFS call because the service requires the use of the cross-memory environment of the calling dispatchable unit.

osi_copy64 — Move data between user and PFS buffers with 64-bit addresses

Function

The osi_copy64 service moves a block of data in either direction between 64-bit addressed user and PFS buffers

Requirements

Operation Environment

Authorization: Supervisor state; any PSW key

Dispatchable unit mode: Task or SRB

Cross memory mode: Any

AMODE: 31- or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be 31-bit addressable by the caller and in the

primary address space.

Format

osi_copy64(copy64_struct, Workarea);

Parameters

copy64_struct

Supplied and returned parameter

Type:

Structure

Length:

Specified by the 64_length field

The parameters of this service are contained in the copy64_struct. See <u>"Usage notes" on page 364</u> for a description of the fields in this structure.

Workarea

Supplied parameter

Type:

Character

Length:

512 bytes

Workarea is a 512-byte buffer that resides below the 2GB line and is aligned on a doubleword boundary. It can be used by the service for dynamic storage.

Usage notes

- 1. The osi_copy64 service can be called in AMODE 31 or AMODE 64, and the buffers may be above or below the 2GB line. In all cases the full 64-bit addresses must be valid. In releases prior to z/OS V1R5, the osi_copy64 service may be called only in AMODE 31.
- 2. The size of the R1 address and of the parameter list addresses that it points to are assumed to correspond to the AMODE of the caller at the time of the call.
- 3. copy64_struct contains the following fields:

c64_sourcebuff

The source address for the copy. The source is always copied to the destination (c64_destbuff).

c64 destbuff

The destination address for the copy.

c64 direction

Specifies whether MVCSK (In) or MVCDK (Out) should be used.

c64_keybits

Contains the 4-bit key of the user's data.

c64_copylen

Specifies the length of the data to be copied. This is a 32-bit field.

c64 dontincrsrc

The source address will be incremented by the c64_copylen to facilitate looping calls, unless this flag is set.

64_dontincrdest

The destination address will be incremented by the c64_copylen to facilitate looping calls, unless this flag is set.

c64_gotrecovery

If the PFS has its own EFAULT recovery, you can avoid the overhead involved in the setting up and taking down of an FRR on each call to this service by setting this flag.

c64 rc

Indicates the success or failure of the operation, as described in this topic.

c64 rsn

Indicates the success or failure of the operation, as described in this topic.

c64 sourcealet

Contains the ALET of the source buffer.

c64 destalet

Contains the ALET of the destination buffer.

c64 length

Contains the length of the copy64_struct itself.

4. The results of the operation are returned in c64_rc as either:

0

The operation was successful, and c64_copylen bytes were moved.

Nonzero

The operation failed. This is the failing return code, and c64_rsn contains the failing reason code. The osi_copy64 service may return the following return code:

Return_code

Explanation

EFAULT

A specified buffer address is not in addressable storage.

- 5. The osi_copy64 routine is a high-performance routine. It does not issue program calls into the kernel.
- 6. If the PFS has no storage below the 2 GB line for the Workarea, the OSI WorkArea can be used.

Related services

- "osi_uiomove Move data between PFS buffers and buffers defined by a UIO structure" on page 410
- "osi_copyout Move data from a PFS buffer to a user buffer" on page 360
- "osi_copyin Move data from a user buffer to a PFS buffer" on page 357

Characteristics and restrictions

Whenever it is used to copy user address space areas, this routine must be used only on the dispatchable unit (task or SRB) that made the original vnode or VFS call because the service requires the use of the cross-memory environment of the calling dispatchable unit.

osi_ctl — Pass control information to the kernel

Function

The osi_ctl service passes control information to the kernel or to a file exporter exit in the kernel.

Requirements

| Operation | Environment |
|-------------------------|--------------------------------------|
| Authorization: | Problem or Supervisor state, any key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_ctl(Command,
Argument_length,
Argument,
Return_value,
Return_code,
Reason_code);
```

Parameters

Command

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the command code for this operation. The allowed command codes and their associated commands are as follows:

| Command code | Associated command | Notes |
|--------------|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | OSI_GLUECALL | Provides general communication between a file exporter and the exporter exit that was established during v_reg(). |
| 4 | OSI_UPDATEFILESYS | See <u>"BPXYPFSI"</u> on page 484. |
| 5 | OSI_REMOUNTSAMEMODE | Enables a PFS to remount a file system without changing the mount mode. |
| 6 | OSI_QSE | Allows the PFS to issue notifications that a file system is being quiesced in the PFS so that the LFS can also quiesce it in the LFS layer. |
| 7 | OSI_UQS | Allows the PFS to issue notifications that a file system is being unquiesced in the PFS so that the LFS can also unquiesce it in the LFS layer. |
| 8 | OSI_GETMNTSTATUS | Enables a PFS to obtain the LFS status of a file system. |
| 9 | OSI_DUB | Enables the PFS to dub and undub a worker task. |
| 10 | OSI_PFSSTATUS | Enables a PFS to provide PFS-specific status information to the logical file system. |
| 13 | OSI_TERMINATE | Enables the PFS to notify the LFS that the PFS is abnormally terminating. The LFS will terminate any task still in an active call to the PFS. |

These commands are defined in BPXYPFSI. See "BPXYPFSI" on page 484.

Argument_length

Supplied parameter.

Type:

Integer

Length:

Fullword

The name of a fullword that contains the length of the Argument.

Argument

Parameter supplied and returned

Type:

Defined by the receiver.

Length:

Specified by the Argument_length parameter

Specifies the address of a buffer, of length Argument_Length, that contains the argument of the operation. The Argument depends on the command, as follows:

- For OSI_GLUECALL, Argument is a buffer of variable length up to 256 bytes.
- For OSI_REMOUNTSAMEMODE, Argument is the osi_remnt structure in "BPXYPFSI" on page 484).
- For OSI_GETMNTSTATUS, Argument is the osi_getmntstat structure in "BPXYPFSI" on page 484.
- For OSI_DUB, Argument is a 4-byte integer whose value is either osi_dubtask or osi_undubtask. These fields are defined in "BPXYPFSI" on page 484.
- For OSI_PFSSTATUS, Argument is the osipfsstatus structure in the BPXYPFSI, PFS interface definitions. See "BPXYPFSI" on page 484.
- For OSI_QSE, Argument is the osi_quiesce_struct structure in BPXYPFSI, PFS interface definitions. See "BPXYPFSI" on page 484.

- For OSI_UQS, Argument is the osi_quiesce_struct structure in BPXYPFSI, PFS interface definitions. See "BPXYPFSI" on page 484.
- For OSI_TERMINATE, argument is the osi_term structure in BPXYPFSI, PFS interface definitions. See "BPXYPFSI" on page 484.

Specifies the name of a buffer, of length Argument_Length, that contains the argument of the operation.

The buffer can be modified to return information to the caller.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_ctl service returns 0 if the request is successful, and -1 if the request is not successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_ctl service stores the return code. The osi_ctl service returns Return_code only if Return_value is.-1 For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The return code may come from the exporter exit.

The osi_ctl service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | A supplied parameter is incorrect. |
| | Possible reason codes are: |
| | Nonregistered. The caller is not registered or is not a file exporter type. |
| | • Indoctrination. The command was not a supported value. |
| ENOENT | A matching file system was not found. |
| ENOMEM | A C environment cannot be obtained to invoke the exit. |
| EPERM | A task is already dubbed or undubbed. |
| | For OSI_DUB, if Argument is osi_dubtask and the task is already dubbed, the return value is returned as -1 and the reason code is JrAlreadyDubbed. |
| | If Argument is osi_undubtask and the task is already undubbed, the return value is -1 and the reason code is JrAlreadyUnDubbed. |
| ESRCH with JrPfsNotDubbed | The caller is not on a POSIX thread. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_ctl service stores the reason code. The osi_ctl service returns the reason code only if the return value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

The reason code may come from the exporter exit, in which case it would be documented with that product.

Usage notes

1. The OSI_GLUECALL command is provided for general communication between a file exporter and the exporter exit that was established during v_reg().

The argument buffer can be modified to convey information from the exit to the caller. The exit must not write in the argument buffer beyond the amount that was passed in by the caller. The caller and the exit should agree on the size of the argument, or should use an embedded length field to limit the amount of data that is moved to the argument buffer for output.

- If the amount of data to be transferred is more than the amount that is allowed by this service, the caller should use the argument to pass the address of a buffer that contains the data. The exit can use osi_copyin and osi_copyout to move data between the caller's address space and the kernel.
- 2. For OSI_GETMNTSTATUS, the PFS must fill in the mt_devno in osi_getmntstat_devno. The PFS must also fill in the eye catcher, version, buffer address, and buffer length. The buffer length must be at least as large as the length of an mnteh (header) plus the length of one mnte entry. The buffer pointed to by osi_getmntstat_bufferaddr does not need to be initialized. The length that was copied into the buffer is stored in osi_getmntstat_bufferlen as output.
 - OSI_GETMNTSTATUS performs an internal getmntent (BPX1GMN), and the osi_getmntstat_bufferaddr points to a buffer that will hold the output of that getmntent call, which includes an mnteh (header) and mnte, which are described in BPXYMNTE. If a file system was found matching the input osi_getmntstat_devno, the return_value will be zero and the buffer will contain an mnteh and the mnte entry for that file system. The PFS can examine fields in the mnte to determine the status of the file system. For example, mntentfstname will contain the PFS type name and mntentfsclient will indicate if LFS function-shipping or locally-mounted to PFS. The PFS should also check the mntentstatus flags to ensure the file system is valid. If no matching file system is found, the return_value is -1 and the return code is ENOENT.
- 3. For OSI_REMOUNTSAMEMODE, osi_remnt is the osi_remnt structure in "BPXYPFSI" on page 484. The PFS calls osi_ctl with osi_remountsamemode, passing the osi_remnt as the Argument. osi_remnt_name, osi_remnt_version, osi_remnt_devno and osi_remnt_pfsid must be filled in. The osi_remnt_devno identifies the file system. osi_remnt_pfsid is the pfsi_pfsid passed on initialization.
- 4. For OSI_DUB, if Argument is OSI_DUBTASK and the task is already dubbed, the return_value is returned as -1, and the return_code is EPERM with JrAlreadyDubbed. If Argument is OSI_UNDUBTASK and the task is already undubbed, the return_value is returned as -1, and the return_code is EPERM with JrAlreadyUnDubbed.
- 5. For OSI_PFSSTATUS, the parameter argument is specified as structure osi_pfsstatusinfo, which is documented in BPXYPFSI. osi_pfsstatus_linex contains the formatted text of 60 characters. (See "BPXYPFSI" on page 484.) In any part of the osi_pfsstatus_linex, if the first character is a null character, or if the entire line contains blanks, this indicates that there is no status on that line. The command D OMVS,PFS skips null or blank lines and displays only osi_pfsstatus_linex with status information.
- 6. For OSI_QSE, the argument is specified as structure osi_quiesce_struct, which is documented in BPXYPFSI. In the structure, the PFS sets the osi_quiesce_name to OSIQ, and osi_quiesce_version to OSI_QUIESCEV1. It sets osi_quiesce_devno to the mt_devno identifying the file system to be quiesced. It passes the process ID of the quiescing process in osi_quiesce_pid, and a unique quiesce

instance ID in osi_quiesce handle. The job name and system name of the quiesce owner is passed in osi_quiesce_jobname and osi_quiesce_sysname. The PFS passes its pfsi_pfsid in osi_quiesce_pfsid. The osi_quiesce_flags must be set to identify the quiesce reason. The PFS must have support for a vfs_pfsctl to allow notification to the PFS to unquiesce, passing the quiesce handle and file system name. Unquiesce might be necessary under certain exceptional conditions, such as PFS termination or the quiesce owner's system leaving the sysplex.

- 7. For OSI_UQS, the argument is specified as structure osi_quiesce_struct, which is documented in BPXYPFSI. In the structure, the PFS sets the osi_quiesce_name to OSIQ, and osi_quiesce version to OSI_QUIESCEV1. It sets osi_quiesce_devno to the mt_devno identifying the file system to be unquiesced.
- 8. For OSI_TERMINATE, the parameter argument is specified as a structure osi_term, which is documented in BPXYPFSI. The PFS must fill osi_term_pfsid. osi_term_pfsid is the pfsi_pfsid that is passed on initialization.

The PFS must also fill an eyecatcher, osi_term_name. The osi_term_name can be set to OSI_TERMID and osi_term_version can be set to OSI_TERMV1.

The osi_quiesce_handle must be passed and must match the osi_quiesce_handle that was passed on the quiesce, unless it is FFFFFFF hex, which is a force unquiesce. If the PFS wants the LFS to perform quiesce handle validation only and not proceed with the unquiesce, it should set flag osi_quiesce_checkonly.

Characteristics and restrictions

None.

osi_getcred — Obtain SAF UIDs, GIDs, and supplementary GIDs

Function

The osi_getcred service obtains the real, effective, and saved user IDs, group IDs, and supplementary group IDs from System Authorization Facility (SAF).

Requirements

| O +: | F |
|-----------|-------------|
| Operation | Environment |
| | |

Authorization: Supervisor state, any PSW key

Dispatchable unit mode: Task
Cross memory mode: Any

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and, except for the

Getcred_Parms and area for the supplemental GIDs, must be in the

primary address space.

Format

osi_getcred(OSI_structure, Workarea, Alet, Getcred_Parms, Return_value, Return_code,
Reason_code);

Parameters

Alet

Supplied parameter

Type:

Integer

Length:

Fullword

The Alet for the Getcred_Parms structure and the supplementary GID list that is pointed to by Getcred_Parms.

Getcred_parms

Supplied parameter

Type:

Structure

Length:

Specified by sizeof(OGCDPRM)

An area that contains the osi_getcred parameters. It may reside above the bar when the caller is AMODE=64. The entries in this area are mapped by the OGCDPRM typedef, which is defined in the BPXYPFSI header.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure. Following is a description of the parameters in this structure:

| Parameter | Description |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| oc_effective_gid | The effective GID, returned by the security product. |
| oc_effective_uid | The effective UID, returned by the security product. |
| oc_gid_list | A pointer to an area to contain the array of supplementary GIDs. It is a 31-bit pointer, regardless of the caller's AMODE. |
| oc_hdr | A header that contains an eyecatcher and length. It can be initialized using OGCDPRM_HDR. |
| oc_maxsgids | Set by the invoker to the maximum number of supplementary GIDs that will fit in the area that is pointed to by oc_gid_list. If there is not enough room for all available GIDs, this maximum is returned. In this case, this field is updated, on return to the caller, to indicate the total number of GIDs which could have been returned had there been room for all. |
| oc_numsgids | The number of supplementary GIDs returned by the security product. |
| oc_real_gid | The real GID, returned by the security product. |
| oc_real_uid | The real UID, returned by the security product. |
| oc_saved_gid | The saved GID, returned by the security product. |
| oc_saved_uid | The saved UID, returned by the security product. |

OSI structure

Supplied parameter

Type:

Structure

Length:

Specified by the Osilen field

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_getcred service stores the reason code. The osi_getcred service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. .

If the Return_code that is returned by osi_getcred is EMVSSAF2ERR, the low-order two bytes of the Reason_code will be the RACF return and reason codes.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_getcred service stores the return code. The osi_getcred service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_getcred service returns the results of the service, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_code parameters contain the values that are returned by the service.

0

The operation was successful, and there was room for all supplementary GIDs in the caller-provided area.

+1

The operation was successful, but there were more supplementary GIDs than could fit in the caller-provided area. A partial list of GIDs has been returned. The oc_maxsgids field has been updated with the actual number of supplementary GIDs that are available. The oc_maxsgids field should be reset to the proper value, if necessary, before the Getcred_Parms structure is used again on a subsequent call.

Workarea

Supplied parameter

Type:

Char

Length:

3 K

Workarea is a buffer aligned on a doubleword boundary. It must reside below the bar.

Usage notes

- 1. The osi getcred calls SAF to obtain the UID and GID information.
- 2. If there is not room in the supplementary GID area, SAF returns as many as will fit. A return value of 1 indicates that this has occurred. In this case, the oc_maxsgids field is updated with the number that would have been returned had there been room for all supplementary GIDs. The caller should not depend upon those GIDs that are returned when there is not enough room for all supplementary GIDs. The subset of the available GIDs that is returned may differ among various security products, or even from call to call for some security products.
- 3. The OSI_structure contains an area that is pointed to by osi_workarea, which may be passed to this service as the Workarea parameter.

Related services

None.

Characteristics and restrictions

None.

osi_getvnode — Get or return a vnode

Function

The osi_getvnode service is used by a PFS to create a vnode or return a vnode that it created but never used.

Requirements

| Operation | Environment |
|-------------------------|-----------------------------|
| Authorization: | Supervisor state, PSW key 0 |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_getvnode(Entry_code,
	Token_structure,
	attribute_structure,
	PFS_token,
	Vnode_token,
	Return_value,
	Return_code,
	Reason_code);
```

Parameters

Entry_code

Supplied parameter

Type:

Integer

Length:

Fullword

Entry_code specifies the function that is being requested for the osi_getvnode service.

| Entry_code | Explanation |
|-----------------|-----------------------------------------------------|
| OSI_BUILDVNOD | Get a vnode |
| OSI_BUILDVNODNL | Get a vnode that is never locked by the LFS. |
| OSI_RTNVNOD | Return an unused vnode. |
| OSI_BUILDVNODXL | Get a vnode that is always under an exclusive lock. |
| OSI_PURGELLA | Purge LLA entries for a vnode. |
| OSI_INACTASAP | Deactivate a vnode as soon as possible. |
| OSI_MEMCRITICAL | PFS requests memory relief for its file systems. |
| OSI_STALEVNODE | Indicate that a file is no longer usable. |

Token_structure

Supplied parameter

Type:

TOKSTR

Length:

Specified by TOKSTR.ts_hdr_cblen.

This token_structure is the one that was passed to the vnode or VFS operation from which this call is being made. It represents the parent file or file system of the file for which a vnode is being created. This parameter is 0 for OSI_PURGELLA and OSI_INACTASAP.

attribute_structure

Supplied parameter

Type:

Structure

Length:

Specified by the attr.cbhdr.cblen field of the structure.

The file attributes of the file for which this vnode is being created. This structure is mapped by typedef ATTR in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465).

PFS_token

Supplied parameter

Type:

Token

Length:

8

The PFS token for the file for which this vnode is being created.

Vnode token

Returned parameter for entry code OSI_BUILDVNOD, OSI_BUILDVNODXL, and OSI_BUILDVNODNL; supplied parameter for entry code OSI_RTNVNOD, OSI_PURGELLA, and OSI_INACTASAP.

Type:

Token

Length:

8

The vnode token for the file.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_getvnode service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_getvnode service stores the return code. The osi_getvnode service can return one of the following values in the Return_code parameter only if Return_value is -1. Reason_code further qualifies the Return_code value.

Return_codeExplanation0Successful completionOsi_BadParmInvalid OSI_structureOsi_AbendAbend in osi_getvnode

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_getvnode service stores the reason code. The osi_getvnode service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

- 1. For additional information, see "Creating, referring to, and inactivating file vnodes" on page 29.
- 2. The PFS should use the OSI_RTNVNOD function to return an unused vnode only when it gets a vnode, but decides it does not need it, before returning the vnode token to the LFS.

The Token_structure, attribute_structure, and PFS_token parameters are not referenced for OSI_RTNVNOD, and the PFS may pass a zero for each parameter.

- 3. The address of the osi_getvnode routine is passed to the PFS in the OSIT when the PFS is initialized.
- 4. OSI_BUILDVNODNL is used when the PFS does not need the vnode serialization provided by the LFS. A vnode that is obtained in this way is locked only for vn_open and vn_close.
- 5. The PFS may pass a minimum File_Attribute_Structure, for performance reasons. This structure must include:

at_hdr.cbid

Set to ATT2 to distinguish this subset ATTR

at hdr.cblen

Set to the correct length

at mode

The file type field, at least

at ino

at_major

at_minor

at genvalue

The LFS bits, at least

at_fic

- 6. No Token_structure is required on an OSI_PURGELLA or OSI_INACTASAP request. This parameter may be 0.
- 7. The PFS can use OSI_STALEVNODE to tell the LFS that a file is no longer usable. After this call, the LFS will not allow new vnode operations. The PFS must continue to handle any operations already in progress at least well enough to fail the operation until the vnode is inactivated.

For a sysplex-aware PFS, this call must be made to the LFS on all systems in the sysplex. Any future vn_lookup call for the old file name or vfs_vget call for the old FID should return a new vnode. The PFS must also ensure that the target vnode cannot be deactivated while processing the OSI_STALEVNODE request. While it is processing an OSI_STALEVNODE request, the PFS must reject any vn_inact calls for that vnode.

Characteristics and restrictions

- 1. This routine can be called only for a vnode or VFS operation that returns a vnode token on the interface —for example, vn_lookup.
- 2. This routine must be used only on the task that made the vnode or VFS call, with the exception of the OSI_INACTASAP requests. OSI_INACTASAP requests can be invoked on a physical file system worker task; no serialization is necessary for these operations.
- 3. OSI_MEMCRITICAL is not a vnode-related function. Only the Token_Structure is used as input. The PFS should first check the PFS initialization block (PFSI) to see if the OSI_MEMCRITICAL function is supported. If it is, the PFS may use it to request memory relief by requesting that LFS clean up the vnode cache quickly. The PFS will also be called to harden its cached data to disk for each of its mounted file systems, using vfs_sync. To indicate the completion of this LFS memory-critical function, LFS will set the ts_sysd1 field to OSI_MEMCRITICAL for the last vfs_sync operation.

osi_kipcget — Query interprocess communications

Function

The osi_kipcget service queries shared memory, messages, and semaphors for the "next or specified member".

It is a secondary interface to the w_getipc service and is provided for use by a PFS that is running in a colony address space. For information about the w_getipc service, see w_getipc (BPX1GET, BPX4GET)

— Query interprocess communications in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Requirements

Operation

| - | |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state; any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| | |

Environment

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Buffer_address

Supplied parameter

Type:

Address

Length:

Fullword or doubleword, depending on the AMODE.

Address of the buffer structure that is defined by IPCQ. For the structure that describes this buffer, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

Buffer_Length

Supplied parameter

Type:

Integer

Length:

Fullword

Length of the structure that is defined by IPCQ. This parameter is set to IPCQ#LENGTH. Field IPCQLENGTH differs from IPCQ#LENGTH when the system call is at a different level than the included IPCQ. An error is returned if this length is less than 4. The buffer is filled to the lesser of IPCQ#LENGTH or the value that is specified here.

Command

Supplied parameter

Type:

Integer

Length:

Fullword

| Command | Description |
|-----------|-----------------------------------------------------------------------------------|
| Ipcq#ALL | Retrieve next shared memory, message, and semaphore member. |
| Ipcq#MSG | Retrieve next message member. |
| Ipcq#SEM | Retrieve next semaphore member. |
| Ipcq#SHM | Retrieve next shared memory member. |
| Ipcq#0VER | Overview of system variables. Ignores the value of the first operand (Ipc_Token). |

Ipc_Member_ID

Supplied parameter

Type:

Integer

Length:

Word

Specifies a message queue ID, semaphore ID, or shared member ID.

Ipc_Token

Supplied parameter

Type:

Integer

Length:

Word

Specifies a token that corresponds to a message queue, shared memory segment, or semaphore member ID. Zero represents the first member ID. The token that is to be used in the next invocation is passed back in Return_value. Ipc_Token is ignored when Ipc_OVER is specified.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kipcget service stores the reason code. The osi_kipcget service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kipcget service stores the return code. The osi_kipcget service returns Return_code only if Return_value is -1. The osi_kipcget service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINVAL | One of the following errors occurred: |
| | The Ipc_Member_ID is not valid for the command that was specified. |
| | The Command parameter is not a valid command. |
| | • The buffer pointer was zero; or the buffer length was less than 4. |
| | The following reason codes can accompany the return code: JRBuffTooSmall, JRIpcBadID, or JRBadEntryCode. |
| EFAULT | An input parameter specified an address that caused the callable service to program check. The following reason code can accompany the return code: JRBadAddress. |

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kipcget service returns the next Ipc_Token (a negative number), 0, or -1 (error). If Ipc_Token is specified, 0 indicates end of file. If Ipc_Member_ID is specified, 0 indicates success.

Usage notes

- 1. With Ipc_Token, return_values should be tested for 0 (end of file) or -1 (error). Other values are negative and will be the next Ipc_Token.
- 2. With Ipc_Member_ID, return_values should be tested for -1 (error).
- 3. A member's accessibility can change if the permissions are changed.
- 4. A given Ipc_Token may not always retrieve the same member.
- 5. If a specific member is desired and was found using Ipc_Token, subsequent requests may place it at that token or later (never earlier).
- 6. The address of the osi_kipcget routine is passed to the PFS in the OSIT structure when the PFS is initialized.

Related services

None.

Characteristics and restrictions

This service is invoked only from a colony address space.

osi_kmsgctl — Perform message queue control operations

Function

The osi_kmsgctl service provides various message control operations as specified by command. These functions include reading and changing message variables within the MSQID_DS data structure and removing a message queue from the system.

This is a secondary interface to the msgctl service. It is provided for use by a PFS running in a colony address space. For information about the msgctl service, see msgctl (BPX1QCT, BPX4QCT) — Perform message queue control operations in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Requirements

| Operation | Environment |
|-----------|-------------|
|-----------|-------------|

Authorization: Supervisor state or problem state; any PSW key

Dispatchable unit mode: Task
Cross memory mode: Any

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Buffer

Parameter supplied and returned

Type:

Address

Length:

Fullword or doubleword, depending on the AMODE.

The name of the fullword that contains the address of the buffer into which or from which the message queue information is to be copied. This buffer is mapped by MSQID_DS.

Command

Supplied parameter

Type:

Integer

Character set:

N/A

Length:

Fullword

The name of a fullword field that indicates the message command that is to be executed. For the structure that contains these constants, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*. The values for Command are:

Ipc_RMID

Remove the message identifier that is specified by Message_Queue_ID from the system, and destroy the message queue and MSQID_DS data structure that are associated with it. This Command can only be executed by a process that has an effective user ID equal to either that of a process with appropriate privileges, or the value of IPC_CUID or IPC_UID in the MSQID_DS data structure that is associated with Message Queue ID.

Ipc_SET

Set the value of the IPC_UID, IPC_GID, IPC_MODE and MSG_QBYTES for associated Message_queue_ID. The values that are to be set are taken from the MSQID_DS data structure that is pointed to by argument Buffer. Any value for IPC_UID and IPC_GID can be specified. Only mode bits that are defined by BPX1QGT under the Message_Flag argument can be specified in the IPC_MODE field. This command can only be executed by a task that has an effective user ID equal to either that of a task with appropriate privileges, or the value of IPC_CUID or IPC_UID in the MSQID_DS data structure that is associated with Message_Queue_ID. This information is taken from the buffer that is pointed to by the Buffer parameter. For the data structure, see MSQID_DS DSECT.

Ipc_STAT

This command obtains status information about the message queue that is identified by the Message_Queue_ID parameter, if the current process has read permission. This information is stored in the area that is pointed to by argument Buffer and mapped by area MSQID_DS data structure. For the data structure, see MSQID_DS DSECT.

Message_Queue_ID

Supplied parameter

Type:

Integer

Length:

Fullword

Specifies the message queue identifier.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgctl service stores the reason code. The osi_kmsgctl service returns Reason_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgctl service stores the return code. The osi_kmsgctl service returns Return_code only if Return_value is -1. see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The osi_kmsgctl service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | The command specified was Ipc_STAT, and the calling process does not have read permission. The following reason code can accompany the return code: JRIpcDenied. |
| EINVAL | One of the following errors occurred: |
| | Message_Queue_ID is not a valid Message queue identifier |
| | The Command parameter is not a valid command. |
| | The mode bits were not valid (SET). |
| | The following reason codes can accompany the return code: JRIpcBadFlags, JRMsqQBytes, or JRIpcBadID. |
| EPERM | The command specified was Ipc_RMID or Ipc_SET, and the effective user ID of the caller is not that of a process with appropriate privileges, and is not the value of IPC_CUID or IPC_UID in the MSQID_DS data structure that is associated with Message_Queue_ID. |
| | The command specified was Ipc_SET, and an attempt is being made to increase MSG_QBYTES. The effective user ID of the caller does not have superuser privileges. The following reason codes can accompany the return code: JRIpcDenied or JRMsqQBytes. |
| EFAULT | The Buffer parameter specified an address that caused the syscall to program check. The following reason code can accompany the return code: JRBadAddress. |

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgctl service returns -1 or 0.

Usage notes

- Changing the access permissions only affects message queue syscall invocations that occur after msgctl has returned. msgsnd and msgrcv, which are waiting while the permission bits are changed by msgctl, are not affected.
- 2. Ipc_SET can change permissions, and might affect the ability of a thread to use the next message queue syscall.
- 3. Quiescing a message queue stops additional messages from being added, while allowing existing messages to be received. A message queue can be quiesced by clearing (Ipc_SET) write permission bits.

- 4. A message queue can also be quiesced by reducing MSG_QBYTES (Ipc_SET) to zero. (Note: it would take superuser authority to reraise the limit.) Requesters are told EAGAIN or wait.
- 5. When a message queue ID is removed (Ipc_RMID) from the system, all waiting threads regain control with RV=-1, RC=EIDRM, and RC=JRIpcRemoved.
- 6. If you do not want to change all the fields, first initialize (Ipc_STAT) the buffer, change the desired fields, and then make the change (Ipc_SET).
- 7. For Command Ipc_RMID, the remove is complete by the time control is returned to the caller.

Related services

"osi_kmsgget — Create or find a message queue" on page 382

Characteristics and restrictions

This service is invoked only from a colony address space.

The caller is restricted by ownership, read, and read/write permissions that are defined by OSI_kmsgget and OSI_kmsgctl Ipc_SET.

osi_kmsgget - Create or find a message queue

Function

The osi_kmsgget service returns a message queue ID.

This service is a secondary interface to the msgget service. It is provided for use by a PFS running in a colony address space. For information about the msgget service, see msgget (BPX1QGT, BPX4QGT) — Create or find a message queue in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------|
| Authorization: | Supervisor state or problem state; any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL osi_kmsgget,(Key,

Message_Flag,
Return_value,
Return_code,
Reason_code)
```

Parameters

Kev

Supplied parameter

Type:

Integer

Length:

Fullword

Identification for this message queue. This is a user-defined value that serves as a lookup value to determine whether this message queue exists, or the reserved value Ipc_PRIVATE.

Message_Flag

Supplied parameter

Type:

Integer

Length:

Fullword

Valid values for this field include any combination of the following (additional bits cause an EINVAL):

Ipc_CREAT

Creates a message queue if the key that is specified does not already have an associated ID. Ipc_CREATE is ignored when Ipc_PRIVATE is specified.

Ipc_EXCL

Causes the msgget function to fail if the key that is specified has an associated ID. Ipc_EXCL is ignored when Ipc_CREAT is not specified, or when Ipc_PRIVATE is specified.

S IRUSR

Permits the process that owns the message queue to read it.

S_IWUSR

Permits the process that owns the message queue to alter it.

S_IRGRP

Permits the group that is associated with the message queue to read it.

S IWGRP

Permits the group that is associated with the message queue to alter it.

S IROTH

Permits others to read the message queue.

S IWOTH

Permits others to alter the message queue.

The values that begin with an Ipc_ prefix are defined in BPXYIPCP, and are mapped onto S_TYPE, which is in BPXYMODE.

The values that begin with an S_I prefix are defined in BPXYMODE, and are a subset of the access permissions that apply to files.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgget service stores the reason code. The osi_kmsgget service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgget service stores the return code. The osi_kmsgget service returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes. The osi_kmsgget service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EACCES | A message queue identifier exists for the Key parameter, but operation permission, as specified by the low-order 9-bits of the Message_Flag parameter, is not granted (the "S_" items). The following reason code can accompany the return code: JRIpcDenied. |
| EEXIST | A message queue identifier exists for the Key parameter, and both Ipc_CREAT and Ipc_EXCL are specified. The following reason code can accompany the return code: JRIpcExists. |
| EINVAL | The Message_Flag operand included bits that are not supported by this function. The following reason code can accompany the return code: JRIpcBadFlags. |
| ENOENT | A message queue identifier does not exist for the Key parameter, and Ipc_CREAT was not set. The following reason code can accompany the return code: JRIpcNoExist. |
| ENOSPC | The system limit of the number of message queue IDs has been reached. The following reason code can accompany the return code: JRIpcMaxIDs. |

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgget service returns -1 or the message queue identifier.

Usage notes

- 1. If the thread knows the message queue ID, it can issue a msgctl, msgsnd, or msgrcv. msgget is not needed.
- 2. This function returns the message queue identifier that is associated with the Key parameter.
- 3. This function creates a data structure, which is defined by MSQID_DS, if one of the following is true:
 - The Key parameter is equal to Ipc_PRIVATE.
 - The Key parameter does not already have a message queue identifier that is associated with it, and Ipc_CREAT is set.
- 4. Upon creation, the data structure that is associated with the new message queue identifier is initialized as follows:

- Ipc_CUID and Ipc_UID are set to the effective user ID of the calling task.
- Ipc_CGID and Ipc_GID are set to the effective group ID of the calling task.
- The low-order 9-bits of Ipc_MODE are equal to the low-order 9-bits of the Message_Flag parameter.
- MSG_QBYTES is set to the system limit that is defined by parmlib.
- 5. The message queue is removed from the system when BPX1QCT (msgctl) is called with command Ipc_RMID.
- 6. Users of message queues are responsible for removing them when they are no longer needed. Failure to do so ties up system resources.

Related services

• "osi_kmsgctl — Perform message queue control operations" on page 379

Characteristics and restrictions

- 1. This service is invoked from a colony address space.
- 2. There is a maximum number of message queues that are allowed in the system.

3. The caller is restricted by ownership, read, and read/write permissions that are defined by OSI_kmsgget and OSI_kmsgctl Ipc_SET.

osi kmsgrcv – Receive from a message queue

Function

The osi_kmsgrcv service receives a message from a message queue.

This service is a secondary interface to the msgrcv service. It is provided for use by a PFS that is running in a colony address space. For information about the msgrcv service, see msgrcv (BPX1QRC, BPX4QRC) — Receive from a message queue in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------------------------------------------------|
| Authorization: | Supervisor state or problem state; any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary address space. |

Format

Parameters

Message_Address

Supplied parameter

Type:

Address

Length:

Fullword or doubleword, depending on the AMODE.

The name of a field that contains the address of a buffer that is mapped by MSGBUF or MSGXBUF. For more information, see <u>Mapping macros</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

Message_Alet

Supplied parameter

Type:

Integer

Length:

Fullword

The name of the fullword that contains the ALET for Message_Address, which identifies the address space or data space in which the buffer resides.

Specify a Message_Alet of 0 if the buffer resides in the user's address space (current primary address space).

Specify a Message_Alet of 2 if the buffer resides in the home address space.

If a value other than 0 or 2 is specified for the Message_ALET, the value must represent a valid entry in the dispatchable unit access list (DUAL).

Message_Flag

Supplied parameter

Type:

Integer

Length:

Fullword

MSG_NOERROR specifies that the received message is to be truncated to Message_Length (mapped in BPXYMSG). The truncated part of the message is lost, and no indication of the truncation is given to the caller.

MSG_INFO specifies that the received message is to be of the MSGXBUF and not the MSGBUF format mapped in BPXYMSG. MSG_INFO specifies that extended information is to be received, which is similar to the msgxrcv() C language function.

Ipc_NOWAIT specifies the action that is to be taken if a message of the desired type is not on the queue, as follows:

- If Ipc_NOWAIT is specified, the caller is to return immediately with an error (ENOMSG).
- If Ipc_NOWAIT is not specified, the calling thread is to suspend execution until one of the following occurs:
 - A message of the desired type is placed on the queue.
 - The message queue is removed from the system (EIDRM).
 - The caller receives a signal (EINTR).

Message_Length

Supplied parameter

Type:

Integer

Length:

Fullword

Specifies the length of the message text that is to be placed in the buffer that is pointed to by Message_Address parameter. If Msg_Info is specified, this buffer is 20 bytes longer than Message_Length; otherwise this buffer is 4 bytes longer than Message_Length. The message that is received might be truncated (see MSG_NOERROR of Message_Flag). A value of zero with MSG_NOERROR is useful for receiving the message type without the message text.

Message_Queue_ID

Supplied parameter

Type:

Integer

Length:

Fullword

Specifies the message queue identifier.

Message_Type

Supplied parameter

Type:

Integer

Length:

Fullword or doubleword, depending on the AMODE.

Specifies the type of message that is requested, as follows:

- If Message_Type is equal to zero, the first message on the queue is received.
- If Message_Type is greater than zero, the first message of Message_Type is received.
- If Message_Type is less than zero, the first message of the lowest type that is less than or equal to the absolute value of Message_Type is received.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgrcv service returns -1, or the number of MSG_MTEXT bytes returned.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgrcv service stores the return code. The osi_kmsgrcv service returns Return_code only if Return_value is -1. See <u>z/OS UNIX System Services Messages and Codes</u> for a complete list of possible return code values. The osi_kmsgrcv service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| E2BIG | MSG_MTEXT is greater than Message_Length, and MSG_NOERROR is not set. The following reason code can accompany the return code: JRMsq2Big. |
| EACCES | Operation permission is denied to the calling task. The following reason code can accompany the return code: JRIpcDenied. |
| EIDRM | The Message_Queue_ID was removed from the system while the invoker was waiting. The following reason code can accompany the return code: JRIpcRemoved. |
| EINTR | The function was interrupted by a signal. The following reason code can accompany the return code: JRIpcSignaled. |
| EINVAL | Message_Queue_ID is not a valid message queue identifier; or the Message_Length parameter is less than 0. The following reason codes can accompany the return code: JRIpcBadID or JRMsqBadSize. |
| EFAULT | The Message_Address parameter specified an address that caused the syscall to program check. The following reason code can accompany the return code: JRBadAddress. |
| ENOMSG | The queue does not contain a message of the desired type, and Ipc_NOWAIT is set. The following reason code can accompany the return code: JRMsqNoMsg. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgrcv service stores the reason code. The osi_kmsgrcv service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. Within the type specifications, the longest waiting thread is reactivated first (FIFO). For example, if there are two threads waiting on message type 3 and one thread waiting on message type 2, when a message send for type 3 occurs, the oldest waiter for message type 3 receive is posted first.
- 2. Read access to the specified message queue is required.

Related services

• "osi_kmsgctl — Perform message queue control operations" on page 379

- "osi_kmsgget Create or find a message queue" on page 382
- "osi_kmsgsnd Send a message to a message queue" on page 389

Characteristics and restrictions

- This service is invoked only from a colony address space.
- There is a maximum number of message queues that are allowed in the system.
- The caller is restricted by ownership, read, and read/write permissions that are defined by OSI_kmsgrcv and OSI_kmsgctl Ipc_SET.

osi_kmsgsnd — Send a message to a message queue

Function

The osi_kmsgsnd service sends a message to a message queue.

This service is a secondary interface to the msgsnd service. It is provided for use by a PFS that is running in a colony address space. For information about the msgsnd service, see msgsnd (BPX1QSN, BPX4QSN) — Send to a message queue in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

Requirements

Interrupt status:

| Environment |
|------------------------------------------------|
| Supervisor state or problem state; any PSW key |
| Task |
| Any |
| 31-bit or 64-bit |
| Any |
| |

Enabled for interrupts Unlocked Locks:

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
CALL osi_kmsgsnd,(Message_Queue_ID,
                  Message_address,
                  Message_Alet,
Message_Size,
Message_Flag,
                  Return_value,
                  Return_code,
                  Reason_code)
```

Parameters

Message_address

Supplied parameter

Type:

Address

Length:

Fullword or doubleword, depending on the AMODE.

The name of a field that contains the address of the message that is to be sent. This area is mapped by MSGBUF and is AMODE-dependent. The message type is the first word of the message, and must be greater than zero.

Message_Alet

Supplied parameter

Type:

Integer

Length:

Fullword

The name of the fullword that contains the ALET for Message_address that identifies the address space or data space in which the buffer resides.

Specify a Message_Alet of 0 if the buffer resides in the user's address space (current primary address space).

Specify a Message_Alet of 2 if the buffer resides in the home address space.

If a value other than 0 or 2 is specified for the Message_Alet, the value must represent a valid entry in the dispatchable unit access list (DUAL).

Message_Flag

Supplied parameter

Type:

Integer

Length:

Fullword

Specifies the action that is to be taken if one or more of the following are true:

- Placing the message on the message queue would cause the current number of bytes on the message queue (msg_cbytes) to be greater than the maximum number of bytes that are allowed on the message queue (msg_qbytes).
- The total number of messages on the message queue (msg_qnum) is equal to the system-imposed limit.

The actions that are taken are as follows:

- If Ipc NOWAIT is specified, the caller returns immediately with an error (EAGAIN).
- If Ipc_NOWAIT is not specified, the calling thread suspends execution until one of the following events occurs:
 - The message is sent.
 - The message queue is removed from the system (EIDRM).
 - The caller receives a signal (EINTR).

Message Queue ID

Supplied parameter

Type:

Integer

Character set:

N/A

Length:

Fullword

Specifies the message queue identifier.

Message_Size

Supplied parameter

Type:

Integer

Length:

Fullword

Specifies the length of the message text that is pointed to by the Message_address parameter. The length does not include the 4-byte type that precedes the message text. For example, a message with a MSG_TYPE and no MSG_MTEXT has a Message_Size of zero.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgsnd service stores the reason code. The osi_kmsgsnd service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgsnd service stores the return code. The osi_kmsgsnd service returns Return_code only if Return_value is -1. The osi_kmsgsnd service can return one of the following values in the Return_code parameter:

| 5 = 1 | |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Return_code | Explanation |
| EACCES | Operation permission is denied to the calling task. The following reason code can accompany the return code: JRIpcDenied. |
| EAGAIN | The message cannot be sent, and Message_Flag is set to Ipc_NOWAIT. The following reason codes can accompany the return code: JRMsqQueueFullMessages, JRMsqQueueFullBytes. |
| EIDRM | The Message_Queue_ID was removed from the system while the invoker was waiting. The following reason code can accompany the return code: JRIpcRemoved. |
| EINTR | The function was interrupted by a signal, and the message was not sent. The following reason code can accompany the return code: JRIpcSignaled. |
| EINVAL | Message_Queue_ID is not a valid message queue identifier; the value of MSG _TYPE is less than 1; or the value of Message_Size is less than zero or greater than the system-imposed limit. The following reason codes can accompany the return code: JRIpcBadID, JRMsqBadSize, or JRMsqBadType. |

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EFAULT | The Message_address parameter specified an address that caused the syscall to program check. The following reason code can accompany the return code: JRBadAddress. |
| ENOMEM | There are not enough system storage exits to send the message; the message was not sent. The following reason code can accompany the return code: JrSmNoStorage. |

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_kmsgsnd service returns -1 or 0. The message was sent unless a -1 is received.

Usage notes

AMODE: 31-bit or 64-bit

Related services

- "osi_kmsgget Create or find a message queue" on page 382
- "osi_kmsgctl Perform message queue control operations" on page 379
- "osi_kmsgrcv Receive from a message queue" on page 385

Characteristics and restrictions

- 1. Invoke this service from a colony address space.
- 2. The caller is restricted by ownership, read, and read/write permissions that are defined by OSI_kmsgsnd and OSI_kmsgctl Ipc_SET.

osi_mountstatus — Report file system status to LFS

Function

The osi_mountstatus service is used by a PFS to indicate to the LFS a change in the status of a file system, such as completion of an asynchronous mount operation.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------|
| Authorization: | Problem or supervisor state; any PSW key |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_mountstatus(Entry_code,
StDev,
Return_value,
Return_code,
Reason_code);
```

Parameters

Entry_code

Supplied parameter

Type:

Integer

Length:

Fullword

Entry_code specifies the function that is being requested for the osi_mountstatus service.

Entry_code

Explanation

OSI_MOUNTCOMPLETE

Mount complete

StDev

Supplied parameter

Type:

Integer

Length:

Fullword

This is a copy of MTAB.mt_stdev that is passed by the LFS on the original vfs_mount. It identifies the file system for which status is being reported.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_mountstatus service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful.

0

The operation was successful.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_mountstatus service stores the return code. The osi_mountstatus service can return the following value in the Return_code parameter only if Return_value is -1. Reason_code further qualifies the Return_code value.

Return_code Explanation

EINVAL Parameter error. Consult Reason_code to determine the exact reason the error occurred. The following reason codes can accompany the return code: JRIsMounted, JRBadStDev.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_mountstatus service stores the reason code. The osi_mountstatus service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

- 1. For the OSI_MOUNTCOMPLETE Entry_code:
 - The PFS uses this entry code to inform the LFS of the completion of a mount operation that was previously identified as asynchronous. The LFS calls vfs_mount again to complete the mount. See "Asynchronous mounting" on page 27.
 - If the PFS has a Return_value, Return_code, and Reason_code to present, indicating the status of the mount, they must be returned to the LFS at the time vfs_mount is called again.
- 2. The address of the osi_mountstatus routine is passed to the PFS in the OSIT when the PFS is initialized.

osi_post — Post an OSI waiter

Function

The osi_post service posts a process that is waiting in osi_wait.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------|
| Authorization: | Problem or supervisor state, any PSW key |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |

Operation Environment

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

OSI_post_token

Supplied parameter

Type:

Token

Length:

24

OSI_post_token is the post token that is saved from the OSI_structure of the task that is to be posted.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

Return code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_post service stores the return code. The osi_post service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|-------------|-----------------------|
| 0 | Successful completion |
| Osi_BadParm | Invalid OSI_structure |
| Osi_Abend | Abend in osi_post |

Usage notes

- 1. For additional information, see "Waiting and posting" on page 20.
- 2. The task that is posted is the task that is represented by OSI_post_token. Before a PFS uses OSI_wait, it should copy the OSI_post_token from the OSI structure to a place that is addressable by the task that performs the OSI_post. The storage for the OSI for the waiting task is freed if the task terminates.
- 3. The PFS must never call OSI_post for a waiting process more than once, and it should have sufficient logic and recovery to avoid calling OSI_post for a task that is no longer waiting.
- 4. The address of the osi_post routine is passed to the PFS in the OSIT structure when the PFS is initialized.

Related services

• "osi_wait — Wait for an event to occur" on page 415

osi_sched — Schedule async I/O completion

Function

The osi_sched service schedules the completion of an asynchronous request.

Requirements

Operation Environment

Authorization: Problem or Supervisor state, any key

Dispatchable unit mode: Task or SRB

Cross memory mode: Any

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Saved_Osi_AsyTok

Supplied parameter

Type:

Token

Length:

8 bytes

The name of the field that contains the osi_asytok value that was saved by the PFS during Part 1 of the asynchronous vnode operation that is now completing.

Return_value

Supplied and returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the PFS passes the results of Part 1 of the asynchronous operation, and the LFS returns the results of the scheduling.

On input to osi_sched, one of the following return values is returned:

0 or greater

The request is successful.

The LFS invokes the PFS for Part 2 of the asynchronous operation.

If the user has requested a preprocessing exit call, this value is passed to the exit before Part 2 is invoked.

On receive-type operations, the PFS should pass the actual length of the data that is to be received, if it can do so at this point. This allows a preprocessing exit to allocate smaller buffers than the size that was originally specified at the beginning of the operation. If this value cannot be passed to osi_sched, a Return_value of 0 should be used, and the exit will allocate buffers to accommodate the amount that was originally requested. For more information about those operations, see asyncio (BPX1AIO, BPX4AIO) — Asynchronous I/O for sockets in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

-1

The request has failed.

The LFS does not invoke the PFS for Part 2 of the asynchronous operation.

The Return_value, Return_code, and Reason_code are passed back to the user as the results of the operation.

If the PFS has resources to free that cannot be freed by the caller of osi_sched, or if for any other reason Part 2 needs to be called, it should set Return_value to 0 and report the failure of the user's operation as output from Part 2.

On output from osi_sched, one of the following return values is returned:

0

The scheduling was successful.

The LFS invokes the PFS for Part 2 of the asynchronous operation based on the input Return_value.

If Part 2 cannot be run because of process termination, the PFS gets a vn_cancel instead.

-1

The Saved_Osi_AsyTok value was not recognized.

The LFS always accepts valid calls to osi_sched. Even when the user's process is terminating and Part 2 cannot be run, cleanup for the request is deferred to vn_cancel.

If the saved LFS token is bad, it is not clear what the PFS should do about it. This could be a logic error in the PFS. If the value that was passed was once an LFS token, and this is not a late or redundant call, then it is unlikely that this can happen, because the LFS does not clean up its request while there is still any valid chance that osi_sched will be called.

Return_code

Supplied and returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the PFS passes the return code from Part 1, and the LFS returns the return code from the scheduling.

The Return_code parameter is meaningful only if Return_value is -1.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the PFS passes the reason code from Part 1 and the LFS returns the reason code from the scheduling. Reason_code further qualifies the Return_code value.

The Reason_code parameter is meaningful only if Return_value is -1.

For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Usage notes

- 1. For more information about asynchronous operations, see "Asynchronous I/O processing" on page 55.
- 2. osi_sched is called by the PFS when an asynchronous vnode operation is ready to complete. For instance, data has arrived for receive-type operations or buffers are available for write-type operations.
- 3. Osi_asytok on entry to Part 1 of an asynchronous vnode operation contains the LFS's request token. This value must be saved by the PFS, and is used here to identify the operation that is completing.
- 4. As a result of calling osi_sched, the LFS calls the PFS for Part 2 of the original operation again. Part 2 is run from an SRB in the user's address space.

Characteristics and restrictions

None.

osi_selpost — Post a process waiting for select

Function

The osi_selpost service posts a process that is waiting because of a select request.

Requirements

| Operation Er | nvironment |
|--------------|------------|
|--------------|------------|

Authorization: Problem or supervisor state, any PSW key

Dispatchable unit mode: Task or SRB

Cross memory mode: Any

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_selpost(Select_token,
Return_value,
Return_code,
Reason_code);
```

Parameters

Select_token

Supplied parameter

Type:

Token

Length:

16 bytes

Select_token is the token that was saved by the PFS when it was called for the select query request. The PFS does not need to be aware of the contents of this field; it just needs to save it on the select request and pass it to this module when it is time to post.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_selpost operation returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_selpost operation stores the return code. The osi_selpost operation returns Return_code only if Return_value is -1. For a complete list of possible return code values, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_selpost operation stores the reason code. The osi_selpost operation returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Usage notes

- 1. For additional information, see "Select/poll processing" on page 45.
- 2. The task that is posted is the task that is represented by Select_token. Before a PFS uses osi_selpost, it should copy the Select_token to a place that is addressable by the task that will perform the osi_selpost.

- 3. The PFS must never call osi_selpost for a waiting process more than once, and it should have sufficient logic and recovery to avoid calling osi_selpost for a task that is no longer waiting.
- 4. The address of the osi_selpost routine is passed to the PFS in the OSIT structure when the PFS is initialized.

Related services

• "vn_select — Select or poll on a vnode" on page 201

Characteristics and restrictions

The caller of this service must be on a process thread.

osi_signal — Generate the requested signal event

Function

The osi_signal service generates the requested signal to the target process.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------|
| Authorization: | Problem or supervisor state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| | |

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

OSI structure

Supplied parameter

Type:

Structure

Length:

Specified by the Osilen field.

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

For more information about the full description of this structure, see <u>Appendix D</u>, "Interface structures for C language servers and clients," on page 465.

Target_Osipid

Supplied parameter

Type:

Integer

Length:

Fullword

A copy of the Osipid field from the target process.

Signal_value

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the signal value. For a description of the signal. h header and the signal values, see Handling signals using Language Environment callable services in z/OS XL C/C++ Programming Guide.

Signal_options

Supplied parameter

Type:

Integer

Length:

Fullword

The name of a fullword that contains the signal option flags. For a description of the declaration of signal option flags, see <u>kill (BPX1KIL, BPX4KIL) — Send a signal to a process</u> in *z/OS UNIX System Services Programming: Assembler Callable Services Reference.*

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_signal service returns the results of the signal request, as one of the following values:

-1

The operation was not successful.

0

The operation was successful.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_signal service stores the return code. The osi_signal service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_signal service stores the reason code. The osi_signal service returns Return_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in *z/OS UNIX System Services Messages and Codes*.

Usage notes

- 1. The PFS must have the process ID of the task that is to receive the signal. This information must be retrieved from the target OSI_structure and placed in a variable that is visible to the task that will eventually invoke the osi_signal service.
- 2. The address of the osi_signal routine is passed to the PFS in the OSIT structure when the PFS is initialized.

osi_sleep — Sleep until a resource is available

Function

The osi_sleep service waits for an osi_wakeup to be called with a matching Resource_id and Pfs_id.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------|
| Authorization: | Problem or supervisor state, any PSW key |
| Dispatchable unit mode: | Task |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_sleep(OSI_structure,
Resource_id,
Time_interval,
Return_value,
Return_code,
Reason_code);
```

Parameters

OSI_structure

Supplied parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_sleep service stores the reason code. The osi_sleep service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Resource_id

Supplied parameter

Type:

Integer

Length:

Fullword or doubleword, depending on the AMODE.

The Resource_id identifies the resource for which the thread is waiting.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_sleep service stores the return code. The osi_sleep service can return one of the following values in the Return_code parameter only if Return_value is -1. Reason_code further qualifies the Return_code value.

| Return_code | Explanation |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EDEADLK | An FRR was active when the service was requested. |
| EINTR | The service was interrupted. Consult Reason_code to determine the exact reason that the error occurred. The following reason codes can accompany the return code: JRSIGDURINGWAIT, JRTIMEOUT. |
| EINVAL | Incorrect parameter. Consult Reason_code to determine the exact reason that the error occurred. The following reason codes can accompany the return code: JRBADOSI, JRBADPFSID. |
| EIO | The file system was unmounted while LFS serialization was dropped. |

Return_code

Explanation

EMVSNOTUP

The system is being stopped.

Return value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_sleep service returns the results of the operation as one of the following:

Return_value

Meaning

-1

The operation was not successful.

0

The operation was successful, and the task was awakened by osi_wakeup.

Time_interval

Supplied parameter

Type:

Integer

Length:

Doubleword

The Time_interval is the maximum time for which osi_sleep will sleep. The value is specified in timer units and is rounded up to approximate seconds (the value of the high-order word). See *z/Architecture Principles of Operation* for more information about timer units. The rounded-up value is added to the current time; therefore a very large time interval added to the current time could wrap to a very small number and result in an immediate timeout of osi_sleep. A value of 0 indicates that there is no time limit.

Usage notes

- 1. For additional information, see "Waiting and posting" on page 20.
- 2. All LFS serialization is dropped during an osi_sleep and reestablished after the osi_wakeup.
- 3. Before calling osi_sleep, the PFS must copy the osi_pfsid value to a location that is addressable by the task that will call osi_wakeup. It must be passed as the Pfs_id on osi_wakeup. The osi_pfsid value that is passed to the PFS is the same for all operations of this PFS. It is also passed as pfsi_pfsid during PFS initialization. This initialization value can be used on osi_wakeup instead of saving the OSI value.
- 4. The osi_wakeup service does not wake up a task that is not currently sleeping. If osi_wakeup is issued before osi_sleep for the same resource, the task sleeps until the next osi_wakeup for that resource. Therefore, the PFS must have sufficient logic and recovery to ensure that sleeping tasks are eventually awakened.
- 5. The address of the osi_sleep routine is passed to the PFS in the OSIT structure when the PFS is initialized.

Related services

"osi_wakeup — Wake up OSI sleepers" on page 419

Characteristics and restrictions

- 1. This routine must be used only on the task that made the vnode or VFS call.
- 2. An osi_sleep is not permitted if an FRR is established.

osi_thread — Fetch and call a module from a colony thread

Function

The osi_thread service is used by a PFS to call a module on an asynchronous colony thread that is in the same colony address space that the PFS is running on. For a synchronous request, the caller's task is put into a wait while the module is running.

Requirements

| Operation | Environment |
|-----------|-------------|
|-----------|-------------|

Authorization: Problem or supervisor state, any PSW key

Dispatchable unit mode: Task
Cross memory mode: Any
AMODE: 31-bit
ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_thread(OSI_structure,
OsitThread_Parm_structure,
Return_value,
Return_code,
Reason_code);
```

Parameters

OSI_structure

Supplied parameter

Type:

Structure

Length:

Specified by the Osilen field

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

OsitThread_Parm_structure

Supplied parameter

Type:

Structure

Length:

Specified by the Othdlen field

An area that contains the OsitThread parameters. The entries in this area are mapped by the OTHDPRM typedef.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure. The following OsitThread parameters must be supplied:

ot_modname

The name of the module that is to be fetched and called on the colony thread. The name must be a null-terminated string that is acceptable to the C fetch function.

ot parms

The address of the parameters that is to be passed to the module specified by ot_modname. This parameter is also passed to the named exit if it is called. If any parameters are passed, the first parameter is used by the LFS to pass a state token to the named module or exit routine. The area whose address is passed in ot_parms must reserve the first word for this purpose.

The address that is specified in this parameter points to a structure, or control block, in whose first word the LFS inserts the address of the 8-byte state token. A pointer containing ot_parms is the first parameter to the module and to the exit routine.

ot_exitname

The name of the exit routine that may be called after the module completes. This routine is called for a request that specifies NOWAIT, or when the caller's wait is terminated before the module completes. The name must be a null-terminated string that is acceptable to the C fetch function.

ot_option_flags

A field in which the caller can specify:

- OSI_SIGWAIT—the caller's task is put into a signal-enabled wait until the module that is named in ot_modname completes.
- OSI_NOWAIT—the caller's task is not put into a wait; the module is run asynchronously.

If neither OSI_SIGWAIT nor OSI_NOWAIT is specified, the caller's task is placed in a wait that is not signal-enabled.

• OSI_RELEASEMODS—the fetched module and exit routine, if called, are released when the request is complete.

When a module is released, any state token that is associated with this module on the current osi worker thread is freed.

IF OSI_RELEASEMODS is not specified, the named module and the exit routine, if called, remain in storage. The next request that specifies these routines does not fetch them before calling them.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_thread service returns the results of the operation, as one of the following return codes:

$Return_value$

Meaning

-1

The operation was not successful. The resources that are associated with this request can be safely freed.

0

The operation was successful. The resources that are associated with this request can be safely freed.

+1

The named module was scheduled to be called, but might not have completed. Resources that are associated with this request should not be freed. This value is returned if the request specified OSI_NOWAIT, or if the caller's wait is terminated before the request completes.

Note: The return value indicates the results of the osi_thread service. It does not indicate the results of the named module. Some other mechanism must be used by the caller to determine these results.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_thread service stores the return code. The osi_thread service can return one of the following values in the Return_code parameter only if Return_value is +1 or -1. Reason_code further qualifies the Return_code value.

| Return_code | Explanation |
|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| EINTR | The service was interrupted by a signal. |
| EINVAL | Parameter error. Consult Reason_code to determine the exact reason that the error occurred. The following reason codes can accompany the return code: JROWaitSetupErr, JRNoClnyThreadSuppt. |

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_thread service stores the reason code. The osi_thread service returns Reason_code only if Return_value is +1 or -1. Reason_code further qualifies the Return_code value.

Usage notes

- 1. The osi_thread service is invoked only from a PFS that is running in a colony address space.
- 2. For more information, see "Using daemon tasks within a PFS" on page 42.
- 3. The osi_thread service is not available for use until kernel initialization is complete. The PFS can determine when kernel initialization is complete by interrogating the ot_available flag whose address is passed in the pfsi_otstatptr field.
- 4. The caller must not free any resources that can be used by the module that is running on the colony thread unless a return value of 0 or -1 is returned. If a return value of +1 is returned, the resources must be freed by the exit routine.
- 5. The osi_thread service undoes any Osi_Wait Setup that was done before this service was called.
- 6. The named module and the named exit routine are fetched on the colony thread using the C/370 fetch() function. The named module must comply with any requirements of this function. For more


- information about the fetch() function, see <u>fetch() Get a load module</u> in *z/OS XL C/C++ Runtime Library Reference*.
- 7. The named module, and the exit routine, if it is called, remain in storage after the request completes, unless OSI RELEASEMODS was specified.
- 8. The named module and the exit routine can use C/RTL or POSIX services. The writer of the PFS should remember that this thread could be used to fetch and call the specified module on another osi_thread call. Therefore, the named module should not request any services that would affect the process that is associated with this thread, such as exit or exec. Pthread services should not be requested either.
- 9. The named module and the exit routine must be reentrant.
- 10. The named module and the exit routine are invoked using OS linkage conventions.
- 11. The named module and the exit routine receive control in the following environment:

Operation **Environment** Authorization: Problem state, PSW key 8 Dispatchable unit mode: Task Cross memory mode: PASN=HASN=SASN AMODE: 31-bit ASC mode: Primary Interrupt status: **Enabled for interrupts** Locks: Unlocked


Signals: All signals are blocked except SIGALRM

12. If any parameters are passed to the named module or exit routine, the first parameter should be the address of an 8-byte state token. The first time a named module or exit routine is invoked on a particular osi worker thread, this token is zeros. The named module or exit routine can modify this token to preserve some state information from one invocation to the next. For all subsequent invocations of this module on this particular worker thread, the token is provided unmodified by the LFS.

When the PFS uses a parameter structure, the first word is used by the LFS to point to the state token. The input to the module and exit looks like this:



When the PFS does not use a parameter structure, the input to the module and exit looks like this:



13. ESTAE-like recovery is available to the module and exit routines. This saves the overhead involved in having these routines set up and take down their own ESTAEs on each entry.

A pointer to a Recovery Block (RcvyBlk) is passed as the second parameter to these routines. The pointer is used as follows:

- a. On entry, or when recovery protection is needed, the module or exit sets the RcvyData pointer to the address of its own recovery information.
 - Pertinent data can also be placed in the work area. This data will be available to the recovery routine.
 - The RcvyRtn pointer is set to the address of a recovery routine.
- b. If the module or exit ends abnormally, and RcvyRtn is nonzero, the RcvyRtn routine is called from the LFS's ESTAE and passed all the parameters provided by RTM, including the pointer to RcvyBlk. An exception is that register 15 contains the address of the recovery routine (RcvyRtn), rather

than the address of the LFS's permanent ESTAE exit. When the RcvyRtn routine returns, it returns directly to RTM, rather than to the LFS's permanent ESTAE exit.

c. Under normal circumstances, before returning, or when recovery protection is no longer needed, the module or exit zeros out the RcvyRtn field.

The recovery routine is invoked in the same way as an MVS ESTAE routine, not a C subroutine. The registers on entry are:

Register

Contents

R0

12, if an SDWA is not provided; otherwise, an SDWA address is provided in R1.

R1

SDWA address, if an SDWA is provided; otherwise, completion code.

R2

Pointer to RcvyBlk, with or without an SDWA. This value is also contained in SDWAPARM when an SDWA is provided.

R13

Address of the save area that is provided by RTM.

R14

Return address, as provided by RTM.

R15

Address of the recovery routine that is being called (RcvyRtn).

- 14. The recovery block (RcvyBlk) is mapped by OTHDCRCV in bpxypfsi.h.
- 15. The work area in the recovery block can be used to pass information to the recovery routine. It can also be used as a work area for the recovery routine to build dump titles or list forms of assembler macros.
- 16. The recovery routine is entered in problem program state, key 8.
- 17. The address of the osi_thread routine is passed to the PFS in the OSIT when the PFS is initialized.

Characteristics and restrictions

This routine must be used only on the task that made the vnode or VFS call.

osi_uiomove — Move data between PFS buffers and buffers defined by a UIO structure

Function

The osi_uiomove service moves blocks of data between PFS buffers and buffers that are defined by a UIO structure.

Requirements

| Operation | Environment |
|-------------------------|-----------------------------|
| Authorization: | Supervisor state, PSW key 0 |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |

Operation Environment

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Number_of_bytes

Supplied parameter

Type:

Integer

Length:

Fullword

The number of bytes to move.

OSI_structure

Supplied parameter

Type:

Structure

Length:

Specified by the Osilen field

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

PFS_Buffer

Supplied parameter

Type:

Char

Length:

N/A

The name of the buffer to or from which data is to be moved. This parameter can also be a 64-bit address; refer to the usage notes.

PFS_Buffer_Alet

Supplied parameter

Type:

Integer

Length:

Fullword

The Alet for the specified PFS_Buffer.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_uiomove service stores the reason code. The osi_uiomove service returns Return_code only if Return_value is -1. Reason_code further qualifies the Return_code value. For a list of reason codes, see Reason codes in z/OS UNIX System Services Messages and Codes.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_uiomove service returns the results of the service, as one of the following:

Return_value

Meaning

-1

The operation was not successful. The Return_code and Reason_code parameters contain the values that are returned by the service.

0 or greater

The operation was successful. The value represents the number of bytes that were transferred.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_uiomove service stores the return code. The osi_uiomove service returns Return_code only if Return_value is -1. For a complete list of supported return codes, see Return codes (errnos) in z/OS UNIX System Services Messages and Codes.

User_IO_structure

Supplied and returned parameter

Type:

UIO

Length:

Specified by UIO.u_hdr.cblen.

An area that contains the parameters for the I/O that is to be performed. This area is mapped by the UIO typedef in the BPXYVFSI header file (see <u>Appendix D</u>, "Interface structures for C language <u>servers and clients," on page 465</u>). See "Specific processing notes" on page 413 for details on how the fields in this structure are processed.

Workarea

Supplied parameter

Type:

Char

Length:

2048 bytes

Workarea is a 2K-buffer that is aligned on a word boundary. For 64-bit callers, it may reside above the bar. It is used during the OSI operation.

Usage notes

- 1. The osi_uiomove service moves the number of bytes of data that is specified by the Number_of_bytes parameter or the UIO.u_count field, whichever is less. If either of these parameters is zero, no data is moved, and Return_value field is set to 0.
- 2. The u_iovresidualcnt and u_totalbytesrw fields, described in this topic, are not set until after the first call to osi_uiomove.
- 3. This service requires the calling program to run in key 0 storage, because it must update the UIO, and this structure is usually in key 0 storage. Osi_copyin and osi_copyout do not require the calling program to be in key 0 storage.
- 4. The address of the osi_uiomove routine is passed to the PFS in the OSIT structure when the PFS is initialized.
- 5. The OSI_structure contains an area, pointed to by osi_workarea, that may be passed to this service as the Workarea parameter.
- 6. The osi_indirect64 bit in BPXYPFSI indicates that the PFS_Buffer parameter is a 64-bit address that points to the PFS_ Buffer to be used by the osi_uiomove service. osi_uiomove turns this bit off before returning to the caller. Because of this, the caller of osi_uiomove is responsible for setting the osi_indirect64 flag prior to each invocation of osi_uiomove that requires a 64-bit address for the PFS_Buffer parameter.

If the osi_indirect64 flag is set, the PFS_Buffer parameter is assumed to be an 8-byte address of the actual PFS Buffer. This allows a program to call the osi_uiomove service in AMODE(31) and still pass the address of a PFS buffer that is above the bar. The osi_uiomove service turns this flag off, so it must be reset to ON for every call for which you want to use indirect buffer addressing. PFS_Buffer_Alet still refers to the actual buffer itself, not to the 8-byte pointer. The 8-byte pointer must be in the primary address space.

Specific processing notes

The following UIO fields are provided by the LFS:

UIO.u_count

Specifies the number of bytes in the buffer, or the number of elements in the IOV array.

UIO.u_rw

Specifies whether the request is a read (0) or a write (1). On a read, the contents of PFS_buffer are moved to Uiouserbuffer. On a write, the contents of Uiouserbuffer are moved to PFS_buffer.

UIO.u_iovinuio

Specifies whether the user_IO_structure points to an iov structure.

UIO.u_realpage

Specifies whether the user_IO_structure contains addresses of real pages. This flag must be OFF (0), or the osi_uiomove service fails the request.

UIO.u_key

Specifies the storage key of the caller's buffer.

UIO.u_iovresidualcnt

Specifies the number of bytes remaining in the buffer or iov structure that is pointed to by the user_IO_structure.

u_totalbytesrw

Specifies the total number of bytes that are to be moved.

Related services

- "osi_copyin Move data from a user buffer to a PFS buffer" on page 357
- "osi_copyout Move data from a PFS buffer to a user buffer" on page 360
- "osi_copy64 Move data between user and PFS buffers with 64-bit addresses" on page 363

Characteristics and restrictions

- 1. This routine must be used only on the dispatchable unit (task or SRB) that made the vnode or VFS call because the service requires the use of the cross-memory environment of the calling dispatchable unit.
- 2. The osi_uiomove service does not support DATOFF moves; that is, it fails requests if the UIO.u_realpage flag is ON.

osi_upda — Update async I/O request

Function

The osi_upda service updates an asynchronous request with the PFS's request token.

Environment

address space.

Requirements

Operation

| Authorization: | Supervisor state, key 0 |
|-------------------------|---------------------------------------------------------------------|
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |
| AMODE: | 31-bit or 64-bit |
| ASC mode: | Any |
| Interrupt status: | Enabled for interrupts |
| Locks: | Unlocked |
| Control parameters: | All parameters must be addressable by the caller and in the primary |

Format

```
osi_upda(Osi_AsyTok,
PFS_AsyTok);
```

Parameters

Osi_AsyTok

Supplied parameter

Type:

Token

Length:

8 bytes

The name of the field that contains the osi_asytok value that was passed to the PFS on this vnode operation.

The field from the input osi itself may be used on this call.

PFS_AsyTok

Supplied parameter.

Type:

Token

Length:

8 bytes

The name of the field containing the PFS's token for this asynchronous request. This value is saved by the LFS and passed back to the PFS on the second part of the asynchronous operation, or on vn_cancel.

Usage notes

- 1. Refer to "Asynchronous I/O processing" on page 55 for details on asynchronous operations.
- 2. osi_upda is called by the PFS early in Part 1 of an asynchronous vnode operation. It must be called some time before there is any possibility that osi_sched will be called for an asynchronous completion of this I/O.

When an operation can be completed immediately, Osi_upda does not have to be called if osi_ok2compimd=ON, or if the PFS does not need to participate in Part 2.

3. On entry to Part 1, Osi_asytok contains the LFS's request token, and osi_upda is called so that the LFS can save the PFS's request token.

Osi_asytok is also saved by the PFS during Part 1, and is used later for osi_sched.

4. Osi_asytok on entry to Part 2 contains this PFS_AsyTok value.

It is important that osi_upda be called before osi_sched is called, when the PFS is participating in Part 2, because Part 2 could run anytime after osi_sched is called, and the LFS might not have the PFS's request token to pass.

5. This PFS_AsyTok value is also passed on vn_cancel to identify the request that is being canceled.

Canceled requests do not generate a call to vn_cancel if osi_upda has not been called.

6. If the Osi_Asytok value is not valid, osi_upda issues an 0xEC6 abnormal end with a reason code of 0x11450727.

Characteristics and restrictions

None.

osi_wait — Wait for an event to occur

Function

The osi wait service waits for a signal to occur or for osi post to be called.

Requirements

| Operation | Environment |
|-------------------------|------------------------------------------|
| Authorization: | Problem or supervisor state, any PSW key |
| Dispatchable unit mode: | Task or SRB |
| Cross memory mode: | Any |

Operation Environment
AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

Parameters

Entry_code

Supplied parameter

Type:

Integer

Length:

Fullword

The Entry_code specifies the function that is being requested for the osi_wait service.

| Entry_code | Explanation |
|--------------|-----------------------------------------------------------------|
| OSI_SETUP | Set up for a subsequent wait request. |
| OSI_SETUPSIG | Set up for a subsequent wait request with signals enabled. |
| OSI_SUSPEND | Wait to be posted from osi_post. |
| OSI_WAITX | Wait to be posted from osi_post or for a timer to expire. |
| OSI_INIT2 | Initialize for use by an independent task. See the usage notes. |

OSI_structure

Supplied and returned parameter

Type:

OSI

Length:

Specified by OSI.osi_hdr.cblen.

OSI_structure contains information that is used by the OSI operations. The PFS receives this structure on each PFS interface operation.

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_wait service stores the return code. The osi_wait service can return one of the following values in the Return_code parameter:

| Return_code | Explanation |
|---------------|------------------------------------------------------------------------------|
| OSI_POSTED | Successful completion. |
| OSI_SIGNALRCV | A signal arrived. |
| OSI_SHUTDOWN | The system is being stopped. |
| OSI_TIMEOUT | A specified time interval expired before a post or signal. |
| OSI_UNMOUNTED | The file system was unmounted while LFS serialization was dropped. |
| OSI_POSTERTRM | The address space that is responsible for doing the osi_post has terminated. |
| OSI_BADPARM | Incorrect OSI_structure. |
| OSI_ESTAEF | Unable to establish a recovery environment. |
| OSI_ABEND | Abnormal end in osi_wait. |
| OSI_SYSTEMERR | Unable to release latches before a signal wait. |

Wait_Flags

Supplied parameter (only when Entry_code is OSI_WAITX)

Type:

Integer

Length:

Fullword

Wait_flags contains flags that specify options on the wait request.

| Flag | Explanation |
|-----------------|----------------------------------------------------------------------------|
| osi_wtdroplocks | Drop LFS serialization during the wait, and reestablish it after the wait. |

Refer to Appendix D, "Interface structures for C language servers and clients," on page 465 for a full description of this structure.

Time_interval

Supplied parameter (only when Entry_code is OSI_WAITX)

Type:

Integer

Length:

Doubleword

The Time_interval is the time for which osi_wait will wait. The value is specified in timer units. If the high-order word is non-zero, the 8-byte value is rounded to approximate seconds. See *z/Architecture Principles of Operation* for more detail on timer units. The value is added to the current time; therefore a very large time interval added to the current time could wrap to a very small number and result in an immediate timeout of osi_wait. A value of 0 indicates there is no time limit.

Usage notes

1. For additional information, see "Waiting and posting" on page 20.

- 2. The PFS must call osi_wait for setup before making the call to do the wait and before OSI_post is called to wake up the task. On the setup call, Entry_code specifies whether the PFS wants the wait to be terminated if the process receives a signal.
 - The order of the calls to wait and to OSI_post is not important after the setup call has been made.
- 3. If Entry_code is OSI_SUSPEND and a signal-enabled wait was set up, all LFS serialization is dropped during the wait and reestablished after the wait.
 - If Entry_code is OSI_WAITX, the Wait_flags specify whether LFS serialization is dropped during the wait and reestablished after the wait.
 - For writes on stream sockets, the default socket option of exclusive write will prevent the dropping of LFS serialization during signal-enabled waits.
- 4. Between the calls to setup and suspend, the PFS should make sure that the OSI token that is returned by setup is addressable to the program that will eventually call OSI_post. The PFS can copy the OSI token. If only the address is used, be careful using this OSI, because the storage for a task will be freed if the task terminates.
- 5. The PFS must never call OSI_post for a waiting task more than once, and should have sufficient logic and recovery to avoid calling OSI_post for a task that is no longer waiting.
- 6. The osi thread service undoes any osi wait setup that was done before osi thread was called.
- 7. Osi_wait issues an MVS WAIT or SUSPEND, respectively, as appropriate for TCB or SRB mode callers. Osi_post invokes the corresponding MVS service to wake up osi_waiters.
- 8. When osi_wait is called from an SRB, OSI_SETUPSIG may be requested, but signals are not really enabled. This is because signals are not delivered to SRBs, therefore the wait is not interrupted by a signal.
 - Using OSI_SETUPSIG allows z/OS UNIX to interrupt an SRB's wait if the associated user process goes into termination. It is awakened as if a signal had been delivered.
- 9. The OSI_INIT2 Entry_code is used to initialize an OSI_Structure for use by an independent task (TCB) in an address space that is associated with the PFS. This allows the task to wait with osi_wait and be posted with osi_post. An independent task is one that was attached in that address space; it is not running from within a vnode operation.

Note: Generally an independent task would use MVS WAIT, and be posted by MVS POST. Osi_wait and osi_post take several hundred more instructions to execute than MVS WAIT/POST.

There are several restrictions on this service:

- a. Only tasks (TCBs) are supported, not SRBs.
- b. The task must already be dubbed a z/OS UNIX thread. If this is not the case, the task can get dubbed by calling a z/OS UNIX service such as getpid() before calling osi_wait for OSI_INIT2.
- c. The only osi service that is expected to be used by this task with the OSI_structure returned is osi wait.

Osi_wait(OSI_INIT2) needs to be called only once for the life of a TCB.

The storage for the OSI_structure is provided by the caller as input, and osi_wait(OSI_INIT2) initializes this area for use on subsequent calls for setup and suspension. This storage belongs to the caller, and is freed by the caller, usually at task termination. Calls for setup and suspension may be made with a copy of the structure that is built from this call.

Only the task that made the OSI_INIT2 call can use this OSI_structure.

- The OSI_structure must be initialized with the length of the area that is being passed before osi_wait(OSI_INIT2) is called. For example, osi.osi_hdr.cblen=sizeof(OSI).
- 10. The address of the osi_wait routine is passed to the PFS in the OSIT structure when the PFS is initialized. Calls that are made from independent address spaces require their own loaded OSIT structure. Refer to "Using OSI services from a non-kernel address space" on page 356 for details.

Related services

• "osi_post - Post an OSI waiter" on page 394

Characteristics and restrictions

Calls that are made with the OSI_structure that was passed to the PFS on a vnode or VFS operation must be made only on the task that made the vnode or VFS call.

osi_wakeup — Wake up OSI sleepers

Function

The osi_wakeup service wakes up all threads that are sleeping in osi_sleep with a matching Resource_id and Pfs_id.

Requirements

| ironment |
|----------|
| |

Authorization: Problem or supervisor state, any PSW key

Dispatchable unit mode: Task or SRB

Cross memory mode: Any

AMODE: 31-bit or 64-bit

ASC mode: Any

Interrupt status: Enabled for interrupts

Locks: Unlocked

Control parameters: All parameters must be addressable by the caller and in the primary

address space.

Format

```
osi_wakeup(Resource_id,
Pfs_id,
Return_value,
Return_code,
Reason_code);
```

Parameters

Pfs id

Supplied parameter

Type:

Token

Length:

Fullword

The Pfs_id identifies the calling PFS. The PFS receives its unique identifier from the LFS in the osi_pfsid field of the OSI structure on each VFS and vnode operation. This identifier is also passed as pfsi_pfsid during PFS initialization, and the initialization value can be used instead of the OSI value that is saved from osi_sleep.

Reason_code

Returned parameter

Type:

Integer

Length:

Fullword

A fullword in which the osi_wakeup service stores the reason code. The osi_wakeup service returns Reason_code only if Return_value is -1. Reason_code further qualifies the Return_code value.

Resource_id

Supplied parameter

Type:

Integer

Length:

Fullword or doubleword, depending on the AMODE.

The Resource_id identifies the resource that is available. All osi_sleep services that are waiting for this Resource_id are to return to their callers.

Return_code

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_wakeup service stores the return code. The osi_wakeup service returns Return_code only if Return_value is -1. Reason_code further qualifies Return_code.

Return_value

Returned parameter

Type:

Integer

Length:

Fullword

The name of a fullword in which the osi_wakeup service returns the results of the operation, as one of the following:

Return_value

Meaning

-1

The operation was not successful.

0 or greater

The operation was successful; the value represents the number of sleeping tasks that were awakened.

Usage notes

- 1. For additional information, see "Waiting and posting" on page 20.
- 2. Before calling osi_sleep, the PFS must copy the osi_pfsid value to a location that is addressable by the task that is to call osi_wakeup. It must be passed as the Pfs_id on osi_wakeup. The osi_pfsid value that is passed to the PFS is the same for all operations of this PFS. It is also passed as pfsi_pfsid during PFS initialization. This initialization value may be used on osi_wakeup instead of the OSI value that is saved from osi_sleep.

- 3. The osi_wakeup service does not wake up a task that is not currently sleeping. If osi_wakeup is issued before osi_sleep for the same resource, the task sleeps until the next osi_wakeup for that resource. Therefore, the PFS must have sufficient logic and recovery to ensure that sleeping tasks will eventually be awakened.
- 4. The address of the osi_wakeup routine is passed to the PFS in the OSIT structure when the PFS is initialized.

Related services

• "osi_sleep — Sleep until a resource is available" on page 402

Characteristics and restrictions

The caller of this service must be on a process thread.

osi_wakeup

Appendix A. System control offsets to callable services

An alternative to loading or link-editing the service stub is to include in the code the system control offset to the callable service. For example, use decimal 52 for the offset of access (BPX1ACC).

When using the offsets, set the registers up as follows:

Register 1

To contain the address of your parameter list. Set bit 0 of the last address in the list on.

Register 14

To contain the return address in the invoking module.

Register 15

To contain the address of the callable service code.

Example

The following is an example of code that specifies the offset. The example assumes that register 1 is set up with the address of the parameter list. Replace *offset* with the appropriate value from the following offset table.

```
L 15,16 CVT - common vector table
L 15,544(15) CSRTABLE
L 15,24(15) CSR slot
L 15,offset(15) Address of the service
BALR 14,15 Branch and link
```

List of offsets

Table 16. System control offsets to callable services

| Tuble 10. System control offsets to cultuble services | | |
|-------------------------------------------------------|--------|------------------------------------|
| Service | Offset | Function |
| BPX1ACC | 52 | access |
| BPX1ACK | 972 | auth_check_rsrc_np |
| BPX1ACP | 508 | accept |
| BPX1AIO | 988 | asyncio |
| BPX1ALR | 224 | alarm |
| BPX1ANR | 1060 | accept_and_recv |
| BPX1ASP | 1088 | aio_suspend |
| BPX1ATM | 668 | attach_execmvs |
| BPX1ATX | 664 | attach_exec |
| BPX1BND | 512 | bind |
| BPX1BAS | 592 | bind with source address selection |
| BPX1CCA | 480 | cond_cancel |
| BPX1CCS | 1012 | console_np |
| BPX1CHA | 84 | chaudit |
| BPX1CHD | 56 | chdir |

Table 16. System control offsets to callable services (continued)

| Table 10. System C | onthol offsels to co | unable services (continuea) |
|--------------------|----------------------|-----------------------------|
| Service | Offset | Function |
| BPX1CHM | 60 | chmod |
| BPX1CHO | 64 | chown |
| BPX1CHP | 764 | chpriority |
| BPX1CHR | 500 | chattr |
| BPX1CID | 968 | convert_id_np |
| BPX1CLD | 68 | closedir |
| BPX1CLO | 72 | close |
| BPX1CON | 516 | connect |
| BPX1CPL | 1132 | cpl |
| BPX1CPO | 484 | cond_post |
| BPX1CRT | 872 | chroot |
| BPX1CSE | 488 | cond_setup |
| BPX1CTW | 492 | cond_timed_wait |
| BPX1CWA | 496 | cond_wait |
| BPX1DEL | 888 | deletehfs |
| BPX1DSD | 1124 | sw_signaldelv |
| BPX1ENV | 960 | oe_env_np |
| BPX1EXC | 228 | exec |
| BPX1EXI | 232 | _exit |
| BPX1EXM | 236 | execmvs |
| BPX1EXT | 200 | extlink_np |
| BPX1FAI | 1168 | FreeAddrInfo |
| BPX1FCA | 140 | fchaudit |
| BPX1FCD | 852 | fchdir |
| BPX1FCM | 88 | fchmod |
| BPX1FCO | 92 | fchown |
| BPX1FCR | 504 | fchattr |
| BPX1FCT | 96 | fcntl |
| BPX1FPC | 100 | fpathconf |
| BPX1FRK | 240 | fork |
| BPX1FST | 104 | fstat |
| BPX1FSY | 108 | fsync |
| BPX1FTR | 112 | ftruncate |
| BPX1FTV | 848 | FstatVfs |
| BPX1GAI | 1164 | GetAddrInfo |
| BPX1GCL | 1024 | getclientid |
| | | |

Table 16. System control offsets to callable services (continued)

| Tuble 16. System con | | ole services (continuea) |
|----------------------|--------|--------------------------|
| Service | Offset | Function |
| BPX1GCW | 116 | getcwd |
| BPX1GEG | 244 | getegid |
| BPX1GEP | 860 | getpgid |
| BPX1GES | 864 | getsid |
| BPX1GET | 736 | w_getipc |
| BPX1GEU | 248 | geteuid |
| BPX1GGE | 772 | getgrent |
| BPX1GGI | 252 | getgrgid |
| BPX1GGN | 256 | getgrnam |
| BPX1GGR | 260 | getgroups |
| BPX1GHA | 1160 | gethostbyaddr |
| BPX1GHN | 1156 | gethostbyname |
| BPX1GID | 264 | getgid |
| BPX1GIV | 1028 | givesocket |
| BPX1GLG | 268 | getlogin |
| BPX1GMN | 76 | w_getmntent |
| BPX1GNI | 1172 | GetNameInfo |
| BPX1GNM | 524 | getpeername |
| BPX1GPE | 776 | getpwent |
| BPX1GPG | 272 | getpgrp |
| BPX1GPI | 276 | getpid |
| BPX1GPN | 280 | getpwnam |
| BPX1GPP | 284 | getppid |
| BPX1GPS | 428 | w_getpsent |
| BPX1GPT | 916 | grantpt |
| BPX1GPU | 288 | getpwuid |
| BPX1GPY | 744 | getpriority |
| BPX1GRL | 820 | getrlimit |
| BPX1GRU | 824 | getrusage |
| BPX1GTH | 1056 | getthent |
| BPX1GTR | 752 | getitimer |
| BPX1GUG | 292 | getugrps |
| BPX1GUI | 296 | getuid |
| BPX1GWD | 936 | getwd |
| BPX1HST | 520 | gethostid |
| BPX1IOC | 120 | w_ioctl |
| | | |

Table 16. System control offsets to callable services (continued)

| Tuble 16. System conti | oi ojjseis to callab | nie services (continuea) |
|------------------------|----------------------|--------------------------|
| Service | Offset | Function |
| BPX1IPT | 396 | MvsIptAffinity |
| BPX1ITY | 12 | isatty |
| BPX1KIL | 308 | kill |
| BPX1LCO | 832 | lchown |
| BPX1LCR | 1180 | lchattr |
| BPX1LNK | 124 | link |
| BPX1LOD | 880 | loadhfs |
| BPX1LSK | 128 | lseek |
| BPX1LSN | 532 | listen |
| BPX1LST | 132 | lstat |
| BPX1MAT | 720 | shmat |
| BPX1MCT | 724 | shmctl |
| BPX1MDT | 728 | shmdt |
| BPX1MGT | 732 | shmget |
| BPX1MKD | 136 | mkdir |
| BPX1MKN | 144 | mknod |
| BPX1MMI | 1136 | map_init |
| BPX1MMP | 796 | mmap |
| BPX1MMS | 1140 | map_service |
| BPX1MNT | 148 | mount |
| BPX1MP | 688 | MVSpause |
| BPX1MPC | 408 | mvsprocclp |
| BPX1MPI | 680 | MVSpauseInit |
| BPX1MPR | 800 | mprotect |
| BPX1MSD | 336 | mvsunsigsetup |
| BPX1MSS | 312 | mvssigsetup |
| BPX1MSY | 804 | msync |
| BPX1MUN | 808 | munmap |
| BPX1NIC | 748 | nice |
| BPX10PD | 152 | opendir |
| BPX10PN | 156 | open |
| BPX10PT | 528 | getsockopt |
| BPX10SE | 1100 | osenv |
| BPX1PAF | 1072 | pid_affinity |
| BPX1PAS | 316 | pause |
| BPX1PCF | 160 | pathconf |
| | | |

Table 16. System control offsets to callable services (continued)

| Table 10. System | | ullable services (continuea) |
|------------------|--------|------------------------------|
| Service | Offset | Function |
| BPX1PCT | 768 | pfsctl |
| BPX1PIO | 984 | w_pioctl |
| BPX1PIP | 164 | pipe |
| BPX1P0E | 1176 | poe |
| BPX1POL | 932 | poll |
| BPX1PQG | 1152 | Pthread_quiesce_and_get_np |
| BPX1PSI | 460 | pthread_setintr |
| BPX1PST | 472 | Pthread_setintrtype |
| BPX1PTB | 448 | pthread_cancel |
| BPX1PTC | 432 | pthread_create |
| BPX1PTD | 444 | pthread_detach |
| BPX1PTI | 476 | Pthread_testintr |
| BPX1PTJ | 440 | pthread_join |
| BPX1PTK | 464 | pthread_kill |
| BPX1PTQ | 412 | pthread_quiesc |
| BPX1PTR | 320 | ptrace |
| BPX1PTS | 452 | pthread_self |
| BPX1PTT | 1016 | pthread_tag_np |
| BPX1PTX | 436 | pthread_xandg |
| BPX1PWD | 788 | password |
| BPX1QCT | 692 | msgctl |
| BPX1QDB | 948 | querydub |
| BPX1QGT | 696 | msgget |
| BPX1QRC | 700 | msgrcv |
| BPX1QSE | 388 | quiesce |
| BPX1QSN | 704 | msgsnd |
| BPX1RCV | 540 | recv |
| BPX1RDD | 168 | readdir |
| BPX1RDL | 172 | readlink |
| BPX1RDV | 536 | readv |
| BPX1RDX | 940 | read_extlink |
| BPX1RD2 | 856 | readdir2 |
| BPX1RED | 176 | read |
| BPX1REN | 180 | rename |
| BPX1RFM | 544 | recvfrom |
| BPX1RMD | 188 | rmdir |
| | | |

Table 16. System control offsets to callable services (continued)

| Tuble 10. System (| | ulluble services (continueu) |
|--------------------|--------|------------------------------|
| Service | Offset | Function |
| BPX1RMG | 8 | resource |
| BPX1RMS | 548 | recvmsg |
| BPX1RPH | 884 | realpath |
| BPX1RW | 1108 | Pread |
| BPX1RWD | 184 | rewinddir |
| BPX1SA2 | 1084 | Sigactionset |
| BPX1SCT | 708 | semctl |
| BPX1SDD | 300 | setdubdefault |
| BPX1SEC | 1044 | security |
| BPX1SEG | 424 | setegid |
| BPX1SEL | 552 | select |
| BPX1SEU | 420 | seteuid |
| BPX1SF | 1064 | send_file |
| BPX1SGE | 780 | setgrent |
| BPX1SGI | 328 | setgid |
| BPX1SGQ | 1104 | sigqueue |
| BPX1SGR | 792 | setgroups |
| BPX1SGT | 712 | semget |
| BPX1SHT | 572 | shutdown |
| BPX1SIA | 324 | sigaction |
| BPX1SIN | 1004 | server_init |
| BPX1SIP | 340 | sigpending |
| BPX1SLK | 1068 | shm_lock |
| BPX1SLP | 344 | sleep |
| BPX1SMC | 1112 | smc |
| BPX1SMF | 1036 | smf_record |
| BPX1SMS | 560 | sendmsg |
| BPX1SND | 556 | send |
| BPX1SOC | 576 | socket_pair |
| BPX1SOP | 716 | semop |
| BPX1SPB | | 416 sigputback |
| BPX1SPE | 784 | setpwent |
| BPX1SPG | 348 | setpgid |
| BPX1SPM | 352 | sigprocmask |
| BPX1SPN | 760 | spawn |
| BPX1SPR | 568 | setpeer |
| | | |

Table 16. System control offsets to callable services (continued)

| | ninoi ojjsets to ca | lliable services (continuea) |
|---------|---------------------|------------------------------|
| Service | Offset | Function |
| BPX1SPW | 1008 | server_pwu |
| BPX1SPY | 740 | setpriority |
| BPX1SRG | 896 | setregid |
| BPX1SRL | 816 | setrlimit |
| BPX1SRU | 892 | setreuid |
| BPX1SRX | 1080 | srx_np |
| BPX1SSI | 356 | setsid |
| BPX1SSU | 360 | sigsuspend |
| BPX1STA | 192 | stat |
| BPX1STE | 1076 | Set_Timer_Event |
| BPX1STF | 80 | w_statfs |
| BPX1STL | 684 | Set_limits |
| BPX1STO | 564 | sendto |
| BPX1STQ | 1144 | server_thread_query |
| BPX1STR | 756 | setitimer |
| BPX1STV | 844 | StatVfs |
| BPX1STW | 1096 | sigtimedwait |
| BPX1SUI | 364 | setuid |
| BPX1SWT | 468 | sigwait |
| BPX1SYC | 368 | sysconf |
| BPX1SYM | 196 | symlink |
| BPX1SYN | 868 | sync |
| BPX1TAF | 1148 | MvsThreadAffinity |
| BPX1TAK | 1032 | takesocket |
| BPX1TDR | 24 | tcdrain |
| BPX1TFH | 20 | tcflush |
| BPX1TFW | 28 | tcflow |
| BPX1TGA | 32 | tcgetattr |
| BPX1TGC | 900 | tcgetcp |
| BPX1TGP | 36 | tcgetpgrp |
| BPX1TGS | 912 | tcgetsid |
| BPX1TIM | 372 | times |
| BPX1TLS | 964 | pthread_security_np |
| BPX1TRU | 828 | truncate |
| BPX1TSA | 40 | tcsetattr |
| BPX1TSB | 44 | tcsendbreak |
| | | |

Table 16. System control offsets to callable services (continued)

| Table 10. System C | | alluble services (continueu) |
|--------------------|--------|------------------------------|
| Service | Offset | Function |
| BPX1TSC | 904 | tcsetcp |
| BPX1TSP | 48 | tcsetpgrp |
| BPX1TST | 908 | tcsettables |
| BPX1TYN | 16 | ttyname |
| BPX1UMK | 204 | umask |
| BPX1UMT | 208 | umount |
| BPX1UNA | 376 | uname |
| BPX1UNL | 212 | unlink |
| BPX1UPT | 920 | unlockpt |
| BPX1UQS | 392 | unquiesce |
| BPX1UTI | 216 | utime |
| BPX1VAC | 944 | v_access |
| BPX1VCL | 1188 | v_close |
| BPX1VCR | 620 | v_create |
| BPX1VEX | 876 | v_export |
| BPX1VGA | 632 | v_getattr |
| BPX1VGT | 596 | v_get |
| BPX1VLK | 604 | v_lookup |
| BPX1VLN | 640 | v_link |
| BPX1VLO | 660 | v_lockctl |
| BPX1VMD | 624 | v_mkdir |
| BPX1VOP | 1184 | v_open |
| BPX1VPC | 1040 | v_pathconf |
| BPX1VRA | 616 | v_readlink |
| BPX1VRD | 612 | v_readdir |
| BPX1VRE | 644 | v_rmdir |
| BPX1VRG | 584 | v_reg |
| BPX1VRL | 600 | v_rel |
| BPX1VRM | 648 | v_remove |
| BPX1VRN | 652 | v_rename |
| BPX1VRP | 588 | v_rpn |
| BPX1VRW | 608 | v_rdwr |
| BPX1VSA | 636 | v_settatr |
| BPX1VSF | 656 | v_fstatfs |
| BPX1VSY | 628 | v_symlink |
| BPX1WAT | 380 | wait |
| | | |

Table 16. System control offsets to callable services (continued)

| Service | Offset | Function |
|---------|--------|--------------|
| BPX1WLM | 1048 | wlm |
| BPX1WRT | 220 | write |
| BPX1WRV | 580 | writev |
| BPX1WTE | 840 | waitid/wait3 |
| BPX2ITY | 928 | isatty2 |
| BPX2MNT | 1128 | mount |
| BPX20PN | 1052 | openstat |
| BPX2RMS | 976 | recvmsg2 |
| BPX2SMS | 980 | sendmsg2 |
| BPX2TYN | 924 | ttyname2 |

System control offsets

Appendix B. Mapping macros

Mapping macros map the parameter options in many callable services. The fields with the comment "Reserved for IBM use" are not programming interfaces. A complete list of the options for each macro is listed in the macro in "Macros mapping parameters" on page 433.

Most of the mapping macros can be expanded with or without a DSECT statement. The invocation operand DSECT=YES (default) can be used with either reentrant or nonreentrant programs with the appropriate rules governing the storage backed by the USING.

Many of the mapping macros exploit the fact that DC expands as a DS in a DSECT and as a DC with its initialized value in a CSECT. When these fields are expanded as or within DSECTs, the program is responsible for initializing the necessary fields.

Mapping macros not listed are documented in *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.

Macros mapping parameters

Specifying DSECT=YES (the default for all macros) creates a DSECT. Addressability requires a USING and a register pointing to storage.

Specifying DSECT=NO (exceptions are listed when this is not allowed) allocates space in the current DSECT or CSECT. In reentrant programs, programmers can place these macros in the DSECT with DSECT=NO, and addressability is accomplished without the individual USING required by DSECT=YES. Nonreentrant programs can place their macros in the program's CSECT, and addressability is obtained through the program base register(s).

Specifying LIST=YES (the default for most macros) causes the expansion of the macro to appear in the listing. You can override this by using PRINT OFF.

Specifying LIST=NO removes the macro expansion from the listing.

Additional keywords VARLEN and PREFIX are described in the individual sections where they apply.

BPXYATTR — Map file attributes for v_system calls

```
%GOTO ATTRPRO ;
                            /* Bilingual header
       MACRO
       BPXYATTR &DSECT=YES, &LIST=YES
       GBLB &ATTR411
             (&ATTR411 EQ 1).E411
       AIF
&ATTR411 SETB 1
             ('&LIST' EQ 'YES').A411
       PUSH PRINT BPXYATTR: File attributes for v system calls
       PRINT OFF
            .A411
       AGO
*%ATTRPRO:
*/***START OF SPECIFICATIONS*********************
    $MAC (BPXYATTR) COMP(SCPX1) PROD(BPX):
*01* MACRO NAME: BPXYATTR
*01* DSECT NAME: N/A
*01* DESCRIPTIVE NAME: Attribute Structure for the Logical File System
*02*
     ACRONYM: ATTR
*/*01* PROPRIETARY STATEMENT=
*/*
*/* LICENSED MATERIALS - PROPERTY OF IBM
```

```
*/* THIS MACRO IS "RESTRICTED MATERIALS OF IBM"
*/* 5650-ZOS (C) COPYRIGHT IBM CORP. 1993, 2004
*/* STATUS= HBB7709
                                                                                    */
*/***END_OF_PROPRIETARY_STATEMENT****************************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
        The ATTR maps file attributes that the logical file system is
        interested in.
*01* METHOD OF ACCESS:
*02*
        PL/X:
           %INCLUDE SYSLIB(BPXYATTR)
           By default, the ATTR is based on AttrPtr. If
          other basing is desired, use %ATTRBASE='BASED(XXXXXX)'. If %ATTRBASE='BASED(ATTRPTR)' is coded, a Declare for
*
*
           ATTRPTR is also generated.
           By default, the ATTR uses no VIA. If access
          register usage is desired, code %ATTRVIA='VIA(XXXXXX)'. If %ATTRVIA='VIA(AttrAlet)' is coded, a Declare for
*
*
           AttrAlet is also generated.
*02*
        ASM:
           BPXYATTR DSECT=YES | NO, LIST=YES | NO
*
          With DSECT=NO, storage is allocated in line and addressability is provided thru that DSECT or CSECT. With DSECT=YES, a DSECT is produced and "USING ATTR,reg"
*
          is required for addressability. Here "raddress of ATTR#LENGTH bytes of storage.
                                                  Here "reg" contains the
           The defaults are DSECT=YES and LIST=YES.
*01* SIZE: Release dependent. Refer to the mapping.
*01* POINTED TO BY: In dynamic storage of LFS routines or caller of
                        Vnode interface services.
*01* CREATED BY: LFS Syscall Routines and callers of Vnode interface
                    services
*01* DELETED BY: LFS Syscall Routines or caller of Vnode interface
                    services
*01* STORAGE ATTRIBUTES:
*02*
        SUBPOOL: N/A
*02*
        KEY: N/A
        RESIDENCY: Writeable Storage
*02*
*01* FREQUENCY: 1 per syscall
*01* SERIALIZATION: N/A
*01* DEPENDENCIES: None
*01* NOTES: The following mapping macros are closely related.
                  - Interface between an application and the LFS for
                      BPX1CHA (chattr). It maps the subset of BPXYATTR
                      fields which can be modified, and the set flags. Fields match corresponding fields in BPXYATTR.
                      The overall structures are not related.
                      (Field size and type match, but not the offset.)
                      AttSetFlags, AttGenMask, and AttGenValue structures
                      match AttrSetFlags, AttrGenMask, and AttrGenValue
                      in BPXYATTR.
        BPXYATTR - Vnode interface to the LFS and PFS for file
                      attributes.
                     Fields match corresponding fields in BPXYATT.
AttrStat, AttrStat2, and AttrStat3 structures match
st_Part1, st_Part2, and st_Part3 in BPXYSTAT.
*
*
```

```
BPXYSTAT - Interface between an application and the LFS for
                   BPX1STA (stat). It is the POSIX interface to the LFS
                   for file attributes. The st_Part1, st_Part2, and st_Part3 structures match AttrStat, AttrStat2,
*
*
                   and AttrStat3 in BPXYATTR. The entire BPXYSTAT
*
*
                   structure also matches the stat.h structure.
       BPXZATTR - Prior name of BPXYATTR. To facilitate migration, BPXZATTR includes BPXYATTR. In all new code,
                   BPXYATTR should be used.
*
       BPXYVFSI - C program interface for the BPX1V (v ) services.
                   The ATTR structure in BPXYVFSI matches the BPXYATTR
                   structure.
       stat.h
                 - C program interface for stat(). It is the POSIX C
                   form of BPXYSTAT. The entire stat.h structure
                   matches the BPXYSTAT structure.
*01* COMPONENT: z/OS UNIX (SCPX1)
*01* DISTRIBUTION LIBRARY: AMACLIB
*01* EYE-CATCHER: ATTR
       OFFSET:
*02*
*02*
       LENGTH:
%GOTO ATTRPLS ;
                                  /* Bilingual header
.A411
         ANOP
** BPXYATTR:
                File attributes for callable services
              VRP VLK VRW VCR VMD VSY VGA VSA
('&DSECT' EQ 'NO').B411
** Used By:
         AIF
ATTR
                       DSECŤ,
         AGO
                .C411
.B411
         ANOP
                      DS
                             0D
                                                  Clear storage
ATTR
                      DC
                             XL(ATTR#LENGTH)'00'
                      ORG
                             ATTR
.C411
         ANOP
ATTRBEGIN
                      DS
                             0D
                             טט ATTR Header
C'ATTR'
ATTRHDR
                       DS
ATTRID
                                     Eye Catcher
                             AL1(ATTR#SP)
ATTRSP
                      DC
                                     Subpool number of this ATTR
ATTRLEN
                      DC
                             AL3 (ATTR#LENGTH)
                                     Length of this Attr
stat() structure
ATTRSTAT
                             0D
                      DS
                                     File Mode mapped by BPXYMODE
ATTRMODE
                      DS
                             ΘF
ATTRTYPE
                      DS
                             AL1
                                     First byte of mode is file type,
                                     mapped by BPXYFTYP
ATTRREMMODE
                             AL3
                                     Name to know the last 3 byte
                                     File Serial Number
ATTRINO
                      DS
                             F
                             F
                                     Device ID of the file
ATTRDEV
                      DS
ATTRLINK
                      DS
                             F
                                     Number of links
                                     User ID of owner of the file
Group ID of Group of file
                      DS
                             F
ATTRUID
ATTRGID
                      DS
ATTRSIZE
                      DS
                                     File Size in bytes, for
                             ΘD
                                     regular file. This is
                                     unspecified for others.
                      DS
ATTRSIZE H
                                     First word of size
ATTRSIZE L
                             F
                                     Second word of size
                      DS
                                     Time of last access
Time of last data mod
ATTRATTME
                      DS
                             F
                             F
ATTRMTIME
                      DS
ATTRCTIME
                       DS
                             F
                                     Time of last file stat chng
ATTRMAJORNUMBER
                      DS
                                     Major number for this file,
                                     if it is a character
                                     special file.
ATTRMINORNUMBER
                      DS
                             F
                                     Minor number for this file,
                                     if it is a character
                                     special file.
                                     second part of the stat
Area for auditor audit info
                             0F
ATTRSTAT2
                      DS
ATTRAUDITORAUDIT
                             0F
                      DS
ATTRAUDITORAUDIT1
                      DS
                             XL1
                                      Auditor audit byte 1
ATTRAUDITORAUDIT2
                      DS
                             XL1
                                      Auditor audit byte 2
                                      Auditor audit byte 3
ATTRAUDITORAUDIT3
                      DS
                             XL1
ATTRAUDITORAUDIT4
                      DS
                             XI1
                                      Auditor audit byte 4
                             X'01'
ATTRAAUDIT
                       EOU
                                      ON = auditor audit info
                                            change request
```

```
(ON when AttrMAAudit = ON)
ATTRUSERAUDIT
                                     Area for user audit info
ATTRUSERAUDIT1
                      DS
                             XL1
                                      User audit byte 1
ATTRUSERAUDIT2
                      DS
                                      User audit byte 2
                             XL1
ATTRUSERAUDIT3
                      DS
                             XL1
                                      User audit byte 3
ATTRUSERAUDIT4
                      DS
                             XL1
                                      User audit byte 4
ATTRNOTAAUDIT
                             X'01'
                                      Always OFF to indicate
                                              this is NOT auditor audit
                                              info
ATTRBLKSIZE
                      DS
                                     File Block Size
ATTRCREATETIME
                      DS
                                     File Creation Time
ATTRAUDITID
                             CL16
                                     RACF File ID for auditing
ATTRGUARDTIME
                      ORG
                             ATTRAUDITID
                                            Guard Time
                                                                         @D7A
ATTRGUARDTIMESEC
                       DS
                                               Seconds
                                                                         @D7A
ATTRGUARDTIMEMSEC
                       DS
                             F
                                               Micro_Seconds
                                                                         @D7A
                      ORG
                             ATTRAUDITID
                                                                         @D7A
ATTRCVER
                       DS
                             CI8
                                            Creation Verifier
                                                                         @D7A
                      DS
                             CL8
                                            Spacer
                                                                         @D7A
ATTRRES01
                                     Reserved
ATTRGENMASK
                                     Mask to indicate which
                                     General attributes bit to
                                     modify
                                     -- Masks AttrGenValue
ATTROPAQUEMASK
                      DS
                             XL3
                                     Opaque attribute flags -
                                     Reserved for ADSTAR use
ATTRVISIBLEMASK
                      DS
                             XI1
                                     Visible attribute flags
                             X'20'
ATTRNODELFILESMASK
                      EQU
                                     Files should not be deleted
                                                                         @P1A
                             X'10'
ATTRSHARELIBMASK
                       EQU
                                     Shared Library
                                                                         @D6A
                                     No shareas flag
APF authorized flag
ATTRNOSHAREASMASK
                      EQU
                             X'08'
                                                                         @D8A
ATTRAPFAUTHMASK
                      ΕŲŪ
                             X'04'
                                                                         @D6A
                             X'02'
                                     Program controlled flag
ATTRPROGCTLMASK
                      EQU
                                                                         @D6A
ATTREXTLINKMASK
                      EQU
                             X'01'
                                     External Symlink flag
                                     Mask bit not used on
                                     vn setattr
                             0XL4
ATTRSETFLAGS
                      DS
                                     Flags - which fields to set
ATTRSETFLAGS1
                      DS
                             XL1
                                     Flag byte 1
                             X'80'
X'40'
                                     Change to the mode indicated Change to Owner indicated
ATTRMODECHG
                      EQU
ATTROWNERCHG
                      ΕQU
                             X'20'
ATTRSETGEN
                      EQU
                                     Set General attributes
                             X'10'
                      ΕQŪ
                                     Truncate size
ATTRTRUNC
                             X'08'
ATTRATIMECHG
                                     Change the Atime
                      EQU
ATTRATIMETOD
                      ΕQU
                             X'04'
                                     Change to the Current Time
ATTRMTIMECHG
                      ΕQŪ
                             X'02'
                                     Change the Mtime
                                     Change to the Current Time Flag byte 2
                      EQU
DS
ATTRMTIMETOD
                             X'01'
ATTRSETFLAGS2
                             XL1
                             X'80'
                                     Modify auditor audit info
ATTRMAAUDIT
                      EQU
                             X'40'
X'20'
                                     Modify user audit info Change the Ctime
ATTRMUAUDIT
                      EQU
                      ΕŲŪ
ATTRCTIMECHG
ATTRCTIMETOD
                      ΕQU
                             X'10'
                                     Change Ctime to the Current
                                     Time
ATTRREFTIMECHG
                             X'08'
                                     Change the RefTime
ATTRREFTIMETOD
                      ΕQU
                             X'04'
                                     Change RefTime to Current Time
ATTRFILEFMTCHG
                      ΕÕU
                             X'02'
                                     Change File Format
                                                                         ansa
                      ΕQŪ
                                     Guard Time Check Requested
ATTRGUARDTIMECHK
                             X'01'
                                                                         @D7A
                      DŠ
ATTRSETFLAGS3
                             XL1
                                     Flag byte 3 - reserved
ATTRCVERSET
                      EQU
                             X'80'
                                     Creation Verifier Set
                                                                         @D7A
                      ΕQŪ
                             X'40'
ATTRCHARSETIDCHG
                                     CharSetId Change
                                                                         @D9A
                             X'20'
                      ΕÕU
ATTRLP64TIMES
                                     64-bit time fields used
                                                                         @DDA
                             X'10'
ATTRSECLABELCHG
                      ΕQU
                                     Seclabel Change
                                                                         @DEA
ATTRSETFLAGS4
                      DS
                             XL1
                                     Flag byte 4 - reserved
                                     Third part of the stat
Coded Character set id
ATTRSTAT3
                      DS
                             CL12
ATTRCHARSETID
                      ORG
                             ATTRCHARSETID
                                                                         anga
ATTRFILETAG
                      DS
                             CL4
                                        File Tag
                                                                         @D9A
                      DS
                             CL8
                                        Reserved
                                                                         @D9A
                      ORG
                             ATTRCHARSETID
                                                                         @DFA
ATTRVINFO
                      DS
                             0CL 12
                                        Cross MtPt Information:
                                                                         @DFA
                                          Cross MtPt Vfs Tok
ATTRVFSTOK
                      DS
                             CL8
                                                                         @DFA
ATTRVMTPTINO
                      DS
                             CL4
                                          Root's MtPt's Ino
                                                                         @DFA
ATTRBLOCKS D
                      DS
                             0F
                                     Double word num blocks
ATTRBLOCKS H
                      DS
                                     First word of blocks
ATTRBLOCKS
                                     Number of blocks allocated
                      DS
                             0F
                                     General attribute values
ATTRGENVALUE
                                     --Masked by AttrGenMask
ATTROPAQUE
                                     Opaque attribute flags -
                             XL3
                                     Reserved for ADSTAR use
ATTRVTSTBL F
                      DS
                             XI1
                                     Visible attribute flags
ATTRNODELFILES
                      EQU
                             X'20'
                                     Files should not be deleted
                                                                         @P1A
ATTRSHARELIB
                      EQU
                             X'10'
                                                                         @D8A
                                    Shared Library flag
```

```
ATTRNOSHAREAS
                        EQU
                            X'08'
                                     No shareas flag
                                                                             @D6A
                              X'04'
                                      APF authorized flag
ATTRAPFAUTH
                        ΕQU
                                                                            @D6A
                                      Program controlled flag
External Symlink
                        EÕU
                              X'02'
ATTRPROGCTL
                                                                            @D6A
                              X'01'
ATTREXTLINK
                        ΕŲŪ
ATTRREFTTME
                        DS
                                       Reference Time -
                                       Reserved for ADSTAR use
                                      Align ATTRFID
ATTRFID
                        DS
                              CL8
                                      File Identifier
                                      File Format
ATTRFILEFMT
                        DS
                              XI1
                                                                            @D5A
ATTRFSPFLAG2
                                      IFSP_FLAG2
                        DS
                              XL1
                                                                            @DBA
ATTRACCESSACL
                        EQU
                              X'80'
                                      Access ACL exists
                                                                            @DBA
                              X'40'
ATTRFMODELACL
                        ΕQU
                                      File Model ACL exists
                                                                            @DBA
ATTRDMODELACL
                        ΕQŪ
                              X'20'
                                      Directory Model ACL exists
                                                                            @DBA
ATTRRES02
                              CL2
                                       Reserved for future
                                                                            @DBC
ATTRCTIMEMSEC
                        DS
                                       Ctime Micro Seconds
                                                                            @D7A
                                      Security Label
Reserved for future
                              CL8
ATTRSECLABEL
                        DS
                                                                            @DBA
ATTRRES03
                        DS
                              CL4
                                                                            @DBC
                                      End of Version 1 ATTR
ATTRENDVER1
                       EQU
                             *
ATTRATIME64
                                       Access Time
                                      Data Mod Time
ATTRMTIME64
                        DS
                                                                            @DAA
                                      Medadata Change Time
ATTRCTIME64
                        DS
                              D
                                                                            @DAA
ATTRCREATETIME64
                        DS
                                      File Creation Time
                              D
                                                                            @DAA
ATTRREFTIME64
                        DS
                              D
                                      Reference Time
                                                                            @DAA
                        DS
                               D
                                                                            @DAA
                        DS
                              CL16
                                      Reserved
                                                                            @DAA
ATTRENDVER2
                        EQU
                                      End of Version 2 ATTR
                                                                            @DAA
    Constants
ATTR#LEN
                       EQU
                             *-ATTRBEGIN
                                         Length of ATTR
                              ATTR#LEN Length of ATTR
                        EQU
ATTR#LENGTH
                             ATTRENDVER1-ÄTTRBEGIN
ATTR#MINLEN
                        ΕQ̈́U
                                        Minimum length of valid ATTR Subpool for the ATTR
ATTR#SP
                        EOU 2
** BPXYATTR End
          SPACE 3
                 ('&LIST' EQ 'YES').E411
          AIF
          POP
                 PRINT
.E411
          ANOP
          MEND
                                      Terminating PL/X comment
                                                                               */
*%ATTRPLS : ;
                                                                         @EJECT:
* %IF ATTRBASE = '' %THEN
    %D0;
      %ATTRBASE = 'Based(AttrPtr)';
* %IF TRANSLATE(ATTRBASE) = 'BASED(ATTRPTR)' %THEN
   %D0;
      DCL AttrPtr Ptr(31);
                                         /* Pointer to the ATTR
 %IF TRANSLATE(ATTRVIA) = 'VIA(ATTRALET)' %THEN
     %D0;
*
       Dcl AttrAlet Ptr(31);
                                        /* Alet of the ATTR
*
     %END;
*%IF AsaxmacF63 = ''
    %Then %AsaxmacF63 = 'Char(8)';
                                                                       /* @DCA*/
*Dcl
                    ATTRBASE ATTRVIA,
* 1
       Attr
       AttrHdr,
                                      /* +00 Attr Header
*
                                                                          @D2A*/
                    Char(4)
                                       /* +00 EBCDIC ID
*
     5 AttrID
                                                                          @D2C*/
     5 AttrSP
                    Fixed(8),
                                      /* +04 Subpool number of this Attr
                                                                          @D2C*/
                                      /* +05 Length of this Attr
/* +08 stat() structure
     5 AttrLen
                    Fixed(24),
                                                                          @D2C*/
       AttrStat.
                                              File Mode mapped by BPXYMODE*/
First byte of mode is file
type, mapped by BPXYFTYP */
     5 AttrMode
                                      /*
                        Fixed(32),
        7 AttrType
                        Fixed(8),
                                      /* Name to know the last 3 byte*/
/* +0C File Serial Number */
       7 AttrRemMode Fixed(24),
                        Fixed(32),
     5 AttrIno
                                      /* +10 Device ID of the file
/* +14 Number of links
     5 AttrDev
                        Fixed(32),
     5 AttrLink
                         Fixed(32),
                                      /* +18 User ID of owner of the file*/
                        Fixed(31),
     5 AttrUid
                        Fixed(31), /* +10 user 10 of which of the 12.
Fixed(31), /* +1C Group ID of Group of file

8) Bdy(8), /* +20 File Size in bytes, for regular file. This is
     5 AttrGid
     5 AttrSize Char(8) Bdy(8),
                                                 unspecified, for others. */
```

```
7 AttrSize_h Fixed(31), /* +20 First word of size
        7 AttrSize_1
                       Fixed(32), /* +24 Second word of size
                        Fixed(31),
                                    /* +28 Time of last access
/* +2C Time of last data mod
*
     5 AttrAtime
                                                                       @P0C*/
                        Fixed(31),
                                                                       @P0C*/
     5 AttrMtime
     5 AttrCtime
                        Fixed(31),
                                     /* +30 Time of last file stat chng
                                                                       @POC*/
  3 AttrMajorNumber Fixed(32),
                                     /* +34 Major number for this file,
                                               if it is a character
                                               special file.
  3 AttrMinorNumber Fixed(32),
                                     /* +38 Minor number for this file,
                                               if it is a character
                                               special file.
                                     /* +3C second part of the stat
       AttrStat2.
     5 AttrAuditorAudit Bit(32),
                                     /* +3C Area for auditor audit info */
                          Bit(31),
                                               First 31 bits
                                                                       @D1A*/
                                     /*
       7 AttrAAudit
                          Bit(1),
                                               ON = auditor audit info
                                                    change request
                                               (ON when AttrMAAudit = ON)
                                                                       @D1A*/
     5 AttrUserAudit
                          Bit(32),
                                    /* +40 Area for user audit info
                          Bit(31),
                                               First 31 bits
                                                                       @D1A*/
                                               Always OFF to indicate
       7 AttrNotAAudit Bit(1),
                                               this is NOT auditor audit
*
*
                                               info
                                                                       @D1A*/
     5 AttrBlkSize Fixed(31), /* +44 File Block Size 5 AttrCreateTime Fixed(31), /* +48 File Creation Time 5 * UNION Char(16) Bdy(Word),
                                                                       @P0C*/
                                                                      /*@D7A*/
       7 AttrAuditID
                          Char(16), /* +4C RACF File ID for auditing
*
                                            Guard Time Value:
       7 AttrGuardTime
                                                                       @D7A*/
         AttrGuardTime , /* Guard Time value:
8 AttrGuardTimeSec Fixed(32), /* Seconds - compare
                                                                       @D7A
                                      against either AttrCtime or
                                      AttrCtime64L
                                                                       @DCA*/
*
*
         8 AttrGuardTimeMsec Fixed(32),
                                                 /* Micro-seconds
                                                                       @D7A*/
       7 AttrCver
                          Char(8), /*
                                             Creation Verifier
                                                                       @D7A*/
     5 *
                         Fixed(32), /* +5C Reserved
                                                                            */
   3 AttrGenMask Bit(32),
                                     /* +60 Mask to indicate which
                                             General attributes bit to
                                             modify
                                             --Masks AttrGenValue
     5 AttrOpaqueMask
                          Bit(24),
                                             Opaque attribute flags -
                                             Reserved for ADSTAR use @D1A*/
                                             Visible attribute flags @D1A*/
Reserved @D8C @P1C*/
     5 AttrVisibleMask Bit(8), 7 AttrRsvMask Bit(2),
                                             Reserved
                                             Files should not be deleted
       7 AttrNoDelFilesMask Bit(1),/*
                                             from directory
       7 AttrShareLibMask Bit(1), /*
                                             Shared Library
                                                                       @D8A*/
                                             do not run in shareas
Program is APF auth
       7 AttrNoShareasMask Bit(1), /*
                                                                       @D6A*/
       7 AttrApfAuthMask Bit(1), /*
*
                                                                       @D6A*/
       7 AttrProgCtlMask Bit(1), /*
                                             Program controlled
                                                                       @D6A*/
       7 AttrExtLinkMask Bit(1), /*
                                             External Symlink flag
                                             Mask bit not used on
                                                                       @D1A*/
                                             vn_setattr
                                     /* +64 Flags - which fields to set */
   3 AttrSetFlags
                      Bit(32)
     5 AttrModeChg
                           Bit(1),
                                             Change to the mode indicated*/
     5 AttrOwnerChg
                           Bit(1),
                                             Change to Owner indicated
                           Bit(1),
                                             Set General attributes @D1A*/
     5 AttrSetGen
                                                                       @D2C*/
     5 AttrTrunc
                           Bit(1),
                                             Truncate size
                         Bit(1),
       AttrATimeChg
                                     /*
                                             Change the Atime
     5 AttrAtimeTOD
                         Bit(1),
                                             Change to the Current Time
     5 AttrMTimeChg
                         Bit(1),
                                             Change the Mtime
                                             Change to the Current Time
                         Bit(1),
     5 AttrMtimeTOD
                      Bit(1),
                                     /*
                                             Modify auditor audit info
     5 AttrMAAudit
     5 AttrMUAudit
                      Bit(1),
                                     /*
                                             Modify user audit info
     5 AttrCTimeChg
                      Bit(1),
                                             Change the Ctime
                                                                       @D1A*/
     5 AttrCTimeTOD
                      Bit(1),
                                             Change Ctime to the Current
                                             Time
                                                                       @D1A*
                                             Change the RefTime
     5 AttrRefTimeChg
                           Bit(1),
                                                                       @D1A*/
     5 AttrRefTimeTOD
                           Bit(1),
                                             Change RefTime to Current Time
                                                                       @D1A*/
                                             Change the File Format
Guard Time Check Req
     5 AttrFileFmtChg
                           Bit(1),
                                                                       @D5A*/
     5 AttrGuardTimeChk Bit(1),
                                     /*
                                                                       @D7A*/
                          Bit(1),
                                     /*
     5 AttrCverSet
                                             Creation Verifier Set
                                                                       @D7A*/
       AttrCharSetIdChg Bit(1),
                                     /*
                                             Change File Info
                                                                       @D9A*/
                          Bit(1),
                                             64-bit time fields used @DCA*/
     5 AttrLP64Times
     5 AttrSecLabelChg
                                             Change Security Label
                          Bit(1)
                                                                       @DEA*/
                          Bit(12),
                                             Reserved bits
                                                                       @DEC*/
  3 AttrStat3,
                                   /* +68 Third part of the stat
```

```
5 * UNION,
                                                                      @DFA*/
       7 AttrCharSetID Char(12),
                                    /* +68 Character Set Information
                                   /*
                                               File Tag
                                                                      @D9A*/
*
         9 AttrFileTag Char(4),
                         Char(8),
                                    /*
                                               Reserved
                                                                      @D9A*/
                        Char(12),
                                            v_readdir/v_getattr Info@DFA*/
    Cross MtPt Vfs Tok      @DFA*/
       7 AttrVInfo
         9 AttrVfsTok
                        \mathsf{Char}(8),
                                    /*
         9 AttrVMtPtIno Char(4),
                                               Root's MtPt's Ino
     5 AttrBlocks_D Char(8) Bdy(word),/* +74 Double word num blocks */ 7 * Fixed(31),
       7 AttrBlocks Fixed(32),
                                     /* +78 Number of blocks allocated */
     5 AttrGenValue Bit(32),
                                    /* +7C General attribute values
                                         --Masked by AttrGenMask
*
                          Bit(24), /*
                                            Opaque attribute flags
       7 AttrOpaque
                                            Reserved for ADSTAR use @D1A*/
                          Bit(8),
                                            Visible attribute flags @D1A*/Reserved @D8C @P1C*/
       7 AttrVisible
         9 AttrRsv
                           Bit(2),
                                            Reserved
                                            Files should not be deleted
         9 AttrNoDelFiles Bit(1), /*
                                            from directory
                                                                      @P1A*/
            AttrShareLib Bit(1), /*
*
                                            Shared Library
                                                                      @D8A*/
            AttrNoShareas Bit(1), /*
                                            do not run in shareas
                                                                      @D6A*/
            AttrApfAuth Bit(1), /*
                                            Program is APF auth
                                                                      @D6A*/
            AttrProgCtl Bit(1),
AttrExtLink Bit(1),
                                            Program controlled
                                    /*
                                                                      @D6A*/
                                    /*
*
                                            External Symlink
                                                                      @D1A*/
                                    /* +80 Reference Time
*
     5 AttrRefTime
                     Fixed(31),
                                            Reserved for ADSTAR use @D1A*/
     5 AttrFid Char(8) Bdy(Word), /* +84 File Identifier
                                                                      @D2A*/
     5 AttrFileFmt Fixed(8),
                                    /* +8C File Format
                                                                      @D5A*/
                                            Value constants for filefmt */
                                     /*
                                            declared in BPXYFTYP
                                     /*
                                                                     @D5A*/
                                     /********
                                                                     *****
                                     /* +8D byte maps IFSP_FLAG2 - @I
/* These flags are copied by
     5 AttrFspFlag2 Bit(8),
                                                                      @DBA*/
                                            HFS directly into this field.
                                            The bit positions match those defined in the FSP. @DBA*
       7 AttrAccessAcl Bit(1),
                                    /* 1 = Access Acl exists
/* 1 = File Model Acl exists
                                                                      @DBA*/
       7 AttrFModelAcl Bit(1),
                                                                      @DBA*/
                                    /* 1 = Dir Model Acl exists
       7 AttrDModelAcl Bit(1),
                                                                      @DBA*/
                        Bit(5),
                                     /* Reserved for future fsp use @DBA*,
                                     5 * Char( 2),
5 AttrCtimeMsec Fixed(32),
                                                                      @DBC*
                                     /★ +8F Reserved for future
                                     /* +90 Micro-seconds of Ctime
                                                                      @D7A*/
     5 AttrSecLabel Char(8),
                                    /* +94 Security Label
                                                                      @DBA*/
                                    /* +9C Reserved for future
                      Char(4).
                                                                      @DBC*/
   3 AttrEndVer1
                      Char(0).
                                    /* +A0--- End of Version 1 --- @D2C*/
   3 AttrStat4
                                     /* +AO Fourth part of the stat @DAA*/
                          /* +A0 LP64 Versions
Char(8) Bdy(DWord), /*+A8 Access Time
     5 AttrLP64
       7 AttrAtime64
                                                                      @DAA*/
         9 AttrAtime64S AsaxmacF63 Bdy(DWord), /* Signed value
                                                                      @DCA*/
                                                                   /* @DCA*/
*
                           Char(4)
           11 AttrAtime64L Fixed(31), /* @DCA*/
ttrMtime64 Char(8) Bdy(DWord), /*+B0 Data Mod Time @DAA*/
AttrMtime64S AsaxmacF63 Bdy(DWord), /* Signed value @DCA*/
       7 AttrMtime64
         9 AttrMtime64S
                                                                   /* @DCA*/
           11 *
                           Char(4)
            11 AttrMtime64L Fixed(31)
                                                                   /* @DCA*/
       7 AttrCtime64
                           Char(8) Bdy(DWord), /*+B8 Metadata
                                                   Change Time
                                                                      @DAA*/
         9 AttrCtime64S AsaxmacF63 Bdy(DWord), /* Signed value @DCA*/
            11 *
                           Char(4),
                                                                   /* @DCA*/
            11 AttrCtime64L Fixed(31), /* compare w/AttrGuardTime @DCA*/
       7 AttrCreateTime64 Char(8) Bdy(DWord),/*+C0 File
                                                    Creation Time
                                                                      @DAA*/
         9 AttrCreateTime64S AsaxmacF63 Bdy(DWord), /* Signed
                                                                      @DCA*/
           11 * Char(4),
11 AttrCreatetime64L Fixed(31)
                                                                   /* @DCA*/
                                                                   /* @DCA*.
       7 AttrRefTime64 Char(8) Bdy(DWord), /*+C8 Reference Time@DAA*/
         9 AttrReftime64S AsaxmacF63 Bdy(DWord), /* Signed
                                                                      @DCA*/
           11 * Char(4),
11 AttrReftime64L Fixed(31),
Char(8), /*+D0 May be AttrIno64
                                                                   /* @DCA*/
*
                                                                   /* @DCA*/
*
                                                                      @DAA*/
                        Char(16), /* +D0 Reserved (1st consider @DAA
                                    space at +5C,+8D,+94)
/* +E0 End of Version 2
                                                                      @DAA*/
   3 AttrEndVer2 Char(0),
                                                                      @DAA*/
     /************************************
     /* Add fields here for Version 3.
     /* NOTE that the increased length of the ATTR will have
     /* migration considerations in the code that handles ATTR's.
      3 * Char(0) Bdy(Dword); /* +E0 Ensure ATTR ends on doubleword
```

```
* boundary */

*
*DCL

* ATTR#ID Char(4) Constant('ATTR'), /* Control Block Acronym*/

* ATTR#LEN Fixed(24) Constant(Length(ATTR)), /* Length of ATTR */

* ATTR#MINLEN Fixed(24) Constant(Offset(AttrEndVer1)), /* Minimum

* length of valid ATTR @D2A*/

* ATTR#VER2LEN Fixed(24) Constant(Offset(AttrEndVer2)), /* Length

* of version 2 @DCA*/

* ATTR#SP Fixed(8) Constant(2); /* Subpool for the ATTR */
```

BPXYNREG — Map interface block to vnode registration

```
/* Bilingual header
         %GOTO NREGPRO ;
         MACRO
         BPXYNREG &DSECT=YES, &LIST=YES
         GBLB &NREG411
         AIF
                (&NREG411 EQ 1).E411
&NREG411 SETB 1
         AIF ('&LIST' EQ 'YES').A411
PUSH PRINT BPXYNREG: BPX2REG (v_reg) parameter list
         PRINT OFF
         AGO
                .A411
*%NREGPRO:
*/***START OF SPECIFICATIONS************************
     $MAC (BPXYNREG) COMP(SCPX1) PROD(BPX):
*01* MACRO NAME: BPXYNREG
*01* DSECT NAME: N/A
*01* DESCRIPTIVE NAME: Interface Block to VNode Registration
*02*
      ACRONYM: NREG
*/*01* PROPRIETARY STATEMENT=
*/*
*/* LICENSED MATERIALS - PROPERTY OF IBM
*/* THIS MACRO IS "RESTRICTED MATERIALS OF IBM" */* 5650-ZOS (C) COPYRIGHT IBM CORP. 1993, 2003
*/* STATUS= HBB7709
*/***END_OF_PROPRIETARY_STATEMENT***************************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION:
       The NREG maps the input to the v register routine, BPXVNREG.
*01* METHOD OF ACCESS:
*02*
     PL/X:
         %INCLUDE SYSLIB(BPXYNREG)
         By default, the NREG is based on NRegPtr. If
         other basing is desired, use %NREGBASE='BASED(XXXXXX)'.
If %NREGBASE='BASED(NREGPTR)' is coded, a Declare for
         NREGPTR is also generated.
*02*
       ASM:
         With DSECT=NO, storage is allocated in line and addressability is provided thru that DSECT or CSECT.
         With DSECT=YES, a DSECT is produced and "USING NREG, reg"
         is required for addressability. Here "reg" contains the address of NREG#LEN bytes of storage.
         The default is DSECT=YES.
*01* SIZE: Release dependent. Refer to the mapping.
```

```
*01* POINTED TO BY: In dynamic storage of routines calling BPXVNREG.
*01* CREATED BY: Caller of Syscall Routine
*01* DELETED BY: Caller of Syscall Routine
*01* STORAGE ATTRIBUTES:
*02*
      SUBPOOL: n/a
*02*
       KEY: n/a
*02*
      RESIDENCY: Callers storage
*01* FREQUENCY: 1 per syscall that calls BPXVNREG
*01* SERIALIZATION: N/A
*01* DEPENDENCIES: None
*01* NOTES:
            BPXYVFSI is a C program interface for the BPX1V (v_{-})
            services.
                       The NREG structure in BPXYVFSI matches
            the BPXYNREG structure.
*01* COMPONENT: z/OS UNIX (SCPX1)
*01* DISTRIBUTION LIBRARY: AMACLIB
                                                                   @P1C
*01* EYE-CATCHER: NREG
      OFFSET:
*02*
*02*
      LENGTH:
****END OF SPECIFICATIONS***********************************
         %GOTO NREGPLS ;
                                 /* Bilingual header
.A411
         ANOP
** BPXYNREG: NREG - LFS Registration routine parameter list
** Used By: VRG
               ('&DSECT' EQ 'NO').B411
         AIF
                     DSECT,
NREG
               .C411
         AGO
.B411
         ANOP
                     DS
NREG
                     DC
                            XL(NREG#LENGTH)'00'
                     ORG
                           NRFG
.C411
         ANOP
NREGBEGIN
                     DS
                           0D
                           C'NREG'
NREGID
                     DC
                                               Eve catcher
                           AL2(NREG#LENGTH)
                     DC
NREGLEN
                                               Length of the structure
                     DC
NREGVER
                           AL2(NREG#VERSION)
                                               NReg version number
                                               Server Type
NREGSTYPE
                     DS
NREGSNAMELEN
                     DS
                                               Length of Server name
NREGSNAME
                     DS
                           CL32
                                               Server Name
                                               Max # of VNTokens
NREGMAXVNTOKENS
                     DS
NREGFLAGS
                     DS
                           CL1
                                               Flags
                                                                     @D4C
NREGFXHOTC
                     EQU
                           X'80'
                                                Exit uses HOTC
                                                                     @D4A
NREGNOWAIT
                     ΕŌU
                           X'40'
                                               for Quiesced FS
                                                                     @D5A
                                                for SFD severs
                     ΕQŪ
                           X'20'
                                                                     @P3A
NREGSECSFD
                           X'10'
NREGALLOCDEVNO
                     ΕQU
                                                allocate a devno
                                                                     @D6A
NREGRES01
                     DS
                           CL3
                                               Reserved field
                                                                     @D4C
NREGENDOFVER1
                     DS
                                               End of Version 1
                                                                     @D4A
                                               Exit program name
NREGFXEXITNAME
                     DS
                           CL8
                                                                     @D4A
                     DS
NREGEXTNTTPARM
                           CL8
                                               Init parm for Exit
                                                                     @D4A
NREGABENDCODE
                     DS
                                               Abend Code received
                                                                     @D4A
NREGABENDRSN
                     DS
                                               Abend Reason Code
                                                                     @D4A
                     ORG
                           NREGABENDRSN
                                                                     @D6A
NREGDEVNO
                     DS
                                                 or Output Devno
                                                                     @D6A
NREGPESTYPE
                     DS
                           CL8
                                               Dependant PFS
                                                                     @D5A
    Constants
NREG#LENGTH
                     EQU
                            *-NREGBEGIN
                                               Length of NREG
                           NREGENDOFVER1-NREGBEGIN Length of V1 NREG
NREG#LENGTHVER1
                     ΕQŪ
NREG#VERSION1
                     EQU
                                               NReg Version 1
NREG#VERSION2
                     EÕU
                                               NReg Version 2
NREG#VERSION
                     ΕQU
                           NREG#VERSION2
                                               NReg Current Version
       NRegSType constants
NREGSTYPE#FILE
                     EQU
                           1
                                               File Server type
NREGSTYPE#LOCK
                     EQU
                                               Lock Server type
NREGSTYPE#FEXP
                     ΕQŪ
NREGSTYPE#SFDS
                     EÕU
                                               SFD server
                                                                     @P3A
NREGSTYPE#MAX
                     EQU
                            4
                                               Max allowed srvr type
** BPXYNREG End
        SPACE 3
```

```
('&LIST' EQ 'YES').E411
         POP
                PRINT
.E411
         ANOP
                                    Terminating PL/X comment
                                                                         */
         MEND
*%NREGPLS:
*%IF NREGBASE='' %THEN
     %NREGBASE='BASED(NREGPTR)';
*%IF TRANSLATE(NREGBASE)='BASED(NREGPTR)' %THEN
     DCL NRegPtr Ptr(31);
                                    /* Pointer to NReg parameter list */
   %END;
*DCL
 1
       NReg
                   NREGBASE,
                        Char(4),
       NRegID
                                    /* +00 EBCDIC ID
*
       NRegLen
                        Fixed(15), /* +04 Length of NREG structure@P2C*/
       NRegVer
                        Fixed(16), /* +06 NReg Version number
   3
       NRegSType
                        Fixed(32), /* +08 Server type
       NRegSNameLen
                        Fixed(31), /* +0C Length of Server name parm
                        Char(32),
       NRegSName
                                    /* +10 Server Name
       NRegMaxVNTokens Fixed(32), /* +30 Max # of VNTokens that will
*
                                           be created for this server
   3
       NRegFlags
                        Bit(8),
                                    /* +34 Flags
                                                                     @D4C*/
                         Bit(1),
        NregFxHotc
                                            Invoke Exit with HOTC
                                                                     @D4A*/
                         Bit(1),
                                            for Quiesced File Sys
        NregNoWait
                                    /*
                                                                     @D5A*/
                         Bit(1),
                                            Secondary SFD srvr
                                    /*
                                                                     @P3A*/
        NregSecSfd
*
       NregAllocDevno
                         Bit(1),
                                    /*
                                            Allocate a Devno
                                                                     @D6A*
                        Char(3),
   3
                                    /* +35 Reserved
                                                                     @D4C*/
                        Char(0),
*
       NRegEndOfVer1
                                    /* +38 End of Ver1 -----
                                                                     @D4A*/
       NRegFileExporterArea,
                                                                     @D4A*/
       NregFxExitName Char(8),
                                                                     @D4A*
                                    /* +38 Exit program name
        NregFxInitParm Char(8)
                                    /* +40 Init parm for Exit pgm
                                                                     @D4A*/
   3 NRegAbendCode
                        Fixed(32), /* +48 Abend Code received
                                                                     @D4A*/
                                    /* +4C Abend Reason Code
   3 NRegAbendRsn
                        Fixed(32)
                                                                     @D4A*/
                         Fixed(32),
                                     /*
     5 NRegDevno
                                           or Output Devno
                                                                     @D6A*/
                                    /* +50 Dependant PFS
   3 NRegPfsType
                        Char(8),
                                                                     @D5A*/
   3 * Char(0) Bdy(Dword);
                                    /* +58 Ensure NREG ends on
                                           doubleword boundary
*DCL
                            Constant('NREG'),/* Control Block Acronym */
   NReg#ID
                  Char(4)
                  Fixed(15) Constant(Length(NREG)),/\star Length of NREG \star/
   NReg#LEN
                            Constant(NReg#Version2),/* Current
   NReg#Version
                 Fixed(16)
                                             /★ Version 1 of NReg
   NReg#Version1 Fixed(16) Constant(1),
   NReg#LenVer1 Fixed(16) Constant(Offset(NRegEndOfVer1)),
                                                                   /*@D4A*/
   NReg#Version2 Fixed(16) Constant(2);
                                              /* Version 2 of NReg @D4A*/
   /* NRegSType constants
*DCL
   NRegSType#FILE Fixed(32) Constant(1),/* File Server
                                                                     @D1C*/
   NRegSType#LOCK Fixed(32) Constant(2),/* Lock Server
                                                                     @D1A*/
   NregSType#FEXP Fixed(32) Constant(3)
   NRegSType#SFDS Fixed(32) Constant(4),/* SFD server @P3A*/NRegSType#MAX Fixed(32) Constant(4);/* Max allowed srvr type @P3C*/
        /* Note: If new Server types are added, DISPLAY OMVS should
              be updated as follows:
              (1) In BPXZMDEF, msg BPX040If, add a type to the array.(2) Recompile BPXMIMST.
```

BPXYOSS — Specific information for the Map operating system

The numbers of file blocks read and written, along with the number of directory blocks processed, are returned in the OssReadIBC, OssWriteIBC, and OssDirIBC, fields of the OSS. On return from the VFS Callable Service API, the block counts present initially in the OSS have been incremented to reflect the counts for this call to the service. Thus, to obtain the numbers of blocks that are processed on a particular call to a VFS Callable Service API, set the block count fields to zero before calling the service. To accumulate the block counts across a series of calls, pass the same OSS to each, without modifying the count fields.

The following OSS fields must be provided by the caller:

OssId

Contains OSS.

OssLen

Specifies the length of the OSS structure, OSS#LENGTH.

OSSReadIBC

Contains number of blocks read.

OSSWriteIBC

Contains number of blocks written.

OSSDirIBC

Contains number of directory blocks processed.

```
/* Bilingual header
          %GOTO OSSPRO ;
          MACRO
          BPXYOSS
                   &DSECT=YES,&LIST=YES
          GBLB &OSS411
                 (&0SS411 EQ 1).E411
          AIF
&OSS411 SETB
                 ('&LIST' EQ 'YES').A411
          AIF
          PUSH PRINT BPXYOSS: Operating System Specific Information
          PRINT OFF
          AGO
                 .A411
*%OSSPRO:
*/***START OF SPECIFICATIONS***********************
     $MAC (BPXYOSS) COMP(SCPX1) PROD(BPX):
*01* MACRO NAME: BPXYOSS
*01* DSECT NAME: OSS
*01* DESCRIPTIVE NAME: Operating System Specific Information
*02*
       ACRONYM: OSS
*/*01* PROPRIETARY STATEMENT=
*/***PROPRIETARY_STATEMENT***********************
                                                                               */
*/* LICENSED MATERIALS - PROPERTY OF IBM
*/* THIS MACRO IS "RESTRICTED MATERIALS OF IBM"
*/* 5650-ZOS (C) COPYRIGHT IBM CORP. 1993, 2005
*/* STATUS= HBB7720
*/***END_OF_PROPRIETARY_STATEMENT***************************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION:
       To pass information specific to the z/OS UNIX implemenation of the VFS/VNODE interface.
*01* METHOD OF ACCESS:
       PL/X:
*02*
          %INCLUDE SYSLIB(BPXYOSS)
          By default, the OSS is based on OssPtr. If other basing is desired, use %OSSBASE='BASED(XXXXXX)'. If %OSSBASE='BASED(OssPtr)' is coded, a Declare for
          OssPtr is also generated.
          Typical Syscall usage: %OSSBASE = 'Based(Addr(InputOss))'
*02*
       ASM:
          With DSECT=NO, storage is allocated in line and addressability is provided thru that DSECT or CSECT.
          With DSECT=YES, a DSECT is produced and "USING OSS,reg" is required for addressability. Here "reg" contains the
          address of OSS#LENGTH bytes of storage.
          The default is DSECT=YES.
```

```
*01* SIZE: OSS#LENGTH
*01* POINTED TO BY: OssPtr
*01* CREATED BY: Storage obtained by caller of system call
*01* DELETED BY: Caller of system call
*01* STORAGE ATTRIBUTES:
       SUBPOOL/DATASPACE:
*02*
*02*
       KEY:
                            N/A
*02*
       RESIDENCY:
                            N/A
*01* FREQUENCY: 1 per syscall of a vnode op
*01* SERIALIZATION: N/A
*01* DEPENDENCIES: None
*01* NOTES:
            BPXYVFSI is a C program interface for the BPX1V (v_)
            services. The OSS structure in BPXYVFSI matches
            the BPXYOSS structure.
*01* COMPONENT: z/OS UNIX (SCPX1)
*01* DISTRIBUTION LIBRARY: AMACLIB
*01* EYE-CATCHER: OSS
*02*
      OFFSET: 0
*02*
       LENGTH:
/* Bilingual header
         %GOTO OSSPLS
                        ;
.A411
         ANOP
** BPXYOSS: OSS - Operating System Specific Information
** Used By: v_ callable services
AIF ('&DSECT' EQ 'NO').B411
0SS
                      DSECT ,
         AGO
                .C411
.B411
         ANOP
                      DS
                            0D
                                                Clear storage
0SS
                            XL(OSS#LENGTH)'00'
                      DC
                      ORG
                            0SS
.C411
         ANOP
OSSBEGIN
                      DS
                            0D
OSSID
                            C'OSS '
                      DC
                                                Eye catcher
                                                Length of the structure
Directory I/O block cnt
OSSLEN
                      DC
                            AL4(OSS#LENGTH)
OSSDIRIBC
                      DS
OSSREADIBC
                      DS
                                                Read I/O block cnt
                                                Write I/O block cnt
OSSWRITEIBC
                      DS
                            F
OSSOPENFLAGS
                      DS
                            F
                                                Reserved for internal
                                                use - open flags
                      ORG
                            OSSOPENFLAGS
                                                                  @P2C@P1A
OSSFLAGS1
                                                                      @P1A
                      DS
                            В
                            X'80
                                                                      @P1A
                                                 Cross Mount Points
OSSXMTPT
                      EQU
                      DS
                            CL3
                                                                      @P1A
OSSOPENTOKEN
                      DS
                            CL8
                                                V_Open Token
                                                                      @D4A
    Constants
OSS#LENGTH
                      EQU
                            *-OSSBEGIN
                                                Length of OSS
** BPXYOSS End
         SPACE 3
         ATF
                ('&LIST' EQ 'YES').E411
                                                                  6@D1A
         POP
               PRINT
         ANOP
.E411
         MEND
                                    Terminating PL/X comment
                                                                         */
*%0SSPLS : ;
*%Dcl OSSBASE2 Char Ext;
                                   /* Settable by other macros
                                                                     @D2A*/
*%IF OSSBASE = '' %THEN

* %IF OSSBASE2 = '' %THEN
                                                                   /*@D2A*/
     %D0;
       %OSSBASE = 'BASED(OssPtr)';
     %END;
  %ELSE %OSSBASE = OSSBASE2;
                                                                   /*@D2A*/
*%IF Translate(OSSBASE) = 'BASED(OSSPTR)' %THEN
```

```
%D0;
      DCL OssPtr Ptr(31);
                                       /* Pointer to the OSS
   %END;
*DCL
* 1 OSS OSSBASE ,
                                        /* Operating System Specific Info */
                      Char(4),
                                        /* Eye catcher - 'OSS '
    3 OssId
                     Fixed(31),
    3 OssLen
                                       /* Length of structure
    3 OssAcctIBC,
                                        /* I/O Block Counts
                                        /* Directory I/O block cnt
/* Read I/O block cnt
      7 OssDirIBC Fixed(32),
7 OssReadIBC Fixed(32),
                                                                             @01C*/
                                                                             @01C*/
      7 OssWriteIBC Fixed(32),
                                            Write I/O block cnt
                                                                             @01C*/
    3 OssOpenFlags Bit(32),
                                        /* Reserved for internal use -
                                           open flags for internal v_rdwr
                                                                        @P2M@D3A*/
                                            callers
                        Bit(1),
       5 OssXmtpt
                                            Cross Mount Points
                                                                            @P1A*/
                                        /* V Open Token
    3 OssOpenToken Char(8),
                                                                        @D4A@P2D*/
       5 OssOpenTokSpec Char(4);
                                      /* Special Token Values @D4A@P2D*/
*DCL
* Oss#ID Char(4) Constant('OSS'),
                                                /* Eye catcher
* Oss#Len Fixed(31) Constant(Length(Oss));/* Length of Oss
                                                                             @D4A*/
                /* Special Values for OssOpenTokSpec
* (Oss#NoTokAdvChk Constant(0), /* Advisory Check, vs. V4 @D4A*/
* Oss#NoTokMandChk Constant(2), /* Mandatory Check, vs. all @D4A*/
* Oss#NoTokOverride Constant(1) ) /* No Checks, for Reads only @D4A*/
                                  Fixed(32);
                                                                           /*@D4A*/
```

BPXYVLOK — Map the interface block for v_lockctl

The BPXYVLOK macro maps the interface block to pass locking information via the v lockctl service.

```
%GOTO VLOKPRO;
                                  /* Bilingual header
         BPXYVLOK &DSECT=YES, &LIST=YES
         GBLB &VLOK411
               (&VLOK411 EQ 1).E411
         ATF
&VLOK411 SETB 1
               ('&LIST' EQ 'YES').A411
         PUSH PRINT BPXYVLOK: Vnode Byte Range Locking Structure
         PRINT OFF
         AGO
              .A411
*/***START OF SPECIFICATIONS************************
     $MAC (BPXYVLOK) COMP(SCPX1) PROD(BPX):
*01* MACRO NAME: BPXYVLOK
*01* DSECT NAME: VLOK
*01* DESCRIPTIVE NAME: Vnode Services Byte Range Locking Structure
*02* ACRONYM: VLOK
*/*01* PROPRIETARY STATEMENT=
*/***PROPRIETARY_STATEMENT*********************
*/*
*/* LICENSED MATERIALS - PROPERTY OF IBM
*/* THIS MACRO IS "RESTRICTED MATERIALS OF IBM"
*/* 5650-ZOS (C) COPYRIGHT IBM CORP. 1993, 2005
*/*
*/* STATUS= HBB7720
*/***END_0F_PROPRIETARY_STATEMENT****************************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION:
```

```
To pass locking information about the V_lockctl interface.
*01* METHOD OF ACCESS:
*02*
       PL/X:
         %INCLUDE SYSLIB(BPXYVLOK)
         By default, the VLOK is based on VLOKPtr. If
*
         other basing is desired, use %VLOKBASE='BASED(XXXXXX)'. If %VLOKBASE='BASED(VLOKPtr)' is coded, a Declare for
*
         VLOKPtr is also generated.
*
         Typical Syscall usage: %VLOKBASE = 'Based(Addr(InputVLOK))'
*
*02*
       ASM:
         With DSECT=NO, storage is allocated in line
         and addressability is provided thru that DSECT or CSECT. With DSECT=YES, a DSECT is produced and "USING VLOK,reg"
*
*
         is required for addressability. Here "reg" contains the
         address of VLOK#LENGTH bytes of storage.
         The default is DSECT=YES.
*01* SIZE: VLOK#LENGTH
*01* POINTED TO BY: VLOKPtr
*01* CREATED BY: Storage obtained by caller of system call
*01* DELETED BY: Caller of system call
*01* STORAGE ATTRIBUTES:
       SUBPOOL/DATASPACE:
*02*
*02*
       KEY:
                             N/A
*02*
       RESIDENCY:
*01* FREQUENCY: 1 per v_lockctl syscall
*01* SERIALIZATION: N/A
*01* DEPENDENCIES: None
*01* NOTES:
             BPXYVFSI is a C program interface for the BPX1V (v_)
             services. The VLOCK structure in BPXYVFSI matches
             the BPXYVLOK structure.
*01* COMPONENT: z/OS UNIX (SCPX1)
*01* DISTRIBUTION LIBRARY: AMACLIB
*01* EYE-CATCHER: VLOK
       OFFSET:
*02*
*02*
       LENGTH:
%GOTO VLOKPLS ;
                                   /* Bilingual header
.A411
         ANOP
*** BPXYVLOK: VLOK - Vnode Service Byte Range Locking structure
AIF ('&DSECT' EQ 'NO').B411
                      DSECT,
VLOK
         AGO
                .C411
.B411
         ANOP
                                                  Clear storage
                      DC
                             XL(VLOK#LENGTH)'00'
VLOK
                      ORG
                             VLOK
 C411
         ANOP
VLOKBEGIN
                      DS
                             ΘD
VLOKID
                      DC.
                             C'VLOK'
                                                  Eve catcher
                      DC
                             AL4(VLOK#LENGTH)
VLOKLEN
                                                  Length of the structure
VLOKLOCKER
                       DS
                             0F
                                                  Locker
VLOKSERVERPID
                       DS
                                                    Server's Process ID
VLOKCLIENTPID
                       DS
                                                    Server's Client's PID
                                                  Locker Token
Client's Thread ID
Object - a locked file
                      DS
VLOKLOCKERTOK
                             CL8
                      DS
VLOKCLIENTTID
                             CL8
VLOKOBJECT
                      DS
                             0F
VLOKOBJCLASS
                                                    Õbject Class
                       DS
                             0CL12
                                                                         @D1C
VLOKOBJID
                      DS
                                                    Object ID
                      DS
                                                      Object Device ID
VI OKOBJDEV
                             CI 4
VLOKOBJFID
                      DS
                             CL8
                                                      Object File ID
VLOKOBJTOK
                      DS
                             CL8
                                                  Object token
```

```
VLOKDOS
                                                   <--Not used externally
VLOKDOSMODE
                       DS
                              CL1
                                                   <--Not used externally
VLOKDOSACCESS
                       DS
                              CL1
                                                   <--Not used externally
VLOKBLKLOCKLEN
                       DS
                              CL1
                                                   VlokBlockingLock length
VLOKSUBFUNCTION
                       DS
                              CL1
                                                   Internal SubFunction
VLOKRSVD
                       DS
                              CL4
                                                   Reserved
VLOKVNTOKEN
                       DS
                              CL8
                                                   Vnode Token
VLOKBRLK
                       DS
                              CL24
                                                   Lock Information mapped
                                                   by BPXYBRLK
VLOKENDVER1
                                                --- END OF VERSION 1 -----
                              ΘF
                       DS
                       DS
                              F
VLOKBLOCKINGLOCK
                       DS
                                                   Ptr to Ret Blocking Lock
VLOKUNION
                       DS
                              0CL12
                       ORG
VLOKAIOEXT
                            VLOKUNION
                                          Async Extension
                                                      ! Rsvd for Ptr64
                       DS
VLOKAIOCB
                       DS
                              Α
                                            Async Locking Aiocb
                                            Async Aiocb Length
VLOKAIOCBLEN
VLOKUNLOADLOCKSEXT
                       ORG VLOKUNION
                                          Unload Locks Extension
                       DS
                              F
                                                      ! Rsvd for Ptr64
VLOKULLOUTLISTPTR
                       DS
                                             Output List Ptr
VLOKULLSUBPOOL
                       DS
                              CL1
                                            Storage Subpool
                       DS
                              CL1
VLOKULLRETWAITERS
                              CL1
                                            Return Waiters too
                       DS
VLOKPURGEEXT
                       ORG
                            VLOKUNION
                                          Purge Locks Mask Ext
                                                     ! Rsvd for Ptr64
                       DS
                              F
VLOKPGMASKS
                       DS
                              Α
                                             VlokObjOwnMasks
VLOKPGMASKSLEN
                       DS
                                            Length of the two masks
                              CL12
VLOKENDVER2
                                          --- End of Version 2 -----
    Constants
                                                   Length of VLOK
VLOK#LENGTH
                       EQU
                              *-VLOKBEGIN
VL0K#HFS
                       ΕŎU
                              0
                                                   HFS Object Class
                                                   MVS Object Class
VI OK#MVS
                       EQU
                              1
VLOK#LFSESA
                       EQU
                              2
                                                   LFS/ESA Object Class
    Constants for V_lockctl commands
VLOK#REGLOCKER
                              1
                                                Register Locker
VLOK#UNREGLOCKER
                       ΕQU
                                                Unregister Locker
                                                Lock object's byte range
VLOK#LOCK
                       ΕQŪ
                                                Lock object's byte range
- wait if blocked
UnLock object's byte range
VLOK#LOCKWAIT
                       ΕQŪ
                              4
                              5
VLOK#UNLOCK
                       FOU
                                                Query byte range for locks
Purge all locks for a locker
                             6
7
VLOK#QUERY
                       EQU
VLOK#PURGE
                       ΕŲŪ
VLOK#LOCKASY
                       EOU
                             8
                                                Lock Asynchronously
                                                Cancel Async Lock
Unload BRLM Locks
VLOK#LOCKCANCEL
                              9
                       EQU
VLOK#UNLOADLOCKS
                       ΕQU
                             10
    Constants for UnLoadLocks
                                                Ret Held & Waiters
VLOK#RETWAITERS
VLOK#RETALLOBJ
                       EQU
                              3
                                                Total UnLoad
    Mask structure for Purge Locks
VLOKOBJOWNMASKS
VLOKOBJECTMASK
                       DS
                            0CL16
                                                Object Id Mask
                                                 Object Class
VLOKOBJCLASSMASK
                       DS
                           CL4
                                                 Object Class
Object Devno (HFS)
Object Fid (HFS)
Owner Id Mask
VLOKOBJDEVMASK
                       DS
                           CL4
VI OKOBJETDMASK
                       DS
                            CL8
VLOKOWNERMASK
                       DS
                            0CL16
VLOKLOCKERMASK
                       DS
                            0CL8
                                                Locker Mask
VLOKSPIDMASK
                       DS
                                                 Server PID Mask
                           CL4
VLOKCPIDMASK
                       DS
                            CI 4
                                                 Client PID Mask
VLOKTIDMASK
                           CL8
                                                Thread Id Mask
** BPXYVLOK END
          SPACE 3
                 ('&LIST' EQ 'YES').E411
                                                                     6@D1A
          AIF
          POP
                PRINT
.E411
          ANOP
          MEND
                                      Terminating PL/X comment
                                                                             */
*%VLOKPLS:
*%IF VLOKBASE = '' %THEN
* %DO;
```

```
%VLOKBASE = 'BASED(VlokPtr)';
*%IF Translate(VLOKBASE) = 'BASED(VLOKPTR)' %THEN
    DCL VlokPtr Ptr(31);
                                  /* Pointer to the VLOK
                                                                       */
  %END;
*DCL
* 1 Vlok VLOKBASE Bdy(Dword),
                                   /* V_lockctl Byte Range Lock Info */
                                   /* Eye catcher - 'VLOK '
    3 VlokId
                    Char(4),
                                   /* Length of structure
    3 VlokLen
                    Fixed(31),
    3 VlokLocker Bdy(Dword)
                                   /* Locker
                                                                    @01C*/
      5 VlokServerPID Fixed(32),
                                   /* Server's Process ID
        7 * Char(1),
        7 VlokServerPIDByte2 Char(1), /* sysplex system number VlokClientPID Fixed(32), /* Server's Client's PID
                                                                    @D1A*/
*
      5 VlokClientPID Fixed(32),
                                   /* +10 */
    3 VlokLockerTok Char(8)
                                   /* Locker token
                                                                    @01C*/
          Bdy(Dword),
                                                                 /* @01A*/
      5 VlokLockerTok1 Ptr(31),
5 VlokLockerTok2 Ptr(31),
                                   /* For CDS
*
                                                                    @01A*/
                                   /* For CDS
*
                                                                    @@1A*/
    3 VlokClientTID Char(8)
                                   /* Client's Thread ID
                                                                    @01C*/
          Bdy(Dword),
                                                                 /* @01A*/
                                   /* +20 */
                                   /* Object - a locked file
/* Object Class
    3 VlokObject,
                                                                        */
      5 VlokÕbjClass Fixed(32),
*
      5 VlokObjID Char(12),
                                   /* Object ID -unique within Class
        7 VlokŌbjDev
                         Char(4),
                                   /*
                                          Device ID for HFS file
                                          File ID for HFS file
        7 VlokObjFid
                         Char(8),
                                   /*
                                                                        */
                                   /* +30 */
    3 VlokObjTok
                   Char(8),
                                   /* Object token
        ! The fields below were never used and are being left! here so old programs that may have referenced them
                                                                    @D2A
                                                                    @D2A
        ! will not suffer compile failures with this new macro.
                                                                    @D2A
                                         !<--Not used externally
                                                                    @D2C
        5 VlokDOSMode Char(1),
                                        !<--Not used externally
                                                                    @D2C
        5 VlokDOSAccess Char(1),
                                       !<--Not used externally
                                                                    @D2C
                                                                   @D2A
                                   /* Length for VlokBlockingLock @D2A*/
    3 VlokBlkLockLen Fixed(8),
                                   /* Optional internal sub function
    3 VlokSubFunction Fixed(8),
                                      codes - see below
                                                                    @02A*/
                                   /* Reserved for expansion
                    Char(4),
                                   /* +40 */
*
    3 VlokVnToken
                    Char(8),
                                   /* Vnode Token
                                                                    @D2A*/
                                   /* +48 */
    3 VlokBrlk Char(Length(Brlk)),/* Lock Information - BPXYBRLK
*
*
    3 VlokEndVer1
                    Char(0), /* +60 --- End of Version 1 ----- @D2A*/
                        Ptr,
                                                  ! Rsvd for Ptr64 @D2A*/
    3 VlokBlockingLock Ptr,
                                   /* Ptr to Ret Blocking Lock
                                                                   @D2A*/
                                   /* +68 */
*
                                                                  /*@D2A*/
    3 * UNTON
                    Bdy(DWord),
*
      4 VlokAioExt ,
                                   /* Async Extension
                                                                    @D2A*/
                           Ptr,
                                                  ! Rsvd for Ptr64 @D2A*/
                                      /* Async Locking Aiocb
        5 VlokAiocb
                            Ptr,
                                                                    @D2A*/
                           Fixed(32), /* Async Aiocb Length
        5 VlokAiocbLen
                                                                    @D2A*/
*
*
                                                                 /*@D2A*/
      /* Unload Locks Extension
                                                                    @D2A*/
                                                  ! Rsvd for Ptr64 @D2A*/
        5 VlokUllOutListPtr
                              Ptr,
                                          /* Output List Ptr
                                                                    @D2A*/
                              Fixed(8), /* Storage Subpool
*
        5 VlokUllSubpool
                                                                    @D2A*/
                                                              /*@P3D@D2A*/
*
                              Fixed(8),
        5 VlokUllRetWaiters Fixed(8), /* Return Waiters too
                                                                   @D2A*/
*
                                                                  /*@D2A*/
      4 VlokPurgeExt ,
                                   /* Purge Locks Mask Ext
                                                                    @D2A*/
*
                            Ptr,
                                                  ! Rsvd for Ptr64 @D2A*/
                                      /* VlokObjOwnMasks
        5 VlokPgMasks
                            Ptr,
                                                                    @D2A*/
                            Fixed(32), /* Length of the two masks @D2A*/
        5 VlokPgMasksLen
                                  /* +74 */
    /*@D2A*/
*DCL
* Vlok#ID Char(4) Constant('VLOK'),
                                             /* Eye catcher
* Vlok#Len Fixed(31) Constant(Length(Vlok));/* Length of Vlok
```

```
* Vlok#InvalidToken Char(8)
                                                /* Token is invalid due */
    Constant('FFFFFFFFFFFFF'X);
                                                                      @D3A*/
                                               /* to lock error
*/* Constants for VlokSubFunction
                                                         (Internal Use) */
*DCI
* Vlok#Close Fixed(8) Constant(5), /* v_lockctl = Vlok#Unlock & this
                                          is for a close
* Vlok#Getown Fixed(8) Constant(6), /* Query owner locks
                                                                      @03A*/
* Vlok#MoveFs Fixed(8) Constant(7); /* filesystem move
                                                                      @D3A*/
*/* Constants for Object Class (VlokObjClass)
*DCL
* Vlok#HFS Fixed(32) Constant(0), /* z/OS UNIX MVS Hierarchical FS
* Vlok#MVS Fixed(32) Constant(1), /* MVS dataset
* Vlok#LFSESA Fixed(32) Constant(2); /* LAN File Server/ESA files
                                                                          */
                                                                      @D2A*/
*
  /* Constants for UnLoadLocks
* Dcl
                                                                /*@P3D@D2A*/
    Vlok#RetWaiters Fixed(8) Constant(1),
                                              /* Ret Held & Waiters @D2A*/
*
    Vlok#RetAllObj Fixed(8) Constant(3); /* Total UnLoad
                                                                      @D2A*/
  /★ The UnLoaded Locks output is mapped by the
     Brlm_UnloadLocksList structure in the IGWLB2IN macro.
*
*
     This contains an array of (ObjectID, RangeLock) pairs.
     In the RangeLock structure if the RLAccess field equals
     Vlok#OpenModes then the RangeLock structure contains the
     file's open access and deny modes rather than a byte range
            The file's open modes are returned when the VlokVnToken
     field contains a Vnode token and only for opens that have
     specified either DenyRead or DenyWrite. These are mapped
     by the VlokRngLock structure below, which overlays the
     BRLM_UnLoadList_RangeLock element of the array.
                                                                      @D2A*/
  Dcl Vlok#OpenModes Fixed(8) Constant(5);
                                                                    /*@D2A*/
  /* RangeLock structure for RLAccess=Vlok#OpenModes
                                                                      @D2A*/
                                                                    /*@D2A*/
*
  Dcl 1 VlokRngLock Based,
                                /* A BRLM_RangeLock For Open Modes @D2A*/
                              Char(16),
        2 VlokRngOwner
                                           /* V_Open VopnOpenOwner @D2A*/
        2 VlokRngOffLen
                              Char(16)
                                            /* Not used
                                                                      @D2A*/
        2 VlokRngFlags
                              Fixed(32).
                                                                    /*@D2A*/
           3 VlokRngWaiter
                                Bit(1),
                                                                    /*@D2A*/
                                Bit(7)
                                                                    /*@D2A*/
                                Fixed(8),
           3 VlokRngOpenAcc
                                           /* VopnShrAccess value
                                                                      @D2A*/
                                Fixed(8),
Fixed(8);
           3 VlokRngOpenDeny
                                            /* VopnShrDeny value
                                                                      @D2A*/
                                           /* =Vlok#OpenModes
           3 VlokRngRlAccess
                                                                      @D2A*/
  /* Mask structure for Purge Locks
                                                                      @D2A*/
 Dcl 1 VlokObjOwnMasks Based,
*
                                                                    /*@D2A*/
        2 VlokObjectMask Char(16)
                                           /* Object Id Mask
                                                                      @D2A*/
                                                Object Class
           3 VlokObjClassMask Char(4),
                                           /*
                                                                      @D2A*/
           3 VlokObjDevMask
                               Char(4),
                                                Object Devno (HFS)
                                                                      @D2A*/
           3 VlokObjFIDMask
                               Char(8),
                                                Object Fid
                                                               (HFS)
                                                                      @D2A*/
                            Char(16),
                                           /* Owner Id Mask
                                                                      @D2A*/
        2 VlokOwnerMask
           3 VlokLockerMask
                               Char(8)
                                           /*
                                                Locker Mask
                                                                      @D2A*/
             5 VlokSPidMask
                                Char(4),
                                                   Server PID Mask
                                                                      @D2A*/
             5 VlokCPidMask
                                Char(4),
                                                   Client PID Mask
                                                                      @D2A*/
          3 VlokTIDMask
                               Char(8);
                                                Thread Id Mask
                                                                      @D2A*/
                                           /*
*/* Constants for V_lockctl commands
               Changes made to these commands should also be made @P2A*/
               in the BPXZFCNA macro in the BPXFCBRL section.
                                                                      @P2A*/
*DCL
* Vlok#RegLocker
                    Fixed(32) Constant(1), /* Register Locker
* Vlok#UnregLocker Fixed(32) Constant(2), /* Unregister Locker */
* Vlok#Lock Fixed(32) Constant(3), /* Lock object's byte range*/
* Vlok#LockWait
                    Fixed(32) Constant(4), /* Lock object's byte range
                                                  wait if blocked
* Vlok#Unlock
                    Fixed(32) Constant(5), /* UnLock object's byte range
  Vlok#Query
                    Fixed(32) Constant(6), /* Query byte range for locks
* Vlok#Purge
                    Fixed(32) Constant(7), /* Purge all locks for a
                                                locker
* Vlok#LockAsy
                    Fixed(32) Constant(8), /* Lock Asynchronously @D2A*/
  Vlok#LockCancel Fixed(32) Constant(9), /* Cancel Async Lock
                                                                      @D2A*/
  Vlok#UnloadLocks Fixed(32) Constant(10);/* Unload BRLM Locks
                                                                      @D2A*/
*/* VlokObjectVP & VlokObjTokVP are used internally for loading
```

BPXYVOPN — Map the open parameters structure for v_open

The BPXYVOPN macro maps the structure of the Open_Parms parameter of the v_open service.

```
%GOTO VOPNPRO ;
                                   /* Bilingual header
         MACRO
         BPXYVOPN &DSECT=YES, &LIST=YES
         GBLB &VOPN411
               (&VOPN411 EQ 1).E411
         ATF
&VOPN411 SETB 1
               ('&LIST' EQ 'YES').A411
         AIF
         PUSH PRINT BPXYVOPN: v_open parameter definitions
         PRINT OFF
               .A411
         AG0
*%VOPNPRO: ;
*/***START OF SPECIFICATIONS*************************
     $MAC (BPXYVOPN) COMP(SCPX1) PROD(BPX):
*01* MACRO NAME: BPXYVOPN
*01* DSECT NAME: VOPN
*01* DESCRIPTIVE NAME: BPX1VOP(v_open) Parameter Definitions
*02*
     ACRONYM: None
*/*01* PROPRIETARY STATEMENT=
*/***PROPRIETARY_STATEMENT************************
*/*
*/*
*/* LICENSED MATERIALS - PROPERTY OF IBM
*/* THIS MACRO IS "RESTRICTED MATERIALS OF IBM"
*/* 5650-ZOS (C) COPYRIGHT IBM CORP. 2005
*/* STATUS= HBB7720
*/***END_OF_PROPRIETARY_STATEMENT******************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION:
       This macro defines the input parameters for v_open.
*01* METHOD OF ACCESS:
*02*
      PL/X:
         %INCLUDE SYSLIB(BPXYVOPN)
         By default, the VOpenParms structure is simply based.
         If special basing is desired, use %VOPNBASE='BASED(XXXXXX)'.
*
*02*
       ASM:
         With DSECT=YES, a DSECT is produced and "USING VOPN, reg"
         is required for addressability. Here "reg" contains the address of VOPN#LENGTH bytes of storage.
         With DSECT=NO, storage is allocated in line and
         addressability is provided thru that DSECT or CSECT. the default is {\sf DSECT-YES}.
*01* SIZE: VOPN#LENGTH
*01* POINTED TO BY: N/A
```

```
*01* CREATED BY: Caller of system call
*01* DELETED BY: Caller of system call
*01* STORAGE ATTRIBUTES:
*02*
       SUBPOOL/DATASPACE:
        KEY:
*02*
                              Caller's
*02*
       RESIDENCY:
                              Primary
*01* FREQUENCY: 1 per call to v_open
*01* SERIALIZATION: N/A
*01* DEPENDENCIES: N/A
*01* NOTES: None
*01* COMPONENT: z/OS UNIX (SCPX1)
*01* DISTRIBUTION LIBRARY: AMACLIB
*01* EYE-CATCHER: None
       OFFSET:
*02*
*02*
       LENGTH:
%GOTO VOPNPLS ;
                                     /* Bilingual header
.A411
          ANOP
** BPXYVOPN: V_open Parameters
** Used by: VOPN AIF ('8
                 ('&DSECT' EQ 'NO').B411
VOPN
                       DSECT ,
                 .C411
          AGO
.B411
          ANOP
VOPN
                        DS
                              0D
.C411
          ANOP
VOPNOPENTYPE
                              F
                                      Type of v_open
                        DS
VOPNOPENOWNER
                        DS
                              CL16
                                      Owner identification
                                      Read, Write, or Both
None, Read, Write, Both
Output/Input Open Token
Output Vnode Token
                              F
VOPNSHRACCESS
                        DS
VOPNSHRDENY
                        DS
VOPNOPENTOKEN
                        DS
                              CL8
VOPNVNTOKEN
                        DS
                              CL8
VOPNFLAGS
                        DS
                                      Open Flags @D1A
                              CL12
                              *-VOPN Length of this structure
VOPN#LENGTH
                        EQU
** VopnOpenType Values:
OPEN_CREATE_UNCHECKED EQU
OPEN_CREATE_GUARDED EQU
OPEN_CREATE_EXCLUSIVE EQU
                               2
                               3
4
OPEN_FILE
                          ΕQU
OPEN_NLM_SHR
                          EQU
                               5
OPEN UPGRADE
                          ΕŌU
OPEN_DOWNGRADE
                          EQU
** VopnShrAccess Values:
SHRACC_WRITE
SHRACC_READ
                     EQU 1
EQU 2
SHRACC_BOTH
                     EQU 3
** VopnShrDeny Values: @D1C
SHRDENY_NONE
SHRDENY_WRITE
SHRDENY_READ
                           0
                     EQU
                           1
                     ΕQU
SHRDENY_BOTH
                     ΕQŪ
                          3
** VopnFlags Values:
SHRMOD_NONE
                           0
SHRMOD_DENY
SHRMOD_ACC
                     ΕQU
                     ΕÒU
SHRMOD_BOTH
                     EQU
                           3
** BPXYVOPN End
          SPACE 3
                 ('&LIST' EQ 'YES').E411
          AIF
          POP
                 PRINT
          ANOP
.E411
          MEND
                                      Terminating PL/X comment
```

```
*%VOPNPLS: ;
* %IF VOPNBASE = '' %THEN
      %VOPNBASE = 'Based';
    %END;
  /* V_Open OpenParms Parameter
  /*-----
*
 Declare
    1 VOpenParms VOPNBASE Bdy(Word),
       2 VopnOpenType Fixed(32), /* Type of v_open
2 VopnOpenOwner Char(Length(VopnLOwner)), /* Owner Id
                                           /* Access Intent to:
/* READ, WRITE, or BOTH
       2 VopnShrAccess Fixed(32),
                             Bit(30),
                                                 /* Read Access */
/* Write Access */
/* Reservations that deny: */
         3 VopnShrAccRd
                               Bit(1),
                                                /*
                           t Bit(1),
Fixed(32),
         3 VopnShrAccWrt
*
       2 VopnShrDeny
                               Bit(30),
                                                 /* NONE, READ, WRITE, BOTH */
                                                 /* Deny Read Access
/* Deny Write Access
         3 VopnShrDenyRd
                               Bit(1),
         3 VopnShrDenyWrt Bit(1),
                                                  /*
                                                  /* Output/Input Open Token */
/* Output Vnode Token */
       2 VopnOpenToken Char(8),
*
       2 VopnVnToken
                            Char(8),
*
       2 VopnFlags
                            Bit(32),
                                                   /* Flags
          * Bit(30), /* Reserved */
Vopn_ModAcc Bit(1), /* Modify Access (upgrade/downgrade)*/
Vopn_ModDeny Bit(1), /* Modify Deny (upgrade/downgrade) */
* Char(12);
        3 Vopn ModAcc
*
    /* Lock or Open Owner
*
    Declare
      1 VopnLOwner Based Bdy(Word),
2 VopnLO_ServerPid Fixed(32),
2 VopnLO_ClientPid Fixed(32),
*
                                               /* Server's PID
                                               /* Server's Client's ID
         2 VopnLO_ClientTid Char(8);
                                               /* Client's Thread's ID
    /* VopnOpenType Values:
    /* (Note value 99 is reserved for internal use only
                                                                            @P1A*/
    Dcl ( OPEN_CREATE_UNCHECKED
                                        Constant(1),
           OPEN_CREATE_GUARDED
OPEN_CREATE_EXCLUSIVE
                                         Constant(2),
                                        Constant(3),
           OPEN_FILE
                                         Constant(4),
           OPEN_NLM_SHR
OPEN_UPGRADE
                                         Constant(5),
                                         Constant(6),
           OPEN DOWNGRADE
                                         Constant(7)
                                   ) Fixed(32);
    /* VopnShrAccess Values:
    SHRACC_BOTH Constant(3)
                                  ) Fixed(32);
    /* VopnShrDeny Value:
    Dcl ( SHRDENY_NONE Constant(0),
           SHRDENY_WRITE Constant(1), SHRDENY_READ Constant(2),
           SHRDENY_BOTH Constant(3)
                                  ) Fixed(32);
    /* VopnFlags Values: for upgrade/downgrade */
    Dcl ( SHRMOD_NONE Constant(0),
           SHRMOD_DENY Constant(1),
SHRMOD_ACC Constant(2),
           SHRMOD_BOTH Constant(3)
                                   ) Fixed(32);
    Dcl Vopn#Length Fixed(32) Constant(Length(V0penParms));
```

Appendix C. Callable services examples

These examples follow the rules of reentrancy. They use DSECT=NO and place the variables in the program's dynamic storage DSECT, which is allocated upon entry.

The examples are arranged alphabetically and have references to the mapping macros they use. The declaration for all local variables used in the examples follows the examples.

Reentrant entry linkage

This entry linkage is reentrant and saves the caller's registers, allocates a save area and dynamic storage, and establishes program and dynamic storage base registers. This entry linkage is paired with the return linkage that is located at the end of the executable program; see "Reentrant return linkage" on page 461.

```
TITLE 'Alphabetical Invocation of OpenMVS Callable Services'
BPXB5SM6 CSECT
                                           Reentrant entry linkage
BPXB5SM6 AMODE 31
BPXB5SM6 RMODE ANY
          USING *,R15
                                           Program addressability
@ENTRYO
          В
                 @ENTRY1
                                           Branch around program header
          DROP
                                           R15 not needed for addressability
                 C'BPXB5SM6 - Reentrant callable service examples'
          DC
                                           Ensure half word boundary
          DS
          STM
                 R14,R12,12(R13)
                                           Save caller's registers
@ENTRY1
          LR
                 R2,R13
                                           Hold address of caller's area
                 R3,R1
R12,R15
                                           Hold parameter register
          LR
          LR
                                           R12 program base register
                 R11,2048(,R12)
R11,2048(,R11)
                                           Second program base register
          LA
                                           Second program base register
          LA
          LA R9,2048(,R11)
LA R9,2048(,R9)
USING @ENTRYO,R12,R11,R9
                                           Third program base register
                                           Third program base register
Program addressability
                 R0,@SIZEDAT
                                           Size this program's getmain area
          GETMAIN RU, LV=(0)
                                           Getmain storage
                 R13,R1
                                           R13 -> this program's save area
                 R10,2048(,R13)
R10,2048(,R10)
                                           Second getmain base register
Second getmain base register
          LA
          LA
          USING @STORE,R13,R10
                                           Getmain addressability
                 R2,@BACK
                                           Save caller's save area pointer
                 R13,8(,R2)
                                           Give caller our save area
                 R1,R3
                                           Restore parameter register End of the entry linkage code
          LR
@ENTRY2
          EQU
          SPACE ,
PSEUD0
                                           Dummy label used throughout
          EOU
```

BPX1VCR, **BPX4VCR** (v_create)

The following code creates a new and empty regular file named fnewprots in a previously looked-up directory whose vnode token is in DIRVNODETOK with user read-execute, group write, other read-execute permissions. For the callable service, see "v_create (BPX1VCR, BPX4VCR) — Create a file" on page 260. For the data structures, "BPXYOSS — Specific information for the Map operating system" on page 442 and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
BUFFERA(9),=CL9'fnewprots'
BUFLENA,=F'9'
MVC
MVC
MVC.
      OSSSTOR, OSS
                                Initialize BPXYOSS area
MVC
      ATTRSTOR, ATTR
                                Initialize BPXYATTR area
      S_MODE,S_MODE
XC.
                                Clear mode
MVI
      S_TYPE,FT_REGFILE
                                Set regular file type
      S_MODE2,S_IRUSR Read-execute/writ
S_MODE3,S_IXUSR+S_IWGRP+S_IROTH+S_IXOTH
MVI
                                Read-execute/write/read-execute
MVI
      R5, ATTRSTOR
                                Address and
ΙΑ
USING ATTR, R5
                                map BPXYATTR area
MVC
      ATTRMODE, S_MODE
                                Move mode data to attribute
                                structure
DROP
SPACE
      BPX1VCR,
                                Create a file
CALL
```

```
(DIRVNODETOK,
                        Input: Directory vnode token
OSSSTOR,
                        Input/output: BPXYOSS
                       Input: New file name length Input: New file name
BUFLENA,
BUFFERA,
=A(ATTR#LENGTH),
                       Input: BPXYATTR length
                        Input/output: BPXYATTR
ATTRSTOR,
VNODETOK,
                        Output: New file Vnode token
RETVAL,
                        Return value: 0 or -1
RETCODE.
                        Return code
RSNCODE),
                        Reason code
VL,MF=(É,PLIST)
```

BPX1VSF, **BPX4VSF** (v_fstatfs)

The following code obtains the status of the file system containing the previously looked-up file whose vnode token is in VNODETOK. For the callable service, see "v_fstatfs (BPX1VSF, BPX4VSF) — Return file system status" on page 268. For the data structures, see "BPXYOSS — Specific information for the Map operating system" on page 442 and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
OSSSTOR, OSS
                               Initialize BPXYOSS area
MVC
SPACE
CALL BPX1VSF
                               Obtain file system status
                              Input: Vnode token
Input/output: BPXYOSS
      (VNODETOK,
      OSSSTOR.
      =A(SSTF#LENGTH),
                              Input: BPXYSSTF length
      SSTF
                               Output: BPXYSSTF
      RETVAL,
                               Return value: 0 or -1
      RETCODE
                               Return code
      RSNCODE)
                               Reason code
      VL, MF=(E, PLIST)
```

BPX1VGT, **BPX4VGT** (v_get)

The following code obtains a vnode token for the file or directory specified via the input FID, residing within the mounted file system represented by the input VFS token. Previously, the FID might have been obtained from an attribute structure returned by v_lookup, and the VFS token via v_rpn. For the callable service, see "v_get (BPX1VGT, BPX4VGT) — Convert an FID to a vnode Token " on page 271. For the data structure, see "BPXYOSS — Specific information for the Map operating system" on page 442.

```
MVC
      OSSSTOR, OSS
                            Initialize BPXYOSS area
SPACE ,
     BPX1VGT,
CALL
                            Obtain a Vnode token
                            Input: VFS token
      (VFSTOK,
      OSSSTOR,
                            Input/output: BPXYOSS
      FID.
                            Input: File identifier
      VNODETOK,
                            Output: Vnode token for file
      RETVAL,
                            Return value: 0 or -1
      RETCODE,
                            Return code
      RSNCODE),
                            Reason code
      VL,MF=(É,PLIST)
```

BPX1VGA, BPX4VGA (v_getattr)

The following code obtains the status of a file whose previously looked-up vnode token is in VNODETOK. For the callable service, see "v_getattr (BPX1VGA, BPX4VGA) — Get the attributes of a file " on page 274. For the data structures, see "BPXYATTR — Map file attributes for v_ system calls " on page 433 and "BPXYOSS — Specific information for the Map operating system" on page 442.

```
MVC.
      OSSSTOR, OSS
                             Initialize BPXYOSS area
SPACE
                             Obtain file status
CALL
     BPX1VGA
                             Input: Vnode token
      (VNODETOK,
                             Input/output: BPXYOSS
      OSSSTOR,
      =A(ATTR#LENGTH),
                             Input: BPXYATTR length
      ATTRSTOR,
                             Output: BPXYATTR
      RETVAL
                             Return value: 0 or -1
      RETCODE,
                             Return code
```

```
RSNCODE), Reason code + VL,MF=(E,PLIST) ------
```

BPX1VIO, BPX4VIO (v_ioctl)

The following code conveys a command to a physical file system. To use this example correctly, in the COMMAND parameter you must define a command understood by the physical file system. For the callable service, see "v_ioctl (BPX1VIO/BPX4VIO) - Convey a command to a physical file system" on page 276. For the data structure, see "BPXYOSS — Specific information for the Map operating system" on page 442.

```
MVC
      COMMAND, =X'0000D302'
                               GETFACL command
MVC
      ARGBLEN, =F'1024'
      BPX1VIO.
CALL
      (VNODETOK,
                               Input: Vnode token
       OSSSTOR,
                               Input/output: BPXYOSS
       COMMAND,
                               Input: command
       ARGBLEN,
                               Input: argument length
       ARGBUFF,
                               Argument buffer name
       RFTVAL.
                               Return value: 0 or -1
       RETCODE
                               Return code
       RSNCODE)
                               Reason Code
       VL,MF=(E,PLIST)
```

BPX1VLN, BPX4VLN (v_link)

The following code creates a new name, **dataproc.next**, for a previously looked-up file whose vnode token is in VNODETOK in a previously looked-up directory whose vnode token is in DIRVNODETOK. For the callable service, see "v_link (BPX1VLN, BPX4VLN) — Create a link to a file " on page 280. For the data structure, see "BPXYOSS — Specific information for the Map operating system" on page 442.

```
MV/C
      OSSSTOR, OSS
                              Initialize BPXYOSS area
MVC
      BUFLENA, =F'13'
      BUFFERA(13),=CL13'dataproc.next'
MVC.
SPACE
      RPX1VI N
                              Create a link to a file
CALL
      (VNODETOK,
                              Input: File vnode token
      OSSSTOR,
                              Input/output: BPXYOSS
      BUFLENA,
                              Input: Name length: new name
Input: New file name
      BUFFERA
      DIRVNODETOK,
                              Input: Vnode for directory
      RETVAL,
                              Return value: 0 or -1
      RETCODE,
                              Return code
      RSNCODE)
                              Reason code
      VL,MF=(E,PLIST)
```

BPX1VLO, BPX4VLO (v lockctl)

The following code requests a read lock on the file with the input DEVNO and FID. The locker has been previously registered as LOCKERTOK, and the request is for client thread CTID. The byte-range to lock is from the start of the file to byte 10. For the callable service, see "v_lockctl (BPX1VLO, BPX4VLO) — Lock a file" on page 283. For the data structures, see "BPXYOSS — Specific information for the Map operating system" on page 442, "BPXYVLOK — Map the interface block for v_lockctl" on page 445, and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
MVC
      OSSSTOR, OSS
                                      Initialize BPXYOSS area
MVC
      VLOKSTOR, VLOK
                                      Initialize BPXYVLOK area
      BRLK(BRLK#LENGTH), BRLK
                                      Initialize BPXYBRLK
XC
      L_TYPE,F_RDLCK
L_WHENCE,SEEK_SET
L_LEN,=F'10'
MVT
                                      Lock type = read
MVT
                                      Whence = start of file
                                     Len = 10 bytes
MVC
LA
      R5, VLOKSTOR
                                      Address and
USING VLOK, R5
                                      map BPXYVLOK area
MVC
      VLOKLOCKERTOK, LOCKERTOK
                                      Move Locker Token to VLOK
                                      Move Thread ID to VLOK
MVC
      VLOKCLIENTTID, CTID
MVI
      VLOKOBJCLASS, VLOK#HFS
                                      Object Class = HFS
```

```
MVC.
      VLOKOBJDEV, DEVNO
                                     Move Device ID
MVC
      VLOKOBJFID, FID
                                     Move File ID
MVC
      VLOKBRLK, BRLK
                                     Move Lock info to VLOK
DROP
SPACE
      BPX1VLO,
                              Create a link to a file
CALL
      (OSSSTOR,
                             Input/output: BPXYOSS
                             Input: Command = Lock
Input: BPXYVLOK length
      =A(VLOK#LOCK)
      =A(VLOK#LENGTH),
      VLOKSTOR,
                              Input/output: BPXYVLOK
      RETVAL,
                              Return value: 0 or -1
      RETCODE,
                              Return code
      RSNCODE)
                              Reason code
      VL, MF=(É, PLIST)
```

BPX1VLK, BPX4VLK (v_lookup)

The following code looks up a file named **fnewprots** in a previously looked-up directory whose vnode token is in DIRVNODETOK. In the returned attribute structure, ATTRFID contains the file identifier (FID) which can be used to obtain a vnode token for the file, subsequent to freeing the vnode token returned by v_lookup via v_rel. For the callable service, see <u>"v_lookup (BPX1VLK, BPX4VLK) — Look up a file or directory" on page 294</u>. For the data structures, see <u>"BPXYATTR — Map file attributes for v_ system calls" on page 433 and "BPXYOSS — Specific information for the Map operating system" on page 442.</u>

```
BUFFERA(9),=CL9'fnewprots'
BUFLENA,=F'9'
MVC
MVC
      OSSSTOR, OSS
                              Initialize BPXYOSS area
SPACE
      BPX1VLK,
CALL
                              Lookup a file
      (DIRVNODETOK,
                              Input: Directory Vnode token
                              Input/output: BPXYOSS
      OSSSTOR,
      BUFLENA,
                              Input: File name length
                              Input: File name
Input: BPXYATTR length
      BUFFERA,
      =A(ATTR#LENGTH),
      ATTRSTOR,
                              Output: BPXYATTR
      VNODETOK,
                              Output: File Vnode token
      RETVAL,
                              Return value: 0 or -1
      RETCODE
                              Return code
      RSNCODE)
                              Reason code
      VL,MF=(E,PLIST)
```

BPX1VMD, BPX4VMD (v mkdir)

The following code creates a new and empty directory named newprots in a previously looked-up directory whose vnode token is in DIRVNODETOK with user read-execute, group write, other read-execute permissions. For the callable service, see "v_mkdir (BPX1VMD, BPX4VMD) — Create a directory " on page 297. For the data structures, see "BPXYATTR — Map file attributes for v_ system calls " on page 433, "BPXYOSS — Specific information for the Map operating system" on page 442 and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
BUFFERA(8),=CL8'newprots'
BUFLENA,=F'8'
MVC
MVC.
      OSSSTOR, OSS
                               Initialize BPXYOSS area
MVC.
MVC
      ATTRSTOR, ATTR
                               Initialize BPXYATTR area
      S_MODE,S_MODE
XC
                               Clear mode
      S_TYPE,FT_DIR
                               Set directory file type
MVI
      S_MODE2,S_IRUSR Read-execute/writ
S_MODE3,S_IXUSR+S_IWGRP+S_IROTH+S_IXOTH
                               Read-execute/write/read-execute
MVT
MVI
      R5, ATTRSTOR
LA
                               Address and
USING ATTR, R5
                               map BPXYATTR area
      ATTRMODE, S_MODE
MVC
                               Move mode data to attribute
                               structure
DROP
SPACE
      BPX1VMD.
                               Make a directory
                               Input: Directory vnode token
Input/output: BPXYOSS
       (DIRVNODETOK,
      OSSSTOR,
      BUFLENA,
                               Input: New directory name length
                               Input: New directory name
      BUFFERA,
      =A(ATTR#LENGTH),
                               Input: BPXYATTR length
                               Input/output: BPXYATTR
      ATTRSTOR
      DIRVNODETOK2,
                               Output: New directory Vnode token +
```

BPX1VPC, BPX4VPC (v_pathconf)

The following code obtains current values of configurable options of a file or directory whose vnode token is in VNODETOK. For the callable service, see "v_pathconf (BPX1VPC, BPX4VPC) — Get pathconf information for a directory or file" on page 309. For the data structures, see "BPXYATTR — Map file attributes for v_system calls" on page 433, "BPXYOSS — Specific information for the Map operating system" on page 442 and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
Initialize BPXYOSS area
          MVC.
                OSSSTOR, OSS
          MVC
                ATTRSTOR, ATTR
                                      Initialize BPXYATTR area
          CALL BPX1VPC
                (VNODETOK,
                                      Input: File Vnode token
                OSSSTOR,
                                      Input/output: BPXYOSS
                =A(PCFG#LEN),
                                      Input: PCFG length
                BUFFERA,
                                      Output: PCFG buffer area
                                      Input: BPXYATTR length
                =A(ATTR#LENGTH),
                                      Output: BPXYATTR
                ATTRSTOR,
                RETVAL,
                                      Return value: PCFG len or -1
                RETCODE,
                                      Return code
                RSNCODE),
                                      Reason code
                VL,MF=(E,PLIST)
Note: PCFG#LEN is defined as follows. It is not constant in the BPXYPCF macro.
                BPXYPCF
                                      pathconf
      PCFG#LEN EQU
                                       *-PCFG
```

BPX1VRW, BPX4VRW (v_rdwr)

The following code writes data to a previously looked-up file whose vnode token is in VNODETOK, from the buffer provided. Control is not to be returned to the calling program until the data has been written, and authorization to write to the file is to be verified. For the callable service, see "v_rdwr (BPX1VRW, BPX4VRW) — Read from and write to a file " on page 311. For the data structures see "BPXYOSS — Specific information for the Map operating system" on page 442 and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
OSSSTOR, OSS
                             Initialize BPXYOSS area
MVC.
MVC
      FUIOSTOR, FUIO
                             Initialize BPXYFUIO area
      R5,FUIOSTOR
                             Address and
USING FUIO, R5
                             map BPXYFUIO area
      R15, BUFFERA
                             Set address of buffer
LA
      R15,FUIOBUFFERADDR
ST
                             to be written in FUIO
ΩT
      FUIOFLAGS, FUIO#WRT+FUIOSYNC+FUIOCHKACC
                             Indicate write action, write
                             to medium before return,
                             and check authorization
MVC.
      FUIOCURSOR, =F'100'
                             Set offset to begin writing
      FUIOIBYTESRW, =F'80'
                             Max number of bytes to write
DROP
SPACE
      BPX1VRW,
CALL
                             Read or write data to or from file+
      (VNODETOK,
                             Input: Vnode token for file
      OSSSTOR,
                             Input/output: BPXYOSS
                             Input/output: BPXYFUIO
      FUIOSTOR,
      =A(ATTR#LENGTH),
                             Input: BPXYATTR length Output: BPXYATTR
      ATTRSTOR,
                             Return value: 0, -1 or char count +
      RETVAL,
      RETCODE
                             Return code
      RSNCODE).
                             Reason code
      VL,MF=(É,PLIST)
```

BPX1VRD, BPX4VRD (v_readdir)

The following code reads the multiple entries from a directory, whose previously looked-up vnode token is in DIRVNODETOK, into the buffer provided. FUIOCURSOR, set to zero by the BPXYFUIO macro, indicates that the system is to begin reading with the first entry in the directory. Presuming that this is the first time the directory is read, FUIOCHKACC is set, in order to verify access authority. For the callable service, see "v_readdir (BPX1VRD, BPX4VRD) — Read entries from a directory "on page 315. For the data structures, see "BPXYOSS — Specific information for the Map operating system" on page 442and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
Initialize BPXYOSS area
MVC.
      OSSSTOR, OSS
MVC
      FUIOSTOR, FUIO
                                Initialize BPXYFUIO area
LA
      R5,FUIOSTOR
                                Address and
USING FUIO, R5
                                map BPXYFUIO area
                             Set address of buffer for directory data in FUIO
      R15, BUFFERA
LA
      R15, FUIOBUFFERADDR
ST
      FUIOIBYTESRW,=F'1023' Max number of bytes to read FUIOFLAGS,FUIOCHKACC Check authorization
MVC.
ΟI
DROP
SPACE
      BPX1VRD,
CALL
                                Read directory entries
                            Input: Vnode token for directory
Input/output: BPXYOSS
       (DIRVNODETOK,
      OSSSTOR,
                                Input/output: BPXYOSS
                                Input/output: BPXYFUIO
      FUIOSTOR,
      RETVAL,
                                Return value: 0, -1 or char count +
      RETCODE
                                Return code
      RSNCODE),
                                Reason code
      VL, MF=(E, PLIST)
```

BPX1VRA, BPX4VRA (v_readlink)

The following code reads the contents of a previously looked up symbolic link file whose vnode token is in VNODETOK, into the buffer provided. This will be the path name that was specified when the symbolic link was defined. For the callable service, see "v_readlink (BPX1VRA, BPX4VRA) — Read a symbolic link "on page 319. For the data structures, see Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
MVC
      OSSSTOR, OSS
                             Initialize BPXYOSS area
MVC.
      FUIOSTOR, FUIO
                             Initialize BPXYFUIO area
                           Address and
      R5, FUIOSTOR
LA
USING FUIO, R5
                             map BPXYFUIO area
      R15, BUFFERA
LA
                             Set address of buffer
      R15, FUIOBUFFERADDR
                             for symlink in FUIO
      FUIOIBYTESRW,=F'1023' Max number of bytes to read
MVC
DROP
SPACE
CALL
      BPX1VRA
                             Read the value of a symbolic link +
      (VNODETOK,
                             Input: Vnode token for file
                             Input/output: BPXYOSS
Input/output: BPXYFUIO
      OSSSTOR,
      FUIOSTOR,
      RETVAL,
                             Return value: 0, -1 or char count +
      RETCODE
                             Return code
      RSNCODE),
                             Reason code
      VL,MF=(É,PLIST)
```

BPX1VRG, BPX4VRG (v_reg)

The following code registers a file server named **File server**, and accepts the default maximum number of vnode tokens by allowing NREGMAXVNTOKENS to remain zero. For the callable service, see "v_reg (BPX1VRG, BPX4VRG) — Register a process as a server" on page 321. For the data structure, see "BPXYNREG — Map interface block to vnode registration" on page 440.

```
MVC NREGSTOR,NREG Initialize BPXYNREG area
LA R5,NREGSTOR Address and
USING NREG,R5 map BPXYNREG area
MVC NREGSTYPE,=A(NREGSTYPE#FILE) Set server type
MVC NREGSNAME(11),=CL11'File server' Set server name
MVC NREGSNAMELEN,=F'11'
DROP R5
```

```
SPACE ,
CALL BPX1VRG, Register server +
    (=A(NREG#LENGTH), Input: BPXYNREG length +
    NREGSTOR, Input/output: BPXYNREG +
    RETVAL, Return value: 0 or -1 +
    RETCODE, Return code +
    RSNCODE), Reason code +
    VL,MF=(E,PLIST)
```

BPX1VRL, BPX4VRL (v rel)

The following code releases a vnode token, specified in VNODETOK. For the callable service, see "v_rel (BPX1VRL, BPX4VRL) — Release a vnode token" on page 325. For the data structure, see "BPXYOSS—Specific information for the Map operating system" on page 442.

```
OSSSTOR, OSS
                            Initialize BPXYOSS area
SPACE
CALL BPX1VRL
                            Release Vnode token
      (VNODETOK,
                            Input: Vnode token
                            Input/output: BPXYOSS
      OSSSTOR,
      RETVAL,
                            Return value: 0 or -1
      RETCODE
                            Return code
      RSNCODE).
                            Reason code
      VL,MF=(E,PLIST)
```

BPX1VRM, BPX4VRM (v_remove)

The following code deletes the file named **newprots** located in a previously looked-up directory whose vnode token is in DIRVNODETOK. For the callable service, see <u>"v_remove (BPX1VRM, BPX4VRM) — Remove a link to a file " on page 327</u>. For the data structure, see <u>"BPXYOSS — Specific information for the Map operating system" on page 442.</u>

```
BUFFERA(8),=CL8'newprots'
      BUFLENA, =F'8'
MVC
MVC
      OSSSTOR, OSS
                              Initialize BPXYOSS area
SPACE
      BPX1VRM
CALL
                              Remove a file
      (DIRVNODETOK,
                              Input: Directory vnode token
                              Input/output: BPXYOSS
      OSSSTOR,
                              Input: File name length Input: File name
      BUFLENA,
      BUFFERA,
      RETVAL,
                              Return value: 0 or -1
      RETCODE
                              Return code
      RSNCODE),
                              Reason code
      VL,MF=(E,PLIST)
```

BPX1VRN, **BPX4VRN** (v_rename)

The following code changes the name of a file from **samantha** in a previously looked-up directory whose vnode token is in DIRVNODETOK to **sam** in a previously looked-up directory whose vnode token is in DIRVNODETOK2. For the callable service, see "v_rename (BPX1VRN, BPX4VRN) — Rename a file or directory" on page 330. For the data structure, see and "BPXYOSS — Specific information for the Map operating system" on page 442.

```
BUFFERA(08),=CL08'samantha' Old name BUFLENA,=F'08'
MVC
      BUFFERB(03),=CL03'sam'
MVC
                                    New name
MVC
      BUFLENB, =F'03'
MVC
      OSSSTOR, OSS
                             Initialize BPXYOSS area
SPACE
CALL
      BPX1VRN
                             Rename a file
      (DIRVNODETOK,
                             Input: Old directory vnode token
      OSSSTOR,
                             Input/output: BPXYOSS
      BUFLENA,
                             Input: Old name length
                             Input: Old name
      BUFFERA,
      DIRVNODÉTOK2,
                             Input: New directory Vnode token
      BUFLENB,
                             Input: New name length
      BUFFERB,
                             Input: New name
      RETVAL,
                             Return value: 0 or -1
```

BPX1VRE, **BPX4VRE** (v_rmdir)

The following code deletes the directory named **newprots** located in a previously looked-up directory whose vnode token is in DIRVNODETOK. For the callable service, see "v_rmdir (BPX1VRE, BPX4VRE) — Remove a directory" on page 334. For the data structure, see "BPXYOSS — Specific information for the Map operating system" on page 442.

```
BUFFERA(8),=CL8'newprots'
BUFLENA,=F'8'
MVC.
MVC.
MVC
      OSSSTOR, OSS
                                Initialize BPXYOSS area
SPACE
      BPX1VRE,
CALL
                                Remove a directory
       (DIRVNODETOK,
                               Input: Directory vnode token
Input/output: BPXYOSS
      ÒSSSTOR,
      BUFLENA,
                              Input: Directory name length
      BUFFERA,
                               Input: Directory name
      RETVAL,
                                Return value: 0 or -1
      RETCODE,
                               Return code
      RSNCODE)
                                Reason code
      VL,MF=(E,PLIST)
```

BPX1VRP, BPX4VRP (v_rpn)

The following code resolves (that is, looks up) the fully qualified path named /usr/fnewprots. For the callable service, see "v_rpn (BPX1VRP, BPX4VRP) — Resolve a path name" on page 337. For the data structures, see "BPXYATTR — Map file attributes for v_ system calls " on page 433, "BPXYOSS — Specific information for the Map operating system" on page 442, and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
MV/C
       BUFFERA(14),=CL14'/usr/fnewprots'
MVC
       BUFLENA, =F'14'
       OSSSTOR, OSS
                                    Initialize BPXYOSS area
MVC.
SPACE
CALL BPX1VRP
                                    Resolve a pathname
                         Input/output: BPXYOSS
Input: Path name length
Input: Path name
Output: VFS token
        (OSSSTOR,
       BUFLENA,
       BUFFERA,
       VFSTOK,
       VNODETOK.
                                   Output: Vnode token
       =A(MNTEH#LENGTH+MNTE#LENGTH), Input: MNTE length
MNTE, Output: BPXYMNTE
-A(ATTE#LENGTH) Input: PRYYATTE length
                                  Input: BPXYATTR length
Output: BPXYATTR
       =A(ATTR#LENGTH),
       ATTRSTOR,
       RETVAL,
                                   Return value: 0 or -1
       RETCODE
                                    Return code
       RSNCODE),
                                    Reason code
       VL, MF=(E, PLIST)
```

BPX1VSA, BPX4VSA (v_setattr)

The following code sets attributes for a previously looked-up file whose vnode token is in VNODETOK. The owning user and group IDs are changed, the file change time is set to the current time and the user read-execute, group write, other read-execute permissions are set. For the callable service, see "v_setattr (BPX1VSA, BPX4VSA) — Set the attributes of a file "on page 341. For the data structures, see "BPXYATTR — Map file attributes for v_ system calls "on page 433, "BPXYOSS — Specific information for the Map operating system" on page 442, and Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
MVC OSSSTOR,OSS Initialize BPXYOSS area
MVC ATTRSTOR,ATTR Initialize BPXYATTR area
XC S_MODE,S_MODE Clear mode
MVI S_MODE2,S_IRUSR Read-execute/write/read-execute
MVI S_MODE3,S_IXUSR+S_IWGRP+S_IROTH+S_IXOTH
```

```
R5,ATTRSTOR
                             Address and
USING ATTR, R5
                             map BPXYATTR area
MVC
      ATTRMODE, S MODE
                             Move mode data to attribute
                             structure
      ATTRUID, =F'7'
                             Specify new UID
MVC.
      ATTRGID, =F'77'
                             Specify new GID
MVC
      ATTRSETFLAGS1, ATTRMODECHG+ATTROWNERCHG
ΟI
                             Flag UID and GID changes
ΟI
      ATTRSETFLAGS2, ATTRCTIMECHĞ+ATTRCTIMETOD
                             Set change time to current time
DROP
SPACE
CALL
      BPX1VSA
                             Set file attributes
Input: File vnode token
      (VNODETOK,
                             Input/output: BPXYOSS
      OSSSTOR,
      =A(ATTR#LENGTH),
                             Input: BPXYATTR length
      ATTRSTOR,
                             Input/output: BPXYATTR
      RETVAL.
                             Return value: 0 or -1
      RETCODE
                             Return code
      RSNCODE),
                             Reason code
      VL,MF=(E,PLIST)
```

BPX1VSY, BPX4VSY (v_symlink)

The following code creates an external symbolic link to data set MY.DATASET, the "pathname", for link name mydataset, the "link name", which is contained in a previously looked-up directory whose vnode token is in DIRVNODETOK. For the callable service, see "v_symlink (BPX1VSY, BPX4VSY) — Create a symbolic link" on page 348. For the data structures, see "BPXYATTR — Map file attributes for v_system calls" on page 433, "BPXYOSS — Specific information for the Map operating system" on page 442, and in Mapping macros in z/OS UNIX System Services Programming: Assembler Callable Services Reference.

```
BUFFERA(09),=CL09'mydataset' Name of link BUFLENA,=F'09'
MVC
MVC
      BUFFERB(10),=CL10'MY.DATASET' Contents of link
MVC
      BUFLENB, =F'10'
      OSSSTOR, OSS
MVC
                             Initialize BPXYOSS area
MVC
      ATTRSTOR, ATTR
                             Initialize BPXYATTR area
      R5,ATTRSTOR
LA
                             Address and
USING ATTR.R5
                             map BPXYATTR area
      ATTRVISIBLE, ATTREXTLINK
                             Flag as external link
DROP
SPACE
      BPX1VSY,
CALL
                             Create a symbolic link
      (DIRVNODETOK,
                             Input: Directory vnode token
      OSSSTOR,
                             Input/output: BPXYOSS
      BUFLENA,
                             Input: Link name length
                             Input: Link name
Input: Pathname length
      BUFFERA,
      BUFLENB,
      BUFFERB,
                             Input: Path name
                             Input: BPXYATTR length
      =A(ATTR#LENGTH),
                             Input/output: BPXYATTR
      ATTRSTOR,
      RETVAL
                             Return value: 0 or -1
      RETCODE
                             Return code
      RSNCODE),
                             Reason code
      VL,MF=(E,PLIST)
```

Reentrant return linkage

```
R15, R15
        XR
                                   Zero return code
              R0,@SIZEDAT
                                   Size this program's getmain area
              R1,R13
        LR
                                   R1 -> this program's getmain area
              R13,@BACK
                                   R2 -> caller's save area
              R13
        FREEMAIN RU, LV=(0), A=(1)
              R14,12(,R13)
                                   Restore caller's R14
        LM
              R0,R12,20(R13)
                                   Restore caller's RO-R12
        BSM
              0,R14
                                   Branch back to caller
        SPACE , * * * * * * ...

DC A(@ENDSTOR-@STORE)
                 @SIZEDAT DC
MNTEL
              A (MNTE#LENGTH+MNTEH#LENGTH)
        DC
                                   Length of MNTEH and 1 MNTE area
        SPACE
PRIMARYALET DC A(0)
                                   Primary ALET
```

```
* With EQUate only macros, DSECT= is allowed but is ignored
        BPXYCONS LIST=NO
                                  OpenMVS constants
        BPXYERNO LIST=NO
                                  Errno, Errnojr constants
        BPXYFTYP
                                  File type constants
        BPXYSEEK ,
                                  1seek constants
@STORE DSECT
@SAVE00 DS
             0D
                                  Standard 72-byte save area
        DS
@BACK
        DS
                                  Back to caller's save area
@FORWARD DS
             Α
                                  Forwards to callee
BPXYATTR DSECT=NO
                                  Attributes for Vnode services
        BPXYFUIO DSECT=NO
                                  User I/O block
                                  Registration structure for
        BPXYNREG DSECT=NO
                                  for Vnode services
        BPXYOSS DSECT=NO
                                 Operating system info for Vnode
                                  services
        BPXYVLOK DSECT=NO
                                  Lock request info for v lockctl
        SPACE 2 * * * * * * * * * * * Getmain for mappings * * * * *
                              BPXYATTR storage
             CL(ATTR#LENGTH)
ATTRSTOR DS
                                  ->BPXYBRLK
BRLKA
        DS
        BPXYBRLK DSECT=NO
                                 Byte range locking for v_lockctl
             CL(FUIO#LENGTH)
                                  BPXYFUIO storage
FUIOSTOR DS
        BPXYMODE DSECT=NO
                                  Mode constants
                                  Get mount entries for v_rpn
because MNTE has DSECT in it
        BPXYMNTE DSECT=NO
        DSECT
@STORE
NREGSTOR DS
             CL(NREG#LENGTH)
                                 BPXYNREG storage
OSSSTOR DS
             CL(OSS#LENGTH)
                                  BPXYOSS storage
                                 BPXYVLOK storage
VLOKSTOR DS
             CL(VLOK#LENGTH)
       BPXYSSTF DSECT=NO
                                 Response data for v_fstatfs
DS
                 0D
                                  Argument count
Argument lengths list
ARGCNT
             DS
             DS
ARGLLST
                  3A
ARGSLST
             DS
                  ЗА
                                  Arguments list
BUFA
             DS
                                  ->buffer
BUFFERA
             DS
                  CL1024
                                  Utility buffer A, length 1024
                                  Number of bytes used in buffer A
Utility buffer B, length 1024
BUFLENA
             DS
BUFFERB
             DS
                  CL1024
             DS
BUFLENB
                                  Number of bytes used in buffer B
BUFW
             DS
                                  Number of words used in BUF
COMMAND
             DS
                                 User defined command
                                 Client Thread ID
Device ID
             DS
                  CL8
CTID
DEVNO
             DS
            DS
                  F
DIRECTDES
                                  Directory descriptor
                                 Directory Vnode token
Directory Vnode token
DIRVNODETOK
             DS
                  2F
DIRVNODETOK2 DS
                  2F
ENVCNT
             DS
                  F
                                  Number of environment variables
ENVLENS
                  F
             DS
                                 Length of environment variables
                  F
ENVPARMS
             DS
                                 Environment variables
EVENTLIST
             DS
                                  Event list for thread posting
EXITRTNA
             DS
                                 Exit routine address
             DS
EXITPLA
                                 Exit Parm list address
                  2F
             DS
FTD
                                 File identifier (FID)
FILEDESC
             DS
                                 File descriptor
FILEDES2
             DS
                                  File descriptor
                                 File system name
             DS
FSNAME
                  CL44
             DS
                  CI 8
                                  File system_type
FSTYPE
GRNAMELN
             DS
                                  Group name length
GROUP
             DS
                                  Group
GROUPCNT
             DS
                  F
                                  Group count
                                 Group ID (PID of group leader)
GROUPID
             DS
GRPGMNAME
             DS
                  CL8
                                  Group program name
INTMASK
             DS
                  XL8
                                  Signal mask
INITRTNA
             DS
                                  ->Ĭnitialization routine
                                  Interrupt state
INTRSTATE
             DS
                  Α
TNTRTYPF
             DS
                                  Interrupt type
             DS
                  CL8
LOCKERTOK
                                  Locker Token
NANOSECONDS
             DS
                                  Count of nanoseconds
NCATCHER
             DS
                                  New catcher
NEWFLAGS
             DS
                                  New flags
                                  New Handler
NEWHANDL
             DS
                  XL8
             DS
NEWLEN
                                  Length file
NEWMASK
             DS
                  XL8
                                  New mask for signals
NEWMASKA
             DS
                                  ->New mask
NEWTIMES
             DS
                  D
                                  New access/modification time
             DS
                                  Old catcher
OCATCHER
0FFSFT
             DS
                  CL8
                                  File offset
OLDHANDL
             DS
                                  Old handler
```

```
OLDFLAGS
                                         Old flags
OLDMASK
               DS
                      CL8
                                         Old signal mask
                      A
F
OLDMASKA
               DS
                                          ->0ld mask
               DS
OPTIONS
                                         Options
PGMNAME
               DS
                      CL8
                                         Program name
Length PGMNAME
PGMNAMEL
               DS
                                         Max number of parms
PLIST
               DS
                      13A
               DS
                      F
PROCID
                                         Process ID
PROCTOK
               DS
                      F
                                         Relative process number
                      F
F
               DS
READFD
                                         File descriptor - input file
               DS
REFPT
                                         File reference point
                                         Return code (ERRNO)
                      F
RETCODE
               DS
                                         Return value (0, -1 or other)
Reason code (ERRNOJR)
RETVAL
               DS
                      F
               DS
                      F
RSNCODE
               DS
                      F
SECONDS
                                         Time in seconds
SIGNAL
               DS
                      Α
                                         Signal
SIGNALREG
               DS
                                         Signal registration, user data
                      Α
                                         Signal options
Signal return mask
SIGNALOPTIONS DS
               DS
                      CL8
SIGRET
SIRTNA
               DS
                      Α
                                         Signal interrupt routine
STATFLD
               DS
                                         Status field
STATUS
               DS
                                         Status
               DS
DS
STATUSA
                                          ->STATUS
TERMMASK
                      XL8
                                         Signal termination mask
               DS
                                         Thread ID
THID
                      XL8
USERID
               DS
                                         User ID
USERNAME
               DS
                      CL8
                                         User name
               DS
DS
                                         Length USERNAME
USERNLEN
                      F
USERWORD
                      F
                                         User data
               DS
                      F
WAITMASK
                                         Mast for signal waits
WRITEFD
               DS
                                         File descriptor - output file
VFST0K
               DS
                      2F
                                         VFS token
VNODETOK
               DS
                      2F
                                         Vnode token
               SPACE
          EQU
SPACE 3
@ENDSTOR
                                         End of getmain storage
                    * * * * * * * * * * * * Register equates * * * * * * *
               SPACE
                      ó
R0
               EQU
               EQU
EQU
R1
                                         Parameter list pointer
                      2
R2
R3
               ΕŲŪ
               ΕŲŪ
                      4
R4
               EQU
EQU
R5
                      5
                      6
7
R6
R7
               ΕQŪ
               EQU
EQU
EQU
R8
                      8
R9
                                         Third program base register
R10
                      10
                                         Second getmain storage register
               ΕQŪ
R11
                                         Second program base register
               ΕŲŪ
                                         Program base register
R12
                      12
               ΕQŪ
R13
                      13
                                         Savearea & getmain storage base
               EQU
EQU
                                         Return address
R14
                      14
R15
                      15
                                         Branch location
```

Reentrant Return Linkage

Appendix D. Interface structures for C language servers and clients

This appendix describes the following C language header files:

- <u>"BPXYVFSI" on page 465</u>, which is for the VFS callable services API (v_xxxxx, as described in <u>Chapter 5</u>, "VFS callable services application programming interface," on page 253)
- "BPXYPFSI" on page 484, which is for the PFS interface operations (vfs_xxxxx and vn_xxxxx, as described in Chapter 3, "PFS operations descriptions," on page 73)

These headers are placed in SYS1.SFOMHDRS when z/OS UNIX is installed.

BPXYVFSI

```
/****START OF SPECIFICATIONS**************************
     $MAC (BPXYVFSI) COMP(SCPX4) PROD(FOM):
*01* MACRO NAME: BPXYVFSI
*01* DSECT NAME: N/A
*01* DESCRIPTIVE NAME: Virtual File System Interface Definition for C
*02*
      ACRONYM: N/A
/*01* PROPRIETARY STATEMENT=
 /* LICENSED MATERIALS - PROPERTY OF IBM
 /* 5650-ZOS COPYRIGHT IBM CORP. 1993, 2013
 /* STATUS= HBB7790
 /***END_0F_PR0PRIETARY_STATEMENT*****************************/
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION: Provide a C language header file for the VFS Callable
               Services Interface.
      Defines C structures for the control blocks and tokens that
      are used with the v (BPX1V) Callable Services.
      Defines C prototypes and macros for the Callable Services.
      The macros make use of the callable services vector tables
      so that the caller does not have to be statically bound
      to the services or to their stubs.
     The callable services may be invoked by either their official names or by C-friendly names, i.e. as bpx1vgt() or v_get().
  The following structures are defined here:
      Common structures used on both the VFS and PFS interfaces.
        GTOK
              - General Eight Byte Token
              - File Identifier
        CBHDR - General Control Block Header
        ATTR - File Attribute Structure
        UIO - User I/O Structure
DIRENT - Directory Entries for v_readdir/vn_readdir.
        FSATTR - File System Attributes of v_fstatfs/vfs_statfs
      Structures specific to the VFS interface.
        VFSTOK & VNTOK - Opaque Tokens for file systems and files.
               - Operating System Specific Information Structure
        RPNMNTE - Mount Entry Structures returned by v_rpn.
```

```
NREG

    Registration Parameter Block used with v_reg

                - Byte Range Locking Structure for v_lockctl.
   Conditional Processing is controlled by the following symbols:
      _NOFCNTL - suppresses the inclusion of fcntl.h
          To suppress the inclusion of fcntl.h #define _NOFCNTL
          and do one of the following before you include this header:
           (1) If you are not going to call v_lockctl:
               #define FLOCK char - to provide a dummy type for vl_flock
           or
           (2) If you will call v_lockctl
               #define or typedef FLOCK to your program's flock struct
*
      _BPX_MNTE2 - Produces Version 2 of the Mount Entry
                                                                  @P5A
*
*
      _BPXLL - converts the following fields from (Highword, LowWord)
               pairs into a single 8-byte long long data type: @P5A
                   at_size
                   at_blocks
                   u_offset
                   u fssizelimit
                   fs_maxfilesize
                   me_bytesread
                   me_byteswritten
*
                                                                  @P7A
      _BPXRTL_VFSI - Makes adjustments necessary for the RTL.
      _LP64 - Makes the UIO and ATTR compatable with LP64
                                                                  @P7A
      __XPLINK__ - Makes the V_XXXX Linkages OS_UPSTACK
                                                                  @P7A
  Structures that are input to the services must be initialized
   prior to being passed on the calls.
This means that the id and length fields are set correctly
   and that unused fields are zero.
      Macros are provided for initializing these structures
      in two ways:
      (1) For each potential input structure, XXX, there is an XXX_HDR
          macro defined that can be used to initialize the header and
          zero out the rest of the structure when the local copy
          is declared. For example:
          ATTR attr2 = { ATTR_HDR };
      (2) The CBINIT macro can be used to initialize an area after
          it has been declared. For example:
         struct { int abc;
    UIO uio2;
                   ATTR attr2;
                   int def;
              } area2;
          CBINIT(area2.uio2,UIO);
**********************
*01* METHOD OF ACCESS:
*02*
     C/370:
         #include <bpxyvfsi.h>
*02* PL/X:
```

```
None
*02*
    ASM:
*
      None
*01* DEPENDENCIES: Changes to the macros listed below must be reflected
             in the corresponding structures of this header.
    This header file is consistent with the following mappings:
*
        BPXYATTR
        BPXYDIRE
        BPXYFUIO
        BPXYMNTE
        BPXYOSS
        BPXYSSTF
        BPXYVL0K
*01* COMPONENT: OpenMVS (SCPX4)
*01* DISTRIBUTION LIBRARY: AFOMHDR1
#ifndef __BPXYVFSI_Common
#define __BPXYVFSI_Common
/**
/**
   Common structures used on both the VFS and PFS interfaces.
                                               **/
/**
                                               **/
/* Deal with gratuitous longs
                                           7@DVA*/
    For compatibility with 31-bit apps, they stay as longs. For 64-bit apps, they get converted to ints.
                                             */
  In common section because they are in both PFSI and VFSI.
 #ifdef _LP64
 typede<del>f</del> int
                BPXL32 ;
  typedef unsigned int BPXUL32;
 typedef long
                 BPXL32 :
  typedef unsigned long BPXUL32;
 #endif
/*-----
/* Set up for 64-bit addressing and pack the structures 6@DVA*/
 #ifdef LP64
 #define _PTR32 __ptr32
#pragma pack(1)
 #else
 #define _PTR32
 #endif
/*-----
typedef struct s_gtok { /* General Eight Byte Token */
 #ifdef _LP64
           void *gtok[1]; /*
                                            @DVA*/
 #else
            void *gtok[2];
     } GTOK;
 typedef struct s_fid {
                          /* File Identifier
            int fid[2];
                          /* PFS Specific values
/* General Control Block Header and Typedef for BIT
/*-----
```

```
typedef struct s_cbhdr {
                     char cbid[4];
                                           /* Eye catcher
                     int cblen;
                                           /* Length
         ? CBHDR:
  typedef unsigned int BIT;
 /* ATTR - File Attribute Structure
                                                                 (BPXYATTR)*/
                                                                             */
 /*
       File types and permissions of at_mode are defined in modes.h. */
       Audit bits of at aaudit & at uaudit are defined in stat.h.
#ifdef BPXLL
  typedef _Packed struct s_attr {
  typedef struct s_attr {
#endif
            CBHDR at_hdr;
                                                           /* POSIX fields */
                                          /* Type & Permissions st_mode */
            int
                     at mode;
                                          /* inode number st_ino */
            int
                     at_ino;
                                          /* device number
/* link count
/* uid of owner
                                                                   st_dev */
            int
                     at_dev;
            int
                     at_nlink;
                                                                   st_nlink*/
                                                                  st_uid */
            int
                     at_uid;
                     at_gid;
            int
                                          /* group id of owner st_gid */
#ifdef _BPXLL
            long long at_size;
#else
            int
                     at_sizeh;
                                          /* file size (high word)
            int
                     at_size;
                                          /* file size
                                                                    st size */
#endif
                                         /* last access time st_atime*/
/* last modified time st_mtime*/
/* status change time st_ctime*/
            int
                     at_atime;
            int
                     at mtime;
                     at_ctime;
                                                          /* OE Extensions */
                                          /* Major number for char spec */
            int
                     at_major;
                                          /* Minor number for char spec */
            int
                     at_minor;
            int
                     at_aaudit;
                                          /* auditor audit info
                     at_uaudit;
                                          /* user audit info
            int
                                           /* File block size
                     at_blksize;
            int
                                          /* File Creation time
            int
                     at_createtime;
            union {
                                                                       /*@DFA*/
                       AT_auditid[16];
                                            /* SAF Audit ID
                                            /* Guard Time Value:
               struct {
                                                                         @DFA*/
                         int sec;
                                               /* Seconds
                                                                         @DFA*/
                         int msec;
                                                /* Micro-seconds
                                                                         @DFA*/
                     } AT_guardtime;
                                                                       /*@DFA*/
                                             /★ Creation Verifier
               char AT_cver[8];
                                                                       @DFA*/
                                    /* See below for non-union names @DFA*/
            } at_u1;
                                                                       /*@DFA*/
            char
                        rsvd1[4];
                     at_genmask;
                                           /* Setgen Mask
            int
                                          /* SetAttr Change Flags:
                                                                             */
                                               to mode indicated
            BTT
                     at_modechg
                                    :1;
                                           /*
                                         /*
            BIT
                     at_ownchg
                                    :1;
                                                 to UID indicated
                                    :1;
:1;
                                                to General Attr flags
truncate size
                     at_setgen
at_trunc
                                          /*
            BIT
                                          /*
            BIT
                                    :1; /*
:1; /*
:1; /*
                                                 the Atime
Atime to TOD
                     at_atimechg
            BTT
            BIT
                     at_atimeTOD
            BIT
                     at_mtimechg
                                                  the Mtime
                                    :1; /*
:1; /*
:1; /*
            BIT
                     at_mtimeTOD
                                                  Mtime to TOD
                                                  auditor audit info
            BIT
                     at_aauditchg
                                                  user audit info
            BIT
                     at_uauditchg
                                      :1; /*
:1; /*
            BIT
                     at_ctimechg
                                                  the Ctime
            BIT
                     at_ctimeTOD
                                                  Ctime to TOD
                     at_reftimechg :1; /*
at_refTOD :1; /*
at_filefmtchg :1; /*
                                                  Reference time change
Reference time to TOD
            BIT
            BTT
                                                  File format change @DAA*/
            BIT
                     at_guardtimechk :1; /*
at_cverset :1; /*
            BIT
                                                  Guard Time Check
                                                                         @DFA*/
            BIT
                                                  Creation Ver Set
                                                                         @DFA*/
                     at_charsetidchg :1; /*
at_lp64times :1; /*
at_seclabelchg :1; /*
            BIT
                                                  Change File Info
                                                                         @DNA*/
                                                  64-bit fields used @P7A*/
            BIT
            BIT
                                                  change seclabel
                                                                         @DQA*/
            BTT
                                    :12;
#ifdef _BPXRTL_VFSI
                                                                       /*@P7A*/
                                                                         @P7A*/
            struct file_tag at_filetag; /* Ccsid and TxtFlag
                  at_charsetid[8];
                                            /* (Not used)
                                                                         @P7C*/
#else
                                                                       /*@P7A*/
```

```
char at_charsetid[12]; /* CharSetId
                    /* First 4 bytes of CharSetId is the FileTag
                                                                      /*@P7A*/
#endif
#ifdef _BPXLL
           long long at_blocks;
#else
                                        /* blocks allocated (high word)*/
                    at_blocksh;
                    at_blocks;
                                        /* blocks allocated
           int
#endif
            int
                    at_genvalue;
                                         /* General Attribute Flags
                                         /* Reference Time
                    at_reftime;
            int
                                        /* File format
            FID
                    at fid;
                    at_filefmt;
                                                                       @DAA*/
           char
                                         /* Fsp flag2 w/acl flags @DOA*/
                    at_fspflag2;
            char
                                                                   /* @DOC*/
            char
                       rsvd2[02];
                                          /* Micro-seconds of Ctime @DFA*/
            int
                    at_ctimemsec;
                    at_seclabel[8];
                                         /* security label
            char
                                                                       @DOA*/
                       rsvd3[4];
                                                                    /* @DOC*/
            char
                                         /* +A0 --- End Ver 1 --- @P5A*/
            char
                    at_atime64[8];
                                         /* Large Time Fields
                    at mtime64[8];
                                                                      /*@P5A*/
            char
                                                                      /*@P5A*/
            char
                    at_ctime64[8];
                    at_createtime64[8];
                                                                      /*@P5A*/
            char
                                                                      /*@P5A*/
            char
                    at_reftime64[8];
                                                                      /*@P5A*/
            char
                    at_rsvd4[8];
                    at_rsvd5[16];
                                                                     /*@P5A*/
            char
                                         /* +E0 --- End Ver 2 ---
                                                                     @P5A*/
    } ATTR ;
            #define ATTR_ID "ATTR"
            #define ATTR_HDR {{ATTR_ID}, sizeof(ATTR)}
               /* Field names without the union qualifiers
                                                                       @DFA*/
           #define at_auditid at_u1.AT_auditid
                                                                     /*@DFA*/
            #define at_guardtime at_u1.AT_guardtime
                                                                     /*@DFA*/
            #define at_cver at_u1.AT_cver
                                                                     /*@DFA*/
                /* FSP Flag2 (ACL) constants
           #define ATTR_ACCESS_ACL 128 /* access acl exists @DOA*/
#define ATTR_FMODEL_ACL 64 /* file model acl exists @DOA*/
#define ATTR_DMODEL_ACL 32 /* dir model acl exists @DOA*/
                 *-----
                /* File Format Type Constants
           #define ATTR_FFNA 0 /* Not specified
           #define ATTR_FFNL 2 /*
#define ATTR_FFCR 3 /*
#define ATTR_FFLF 4 /*
#define ATTR_FFCRLF 5 /*
#define ATTR_FFCRNL 7 /*
#define ATTR_FFCRNL 7 /*
                                              New Line
                                              Carrage Return
                                             Line Feed
                                            CR & LF
LF & CR
                                              CR & NL
                                          /* Data consists of Records:
            #define ATTR_FFRECORD 8 /*
                                                                     @DZA*/
                                             Records
                /* genvalue Constants -- use for ATTR or any other */
                          structures with genvalue
                /*-----
     #define GENVAL_PROGCTL 2 /* file can be program controlled */
#define GENVAL_APF 4 /* file can be APF authorized */
#define GENVAL_NOSHRAS 8 /* file cannot run in a shared AS */
#define GENVAL_NODELFILES 32 /* files are not to be deleted from
                                         this directory
     /* The macro below tests the at_mode and at_genvalue fields */
/* to see if the file is an External Symbolic Link. */
     #ifndef S_IFEXTL
       #define S_IFEXTL 0x00000001 /* External Link in at_genvalue */
       #define S_ISEXTL(m,gv) ( S_ISLNK(m) && ((gv) & S_IFEXTL) )
     #endif
     /* Vfs_Token and/or Mount Point Inode Number that may be @PBA*/
```

```
returned by v_lookup, v_readdir, and v_getattr.
     ^{\prime}/\star These are placed in the 12 byte at_charsetid field and /\star can be extracted as follows:
          ATTR *A;
                                              given an attr structure define a ptr to at_vinfo
           struct at_vinfo *AV;
          unsigned int MtPtInodNum;
                                              area to put Inode number
          unsigned int MtPtDevno;
                                              area to put Devno
          VFSTOK VT:
                                              area to put vfs token
     /*
          AV = (struct at_vinfo *)(&A->at_charsetid);
     //* For v_lookup and v_readdir the Vfs Token can be gotten with:
/* memcpy(&VT,&AV->at_vfstok,sizeof(VT));
     /* For v_readdir and v_getattr to get the Mount Point Ino:
         MtPtInodNum = AV->at_vmtptino;
     /*
      /* For v_getattr to get the Mount Point's Devno:
     /*
          MtPtDevno = (unsigned int)(AV->at_vfstok.gtok[1]);
     /*
      struct at_vinfo {
                                          /* Cross Mount Point Info @PBA*/
                                            /* Cross MtPt Vfs Tok
                GTOK at_vfstok;
                                                                       @PBA*/
                                             /* Root's MtPt's Ino
                                                                       @PBA*/
        unsigned int at_vmtptino;
       };
 /* UIO - User I/O Structure
                                                                 (BPXYFUIO)*/
      For 31-Bit addresses: u_buffaddr points to the buffer
      For 64-Bit addresses: u_addr64 is on and
                              u_buff64vaddr points to the buffer
  typedef struct s_uio {
             CBHDR u_hdr;
                                          /* u_buffaddr64 (Real)
#ifndef _LP64
                                                                     /*@P7A*/
             char *u buffaddr;
                                               Buffer 31-bit address
                                                                     /*@P7A*/
 #else
                                                                     /*@P7A*/
                       u_buffaddr[4];
               char
 #endif
                                                                     /*@P7A*/
                     u_buffalet;
                                         /* Alet for Buffer Address */
             int
#ifdef _BPXLL
             long long u_offset;
 #ifndef _LP64
                                                                     /*@P7A*/
                     u_offseth;
                                          /* Cursor (high word)
             int
                                                                           */
             int
                     u_offset;
                                         /* Cursor
  #else
                                                                     /*@P7A*/
                                                                     /*@P7A*/
               off_t u_offset;
  #endif
                                                                     /*@P7A*/
#endif
                                          /* Number of bytes
             int
                      u_count;
             short
                      u_asid;
                                         /* Addr Space ID: set by LFS
                                         /* 0=Read, 1=Write
/* Storage Key:
                               :1;
             BIT
                      u_rw
                               :4;
                      u_key
                                                              set by LFS
             BIT
                               :1;
                                         /* Sync data on write
             BTT
                      u_sync
                      u_syncd :1;
                                         /* Sync was done: LFS/PFS only*/
             BIT
             BIT
                      u_chkacc :1;
                                         /* Perform Access check
                     u_realpage :1;
u_limitex :1;
                                         /* u_buffaddr -> real page @D4A*/
             BIT
                                         /* File size limit exceeded
             BIT
                                                                       @D6A*/
             BTT
                      u_iovinuio :1;
                                          /* uio buff is an iov
                                                                       @D9A*/
             BIT
                      u_shutd :1;
                                         /* do shutdown after send
                                                                       @DMA*/
                      u_addr64
                                         /* 64-Bit Addressing
             BIT
                                  :1;
                                                                       @DMA*/
             BTT
                      u_seekcur :1;
                                          /* For pread/pwrite
                                                                       @P5A*/
                                  :2:
                                         /* Reserved
                                                                       @D6C*/
             BTT
             union {
                                          /* Vnop Specific Fields:
                       u_rdindex;
                                          /* Readdir Index
               int
                                             Sendmsg/Recvmsg IOV's ALET */
               int
                       u_iovalet;
                   } u_vs;
                                          /*
             union {
                                          /* Vnop Specific Fields2:
                                                                       @DFA*/
                                         /* Readdir Flags
/* IOV's Buffer's ALET
               int
                        U_rddflags;
                                                                       @DFA*/
                        U_iovbufalet;
               int
                                                                       @DFC*/
                                   /* See below for non-union names @DFA*/
                   } u_vs2;
                                                                     /*@DFA*/
#ifndef _BPXLL
```

```
u_fssizelimithw; /* filesize limit hiword @D6A*/
u_fssizelimitlw; /* filesize limit loword @D6A*/
             int
#else
             long long u_fssizelimit;
#endif
                                         /* Vnop Specific Fields3: @DFA*/
             union {
                       U_cver[8];  /* Readdir Cookie Verifier@DFA*/
u_internal[16]; /* Internal fields     @D9A*/
              char
               char
                                  /* See below for non-union names @DFA*/
                                                                     /*@DFA*/
                      u_iovresidualcnt; /* remaining bytes to be moved
             int
                                                                      @D9A*/
                                         /* total number of bytes to be
             int
                      u_totalbytesrw;
                                                                       @D9A*/
                                             moved
                                                                     /*@P7A*/
#ifndef _LP64
            char
                     u_buff64vaddr[8]; /* 64-Bit Virtual Addr
                                                                       @P5A*/
 #else
                                                                     /*@P7A*/
              char *u buff64vaddr;
                                                                     /*@P7A*/
                                                                     /*@P7A*/
 #endif
   } UIO ;
               /* Field names w/o the union qualifier
                                                                      @DFA*/
           #define u_iovbufalet u_vs2.U_iovbufalet
#define u_rddflags u_vs2.U_rddflags
#define u_cver u_vs3.U_cver
                                                                     /*@DFA*/
                                                                     /*@DFA*/
                                                                     /*@DFA*/
               /* u_rddflags - Readdir/ReaddirPlus Flags
           #define FUIORETCURSOR 4 /* Return cursor in dirents @E1A*/
#define FUIOCVERRET 2 /* Cookie Ver being Returned @DFA*/
#define FUIORDDPLUS 1 /* ReaddirPlus requested @DFA*/
           #define UIO_ID "FUIO"
#define UIO_HDR {{UIO_ID}, sizeof(UIO)}
#ifdef _BPXLL
            #define UIO_NONEWFILES 0x8000000000000000LL
#else
            #define UIO_NONEWFILES 0x80000000 /* No new files
                                            can be created
                                                                       @D6A*/
#endif
 /* DIRENT - Directory Entries for v_readdir/vn_readdir. (BPXYDIRE)*/
 /*
                                        Extension
           Entry
          | TL | NL | name
 /*
/*
                                        4+NL 8+NL TL
 /****
///*
         The Extension may not be returned by all PFSes.
      When (u rddflags & FUIORDDPLUS) == FUIORDDPLUS
                                                                       @DFA*/
        the directory entries look like:
                                                                       @DFA*/
           ---- -----//-----
               | TL | NL | name
                                        4+NL TL @DFA*/
 ./*/*
/*/*
/*
      When (u_rddflags & FUIORETCURSOR) == FUIORETCURSOR
        the directory entries look like:
            --- ---- //-----
           | TL | NL | name
                                       4+NL 8+NL
 typedef struct s_dirent {
  unsigned short dir_len;
  unsigned short dir_namelen;
      char dir_name[1];
                                          /* Directory Entry
                                        /*
/*
                                                Total entry length
Name length
                                                                       @E3C*/
                                                                      @E3C*/
                                         /* File name, 1-255 bytes
    } DIRENT ;
  typedef struct s_dirext {
    int dir ino;
                                          /* Directory Extension
                   dir_ino;
                                          /* File Ino number
             union {
               char DIR_other[1]; /* PFS specific data
```

```
char DIR_cursor[8]; /* cursor
                                                                     @E1A*/
           } dir_u1;
  } DIREXT;
  /* Field names without the union qualifiers
                                                                  /* @E1A*/
  #define dir_other dir_u1.DIR_other
  #define dir_cursor dir_u1.DIR_cursor
                                                                  /* @E1A*/
     /* The dir_name field is of variable length.
        Given the following two pointers:
             DIRENT *dp;
             DIREXT *dx;
        To move from one entry to the next:
           dp = (DIRENT *) ((int)dp + dp->dir_len);
        To copy the name field to a standard C string buffer:
           \label{eq:memcpy} $$ \ensuremath{\mathsf{memcpy}}$ (dp->dir\_name, name, dp->dir\_namelen); $$ \ensuremath{\mathsf{name}}$ [dp->dir\_namelen] = '\0'; $$
        To address the optional extension structure:
          if ((dp->dir_len) > (4 + dp->dir_namelen)) {
             dx = (DIREXT *) ((int)dp + 4 + dp->dir_namelen);
             ino = dx->dir_ino;
          else
            ino = 0;
        To address the readdirplus attributes:
                                                                     @DFA
                                                                     @DFA
                                                                     @DFA
          ATTR *da:
                                                                     @DFA
          da = (ATTR *) ((int)dp + 4 + dp->dir_namelen);
                                                                     @DFA
          ino = da->at_ino;
                                                                     @DFA
/* FSATTR - File System Attributes of v_fstatfs/vfs_statfs(BPXYSSTF)*/
         struct fsf_prop {
                                        /* NFS V3 Properties
                                                                     @DFA*/
                                       :1; /* V3 Prop Returned
             BIT fs_fsf_v3ret
                                                                     @DFA*/
                                       :2;
             BIT fs_fsf_CanSetTime
                                      :1; /* time_delta accuracy @DFA*/
             BIT fs_fsf_homogeneous :1; /* pathconf same for all@DFA*/
             BIT
                                       :1;
             BIT fs_fsf_symlink
                                       :1; /* Supports Symlinks
                                       :1; /* Supports Hard Links
             BIT fs_fsf_link
                                                                     @DFA*/
          3;
                                                                   /*@DFA*/
typedef struct s_fsattr {
             CBHDR fs_hdr;
                                         /* (f_0Ecbid and f_0Ecblen)
                                         /* Block size (f_bsize)
                                                                     @DVC*/
            BPXUL32 fs_blocksize;
             int
                      rsvd1;
                                         /* Reserved
                                                                         */
             int
                        rsvd2:
                                         /* Reserved
            BPXUL32 fs_totalspace;
                                         /* Total space. The total
                                            number of blocks on file
                                            system in units of f_frsize
                                            (f_blocks)
                                                                     @DVC*/
             int
                        rsvd3;
                                         /* Reserved
                                                                         */
            BPXUL32 fs_usedspace;
                                         /* Used space in blocks
                                            (f_0Eusedspace)
                                                                     @DVC*/
             int
                        rsvd4;
                                         /* Reserved
            BPXUL32 fs_freespace;
                                         /* Free space in blocks
                                                                     @DVC*/
                                            (f_bavail)
            BPXUL32 fs_fsid;
                                         /* File system ID (f_fsid)@DVC*/
                                         /* Flags:
                                        /*
             BIT
                                   :1;
                                                                     @DCA*/
                                             Reserved
                                             Filesys is exported
             BIT
                     fs_exported
                                   :1;
                                         /*
                                             (ST_OEEXPORTED)
                                                                     @DCA*/
             BIT
                                   :6;
                                             Reserved
                                                                     @DFC*/
   struct fsf_prop
                                             NFS V3 Properties
                                                                     @DFA*/
                     fs_nfsprop;
                                         /*
                                   :8;
                                         /*
             BIT
                                             Reserved
                                                                     @DFC*/
                                   :5;
             BTT
                                         /*
                                             Reserved
                                                                     @D.J.C.* /
             BIT
                     fs_nosec
                                   :1;
                                         /*
                                             No Security Checks
                                                                     @DJA*/
                                             SetUID/SetGID not supported
             BIT
                     fs_nosuid
                                   :1;
```

```
(ST_NOSUID)
                                                                          @DBM*/
                BIT
                        fs_rdonly
                                      :1; /* Filesys is read only
                                                 (ST_RDONLY)
                                                                          @DBM*/
#ifdef _BPXLL
                long long fs_maxfilesize;
#else
                       fs_maxfilesizehw; /* High word of max file size
                (f_OEmaxfilesizehw) @DEBPXUL32 fs_maxfilesizelw;/* Low word of max file size
                                                                          @DBM*/
                                                                        @DVC*/
                                                (f_0Emaxfilesizelw)
#endif
                           rsvd5[16];
                                            /* Reserved
                BPXUL32 fs_frsize;
                                            /* Fundamental filesystem
                                               block size (f_frsize) @DVC*/
                           rsvd6;
                                             /* Reserved
                                                                          @DBC*/
                           rsvd7;
                                             /* Reserved
                                                                           @DBC*/
                                           /* Total number of free blocks (f_bfree) @DVC
                BPXUL32 fs_bfree;
                                                                          @DVC*/
                                            /* Total number of file nodes
                BPXUL32 fs_files;
                                               in the file system (f_files)
                                                                          @DVC*/
                BPXUL32 fs_ffree;
                                            /* Total number of free file
                                            \begin{array}{c} \text{nodes (f\_ffree)} & \text{@D'} \\ /* \text{ Number of free file nodes} \end{array}
                                                                          @DVC*/
                BPXUL32 fs_favail;
                                                available to unprivileged
                                            users (f_favail) @[
/* Maximum file name length
                                                                          @DVC*/
                BPXUL32 fs_namemax;
                                                                          @DVC*/
                                                (f_namemax)
                BPXUL32 fs_invarsec;
                                             /* Number of seconds fs will
                                                remain unchanged
                                                (f_OEinvarsec)
               BPXUL32 fs_time_delta_sec;/* Granularity of setting @DVC*/
                BPXUL32 fs_time_delta_ns;/* file times
                                                                          @DVC*/
                         rsvd8[12]; /* Reserved
                                                                          @DBC*/
    } FSATTR ;
            #define FSATTR_ID "SSTF"
            #define FSATTR_HDR {{FSATTR_ID}, sizeof(FSATTR)}
 //* PFS Type values for me_fstype and pfsi_pfstype.
            #define MNT_FSTYPE_LOCAL 1 /* Files are local
            #define MNT_FSTYPE_REMOTE 2 /* Files are remote
#define MNT_FSTYPE_PIPE 3 /* Files are pipes/fifos
#define MNT_FSTYPE_SOCKET 4 /* Files are sockets
#define MNT_FSTYPE_CSPS 6 /* STREAMS char spec @C
 /* Alternative Macro for Initializing Input Structures.
    ((CBHDR *)(\&(cb))) \rightarrow cblen = sizeof(typ);
 /* I/O Control Command Codes used by w_pioctl & vn_ioctl (BPXYIOCC)*/
    #ifndef IOC EDITACL
       #define \overline{I}OC_EDITACL 0x2000C100 /* Edit ACL: \underline{I}O('A',0) @P2A*/
    #endif
 /* File Group Pathconf structure used by v_pathconf (BPXYPCF) */
                                           /* raincont File Group
/* Link Max
/* Name Max
/* 51
   struct PC_filegrp {
                                              /* PathConf File Group @DFA*/
           int pcfglinkmax;
                                                                          @DFA*/
                                                                          @DFA*/
           int
                  pcfgnamemax;
                                                   Flags:
                                                                          @DFA*/
                                               /* No Trunc @DFA*/
/* Chown Rstd @DFA*/
/* Case Insensitive @DFA*/
           BIT
                  pcfgnotrunc
                                           :1;
                  pcfgchownRstd
           BIT
                                           :1;
                                          :1;
                  pcfgcaseinsensitive
           BIT
                                                  /* Case non-presrv @DFA*/
           BTT
                  pcfgcasenonpreserving :1;
           BTT
                                           :4;
                                                                        /*@DFA*/
           char pcfgRsvd[3];
                                                                        /*@DFA*/
```

```
};
                                                                /* 3@PDA*/
/* VLOCK - Byte Range Locking Structure for v_lockctl. (BPXYVLOK)*/
            and for vn_lockctl
     The POSIX flock structure and locking constants are defined in the fcntl.h header, which is included here.
/*
  #include <fcntl.h>
#ifndef _NOFCNTL
                                       /* If pgm does not request that*/
                                      /* fcntl.h be suppressed, */
/* see prolog for details. */
  #define FLOCK struct flock
#endif
typedef struct s_vlock {
           CBHDR vl_hdr;
                    /* LOCKER: fields that are used with VL_REGLOCKER*/
vl_serverpid; /* Server's PID */
vl_clientpid: /* Server's Client's PID */
                    vl_clientpid;
                                       /* Server's Client's PID
           int
           GTOK
                    vl lockertok;
                                       /* Token for Locker(Spid+Cpid) */
                    /* TID: individual lock owner within a locker.
           char
                    vl_clienttid[8]; /* Client's Thread's TID
                    /* OBJECT: represents a single locked file
                    vl_objclass; /* Object Class: HFS, MVS, etc */
vl_objid[12]; /* Obj's Unique Id within class*/
           int
           char
           GTOK
                    vl objtok;
                                       /* Token for Object(Class+Id) */
                    /*-----
                     ! The two fields below were never used and are
                     ! being left here so old programs that may
                     ! have referenced them will not suffer ! compile failures with this new header.
                     ! We are taking back these two fields:
                     ! char vl_dosmode
! char vl_dosaccess
! Have advised FVT on the disappearing of the
                                                                @DYA*/
                     ! fields
           BIT
                    vl_nosplitmerge :1; /*Do not split or merge
                                                                     @DYA*/
                                            ranges
                                      :7; /* Reserved
/* Reserved
           RTT
                                                                     @DYA*/
              char vl_rsvd;
                                                               @DUC @DYC*/
           char
                    vl blklocklen;
                                      /* Length for Blocking Lk @DUA*/
           char
                    vl_rsvd2[5];
                                                                   /*@DUC*/
           GTOK
                    vl vntoken;
                                       /* Unix Obj Vnode Token
                                                                     @DUA*/
                    /* Lock information: range and type, etc
           FLOCK
                    vl flock;
                                      /* POSIX flock structure
                    /* Version 2 Extensions - - - - - - @DUA*/
  #if defined(__PFS64) && defined(_LP64) /* 64bit PFS in am64 @E2A*/
                                                                  /*@E2A*/
     struct s_brlm_rangelock * vl_blockinglock;
                                /* 64bit Ptr to Blocking Lock
                                                                    @E2C*/
                                            /* 31bit PFS or am31 @E2A*/
 #else
           int
                   vl_rsvd3;
                                                                   /*@DUA*/
     struct s_brlm_rangelock
                                                                   /*@DUA*/
          * _PTR32_vl_blockinglock; /* Ptr to Blocking Lock
                                                                     @DVC*/
  #endif
                                                                   /*@DUA*/
           union {
                                                                   /*@DUA*/
                     /*----@DUA*/
#ifdef _LP64
                                                  /* Aiocb Ptr64 @PGA*/
                      void * vl_ax_aiocb;
                     #else
                                                                   /*@PGA*/
                                                                   /*@DUA*/
                       int
                               vl_rsvd4;
                      void * _PTR32 vl_ax_aiocb; /* Aiocb
                                                                     @DVC*/
                     #endif
  int vl_ax_aiocblen;
                                                                   /*@PGA*/
                                                    /* Aiocblen
                                                                     @DUA*/
                   } vl_aioext;
                                                                   /*@DUA*/
```

```
struct {
                        /* Ptr_to Output Chain is always Ptr32 @PHA*/
                     int vl_rsvd52;
                  struct s_brlm_unloadlockslist
                     char vl_ull_subpool; /* Subpool @DUA*/
char vl_ull_masklen; /* InMask Len @DYA*/
char vl_ull_retwaiters; /* Held & Wait @DUA*/
                                                          /*@PIC @PHA*/
                 } vl_ullext;
            struct {
                        /* UnloadLocks Input Extension
                   #ifdef _LP64
                                 /* Input Ptr64 to Object Mask @PHA*/
                                 /* like vl_objectmask
                                                                 @PHA*/
                       void * vl ull inmaskptr;
                   #else
                                                               /*@PHA*/
                                                                /*@DUA*/
                      int vl_rsvd5;
                                /* Input Ptr32 to Object Mask @PHA*/
                                                                @PHA*/
                                 /* like vl_objectmask
                       void * _PTR32 vl_ull_inmaskptr;
                                                               /*@PHA*/
                   #endif
                                                               /*@PHA*/
                           /* Input Fields: subpool,masklen,retwaiters
                             logically belong here but that would
                             change their fully qualified names. PIA*/
                 } vl ullIext;
                                                        /*@PIC @DUA*/
                        /* Purge Masks Extension @DUA*/
            struct {
                   vl_pg_masks; /* Obj/Own Masks Ptr64 @PHA*/
                                                               /*@PHA*/
                             vl_rsvd6;
                    struct vl_purgemasks * _PTR32
                                                                /*@DVC*/
                             vl_pg_masks; /* Obj/Own Masks @DVC*/
                   #endif
                                                               /*@PHA*/
                             vl_pg_maskslen; /* Masks Len
                                                                  @DUA*/
                     int
                 } vl_pgext;
                                                                /*@DUA*/
           } v1_u;
                                                                /*@DUA*/
                                                                /*@DUA*/
          char vl_rsvd7[12];
                                                                /*@DUA*/
 ? VLOCK;
/* Simple Field Names
                                                                 @DUA*/
                                                                /*@DUA*/
  #define vl_aiocb vl_u.vl_aioext.vl_ax_aiocb
#define vl_aiocblen
                                                               /*@DUA*/
                                                               /*@DUA*/
                                                                /*@DUA*/
                                                              /*2@PHC*/
   #define vl_outlistptr vl_u.vl_ullext.vl_ull_outlistptr
                                                                /*@DUA*/
  #define vl_inmaskptr vl_u.vl_ulllext.vl_ull_inmaskptr /*@PIC@DYA*/
#define vl_subpool vl_u.vl_ullext.vl_ull_subpool /*@DUA*/
#define vl_masklen vl_u.vl_ullext.vl_ull_masklen /*@DYA*/
   #define vl_retwaiters vl_u.vl_ullext.vl_ull_retwaiters /*@PHA*/
   #define vl_pgmasks vl_u.vl_pgext.vl_pg_masks
                                                               /*@DUA*/
  #define vl_pgmaskslen vl_u.vl_pgext.vl_pg_maskslen
                                                               /*@DUA*/
/* Constants
         #define VLOCK ID "VLOK"
         #define VLOCK_HDR {{VLOCK_ID}, sizeof(VLOCK)}
                   /* Values for Object Class: vl_objclass
         #define VL_HFS 0 /* Unix File #define VL_MVS 1 /* Legacy MVS #define VL_NFSCOBJCL 3 /* NFS Client
                                      /* Legacy MVS dataset
/* Lan File Server
                                      /* NFS Client object
                                                                  @DYA*/
         /* Values for v_lockctl cmd #define VL_REGLOCKER 1
         #define VL_UNREGLOCKER
                                    2
         #define VL_LOCK
                                    3
```

```
#define VL_LOCKWAIT
         #define VL_UNLOCK
#define VL_QUERY
#define VL_PURGE
         #define VL_LOCKASY
                                                                 /*@DUA*/
         #define VL_LOCKCANCEL 9
#define VL_UNLOADLOCKS 10
                                                                 /*@DUA*/
                                                                 /*@DUA*/
   /* UnLoadLocks Constants, for vl_retwaiters @DUA*/
#define ull_retwaiters 1 /* Output Holders & Waiters @DUA*/
#define ull_retalllocks 3 /* All Locks, Held & Waiting @DUA*/
/* The vl_objid used by fcntl() for POSIX locking of HFS files
      struct hfsobjid {
           /*-----*/
     /* Purge Locks Masks
                                                                   @DUA*/
          struct vl_purgemasks {
                                                                 /*@DUA*/
                                                                   @DUA*/
            /* These can be set, for example, as follows:
    int AllFoxes[4] = {-1,-1,-1,-1};
    int ClientTIDs[4] = {-1,-1,0,0};
    struct vl_purgemasks PM;
    memcpy(PM.vl_objectmask,AllFoxes,16);
    memcpy(PM.vl_ownermask,ClientTIDs,16);
     /* Lock Owner Structure - v_lockctl and v_open @DUA*/
     } LOCKOWNER ;
                                                           /*@DUA*/
    /* BRLM_RangeLock - A blocking lock or an unloaded lock. @DUA*/
             /* Values for rl_access
                                                                   @DUA*/
       #define rl_shr2excl 1 /* Read lock
#define rl_shr2excl 2 /* Write lock
#define rl_shr2excl 3 /* Read waiting for wrt
#define rl_openmodes 5 /* Acc & Deny Modes
                                                                       */
     /*-----*/
     /* BRLM UnloadLocks List
        @DIIA*/
                     int rsvd2;
                                                                 /*@DUA*/
    /* One Unloaded Lock List Segment @DUA*/
                                                                 /*@DUA*/
            char ull_id[8]; /* 'IGWLBULL'
unsigned int ull_length; /* Total length
char ull_ver; /* Version
char ull_sp; /* Storage SubPool
char ull_key; /* Storage Key
char rsvd1;
                                                                   @E3C*/
                      \verb|struct s_brlm_unloadlocks|| ist
                        * _PTR32 ull_next; /* Next on Chain @DVC*/
```

```
/*@DUA*/
       } BRLM_UNLOADLOCKSLIST;
 #ifdef _LP64
 #pragma pack(reset)
 #endif
#endif
                                     /* End of Common Structures */
#if !defined(__BPXYVFSI) && !defined(__BPXYVFSI_Common_Only)
 #define BPXYVFSI
/*****************************
**/
/**
/** Structures specific to the VFS interface.
                                                               **/
/**
#ifdef LP64
 #pragma pack(1)
 #endif
/*-----*/
/* VFSTOK & VNTOK - Opaque Tokens for file systems and files. */
/*-----*/
 typedef struct s_vfstok {
               char vfstok[8];
      } VFSTOK ;
                                  /* Vnode Token
typedef struct s_vntok {
                                                               */
               char vntok[8];
      } VNTOK ;
/*-----*/
//* OSS - Operating System Specific Information Structure (BPXYOSS)*/
/*------*/
 typedef struct s_oss {
            CBHDR os_hdr;
int os_diribc;
             int os_diribc; /* Directory I/O block cnt */
int os_readibc; /* Read I/O block cnt */
int os_writeibc; /* Write I/O block cnt */
BIT os_xmtpt :1; /* v_lookup cross mt pts @P5A*/
BIT os_noremote :1; /* v_rpn don't cross into remote
file sys, like NFSC @01A*/
             BIT
                           :30:
             GTOK os_opentoken;
                                /* v_open token
                                                           @DUA*/
  } OSS ;
         #define OSS_ID "OSS"
         #define OSS_HDR {{OSS_ID}, sizeof(OSS)}
     /*----- @DUA*/
      /* Special os_opentoken values -
         These are to be used to set the first word of the
                                                            @DUA*/
     /* open token to the special values that correspond
                                                            @DUA*/
      /*
          to the special stateids passed by the client.
                                                            @DUA*/
     /* They are used as in this example:
                                                            @DUA*/
         OSS 0;
                                                            @DUA*/
          0.os_opentoken.gtok[0] = OS_OTMANDCHK;
                                                            @DUA*/
                                              ----- @DUA*/
 #define OS_OTADVCHK (void*)(0) /* Advisory Check, V4 only @DUA*/#define OS_OTMANDCHK (void*)(2) /* Mandatory Check, all @DUA*/#define OS_OTOVERRIDE (void*)(1) /* No Checking - Rd Only @DUA*/
#ifdef _BPX_MNTE3
  #ifndef _BPX_MNTE2
                                                          /*@DXA*/
                                                          /*@DXA*/
   #define _BPX_MNTE2 1
                                                          /*@DXA*/
 #endif
                                                          /*@DXA*/
#endif
                                                          /*@DXA*/
/* RPNMNTE - Mount Entry Structures returned by v_rpn. (BPXYMNTE)*/
/* NOTE: me_mountpoint is not filled in by v_rpn.
/*-----
#ifdef _BPX_MNTE2
 #ifndef __syslistdef
                                                          /*@P8A*/
  #define __syslistdef 1
                                                          /*@P8A*/
  typedef struct s_syslistdef {
```

```
short int mt_syslistnum; /* Number of systems in list
                                                                     @DRA*/
            short int mt_syslistflags; /* Flags
                                                                     @DRA*/
                      mt_syslist[32] [8];/* System names
                                                                     @DRA*/
            } SYSLISTDEF;
                                                                   /*@DRA*/
                              /* Use the definition from mntent.h @P8A*/
   #define mt_syslistnum mnt2_syslistnum
#define mt_syslistflags mnt2_syslistflags
                                                                   /*@P8A*/
                                                                   /*@P8A*/
                                                                   /*@P8A*/
    #define mt_syslist
                             mnt2_syslist
                                                                   /*@P8A*/
     * Values for mt_syslistflags
    #define MNT_SYSLIST_INCLUDE 0x0000
                                                                   /*@DRA*/
    #define MNT_SYSLIST_EXCLUDE 0x0001
                                                                   /*@DRA*/
  #endif
  typedef struct s mnteh {
                                         /* w getmntent header
                                         /* Header with total length
         CBHDR
                       mh_hdr;
                                                                         */
         char
                       mh_cursor[8];
                                         /* Internal cursor
                                                                         */
                                         /* File System devno to find
         int
                       mh_devno;
   #ifndef _BPX_MNTE2
                                         /* mnte header definition @DLA*/
         int
                           rsvd;
                                         /* Reserved - must be
                                            zero on entry
                                         /* mnte2 header definition@DLA*/
   #else
         int
                       mh_bodylen;
                                         /* Length of the mnte body@DLA*/
                           rsvd[8];
                                         /* Reserved - must be
         char
                                            zero on entry
                                                                     @DIC*/
   #endif
                                                                   /*@DLA*/
    } MNTEH;
  typedef struct s_mnte {
                                         /* w_getmntent returned entry */
                       me_fstype;
                                         /* File system type
         int
                                         /* File system mount mode
         int
                       me_mode;
         int
                       me_dev;
                                         /* st_dev of this file system */
                                         /* st_dev of parent file sys
/* st_ino of the mount point
                       me_parentdev;
         int
                       me_rootino;
         int
                       me_status;
me_ddname[9];
                                         /* status of the file system. */
         char
         char
                                         /* ddname specified on mount
                       me_fstname[9];
                                         /* FILESYSTYPE Name
         char
         char
                       me_fsname[45];
                                         /* File System Name (HFS DSN) */
                                         /* Length of mount point path */
         int
                       me_pathlen;
                       me_mountpoint[1024]; /* Mount point pathname */
         char
                                         /* Job Name issuing Quiesce
/* PID that issued Quiesce
         char
                       me_jobname[8];
         int
                       me_pid;
                       me_parmoffset;
                                         /* Offset of mount parameter
         int
                                            from me_fstype
                                                                     @D8C*/
         short
                       me_parmlen;
                                         /* Length of mount parameter
   #ifndef BPX MNTE2
                                         /* mnte base
                                                        definition @DLA*/
                                         /* Reserved for expansion @D5C*/
                           rsvd[54];
         char
   #else
                                         /* mnte2 base definition@DLA*/
         char
                       me_sysname[8];
                                         /* system mounted on
                                                                     @DKA*/
                       me_qsysname[8];
me_fromsys[8];
                                         char
                                                                     @DKA*/
         char
                                            system
                                                                     @DKA*/
                                         /* reserved for alignment
         short
                       rsvd1;
                                                                     @DKA*/
                                         /* request flags
                       me_rflags;
                                                                     @DKA*/
                                         /* more status fields
         int
                       me status2;
                                                                     @DKA*/
                                                                     @DKA*/
         int
                       me_success;
                                         /* filesystems moved ok
                                         /* Number of reads
         int
                       me_readct;
                                                                      @DLA*/
                       me_writect;
                                                                      @DLA*/
         int
                                         /* Number of writes done
                       me_diribc;
                                         /* Number directoryI/O blks@DLA*/
         int
                                         /* Number read I/O blocks @DLA*/
                       me_readibc;
         int
                                         /* Number write I/O blocks @DLA*/
         int
                       me writeibc;
#ifdef BPXLL
         long long
                       me_bytesread;
         long long
                       me_byteswritten;
#else
                                         /* Total number bytes read
         int
                       me bytesreadhw;
                                                                      @DLA*/
                                            high word
         int
                       me bytesreadlw;
                                            Total number bytes read
                                            low word
                                                                      @DLA*/
         int
                       me_byteswrittenhw;/*Total number bytes-wrote
                                                                      @DLA*/
                                            high word
         int
                       me_byteswrittenlw;/*Total number bytes-wrote
                                            low word
```

```
#endif
            char
                             me_filetag[4];
                                                    /* File tag
                                                                                       @DNA*/
                             me_syslistoff;
                                                    /* offset to syslist
/* length of syslist
            int
                                                                                       @DRA*/
                             me_syslistlen;
            short
                                                                                      @DRA*/
            short
                             me_aggnamelen;
                                                    /* length of aggregate name
                                                                                      @DSA*/
                             me_aggnameoff;
                                                    /* offset to aggregate name
                                                                                      @DSA*/
            char
                             me_roseclabel[8];/* read only seclabel
                                                                                      @DTA*/
     #endif
                                                                                    /* @DLA*/
     #ifdef BPX MNTE3
                                                                                    /*@DXA*/
                                                 /* Seconds since mount
/* VfsPtr for this filesys
                                                                                      @DXA*/
         int me_mntsec;
         int me fstoken;
                                                                                      @DXA*/
         int me_pfsnormalstatusoffset;/* Offset of Pfs normal status
                                                                                      @DXA*/
         short me_pfsnormalstatuslength;/* Length of Pfs normal status
                                                                                      @DXA*/
         short me_pfsexcpstatuslength; /* Length of Pfs exception status
                                                                                       @DXA*/
         int me pfsexcpstatusoffset; /* Offset of Pfs exception status
                                                                                      @DXA*/
         unsigned int me_fsusrmntuid; /* UID of user that mounted the
                                                     file system. Always 0 for
                                                                                      @E0A*/
                                                     privileged mounts.
                                                                                 @E0C@DXA*/
         char me_expansion[76];
                                                 /* Expansion room
     #endif
                                                                                    /*@DXA*/
     } MNTE;
  typedef struct s_rpnmnte {
                                                    /* v_rpn returned entry:
                                                    /* w_getmntent neads_
/* one w_getmntent entry
            MNTEH rpn_mnteh;
           MNTE rpn_mnte;
     } RPNMNTE;
              #define
                          MNTEH ID
                          MNTE2H_ID
                                         "MNT2"
            /*#define
                                                                                    /*@DLA*/
                                                      */
            #define MNTE2H_ID "\xD4\xD5\xE3\xF2" /* MNT2 In Hex @DSC*/
#define MNTE3H_ID "\xD4\xD5\xE3\xF3" /* MNT3 In Hex @DXC*/
/*#define MNTE2H MNTEH delete conflict @P8D @DLA*/
              #define MNTEH_HDR {{MNTEH_ID}, sizeof(MNTEH)+sizeof(MNTE)}
                      /* Values for me_fstype are in the common area.
                       /* Values for me_mode
              #define MNT_MODE_RDWR
                                                0x00000000
                                                                             /*@P8C*/
              #define MNT_MODE_RDONLY
                                                                             /*@P8C*/
                                                0x0000001
              #define MNT_MODE_NOSUID #define MNT_MODE_EXPORT
                                                                             /*@P8C @DCA*/
/*@P8C @DCA*/
                                                0x00000002
                                                0x00000004
              #define MNT_MODE_NOSEC
#define MNT_MODE_NOAUTO
                                                0x00000008
                                                                             /*@P8C*/
                                                                                    /*@DKA*/
                                                16
              #define MNT_MODE_CLIENT 32
#define MNT_MODE_AUNMOUNT 64
#define MNT_MODE_SECACL 128
                                                                                    /*@DKA*/
                                                                                    /*@DPA*/
                                                                                    /*@DOA*/
                                                                                    /*@P9A*/
              #define MNT_MODE_RSVD1
                      /* Values for me_status
              #define MNT_FILE_ACTIVE #define MNT_FILE_DEAD
                                                                                    /*@D5A*/
                                                             0x00
                                                             0x01
              #define MNT_FILE_RESET
                                                             0 \times 02
              #define MNT_FILE_DRAIN
                                                             0x04
              #define MNT_FILE_FORCE
#define MNT_FILE_IMMED
#define MNT_FILE_NORM
                                                             0x08
                                                             0x10
                                                             0x20
              #define MNT_FILE_IMMED_TRIED
#define MNT_FILE_QUIESCED
                                                             0 \times 40
                                                             0x80
              #define MNT_FILE_MOUNT_IN_PROGRESS 0x81
                                                                                    /*@D7A*/
              #define MNT_FILE_ASYNCH_MOUNT
                                                             0x82
                                                                                    /*@D5A*/
              /* Values for me_status2
#define MNT_FILE_UNOWNED
                                                                                            */
                                                             0x01
              #define MNT_FILE_INRECOVERY
#define MNT_FILE_SUPERQUIESCED
#define MNT_FILE_RECYCLESTARTED
#define MNT_FILE_RECYCLEMOUNTING
#define MNT_FILE_RECYCLENOTACTIVE
                                                             0x02
                                                             0x04
                                                                                    /*@DXA*/
                                                             0x08
                                                             0x10
                                                                                    /*@DXA*/
                                                             0x20
                                                                                    /*@DXA*/
              /* Values for me_rflags
#define MNT_REQUEST_CHANGE
#define MNT_REQUEST_NEWAUTO
                                                                                            */
                                                             0 \times 01
                                                             0x02
```

```
/* NREG - Registration Parameter Block used with v_reg (BPXYNREG)*/
      NOTE: The CBINIT macro cannot be used with this structure.
 typedef struct s_nreg {
       char nr_id[4];
signed short nr_len;
short nr_ver;
                                              /* Identifier
                                              /* Length
/* Version
                       nr_type; /* Server Type in*/
nr_namelen; /* Server Name Length in*/
nr_name[32]; /* Server Name in*/
nr_maxvntok; /* Maximum VNTOK limit inout*/
nr_hotc :1; /* Exit needs Hotc Env in*/
nr_nowait :1; /* Don't wait for Quiesce in*/
nr_secsfd :1; /* secondary sfd server in*/
nr_allocdevno :1: /* Allocate a Devno in @DUA*/
                int
                char
                int
                BIT
                BIT
                BIT
                     BTT
               char nr_exitname[8]; /* Reserved
char nr_initparm[8]; /* Exit name
char nr_initparm[8]; /* Init parm for Exit
int nr_abendcode; /* Abend Code
int nr_abendrsn; /* Abend Reason
char nr_pfstype[8]; /* Dependant PFC
                                                                                    in*/
                                                                                  in*/
                                                                                   out*/
                                                                                  out*/
   } NREG;
                                    "NREG"
            #define NREG_ID "NR
#define NREG_VERSION 2
            #define NREG_HDR {NREG_ID}, sizeof(NREG), NREG_VERSION
            #define NREG_FILE 1
                                                /* File Server e.g.NFSS
            #define NREG_LOCK 2
#define NREG_FEXP 3
                                               /* Lock Server e.g.LOCKD
            #define NREG_SFDS 4
                                                /* Shared FD server: NW @DIA*/
            #define nr_devno nr_abendrsn /* Output Devno
/*-----*/
/* v_open
            /* Open_Parms Structure
                                                                                 @DUA*/
                     /*@DUA*/
   typedef struct s_openparms {
           } OPENPARMS ;
                                                                               /*@DUA*/
   /* Shr_Access parameter constants @DUA*/
#define SHRACC_WRITE 1 /* Access Intent is to Write @PAC*/
#define SHRACC_READ 2 /* Access Intent is to Read @PAC*/
#define SHRACC_BOTH 3 /* Access Intent is Read & Write */
   /* Shr_Deny parameter constants @DUA*/#define SHRDENY_NONE 0 /* No access is denied. */#define SHRDENY_WRITE 1 /* Deny Write access. @PAC*/#define SHRDENY_READ 2 /* Deny Read access. @PAC*/#define SHRDENY_BOTH 3 /* Deny Read and Write access. */
/**
                                                                                       **/
/**
    Calling Interface Definitions
                                                                                       **/
                                                                                       **/
```

```
/* Macros to translate the vnode calls to their callable services */
#define v_ioctl _VCALL(V_IOCTL #define v_reg _VCALL(V_REG #define v_rpn _VCALL(V_RPN _VCALL(V_GET #define v_rel VCALL(V_RFI
                                                  ,99)
                                                                                    /*@DWA*/
                                                 ,145)
                                                 ,146)
                                                ,148)
#define v_rel __VCALL(V_REL ,149)
#define v_rel __VCALL(V_REL ,149)
#define v_rdwr __VCALL(V_LOOKUP ,150)
#define v_readdir __VCALL(V_RDWR ,151)
#define v_readdir __VCALL(V_READDIR ,152)
#define v_create __VCALL(V_READLINK,153)
#define v_mkdir __VCALL(V_CREATE ,154)
#define v_mkdir __VCALL(V_SYMITNK ,155)
#define v_mkdir __vCALL(v_MkDiR ,155)
#define v_symlink __vCALL(v_SYMLINK ,156)
#define v_setattr __vCALL(v_GETATTR ,157)
#define v_setattr __vCALL(v_SETATTR ,158)
/*@DCA*/
                                                                                     /*@DDA*/
                                                                                     /*@P2A*/
                                                                                     /*@DFA*/
#define v_open _VCALL(V_OPEN_
                                               ,295)
                                                                                     /*@DUA*/
#define v_close
                         _VCALL(V_CLOSE
                                                 ,296)
                                                                                     /*@DUA*/
 /* Callable Services Typedefs and Prototypes
       NOTE: Each "len" parameter contains the length of the parameter that follows.
/*
 /*----
typedef void V_REG
                            (int len, NREG \star,
                                   int *rv, int *rc, int *rsn);
                               (OSS *,
typedef void V_RPN
                                   int pathlen, char *path,
                                   VFSTOK *, VNTOK *, int mlen, RPNMNTE *,
                                   int alen, ATTR *,
                                   int *rv, int *rc, int *rsn);
typedef void V_EXPORT (OSS *,
                                                                                    /*@DCA*/
                                   int
                                          function,
                                   char *filesysname,
                                   VFSTOK *, VNTOK *, int mlen, RPNMNTE *,
                                   int alen, ATTR *,
char *volhdl,
                              int *rv, int *rc, int *rsn);
(VFSTOK, OSS *,
FID, VNTOK *,
typedef void V GET
                                   int *rv, int *rc, int *rsn);
typedef void V REL
                               (VNTOK, OSS *,
                              int *rv, int *rc, int *rsn);
(VNTOK, OSS *,
typedef void V LOOKUP
                                   int namelen, char *name,
                                   int alen, ATTR *,
                                   VNTOK *,
int *rv, int *rc, int *rsn);
                               (VNTOK, OSS *,
typedef void V_RDWR
                                   UIO *,
                                   int alen, ATTR *,
int *rv, int *rc, int *rsn);
int *rv, int *rc, int *rsn);
typedef void V_READLINK(VNTOK, OSS *,
                                   UIO *,
int *rv, int *rc, int *rsn);
typedef void V_CREATE (VNTOK, OSS *,
                                   int namelen, char *name,
                                   int alen, ATTR *,
                                   VNTOK *,
                              int *rv, int *rc, int *rsn);
(VNTOK, OSS *,
typedef void V_MKDIR
                                   int namelen, char *name,
                                   int alen, ATTR *,
```

```
VNTOK *,
                          int *rv, int *rc, int *rsn);
typedef void V_SYMLINK (VNTOK, OSS *,
                         int namelen, char *name,
                          int pathlen, char *pathname,
                          int alen, ATTR *,
int *rv, int *rc, int *rsn);
typedef void V_SETATTR (VNTOK, OSS *
                         int alen, ATTR *,
                       int *rv, int *rc, int *rsn);
(VNTOK, OSS *,
typedef void V_LINK
                          int namelen, char *name,
                          VNTOK todir,
                          int *rv, int *rc, int *rsn);
typedef void V RMDIR
                       (VNTOK, OSS_*,
                          int namelen, char *name,
                          int *rv, int *rc, int *rsn);
typedef void V REMOVE
                       (VNTOK, OSS *,
                          int namelen, char *name,
int oldlen, char *oldname,
                          VNTOK newdir,
                          int newlen, char *newname,
int *rv, int *rc, int *rsn); typedef void V_FSTATFS (VNTOK, OSS *,
                          int falen, FSATTR *,
int *rv, int *rc, int *rsn);
typedef void V_ACCESS (VNTOK, OSS *,
                          int mode,
                          int *rv, int *rc, int *rsn);
typedef void V_LOCKCTL (OSS *,
                          int cmd,
                          int vlen, VLOCK *,
                          int *rv, int *rc, int *rsn);
typedef void W_PIOCTL (int pathlen, char *path,
                                                             /*@P2A*/
                          int cmd
                          int arglen, char *arg,
                          int *rv, int *rc, int *rsn);
/*@DFA*/
                          int *rv, int *rc, int *rsn);
typedef void V_OPEN
                       (VNTOK, OSS *,
                          int OpenParm_Length, OPENPARMS *OpenParm,
                         int Name_length, char *Name,
int CreateParm_Length, void *CreateParm,
int OAttr_length, ATTR *OAttr,
int *rv, int *rc, int *rsn);
typedef void V_CLOSE
                       (VNTOK, OSS *,
                                                              /*@DUA*/
                          GTOK *Open_Token,
                          int *rv, int *rc, int *rsn);
                       (VNTOK, OSS *,
typedef void V_IOCTL
                        int cmd,
                        int Argumentlen,
                        char *Argument,
                        int *rv, int *rc, int *rsn);
                                                          /*@DWA*/
/* Macros & structures used to address the OE Callable Services
   _VCALL Macro to invoke the i'th Vnode Callable Service
#define _VCALL(op,i) ((op *)
             ( (*(struct _v_cvt *_PTR32 *_PTR32)0x10) -> \
    _v_cvtcsrt -> _v_csrtvopt -> _v_vopptr[i] ))
                                                              /*@PFC*/
/* Stub System Control Blocks for addressing the Callable Services
/* OpenEdition Callable Services
                                                             /* @DVC*/
                                                             /* @DVC*/
                 /* MVS Callable Services Table */
 struct _v_csrt {
```

```
char filler[0x18];
          struct _v_vopt *_PTR32 _v_csrtvopt;
                                                                                                                      /* @DVC*/
    */
                                                            /* The CVT
                                                                                                                      /* @DVC*/
   #ifdef _LP64
      #pragma pack(reset)
     #endif
   /* Interface Linkages
                                   */
-----*/
#pragma linkage(V_RENAME , OS)
#pragma linkage(V_FSTATFS , OS)
#pragma linkage(V_LOCKCTL , OS)
#pragma linkage(V_EXPORT , OS)
#pragma linkage(V_ACCESS , OS)
#pragma linkage(W_PIOCTL , OS)
#pragma linkage(V_PATHCONF, OS)
#pragma linkage(V_COSE , OS)
#pragma linkage(V_COSE , OS)
                                                                                                                           /*@DCA*/
                                                                                                                           /*@DDA*/
                                                                                                                           /*@P2A*/
                                                                                                                           /*@DFA*/
                                                                                                                           /*@DUA*/
                                                                                                                           /*@DUA*/
   #pragma linkage(V_IOCTL
                                                       0S)
                                                                                                                           /*@DWA*/
 #else
                                            /* Linkage Versions for LP64 & XPLINK
                                                                                                                              @P7A*/
 #ifdef _LP64
                                                                                                                           /*@P7A*/
  #pragma linkage(V_REG , OS64_NOSTACK)
#pragma linkage(V_RPN , OS64_NOSTACK)
#pragma linkage(V_REL , OS64_NOSTACK)
#pragma linkage(V_LOSSICE)
  #pragma linkage(V_KEL , USO4_NUSTACK)
#pragma linkage(V_LOOKUP , OS64_NOSTACK)
#pragma linkage(V_RDWR , OS64_NOSTACK)
#pragma linkage(V_READDIR , OS64_NOSTACK)
#pragma linkage(V_CREATE , OS64_NOSTACK)
#pragma linkage(V_CREATE , OS64_NOSTACK)
#pragma linkage(V_CREATE , OS64_NOSTACK)
  #pragma linkage(V_PATHCONF, OS64_NOSTACK)
#pragma linkage(V_OPEN , OS64_NOSTACK)
#pragma linkage(V_CLOSE , OS64_NOSTACK)
#pragma linkage(V_IOCTL , OS64_NOSTACK)
#else /* XPLINK */
                                                                                                                           /*@DUA*/
                                                                                                                           /*@DUA*/
                                                                                                                           /*@DWA*/
  #else /* XPLINK */
#pragma linkage(V_REG , OS_UPSTACK)
#pragma linkage(V_RPN , OS_UPSTACK)
#pragma linkage(V_GET , OS_UPSTACK)
#pragma linkage(V_REL , OS_UPSTACK)
#pragma linkage(V_LOOKUP , OS_UPSTACK)
#pragma linkage(V_READDIR , OS_UPSTACK)
#pragma linkage(V_READDIR , OS_UPSTACK)
#pragma linkage(V_READLINK, OS_UPSTACK)
#pragma linkage(V_READLINK, OS_UPSTACK)
   #pragma linkage(V_CREATE , OS_UPSTACK)
```

```
, OS_UPSTACK)
 #pragma linkage(V_MKDIR
 #pragma linkage(V_SYMLINK , OS_UPSTACK)
 #pragma linkage(V_STHLINK , OS_UPSTACK)
#pragma linkage(V_SETATTR , OS_UPSTACK)
#pragma linkage(V_LINK , OS_UPSTACK)
#pragma linkage(V_RMDIR , OS_UPSTACK)
#pragma linkage(V_RMDIR , OS_UPSTACK)
 #pragma linkage(V_RMDIR , OS_UPSTACK)
#pragma linkage(V_REMOVE , OS_UPSTACK)
#pragma linkage(V_RENAME , OS_UPSTACK)
#pragma linkage(V_LOCKCTL , OS_UPSTACK)
#pragma linkage(V_EXPORT , OS_UPSTACK)
#pragma linkage(V_EXPORT , OS_UPSTACK)
 #pragma linkage(V_ACCESS , OS_UPSTACK)
#pragma linkage(W_PIOCTL , OS_UPSTACK)
#pragma linkage(V_PATHCONF, OS_UPSTACK)
#pragma linkage(V_OPEN , OS_UPSTACK)
#pragma linkage(V_CLOSE , OS_UPSTACK)
                                                                                                              /*@DUA*/
                                             , OS_UPSTACK)
                                                                                                              /*@DUA*/
 #pragma linkage(V_IOCTL , OS_UPSTACK)
                                                                                                              /*@DWA*/
                                                                                                              /*@P7A*/
#endif
                                                                                                              /*@P7A*/
#endif
  /* Macros to allow the calls by either the v_ or bpx1 names
                                                                                                                    */
#ifndef _BPXRTL_VFSI
                                                                                                /*@P7A*/
 #define bpx1vrg v_reg
 #define bpx1vrp v_rpn
#define bpx1vgt v_get
 #define bpx1vrl v_rel
#define bpx1vlk v_lookup
 #define bpx1vrw v_rdwr
 #define bpx1vrd v_readdir #define bpx1vra v_readlink
 #define bpx1vcr v_create
#define bpx1vmd v_mkdir
 #define bpx1vsy v_symlink
 #define bpx1vga v_getattr
#define bpx1vsa v_setattr
#define bpx1vln v_link
 #define bpx1vre v_rmdir
 #define bpx1vrm v_remove
 #define bpx1vrn v_rename #define bpx1vsf v_fstatfs
 #define bpx1vlo v_lockctl
 #define bpx1vex v_export
#define bpx1vac v_access
                                                                                                              /*@DCA*/
                                                                                                              /*@DDA*/
 #define bpx1pio w_pioctl
#define bpx1vpc v_pathconf
                                                                                                              /*@P2A*/
                                                                                                              /*@P2A*/
                                                                                                              /*@DUA*/
 #define bpx1vop v_open
                bpx1vcl v_close
 #define
                                                                                                              /*@DUA*/
 #define bpx1vio v_ioctl
                                                                                                              /*@DWA*/
#endif
                                                                                                              /*@P7A*/
 #endif
                                                                       /* End of VFSI Structures */
```

BPXYPFSI

```
BPXYPFSI
#ifndef
  #define
          BPXYPFSI
 /****START OF SPECIFICATIONS***************************
    $MAC (BPXYPFSI) COMP(SCPX4) PROD(FOM):
*01* MACRO NAME: BPXYPFSI
*01* DSECT NAME: N/A
*01* DESCRIPTIVE NAME: Physical File System Interface Definition for C
    ACRONYM: N/A
*02*
 /*01* PROPRIETARY STATEMENT=
*/
/*
                                                          */
/* LICENSED MATERIALS - PROPERTY OF IBM
/* 5650-ZOS COPYRIGHT IBM CORP. 1993, 2015
/* STATUS= HBB77A0
/*
```

```
/****END_0F_PR0PRIETARY_STATEMENT****************************
*01* EXTERNAL CLASSIFICATION: GUPI
*01* END OF EXTERNAL CLASSIFICATION:
*01* FUNCTION: Provide a C language header file for the PFS Interface.
      Defines C structures for the control blocks and tokens that
      are used by the vfs_ and vn_ operations.
      Defines C prototypes for the PFS entry points
      of the vfs and vn operations.
      Defines C structures and prototypes for the osi_ services
      and the macros used to implement the calling linkages.
      Defines C structures and prototypes for the File Exporter Exit.
*
      The definition of the following can be suppressed, see below.
         Defines C functions for the following Kernel Extension services
          bcopy() - copy data from source to destination
bzero() - zero out bytes starting at a destination
*
         Defines C functions for the following internal services
          _memmove() - copy characters from one data object to another
                       with checks for data overlap. This is invoked from the bcopy() function
*
    The following structures are defined here:
        O_VNTOK - Output Vnode Token
WPTOK - Wait/Post Token for osi_post
*
        SELT0K
                - Vn_select Token for osi_selpost
                - First Parameter of a Vnode or VFS Operation
        TOKSTR
                - Operating System Information - Second Parameter - Security Auditing Information - Third Parameter
        0SI
*
        CRED
        PFSPARM - Text from PARM operand of FILESYSTYPE and MOUNT.
*
        MTAB
                vfs_mount parameter
                vfs_network parameterPFS Initialization Block and related structures,
        NETW
        PFSI
       including the vnode and vfs operations tables.

PFSNAME - Name of the PFS from TYPE operand of FILESYSTYPE.
                - Operating System Interface Table with related
                structures, macros, and OSI function prototypes.
- File Exporter Exit parameter structure
       OTHDPRM - osi_thread parameter
OTHDCRCV- osi_thread called routine recovery block
        OGCDPRM - osi_getcred input structure

    vfs_batsel input array

        vncanflags - vn_cancel input flags
    The following structures are automatically included from BPXYVFSI:
                - General Eight Byte Token
*
       FID
                - File Identifier
                - General Control Block Header
        CBHDR
        ATTR
                - File Attribute Structure
                - User I/O Structure
        DIRENT - Directory Entries for v_readdir/vn_readdir.
        FSATTR - File System Attributes of v_fstatfs/vfs_statfs
    The following parts of the interface are defined in other
    headers as specified:
                         for vn_open, vn_rdwr, etc. are in fcntl.h, except for 0\_EXEC which is defined here.
       open_flags
*
                         for vn_access is in unistd.h
        access intent
       *
                            which are defined in this header.
                                                                          @DHA
       sigval
                         for osi_signal is in signal.h
        socket structures are in the various standard headers as used
                            by the sockets applications.
        ioctl commands for vn_ioctl are usually in ioctl.h.
                        Those used with Common Inet for initialization
                        and route changes are also included here.
  The following symbols provide for replaceable features:
```

```
_SOCKADDR - defines the socket address structure used in
*
                    the prototypes of the socket oriented vnode ops.
                    Default: #define _SOCKADDR char
Example: #define _SOCKADDR struct mysocketaddr
*
*
*
       _OSIT_PTR - defines the name of the variable or structure member
                    that holds the OSIT table address that was saved during PFS initialization. This is used to call
                    the OSI services.
                    Default: #define _OSIT_PTR osit_ptr
                    Examples: There are two ways this can be used:
*
                       (1) Declare and set osit_ptr to the saved value:
*
                            OSIT *osit_ptr;
                            osit_ptr = saved_address;
*
                       (2) Change the #define for _OSIT_PTR:
*
                            #undef _OSIT_PTR
#define _OSIT_PTR saved_address
*
       _OSICALL - internal macro for invoking the OSI_ services.
This macro is not normally replaced, refer to
                    its definition for details on how it works.
       _ADDR64 - Controls definition of the ADDR64 data type.
                    ADDR64 is an 8-byte data type used to deal with 64-Bit user pointers. If __ADDR64 is #defined then ADDR64 may be defined by the PFS else it will
                    be defined here based on _LP64.
       __FSPL
                  - Exposes the Fast Socket Parameter List.
                    This requires inclusion of socket.h.
   Conditional Processing is controlled by the following symbol:
       _NO_PFS_KES - suppresses the Kernel Extension Services.
                       Default: Include the service definitions.
                       Example use: #define _NO_PFS_KES
************************
*01* METHOD OF ACCESS:
*02*
       C/370:
          #include <string.h>
          #include <bpxypfsi.h>
*02*
       PL/X:
          None
*02*
       ASM:
          None
*01* DEPENDENCIES: Changes to the macros listed below must be reflected
                      in the corresponding structures of this header.
*01* NOTES:
      This header file is consistent with the following mappings:
             BPXZBSIC
             BPXYSEL
             BPXZCJAR
*
             BPXZGXPL
             BPXZMTAB
             BPXZNETW
*
             BPXZOSI
             BPXZOSIT
*
             BPXZPFSI
             BPXZTPRM
```

```
BPXZCPRM
           BPXZVFS0
           BPXZVNOP
           BPXZFSPL
           TRRPCRED
*01* COMPONENT: OpenMVS (SCPX4)
*01* DISTRIBUTION LIBRARY: AFOMHDR1
****END OF SPECIFICATIONS***********************************
 /* Include the common data areas
#define __BPXYVFSI_Common_Only
#include <bpxyvfsi.h>
#undef __BPXYVFSI_Common_Only
 /* Pack structures for 64-bit compiles
#ifdef _LP64
 #pragma pack(1)
 #endif
#pragma page()
 /* Opaque Tokens
 } 0 VNTOK ;
 WPTOK ;
 char seltok[16];
       } SELTOK;
 /* TOKSTR - Token Structure (BP:
/* This is the first parameter on all Vnode/VFS Operations
                                                 (BPXZCJAR)*/
 typedef struct s_tokstr {
     CBHDR ts_hdr;
                                /*+00 Id & Length
                               /*+00 Id & Length
/* PFS's Tokens: */
/*+08 Init Token (Vnode & VFS) */
/*+10 Mount Token (Vnode & VFS) */
/*+18 File Token (Vnode Only) */
          ts_init;
          ts_mount;
ts_file;
     GTOK
     GTOK
                               /*+20 LFS specific fields
/*+38 System Data 1
     char ts_LFS[24];
            ts_sysd1;
     int
          ts_sysd2;
                               /*+3C System Data 2
 } TOKSTR ;
   /* Constants for ts_sysd1 field
   /*----
 /* 64-Bit User Buffer Address Considerations
                -----
 /* An attempt is being made to accommodate C PFSes that are compiled
 * with LP64, those that are not, and those that aren't even compiled 
* with the 2.6 level of Language Extended (for long long).
 * A non-exploiting PFS mostly needs to be able to copy the 64-bit

* u_buff64vaddr field and its own 31-bit buffer address into the
 * 6\overline{4}-bit fields of the copy64_struct.
 * The PFS may typedef ADDR64 to an 8-byte data type of its own
 * choice and #define __ADDR64 to bypass the default typedef.
    #ifndef __ADDR64
#ifdef _LP64
                                       /* Compiler Flag */
```

```
typedef char * ADDR64; /* 64-bit pointer */
                                               /* 64-bit area
          typedef struct {
                                               /* High Word */
/* Low Word 31-bit ptr */
                    int HW;
                     char *LW;
                      } ADDR64;
    #endif
/* OSI - Operating System Information - Second Parameter (BPXZOSI)*/
typedef struct s_osi {
     CBHDR osi_hdr;
                                        /*+00 Id & Length
           * _PTR32 osi_ascb; /*+08 ASCB ptr(set by osi_wait)@E5C*/
* _PTR32 osi_ecb; /*+0C ECB ptr(set by osi_wait)@E5C*/
osi_pid; /*+10 Caller's PID for osi_signal*/
   BPXL32
     int
                                         /*+14 LFS data
     char
                osi_lfs[8];
                                         /* SMF I/O Counts Set by PFS: */
/*+1C Directory I/O block cnt */
/*+20 Read I/O block cnt */
                                         /*
                osi diribc;
     int
             osi_readibc;
     int
                                                  Write I/O block cnt
               osi_writeibc;
                                         /*+24
     int
                                                 Read Bytes (double word) */
                                         /*+28
     int
                osi_bytesrd_h;
                                         /*
                                         /*+2C Read bytes (single wd) */
/*+30 Write Bytes (double word)*/
     int
               osi_bytesrd;
     int
               osi_byteswr_h;
                                          /*
                                          /*+34 Written bytes (one wd)
     int
               osi_byteswr;
  #ifdef __PFS64
                                         /* --64 bit PFS--
     char osi_lfs64rsvd1[4];
                                         /*+38 LFS internal use
                                                                            @FOA*/
                                         /* --31 bit PFS--
  #else
                                                                            @E0A*/
            * _PTR32 osi_fsp;
                                         /*+38 Opt ptr to output FSP @E5C*/
     char
  #endif
                                                                         /*@EOA*/
     int
                                         /*+3C PFS identifier
                                                                            @D6A*/
              osi_pfsid;
  #ifdef __PFS64
                                          /* --64 bit PFS--
                                                                            @EOA*/
     char osi_lfs64rsvd2[4];
                                         /*+40 LFS internal use
                                                                            @E0A*/
                                         /* --31 bit PFS--
     struct osirtoken
                                          /*+40 Ptr to Recovery Token
                                                                            @E5C*/
             * _PTR32 osi_rtokptr;
  #endif
                                                                          /*@EOA*/
                                         /*+44 Flags
     BIT
               osi_LFSrsvd
                                                Reserved by LFS
                                                                            @PMA*/
                                       /* Reserved by LFS GPMA*/
/* External Caller GPMA*/
/* Reserved for LFS Use GEOA*/
/* No wait on quiesce GEOA*/
/* In process termination GPKA*/
/* On behalf of quiesce GPKA*/
/* Shared road GDIC*/
     BIT
                                   :1;
               osi_extcaller
     BIT
                                   :1;
     BTT
                osi_qnowait
                                   :1;
     BIT
                                   :1;
                osi_proctrm
     BIT
                osi_quiesce
                                        /*
/*
                osi_sharedread
                                   :1;
                                                Shared read
     BIT
                                                                            @DJC*/
                                                AsyncIO Part 1
     BIT
                osi_asy1
                                    :1;
                                                                            @DGA*/
                                                AsyncIO Part 2
     BIT
                osi_asy2
                                    :1;
                                                                            @DGA*/
                                                May Complete Immed
Did Complete Immed
                                   :1;
     BIT
                osi_ok2compimd
                                                                            @DGA*/
     BTT
                osi compimd
                                                                            @DGA*/
                osi_timedwait
                                   :1;
                                        /*
                                                                            @DJC*/
     BIT
                                                Timed Wait Requested
                osi_usersync
     BTT
                                   :1;
                                         /*
                                                 sync requested by user @DJC*/
     BIT
                osi_remount
                                   :1;
                                        /*
                                                Call is for remount @D9A*/
               osi_privileged :1;
                                                User is Privileged
     short osi_workarealen; /*+46 31bitWork Area Length */
char * _PTR32 osi_workarea; /*+48 31bitWork Area for PFS @E5C*/
 #ifdef __PFS64
    char osi_lfs64rsvd3[4];
                                         /* --64 bit PFS--
                                                                            @E0A*/
                                         /*+4C LFS internal use
/* --31 bit PFS--
                                                                            @EOA*/
  #else
                                                                            @EOA*/
     ATTR * _PTR32 osi_attr; /*+4C Optional Ptr to Output Attr@E5C*/
     WPTOK
                osi_token;
                                         /*+50 Token for osi_post
                                                                            @P7C*/
                osi_rsvd2[8];
                                         /*+68 reserved for LFS
     char
               osi_asytok;
osi_rsvd3[4];
                                         /*+70 AsyncIO LFS/PFS Token
     GTOK
                                                                            @DGA*/
                                         /++78 reserved for LFS
     char
                                                                            @P7C*/
             * _PTR32 osi_xmib;
                                         /*+7C Ptr to XMIB
                                                                            @E5C*/
     char
                                          /*+80 Original End of OSI
                                                                            @PFA*/
                                         /*+80 Flags2
     BIT
                osi_vfsexcl
                                   :1;
                                                VFS Latch is held EXCL @PMA*/
                                                 Running on Kernel Task @PMA*/
     BIT
                osi_onktask
                                   :1;
                                        /*
                                                Reserved, see BPXZOSI @E5C*/
Buffers in Common @DWA*/
     BIT
                                   :6;
                                   :1;
     BTT
                osi_commbuff
                                         /*
     BTT
                osi_fsmoving
                                   :1;
                                         /*
                                                File System is moving @EOA*/
     BIT
                                              osi_notsigreg
                                                                            @E5C*/
```

```
BIT
           osi_indirect64 :1; /*
                                          Buffer address is a pointer
                                           to a 64-bit buffer address
                                          BIT
                               :4; /*
                                    /*+82 unused yet
/*+88 User's Aiocb Addr
                                                                     @PMA*/
   char
             osi_rsvd4[6];
   ADDR64
             osi_uaiocb64;
                                                                     @DWA*/
                                    /*+90 reserved for LFS
   int
             osi_LFSrsvd5;
                                                                     @PMA*/
                                    /*+94 unused yet
/*+98 Open Token
   char
             osi_rsvd5[4];
                                                                     @PMA*/
   union {
                                                                     @F7A*
       char osi_OpenToken[8];
                                           /* Basic token
                                                                     @E7A*/
     struct { BIT
                                     :31;
                                                                  /*@E7A*/
               BIT osi_OTStateless :1; /* Stateless vn_open
                                                                     @E7A*/
               char osi_OTRsvd[3];
char osi_OTSysid;
                                                                   /*@E7A*/
                                          /* Remote open's sysid @E7A*/
             } osi_OTStruct;
                                                                  /*@E7A*/
         FID osi_OTok;
                                          /* Dual word format
                                                                     @E7A*/
         } osi_OT;
                                                                  /*@E7A*/
             osi_lfs2[4];
                                    /*+A0 LFS data
   char
                                                                     @FNC*/
                                    /*+A4 Available for expansion@EMC*/
             osi_rsvd6[28];
   char
                     /*+C0 End of Ver3 OSI ----- @EOA*/
                                    LP64) /*@EOA*/
/* --64bit PFS in amode64-- @EOA*/
#if defined(_PFS64) && defined(_LP64)
                                    /*+C0 Opt ptr to output FSP @EOA*/
   char * osi_fsp;
   struct osirtoken * osi_rtokptr;
                              /*+C8 Ptr to Recovery Token @EOA*/
/*+D0 Optional Ptr to Output Attr @EOA*/
   ATTR * osi_attr;
   char * osi_workarea64;
                                    /*+D8 64bit Work Area for PFS@EOA*/
   short
             osi_workarealen64;
                                    /*+E0 Work Area Length
                                                                    @FOA*/
                                    /* --31bit PFS or amode31-- @EOA*/
   char osi undefined[34];
                                    /*+C0 undefined
                                                                    @E0A*/
#endif
   char osi_rsvd7[46];
                                                                     @EOA*/
                                    /*+E2 available
                                    /*+110 End of OSI
                                                                     @PFA*/
} OSI ;
                                osi_OT.osi_OpenToken
   #define osi_opentoken
                                                                 /*5@E7A*/
   #define osi_otstateless osi_OT.osi_OTStruct.osi_OTStateless
   #define osi_otsysid
                                osi_OT.osi_OTStruct.osi_OTSysid
osi_OT.osi_OTok.fid[0]
   #define osi_otint0
                                osi_OT.osi_OTok.fid[1]
   #define osi_otint1
   #define osi_uaiocb osi_uaiocb64.LW /* User's Aiocb Addr @DWA*/
   /* PFS Recovery Token
        Set and Cleared by the PFS during a VNODE/VFS operation. */ If this is non-zero when an abend in the PFS is percolated*/
          to the LFS's ESTAE the PFS will be invoked for
           VN_RECOVERY to clean up its resources.
   /*
                                                                     @D5A*/
        If this is non-zero during user EOM processing the PFS will be invoked for VFS_RECOVERY to clean up
                                                                         */
          whatever was recorded with the token.
   /*-
   /* Use 16-byte osirtoken for 64-bit PFS
/* Use 8-byte osirtoken for 31-bit PFS
   #if defined(_PFS64) && defined(_LP64) /* 64 bit PFS  @EOC@EMA*/ struct osirtoken {    /*@EMA*/
                                                      64-bit ptrs @EMA*/
            void *
                           osirt_ptr[2];
                                               /*
                                                                   /*@EMA*/
   #else
                                                /* 31 bit PFS @EOC@EMA*/
    struct osirtoken {
            void * _PTR32 osirt_ptr[2];
                                               /*
                                                      31-bit ptrs @E5C*/
   #endif
                                                                  /*@EMA*/
   /* Extended recovery token area passed to vn_recovery @PCA*/ #if defined(__PFS64) && defined(_LP64) /* 64 bit PFS @EOC@EMA*/
    struct osirtokenx {
                                                                  /*@EMA*/
            struct osirtoken osirtx_rtoken; /* Orig osirtoken @EMA*/
                char
                                osirtx_rsv[8]; /* Reserved
                struct vnrcvydumplist * osirtx_dumplist; /* 64bit @EOC*/
                                                                   /*@EMA*/
   #else
                                              /* 31 bit PFS
                                                                @EOC@EMA*/
    struct osirtokenx {
                                                                  /*@PCA*/
            struct osirtoken osirtx_rtoken; /* Original osirtoken */
                char
                                osirtx_rsv[16];/* Reserved
                void * _PTR32 osirtx_sdwa; /* Ptr to SDWA or 0 @E5C*/
```

```
struct vnrcvydumplist * _PTR32 osirtx_dumplist; /*@E5C*/
                              osirtx_rsv2[8];
       } ;
                                                                  /*@PCA*/
     #endif
          /* The fourth parameter to vn_recovery may be considered as either osirtoken or osirtokenx. For migration
             purposes the prototype is not being changed.
                                                                    @PCA*/
     #if defined(__PFS64) && defined(_LP64) /* 64-bit PFS
                                                                    @FOA*/
          /* vn_recovery output dumplist for 64-bit PFS
                                                                    @E0A*/
          struct vnrcvydumplist {
                                                                  /*@EOA*/
                      int vnrcvydumpcount;
                                                                  /*@EOA*/
                   char vnrcvy_rsvd[4];
struct vnrcvydumparea {
                                                                  /*@EOA*/
                                                                  /*@EOA*/
                            char vnrcvydumpstoken[8];
                                                                  /*@EOA*/
                            void * vnrcvydumpaddr;
                                                         /* 64bit @EOA*/
                                                           /*@E0A*/
                            int vnrcvydumplength;
                            BTT
                                  vnrcvydumpsumm :1;
                                                                  /*@EOA*/
                            BTT
                                                                  /*@EOA*/
                    } vnrcvydumpareas[1];
                                                                  /*@EOA*/
                                                                  /*@EOA*/
           };
     #else
                                             /* 31-bit PFS
                                                                    @E0A*/
          /* vn_recovery output dumplist for 31-bit PFS
struct vnrcvydumplist {
                                                                    @EOC*/
                                                                  /*@PKA*/
                      int vnrcvydumpcount;
                                                                  /*@PKA*/
                   struct vnrcvydumparea {
                                                                  /*@PKA*/
                            char vnrcvydumpstoken[8];
                                                                  /*@PKA*/
                            void * _PTR32 vnrcvydumpaddr;
                                                                  /*@E5C*/
                                                                  /*@PKA*/
                            int vnrcvydumplength;
                            BIT
                                 vnrcvydumpsumm :1;
                                                                  /*@PKA*/
                            BTT
                                                                  /*@PKA*/
                    } vnrcvydumpareas[1];
                                                                  /*@PKA*/
                                                                  /*@PKA*/
     #endif
                                                                  /*@EOA*/
  /* vn_recovery retval flags
 /* CRED - Security Auditing Information - Third Parameter (IRRPCRED)*/
/*
/*
                                                                        */
          This parameter is generally just passed to SAF.
          Refer to SAF documentation for details on security
/*
          related interfaces and structures.
 /* length, alet, ptr set used by CREDACLINFO 6@DSA*/
 typedef struct s_credacl {
   int len;
int alet;
int rsv;
int ptr;
                            /* cred_aclinfo[].len
                            /* cred_aclinfo[].alet
                            /* cred_aclinfo[].ptr */
    } CREDACL;
 /* aclinfo area pointed to from cred 3@DSA*/typedef struct s_credaclinfo \{
    CREDACL cred_aclinfo[5];
    } CREDACLINFO;
  /* constants used to access an aclinfo slot for an acl type 6@DSA*/
  #define CREDACCESSACL 0
  #define CREDFMODELACL
  #define CREDDMODELACL
  #define CREDPFMODELACL 3
  #define CREDPDMODELACL 4
  /* Constants for cred_utype:
#define CRED_UREGULAR 1
                                     /∗ Regular User
  #define CRED_USYSTEM
                                     /* System User, like a superuser */
                                     */
/* Use Real UID/GID on checks
  /* Constants for cred_function:
  #define AFC_ACCESS
 typedef struct s_cred {
              cred_hdr;
cred_ver;
                                     /*+00 Id & Length
     CBHDR
                                     /*+08 Version
     char
     char
              cred_utype;
                                     /*+09 User Type
                                    /*+OA User Function
           cred_function;
```

```
/*+0C Reserved
     char
               rsv4;
                                                                      @DYA*/
               cred_rsv_bit8 :1; /*+OD reserved bit #8
     BIT
                                                                      @DYC*/
               cred_seclablactive :1; /* seclabel class active
cred_SeclRequired :1; /* mlfsobj option active
     BIT
                                                                      @DYA*/
     BIT
                                                                      @DZA*/
                                      /* reserved bits
/*+0E Security Audit Info
     BTT
                              :5;
                                                                      @D7C*/
               cred_info[50];
     char
                                                                      @DYC*/
     int
               rsv1:
                                      /*+40
                                                                     6@DSA*/
     int
               cred aclalet;
                                      /*+44
                                      /*+48
     int
               rsv2:
     void * _PTR32 cred_aclptr;
                                      /*+4C points to an ACL for access
                                                                      @E5C*/
     #define cred aclinfoptr cred aclptr /* for makefsp and setfacl*/
     char cred_seclabel[8];
void * _PTR32 cred_aceeptr;
                                     /*+50 security label
/*+58 ACEE for SRB requests
                                                                      @DYA*/
                                                                      @E5C*/
               cred_ROSeclabel[8];
                                     /*+5C Seclabel for RO Files
     char
                                                                      @DYA*/
     char
               rsv5[28];
                                      /*+64
  } CRED ;
#pragma page()
/* PFSPARM - Text from PARM operand of FILESYSTYPE and MOUNT.
    The parmtext field is of variable length, from 0 to 1024 bytes, */
   with the actual length passed in the parmlen field.
 typedef struct s_pfsparm {
 unsigned short parmlen;
                                          /* Length of the text
           char parmtext[1024];
                                         /* Text, not null terminated.*/
   } PFSPARM ;
/* MTAB - vfs_mount parameter
                                                              (BPXZMTAB)*/
                                                                          */
     This structure passes to the PFS the parameters that were
     specified on a ROOT or MOUNT command and provides for the
/*
     exchange of information between the LFS and PFS.
/*
     The PFS is expected to set the fields marked with an S,
     if appropriate.
    typedef char mt_aggname[45]; /* Aggregate Name
                                                                      @DUA*/
 typedef struct s_mtab {
    CBHDR
             mt_hdr;
                                    /* +00 Id & Length
                 rsvd1:
                                    /* +08 Reserved
    int
                                                                          */
              mt_filesys[44];
                                    /* +0C Name of the file system
    char
                                    /*S+38 DD name of the file system if
    char
              mt_ddname[8];
                                            mt_filesys is an MVS´DSN
              mt_filesystype[8]; /* +40 Type name of the PFS that
    char
                                            owns this file system.
                                    /* +48 Mount mode for this file sys*/
                                    /*
/*
                                            Read only specified Read/Write specified
    BIT
              mt_readonly :1;
                                                                          */
    BTT
              mt readwrite :1;
                            :1;
                                    /*
    BIT
                                                                      @D8A*/
              mt_nosuid
                                            no setuid
                                                                      @DNA*/
    BTT
              mt_nosec
                            :1;
                                    /*
                                            no security
    BIT
              mt noauto
                            :1;
                                    /*
                                            no automove
                                                                      @DPA*/
                                            Unmount during recovery@DTA*/
Reserved @DTC @DPC*/
                                    /*
    BIT
              mt_aunmount
                            :1;
                            :2;
                                    /*
                                                                @DTC @DPC*/
    BIT
                                    /* +49 Lfs specific flags
                                          Mount from an internal
    BIT
              mt_internalcall :1; /*
                                             module - no authority check
                                              is needed.
                                            If requests are made of this file system while it is
    BIT
              mt nowait
                               :1; /*S
                                              quiesced, don't wait for the
                                              unquiesce, give error rc. */
                               :1; /*
    BIT
              mt remount
                                           mount is a remount
                                                                     @DCA*/
    BTT
                                :5; /*
                                           Reserved
                                                                      @DCC*/
                                    /*S+4A Interval to use for sync
              mt_syncinterval;
    short
#ifdef __PFS64
                                            --64 bit PFS--
                                                                      @E0A*/
                                    /* +4C LFS internal use
/* +50 TAG Ccsid value
    char
              mt_lfs64rsvd1[4];
                                                                      @E0A*/
                                                                      @DRC*/
    int
              mt_ccsid;
                                    /*
                                           Mount Point: (for info only)*/
    char
              mt lfs64rsvd2[4];
                                    /* +54 LFS internal use
                                                                      @E0A*/
                                           --31 bit PFS--
                                                                      @E0A*/
    PFSPARM * _PTR32 mt_parmaddr; /* +4C Address of PARM specified on MOUNT or ROOT. @E!
                                                                      @E5C*/
    int
              mt_ccsid;
                                    /* +50 TAG Ccsid value
                                                                      @DRC*/
                                    /* Mount Point: (for info only)*/
```

```
* _PTR32 mt_mountptaddr; /* +54 Address of the pathname
#endif
                                                                     /*@EOA*/
    int
              mt_pathlen;
                                     /* +58
                                              Length of the pathname
    int
              mt_stdev;
                                    /* +5C The unique ID assigned to
                                            this filesystem.
                                                                This value
                                            must be returned in at_dev. */
                                     /* +60 Pathconf values for File Sys*/
    int
              mt_linkmax;
                                     /*S+60
                                              PFS: link_max
              mt namemax;
                                     /*S+64
                                              LFS & PFS: name max
    int
                                     /* +68 Pathconf flags */
/*S LFS & PFS: posix_No_trunc */
    BIT
              mt_notrunc
              mt_chownrstd :1;
    BIT
                                    /*S
                                              Security: chown restricted*/
    BIT
              mt_caseinsensitive
                                     :1; /*S 0=sensitive,1=not
              mt_casenonpreserving :1; /*S 0=perserving,1=not
    BIT
                                                                       @DHA*/
    BTT
                             :4:
                                     /*
                                              Reserved
                                     /* +69
                                                                       @DRC*/
    char
                 rsvd3[3];
                                              Reserved
    BIT
              mt_nullFS
                             :1;
                                     /* Null value for FILESYSTEM
                                                                       @DRC*/
              mt_nullMP
                             :1;
                                     /* Null value for MOUNTPOINT
    BIT
                                                                       @DRC*/
              mt_TagText
                                     /* TAG TEXT value. Auto conversion */
    BIT
                                     /* is allowed for every untagged */
/* file & mt_ccsid is the implicit */
                                     /* charset id. When off, auto
                                     /* conversion is precluded.
                                                                       @DRA*/
    BIT
                             :13;
                                     /*
                                              Reserved
                                     /* +6E PFS communication flags
    BTT
              mt_asynchmount :1;
                                    /*S
                                              Asynchronous mount in
                                              progress.
                                                  Set by PFS to indicate to LFS that mount will
                                                  complete asynchronously
                                                  Set by LFS to indicate to PFS that this call
                                                  is to complete an
                                                  asynchronous mount @DCC*/
    BTT
              mt_synchonly
                               :1:
                                    /*
                                              Mount must be completed
                                              synchronously. That is,
                                              vfs_mount must not return
                                              +1
                                                                       @D7A*/
    BIT
              mt noclient :1;
                                    /*S
                                              Mount must not be completed
                                              by establishing a client
                                              server relationship with
                                              owning system. Set by PFS
                                                                      @01C*
    BIT
                                              Set by the LFS to allow PFS
              mt_ininit
                             :1;
                                    /*
                                              to know mount was done
                                              during initialization @PAA*/
                                              Sysplex environment only:
    BIT
              mt_nevermove :1;
                                    /*S
                                              file system cannot be moved
                                                                       @DPA*/
                                               to another system
    BIT
              mt_secacl
                             :1;
                                    /*S
                                              Security product supports
                                              ACLS.
                                                                       @DSA*/
                                    /*S
    BIT
                                              Agg is attached R/W
                                                                       @DUA*/
              mt_aggattachrw :1;
                               :1;
                                              Agg is HFS Compatible @DUA*/
    BIT
              mt_agghfscomp
                                     /*S
                               :3;
    BIT
                                     /*
                                              Reserved for HFS @04C @03A*/
                                              Mount catchup
mount is for deadsys
    BIT
              mt_catchup
                               :1;
                                                                       @PQA*/
              mt_deadsystakeover
                                                                       @PSA*/
    BIT
                                    :1;
                                                                       @PSA*/
                               :1;
    BTT
              mt_bh
                                     /*
                                              blackhole mount
    BIT
              mt_restart
                               :1;
                                    /*
                                              mount for recycle must
                                              be asynchronous
                                                                       @EAA*/
              mt_nolocking
    BIT
                               :1;
                                    /*
                                          Locking not supported @04C@EBC*/
                rsvd4[8];
    char
                                     /*
                                              Reserved
                                                                       @DPA*/
              mt_sysname[8];
                                    /*
    char
                                              system to be mounted
                                                                       @DPA*,
                                              on
                    /*+80 End of Ver1 Mtab
                                                                       @DUA*/
    char
                rsvd5[14];
                                                                     /*@DUA*/
              mt_disablella
                                     /* +8E Disable LLA
    BTT
                                                                       @06A*/
                                            Mount as client if R/W
                                    /*
    BIT
              mt_rwmntclient :1;
                                                                       @06A*/
                               :1;
                                            samemode remount
    BIT
                                    /*
                                                                       @06A*/
              mt_samemode
    BIT
              mt_osictl
                                            osi_ctl
                                                                       @ESA*/
              mt_noblkinode3 :1;
mt_migtarget :1;
                                    /*
    BIT
                                            ok to create fid=3 node @EWA*/
    BIT
              mt_migtarget
                                     /*
                                            migration target
                                                                       @EYA*/
                                                                    EYC@EWC*/
    BIT
                               :10;
                                            Reserved
    char
                rsvd6[16];
                                                                     /*@06A*/
#ifdef __PFS64
                                            --64 bit PFS--
                                                                       @E0A*/
              mt_lfs64rsvd3[4];
                                     /*+A0
                                            LFS internal use
                                                                       @EOA*/
    char
                                            --31 bit PFS--
                                     /*
                                                                       0F0A*/
mt_aggname * _PTR32 mt_aggnameptr; /*+A0 Ptr to AggName Area
                                                                       @E5C*/
                                                                     /*@EOA*/
```

```
char rsvd7[12];
                                                                 /*@DUA*/
                   /*+B0 End of Ver2 Mtab ----- @DUA*/
     /* owner version and protocol are passed to the PFS on vfs_mount*/
     char mt_ownerprotocol; /*+B0 owner version @PRA*/
char mt_ownerprotocol; /*+B1 owner protocol @PRA*/
char rsvd8[6]; /*+B2 available @EOC*/
char * mt_mountptaddr; /*+D0 Address of the pathname@EOA*/
    mt_aggname * mt_aggnameptr; /*+D8 Ptr to AggName Area @EOA*/e /* 31-bit PFS or am31 @EOA*/
char mt_undefined[40]; /*+B8 undefined @EOA*/
    char
#endif
                                                                 /* @EOA*/
              GTOK
    char
 } MTAB ;
 /*-----
 /* NETW - vfs_network parameter (BPXZNETW)*/
 /*
      This structure passes to the PFS the parameters that were
      specified on a NETWORK command and provides for the
      exchange of information between the LFS and PFS.
      The PFS is expected to set the fields marked with an S.
  typedef struct s_netw {
     CBHDR nt_hdr;
int rsvd1;
                                   /* +00 ID & Length
                                   /* +08 Reserved
              nt_domnum;
                                  /* +00 Reserved
/* +00 Numeric value of the domain */
/* +10 Name of the domain */
/* +20 Filesystype of the PFS */
/* +28 Max number sockets */
     int
             nt_domname[16];
nt_type[8];
nt_maxsockets;
    char
char
int
int
     char
                                   /* +2C The unique ID assigned to
    this filesystem. This value
     int
              nt_stdev;
                                    must be returned in at_dev. */
/* +30 Parser Flags: */
/* DOMAINNAME given */
/* DOMAINNUMBER given */
/* MAXSOCKETS given */
/* TYPE ***
     BIT
              nt_havename :1;
     BIT
              nt_havenum
                            :1;
              nt_havesock :1;
     BIT
              nt_havetype :1;
                                             TYPE
                                                       given
     BIT
                            :4;
     BIT
                                       DOMAINNAME invalid
DOMAINNUMBER invalid
MAXSOCKETS invalid
TYPE invalid
     BIT
              nt_invaname :1;
              nt_invanum :1;
nt_invasock :1;
                                             DOMAINNUMBER invalid
     BIT
                                             MAXSOCKETS invalid
     BIT
              nt_invatype :1;
                                            TYPE invalid
     BIT
                                    /*
     BIT
                            :4;
                                    /* +32 Flags:
                                    BIT
              nt_localremote :1;
     BTT
              nt_commoninet :1;
     BIT
                              :6;
                 rsvd2[1];
                                    /* +33 Reserved
     char
                                    /* +34 Starting Reserved Port @PGA*/
     short
              nt_iaaport;
              nt_iaacount;
nt_parmmem[8];
                                    /* +36 Number of Reserved Ports@PGA*/
     short
                                    /* +38 Parmlib Member name @PGA*/
     char
                                    /* +40 */
   } NETW ;
       /* nt localremote values
       #define NETW_LOCAL 0 /*
#define NETW_REMOTE 1 /*
                                           Local (intra-system) socket */
                                           Remote (network) socket
 /* O_EXEC flag for the open_flags parameter of vn_open (BPXYOPNF)*/
    #define O_EXEC 0x00800000 /* Do Open Access check for Exec */
  #ifndef O_DENYRD
   #define O_DENYRD 0x00020000 /* v_open (deny_read)
                                                                   @E4A*/
  #endif
  #ifndef O_DENYWRT
   #define O_DENYWRT 0x00010000
                                     /* v_open (deny_write)
                                                                   @E4A*/
                                                      (BPXYSOCK)*/
 /* _SOCKADDR Dummy Value
```

```
#ifndef _SOCKADDR /* This macro can be externally set @PIM*/
   #define _SOCKADDR char /* to the desired sockaddr struct. @PIM*/
/* Select Parameters - vn_select and vfs_batsel (BPXYSEL)*/
/*----*/
 /* sel_function values
   #define SEL_QUERY 1 /* SELECT Query */
#define SEL_CANCEL 2 /* SELECT Cancel */
#define SEL_BATSELQ 3 /* BATCH-SELECT Query */
#define SEL_BATSELC 4 /* BATCH-SELECT Cancel */
#define SEL_POLLQUERY 5 /* POLL Query @P9A*/
#define SEL_BATPOLLQ 6 /* BATCH-POLL Query @P9A*/
#define SEL_BATPOLLC 7 /* BATCH-POLL Cancel @P9A*/
#define SEL_POLLCANCEL 8 /* POLL Cancel @P9A*/
 /* sel_options values
   #define SEL_READ 0x40000000 /* Read
   /* Batch Select Interface Control (BSIC) Block
 @E5C*/
SELTOK bs_seltok; /* Select Token for osi_selpost */
  } BSICENT;
 char * _PTR32 bsh_workptr; /* Work Area Ptr for use by PFS
                                               @E5C*/
    BSICENT bsh_ents[1]; /* Entry array (1 per fdcount) */
  } BSIC ;
/* vn_cancel Flags
/*----
/* PathConf Extensions - vn_pathconf (BPXYPCF)*/
```

```
/*-----*/
      #define PC_CASE 100 /* pathconf_option value @DHA*/
     #define CASE_INSENSITIVE 2 /* Ret if not sensitive @DHA*/
#define CASE_NONPRESERVING 1 /* Ret if not preserving @DHA*/
/*-----*/
struct anr_struct {
                             remote_sockaddr_length;
   /* --64 bit PFS-- @EOA*/
/* LFS internal use @EOA*/
/* --31 bit PFS-- @EOA*/
               _SOCKADDR * _PTR32 remote_sockaddr_ptr;
   #endif
                                                                             /*@E0A*/
              int
                            local_sockaddr_length;
   #ifdef PFS64
                                                       /* --64 bit PFS-- @EOA*/
               char anr_lfs64rsvd2[4];
                                                       /* LFS internal use @EOA*/
                                                       /* --31 bit PFS-- @EOA*/
   #else
               _SOCKADDR * _PTR32 local_sockaddr_ptr;
   #endif
                                                                             /*@EOA*/
                             msg_flags;
anr_length;
               int
                                                    /* len of anr_struct @EOA*/
               int
   #if defined(__PFS64) && defined(_LP64) /* 64bit PFS in AM64 @EOA*/
              _SOCKADDR *remote_sockaddr_ptr; /* 64bit ptr @E0A*/
_SOCKADDR *local_sockaddr_ptr; /* 64bit ptr @E0A*/
_* 31bit PFS or AM31 @E0A*/
   #else
              char anr_undefined[16];
                                                                            /*@E0A*/
   #endif
                                                                              /*@EOA*/
  } ;
                                                                              /*@PHA*/
/* 64-Bit Versions of the Iovec and MsgHdr (BPXYMSGH & BPXYIOV)*/
      /*@POA*/
ADDR64 iov64_base; /* 64-Bit Ptr */
int iov64_lenh; /* Required to be Zero */
signed int iov64_len; /* Length, < 2G */
   struct iov64 {
                                            /* 64-Bit sockaddr ptr */
/* 64-Bit iov ptr */
/* 64-Rit ancillary ptr */
   struct msg64hdr {
          t msg64ndr i //weroA*/
ADDR64 msg64_name; /* 64-Bit sockaddr ptr */
ADDR64 msg64_iov; /* 64-Bit iov ptr */
ADDR64 msg64_control; /* 64-Bit ancillary ptr */
int msg64_flags; /* MSG_flags */
int msg64_namelen; /* 31-Bit sockaddr length */
int msg64_iovlen; /* 31-Bit number of iovecs */
int msg64_controllen; /* 31-Bit ancillary len */
    3;
/* Fast Sockets Parameter List - VN_FSR/FSRF/FSRM (BPXZFSPL)*/
#ifdef _FSPL

struct fs_sr { /* FSP1 - vn_fsr

/*+30*/
                                                                                @POA*/
         int sr_ibufflen; /*+30*/
int sr_ibufflen; /* buf
int sr_ibufferalet; /* buf
int sr_iflags; /* fla
char * _PTR32 sr_ibufferptr; /* 31-
                                                 /* buffer length
/* buffer alet
/* flags
/* 31-bit ptr
                                                                                     */
                                                  /*+40*/
                                         /*+40*/
/* 64-bit buff ptr
          ADDR64 sr_ibufferptr64;
                                     /* FSP2 - vn_fsrf
   struct fs_srf {
                                                                                @POA*/
                   srf_ibufflen;
                                                   /*+30*/
                                                  /* buffer length
/* buffer alet
/* flags
/* sockaddr length
                                                                                     */
          int
                  srf_ibufferalet;
srf_iflags;
srf_isockaddrlen;
          int
                                                                                     */
          int
          int
 #if defined(__PFS64) && defined(_LP64) /* --64 bit PFS--
                                                                                @EOA*/
                                                   /*+40*/
          char srf_lfs64rsvd[4];
                                          /* LFS internal use @EOA*/
```

```
char * _PTR32 srf_ibufferptr;  /* ptr to buffer @EOA*/
ADDR64 srf_ibufferptr64;  /* 64-bit buff ptr @EOA*/
char * srf_isockaddrptr;  /* ptr to sockaddr 64-bit
    in primary @EOA*/
                                                               in primary @EOA*/
                                                  /* --31 bit PFS--
 #else
                                                                             @EOA*/
                                                  /*+40*/
         char * _PTR32 srf_isockaddrptr; /* ptr to sockaddr in pri
                                                                             @E5C*/
         char * _PTR32 srf_ibufferptr;
ADDR64 srf_ibufferptr64;
                                                 /* ptr to buffer
                                                                             @E5C*/
                                                       64-bit buff ptr
                                                 /*
                                                                                 */
                                                                             @E0A*/
                srf_undefined[8];
                                                 /*
                                                       undefined
         char
 #endif
                                                                           /*@EOA*/
     } ;
                                                                             @POA*/
                                    /* FSP3 - vn_fsrm
   struct fs_srm {
                                                 /*+30*/
                                                 /* flags
                   srm_iflags;
                   srm_iiovalet;
                                                       iov structure alet
         int
                                                 /*
                                                 /* alet for iov buffers */
         int
                   srm_iiovbufalet;
         union {
             struct msghdr srm_imsghdr; /* 31-bit msghdr struct { int rsvd; struct msg64hdr srm_imsghdr64; /* 64-bit msghdr } srm_imsghdr64u;
                                                                                  */
                                                                                  */
                } srm_imsgh;
     } ;
 struct s_fspl {
                                                                           /*@POA*/
            fs_hdr;
    CBHDR
                                       /* ID & Length
                                                                                  */
                rsvd1[3];
                                       /* Reserved
                                       /* Flags:
/* user's key
               fs_key
    BTT
                               :4;
                               :1;
                                       /* 64-bit buffer addrs
               fs_addr64
    BIT
    BIT
                               :1;
                                        /*
    BIT
               fs_shutd
                               :1;
                                             send & shutdown (msg_eof)
    BIT fs_rwind
CRED * _PTR32 fs_cred;
                                             0=read, 1=write
ptr to cred
                                        /*
                               :1;
                                        /*
                                                                             @E5C*/
                                        /*+10*/
    GTOK
               fs_pfstok;
                                        /*
                                             pfs token from vnode (ts_file)*/
               fs_openflgs;
                                             open flags
--64 bit PFS--
    int
           PFS64
 #ifdef
                                                                             @E0A*/
                                        /*+1C LFS internal use
/* --31 bit PFS--
    char fs_lfs64rsvd[4];
                                                                             @FOA*/
 #else
                                                                             @E0A*/
    OSI * _PTR32 fs_osi;
                                        /*+1C ptr to osi, 31-bit
                                                                             @E5C*/
                                                                           /*@EOA*/
 #endif
                                        /*+20*/
               fs_rv;
                                        /* return value
    int
                                        /* return code (errno)
/* reason code (errnojr)
/* common socket descriptor
    int
               fs_rc;
                                                                                  */
    int
               fs_rsn;
    int
               fs_sockdes;
                                                                                  */
                                        /*+30*/
                                        /* call specific parms
    union {
                                                                                  */
            struct fs_sr fs_isr;
struct fs_srf fs_isrf;
             struct fs_srm fs_isrm;
     } fs_parms;
                  rsvd2;
                                             Adj to match BPXZFSPL
    int
                                                                             @EKA*/
                                        /*+6C*/
                                        /★ Timout in Milli-seconds
    int
               fs_timeout;
                                                                             @EKA*/
                                        /*+70*/
                                       /* LFS Thread Token
               fs_threadtoken[8];
    char
                                                                             @EKA*/
                                        /*+78*/
 #if defined(__PFS64) && defined(_LP64) /* --64 bit PFS
                                                                             @E0A*/
                                       /*+78 ptr to osi, 64-bit
/* --31 bit PFS--
    OSI * fs_osi;
                                                                             @EOA*/
 #else
                                                                             @EOA*/
                                        /*+78*/
    char fs_undefined[8];
                                                                           /*@EOA*/
                                                                           /*@E0A*/
                                        /*+80*/
    char fs_rsvd[16];
                                        /* available for expansion @EOA*/
                                        /*+90*/
  } ;
#endif
/* Inactive buffer structure (IAB) - vfs_inactive (BPXZOSI)
   typedef struct s_iabent {
    char * _PTR32 iab_vnode;
    /* Individual Entry
    /* Vnode pointer
                                                                             @E5C*/
        char iab_pfs[8];
                                         /* Pfs token
```

```
char * _PTR32 iab_server_vnode; /* Server's vnode ptr
                                 /* Fid for validation
               iab_fid;
       int
                iab_return_value; /* Return value
    } IABENT;
  /* Main structure with array: */
                                    /* Device number
                                       Entry array (1 per vnode) */
    } IAB;
                                                            /*@PLA*/
#ifndef SIOCSETRTTD
   /* Ioctl commands used during initialization of a PFS
   /* when using Common Inet
                                                               @P8A*/
   /* NOTE: Values of the form 000013xx can only be used
                                                                  */
       with the w_ioctl() function, not with ioctl().
    #define SIOCSETRTTD
#define IOCC_TCCE
                               0x8008C981 /* Set TD - Left bookend */
0x0000138e /* (5006) - Right bookend*/
   /★ Ioctl commands used during normal processing of route
                                                               @P8A*/
   /* changes when using Common Inet
                               0x0000138f /* (5007) - Delete Route */
0x00001390 /* (5008) - Add Route */
     #define SIOCMSDELRT
    #define SIOCMSADDRT
                               0x00001391 /* (5009) - Set Interface
     #define SIOCMSSIFADDR
                                                      Address */
     #define SIOCMSSIFFLAGS
                               0x00001392 /* (5010) - Set Interface
                                                     Flags
     #define SIOCMSSIFDSTADDR
                               0x00001393 /* (5011) - Set pt-to-pt
                                                  interface address*/
     #define SIOCMSSIFBRDADDR
                               0x00001394 /* (5012) - Set broadcast
                                                      Address
     #define SIOCMSSIFNETMASK
                               0x00001395 /* (5013) - Set Interface
                                                      Network Mask */
     #define SIOCMSSIFMETRIC
                               0x00001396 /* (5014) - Set Interface
                                                     Routing Metric*/
                               0x00001397 /* (5015) - Rebuild Routing
     #define SIOCMSRBRTTABLE
                                                      Table
                                                                  */
     #define SIOCMSMETRIC1RT
                               0x00001398 /* (5016) - Set Metric1 */
     #define SIOCMSICMPREDIRECT 0x00001399 /* (5017) - ICMP Redirect*/
#endif
#pragma page()
/* Physical File System Initialization Interface Structures
     These structures are used during the activation of a PFS.
     The pfsinit routine is invoked with the following parameters:
/*
       pfsinit(PFSI *P, PFSNAME *N, PFSPARM *M, void *V, OSIT *0)
/*
    The variable names, P,N,M,V, and O are used in the examples.
/****************************
/* PFSI - PFS Initialization Block
                                                         (BPXZPFSI)*/
/*
                                                                   */
/*
     This structure is used to exchange information between
                                                                   */
     the LFS and PFS during initialization.
/*
/*
    The PFS is expected to set the fields marked with an S.
/*
 typedef struct s_pfsi {
  CBHDR pfsi_hdr;
                           /* +00 ID and Length
                                                                   */
                           /* +08 Version number
         /* +0A Reserved
pfsi_tdindex;
pfsi_nfsors

/* +0B Cincl
  short
                                                                   */
  char
         pfsi_tdindex; /* +0B Cinet Td Index passed to PFS @DVA*/
pfsi_pfsanchor; /*S+0C The PFS init token that will be
                                   passed to the PFS on all calls. */
  struct vfsotab
   * _PTR32 pfsi_vfso;
                           /*S+14 Address of the VFS ops table @E5C*/
                           /* +18 Flags
  BIT
         pfsi_ook
                      :1;
                           /* File system is running outside
                                   the kernel
                                                                   */
                             /* File system is the only PFS in
  BTT
          pfsi_alone :1;
                                   this A.S. outside the kernel
         pfsi_new :1; /* File system is being intialized
  BIT
```

```
for the 1st time in this AS @POC*/
BIT
        pfsi_estaeexits :1; /*
                                   osi_thread called routine
                                     permanent ESTAE supported
                                                                    @DMA*/
                                   LFS supports osi_memcritical
BIT
        pfsi_memcritical:1; /*
                                     in this release
                                                                    @@2A*/
BIT
        pfsi_sysplex :1;
                               /*
                                   USS started SYSPLEX(YES)
                                                                    @E0A*/
        pfsi_kernelready_supp :1; /* ot_kernelready supported @EEA*/
BIT
BIT
                       :1:
                                  Reserved
                                                                    @E0C*/
                              /*
                             /* +19 Flags2
                                                                    @DWA*/
BIT
        pfsi_commbuff
                          :1; /*s Common Buffers Supported
BIT
                          :1; /*s Module Indirection for all routine
        pfsi modind
                                   addresses supplied
                                                                    @E1A*
                          :1; /*s Attr supported on create :1; /*s Stop PFS is supported
BIT
                                                                    @E2A*/
        pfsi_attrcreat
BIT
        pfsi_stoppfs
                                                                    @E3A*/
        pfsi_sharessupported :1; /*s shares supported pfsi_opentokens :1; /*s Open context used
BIT
                                                                    @E4A*
BIT
                                                                    @E7A*/
        pfsi_concurrentmount :1; /*S on when PFS supports concurrent
BIT
                                                                    @F8A*
                                        mounts and unmounts.
BTT
        pfsi amode64
                                :1; /*S PFS runs AMODE 64
                                                                    @EKA*/
                            /* +1A Flags3
BIT
        pfsi osync
                               /*S vn open does fsync for O SYNC @PMA*/
                       :1;
                               /*S SRM Mode supported
BIT
        pfsi_srb
                                                                    @DGA*/
                               /*S Async I/O supported
                       :1:
                                                                    @DGA*/
BIT
        pfsi_asyio
                               /*S ReadDirPlus supported
BIT
        pfsi_rddplus :1;
                                                                    @DHA*/
                              /*S 64-Bit Real Page Supported
BIT
        pfsi_64datoff :1;
                                                                    @PMA*/
        pfsi_nolgfile
pfsi_addr64
                               /*S O_NOLARGEFILE size checking
                                                                    @PMA*/
BIT
                         :1;
                              /*S 64-Bit User areas supported
                                                                    @PMA*/
BIT
                         :1;
                         :1;
                              /*S IPv6 Capable
                                                                    @DVA*/
BTT
        pfsi_ipv6
                             /* +1B Flags4
BIT
        pfsi_romntclient :1; /*S=1: Read-only mounts on other than
                                       owner should be client
                                        (i.e. served)
                                   =0: Such mounts should be local
                                        (i.e. file system is sysplex
                                        aware)
                                                                    @PEC*/
BIT
        pfsi_rwmntclient:1; /*S=1: Read-write mounts on other than
                                       owner should be client
                                   =0: Such mounts should be local
                                                                    @DOC*/
        pfsi_usethreads :1; /*S File system requests support for
BIT
                                     the osi_thread function
                                                                    @D7A*/
        pfsi_disableLLA :1; /*S File system requests no lookup
BTT
                                                                    @D5A*/
                                     look aside support
BIT
                          :1; /*S File system requests no other PFS
        pfsi_stayalone
                                     be started in this A.S.
                          :1; /*S Removed files are deleted if, or when, their open count is 0 @D6A*/
BIT
        pfsi_immeddel
        pfsi_cpfs
                          :1; /*S File system is written in C. Invoke
BTT
                                     w/ a preinit. C environment
BIT
        pfsi_datoffmove :1; /*S File system supports DATOFF move
                                     for page read operations
struct vnoptab
* _PTR32 pfsi_vnop;
                            /*S+1C Address of the Vnode ops tbl @E5C*/
        pfsi_tcbaddr;
                             /\star +20 Address of the TCB for this PFS \star/
        pfsi_initcompecb; /* +24 ECB that the PFS posts when
BPXL32
                                     initialization is complete. @E5C*/
                             /*S+28 The type of the PFS
char
        pfsi_pfstype;
                             /* +29 More PFS Input/Output FLAGS
                                                                    @EGA*/
        :8;/* +29 IN: Set by LFS as input @ipfsi_asyncIOANR:1;/* +2A OUT: AsyncIO for ANR supported
BIT
                                                                    @EGA*/
BIT
                                                                    @EGA*/
BIT
         pfsi_rddcursor :1;/*
                                    OUT: PFS supports index to cursor
                                    conversion for readdir
                                                                    @EJA*/
BTT
                         :6;/*
                                    OUT: Set by PFS as output
                                                                    @EGA*/
                         :8;/* +2B reserved
BIT
                                                                    @EGA*/
BPXL32
        pfsi_pfsecb;
                             /* +2C ECB that is posted when the Kernel
                                     is terminating. The PFS should
                                     be waiting on this ECB.
                                                                    @E5C*,
                                    Pathconf() values as applicable: */
                                       pipe_buf
                              /*S+30
int
        pfsi_pipebuf;
                              /*S+34
int
        pfsi_maxcanon;
                                       max_canon
                              /*S+38
int
        pfsi_maxinput;
                                        max_input
                              /* +3C
                                        Flags:
BIT
        pfsi_chownrstd :1; /*S
                                        POSIX Chown restr
                              /*
BIT
                         :7;
                                        Reserved
                                                                         */
        pfsi_rsvd3[2];
                              /* +3D
char
                                       Reserved
                                                                         */
char
        pfsi vdisable;
                              /*S+3F
                                        _posix_vdisable
char \star _PTR32 pfsi_restart; /* +40 Addr of Restart Option Byte@E5C*/struct dmpinf
* _PTR32 pfsi_dumpptr;
                              /* +44 Address of Dump Information @E5C*/
```

```
pfsi_asname[8]; /* +48 Address Space Name of PFS
 char
                                                                     @D1A*/
                             /* +50 Entry point attached during
         pfsi_ep[8];
                                     initialization
                                                                      @D1A*/
                             /* +58 Pfs Identifier
                                                                     @P5A*/
 int
        pfsi_pfsid;
 struct ot_statflags
 * _PTR32 pfsi_otstatptr; /* +5C osi_thread status flags
                                                                      @E5C*/
 char pfsi_rsvd4[8]; /* +60 Reserved
/* Inserts f
                                                                     @P5C*/
         /* Inserts for Dump Titles:
pfsi_compon[3]; /*S+68 This PFS's Component Prefix
pfsi_compid[5]; /*S+6B This PFS's Component ID
                                                                        */
                                                                          */
 char
                                                                         */
          pfsi_startname[8];/* +70 Start name for PFS
                                                                      @DAA*/
         pfsi_pfspc; /* +78 PfsPc Number, Colony Only pfsi_rsvd5[8]; /* +76 Reserved pfsi_complow; /* +84 low reason code value pfsi_comphigh; /* +85 high reason code value pfsi_rsvd6[2]; /* +86 Reserved
 char
 int
                                                                     @PMA*/
                                                                      @E3A*/
 char
 char
                                                                     @E3A*/
 char pfsi_comphigh;
char pfsi_rsvd6[2];
char pfsi_pooltoken
                                                                     @E3A*/
                             /* +86 Reserved
                                                                      @E5C*/
         pfsi_pooltoken[8];/* +88 Storage token for this PFS
                                                                     @E5A*/
 char pfsi_rsvd7[16]; /* +90 Reserved
                                                                     @E5A*/
} PFSI ;
     /*-----
    #define RESTART_WTOR 0 /* Prompt operator first */
#define RESTART_AUTO 1 /* Restart automatically */
#define RESTART_NONE 2 /* Do not restart this PFS */
#define RESTART_KILL 3 /* Terminate OMVS too */
                                        /* Restart Colony and Prompt
operator for PFS restart @D1A*/
     #define RESTART RCWTOR 4
     #define RESTART_RCAUTO 5
                                        /* Restart Colony and
                                           Automatic PFS restart @D1A*/
     #define RESTART_RCNONE 6 /* Bring down Colony and No PFS restart tried @D1A*/
#define RESTART_PFSCTL 7 /* Wait for pfsctl(Restart)
                                                                     @PJA*/
    /* pfsi_pfstype - PFS Type Values
    /* Example usage: P->pfsi_pfstype = MNT_FSTYPE_REMOTE;
           /* These are defined with the common structures in
           /* BPXYVFSI as the constants starting with MNT_FSTYPE_ */
     /* pfsi_ver - Version Values
    /* pfsi_otstatptr - pointer to status flags for the PFS @P5A*/
    /*-----*/
/* pfsi_vnop - VNODE Operations Table (BPXZVNOP)*/
     /\star This table is built by the PFS and returned to the LFS \star/
     /*-----
     #define VN_OPEN
     #define VN_CLOSE
     #define VN_RDWR
#define VN_IOCTL
     #define VN_GETATTR
     #define VN_SETATTR
     #define VN_ACCESS
     #define VN_LOOKUP
     #define VN_CREATE
     #define VN_REMOVE
     #define VN_LINK
                                    10
     #define VN_RENAME
                                    11
     #define VN_MKDIR
#define VN_RMDIR
                                    12
                                    13
     #define VN_READDIR
                                    14
     #define VN_SYMLINK
                             15
```

```
#define VN_READLINK
 #define VN_FSYNC
#define VN_TRUNC
#define VN_INACTIVE
#define VN_AUDIT
#define VN_PATHCONF
                                      20
                                                                           /*@D5A*/
                                      21
 #define VN_RECOVERY
                                                                           /*@D5A*/
 #define VN_LOCKCTL
#define VN_CANCEL
                                      23
                                      24
                                                                           /*@DGA*/
 #define VN_SELECT #define VN_ACCEPT
                                      25
 #define VN BIND
 #define VN_CONNECT #define VN_GETNAME
 #define VN_SOCKOPT #define VN_LISTEN
                                      30
                                      31
 #define VN_READWRITEV
 #define VN_SNDRCV
#define VN_SNDTORCVFM
                                      33
 #define VN_SRMSG
                                      35
 #define VN SHUTDOWN
                                      37
#define VN_FSR
#define VN_FSRF
                                                                           /*@DLA*/
                                      38
                                      39
                                                                           /*@DLA*/
 #define VN_FSRM
                                      40
                                                                           /*@DLA*/
 #define VN_SRX
                                      42
                                                                           /*@DLA*/
 #define VN_ANR
                                      43
                                                                           /*@DLA*/
 #define MAX_VNOPS
                                     44
                                              /★ Generalized Vnode Op
 typedef void VNOP OP();
 #pragma linkage(VNOP_OP, OS)
                                              /* Is called with OS lnkg */
struct vnoptab {
                                               /* The Vnode Op Table
             CBHDR
                     vnop hdr;
          VNOP_OP * _PTR32 vnop_op[MAX_VNOPS];
                                                                          /*@EKC*/
 };
 #define VNOP ID
                         "VNOP"
 #define VNOP_HDR {{VNOP_ID}, sizeof(struct vnoptab)}
     /* Example initialization of this table:
            * Get storage, init hdr & zero out rest *
struct vnoptab pfstab = { VNOP_HDR };

* Set the address of each supported op *
            pfstab.vnop_op[VN_OPEN] = pfs_open;
pfstab.vnop_op[VN_CLOSE] = pfs_close;
pfstab.vnop_op[VN_RDWR] = pfs_rdwr;
              . . . etc.
                        * Return the table address to the LFS
            P->pfsi_vnop = &pfstab;
/* pfsi_vfso - VFS Operations Table (BPXZVFSO)*/
   This table is built by the PFS and returned to the LFS \star/
#define VFS_MOUNT
#define VFS_UMOUNT
#define VFS_SYNC
                                   1
 #define VFS_INACT
                                                                           /*@PPA*/
#define VFS_STATFS
#define VFS_VGET
#define VFS_RECOVERY
#define VFS_BATSEL
 #define VFS_GETHOST
                                  10
#define VFS_SOCKET
#define VFS_NETWORK
#define VFS_PFSCTL
#define MAX_VFSOPS
                                  11
                                  12
                                  13
 typedef void VFS_OP();
                                               /* Generalized VFS Op
 #pragma linkage(VFS_OP, OS)
                                               /* Is called with OS lnkg */
struct vfsotab {
                                              /* The VFS Op Table
                                                                                  */
            CBHDR vfso_hdr;
           VFS_OP * _PTR32 vfso_op[MAX_VFSOPS];
                                                                         /* @E5C*/
3;
```

```
#define VFSO_ID "VFSO"
#define VFSO_HDR {{VFSO_ID}, sizeof(struct vfsotab)}
      /*-----*/
      /\star Dump Information - used by the PFS to add LFS address space \star/
      /* and data space areas to the dumps that are taken by the PFS.*/
         struct pfsi_dumpent { /* Individual Dump Area Entry: */
            char pfsi_dumpstoken[8]; /* Stoken of the space int pfsi_dumpalet; /* Reserved int pfsi_dumpflag; /* Reserved
                                                                             @P8C*/
            char * _PTR32 pfsi_dumpstart;/* Starting address char * _PTR32 pfsi_dumpend; /* Ending address
                                                                             @E5C*/
                                      /* Area pointed to by pfsi_dumpptr */
       struct dmpinf {
                                       /* Number of Dump Area Entries
/* EBCDIC ID - FDUM @P8
                  pfsi_dumpents;
pfsi_dumpid[4];
         int
                                                                             @P8A*/
         char
                                      /* Reserved
                   pfsi_rsvd7[8];
                  pfsi_dumpent /* Array of Dump Areas, actual */
pfsi_dumpdata[16]; /* number of entries is in */
/* pfsi_dumpents. */
         struct pfsi_dumpent
      };
/* PFSNAME - Name of the PFS from TYPE operand of FILESYSTYPE.
/* This string is blank padded and not null terminated.
/*-----
 typedef struct s_pfsname {
                                            /★ PFS Type or Name
            char pfsname[8];
                                                                                 */
   } PFSNAME ;
/* pfctl buffer header for reason code text
 typedef struct pfsctl_et_hdr {
             short et_rqst;  /* type of text requested pfstcl_et_xx */
             short rsvd;
             char et_reasoncd[4];
   };
/* pfctl buffer header for PC_MODIFYPFS
typedef struct s_pc_modify {
    char    pc_modeye[4];
    short    pc_modlen;
    short    pc modvers:
                                        /*+00 EBCDIC ID - "MODP"
                                       /*+04 Length of pc_modify struct */
             pc_modvers; /*+06 Version number */
pc_modconsid; /*+08 Console id */
pc_modcart[8]; /*+0C Command And Response Token */
pc_modstringlen; /*+14 length of modify string */
pc_modstring[120]: /*+18 modify string */
       short
       int
      char
       int
       char
                 pc_modstring[120]; /*+18 modify string
   } PC_MODIFY;
      #define PC_MOD_ID
                                   "MODP"
                                                                         /* @ELA*/
       #define PC_MOD_V1
                                                                         /* @ELA*/
/*-----
/* pfctl buffer header for PC_THREADUNDUB
/* PC_UNDUB_TYPE_EOM data
 typedef struct s_pc_undubeomt {
   struct osirtoken pc_undubrtok; /* Orig op recovery token #if !defined(_PFS64) || !defined(_LP64)/* 31 bit PFS char pc_undubres1[8]; /* pad to 64bit osirtoken size
                                      /* pad to 64bit osirtoken size
   #endif
   char pc_undubpfstok[8];  /* pfs token (ts_mount)
} PC_UNDUBEOMT;
                                                                           /*@ERA*/
 typedef struct s_pc_undub {
              pc_undubeye[4];
                                        /*+00 EBCDIC ID - "UNDB"
      char
                                         /*+04 Length of pc_modify struct
       short
                 pc_undublen;
                                        /*+06 Version number
       short
                 pc_undubvers;
       short
                 pc_undubtype;
                                         /*+08 Undub type
                                        /*+0A ASID of undub thread
       short
                 pc_undubasid;
                 pc_undubtcb;
                                         /*+0C TCB address of undub thread */
       int
                                         /*+10 Type-specific data
       union {
         PC_UNDUBEOMT pc_undubeomt;
      } pc_typedata;
```

```
} PC_UNDUB;
                                                             /* @ERA*/
     #define PC_UNDUB_ID
#define PC_UNDUB_V1
                                  "UNDB"
                                                             /* @ERA*/
                                                             /* @ERA*/
     #define PC_UNDUB_TYPE_EOM
                                       /∗ EOM Timeout
                                                                @ERA*/
#define pfsctl_et_desc 0
#define pfsctl_et_action 1
#define pfsctl_et_modname 2
#define pfsctl errortext 0xc000000b /* pfsctl cmd for error text */
#define PC_SHUTTINGDOWNFS 0xC0000015 /* pfsctl for shutdown
                                                                @E4A*/
#define PC_TYPEFILESYS #define PC_TYPEFILEOWNER
                          1
                                      /* shutdown=filesys
                                                                @E4A*/
                          2
                                      /* shutdown=fileowner
                                                                @E4A*/
#define PC_TYPEOMVS
                                      /* omvs shutdown
                                                                @E4A*/
#define PC_RECYCLEDONE
                           0xC0000016 /* pfsctl to notify PFS that
                                        recycle is complete
                                                                @EAA*/
                          #define PC_ISSRCADDR
#define PC_OWNEROK
                                                                @EIA*/
                                        to become owner
                                                                @PUA*/
#define PC_MODIFYPFS
                           0xC000001D /* pfsctl for F OMVS,PFS= @ELA*/
@ERA*/
                                                                @ETA*/
                                                              @EUA*/
                                         parms
                           0x80000027 /* pfsctl to start migration
#define PC MIGSTART
                                                              @EXC*/
#define PC MIGSTOP
                           0x80000028 /* pfsctl to stop migration
                                                              @EXC*/
/* File Exporter Exit Interfaces
                                                                    */
/***********************************
/* Exit Parameter Structure
                                                          (BPXZGXPL)*/
                                                                   --*/
typedef struct s_gxpl {
            gx_id[4];
                                 /*+00 EBCDIC ID
     char
                                  /*+04 Gxpl Version number
     short
              gx_ver;
            gx_len;
                                 /*+06 Length of Gxpl structure
     short
     short
                                  /*+08 Operation Code
              gx_op;
                                 /*+0A Flags:
                                                                    */
                                  .
/*
              gx_postop :1;
     BIT
                                          1=PostOp Call
                                          O=Read mode, 1=Write mode */
     BIT
              gx_readwrite :1;
     BIT
              gx_eom :1;
                                  /*
                                     1=Carred _..
1=File Size Change
v_export catchup open @E9A*/
Suppress Dump @E9A*/
                                         1=Called from user EOM */
                                  /*
     BIT
              gx_trunc
                            :1;
     BIT
              gx_expopen
                           :1;
                                  /*
     BIT
              gx_nodump
                            :1;
     BTT
                           :10;
     OSI * _PTR32 gx_osi;
                                  /*+0C OSI address
                                                                @E5C*/
     int
              gx_volhdl[4];
                                  /*+10 VolHdl from v_export
              gx_anchor[2];
gx_state[2];
                                  /*+20 Exit Anchor
     int
                                                                    */
                                 /*+28 Exit State Area
                                                                    */
     int
                                  /* File Identifiers:
/*+30 The principal target
              gx_fid1;
     FID
                                                                    */
                                 /*+38 The secondary target
/*+40 for rename, the to-dir
/*+48 for rename, the to-file
              gx_fid2;
gx_fid3;
     FID
     FID
              gx_fid4;
     FID
                                                                    */
                                  /*+50 Op Return Value to PostOp
     int
              gx_opretval;
              gx_retcode;
                                 /*+54 Exit Return Code
     int
     union {
                                                              /*@E9A*/
                                  /*+58 Exit Reason Code
               gxU1_rsncode;
                                                                @F9C*/
       int
                                  /*+58 or Recovery SDWA/0
                                                                @E9A*/
       void *gxU1_rcvysdwa;
     } gxU1;
char * _PTR32 gx_optparm;
                                                              /*@E9A*/
                                 /*+5C Optional Parameter
                                                                @E5C*/
              gx_lfs[8];
     char
                                  /*+60 Reserved for the LFS
     char
                 rsvd1[8];
                                  /*+68 Reserved for expansion
 } GXPL ;
   #define GXPL_ID
#define GXPL_VERSION
                           "GXPL"
                          1
   #define gx_rsncode gxU1.gxU1_rsncode /* Exit Reason Code @E9A*/
```

```
#define gx_rcvysdwa gxU1.gxU1_rcvysdwa /* Rcvy SDWA or 0 @E9A*/
    /* Constants for gx_op
    /*
#define GXPL_INIT 0x1001 /* Initialization Call */
#define GXPL_EXPCMD 0x1002 /* Exporter Command */
#define GXPL_RECOVERY 0x1003 /* Recovery Call */
#define GXPL_UNMOUNT 0x1004 /* Unmount 1 @DBA*/
#define GXPL_UNEXPORT 0x1005 /* Unexport Call @DBA*/
#define GXPL_UNEXPORT 0x1005 /* Exporter has terminated */
     #define GXPL_EXPTERM 0x1006
#define GXPL_TERM 0x1007
#define GXPL_MTPTCHG 0x1008
                                                  /* Exporter has terminated */
                                                    /* Termination Call
                                  0x1008
                                                  /* Mount Point Change
     /* The Vnode operation values are the same as the pfsi_vnop
      | constants listed above, i.e. VN_OPEN, VN_RDWR, etc.
     /* Byte Range Lock Parameters
     struct gxlk {
           ct gxlk }
  int  gxl_version;
  int  gxl_lckcmd;
  int  gxl_lcktype;
  int  gxl_brbh;
  int  gxl_brbl;
  int  gxl_breh;
  int  gxl_brel;
  int  gxl_blkpid;
  int  rsvd[2]
                                           /* gxlk version number
/* Lock Cmd: F_SETLK, etc.
/* Lock Type: F_RDLCK, etc.
/* Range Beginning, high word
/* Range Beginning, low word
/* Range End, high word
/* Range End, low word
/* Blocking PID
                   rsvd[2];
           int
      };
         /* gxl_lckcmd and gxl_lcktype values are defined in fcntl.h. */
         #define GXL_VER0
                                                    /* First gxlk version
         #define GXL_EOFH 0x7FFFFFF
#define GXL_EOFL 0xFFFFFFF
                                                    /* End-Of-File High word
                                                                       Low word
         /*@05A*/
         #define GXPL_MTPT_UNMOUNT 0 /* Mount Point Unmounted @05A*/
         #define GXPL_MTPT_MOUNT 1 /* Mounting on Mt Pt @05A*/
#define GXPL_REMOUNT_RO 3 /* File Sys ReMount(RO) @05A*/
#define GXPL_REMOUNT_RW 4 /* File Sys ReMount(RW) @05A*/
 /* Exit Routine Prototype - as called by the LFS
  #pragma linkage(gx_exitrtn, OS)
  void gx_exitrtn (GXPL *);
#pragma page()
/**********************************
/* Operating System Interface (OSI) Services
/* Macros used to invoke the OSI services
      The OSIT table address must be saved during initialization and made available at the time of an OSI service call.
      Refer to the prolog for details on using this macro.
                        ------
  #ifndef _OSIT_PTR
                                              /* Establish the default osi_ptr */
      #define _OSIT_PTR osit_ptr
  #endif
/* OSI Service Names
   The OSI services are called with these names and the macros
/*
        use the OSIT table to find the associated routine.
                                                                                           */
    For example: osi_wait(OSI_SETUP, osiaddr, &rc);
  #define osi_getvnode _OSICALL(GETVNODE)
  #define osi_mountstatus _OSICALL(MOUNTSTATUS)
#define osi_ctl __OSICALL(CTL)
#define osi_selpost __OSICALL(SELPOST)
#define osi_wait __OSICALL(WAIT)
                                                                                  /*@D4A*/
                                                                                  /*@DAA*/
```

```
#define osi_post
#define osi_signal
#define osi_signal
#define osi_sleep
#define osi_wakeup
#define osi_kmsgget
#define osi_kmsgget
#define osi_kmsgsnd
#define osi_kmsgsrd
#define osi_kmsgctv
#define osi_kmsgctl
#define osi_kmsgctl
#define osi_kipcget
#define osi_uiomove
#define osi_copyin
#define osi_copyout
#define osi_copyout
#define osi_copyout
#define osi_si_mead
#define osi_getcred
#define osi_getcred
#define osi_si_getcred
#define osi_si_kfs
#define osi_sched
#define osi_sched
#define osi_sched
#define osi_sched
#define osi_ctrace
#define osi_ctrace
#define osi_copy64
#define osi_buffcache
                                                                                               /*@D6A*/
                                                                                               /*@D6A*/
                                                                                               /*@D6A*/
                                                                                                /*@D6A*/
                                                                                               /*@D6A*/
                                                                                               /*@D6A*/
                                                                                               /*@DDA*/
                                                                                                  @D7A*/
                                                                                                  @D7A*/
                                                                                                @D7A*/
                                                                                                  @D7A*/
                                                                                                  @P6A*/
                                                                                               /*@DGA*/
                                                                                               /*@DGA*/
                                                                                               /*@DJA*/
                                                                                               /*@DTA*/
                                                                                               /*@DKA*/
                                                                                               /*@PMA*/
   #define osi buffcache OSICALL(BUFFCACHE)
                                                                                               /*@E5A*/
      /* Internal Macro used to invoke the OSI_ service from the OSIT */
  #ifndef _OSICALL #define _OSICALL(op) ((_OSIT_PTR) -> osit_ ## op)
                  -----
/* OTHDPRM - Parameter structure input to osi_thread (BPXZTPRM)*/
/*-----*/
typedef struct s_othdprm {
                CBHDR ot_hdr; /*+00 Id & Length
char ot_modname[64]; /*+08 Name of module to fetch
                BIT ot_sigwait :1; /* Signal enabled wait */
BIT ot_nowait :1; /* no wait */
BIT ot_releasemods:1; /* release modules when done */
BIT ot_rsvrd1:29; /* reserved */
char ot_rsrvd2[8]; /*+90 reserved @DDC*/
PM · ODDC*/
                                                                                    @DDC*/
    } OTHDPRM ;
                                                                                             /* @D7A*/
         #define OTHDPRM_ID "TPRM"
         #define OTHDPRM_HDR {{OTHDPRM_ID}, sizeof(OTHDPRM)}
          /* OTHDCRCV - osi_thread called routine recovery block
/* This is the second parameter passed to the routine specified /* in ot_modname and the "PARAM" for the ESTAEX routine.
 typedef struct s_othdcrcv {
                void * _PTR32 otr_rcvyrtn; /*+00 Pointer to called module's
                                                               recovery routine @E5C*/
                void * _PTR32 otr_parms; /*+04 Pointer to parms to pass
                                                           to called module's
                                                                recovery routine
             BPXL32 reserved1; /*+08 Reserved @E5
BPXL32 reserved2; /*+0C Reserved @E5
char work_area[496]; /*+10 Work area for ESTAEX rtn
                                                                                                  @E5C*/
                                                                                                 @E5C*/
    } OTHDCRCV ;
                                                                      /* @DMA*/
/* OGCDPRM - Parameter structure input to osi_getcred (BPXZCPRM)*/
 typedef struct s_ogcdprm {
                CBHDR oc_hdr; /*+00 Id & Length
int oc_real_uid; /*+08 Real uid
int oc_effective_uid; /*+08 Effective uid
int oc_saved_uid; /*+10 Saved uid
int oc_real_gid; /*+14 Real gid
                                                                                                       */
                         oc_effective_gid; /*+18 Effective gid
oc_saved_gid; /*+1C Saved gid
oc_maxsgids; /*+20 Maximum number of
                int
                int
                int
                                                                supplementary gids there is room for.
                                                                Set to actual number
                                                                if not room for all I/O */
                                                    /*+24 Number of supplementary
                int 
                         oc_numsgids;
                                                                gids returned 0 */
```

```
int * _PTR32 oc_gid_list; /*+28 Pointer to array of
                                supplementary gids I @E5C*/
  } OGCDPRM ;
                                             /*@EOC @P6A*/
     #define OGCDPRM_ID
                     "CPRM"
     #define OGCDPRM_HDR {{OGCDPRM_ID}, sizeof(OGCDPRM)}
/* Time Interval - Input to osi_sleep and osi_wait @P8A*/
/* Double word S/390 timer units, or (time[\bar{0}]*1.04) sec. approx. */
/*-----*/
  struct time_int {
                BPXUL32 time[2];
                                                /*@E5C*/
/* Share Reservation Support
     /★ Open Type constants for vn_open
                                                 @F6A*/
#define VNOPEN_FILE 0 /* For open() or v_open() @E6A*/#define VNOPEN_INTERNAL 99 /* For LFS Internal Open @E6A*/
#define VNSHRCHK_NONE 0 /* No Checking WSHRCHK_ADV 1 /* Advisory Check, V4 only @E6A*/
#define VNSHRCHK_MAND 3 /* Mandatory Check, all @E6A*/
/*-----*/
/* Passed to osi_LkFs service.
                                                  @DJA*/
@PMA*/
   };
     #define C64_OUT 0
     #define C64_IN 1
/* osi_buffcache parameter
      char osi_bchs_name[4]; /* Eyecatcher ("BCHS") */
int osi_bchs_length; /* Length of this structure -
   struct osi_bfche_struct {
      int osi_bchs_rc; /* Return code */
```

```
osi_bchs_rs;
                                                /* Reason code
                       osi_bchs_sttok[8]; /* Storage token **
osi_bchs_rsvd1[24];/* Reserved for future use *
osi_bchs_fcnspecific[1]; /* Remainder depends on the
           char
           char
                                                        service selected by bchs_fcn */
     };
    #define OSI_BCHS_ID "BCHS" /* Acronym for bfche_struct @E5A*/
/* osi_upd_filesys structure
     struct osi_upd_filesys {
   char osi_upd_name[4]; /* Eyecatcher ("UPDA")
   int osi_upd_devno; /* mt_devno from vfs_mount
   short osi_upd_type; /* osi_regstatus, osi_excpst
                                                  /* osi_regstatus, osi_excpstatus,
                                                      or osi_mountparm entry types */
           short osi_upd_textlen; /* text length or 0 to remove char osi_upd_textstring[512]; /* text string
    #define OSI UPD ID "UPDA"
/* osi_quiesce_struct structure
     struct osi_quiesce_struct {
   char osi_quiesce_name[4]; /* Eyecatcher ("OSIQ")
           unsigned int osi_quiesce_version; /* version
           unsigned int osi_quiesce_devno; /* mt_devno */
unsigned int osi_quiesce_pid; /* pid of quiesce caller */
BIT osi_quiesce_noops :1;
                       osi_quiesce_backup :1;
           BIT
           BIT
                       osi_quiesce_clone :1;
           BIT
                       osi_quiesce_delete :1;
           BIT
                      osi_quiesce_checkonly :1; /* check handle only
                                                                  during unquiesce @EJA*/
           BTT
           char osi_quiesce_rsvd1[3];
           unsigned int osi_quiesce_handle; /* quiesce instance id
                    osi_quiesce_jobname[8];
osi_quiesce_sysname[8];
           char
           char
           int
                      osi_quiesce_pfsid;
                                                             /* pfsi_pfsid
                     osi_quiesce_rsvd2[12];
           char
     };
    #define OSI_QUIESCE_ID "OSIQ"
    #define OSI_QUIESCEV1 1 /* version 1 for osi_quiesce_version @EFA*/
/* osi_getmntstat structure
struct osi_getmntstat {
    char osi_getmntstat_name[4]; /* Eyecatcher ("GTMT") */
    unsigned int osi_getmntstat_version; /* version */
    unsigned int osi_getmntstat_devno; /* mt_devno */

#if defined(__PFS64) && defined(_LP64) /* --64 bit PFS-- 5@EOA*/
    char osi_getmntstat_lfs64rsvd[4];/* LFS internal use*/
    unsigned int osi_getmntstat_bufferlen; /* in/out buffer len*/
    char osi_getmntstat_rsvd1[4];

    char * osi_getmntstat_bufferaddr: /* 6/B buf for meto-*/
     struct osi_getmntstat {
      char OSI_getmntstat_bufferaddr;
char * osi_getmntstat_bufferaddr;
                                                                       /* 64B buf for mnte */
                                                         /* --31 bit PFS-- @EOA*/
      char * _PTR32 osi_getmntstat_bufferaddr; /* 31B buf for mnte */
unsigned int osi_getmntstat_bufferlen; /* in/out buffer len*/
      char
                              osi_getmntstat_rsvd[12];
 #endif
                                                                                           /*@EOA*/
     };
                                                                                          /* @EFA*/
   #define OSI_GETMNTSTAT_ID "GTMT"
                                 /* eyecatcher for osi_getmntstat_name
    #define OSI_GETMNTSTATV1 1
                                 /* version 1 for osi_getmntstat_version @EFA*/
/* osi_remnt structure
                                  -----
     struct osi_remnt {
      char osi_remnt_name[4]; /* Eyecatcher ("RMNT")
unsigned int osi_remnt_version; /* version
unsigned int osi_remnt_devno; /* mt_devno
      unsigned int osi_remnt_pfsid; /* pfsi_pfsid
```

```
char
                   osi_remnt_rsvd[16];
   };
                                                            /* @EFA*/
  #define OSI REMNT ID "RMNT"
                      /* eyecatcher for osi_remnt_name
                                                               @EFA*/
  #define OSI_REMNTV1 1
                      /* version 1 for osi_remnt_version
                                                               @EFA*/
/* osi_pfsstatusinfo structure
/* If there is no status information, set the first character of
                                                                   */
/* each_status line (osi_pfsstatus_line1, ..._line2 or ..line3)
                                                                   */
/* to blank.
   struct osi_pfsstatusinfo {
    char osi_pfsstatus_name[4];
                                        /* Version
/* Lension
                                           /* Eyecatcher ('PFST')
    unsigned int osi_pfsstatus_version;
unsigned int osi_pfsstatus_length;
                                                                  */
    unsigned int osi_pfsstatus_pfsi_pfsid; /* Pfs identifier
    char osi_pfsstatus_line1[60];
char osi_pfsstatus_line2[60];
    char osi_pfsstatus_line3[60];
                                                        /* @PTC@EHA*/
 #define OSI_PFSSTATUS_ID "PFST"
                                                        /* @PTC@EHA*/
  #define OSI_PFSSTATUSV1 1
                                                        /* @PTC@EHA*/
.
/* OSI Services Prototypes
                                    typedef void OSI_GETVNODE(int ent,
                          TOKSTR *,
                            ATTR *,
                            GTOK *,
                       0_VNTOK *, /* Object's vnode token
int *retval, int *retcode, int *rsncode);
                                       /* Object's vnode token
@D4A*/
                                                               @D5C*/
                                        /* Entry Code
typedef void OSI_WAIT(int ent,
                         OSI *,
                                        /* Caller's (waiter's) OSI */
                       int *rc,
                                        /* waitx parms:
                                              int wait_flags
struct time_int *
typedef void OSI_POST(WPTOK *,
                                        /* osi_token of waiter
                       int *rc);
typedef void OSI_SIGNAL(OSI *
                                        /* Caller's OSI
                    int pid,
                                       /* Target's osi_pid value
                                        /* Signal to issue
                    int sigval,
                    int sigopt,
                                        /* Signal options
                   int *retval, int *retcode, int *rsncode);
/* Vn_select's select token*/
typedef void OSI_SLEEP(OSI *,
                                                               @D6A*/
                                        /* Caller's OSI
                      long resid,
                                       /* Resource id
                                                               @EPC*/
               @P8C*/
typedef void OSI_WAKEUP(long resid,
                                                           @EPC@D6A*/
                                        /* Resource id
                                        /* Pfs id
                        int pfsid,
                      int *retval, int *retcode, int *rsncode);
                                      /* Message Q Id
/* Flag field
typedef void OSI_KMSGGET(int msgqkey,
                                                          @D6A @D7C*/
                         int msgflag,
                      int *retval, int *retcode, int *rsncode);
typedef void OSI_KMSGSND(int msgqkey,
                                        /* Message Q Id @D6A @D7C*/
                        void *msgaddr,
                                        /* Message address
                                        /* Message alet
                         int msgalet,
                         int msgsize,
                                        /* Message size
                      int msgflag, /* Flag field
int *retval, int *retcode, int *rsncode);
typedef void OSI_KMSGRCV(int msgqkey,
                                        /* Message Q Id @D6A @D7C*/
                       void *msgaddr, /* Message address */
```

```
int msgalet,
                                         /* Message alet
                                         /* Message size
                          int msgsize,
                         long msgtype,
int msgflag,
                                        /* Message type
/* Flag field
                       int *retval, int *retcode, int *rsncode);
typedef void OSI_KMSGCTL(int msgqkey,
                                          /* Message Q Id
                          int msgcmd,
                                         /* Message command
                                        /* Message bufffer
                         void *msgbuff,
                       int *retval, int *retcode, int *rsncode);
typedef void OSI KIPCGET(int ipctoken,
                                         /* IPC token
                         void *ipcbuff, /* Output bufffer
                          int bufflen, /* IPC buffer length
                                          /* IPC command
                          int ipccmd,
                       int *retval, int *retcode, int *rsncode);
typedef void OSI_UIOMOVE(OSI *,
                                          /* OSI struct
                                                                  @D7A*/
                          char *uiomworkarea, /* work area for use by
                                                 uiomove
                                                                  @D7A*/
                                         /* Pfs buffer
                          char *pfsbuf
                                                                  @D7A*/
                          int pfsbufalet,/* Alet for the PFS buf@D7A*/
                          int movelen, /* number of bytes to move */
                          UIO *,
                                         /* Uio structure
                          int *retval, int *retcode, int *rsncode);
                                         /* destination buffer @D6A*/
typedef void OSI_COPYIN(char *desbuf,
                         int desbufalet, /* destination buffer alet */
char *srcbuf, /* source buffer */
                         int srcbufalet, /* source buffer alet
                                      /* source storage key
/* length to move
                         int srckev.
                         int movelen,
                         int *retval, int *retcode, int *rsncode);
typedef void OSI_COPYOUT(char *desbuf, /* destination buffer @D6A*/
                          int desbufalet,/* destination buffer alet */
                          char *srcbuf, /* source buffer
                          int srcbufalet,/\star source buffer alet
                          int deskey,   /* destination storage key */
int movelen,   /* length to move   */
                          int movelen,
                          int *retval, int *retcode, int *rsncode);
typedef void OSI_THREAD(OSI *,
                                         /* OSI
                                         /* Osit_Thread parm struct */
                         OTHDPRM *,
                         int *retval, int *retcode, int *rsncode);
                                         /* OSI
typedef void OSI_GETCRED(OSI *,
                                                                  @P6A*/
                          char *workarea, /* 3K work area for
                                         use by getcred */
/* alet for getcred parm and
                                alet,
                                             supplementary gid list */
                          OGCDPRM *,
                                          /* Osit_Getcred parm struct*/
                          int *retval, int *retcode, int *rsncode);
typedef void OSI CTL
                        (int cmd,
                                          /* Command Code
                                                                  @DAA*/
                                       /* Argument Length
                         int arglen,
                                                                      */
                         char *arg,
                                          /* Argument Length
                         int *retval, int *retcode, int *rsncode);
typedef void OSI_UPDA (GTOK *lfs_asytok, /* LFS's Token GTOK *pfs_asytok ); /* PFS's Token
                                                                   @DGA*/
typedef void OSI_SCHED (GTOK *lfs_asytok,
                                              /* LFS's Token
                                                                   @DGA*/
                         int *retval, int *retcode, int *rsncode);
typedef void OSI_CTRACE(char *pfs_name, /* name of the PFS
                                                                  @DIA*/
                         char *workarea, /* 3K work area for
                                              use by osi_ctrace
                         int arglen,
                                         /* Argument Length
                                                                      */
                                          /* Argument Length
                         char *arg,
                         int *retval, int *retcode, int *rsncode);
typedef void OSI_SOCKET(char *function, /* socket function
                                         /* args for equiv BPX1xxx */
                         ...);
typedef void OSI_LKFS (OSILPARM *,
                                                 /* LkFs parm
                                                                   @PDC*/
                         int *retval, int *retcode, int *rsncode);
```

```
typedef void OSI_BUFFCACHE(OSI *, /* Caller's OSI
                                              struct osi_bfche_struct *); /* Buffer
                                                                   cache management structure */
   /\star OS linkage pragmas for the Services \# pragma \ linkage (OSI_GETVNODE,OS)
  #pragma linkage(OSI_GETVNODE,OS)
#pragma linkage(OSI_MOUNTSTATUS,OS)
#pragma linkage(OSI_CTL,OS)
#pragma linkage(OSI_SELPOST,OS)
#pragma linkage(OSI_WAIT,OS)
#pragma linkage(OSI_POST,OS)
#pragma linkage(OSI_SIGNAL,OS)
#pragma linkage(OSI_SLEEP,OS)
#pragma linkage(OSI_WAKEUP,OS)
#pragma linkage(OSI_KMSGGET,OS)
#pragma linkage(OSI_KMSGGSND,OS)
#pragma linkage(OSI_KMSGRCV,OS)
                                                                                                       /*@D4A*/
                                                                                                       /*@DAA*/
                                                                                                       /*@D6A*/
                                                                                                       /*@D6A*/
                                                                                                       /*@D6A*/
  #pragma linkage(OSI_KMSGSND,OS)
#pragma linkage(OSI_KMSGRCV,OS)
#pragma linkage(OSI_KMSGCTL,OS)
#pragma linkage(OSI_KIPCGET,OS)
#pragma linkage(OSI_UIOMOVE,OS)
#pragma linkage(OSI_COPYOUT,OS)
#pragma linkage(OSI_COPYOUT,OS)
#pragma linkage(OSI_THREAD,OS)
#pragma linkage(OSI_GETCRED,OS)
#pragma linkage(OSI_SCHED,OS)
#pragma linkage(OSI_SCHED,OS)
#pragma linkage(OSI_SCKET,OS)
#pragma linkage(OSI_SOCKET,OS)
#pragma linkage(OSI_SOCKET,OS)
#pragma linkage(OSI_COPY64,OS)
                                                                                                       /*@D6A*/
                                                                                                       /*@D6A*/
                                                                                                       /*@D6A*/
                                                                                                       /*@DDA*/
                                                                                                      /*@D6A*/
                                                                                                          @D7A*/
                                                                                                       @D7A*/
                                                                                                         @D7A*/
                                                                                                          @P6A*/
                                                                                                       /*@DGA*/
                                                                                                       /*@DGA*/
                                                                                                       /*@DIA*/
                                                                                                       /*@DJA*/
                                                                                                       /*@DKA*/
   #pragma linkage(OSI_COPY64,OS)
                                                                                                       /*@PMA*/
   #pragma linkage(OSI_BUFFCACHE,OS)
           *-----*/
} OSIT;
/*------*/
/* Done packing structures for 64-bit compiles 3@E5A*/
/*------*/
#ifdef _LP64
 #pragma pack(reset)
```

```
#endif
                                                     */
/* Rel 1 and Rel 2 Base */
/* Rel 2 with copyin,copyout,ctl */
/* Rel 3 sleep,wkup,kmsg,uiom,thrd */
         /* Version numbers
        /* Version numbers
#define OSIT_VER1 1
#define OSIT_VER2 2
#define OSIT_VER3 3
#define OSIT_VER4 4
#define OSIT_VER5 5
#define OSIT_VER6 6
                                                     /* Rel 4 lkfs
/* Ver 5 copy64
/* Ver 6 sysplex zfs
                                                                                                             @PMA*/
/* Constants used with the Service calls
  @D4C*/
   /* Input Entry Codes for osi_wait
  /* Input Entry Codes for OSI_Walt
#define OSI_SETUP 1 /* Setup request */
#define OSI_SETUPSIG 4 /* Setup with signals */
#define OSI_SUSPEND 2 /* Wait request */
#define OSI_WAITX 5 /* Wait ext request with Latch
and Timer control @D6A*/
#define OSI_INIT 6 /* Init OSI for a Task @DGA*/
#define OSI_INIT2 7 /* Init OSI with Length @PFA
osi hdr.cblen=sizeof(OSI) @PFA*/
                                                               osi_hdr.cblen=sizeof(OSI) @PFA*/
  /* Output Return Codes from osi_wait
                                                                    enabled
                                                                                                            @D6A*/
    /* Input Entry Codes for osi_ctl
  /* Input Entry Codes for osi_ctl
#define OSI_GLUECALL 1 /* Glue request @EAA*/
#define OSI_RECYCLESTART 2 /* PFS starting recycle @EAA*/
#define OSI_RECYCLEFINISHED 3 /* PFS recycle is complete @EAA*/
#define OSI_UPDATEFILESYS 4 /* file system update @EAA*/
#define OSI_REMOUNTSAMEMODE 5 /* remount in same mode @EFA*/
#define OSI_QSE 6 /* quiesce @EFA*/
#define OSI_UQS 7 /* unquiesce @EFA*/
#define OSI_GETMNTSTATUS 8 /* get mount status @EFA*/
#define OSI_DUB 9 /* dub or undub a task @EFA*/
#define OSI_PFSSTATUS 10 /* PFS report status @EHA*/
   #define OSI_VOS 7
#define OSI_UQS 7
#define OSI_GETMNTSTATUS 8
#define OSI_DUB 9
#define OSI_PFSSTATUS 10
   /* dub task
/* undub task
                                                                                                             @EFA*/
                                                                                                            @EFA*/
   @EAA*/
                                                                                                             @EAA*/
   /* Output Return Codes from osi_post (in addition to above) @DDA*/#define OSI_NOTWAITING 4 /* Waiter has gone @DDA*/
   signals enabled
                                           0x40000000 /* Don't wait caller's task */
   #define OSI_NOWAIT
```

```
#define OSI_RELEASEMODS 0x20000000 /* Release modules when done
  /* Flag values for wait_flags on osi_wait(waitx) calls @P8A*/#define OSI_WTDROPLOCKS 0x00000001 /* Drop Locks over wait @P8A*/
/\star Information used for loading the OSIT into a separate addr space \star/
  #define OSIT_INIT "BPXVOSIT"
                                          /* The module to load & call
  typedef void OSIT_INITMOD (
                                           /* Prototype for the call:
                                          /* Output is a ptr to an OSIT */
                                OSIT **,
                                int *retcode, int *rsncode);
MOD,OS) /* Called with OS linkgage
  #pragma linkage(OSIT_INITMOD,OS)
/* Prototype of the PFS Initialization Routine
                                                                                 */
     This routine is attached as an MVS task and invoked by the
     system with the following parameters:
  void pfsinit (PFSI *, PFSNAME *, PFSPARM *, void *, OSIT *);
  #pragma linkage(pfsinit,OS)
                                             /* Is invoked with OS linkage */
/* Prototypes of the Vnode and VFS operation routines.
     These routines are called by the LFS to perform their functions*/
                    /* File and Directory oriented operations
  void vn open
                     (TOKSTR *, OSI *, CRED *,
                        int *open_flags,
                        int *retval, int *retcode, int *rsncode);
  void vn close
                     (TOKSTR *, OSI *, CRED *,
                         int *open_flags,
  int *retval, int *retcode, int *rsncode);
void vn_readdir (TOKSTR *, OSI *, CRED *,
                        UIO *,
                         int *retval, int *retcode, int *rsncode);
  void vn_readlink(TOKSTR *, OSI *, CRED *,
                        UIO *,
                        int *retval, int *retcode, int *rsncode);
  void vn_create
                     (TOKSTR *, OSI *, CRED *,
                        int *namelen, char *name, ATTR *, 0_VNTOK *,
int *retval, int *retcode, int *rsncode);
                     (TOKSTR *, OSI *, CRED *, int *namelen, char *name, ATTR *, O_VNTOK *,
  void vn_mkdir
                        int *retval, int *retcode, int *rsncode);
  void vn_symlink (TOKSTR *, OSI *, CRED *,
                        int *namelen, char *name,
                        int *symlen, char *symlink,
int *retval, int *retcode, int *rsncode);
  void vn_lookup
                     (TOKSTR *, OSI *, CRED *,
                        int *namelen, char *name, O_VNTOK *,
int *retval, int *retcode, int *rsncode);
  void vn_getattr (TOKSTR *, OSI *, CRED *,
                        ATTR *
                        int *retval, int *retcode, int *rsncode);
  void vn_setattr (TOKSTR *, OSI *, CRED *,
                        ATTR *
                        int *retval, int *retcode, int *rsncode);
                     (TOKSTR *, OSI *, CRED *,
  void vn_access
                        int *access_intent,
                     int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
  void vn_trunc
                         int *offset,
                         int *retval, int *retcode, int *rsncode);
  void vn_fsync
                     (TOKSTR *, OSI *, CRED *
                     int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
int *retval, int *retcode, int *rsncode);
  void vn_link
                        int *namelen, char *name, TOKSTR *,
int *retval, int *retcode, int *rsncode);
  void vn_rmdir
                     (TOKSTR *, OSI *, CRED *,
                        int *namelen, char *name,
int *retval, int *retcode, int *rsncode);
                     (TOKSTR *, OSI *, CRED *,
  void vn_remove
                         int *namelen, char *name,
                     int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
  void vn_rename
                        int *oldlen, char *oldname,
                        int *newlen, char *newname, TOKSTR *;
                        int *retval, int *retcode, int *rsncode);
```

```
void vn_audit (TOKSTR *, OSI *, CRED *,
                       int *retval, int *retcode, int *rsncode);
                  /* File System oriented operations
                                                                                */
int *retval, int *retcode, int *rsncode);
void vfs_umount (TOKSTR *, OSI *, CRED *,
                       int *unmount_options,
                       int *retval, int *retcode, int *rsncode);
void vfs_statfs (TOKSTR *, OSI *, CRED *,
                       FSATTR *,
                   int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
void vfs_sync
                   int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
void vfs_inact
                   struct s_iab *, int *iablen,
int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
FID *, O_VNTOK *,
void vfs_vget
                       int *retval, int *retcode, int *rsncode);
                  /* General operations
  (TOKSTR *, OSI *, CRED *,
                                                                                */
void vn_select
                         SELTOK *,
                         int *sel_function,
int *sel_options,
                         char *pfsworkptr,
int *retval, int *retcode, int *rsncode);
void vfs_batsel
                      (TOKSTR *, OSI *, CRED *,
                         int *rsvd1,
                         int *sel_function,
                         BSIC *,
                         int *rsvd2,
                      int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
void vn rdwr
                         int *open_flags, UIO *,
int *retval, int *retcode, int *rsncode);
void vn_readwritev(TOKSTR *, OSI_*, CRED *,
int *retval, int *retcode, int *rsncode);
void vn_ioctl
                      (TOKSTR *, OSI *, CRED *,
                         int *open_flags,
                         int *cmd, int *arglen, char *arg,
int *retval, int *retcode, int *rsncode);
                                                                         /*@E7A*/
                      (TOKSTR *, OSI *, CRED *,
void vn_lockctl
                         int *cmd,
                         int *vlocklen, VLOCK *,
                     int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *, /*
                                                                         /*@D5A*/
void vn_pathconf
                         int *pathconf_option,
                     int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *, /*
                                                                         /*@D5A*/
void vn recoverv
                         struct osirtoken *,
int *retval, int *retcode, int *rsncode); void vfs_recovery (TOKSTR *, OSI *, CRED *,
                         struct osirtoken *,
                         int *retval, int *retcode, int *rsncode);
                      (TOKSTR *, OSI *, CRED *,
void vfs_pfsctl
                         int *cmd, UIO *
                          int *retval, int *retcode, int *rsncode);
                      (TOKSTR *, OSI *, CRED *,
                                                                         /*@DGA*/
void vn cancel
                         struct vncanflags *,
                         GTOK
                                *pfs_asytok,
                         GTOK
                                 *lfs_asytok,
                         int *retval, int *retcode, int *rsncode);
/* Socket Network (domain) oriented operations void vfs_network (TOKSTR *. OST * CPED *
                                                                               */
                         NETW *,
                          int *retval, int *retcode, int *rsncode);
                      (TOKSTR *, OSI *, CRED *, /* socket|socketpair*/
int *domain, int *type, int *protocol,
void vfs socket
                         int *dim, O_VNTOK (*vntoks)[2],
                         int *retval, int *retcode, int *rsncode);
                     (TOKSTR *, OSI *, CRED *, /* get host id|name */
  int *namelen, char *name,
  int *retval, int *retcode, int *rsncode);
void vfs_gethost
                  /* Socket oriented operations
                                                                                */
```

```
(TOKSTR *, OSI *, CRED *,
   int *addrlen, _SOCKADDR *,
   int *open_flags, O_VNTOK *,
   int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
   int *addrlen, _SOCKADDR *,
   int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
   int *addrlen _SOCKADDR *
  void vn_accept
  void vn_bind
  void vn_connect
                                int *addrlen, _SOCKADDR *,
                                int *open_flags,
                                int *retval, int *retcode, int *rsncode);
                            (TOKSTR *, OSI *, CRED *, /* peername|sockname*/
  void vn getname
                                int *function,
                            int *addrlen, _SOCKADDR *,
  int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
  void vn_listen
                                int *backlog,
int *retval, int *retcode, int *rsncode);
  void vn_sndrcv
                            (TOKSTR *, OSI *, CRED *,
                                int *open_flags, UIO *, int *sr_flags,
int *retval, int *retcode, int *rsncode);
  void vn_sndtorcvfm(TOKSTR *, OSI_*, CRED *,
                            int *open_flags, UIO *, int *sr_flags,
  int *addrlen, _SOCKADDR *,
  int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *,
  int *coop flags UIO *, int *cor flags
  void vn_srmsg
                                int *open_flags, UIO *, int *sr_flags,
int *retval, int *retcode, int *rsncode);
  void vn_shutdown
                            (TOKSTR *, OSI *, CRED *,
                                int *how,
                                int *retval, int *retcode, int *rsncode);
                            void vn_sockopt
  void vn_srx
                                int *open_flags, UIO *
                            int *retval, int *retcode, int *rsncode);
(TOKSTR *, OSI *, CRED *, /*
                                                                                       /*@PHA*/
  void vn_anr
                                struct anr_struct *, UIO *, int *open_flags, O_VNTOK *,
                                                            ÚΙΟ *,
                                                                                       /*@PIC*/
                                int *retval, int *retcode, int *rsncode);
#pragma page()
                        /* The PFS operations are invoked with OS linkage */
  #pragma linkage(vn_open
                                        ,OS)
  #pragma linkage(vn_close
                                         ,OS)
  #pragma linkage(vn_rdwr
  #pragma linkage(vn_readdir ,0S)
  #pragma linkage(vn_readlink,OS)
                                       ,OS)
  #pragma linkage(vn_create
                                        , OS)
  #pragma linkage(vn_mkdir
  #pragma linkage(vn_symlink ,0s)
#pragma linkage(vn_lookup ,0s)
  #pragma linkage(vn_inactive,OS)
  #pragma linkage(vn_getattr ,OS)
  #pragma linkage(vn_setattr ,0S)
  #pragma linkage(vn_access ,0S)
#pragma linkage(vn_trunc ,0S)
#pragma linkage(vn_fsync ,0S)
                                         , OS)
                                         , OS)
  #pragma linkage(vn_link
                                         , OS)
  #pragma linkage(vn_rmdir
                                         , OS)
  #pragma linkage(vn_remove
                                         , OS)
  #pragma linkage(vn_rename
                                         , OS)
  #pragma linkage(vn_audit
                                          05)
  #pragma linkage(vn_pathconf,OS)
                                                                                       /*@D5A*/
  #pragma linkage(vn_recovery,OS)
                                                                                        /*@D5A*/
  #pragma linkage(vn_cancel
#pragma linkage(vn_ioctl
#pragma linkage(vn_ioctl)
                                        , OS)
                                                                                       /*@DGA*/
                                         , OS)
  #pragma linkage(vn_lockctl ,0S)
                                                                                       /*@E7A*/
                                         , OS)
  #pragma linkage(vn_select
  #pragma linkage(vn_accept
  #pragma linkage(vn_bind ,0S)
#pragma linkage(vn_connect ,0S)
  #pragma linkage(vn_getname ,OS)
  #pragma linkage(vn_listen ,0S)
  #pragma linkage(vn_sndrcv
                                       , OS)
  #pragma linkage(vn_srmsg ,0S)
#pragma linkage(vn_shutdown,0S)
  #pragma linkage(vn_sockopt ,OS)
  #pragma linkage(vn_readwritev,OS)
```

```
#pragma linkage(vn_sndtorcvfm,OS)
  #pragma linkage(vn_srx
  #pragma linkage(vn_anr
                               ,05)
  #pragma linkage(vfs_mount
#pragma linkage(vfs_umount
                              ,OS)
  #pragma linkage(vfs_statfs ,OS)
  #pragma linkage(vfs_sync
#pragma linkage(vfs_inact
                              ,0S)
                              , OS)
                                                               /*@PPA*/
  #pragma linkage(vfs_vget
                               ,OS)
  #pragma linkage(vfs_recovery,OS)
  #pragma linkage(vfs_batsel ,0S)
  #pragma linkage(vfs_network ,0S)
#pragma linkage(vfs_socket ,0S)
  #pragma linkage(vfs_gethost ,0S)
 /* Ctrace utility
 /*----
struct ctrcvt {char x[0x8c];struct ctrcve * _PTR32 cve;}; /* @E5C*/
struct ctrcve {char x[0xf0];struct ctrcvt * _PTR32 ocvt;}; /* @E5C*/
struct ctrocvt {char x[0x130];unsigned int csptrace:1;};
                                                             /* 1@E5C*/
#define TRACEISON ((*(struct ctrcvt* _PTR32 * _PTR32)0x10) -> \
                     cve -> ocvt -> csptrace)
#pragma page()
 #ifndef _NO_PFS_KES
 /* Internal Services Prototypes
  void * _memmove (void *, const void *, size_t);
                                                            /* @D7A */
 /* Kernel Extension Services
/\star These functions are a subset of the OS/390 Language Environment
 /* C functions. LE functions are not available to PFSes and
 /* the functions included here may be called in their place.
/* Name:
           bcopy
/* Format: #include <string.h>
           #include <bpxypfsi.h>
/*
/*
           void bcopy( source, destination, length )
/* Description:
           Copies 'length' bytes from 'source' to 'destination'.
/*
           Overlapping source and destination are handled
/*
           correctly.
/* Returned Value:
           None
/* External References: _memmove
/* Synopsis:
/* void bcopy (const void *source, void *destination, size_t length)
/* Related Information:
        <bpxypfsi.h>
/*
           _memmove()
/*@DIA*/
void bcopy (const void *src, void *dst, size_t length)
                                                              /*@D7A*/
 * let _memmove do the work...
                                                              /*@D7A*/
      _memmove( dst, src, length );
#pragma page()
/* Name:
           bzero
```

```
/* Format: #include <string.h>
            #include <bpxypfsi.h>
/*
            void bcopy( destination, length )
/* Description:
            Zeroes out 'length' bytes, starting at 'destination'.
/* Returned Value:
            None
/* External References: memset
/* Synopsis:
/* void bzero (const void *destination, size_t length)
/* Related Information:
           <bpxypfsi.h>
            memset()
/*
/*@DIA*/
void bzero (void *dest, size_t length)
                                                                 /*@D7A*/
 * let memset do the work ...
                                                                /*@D7A*/
         memset( dest, 0, length );
3
 #pragma page()
 /* Internal Services
   Name: _memmove
/*
   Purpose: Copies characters from one data object to another
             with check for overlap
   Input: s1 - object to move the characters to
           s2 - object to move the characters from \boldsymbol{n} - the number of characters to move
/*
/*
    Output: Returns a pointer to object s1
    External References: None
/*
   Description:
/*
/*
    Copy n characters from object s2 to object s1.
    If overlay exists between s2 and s1, the move shall take place correctly. A pointer to the object s1 shall
/*
     be returned.
/*
static
                                                               /*@DIA*/
void *_memmove (register void *s1, register const void *s2,
                register size_t n) {
   register void *anchor = s1; /* save s1 to return
                                                                       */
   char
                  *p1;
    char
                  *p2;
    size_t
                   х;
    size_t
                   у;
  /st check for destructive overlap and if it exists, move the end st/
  /* of the string first.
  if ( ((char *)s1 > (char *)s2) && (((char *)s2 + n) > (char *)s1)) \{
      p2 = (char *)s2 + n - 1; /* point to last character to move */
p1 = (char *)s1 + n - 1; /* point to last position in result */
x = (char *)s2 + n - (char *)s1; /* # of bytes colliding */
       y = x;
       while (y-->0)
```

Appendix E. Assembler and C-language facilities for writing a PFS in C

This appendix contains assembler routines that can be useful for writing a PFS in C.

Replacements for the C/370 Systems Programming Facilities routines @@XGET and @@XFREE are included. **These routines must be included in your PFS.** They are supplied in the BPXFASM sample, included here, which must be assembled and link-edited with all PFS load modules.

C-function prototypes and assembler routines are also included for the following facilities:

BPXT4KGT

Allocate a page of storage

BPXT4KFR

Free a page of storage

BPXTWAIT

Wait on an ECB list

BPXTPOST

Post an ECB

BPXTEPOC

Convert time-of-day clock format to seconds-since-the-epoch

Assembler replacements for @@XGET and @@XFREE

```
TITLE 'BPXFASM: File System Assembler Utilities'
*/***START OF SPECIFICATIONS*************************
    $MOD(BPXFASM) COMP(SCPX1) PROD(BPX):
*01* MODULE-NAME: BPXFASM
*01* CSECT NAME: @@XGET and @@XFREE
*01* DESCRIPTIVE-NAME: HOTC Replaceable Get/Free Storage for C PFSs
BPXFASM CSECT
BPXFASM AMODE ANY BPXFASM RMODE ANY
BPXFASM MODID BR=NO
*************************
   CSECT-NAME: @@XGET
   DESCRIPTIVE-NAME: Allocate storage for C/370
   Input: RO - length of storage to obtain (high bit on for storage
             above the line).
         R14 - Return address
   Output: R0 - length of storage obtained R1 - address of memory obtained
   No save area is provided.
   R2 and R4 are used as work regs
   Regs and Access Regs 0, 1, 14, 15 may be modified.
*************************
@@XGET CSECT
@@XGET AMODE
       AMODE ANY
@@XGET
       RMODE ANY
       ENTRY @@XGET
```

```
R2,R0
                                   Save Input Length
         LR
               R4,R14
                                   Save Return Addr
         EPAR
               R15
                                   Extract Primary ASID
         LOCASCB ASID=(R15)
                                  Locate the Primary ASCB, Ret in R1
         USING ASCB, R1
               R15, ASCBXTCB
                                   Save Xmem Resource Owning TCB
         DROP
                                   Restore Input Length to R0 Establish Addressability
         LR
               R0,R2
         BALR R2, R0
         USING *,R2
         LTR
               R0, R0
                                   request for below?
               BELOW
                                  yes
allocate anywhere
         BNL
               R0,1
         SLL
         SRL
               R0,1
                                   clear high bit
         LTR
               R2,R2
                                   are we running below the line
         BNL BELOW yes, get below instead of anywhere STORAGE OBTAIN, LENGTH=(R0), COND=YES, SP=3, TCBADDR=(R15)
                                  successful?
         I TR
               R15,R15
         BZR
               R4
                                   yes, return
         SR
               R1,R1
                                   R1=0, R15<>0 for failure
               R4
         BR
                                   Return
BELOW
         DS
               0H
                                   Get memory below the line
         STORAGE OBTAIN, LENGTH=(R0), COND=YES, LOC=BELOW,
               SP=3,TCBADDR=(R15)
         LTR
               R15,R15
                                  Was it successful?
                                  yes, return
R1=0, R15<>0 for failure
         BZR
         SR
               R1,R1
         BR
               R4
                                   Return
*************************
    CSECT-NAME: @@XFREE
    DESCRIPTIVE-NAME: Free allocated storage for C/370
*
    Input: R0 - length of storage to free
           R1 - address of storage to free
R14 - Return address
    No save area is provided.
    R2 and R4 are used as work regs
    Regs and Access Regs 0, 1, 14, 15 may be modified.
*************************
@@XFREE CSECT
@@XFREE
         AMODE ANY
@@XFREE
         RMODE ANY
         ENTRY @@XFREE
               R2,R1
                                   Save Input Addr
         ST
               R0,0(R2)
                                   Save Input Length in the passed area
         LR
               R4,R14
                                  Save Return Addr
         EPAR R15
                                   Extract Primary ASID
         LOCASCB ASID=(R15)
                                  Locate the Primary ASCB, Ret in R1
         USING ASCB,R1
               R15, ASCBXTCB
                                  Save Xmem Resource Owning TCB
         DROP
               R1
               R0,0(R2)
                                   Restore Input Length to R0
Restore Input Addr to R1
         I R
               R1,R2
         BALR R2, R0
                                   Establish Addressability
         USING *,R2
         STORAGE RELEASE, LENGTH=(R0), ADDR=(R1), SP=3, TCBADDR=(R15)
         BR
               R4
R0
         EQU
               0
R1
         ΕŎU
               1
         EQU
R2
               2
R4
         ΕQŪ
               4
R14
         EQU
               14
R15
         ΕQU
         PRINT OFF
         IHAASCB
         PRINT ON
```

END

BPXT4KGT—Get a page of storage

This function gets a 4KB page of storage.

C function

```
#pragma linkage(BPXT4KGT,OS)
char *BPXT4KGT (long len,long key);
```

Assembler routine

```
*************************
   CSECT-NAME: BPXT4KGT
   DESCRIPTIVE-NAME: Allocate storage on a page boundary with key.
                     Storage is allocated in subpool 229.
  Input: R1 - Parm list
                 length of storage to obtain
                 key for storage
   Output: R15 - address of storage obtained
***************************
BPXT4KGT CSECT
BPXT4KGT AMODE ANY
BPXT4KGT RMODE ANY
        ENTRY BPXT4KGT
        EDCPRLG
              R2,0(R1)
                               get addr of length get length
              R0,0(R2)
              R2,4(R1)
R2,0(R2)
                               get addr of key
                               get key
                               put in bits 24-27
              R2,4
        STORAGE OBTAIN, LENGTH=(RO), BNDRY=PAGE, COND=YES, SP=229, KEY=(2)
              R15,R15
        I TR
                               successful?
                              yes, return
        ΒZ
              OUT4KGT
                             addr=0 for failure return storage address
        SR
              R1,R1
              R15,R1
OUT4KGT LR
        EDCEPIL
```

BPXT4KFR—Free a page of storage

This function frees a 4KB page of storage.

C function

```
#pragma linkage(BPXT4KFR,OS)
void BPXT4KFR (long len,long key,char *stor);
```

Assembler routine

```
ENTRY BPXT4KFR
EDCPRLG

L R2,0(R1) get addr of length
L R0,0(R2) get length
L R2,4(R1) get addr of key
L R2,0(R2) get key
SLL R2,4 put in bits 24-27
L R1,8(R1) get storage addr
STORAGE RELEASE,LENGTH=(R0),ADDR=(R1),SP=229,KEY=(R2)
EDCEPIL
```

BPXTWAIT—Wait on an ECB list

This function waits for an ECB in a list to be posted.

C function

```
#pragma linkage(BPXTWAIT,OS)
void BPXTWAIT (ECB *ecb1,...);
```

Assembler routine

BPXTPOST—Post an ECB

This function posts an ECB.

C function

```
#pragma linkage(BPXTPOST,OS)
void BPXTPOST (long ascb,ECB *ecb);
```

Assembler routine

```
BPXTPOST CSECT
BPXTPOST AMODE ANY
BPXTPOST RMODE ANY
ENTRY BPXTPOST
         EDCPRLG USRDSAL=POSTLN
         USING POSTDYN, R13
               POSTL(POSTLN), POSTS copy POST parmlist to dynamic area
               R2,0(,R1)
R2,0(,R2)
                                   get addr of ascb addr
                                  get ascb addr
               R4,4(,R1)
                                   get addr of ECB to post
         POST (R4), ASCB=(R2), ERRET=POSTERR, ECBKEY=0, LINKAGE=SYSTEM,
               MF=(E,POSTL)
         EDCEPIL
POSTS
         POST 0, ASCB=0, ERRET=0, ECBKEY=YES, MF=L
POSTERR BR
               R14
POSTDYN EDCDSAD
         POST 0, ASCB=0, ERRET=0, ECBKEY=YES, MF=L
P0STL
POSTLN
         EQU *-POSTL
         IĤAPSA
```

BPXTEPOC—Convert time-of-day to epoch time

This function converts time-of-day to seconds-since-the-epoch.

C function

```
#pragma linkage(BPXTEPOC,OS)
void BPXTEPOC(char *tod, long *epoch);
```

Assembler routine

```
*****************
   CSECT-NAME: BPXTEPOC
*
    DESCRIPTIVE-NAME: Convert TOD to Epoch time
               address of TOD value to convert (double word)
               address of output epoch time (one word)
BPXTEPOC CSECT
BPXTEPOC AMODE ANY
BPXTEPOC RMODE ANY
         EDCPRLG
              R14,R14 Check bight
        LM
        LTR
                                 check high word for 0
         BNZ
              EPOCTOD
                               get current tod
get tod
                                if input tod is 0
         STCK 0(R2)
              R14, R15, O(R2)
              R2,4(R1) get output area
R0,R1,EPOCJ70 get epoch tod
EPOCTOD L
         LM
         SLR
               R15,R1
        BC
               11,*+6
        BCTR
              R14,0
        SLR
               R14,0
               R14, EPOCST
                                divide by seconds per tod unit
         SLR
              R14,R14
         LA
               R1,2
               R14,R1
         DR
               R15,0(R2)
         EDCEPIL
EPOCJ70
               X'7D91048BCA000000'
```

BPXTEPOCcnn

EPOCST DC X'7A120000'

Appendix F. Accessibility

Accessible publications for this product are offered through IBM Documentation (www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the Contact the z/OS team web page (www.ibm.com/systems/campaignmail/z/zos/contact_z) or use the following mailing address.

IBM Corporation
Attention: MHVRCFS Reader Comments
Department H6MA, Building 707
2455 South Road
Poughkeepsie, NY 12601-5400
United States

Accessibility features

Accessibility features help users who have physical disabilities such as restricted mobility or limited vision use software products successfully. The accessibility features in z/OS can help users do the following tasks:

- Run assistive technology such as screen readers and screen magnifier software.
- Operate specific or equivalent features by using the keyboard.
- Customize display attributes such as color, contrast, and font size.

Consult assistive technologies

Assistive technology products such as screen readers function with the user interfaces found in z/OS. Consult the product information for the specific assistive technology product that is used to access z/OS interfaces.

Keyboard navigation of the user interface

You can access z/OS user interfaces with TSO/E or ISPF. The following information describes how to use TSO/E and ISPF, including the use of keyboard shortcuts and function keys (PF keys). Each guide includes the default settings for the PF keys.

- z/OS TSO/E Primer
- z/OS TSO/E User's Guide
- z/OS ISPF User's Guide Vol I

Dotted decimal syntax diagrams

Syntax diagrams are provided in dotted decimal format for users who access IBM Documentation with a screen reader. In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line because they are considered a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that the screen reader is set to read out punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1)

are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The * symbol is placed next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element *FILE with dotted decimal number 3 is given the format 3 * FILE. Format 3* FILE indicates that syntax element FILE repeats. Format 3* * FILE indicates that syntax element * FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol to provide information about the syntax elements. For example, the lines 5.1*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, it indicates a reference that is defined elsewhere. The string that follows the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %0P1 means that you must refer to separate syntax fragment OP1.

The following symbols are used next to the dotted decimal numbers.

? indicates an optional syntax element

The question mark (?) symbol indicates an optional syntax element. A dotted decimal number followed by the question mark symbol (?) indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that the syntax elements NOTIFY and UPDATE are optional. That is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.

! indicates a default syntax element

The exclamation mark (!) symbol indicates a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicate that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the dotted decimal number can specify the ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In the example, if you include the FILE keyword, but do not specify an option, the default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, the default FILE (KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP applies only to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

* indicates an optional syntax element that is repeatable

The asterisk or glyph (*) symbol indicates a syntax element that can be repeated zero or more times. A dotted decimal number followed by the * symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line 5.1* data area, you know that you can include one data area, more than one data area, or no data area. If you hear the lines 3*, 3 HOST, 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

Notes:

- 1. If a dotted decimal number has an asterisk (*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
- 2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you can write HOST_STATE, but you cannot write HOST_HOST.
- 3. The * symbol is equivalent to a loopback line in a railroad syntax diagram.

+ indicates a syntax element that must be included

The plus (+) symbol indicates a syntax element that must be included at least once. A dotted decimal number followed by the + symbol indicates that the syntax element must be included one or more times. That is, it must be included at least once and can be repeated. For example, if you hear the line 6.1+ data area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. Similar to the * symbol, the + symbol can repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the * symbol, is equivalent to a loopback line in a railroad syntax diagram.

Notices

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
United States of America

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Site Counsel 2455 South Road Poughkeepsie, NY 12601-5400 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at ibm.com®/privacy and IBM's Online Privacy Statement at ibm.com/privacy/details in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at ibm.com/software/info/product-privacy.

Policy for unsupported hardware

Various z/OS elements, such as DFSMSdfp, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Minimum supported hardware

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: IBM Lifecycle Support for z/OS (www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. If these and other IBM trademarked terms are marked on their first occurrence in this information with a trademark symbol (° or ™), these symbols indicate U.S. registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current list of IBM trademarks is available on the Web at Copyright and Trademark information (www.ibm.com/legal/copytrade.shtml).

UNIX is a registered trademark of The Open Group in the United States and other countries.

Acknowledgments

InterOpen/POSIX Shell and Utilities is a source code product providing POSIX.2 (Shell and Utilities) functions to z/OS UNIX System Services. InterOpen/POSIX Shell and Utilities is developed and licensed by Mortice Kern Systems (MKS) Inc. of Waterloo, Ontario, Canada.

Index

| Special Characters | В |
|-----------------------------------------------------------------------------------------|-------------------------------------------------------------|
| @@XFREE, assembler replacement for 517 | batch-select 74 |
| @@XGET, assembler replacement for 517 | bind a name to a socket 123 |
| | BPX1VAC, BPX4VAC 255 |
| Numerics | BPX1VCL BPX4VCL 257 |
| | BPX1VCR, BPX4VCR example 453 |
| 64-bit addressing | BPX1VEX, BPX4VEX 264 |
| indicating to the PFS <u>66</u> 64-bit addressing, considerations for | BPX1VGA, BPX4VGA |
| VFS server interface 242 | example 454 |
| 64-bit virtual addressing | BPX1VGT, BPX4VGT |
| PFS support for | example <u>454</u> |
| indicating 66 | BPX1VIO, BPX4VIO |
| levels 66 | example 455 |
| | BPX1VLK, BPX4VLK |
| A | example 456 |
| | BPX1VLN, BPX4VLN example 455 |
| abnormal ends, PFS <u>23</u> | BPX1VLO, BPX4VLO |
| accept a socket connection and read the first block of data | example 455 |
| 116 | BPX1VMD, BPX4VMD |
| accept a socket connection request 111 | example 456 |
| access check | BPX1VOP, BPX4VOP 301 |
| against remote systems <u>13</u> availability 271 | BPX1VPC, BPX4VPC |
| access to a file or directory 114 | example 457 |
| accessibility | BPX1VRA, BPX4VRA |
| contact IBM 523 | example 458 |
| features 523 | BPX1VRD, BPX4VRD |
| address space control block (ASCB) 19 | example <u>458</u> BPX1VRE, BPX4VRE |
| address space termination <u>23</u> | example 460 |
| AMODE 64 | BPX1VRG, BPX4VRG |
| PFS support for 71 | example 458 |
| appropriate privileges 12, 241 | BPX1VRL, BPX4VRL |
| assembler facilities for writing a PFS in C <u>517</u> assembler language syntax 253 | example <u>459</u> |
| assembler programming language routines | BPX1VRM, BPX4VRM |
| converting TOD to epoch time 521 | example 459 |
| freeing a page of storage 519 | BPX1VRN, BPX4VRN |
| getting a page of storage 519 | example <u>459</u> BPX1VRP, BPX4VRP |
| posting an ECB 520 | example 460 |
| waiting on an ECB posting <u>520</u> | BPX1VRP, BPX4VRP) 337 |
| assembler-language replacements for @@XGET and | BPX1VRW, BPX4VRW |
| @@XFREE 517 | example 457 |
| assistive technologies 523 | BPX1VSA, BPX4VSA |
| async I/O vn_cancel for asynchronous operations 126 | example <u>460</u> |
| asynchronous mount processing 27 | BPX1VSF, BPX4VSF |
| ATTR structure | example 454 |
| security fields 38 | BPX1VSY, BPX4VSY |
| time fields 38 | example <u>461</u> BPXT4KFR (Free a page of storage) 519 |
| attributes | BPXT4KGT (Get a page of storage) 519 |
| getting and setting <u>37</u> | BPXTEPOC (Convert TOD to epoch time) 521 |
| getting and setting with VFS servers 251 | BPXTPOST (Post an ECB) 520 |
| audit an action <u>121</u> | BPXTWAIT (Wait on an ECB list) 520 |
| | BPXXCTME macro 68 |

| BPXYALIR 433 | control blocks (continued) |
|---------------------------------------------------------------|------------------------------------------------------|
| BPXYNREG 440 | VFS-vnode vector tables <u>16</u> |
| BPXYOSS 443 | vnode operations vector table 8 |
| BPXYPFSI macro 484 | vnode-inode pair 18 |
| BPXYVFSI macro 465 | convert a file identifier to a vnode token 108, 271 |
| BPXYVLOK 445 | converting TOD to epoch time 521 |
| BPXYVOPN 450 | convey |
| | • |
| buffers, read or write using multiple <u>184</u> | command to a file system 276 |
| byte-range locking <u>283</u> | create a directory <u>165</u> , <u>297</u> |
| | create a file open a file <u>301</u> |
| C | create a link to a file 152, 280 |
| | create a new file 136 |
| C-language facilities for writing a PES in C 517 | create a socket or a socket pair 97 |
| C-language facilities for writing a PFS in C 517 | create a symbolic link 234, 348 |
| C-language PFSs <u>12</u> | creating a file 260 |
| CALL macro 253 | |
| callable services | cross memory for a PFS using daemons 42 |
| invoking 253 | cross-memory considerations for a PFS 11 |
| return_value parameter 254 | cross-memory local lock <u>22</u> |
| syntax 253 | cursor technique for reading directories 36 |
| callable services examples 453 | |
| callable services reentrant entry 453 | |
| | D |
| cancel asynchronous operations that are still in progress 126 | |
| check access to a file or directory <u>114</u> | daemon tasks <u>42</u> |
| check file accessibility <u>255</u> | define a socket domain to the PFS <u>88</u> |
| check file availability 271, 280 | determine configurable path name values 171 |
| close a file 257 | directories |
| closing files 31, 130 | creating 297 |
| command | reading 35, 36 |
| | |
| to file system 276 | removing 334 |
| Common INET (CINET) sockets | dynamic service activation, PFS support for <u>8</u> |
| initialization | |
| AF_INET (IPV4) transport driver <u>51</u> | E |
| AF_INET6 (IPV6) transport driver 52 | - |
| master socket 48 | ECB 4 |
| PFS structure | _ |
| transport driver (TD) 47 | end-of-memory resource manager 23 |
| | entry interface <u>5</u> |
| transport provider (TP) <u>47</u> | EOM resource manager 23 |
| prerouter <u>50</u> | ESTAE exits 23 |
| rebuilding routing tables <u>54</u> | export a file system 264 |
| route changes <u>52</u> | exporting files to a VFS server 42 |
| comparing the VFS server and PFS interfaces 251 | external name, symbolic link to 348 |
| connect to a socket 133 | external name, symbolic link to 340 |
| contact | |
| | F |
| z/OS <u>523</u> | |
| control block structure for the LFS-PFS 16 | feedback xv |
| control blocks | FID (file identifier) 42 |
| address space control block (ASCB) <u>19</u> | file |
| ATTR structure 37 | |
| file security packet (FSP) 12, 37 | attributes 142 |
| general file system table (GFS) 4 | attributes, getting <u>274</u> |
| GFS-PFS_anchor pair 17 | availability 271, 280 |
| initialization complete ECB 4 | caching 30 |
| | creating 260 |
| integrity of 18 | exporter 365 |
| NREG structure 245 | exporting to a VFS server 42 |
| OSI service routine vector table <u>6</u> | handles, NFS 248 |
| OSI structure <u>18</u> | |
| OSIT structure 4, 355 | identifier (FID) 42 |
| PFS initialization structure 6 | management PFS <u>14</u> |
| serializing 22 | sharing <u>18</u> |
| termination ECB 5 | system status 268 |
| | system status, report 392 |
| Token_structure 18 | truncating 237 |
| UIO structure <u>34</u> | file access, checking 255 |
| VFS operations vector table <u>8</u> | |
| VFS-MNT pair 17 | file security packet (FSP) |

| file security packet (FSP) (continued) created by SAF 30 | IRRPIFSP (file security packet) $\underline{12}$, $\underline{37}$ |
|-------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| file systems | K |
| exporting 264 | |
| mounting <u>25</u> unmounting 27 | keyboard |
| file tag 41 | navigation 523 |
| file token 17 | PF keys 523 |
| files | shortcut keys <u>523</u> |
| closing <u>257</u> | and the second s |
| creating 301 | L |
| opening 301 | LFS-PFS control blocks |
| FILESYSTYPE statement 3 | serializing 22 |
| freeing a page of storage <u>519</u> FRR 402, 415 | structure 16 |
| FRR exits 23 | link |
| FSP (file security packet) 12, 37 | external 319 |
| | reading a symbolic <u>319</u> |
| G | to a file <u>152</u> link counts 31 |
| | listen on a socket 156 |
| general file system table (GFS) <u>4</u> | lock a file 283 |
| generate the requested signal event 400 | lock control 158 |
| get | locking, byte-range 283 |
| attributes of a file <u>274</u> file attributes 142 | look up a file or directory 162, 294 |
| file system status 100 | LP64 (64-bit longs and pointers) <u>67</u> |
| page of storage 519 | |
| peer name 144 | M |
| socket host ID or name 78 | make a directory 165 |
| socket name 144 | mapping macro |
| socket options 224 | BPXYATTR 433 |
| vnodes 372 | BPXYNREG 440 |
| getting and setting attributes VFS servers 251 | BPXYOSS 443 |
| GFS (general file system table) 4 | BPXYVLOK <u>445</u> |
| GFS-PFS_anchor pair 17 | BPXYVOPN 450 |
| GIDs, obtaining with osi_getcred 369 | messages to or from a socket 227 |
| | MODIFY OMVS,PFS PFS support for 70 |
| H | modules, invoking 253 |
| | mount |
| harden all file data for a file system | a file system <u>25, 84</u> |
| unmount a file system 105 | key <u>246</u> |
| harden file data <u>139</u> | points <u>27</u> |
| _ | structure 249 |
| I | VFS servers <u>245</u> MOUNT statement 3 |
| I/O control 149 | mount token 17 |
| inactivate a vnode | mounting file systems |
| deleting 29 | asynchronously 27 |
| inactivating 29 | moving data |
| index technique for reading directories <u>36</u> | between PFS buffers and buffers defined by a UIO 410 |
| initialization token 16 | between user and PFS buffers with 64-bit addresses |
| initialization-complete ECB <u>4</u> inodes 16 | 363 from a PFS buffer to a user buffer 360 |
| installing a PFS 3 | from a user buffer to a PFS buffer 357 |
| interface between LFS and PFS 13 | msgctl(), in-kernel 379 |
| Internet Protocol Version 6 (IPv6) | msgget(), in-kernel 382 |
| activating <u>61</u> | msgrcv(), in-kernel 385 |
| invoking callable services 253 | msgsnd(), in-kernel <u>389</u> |
| ioctl, convey a command 149 | multilevel security |
| ipcget(), in-kernel <u>376</u> IPv6 (Internet Protocol Version 6) | PFS support for <u>64</u> multiple buffers, read or write 184 |
| activating <u>61</u> | mattiple bullers, read of write 104 |

| installation 3 share reservations 38 tokens 16 NETWORK statement activating IPv6 61 in parmible 3 NFS file handles 248 NREG structure 245 O O Offset system control callable services 423 open token 33 opening files 31, 168 OSI services routine vector table 6 OSI services orutine vector table 6 OSI services orutine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi. copyo4 67, 363 osi. copyo4 67, 363 osi. gebronde 372 osi. copyo4 356 osi. getroed 369 osi. gebronde 372 osi. kmsgert 376 osi. kmsgert 376 osi. kmsgert 379 osi. kmsgert 389 osi. mountstatus 392 osi. mountstatus 392 osi. mountstatus 392 osi. pentoken 33 osi. post 394 osi. spentoken 350 osi | N | PFS (continued) |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------|----------------------------------------------|
| keyboard 523 NETWORK statement activating IPv6 61 in parmilb 43 NFS file handles 248 NREG structure 245 O offset system control callable services 423 open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi copyod 467, 363 osi copyou 350 osi copyou 350 osi getered 369 osi getered 369 osi getered 369 osi getered 369 osi kipeget 376 osi kmsget 379 osi kmsget 379 osi kmsget 382 osi kmsgro 385 osi kmsget 382 osi kmsgro 385 osi kmsget 389 osi mountstatus 392 osi pentoken 33 osi post 394 osi selpost 398 osi mountstatus 392 osi pentoken 33 osched-oriented 43, 47 PFS support for 64-bit virtual addressing 66 PFS support for 64-bit virtual address | | _ |
| NETWORK statement activating IPv6 61 in parmilb 43 NR5 file handles 248 NREG structure 245 Offset System control callable services 423 Open token 33 Open token 33 Open token 33 Open token 63 Services of the state | | |
| activating IPv6 61 in parmilb 43 NFS file handles 248 NREG structure 245 O offset system control callable services 423 open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services orutine vector table 6 OSI services de vector orutine vector vect | | |
| in parmitib 43 NREG structure 245 NREG structure 245 O offset system control callable services 423 open token 33 open token 33 open token 33 open token 34 osi _copyou 360 osi _cot _cot _cot _cot _cot _cot _cot _cot | | |
| NFS file handles 248 NREG structure 245 O offset system control callable services 423 open token 33 open ing files 31, 168 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi, copy64 67, 363 si, copyoin 357 OSI structure 18 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 OSI structure 19 OSI (post 369 OSI (post 376 OSI (post 376 OSI (post 377 OSI (post 378) OSI (post 379 | <u> </u> | |
| File-oriented 13, 43 socket-oriented 43, 47 PFS recovery considerations abnormal ends 23 address space termination 23 task ter | • | · · · · · · · · · · · · · · · · · · · |
| socket-oriented 43, 47 PFS recovery considerations abnormal ends 23 address space termination 23 task termination 23 thread | | |
| offset system control callable services 423 open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi copy64 67, 363 osi_copyout 360 osi_ctal 365 osi_getcred 369 osi_getered 369 osi_kingset 376 osi_kmsget 379 osi_kmsget 382 osi_kmsget 382 osi_kmsget 382 osi_kmsget 389 osi_mountstatus 392 osi_opentoken 33 osi_selond 398 osi_selond 399 osi_mountstatus 392 osi_opentoken 33 osi_selond 398 osi_selond 398 osi_selond 398 osi_selond 398 osi_selond 399 osi_si_selond 399 osi_selond 399 osi_si_selond 399 osi_selond 399 osi_si_selond 399 osi_selond 399 osi_si_selond 399 osi_si_selond 399 osi_si_selond 399 osi_si_selond 399 osi_si_selond 399 osi_si_selond 399 osi_selond 399 osi_si_selond 399 osi_si_selond 399 osi_si_selond 399 osi_selond 399 o | INNER STRUCTURE 245 | |
| abnormal ends 23 address space termination 23 task termination 23 | | |
| offset system control callable services 423 open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy64 67, 363 osi_copy64 67, 363 osi_copy64 67, 365 osi_copyout 360 osi_cotyn 357 osi_copyout 360 osi_getrond 372 osi_kincget 376 osi_kmsget 379 osi_kmsget 382 osi_kmsget 382 osi_kmsget 389 osi_mountstatus 392 osi_kmsget 389 osi_mountstatus 392 osi_sopen 394 osi_soled 394 osi_soled 395 osi_si_soled 396 osi_si_soled 396 osi_si_soled 396 osi_si_soled 396 osi_si_soled 396 osi_si_soled 397 osi_si_soled 396 osi_soled 397 osi_post 394 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 397 osi_soled 398 osi_mountstatus 392 osi_nonet 394 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 396 osi_soled 397 osi_soled 396 osi_soled 397 osi_post 394 osi_soled 397 | 0 | |
| system control callable services 423 open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services routine vector table 6 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy64 67, 363 osi_copy1 357 osi_copyout 360 osi_ct 1365 osi_getred 369 osi_getred 369 osi_kmsgrt 379 osi_kmsgrt 379 osi_kmsgrt 379 osi_kmsgrt 382 osi_opentoken 33 osi_post 394 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_wait 415 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 PR parm parameters 254 parmib statements FILESSYTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 finitialization structure 6 task ttermination 23 thread 403 vfs_recovery 23 PFS recycling 9 PFS support for fe4-bit virtual addressing 66 PFS support for fe4-bit virtual addressing 66 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for multilevel security 64 PFS support for reason code error text 69 PFS_support for multilevel security 64 PFS support for multilevel security 64 PFS support for multilevel security 69 PFS_suport for multilevel security 69 PFS_suport for fe4-bit virtual addressing 66 PFS support for multilevel security 69 PFS_suport for fe4-bi | offcot | |
| callable services 423 open token 33 open token 33 open ing files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi copy64 67, 363 osi copy64 67, 363 osi copyout 360 osi _ctil 365 osi _ctil 365 osi _ctil 365 osi _ctil 365 osi _kingegt 376 osi _kmsget 379 osi _kmsget 382 osi _mountstatus 392 osi _opentoken 33 osi _mountstatus 392 osi _opentoken 33 osi _stopion 394 osi _stel 396 osi _stelp 402 osi _stelp 402 osi _stelp 405 osi _unda 414 osi _stelp 405 osi _wakeup 419 OSIT (OSI operations vector table (OSIT) 4 output file attribute buffer address 19 P aparm parameters 254 parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 433 Path and | | |
| open token 33 opening files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copyol 4 67, 363 osi_copyoi 357 osi_copyoi 357 osi_copyoi 357 osi_copyoi 357 osi_getred 369 osi_getred 369 osi_getred 376 osi_kmsgert 382 osi_kmsgert 382 osi_kmsgert 389 osi_mountstatus 392 osi_kmsgert 389 osi_sophotken 33 osi_sophotken 33 osi_sophotken 33 osi_sophotken 33 osi_sophotken 33 osi_sophotken 33 osi_pots 394 osi_sophotken 34 osi_sophotken 35 osi_sophotken 36 osi_sophotken 36 osi_sophotken 37 osi_sophotken 37 osi_knaper 402 osi_thread 405 osi_sophotken 36 osi_sophotken 37 osi_sophotken 37 osi_sophotken 38 osi_sophot 398 osi_sophotken 39 osi_sophotken 34 osi_sophotken 34 osi_sophotken 35 osi_pots 398 osi_sophotken 36 osi_sophotken 37 osi_sophotken 37 osi_sophotken 38 osi_sophotken 38 osi_sophotken 39 | | |
| opening files 31, 168 OSI service routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy64 67, 363 osi_copy04 67, 363 osi_copyin 357 osi_copyout 360 osi_getrod 372 osi_getrod 372 osi_kingget 376 osi_kmsget 379 osi_kmsget 382 osi_kmsget 382 osi_kmsget 382 osi_kmsget 382 osi_kmsget 389 osi_mountstatus 392 osi_opontoken 33 osi_post 394 osi_sleep 402 osi_opentoken 33 osi_sleep 402 osi_sleep 402 osi_sleep 405 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P parm parameters 254 parmilb statements FILESYSTYPE 3 Nathornal ends 23 file protocols 25 intitalization structure 6 | | user process termination 23 |
| OSI services routine vector table 6 OSI services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy64 67, 363 osi_copy64 67, 363 osi_copyout 360 osi_ctl 365 osi_ctl 365 osi_getred 369 osi_getred 369 osi_kingget 376 osi_kingget 376 osi_kingget 378 osi_kingget 382 osi_kingget 383 osi_poptoken 33 osi_post 394 osi_si_selpost 398 osi_selpost 398 osi_selpo | • | · · · · · · · · · · · · · · · · · · · |
| OSJ services from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSJ structure 18 osi_copyle 467,363 osi_copyin 357 osi_copyout 360 osi_ct 1365 osi_getered 369 osi_ketered 369 osi_ketered 376 osi_kmsget 376 osi_kmsget 376 osi_kmsget 382 osi_kmsget 382 osi_kmsget 382 osi_kmsget 383 osi_post 394 osi_post 394 osi_sched 396 osi_selpost 398 osi_sclabed 402 osi_thread 405 osi_slighal 400 osi_slighal 400 osi_slighal 415 osi_wait 64 osi_ketclinia 406 osi_set 110 blocks osi_ketclinia 415 osi_wai | | vn_recovery 23 |
| from a non-kernel address space 356 invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy\u00e467, 363 osi_copy\u00e467, 363 osi_copy\u00e467, 363 osi_copy\u00e467, 363 osi_copy\u00e467, 363 osi_copy\u00e41360 osi_cti 365 osi_cepy\u00e46372 osi_getroed 370 osi_getroed 372 osi_kingget 376 osi_kingget 376 osi_kingget 379 osi_kingget 382 osi_kingget 383 osi_kost 394 osi_mountstatus 392 osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_si sched 396 osi_si selpost 398 osi_si sched 305 osi_tinead 405 osi_si_uomev 410 osi_uomev | _ | PFS recycling 9 |
| invoking in 31-bit and 64-bit addressing mode 357 OSI structure 18 osi_copy64 67, 363 osi_copyin 357 osi_copyour 360 osi_ctrl 365 osi_getcred 369 osi_getrode 372 osi_kingget 376 osi_kmsgrtv 385 osi_kmsgrtv 385 osi_kmsgrtv 385 osi_kmsgrtv 385 osi_mountstatus 392 osi_opontoken 33 osi_post 394 osi_selpost 394 osi_selpost 394 osi_selpost 398 osi_signal 400 osi_uelde 4.15 osi_wait 415 | | PFS support for 64-bit virtual addressing 66 |
| osi structure 18 osi_copy64 67, 363 osi_copyout 360 osi_cotyout 360 osi_cotyout 360 osi_getred 369 osi_getred 369 osi_kmsgct 376 osi_kmsgct 379 osi_kmsgct 382 osi_kmsgst 382 osi_kmsgst 383 osi_pest 383 osi_pest 384 osi_selbed 396 osi_selbed 400 osi_selbed 400 osi_selbed 410 osi_selbed 410 osi_upda 414 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 interes 198 proving 122 proving 122 proving 122 proving | | |
| osi_copyin_357 osi_copyout_360 osi_cot_365 osi_getcred_369 osi_getrod_372 osi_kingset_376 osi_kingset_376 osi_kmsgct_379 osi_kmsgct_382 osi_kmsgct_382 osi_kmsgct_382 osi_kmsgct_383 osi_post_394 osi_opentoken_33 osi_post_394 osi_scled_396 osi_selpost_398 osi_scled_396 osi_selpost_398 osi_scled_396 osi_selpost_398 osi_scled_396 osi_selpost_398 osi_lopentoken_306 osi_selpost_398 osi_scled_396 osi_scled_497 osi_scled_19postcled_49 osi_scled_19postcled_49 osi_scled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcled_19postcl | <u> </u> | |
| osi_copyin 357 osi_copyout 360 osi_cett 365 osi_getcred 369 osi_getvnode 372 osi_kipcget 376 osi_kmsget 379 osi_kmsget 382 osi_kmsget 382 osi_kmsger 385 osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_sisled 400 osi_steped 402 osi_tread 405 osi_umate 410 osi_umate 415 osi_wait 416 osi_wait 417 osi_wait 418 osi_wait 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 pisctt (PFS control) blocks serializing 22 structure 16 pfsett (PFS control) 91 physical file system See PFS 14 physical file system See PFS 14 physical file system See PFS 14 physical file system interface facilities for writing in C 517 socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 43 mounting file systems 26 some operations not in this interface 14 vn_inactive not required for sockets 44 vn_ode structure 17 post a process mosting for select 398 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process, registering as a server 321 P R read a symbolic link 181, 319 directory entries 178 entries from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading and writing with sockets 44 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 | osi_copy64 67, 363 | |
| ssi_ctl 365 si_getcred 369 si_getrond 372 si_kipcget 376 si_kipcget 376 si_kinsget 379 si_kinsget 382 si_kinsger 385 si_kinsger 386 si_kinsger 386 si_kinsger 387 si_kinsger 385 si_kinsger 388 si_post 394 si_sched 396 si_selpost 398 si_signal 400 si_slepe 402 si_signal 400 si_slepe 402 si_thread 405 si_uiomove 410 so_uiomove 410 so_uio | | |
| osi_getrod 369 osi_getrod 372 osi_knows 21379 osi_knows 21389 osi_mountstatus 392 osi_post 394 osi_solution 217, 337 PP parm parameters 254 parmibi statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 path name resolution 27, 337 PFS abnormal ends 23 file protocols 25 initalization structure 6 pisking 21379 physical file system See PFS 14 physical file system See FS 14 physical file system See F | osi_copyout 360 | <u> </u> |
| osi_getvnode 372 osi_kipcget 376 osi_kmsget 382 osi_kmsget 382 osi_kmsget 382 osi_kmsget 389 osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_sched 396 osi_selpost 398 osi_selpost 398 osi_signal 400 osi_signal 400 osi_signal 405 osi_upda 414 osi_upda 415 osi_upda 414 osi_upda 414 osi_upda 415 osi_upda 414 osi_upda 416 osi_upda 417 osi_utomove 410 osi_upda 418 osi_upda 419 osi_upda 419 osi_upda 419 osi_upda 419 osi_tried attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 physical file system See PFS 14 physical file system 1ce 1517 socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 43 mounting file system 1ce 1517 socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 43 mounting file system socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 43 mounting file system socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 92 file export operations 43 mounting file system socket-oriented 43, 47 PID (process id) 19 porting file caching not done by PFS 29 file export operations 92 file export operations 92 some operations not in this interface 14 vn_inactive not not by PFS 29 file export operations 92 file caching not done by PFS 29 file export operations 92 file caching not done by PFS 29 file export operations 92 file caching not done by PFS 29 | osi_ctl <u>365</u> | |
| osi_kipcget 376 osi_kmsgct 379 osi_kmsgct 382 osi_kmsgct 382 osi_kmsgcr 385 osi_kmsgcr 385 osi_kmsgcr 385 osi_kmsgcr 389 osi_mountstatus 392 osi_post 394 osi_sched 396 osi_selpost 398 osi_se | | |
| osi_kmsgct 379 osi_kmsgct 382 osi_kmsgct 385 osi_kmsgct 385 osi_kmsgct 386 osi_kmsgct 389 osi_mountstatus 390 osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_sched 396 osi_sched 396 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 398 osi_selpost 390 osi_stread 405 osi_slep 402 osi_thread 405 osi_supda 414 osi_uomove 410 osi_uomove | | |
| osi_kmsget 382 osi_kmsget 382 osi_kmsget 385 osi_kmsget 385 osi_kmsget 386 osi_kmsget 387 osi_kmsget 389 osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_sched 396 osi_selpost 398 osi_sched 396 osi_selpost 398 osi_signal 400 osi_signal 400 osi_signal 400 osi_thread 405 osi_uiomove 410 osi_uiomove 410 osi_uiomove 410 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 | | |
| soi_kmsgrov 385 osi_kmsgrov 385 osi_kmsgrov 385 osi_kmsgrov 385 osi_kmsgrov 389 osi_mountstatus 392 osi_opentoken 33 osi_operations 43 osi_opentoken 33 osi_operations 43 osi_operations 43 osi_operations 43 osi_operations 43 osi_operations and this interface 14 osi_osi_operations and this interface 14 osi_osi_operation and 405 osi_operation and 406 osi_operation and | | |
| osi_kmsgsnd 389 osi_mountstatus 392 osi_opentoken 33 osi_poentoken 33 osi_opentoken 33 osi_opentoken 33 osi_opentoken 33 osi_opentoken 34 osi_sched 396 osi_sched 396 osi_sched 396 osi_sched 398 osi_sched 398 osi_sched 398 osi_sched 398 osi_sched 309 osi_sched 398 osom operations oblint his interface 14 vn_inaction of the sport operations vector 127 post a process in osi_wait 394 posting a FCB 520 posting an ECB 520 posting an ECB 520 posting internal events 20 privileges, approriate 12, 241 process ID (PID) 19 process, registering as a server 321 P R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for V | | |
| osi_mountstatus 392 osi_opentoken 33 osi_post 394 osi_sched 396 osi_selpost 398 osi_signal 400 osi_selpost 398 osi_signal 400 osi_selpost 398 osi_signal 400 osi_signal 405 osi_signal 405 osi_unimove 410 osi_unimove 410 osi_unimove 410 osi_unimove 419 osi_wait 415 osi_wait 416 osi_wait 417 osi_wait 418 osi_wait 419 osi_wait 415 osi_wait 394 osi a process in osi_wait 394 osi_wait 394 osi_wait 394 osi_wait 394 osi_wait 394 osi_wait 415 osi_wait 394 osi_wait 394 osi_wait 394 osi_wait 394 osi_wait 415 osi_wait 394 osi_wait 3 | | |
| osi_opentoken 33 osi_post 394 osi_sched 396 osi_sched 396 osi_sched 398 osi_signal 400 osi_signal 400 osi_signal 400 osi_upda 414 osi_upda 414 osi_wakeup 419 osi_wakeup 419 osi_roperations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 file caching not done by PFS 29 file export operations 43 mounting file systems 26 some operations not in this interface 14 vn_inactive not required for sockets 44 vnode not freed by PFS 29 vnode structure 17 post a process in osi_wait 394 post a process waiting for select 398 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 P R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 index technique for VFS se | | |
| si_post 394 osi_sched 396 osi_selpost 398 osi_selpost 39 osi_selpost 398 osi_selpost 399 osi_sels 415 osi_sels 44 osi_sels | | • |
| osi_sched 396 osi_selpost 398 osi_signal 400 osi_sleep 402 osi_thread 405 osi_uiomove 410 osi_uuda 414 osi_wakt 415 osi_wakt 415 osi_wakt 415 osi_wakt 415 osi_wakt 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 mounting file systems 26 some operations not in this interface 14 vn_inactive not required for sockets 44 post aprocess in osi_wait 394 post a process in osi_wait 415 post a process in osi_wait 415 post a process i | | - |
| soi_selpost 398 osi_selpost 398 osi_signal 400 osi_sleep 402 osi_thread 405 osi_uiomove 410 osi_upda 414 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 soi_wakeup 410 soi_wakeup 419 post a process in osi_wait 394 post a process waiting for select 398 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | | |
| osi_signal 400 osi_sleep 402 osi_thread 405 osi_uomove 410 overouomove 410 osi_uomove 410 overouomove 410 osi_uomove 410 overouomove 410 overo | | some operations not in this interface 14 |
| osi_sleep 402 osi_thread 405 osi_uiomove 410 osi_upda 414 osi_upda 415 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 vnode structure 17 post a process in osi_wait 394 post a process waiting for select 398 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 R R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 index technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | | vn_inactive not required for sockets 44 |
| osi_thread 405 osi_uiomove 410 osi_upda 414 osi_wait 415 osi_wait 415 osi_wait 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 vnode structure 17 post a process in osi_wait 394 post a process in osi_wait select 398 posting an ECB 520 posting internal events 20 posting internal | | vnode not freed by PFS 29 |
| osi_uiomove 410 osi_upda 414 osi_uvait 415 osi_wait 415 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 post a process in osi_wait 394 post a process in osi_wait a 98 post a process in osi_valta 59 post a process in osi_valta 520 post a process in osieut 520 post a process in call 69 post a process in call 69 | - · · <u></u> | |
| osi_upda 414 osi_wait 415 osi_wait 415 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 post a process waiting for select 398 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 posting internal events 20 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 | | |
| osi_wait 415 osi_wakeup 419 OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 posting an ECB 520 posting internal events 20 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | | |
| OSIT (OSI operations vector table) 4 OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 privileges, appropriate 12, 241 process ID (PID) 19 process, registering as a server 321 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | | |
| OSIT operations vector table (OSIT) 4 output file attribute buffer address 19 P R parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | osi_wakeup 419 | |
| parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 R read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | OSIT (OSI operations vector table) 4 | |
| parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | | |
| parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | output file attribute buffer address 19 | process, registering as a server 321 |
| parm parameters 254 parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 read a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 reason code error text, pfsctl call 69 | _ | D. |
| parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | P | K |
| parmlib statements FILESYSTYPE 3 NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 a symbolic link 181, 319 directory entries 178 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | parm parameters 254 | |
| NETWORK 4, 43 path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 entries from a directory 315 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | parmlib statements | |
| path name symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 from a file 174, 311 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | FILESYSTYPE 3 | |
| symbolic link 348 pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 using multiple buffers 184 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | NETWORK <u>4</u> , <u>43</u> | |
| pathname resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 reading and writing with sockets 44 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | · | |
| resolution 27, 337 PFS abnormal ends 23 file protocols 25 initialization structure 6 reading directories cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 reason code error text, pfsctl call 69 | | |
| PFS cursor technique for VFS servers 250 index technique for VFS servers 250 with VFS servers 250 initialization structure 6 reason code error text, pfsctl call 69 | | |
| abnormal ends 23 index technique for VFS servers 250 with VFS servers 250 initialization structure 6 reason code error text, pfsctl call 69 | | |
| file protocols 25 with VFS servers 250 initialization structure 6 reason code error text, pfsctl call 69 | | |
| initialization structure 6 reason code error text, pfsctl call 69 | | • |
| | | |
| | milianzation structure o | |

| receive | set (continuea) |
|---------------------------------------------------|----------------------------------------------------|
| data from a socket 206 | socket options 224 |
| datagrams from a socket 221 | socket peer address 215 |
| messages from a socket 227 | share reservations 38 |
| recover | shared read support |
| resources after an abend 188 | specifying 22, 45 |
| resources at end-of-memory 94 | vn_close 133 |
| recovery | vn_open 170 |
| token area 19 | vn_rdwr 177 |
| vfs_recovery at end-of-memory 94 | vn_readwritev 187 |
| vn_recovery after an abend 188 | sharing files 18 |
| | |
| recycling a PFS 9 | shortcut keys 523 |
| reentrant code 453 | shut down a socket 218 |
| reentrant return linkage 461 | socket management PFS <u>14</u> |
| referring to files for the first time 31 | socket options 224 |
| register a process as a server <u>321</u> | sockets |
| registering with z/OS UNIX <u>245</u> | read and write operations <u>44</u> |
| release a vnode token <u>325</u> | select processing <u>45</u> |
| remove a directory 198, 334 | sending data to or receiving data from 206, 221 |
| remove a link to a file 191, 327 | sending messages to or receiving messages from 227 |
| rename a file or directory 194, 330 | SRB-mode callers 54 |
| resolve a pathname 27, 337 | SUBFILESYSTYPE statement 3 |
| restart option byte | summary of changes |
| | |
| address in the PFSI 7 | z/OS UNIX |
| restart options, PFS <u>11</u> | V2R3 xvii |
| return | z/OS UNIX System Services File System Interface |
| codes <u>254</u> | Reference <u>xvii</u> |
| file system status 268 | summary of physical file system operations 14 |
| unused vnodes 372 | supplementary GIDs, obtaining with osi_getcred 369 |
| return_value parameter for callable services 254 | symbolic link |
| ROOT statement 3 | creating 234 |
| _ | read a 319 |
| | to external name 348 |
| S | |
| | to pathname 348 |
| SAF auditing 121 | synchronizing file data 103 |
| SAF UIDs and GIDs, obtaining with osi_getcred 369 | syntax for callable services <u>253</u> |
| save file updates to disk 139 | system control |
| security fields in the ATTR structure 38 | offsets to callable services <u>423</u> |
| select on a vnode 201 | |
| select processing for sockets 45 | T |
| send | Т |
| | A a mara ima A i a m |
| data to a socket 206 | termination |
| datagrams to a socket <u>221</u> | ECB <u>5</u> |
| messages to a socket <u>227</u> | task <u>23</u> |
| sending to IBM | thread <u>23</u> |
| reader comments xv | termination considerations 10 |
| serializing | thread, colony 405 |
| directory reads 35 | time fields in the ATTR structure 38 |
| file creation 30 | time_t data type 67 |
| file deletion 31 | token 33 |
| file system mounts 27 | Token_structure parameter 16 |
| | |
| getting and setting attributes 37 | transport driver (TD) 47 |
| inode creation 30 | transport provider (TP) <u>47</u> |
| LFS-PFS control blocks <u>22</u> | truncate a file <u>237</u> |
| reads and writes <u>35</u> | |
| socket read and write operations 45 | U |
| vn_getattr 37 | |
| vn_open and vn_close 32 | UIDs, obtaining with osi_getcred 369 |
| vn_readdir 35 | |
| vn_setattr 37 | UIO structure 34 |
| set | unmounting file systems |
| | LFS processing <u>28</u> |
| attributes 37 | PFS processing <u>28</u> |
| attributes for VFS servers <u>251</u> | unmounting VFS servers 245 |
| file attributes 210, 341 | |

| user interface | vfs_batsel 74 | |
|-------------------------------------------------|----------------------------------|--|
| ISPF 523 | vfs_get 108 | |
| TSO/E 523 | vfs_gethost 78 | |
| user process termination 23 | vfs_getHest <u>70</u> | |
| user process termination 25 | – | |
| | implementation 29, 32 | |
| V | vfs_mount 84 | |
| | vfs_network <u>88</u> | |
| v_ functions 243 | vfs_pfsctl <u>91</u> | |
| v access 255 | vfs_recovery <u>94</u> | |
| v_close 257 | vfs_socket 97 | |
| v create | vfs_statfs 100 | |
| example 453 | vfs_sync 103 | |
| v export 264 | vfs_unmount 105 | |
| - _ · · · | VFS-MNT pair 17 | |
| v_fstatfs | VFS-vnode vector tables 16 | |
| example <u>454</u> | vn_accept 111 | |
| v_get | vn_access 114 | |
| example <u>454</u> | - | |
| v_getattr | vn_anr <u>116</u> | |
| example <u>454</u> | vn_audit <u>121</u> | |
| v_ioctl | vn_bind <u>123</u> | |
| example 455 | vn_cancel <u>126</u> | |
| v_link | vn_close | |
| example 455 | implementation 32 | |
| v_lockctl | vn_connect <u>133</u> | |
| example 455 | vn_create | |
| v lookup | implementation 29, 31 | |
| example 456 | vn_fsync 139 | |
| v_mkdir | vn_getattr | |
| | implementation 37 | |
| example 456 | vn_getname 144 | |
| v_open 301 | vn_inactive | |
| v_pathconf | implementation 29, 32 | |
| example <u>457</u> | integrity of vnode-inode pair 18 | |
| v_rdwr | vn ioctl 149 | |
| example <u>457</u> | | |
| v_readdir | vn_link <u>152</u> | |
| example <u>458</u> | vn_listen <u>156</u> | |
| v_readlink | vn_lockctl <u>158</u> | |
| example <u>458</u> | vn_lookup | |
| v_reg | implementation 29 | |
| example 458 | vn_mkdir | |
| v_reg() | implementation <u>29, 31</u> | |
| implementation 245 | vn_open | |
| v rel | access checking 32 | |
| example 459 | implementation 32 | |
| v_remove | vn_pathconf 171 | |
| example 459 | vn_rdwr | |
| · | implementation 34 | |
| v_rename | vn_readdir | |
| example <u>459</u> | implementation 35 | |
| v_rmdir | vn_readlink 181 | |
| example <u>460</u> | vn_readwritev | |
| v_rpn | – | |
| example <u>460</u> | implementation 34 | |
| v_setattr | vn_recovery 188 | |
| example 460 | vn_remove <u>191</u> | |
| v_symlink | vn_rename <u>194</u> | |
| example 461 | vn_rmdir <u>198</u> | |
| VFS VFS | vn_select | |
| callable services API functions 243 | implementation 43 | |
| operation vector table, PFSI address 7 | vn_select(Cancel) 46 | |
| operations vector table, 11 of address <u>7</u> | vn_select(Query) 46 | |
| VFS server interface | vn_sendtorcvfm 206 | |
| compared to PFS interface 251 | vn_setattr | |
| | implementation 37 | |
| considerations for 64-bit addressing 242 | vn_setpeer 215 | |
| installation considerations 241 | ***_00:p001 2±0 | |

vn_shutdown 218 vn_sockopt 224 vn_srmsg 227 vn_symlink 234 vn_trunc 237 vnode operations vector table address in the PFSI 7 vnode token, releasing 325 vnode-inode pair 18 vnodes creating 29 getting 372 referring to 29 wait for a resource 402, 419 for an event 415 for internal events 20 wait for an ECB posting 520 write to a file 311 using multiple buffers 184 Z z/OS UNIX summary of changes for V2R3 xvii z/OS UNIX System Services File System Interface Reference

> content, changed <u>xvii</u> summary of changes xvii

IBW.

Product Number: 5650-ZOS

SA23-2285-50

