Lecture 7: Closures

Barinov Denis

March 21, 2023

barinov.diu@gmail.com

You've already seen closures in homeworks and lectures:

```
let x = 4;
let equal_to_x = |z| z == x;
let y = 4;
assert!(equal_to_x(y));
```

Question: What's the difference between the closures and the functions?

You've already seen closures in homeworks and lectures:

```
let x = 4;
let equal_to_x = |z| z == x;
let y = 4;
assert!(equal_to_x(y));
```

Question: What's the difference between the closures and the functions?

A closure is an *anonymous function* that can directly *use variables from the scope* in which it is defined.

Unlike functions, closures infer input and output types since it's more convenient most of the time.

```
let option = Some(2);
let x = 3:
// explicit types:
let new: Option<i32> = option.map(|val: i32| -> i32 {
    val + x
});
println!("{:?}", new); // Some(5)
let y = 10;
// inferred:
let new2 = option.map(|val| val * y);
println!("{:?}", new2); // Some(20)
```

Let's try to duplicate Option::map functionality with handcrafted function.

```
fn map<X, Y>(option: Option<X>, transform: ...) -> Option<Y> {
    match option {
        Some(x) => Some(transform(x)),
        None => None,
    }
}
```

We need to fill in the ... with something that transforms an X into a Y. What it will be?

We want transform to be the callable object. In Rust, when we want to abstract over some property, we use traits!

```
fn map<X, Y, T>(option: Option<X>, transform: T) -> Option<Y> where T: /* the trait */ { ... }
```

Let's design it.

We want transform to be the callable object. In Rust, when we want to abstract over some property, we use traits!

```
fn map<X, Y, T>(option: Option<X>, transform: T) -> Option<Y>
   where T: /* the trait */ { ... }
```

Let's design it.

• Idea: compiler generated structure that implements some trait.

We want transform to be the callable object. In Rust, when we want to abstract over some property, we use traits!

```
fn map<X, Y, T>(option: Option<X>, transform: T) -> Option<Y>
   where T: /* the trait */ { ... }
```

Let's design it.

- Idea: compiler generated structure that implements some trait.
- Our trait will have only one function.

We want transform to be the callable object. In Rust, when we want to abstract over some property, we use traits!

```
fn map<X, Y, T>(option: Option<X>, transform: T) -> Option<Y>
   where T: /* the trait */ { ... }
```

Let's design it.

- Idea: compiler generated structure that implements some trait.
- Our trait will have only one function.
- We'll use tuple as input type since we don't have variadics in Rust (and we don't actually need them, at least in this case).

```
trait Transform<Input> {
        type Output;
        fn transform(/* self */, input: Input) -> Self::Output;
    }
Question: Do we need self, &mut self or &self here?
```

```
trait Transform<Input> {
    type Output;
    fn transform(/* self */, input: Input) -> Self::Output;
}
```

Question: Do we need self, &mut self or &self here?

Since the transformation should be able to incorporate arbitrary information beyond what is contained in Input. Without any self argument, the method would look like fn transform(input: Input) -> Self::Output and the operation could only depend on Input and global variables.

Question: What do we need exactly: self, &mut self or &self?

 $\label{eq:Question: What do we need exactly: self, &mut self or \&self?}$

	User
self	Can only call method once
&mut self	Can call many times, only with unique access
&self	Can call many times, with no restrictions

Question: What do we need exactly: self, &mut self or &self?

	User
self	Can only call method once
&mut self	Can call many times, only with unique access
&self	Can call many times, with no restrictions

We usually want to choose the highest row of the table that still allows the consumers to do what they need to do.

Let's start with self. In summary, our map and its trait look like:

```
trait Transform<Input> {
    type Output;
    fn transform(self, input: Input) -> Self::Output;
}
fn map<X, Y, T>(option: Option<X>, transform: T) -> Option<Y>
    where T: Transform<X, Output = Y>
{
    match option {
        Some(x) \Rightarrow Some(transform.transform(x)),
        None => None,
```

Rust uses Fn, FnMut, FnOnce traits to unify functions and closures, similar to what we've invented.

```
pub trait FnOnce<Args> {
    type Output;
    fn call_once(self, args: Args) -> Self::Output;
}
pub trait FnMut<Args>: FnOnce<Args> {
    fn call_mut(&mut self, args: Args) -> Self::Output;
}
pub trait Fn<Args>: FnMut<Args> {
    fn call(&self, args: Args) -> Self::Output;
}
```

Rust uses Fn, FnMut, FnOnce traits to unify functions and closures, similar to what we've invented.

```
pub trait FnOnce<Args> {
   type Output;
   fn call_once(self, args: Args) -> Self::Output;
}
pub trait FnMut<Args>: FnOnce<Args> {
   fn call_mut(&mut self, args: Args) -> Self::Output;
}
pub trait Fn<Args>: FnMut<Args> {
   fn call(&self, args: Args) -> Self::Output;
}
```

Look carefuly as self. Every FnMut closure can implement FnOnce exactly the same way! Same applies to Fn and FnMut.

The real map looks like this:

```
impl<T> Option<T> {
    pub fn map<U, F>(self, f: F) -> Option<U>
    where
         F: FnOnce(T) \rightarrow U,
         match self {
             Some(x) \Rightarrow Some(f(x)),
             None => None
```

FnOnce(T) -> U is another name for our Transform<X, Output = Y> bound, and f(x) for transform.transform(x).

Returning and accepting closures

Since the closure is a compiler-generated type, it's **non-denotable**, i.e you cannot write its exact type.

```
fn return_closure() -> impl Fn() {
        || println!("hello world!")
    }
Fn, FnMut, FnOnce are traits, and we can benefit from trait objects here too!
    let c1 = || {
        println!("calculating...");
        42 * 2 - 22
    };
    let c2 = || 42;
    let vec: Vec < \&dyn Fn() -> i32 > = vec! [\&c1, \&c2];
    for elem in vec { println!("{}", elem()); }
```

Basically any funtions also implement these traits!

```
fn cast(x: i32) -> i64 {
    (x + 1) as i64
fn func(f: impl FnOnce(i32) -> i64) {
    println!("f(42) = {}", f(42));
fn main() {
    func(cast)
```

So, like everything in Rust, operator () is defined by traits

There's also *function pointers* in Rust. It's not a trait, it's an actual *type* that refers to the code, not data. Unlike closures, they cannot capture the environment.

```
fn add one(x: usize) \rightarrow usize { x + 1 }
let ptr: fn(usize) -> usize = add_one;
assert_eq!(ptr(5), 6);
let clos: fn(usize) \rightarrow usize = |x| x + 5;
assert_eq!(clos(5), 10);
// error: mismatched types
// let y = 2;
// let clos: fn(usize) \rightarrow usize = |x| y + x + 5;
// assert_eq!(clos(5), 10);
```

Let's find out how Rust closures decide how to capture the variables.

```
struct T { ... }

fn by_value(_: T) {}
fn by_mut(_: &mut T) {}
fn by_ref(_: &T) {}
```

```
let x: T = \ldots;
let mut y: T = \ldots;
let mut z: T = \ldots;
let closure = || {
    by_ref(&x);
    by_ref(&y);
    by_ref(&z);
    // Forces `y` and `z` to be at least
    // captured by `&mut` reference
    by_mut(&mut y);
    by_mut(&mut z);
    // Forces `z` to be captured by value
    by_value(z);
};
```

This is how closure environment will look like:

```
struct Environment<'x, 'y> {
   x: &'x T,
   y: &'y mut T,
   z: T
/* impl of FnOnce for Environment */
let closure = Environment {
   x: &x,
   y: &mut y,
    z: z,
};
```

Since this closure implements FnOnce, it cannot be called twice:

```
// Ok
closure();
// error: moved due to previous call
// closure();
```

What if you need to move out a closure from the scope? In this case, you need to move all the variables even if it's enough to have a shared reference.

```
// Returns a function that adds a fixed number
// to the argument. Reminds of Higher Order Functions
// from functional programming!
fn make_adder(x: i32) -> impl Fn(i32) -> i32 {
    |y| x + y
fn main() {
    let f = make_adder(3);
    println!("{}", f(1));
    println!("{}", f(10));
```

```
error[E0597]: `x` does not live long enough
 --> src/main.rs:2:9
2 \mid |y| \times y
        --- ^ borrowed value does not live long enough
        value captured here
  | `x` dropped here while still borrowed
     borrow later used here
```

Let's use move keyword to tell Rust we need to capture by value:

```
fn make_adder(x: i32) -> impl Fn(i32) -> i32 {
    // Compiles just fine!
    move |y| x + y
fn main() {
    let f = make_adder(3);
    println!("{}", f(1)); // 4
    println!("{}", f(10)); // 13
```

Going back to previous example, the closure with move keyword will capture all variables by value:

```
let closure = move || {
    by_ref(&x);
    by_ref(&y);
    by_ref(&z);
    // Forces `y` and `z` to be at least
    // captured by `&mut` reference
    by_mut(&mut y);
    by_mut(&mut z);
    // Forces `z` to be captured by value
    by_value(z);
};
```

```
struct Environment {
    x: T,
    y: T,
    z: T,
}
```

In Rust, there are no fine-grained capture lists like in C++11. But do we need it? In practice, we don't (at least the lecturer doesn't know good examples).

Closure type

Every closure have **distinct type**. This implies that in this example id0, id1, id2 and id3 have **different types**.

```
fn id0(x: u64) \rightarrow u64 \{ x \}
    fn id1(x: u64) \rightarrow u64 \{ x \}
    fn main() {
        let id2 = || 1:
        let id3 = || 1;
And this code won't compile:
    fn make_closure(n: u64) -> impl Fn() -> u64 {
        move || n
    }
    vec![make_closure(1), make_closure(2)];
    vec![(|| 1), (|| 1)]; // Error: mismatched types
```

Closures and optimizations

• We create a structure for the closure, do some moves... It must be expensive!

Closures and optimizations

- We create a structure for the closure, do some moves... It must be expensive!
- Actually, the compiler knows a lot about our code and optimizes it with ease.

 Most closure calls are inlined and in binary is the same as code without closure.

Closures and optimizations

- We create a structure for the closure, do some moves... It must be expensive!
- Actually, the compiler knows a lot about our code and optimizes it with ease.
 Most closure calls are inlined and in binary is the same as code without closure.
- Zero cost abstraction!

Questions?

