Lecture 4: Rewind

Barinov Denis

March 7, 2023

barinov.diu@gmail.com

String and &str

$String^1$

A Rust way to store a string.

¹String documentation

String¹

A Rust way to store a string.

• It's UTF-8-encoded.

¹String documentation

$String^1$

A Rust way to store a string.

- It's UTF-8-encoded.
- Growable like a Vec. It also made up of three components: a pointer to some bytes, a length, and a capacity. This even gives us many functions same to Vec.

¹String documentation

String¹

A Rust way to store a string.

- It's UTF-8-encoded.
- Growable like a Vec. It also made up of three components: a pointer to some bytes, a length, and a capacity. This even gives us many functions same to Vec.
- UTF-8 is a variable-width character encoding, so you cannot index it since it's UTF-8. To find N-th symbol, you should iterate over string, parsing code points.

¹String documentation

String API

```
struct String {
   vec: Vec<u8>,
}
impl String {
   fn new() -> String;
   fn with_capacity(capacity: usize) -> String;
   fn from_utf8(vec: Vec<u8>) -> Result<String, FromUtf8Error>;
   fn from_utf16(v: &[u16]) -> Result<String, FromUtf16Error>;
   fn into_bytes(self) -> Vec<u8>;
   fn as_bytes(&self) -> &[u8];
}
```

String in depth

What will this code print?

```
let s = String::from(""); // hello
println!("{}", s.len());
```

String in depth

What will this code print?

```
let s = String::from(""); // hello
println!("{}", s.len());
```

This outputs 12, since .len() gives count of *bytes* in string.

char type

```
let mut chars = "é".chars();
// U+00e9: 'latin small letter e with acute'
assert_eq!(Some('\u{00e9}'), chars.next());
assert_eq!(None, chars.next());
let mut chars = "é".chars();
// U+0065: 'latin small letter e'
assert_eq!(Some('\setminus u\{0065\}'), chars.next());
// U+0301: 'combining acute accent'
assert_eq!(Some('\u{0301}'), chars.next());
assert_eq!(None, chars.next());
```

char type

The size of char is always 4 bytes:

```
{\tt assert\_eq!} \, ({\tt std::mem::size\_of::<char>()} \,, \  \, 4) \,;
```

&str

&str is a slice type of String, similar to std::string_view. Just like:

```
let vec = vec![1, 2, 3, 4];
let vec_slice = &vec[1..3]; // &[2, 3]
let s = String::from("hello");
let s_slice = &s[1..3]; // "el"
```

&str

Ok, let's take a UTF-8 slice!

```
let s = String::from(""); // hello
let s_slice = &s[1..3];
```

Ok, let's take a UTF-8 slice!

```
let s = String::from(""); // hello
let s_slice = &s[1..3];
// thread 'main' panicked at 'byte index 1 is
// not a char boundary; it is inside '' // h
// (bytes 0..2) of ``' // hello
```

Ok, let's take a UTF-8 slice!

```
let s = String::from(""); // hello
let s_slice = &s[1..3];
// thread 'main' panicked at 'byte index 1 is
// not a char boundary; it is inside '' // h
// (bytes 0..2) of ``' // hello
```

That means &str also have a UTF-8 invariant checked at runtime.

&str

As a string slice, &str have most functions String have:

```
fn as_bytes(&self) -> &[u8];
fn chars(&self) -> Chars<'_>;
fn trim(&self) -> &str;
// And so on
```

&str

All string constants are &str.

```
let s: &str = "Hello world!";
let t1 = s.to_string();
let t2 = s.to_owned(); // The same as t1
let t3 = String::from(s); // The same as t1
```

Box and Rc

We are already familiar with Box type. Let's check one advanced function:

```
fn leak<'a>(b: Box<T, A>) -> &'a mut T;
fn into_raw(b: Box<T, A>) -> *mut T;

Example:

let x = Box::new(41);
let static_ref: &'static mut usize = Box::leak(x);
    *static_ref += 1;
    assert_eq!(*static_ref, 42);
```

Box

But stop! Rust is the safe language, no memory unsafety, no undefined behavior, what's wrong!?

Box

But stop! Rust is the safe language, no memory unsafety, no undefined behavior, what's wrong!?

In reality, when you're creating global objects or interacting with other languages, you have to leak objects. Moreover, it's safe to leak memory, just not good!

Rc is single-threaded reference-counting pointer. "Rc" stands for "Reference Counted".

```
let rc = Rc::new(());
let rc2 = rc.clone(); // Clones Rc, not what inside!
let rc3 = Rc::clone(&rc); // The same
```

Rc is dropped when all instances of Rc are dropped.

Primary functions:

```
fn get_mut(this: &mut Rc<T>) -> Option<&mut T>;
fn downgrade(this: &Rc<T>) -> Weak<T>;
fn weak_count(this: &Rc<T>) -> usize;
fn strong_count(this: &Rc<T>) -> usize;
```

References to the variable inside Rc are controlled at runtime:

pointer. If there are more, you won't have a chance to modify Rc.

```
let mut rc = Rc::new(42);
    println!("{}", *rc);
    *Rc::get_mut(&mut rc).unwrap() -= 41;
    println!("{}", *rc);
    let mut rc1 = rc.clone():
    println!("{}", *rc1);
    // thread 'main' panicked at 'called `Option::unwrap()`
    // on a `None` value'
    // *Rc::get_mut(&mut rc1).unwrap() -= 1;
get_mut guarantees that it will return mutable reference only if there's only one
```

19

Weak

Rc is a **strong** pointer, while Weak is a **weak** pointer. Both of them have *ownership* over allocation, but only Rc have *ownership* over the value inside:

You can upgrade Weak to Rc:

```
fn upgrade(&self) -> Option<Rc<T>>;
```

```
let rc1 = Rc::new(String::from("string"));
let rc2 = rc1.clone();
let weak1 = Rc::downgrade(&rc1);
let weak2 = Rc::downgrade(&rc1);
drop(rc1); // The string is not deallocated
assert!(weak1.upgrade().is_some());
drop(weak1); // Nothing happens
drop(rc2); // The string is deallocated
assert_eq!(weak2.strong_count(), 0);
// If no strong pointers remain, this will return zero.
assert_eq!(weak2.weak_count(), 0);
assert!(weak2.upgrade().is_none());
drop(weak2); // The Rc is deallocated
```

Questions?

