


HOW TO RUN ASDM OVER ASA USING GNS3

Prerequisites


- 1 ASDM image (*.bin)
- 2 TFTP /FTP application (you can download it free from solarwind)
- 3 ASA kernel and initrd files
- 4 GNS3

Diagram



Note I used Router as a switch with Fast Ethernet interfaces (used NM-16ESW),

Step 1 **Load ASA IOS as show below** (for more details see [ASA using GNS3 how to](#) separate document uploaded)



Step 1 (assign IP and name to interface)

```
ciscoasa(config)# int e0/0
ciscoasa(config-if)# nameif inside
ciscoasa(config-if)# ip address 10.10.10.1 255.255.255.0
```


Step 2 (enable http server and allow access from inside)

```
ciscoasa(config)# http server enable
ciscoasa(config)# http 10.10.10.2 255.255.255.0 inside
ciscoasa(config-if)# management-access inside
```

Step 3 (create an user to access through ASDM)

```
ciscoasa(config)# username ismail password ismail1 privilege 3
```

Note: user must have to assign this user above level 2 rights otherwise not works gives you an error message like this



Step 3 (upload ASDM to ASA using TFTP Server)

i PC Activity


Run TFTP Server → Copy ASDM in to TFTP Server Root directoy

ii Copy ASDM file to ASA Flash

```
ciscoasa# copy tftp: flash
Address or name of remote host []? 10.10.10.2
Source filename []? asdm-625.bin
Destination filename [asdm-625.bin]?
Accessing tftp://10.10.10.2/asdm-
625.bin...!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
Writing current ASDM file disk0:/asdm-625.bin
!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
!!!!!!!!!!!!!!
!!!!!!!!!!!!!!
11862220 bytes copied in 58.730 secs (204521 bytes/sec)
Note: must verify files copied successfully or not (view highlighted points)
```

iii PC Activity



Open Explorer and type (<https://> ip address of inside interface you assigned)





In my example I used <https://10.10.10.1/> (first screen will be like this) You can run any of these three options

Note: Alternatively if you have their installation package for windows you can do it from there too


ASDM installation





Launching ASDM

Run ASDM shortcut from desktop and follow below GUI Guide



Popup for Certificate verification (use always trust to avoid future pop up)



May popup for upgrade if you ASA have latest ASDM as compared to windows installed,

If popup press **yes**



=====

Summary steps (for ASDM)

- 1 Upload ASDM Image to ASA using TFTP
- 2 Enabled http services and specified allowed pc used for
- 3 Created user for authentication to access using ASA (user must be having rights access level above 2)

=====

Used for this lab

- 1 Windows 7 (32 bit)
- 2 GNS3 (0.7.4)
- 3 ASA 8.02 (**asa802-k8.initrd.gz** and **asa802-k8.kernel**)
- 4 ASDM 625.bin
- 5 Solar wind TFTP Server