## 1 Implicit Methods

The methods we've used so far to solve partial differential equations are called *explicit* methods. These methods have several disadvantages, especially with stability. In addition, explicit methods have low accuracy in time, being order  $O(\Delta t)$ , and so small time steps are required. This then means many more steps are required.

An alternative approach to solving PDEs numerically exist. These types of methods are called *implicit methods*. We introduce as simple implicit scheme here using the heat equation as a specific example.

The 1-D heat equation is (note, we are not assuming the steady state here)

$$u_t = k u_{xx} \tag{1}$$

where k is the heat conductivity. We use the notation

$$u(x_i, t_m) \equiv u_i^m$$
.

Discretizing the partials gives

$$u_{xx} \approx \frac{u_{i+1}^{m+1} - 2u_i^{m+1} + u_{i-1}^{m+1}}{h_x^2}$$
 $u_t \approx \frac{u_i^{m+1} - u_i^m}{\delta_t}$ 

The term  $h_x$  is the grid spacing in space and  $\delta_t$  the spacing in time. Notice the spatial derivatives all have terms occurring at the same time m+1, and at neighboring positions, while the time derivative occurs at the same spatial point, i, but at neighboring time steps.

Adding the R.H.S yields,

$$-\lambda u_{i-1}^{m+1} + (1+2\lambda)u_i^{m+1} - \lambda u_{i+1}^{m+1} = u_i^m \text{ where } \lambda = k \frac{\delta_t}{h_x^2}.$$
 (2)

In order to apply Eq.(2) two things are required,

• Initial conditions for the case m=0. That is, we need  $u_i^0$  for all i.

• Boundary conditions at i = 0, i = N - 1 for all times m.

Implicit schemes like the one outlined in Eq.(2) are unconditionally stable. Because this scheme is order  $\delta_t^2$  accurate, one can take fewer time steps. However, the calculations become more difficult when dealing with 2 and 3-D problems.

(1) You will apply Eq.(2) to a 1-D bar with a total four interior spatial points and four time points. The left boundary is set to  $100^{\circ}$ C and the right boundary is set to  $50^{\circ}$ C. The temperature is 0 at all other points at t = 0 (m = 0). Using  $\lambda = 0.4$ , write Eq.(2) with i = 1, putting all unknown quantities on the L.H.S. and known quantities on the R.H.S. What interior points are located on the L.H.S.?

(2) Do the same for the interior points i = 2 and i = 3, again, at time step t = 0 (m = 0).

(3) And finally repeat step (1) at the right boundary, (i = 4).

Parts (1) - (3) above develop a simple implicit scheme. The more usual approach in using implicit methods is a scheme called *Crank-Nicolson* method.

Essentially Eq.(2) is replaced with second order in accuracy in both space and time. The central differencing is now

$$u_{xx} = \frac{1}{2} \left[ \frac{u_{i-1}^m - 2u_i^m + u_{i+1}^m}{h_x^2} + \frac{u_{i-1}^{m+1} - 2u_i^{m+1} + u_{i+1}^{m+1}}{h_x^2} \right]$$
(3)

$$u_{tt} = \frac{u_i^{m+1} - u_i^m}{\delta_t} \tag{4}$$

Substituting these into the heat equation yields,

$$-\lambda u_{i-1}^{m+1} + 2(1+\lambda)u_i^{m+1} - \lambda_{i+1}^{m+1} = \lambda u_{i-1}^m + 2(1+\lambda)u_i^m - \lambda_{i+1}^m$$
 (5)

Putting these equations in matrix form, we again get a tridiagonal matrix of the form

$$\begin{pmatrix} 2+2\lambda & -\lambda & 0 & \cdots & 0 \\ -\lambda & 2+2\lambda & -\lambda & \dots & 0 \\ 0 & \vdots & \vdots & \vdots & & \\ 0 & \vdots & -\lambda & 2+2\lambda & -\lambda \\ 0 & \dots & 0 & -\lambda & 2+2\lambda \end{pmatrix} \begin{pmatrix} u_1^{m+1} \\ u_2^{m+1} \\ \vdots \\ \vdots \\ u_{N-1}^{m+1} \end{pmatrix} = \begin{pmatrix} \lambda u_o^m + (2-2\lambda)u_1^m + \lambda u_2^m + \lambda u_o^{m+1} \\ \lambda u_1^m + (2-2\lambda)u_2^m + \lambda u_3^m \\ \vdots \\ \lambda u_{N-2}^m + (2-2\lambda)u_{N-1}^m + \lambda_N^m + \lambda u_N^{m+1} \end{pmatrix}$$

$$(6)$$

On the right hand side, the terms  $u_o^m, u_0^{m+1}, u_N^m, u_N^{m+1}$  are all given by the initial and boundary conditions.

- 4. Discuss in your room how Eq.(6) works and/or what it means.
- 5. Download the files MyCN.m and trisolve.m Teams course page. Make sure you understand how or if the code works. Run the code as is. Then change the initial condition to  $u(x,0) = \sin(\pi * x/L)$  where L is the length of the bar. Plot the temperature as a function of time. Does your solution reach the steady state quickly?