# Module Interface Specification for Digital Twin Forest

Team 8, Forest Mirror
Tingyu Shi
Jiacheng Wu
Junhong Chen
Yichen Jiang
Bowen Zhang

April 4, 2023

# 1 Revision History

Date	Version	Notes
Jan 14	1.0	First Version

# 2 Symbols, Abbreviations and Acronyms

See SRS Documentation at here.

symbol	description
AC	Anticipated Change
DAG	Directed Acyclic Graph
DBH	Diameter at breast height
FR	Functional Requirement
GUI	Graphical User Interface
LAI	Leaf Area Index
M	Module
MG	Module Guide
MVC	Model, Viewer, Controller
NFR	Non-Functional Requirement
OS	Operating System
R	Requirement
SC	Scientific Computing
SRS	Software Requirements Specification
UC	Unlikely Change

## Contents

1	Rev	vision 1	History	i
2	Syn	nbols,	Abbreviations and Acronyms	ii
3	Intr	oducti	ion	1
4	Not	ation		1
5	Mo	dule D	Decomposition	2
6	MIS	S of Js	son File Reader (M1)	7
	6.1		ule	
	6.2			
	6.3		<u>IX</u>	
		6.3.1	Exported Constants	
		6.3.2	Exported Access Programs	
	6.4		ntics	
	0.1	6.4.1	State Variables	
		6.4.2	Environment Variables	
		6.4.3	Assumptions	
		6.4.4	Access Routine Semantics	
		6.4.5	Local Functions	
7	MIS	S of Js	son File Writer (M2)	10
•	7.1		de	
	7.2			
	7.3		X	
		7.3.1	Exported Constants	
		7.3.2	Exported Access Programs	
	7.4		ntics	
		7.4.1	State Variables	
		7.4.2	Environment Variables	
		7.4.3	Assumptions	
		7.4.4	Access Routine Semantics	
		7.4.5	Local Functions	
8	MIS	S of Pa	ause Manager (M3)	13
_	8.1		ile	
	8.2			
	8.3		X	
	0.0	8.3.1	Exported Constants	
			Exported Access Programs	. 13

	8.4	Seman	tics													13
		8.4.1	State Variables													13
		8.4.2	Environment Variables													13
		8.4.3	Assumptions													13
		8.4.4	Access Routine Semantics													13
		8.4.5	Local Functions													14
9	MIS	of Pla	ayer Movement(M4)													15
	9.1	Module	e													15
	9.2	Uses .														15
	9.3	Syntax														15
		9.3.1	Exported Constants													15
		9.3.2	Exported Access Programs													15
	9.4	Seman	tics													15
		9.4.1	State Variables													15
		9.4.2	Environment Variables													15
		9.4.3	Assumptions													15
		9.4.4	Access Routine Semantics													15
		9.4.5	Local Functions													15
10	MIS	of Ne	w Data Input Box Cont	rol	ler	· (	$\mathbf{M}$	<b>5</b> )								16
			e			•										16
																16
	10.3	Syntax	[													16
		10.3.1	Exported Constants													16
		10.3.2	Exported Access Programs													16
	10.4		$\operatorname{tics}$													16
			State Variables													16
		10.4.2	Environment Variables													16
		10.4.3	Assumptions													16
			Access Routine Semantics													16
			Local Functions													16
11	MIS	of Sta	art Button Controller (M	<b>[6</b> )												17
																17
		Modul	e													т,
			e 													17
	11.2	Uses .														17
	11.2	Uses . Syntax							 							
	11.2	Uses . Syntax 11.3.1	Exported Constants					•	  		· ·		  	 	 	 17 17
	11.2 11.3	Uses Syntax 11.3.1 11.3.2	Exported Constants Exported Access Programs						 	 		 	 	 	 	 17 17 17
	11.2 11.3	Uses Syntax 11.3.1 11.3.2 Seman	Exported Constants  Exported Access Programs tics						 	 		 	 	 	 	17 17 17 17
	11.2 11.3	Uses Syntax 11.3.1 11.3.2 Seman 11.4.1	Exported Constants Exported Access Programs						 	 		 	 	 	 	 17 17 17 17 17

		ccess Routine Semantic									17
	11.4.5 L	ocal Functions				 	 	 	 	•	18
12 MIS	S of Instr	ruction Button Cont	roller	(M7	7)					-	19
					*						19
											19
											19
12.5	•	xported Constants									19
		*									19
19.4		xported Access Program									
12.4		S									19
		tate Variables									19
		nvironment Variables .									19
		ssumptions									19
		ccess Routine Semantic									19
	12.4.5 L	ocal Functions				 	 	 	 	•	20
13 MIS	of Und	ate Data Button Co	ntroll	or (N	<b>/</b> [8]					6	21
	_										21
											21
											ر ے 21
10.0	•	xported Constants									ر ہے 21
		xported Constants xported Access Program									دء 21
19 /		s									دء 21
15.4											21 21
		tate Variables									
		nvironment Variables .									21
		ssumptions									21
		ccess Routine Semantic									$\frac{2}{2}$
	13.4.5 L	ocal Functions				 	 	 	 		22
14 MIS	of Cont	act Us Button Cont	roller	(M	9)					6	23
	TTana										23
											23
11.0	•	xported Constants									 23
		xported Access Program									23
14.4		S									23
14.4		tate Variables									23
		nvironment Variables									23 23
		ssumptions									$\frac{23}{23}$
		ccess Routine Semantic									23
	14.4.5 L	$ocal Functions \dots \dots$				 	 	 	 		24

<b>15</b>	MIS of Quit Button Controller (M10)	25
	15.1 Module	25
	15.2 Uses	25
	15.3 Syntax	25
	15.3.1 Exported Constants	25
	15.3.2 Exported Access Programs	25
	15.4 Semantics	25
	15.4.1 State Variables	25
		25
	15.4.3 Assumptions	25
	•	25
		26
<b>16</b>	MIS of Back Button Controller (M11)	27
		27
	16.2 Uses	27
		27
	·	27
	•	27
		27
	16.4.1 State Variables	27
	16.4.2 Environment Variables	27
		27
	16.4.4 Access Routine Semantics	27
	16.4.5 Local Functions	28
<b>17</b>	MIS of Plot Selection Drop Down Controller (M12)	29
		29
	17.2 Uses	29
	17.3 Syntax	29
	17.3.1 Exported Constants	29
	17.3.2 Exported Access Programs	29
		29
	17.4.1 State Variables	29
	17.4.2 Environment Variables	29
	17.4.3 Assumptions	30
	17.4.4 Access Routine Semantics	30
	17.4.5 Local Functions	30
18	MIS of Tree Type Selection Drop Down Controller(M13)	31
		31
		31
		31

18.3.1 Exported Constants	
18.3.2 Exported Access Programs	
18.4 Semantics	
18.4.1 State Variables	
18.4.2 Environment Variables	
18.4.3 Assumptions	
18.4.4 Access Routine Semantics	
18.4.5 Local Functions	
Torrio Bootti i dicololis I I I I I I I I I I I I I I I I I I I	
19 MIS of Show Environmental Data Button	Controller (M14) 33
19.1 Module	
19.2 Uses	
19.3 Syntax	
19.3.1 Exported Constants	
19.3.2 Exported Access Programs	
19.4 Semantics	
19.4.1 State Variables	
19.4.2 Environment Variables	
19.4.3 Assumptions	
19.4.4 Access Routine Semantics	
	34
19.4.5 Local Functions	troller(M15) 35
20 MIS of Show Tree Parameter Button Con	
20 MIS of Show Tree Parameter Button Con 20.1 Module	
20 MIS of Show Tree Parameter Button Con 20.1 Module	
20 MIS of Show Tree Parameter Button Con         20.1 Module	35
20 MIS of Show Tree Parameter Button Con 20.1 Module	
20 MIS of Show Tree Parameter Button Con         20.1 Module	
20 MIS of Show Tree Parameter Button Con 20.1 Module	35 
20 MIS of Show Tree Parameter Button Con         20.1 Module	35         35         35         35         35         35         35
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables	35 
20 MIS of Show Tree Parameter Button Con         20.1 Module	35         35         35         35         35         35         35         35         35         35         35         35         35         35         36         37         38         39         31         32         35
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics	35         35         35         35         35         35         35         35         35         35         35         35         35         35
20 MIS of Show Tree Parameter Button Con         20.1 Module	35         35         35         35         35         35         35         36         37         38         38         38         38         38         38         38
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions	35         35         35         35         35         35         36         37         38         39         36         36         36         36         36
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions	35
20 MIS of Show Tree Parameter Button Con 20.1 Module	35         35         35         35         35         35         35         36         37         37         37         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions          21 MIS of Environmental Selection Button C       21.1 Module         21.2 Uses	35         35         35         35         35         35         35         36         37         37         38         39         31         32         33         34         35         36         37         38         39         31         32         33         34         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33         34
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions          21 MIS of Environmental Selection Button C          21.1 Module          21.2 Uses          21.3 Syntax	35         35         35         35         35         35         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         31         32         33         34         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33         34         35         36         37         38         39         30         31         32         33         34
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions          21 MIS of Environmental Selection Button Constants          21.3 Syntax          21.3 Syntax          21.3.1 Exported Constants	
20 MIS of Show Tree Parameter Button Con         20.1 Module          20.2 Uses          20.3 Syntax          20.3.1 Exported Constants          20.3.2 Exported Access Programs          20.4 Semantics          20.4.1 State Variables          20.4.2 Environment Variables          20.4.3 Assumptions          20.4.4 Access Routine Semantics          20.4.5 Local Functions          21 MIS of Environmental Selection Button C          21.1 Module          21.2 Uses          21.3 Syntax	35

		21.4.2 Environment Variables	37
		21.4.3 Assumptions	37
		21.4.4 Access Routine Semantics	37
		21.4.5 Local Functions	38
<b>22</b>	MIS	of Data Type Selection Buttons Controller(M17)	39
	22.1	Module	36
	22.2	Uses	36
	22.3	Syntax	36
		22.3.1 Exported Constants	36
		22.3.2 Exported Access Programs	36
	22.4	Semantics	39
		22.4.1 State Variables	39
		22.4.2 Environment Variables	39
		22.4.3 Assumptions	39
		22.4.4 Access Routine Semantics	39
		22.4.5 Local Functions	40
		22.1.0 Botal Full colons	1(
<b>23</b>	MIS	of Save Button Controller(M18)	41
		Module	41
		Uses	41
		Syntax	41
		23.3.1 Exported Constants	41
		23.3.2 Exported Access Programs	41
	23 4	Semantics	41
	20.1	23.4.1 State Variables	41
		23.4.2 Environment Variables	41
		23.4.3 Assumptions	41
		23.4.4 Access Routine Semantics	41
		23.4.5 Local Functions	42
		25.4.5 Local Pulictions	42
24	MIS	of File Writer(M19)	43
		Module	43
		Uses	43
		Syntax	43
	- 1.0	24.3.1 Exported Constants	43
		24.3.2 Exported Access Programs	43
	24 4	Semantics	43
	2 1.1	24.4.1 State Variables	43
		24.4.2 Environment Variables	43
		24.4.3 Assumptions	44
		24.4.4 Access Routine Semantics	44
		24.4.5 Local Functions	44
		47.7.0 LANGE FUHLERUES	44

<b>25</b>	$\operatorname{MIS}$ of File Reader(M20)														
	25.1 Module														
	25.2 Uses														
	25.3 Syntax														
	25.3.1 Exported Constants														
	25.3.2 Exported Access Programs														
	25.4 Semantics														
	25.4.1 State Variables														
	25.4.2 Environment Variables														
	25.4.3 Assumptions														
	25.4.4 Access Routine Semantics														
	25.4.5 Local Functions														
	20.1.0 Local Parentons														
<b>26</b>	MIS of Season Change Controller(M21)  48														
	26.1 Module														
	26.2 Uses														
	26.3 Syntax														
	26.3.1 Exported Constants														
	26.3.2 Exported Access Programs														
	26.4 Semantics														
	26.4.1 State Variables														
	26.4.2 Environment Variables														
	26.4.3 Assumptions														
	26.4.4 Access Routine Semantics														
	26.4.5 Local Functions														
	20.4.0 Local I diferions														
<b>27</b>	MIS of move Panel Controller(M22)														
	27.1 Module														
	27.2 Uses														
	27.3 Syntax														
	27.3.1 Exported Constants														
	27.3.2 Exported Access Programs														
	27.4 Semantics														
	27.4.1 State Variables														
	27.4.2 Environment Variables														
	27.4.3 Assumptions														
	27.4.4 Access Routine Semantics														
	27.4.5 Local Functions														
	21.4.0 Local Palicholis														
<b>28</b>	MIS of Tree Planting Controller(M23)														
	28.1 Module														
	28.2 Uses														
	28.3 Syntax														

		28.3.1	Exported Constants	52
		28.3.2	Exported Access Programs	52
	28.4	Semant	iics	52
			State Variables	
		28.4.2	Environment Variables	52
			Assumptions	
			Access Routine Semantics	
		28.4.5	Local Functions	
<b>29</b>			ee Switch Button Controller(M24)	55
			9	
	29.3	Syntax		
		29.3.1	Exported Constants	
			Exported Access Programs	
	29.4	Semant	iics	55
		29.4.1	State Variables	55
		29.4.2	Environment Variables	55
		29.4.3	Assumptions	55
		29.4.4	Access Routine Semantics	55
		29.4.5	Local Functions	56
30	MIS	of Pie	${ m Chart \ Button \ Controller(M25)}$	57
		3.7 1 1		<b>-</b> -
	30.1			
	30.1 30.2	Uses .		57
	30.1 30.2	Uses . Syntax		57 57
	30.1 30.2	Uses . Syntax 30.3.1	Exported Constants	57 57
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2	Exported Constants	57 57 57
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant	Exported Constants	
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1	Exported Constants	57 57 57 57
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2	Exported Constants  Exported Access Programs  ics  State Variables  Environment Variables	
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3	Exported Constants  Exported Access Programs  State Variables  Environment Variables  Assumptions	
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3	Exported Constants  Exported Access Programs  ics  State Variables  Environment Variables	
	30.1 30.2 30.3	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4	Exported Constants  Exported Access Programs  State Variables  Environment Variables  Assumptions	
91	30.1 30.2 30.3 30.4	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5	Exported Constants Exported Access Programs  dics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions	50 50 50 50 50 50 50 50 50 50 50 50 50 5
31	30.1 30.2 30.3 30.4	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 S of Pie	Exported Constants Exported Access Programs  icics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  Chart Controller(M26)	50 50 50 50 50 50 50 50 50 50 50 50 50 5
31	30.1 30.2 30.3 30.4 MIS 31.1	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 S of Pie Module	Exported Constants  Exported Access Programs  ics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  Chart Controller(M26)	50 50 50 50 50 50 50 50 50 50 50 50 50 5
31	30.1 30.2 30.3 30.4 MIS 31.1 31.2	Uses Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5  G of Pie Module Uses	Exported Constants Exported Access Programs  icics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  Chart Controller(M26)	56 57 57 57 57 57 57 57 57 58 58 59 59
31	30.1 30.2 30.3 30.4 MIS 31.1 31.2	Uses . Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 S of Pie Module Uses . Syntax	Exported Constants Exported Access Programs  ics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  Chart Controller(M26)	50 50 50 50 50 50 50 50 50 50
31	30.1 30.2 30.3 30.4 MIS 31.1 31.2	Uses Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 S of Pie Module Uses Syntax 31.3.1	Exported Constants  Exported Access Programs  ics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  Chart Controller(M26)	56 57 57 57 57 57 57 57 58 59 59 59 59 59 59 59 59 59 59
31	30.1 30.2 30.3 30.4 MIS 31.1 31.2 31.3	Uses Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 G of Pie Module Uses Syntax 31.3.1 31.3.2	Exported Constants  Exported Access Programs  cics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  Chart Controller(M26)  Exported Constants  Exported Access Programs	56 57 57 57 57 57 57 57 57 57 57 57 57 57
31	30.1 30.2 30.3 30.4 MIS 31.1 31.2 31.3	Uses Syntax 30.3.1 30.3.2 Semant 30.4.1 30.4.2 30.4.3 30.4.4 30.4.5 S of Pie Module Uses Syntax 31.3.1 31.3.2 Semant	Exported Constants  Exported Access Programs  ics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  Chart Controller(M26)	56 57 57 57 57 57 57 58 59 59 59 59 59 59 59 59 59 59

		31.4.2	Environment Variables	59
		31.4.3	Assumptions	60
		31.4.4	Access Routine Semantics	60
			Local Functions	60
<b>32</b>	MIS	of Sea	ason Change Button Controller(M27)	62
	32.1	Modul	9	62
	32.2	Uses .		62
	32.3	Syntax		62
		32.3.1	Exported Constants	62
		32.3.2	Exported Access Programs	62
	32.4		tics	62
			State Variables	62
			Environment Variables	62
			Assumptions	62
			Access Routine Semantics	62
			Local Functions	62
		321113	200012 01001010	0-
<b>3</b> 3	MIS	of Tre	ee Switch Controller(M28)	63
			2	63
				63
	33.3	Syntax		63
			Exported Constants	63
			Exported Access Programs	63
	33.4		tics	63
			State Variables	63
			Environment Variables	63
			Assumptions	63
			Access Routine Semantics	63
			Local Functions	64
		331213	20001 2 01001010	0.
<b>34</b>	MIS	of Fo	rest Trees (M29)	65
	34.1	Modul	9	65
	34.2	Uses .		65
	34.3	Syntax		65
		34.3.1	Exported Constants	65
			Exported Access Programs	65
	34.4		tics	65
			State Variables	65
			Environment Variables	65
			Assumptions	65
			Access Routine Semantics	65
			Local Functions	66

<b>35</b>	MIS of Forest Sky (M30)	67
	35.1 Module	67
	35.2 Uses	67
	35.3 Syntax	67
	35.3.1 Exported Constants	67
	35.3.2 Exported Access Programs	67
	35.4 Semantics	67
	35.4.1 State Variables	67
	35.4.2 Environment Variables	67
	35.4.3 Assumptions	67
	35.4.4 Access Routine Semantics	67
	35.4.5 Local Functions	68
36	MIS of Forest Terrain (M31)	69
	36.1 Module	69
	36.2 Uses	69
	36.3 Syntax	69
	36.3.1 Exported Constants	69
	36.3.2 Exported Access Programs	69
	36.4 Semantics	69
	36.4.1 State Variables	69
	36.4.2 Environment Variables	69
	36.4.3 Assumptions	69
	36.4.4 Access Routine Semantics	69
	36.4.5 Local Functions	70
<b>37</b>	MIS of Red Pine (M32)	71
0.	37.1 Module	71
	37.2 Uses	71
	37.3 Syntax	71
	37.3.1 Exported Constants	71
	37.3.2 Exported Access Programs	71
	37.4 Semantics	72
	37.4.1 State Variables	72
	37.4.2 Environment Variables	72
	37.4.3 Assumptions	72
	37.4.4 Access Routine Semantics	72
	37.4.5 Local Functions	73
<b>38</b>	MIS of Oak (M33)	<b>74</b>
	38.1 Module	74
	38.2 Uses	74
	20.2 Cristory	74

		38.3.1	Exported Constants	. 74
		38.3.2	Exported Access Programs	. 74
	38.4	Semant	iics	. 74
		38.4.1	State Variables	. 74
			Environment Variables	
		38.4.3	Assumptions	. 75
			Access Routine Semantics	
			Local Functions	
<b>39</b>	MIS	of Bee	ech (M34)	77
			9	. 77
	39.2	Uses .		. 77
	39.3	Syntax		. 77
		39.3.1	Exported Constants	. 77
			Exported Access Programs	
	39.4			
			State Variables	
			Environment Variables	
			Assumptions	
			Access Routine Semantics	
			Local Functions	
		30.1.0	200m Tanoutono IIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIII	
<b>40</b>	MIS	of Bir	ch (M35)	80
	40.1	Module	9	. 80
	40.2	Uses .		. 80
	40.3	Syntax		. 80
		40.3.1	Exported Constants	. 80
		40.3.2	Exported Access Programs	. 80
	40.4			
		40.4.1	State Variables	
		40.4.2	Environment Variables	
			Assumptions	
			Access Routine Semantics	
			Local Functions	
<b>41</b>	MIS	of Wh	nite Pine (M36)	83
41			nite Pine (M36)	
41	41.1	Module		. 83
41	41.1 41.2	Module Uses .	e	. 83
41	41.1 41.2	Module Uses . Syntax	)	. 83 . 83
41	41.1 41.2	Module Uses Syntax 41.3.1		. 83 . 83 . 83
41	41.1 41.2 41.3	Module Uses Syntax 41.3.1 41.3.2	Exported Constants	. 83 . 83 . 83 . 83

		41.4.2	Environmen	t Variab	les					 												83
		41.4.3	Assumptions	3						 												84
		41.4.4	Access Rout	ine Sem	antics					 												84
		41.4.5	Local Funct	ons						 												85
	D STO	6 D	1.7.5 1 (2)	<b>50-</b> )																		0.0
42			d Maple (N																			86
			e																			86
																						86
	42.3																					86
			Exported Co																			86
			Exported A		_																	86
	42.4		tics																			86
			State Variab																			86
			Environmen																			86
			Assumptions																			87
			Access Rout																			87
		42.4.5	Local Funct	ons						 												88
19	MIC	of Do	d Oak (M3	<b>9</b> )																		89
40			e																			89
																						89
																						89
	45.5		Exported Co																			89
			Exported Co Exported Ac																			89
	19 1		-		_																	89
	45.4		tics																			89 89
			State Variab																			
			Environmen																			89
			Assumptions																			90
			Access Rout																			90
		43.4.5	Local Funct	ons			•		•	 	•		•		•	•	•		•	•	•	91
44	MIS	of En	vironmenta	l Data	(M39)	)																92
			e		,	<b>,</b>																92
																						92
			· · · · · · · · · · · · · · · · · · ·																			92
	11.0		Exported Co																			92
			Exported Ac																			92
	11 1		$tics \dots \dots$		0																	92
	11.1		State Variab																			92
			Environmen																			93
																						93 93
			Assumptions Access Rout																			93 93
			Leesl Function		andics		•	• •	•	 	•	•	٠	•	•	٠	•	•	•	٠	•	90 04

<b>45</b>	MIS of Plot Data (M40)	95
	45.1 Module	95
	45.2 Uses	95
	45.3 Syntax	95
	45.3.1 Exported Constants	95
	45.3.2 Exported Access Programs	95
	45.4 Semantics	96
	45.4.1 State Variables	96
	45.4.2 Environment Variables	96
	45.4.3 Assumptions	96
	45.4.4 Access Routine Semantics	96
	45.4.5 Local Functions	99
<b>46</b>	MIS of First Person Player (M41)	100
	46.1 Module	100
	46.2 Uses	100
	46.3 Syntax	100
	46.4 Semantics	100
47	MIS of Json File (M42)	101
	47.1 Module	
	47.2 Local Type	
	47.3 State Variables	
	47.4 Example	
	47.5 Local Functions	
48	MIS of Main Page (M43)	104
10	48.1 Module	_
	48.2 Uses	
	48.3 Syntax	
	48.3.1 Exported Constants	
	48.3.2 Exported Access Programs	
	48.4 Semantics	
	48.4.1 State Variables	
	48.4.2 Environment Variables	
	48.4.3 Assumptions	
	48.4.4 Access Routine Semantics	
	48.4.5 Local Functions	
40	MIS of Start Button (M44)	105
49	49.1 Module	
	49.1 Module	
	49.3 Syntax	108
	T. ( ) 1 V 1 I I ( ) A	

		49.3.1 Exported Constants	105
		49.3.2 Exported Access Programs	105
	49.4	Semantics	105
		49.4.1 State Variables	105
		49.4.2 Environment Variables	105
		49.4.3 Assumptions	105
		49.4.4 Access Routine Semantics	105
		49.4.5 Local Functions	105
50	MIS	of Instruction Button (M45)	106
			106
			106
			106
		·	106
			106
	50.4	·	106
			106
			106
			106
		•	106
			106
51	МТ	of Contact Us Button (M46)	107
$\mathbf{o}_{\mathbf{T}}$	TATTE	of Contact C5 Button (W140)	LOI
	51.1	Module	107
			107 107
	51.2	Jses	107
	51.2	UsesSyntax	107 107
	51.2	Uses	107 107 107
	51.2 51.3	Uses	107 107 107 107
	51.2 51.3	Uses   Syntax   51.3.1 Exported Constants   51.3.2 Exported Access Programs   Semantics	107 107 107 107 107
	51.2 51.3	Uses   Syntax   51.3.1 Exported Constants   51.3.2 Exported Access Programs   Semantics   51.4.1 State Variables	107 107 107 107 107
	51.2 51.3	Uses Syntax Syntax S1.3.1 Exported Constants S1.3.2 Exported Access Programs Semantics Semantics S1.4.1 State Variables S1.4.2 Environment Variables	107 107 107 107 107 107
	51.2 51.3	Uses Syntax Syntax S1.3.1 Exported Constants S1.3.2 Exported Access Programs Semantics Semantics S1.4.1 State Variables S1.4.2 Environment Variables S1.4.3 Assumptions	107 107 107 107 107 107 107
	51.2 51.3	Uses Syntax Syntax Sind Exported Constants Sind Exported Access Programs Semantics Semantics Sind Exported Access Programs Semantics Sind Exported Access Programs Sind Exported Access Programs Sind Exported Access Programs Sind Exported Access Programs Sind Exported Constants Sind Exported Access Programs Sind	107 107 107 107 107 107
<b>F</b> 0	<ul><li>51.2</li><li>51.3</li><li>51.4</li></ul>	Uses Syntax Syntax Since I Exported Constants Since I Exported Access Programs Semantics Since I State Variables Since I Environment Variables Since I Envir	107 107 107 107 107 107 107 107
<b>52</b>	<ul><li>51.2</li><li>51.3</li><li>51.4</li><li>MIS</li></ul>	Uses Syntax Syntax Since I Exported Constants Since I Exported Access Programs Semantics Since I Exported Access Programs Since I Ex	107 107 107 107 107 107 107 107
<b>52</b>	51.2 51.3 51.4 MIS 52.1	Uses Syntax Sol. 3.1 Exported Constants Sol. 3.2 Exported Access Programs Semantics Sol. 4.1 State Variables Sol. 4.2 Environment Variables Sol. 4.3 Assumptions Sol. 4.4 Access Routine Semantics Sol. 4.5 Local Functions  of Quit Button (M47) Module	107 107 107 107 107 107 107 107 107
<b>52</b>	51.2 51.3 51.4 MIS 52.1 52.2	Syntax  Syntax  Sol. 3.1 Exported Constants  Sol. 3.2 Exported Access Programs  Semantics  Sol. 4.1 State Variables  Sol. 4.2 Environment Variables  Sol. 4.3 Assumptions  Sol. 4.4 Access Routine Semantics  Sol. 4.5 Local Functions  of Quit Button (M47)  Module  Uses	107 107 107 107 107 107 107 107 107 108
<b>52</b>	51.2 51.3 51.4 MIS 52.1 52.2	Syntax  Syntax  51.3.1 Exported Constants  51.3.2 Exported Access Programs  Semantics  51.4.1 State Variables  51.4.2 Environment Variables  51.4.3 Assumptions  51.4.4 Access Routine Semantics  51.4.5 Local Functions  of Quit Button (M47)  Module  Uses  Syntax	107 107 107 107 107 107 107 107 108 108
52	51.2 51.3 51.4 MIS 52.1 52.2	Syntax Syntax Syntax Sol. 3.1 Exported Constants Sol. 3.2 Exported Access Programs Semantics Sol. 4.1 State Variables Sol. 4.2 Environment Variables Sol. 4.3 Assumptions Sol. 4.4 Access Routine Semantics Sol. 4.5 Local Functions  of Quit Button (M47) Module Uses Syntax Syntax Sol. 3.1 Exported Constants	107 107 107 107 107 107 107 108 108 108
<b>52</b>	51.2 51.3 51.4 MIS 52.1 52.2 52.3	Syntax Syntax Syntax Sol. 3.1 Exported Constants Sol. 3.2 Exported Access Programs Semantics Sol. 4.1 State Variables Sol. 4.2 Environment Variables Sol. 4.3 Assumptions Sol. 4.4 Access Routine Semantics Sol. 4.5 Local Functions  of Quit Button (M47) Module Uses Syntax Sol. 3.1 Exported Constants Sol. 3.2 Exported Access Programs	107 107 107 107 107 107 107 108 108 108 108
52	51.2 51.3 51.4 MIS 52.1 52.2 52.3	Jses Syntax Syntax S1.3.1 Exported Constants S1.3.2 Exported Access Programs Semantics S1.4.1 State Variables S1.4.2 Environment Variables S1.4.3 Assumptions S1.4.4 Access Routine Semantics S1.4.5 Local Functions  of Quit Button (M47) Module Jses Syntax S2.3.1 Exported Constants S2.3.2 Exported Access Programs Semantics	107 107 107 107 107 107 107 108 108 108

	52.4.2 Environment Variables	08
	52.4.3 Assumptions	08
	52.4.4 Access Routine Semantics	08
	52.4.5 Local Functions	08
53 MI	S of Instruction Page (M48)	)6
53.1	l Module	06
53.2	2 Uses	06
53.3	m 8~Syntax	06
	53.3.1 Exported Constants	06
	53.3.2 Exported Access Programs	06
53.4	4 Semantics	06
	53.4.1 State Variables	06
	53.4.2 Environment Variables	06
		06
	•	06
		06
54 MI	S of Contact Us Page (M49)	10
54.1	Module	10
54.2	2 Uses	10
54.3	3 Syntax	10
	54.3.1 Exported Constants	10
	54.3.2 Exported Access Programs	10
54.4	·	10
		10
		10
		10
	*	10
		10
55 MI	S of Back Button (M50)	11
55.1	Module	11
55.2	2 Uses	11
55.3	3 Syntax	11
		11
		11
55.4	·	11
		 11
		11
		$\frac{1}{1}$
		11
		11

<b>56</b>	MIS of Update Data Page (M51)	112
	56.1 Module	112
	56.2 Uses	112
	56.3 Syntax	112
	56.3.1 Exported Constants	112
	56.3.2 Exported Access Programs	112
	56.4 Semantics	112
	56.4.1 State Variables	112
	56.4.2 Environment Variables	112
	56.4.3 Assumptions	112
	56.4.4 Access Routine Semantics	112
	56.4.5 Local Functions	112
<b>57</b>	MIS of Environmental Data Selection Button (M52)	113
	57.1 Module	113
	57.2 Uses	113
	57.3 Syntax	113
	57.3.1 Exported Constants	113
	57.3.2 Exported Access Programs	
	57.4 Semantics	113
	57.4.1 State Variables	113
	57.4.2 Environment Variables	113
	57.4.3 Assumptions	113
	57.4.4 Access Routine Semantics	
	57.4.5 Local Functions	
58	MIS of Data Type Selection Button (M53)	114
00	58.1 Module	
	58.2 Uses	
	58.3 Syntax	
	58.3.1 Exported Constants	
	58.3.2 Exported Access Programs	114
	58.4 Semantics	
	58.4.1 State Variables	
	58.4.2 Environment Variables	114
	58.4.3 Assumptions	114
	58.4.4 Access Routine Semantics	114
	58.4.5 Local Functions	
<b>5</b> 9	MIS of New Data Input Box (M54)	115
-	59.1 Module	115
	59.2 Uses	
	59.3 Syntax	115

		59.3.1 Exported Constants	115
		59.3.2 Exported Access Programs	115
	59.4	Semantics	115
		59.4.1 State Variables	115
		59.4.2 Environment Variables	115
		59.4.3 Assumptions	115
		59.4.4 Access Routine Semantics	115
		59.4.5 Local Functions	115
<b>60</b>	MIS	of Save Button (M55)	16
			116
			116
	60.3	Syntax	116
		60.3.1 Exported Constants	116
			116
	60.4	Semantics	116
			116
		60.4.2 Environment Variables	116
		60.4.3 Assumptions	116
		60.4.4 Access Routine Semantics	116
		60.4.5 Local Functions	116
61	MIS	of Current Data Dispaly (M56)	17
61			. <b>17</b> 117
61	61.1	Module	
61	$61.1 \\ 61.2$	Module	117
61	$61.1 \\ 61.2$	Module	117 117
61	$61.1 \\ 61.2$	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1	117 117 117
61	61.1 61.2 61.3	Module	117 117 117 117
61	61.1 61.2 61.3	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1	117 117 117 117
61	61.1 61.2 61.3	Module	117 117 117 117 117
61	61.1 61.2 61.3	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1	117 117 117 117 117 117
61	61.1 61.2 61.3	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1	117 117 117 117 117 117
61	61.1 61.2 61.3	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1	117 117 117 117 117 117 117
	61.1 61.2 61.3	Module	117 117 117 117 117 117 117 117
	61.1 61.2 61.3 61.4	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1	117 117 117 117 117 117 117 117 117
	61.1 61.2 61.3 61.4 MIS 62.1	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1         Module       1	117 117 117 117 117 117 117 117 117
	61.1 61.2 61.3 61.4 MIS 62.1 62.2	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1         Module       1         Uses       1	117 117 117 117 117 117 117 117 117 118
	61.1 61.2 61.3 61.4 MIS 62.1 62.2	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1         Module       1         Uses       1         Syntax       1	117 117 117 117 117 117 117 117 118 118
	61.1 61.2 61.3 61.4 MIS 62.1 62.2	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1         Module       1         Uses       1         Syntax       1         62.3.1 Exported Constants       1	117 117 117 117 117 117 117 117 117 118 118
	61.1 61.2 61.3 61.4 MIS 62.1 62.2 62.3	Module       1         Uses       1         Syntax       1         61.3.1 Exported Constants       1         61.3.2 Exported Access Programs       1         Semantics       1         61.4.1 State Variables       1         61.4.2 Environment Variables       1         61.4.3 Assumptions       1         61.4.4 Access Routine Semantics       1         61.4.5 Local Functions       1         of Plot Selection Drop Down (M57)       1         Module       1         Uses       1         Syntax       1         62.3.1 Exported Constants       1         62.3.2 Exported Access Programs       1	117 117 117 117 117 117 117 117 118 118

		62.4.2 E	nvironment V	ariables .		 	 		 			118
		62.4.3 A	ssumptions.			 	 		 			118
			ccess Routine									
			ocal Function									
<b>63</b>			Type Select	_								119
												119
												119
	63.3	•										119
			xported Cons									119
			xported Acce									119
	63.4		S									119
			tate Variables									119
		63.4.2 E	nvironment V	ariables .		 	 		 			119
		63.4.3 A	ssumptions.			 	 		 			119
		63.4.4 A	ccess Routine	Semantics		 	 		 			119
		63.4.5 L	ocal Function	s		 	 		 			119
C 4	NATO	. C T I 1	t. D.t. D.	( <b>)</b>	0)							100
04		_	ate Data Bu	•								120 120
												120
												120
	04.5	•	· · · · · · · ·									
			xported Cons									120
	C 1 1		xported Acce	_								120
	04.4		S									120
			tate Variables									120
			nvironment V									120
			ssumptions.									120
			ccess Routine									120
		64.4.5 L	ocal Function	S		 	 		 		 •	120
<b>65</b>	MIS	of Fores	st Dispaly (	M60)								121
				*		 	 		 			121
												121
												121
	00.0	•	xported Cons									121
			xported Acce									121
	65.4		S									121
	00.1		tate Variables									121
			nvironment V									121
			$\frac{1}{2}$ ssumptions .									121
			${ m ccess~Routine}$									121
			ocal Function			 	 	• • •	 	• •	 •	121
		1 1 4 4 4 4 1 1 4 4 4 4 1 1 4 4 4 4 4 4	осан выписьион	<u> </u>								1/1

<b>66</b>	MIS of Show Environmental Data Button (M61)	122
	66.1 Module	. 122
	66.2 Uses	. 122
	66.3 Syntax	. 122
	66.3.1 Exported Constants	. 122
	66.3.2 Exported Access Programs	
	66.4 Semantics	
	66.4.1 State Variables	
	66.4.2 Environment Variables	
	66.4.3 Assumptions	
	66.4.4 Access Routine Semantics	
	66.4.5 Local Functions	
	00.4.9 Local Functions	. 122
<b>67</b>	MIS of Show Tree Parameters Button (M62)	123
	67.1 Module	. 123
	67.2 Uses	. 123
	67.3 Syntax	
	67.3.1 Exported Constants	
	67.3.2 Exported Access Programs	
	67.4 Semantics	
	67.4.1 State Variables	
	67.4.2 Environment Variables	
	67.4.3 Assumptions	
	67.4.4 Access Routine Semantics	
	67.4.5 Local Functions	
	07.4.9 Local Functions	. 120
<b>68</b>	MIS of Environment Data Display (M63)	124
	68.1 Module	. 124
	58.2 Uses	. 124
	58.3 Syntax	. 124
	68.3.1 Exported Constants	
	68.3.2 Exported Access Programs	
	68.4 Semantics	
	68.4.1 State Variables	
	68.4.2 Environment Variables	
	68.4.3 Assumptions	
	68.4.4 Access Routine Semantics	
	68.4.5 Local Functions	
	COLLO DOCTI differentia	. 145
<b>69</b>	MIS of Tree Parameters Display (M64)	125
	69.1 Module	. 125
	69.2 Uses	. 125
	69.3 Syntax	. 125

		69.3.1	Exported Constants	1	25
		69.3.2	Exported Access Programs	1	25
	69.4	Semanti	iics	1	25
		69.4.1	State Variables	1	25
		69.4.2	Environment Variables	1	25
		69.4.3	Assumptions	1	25
		69.4.4	Access Routine Semantics	1	25
		69.4.5	Local Functions	1	25
<b>70</b>	MIS	of Pau	use Indicator (M65)	1:	26
	70.1	Module	9	1	26
	70.2	Uses .		1	26
	70.3	Syntax		1	26
		70.3.1	Exported Constants	1	26
			Exported Access Programs		26
	70.4	Semanti	${ m cics}$	1	26
		70.4.1	State Variables	1	26
		70.4.2	Environment Variables	1	26
		70.4.3	Assumptions	1	26
			Access Routine Semantics		26
		70.4.5	Local Functions	1	26
<b>7</b> 1	MIS	of Sea	asonChangeButton (M66)	1:	27
<b>7</b> 1			asonChangeButton (M66)		
<b>7</b> 1	71.1	Module		1	
<b>7</b> 1	$71.1 \\ 71.2$	Module Uses .	e	1 	27
<b>7</b> 1	$71.1 \\ 71.2$	Module Uses . Syntax	9	1 	27 27
<b>7</b> 1	$71.1 \\ 71.2$	Module Uses . Syntax 71.3.1			27 27 27
71	71.1 71.2 71.3	Module Uses . Syntax 71.3.1 1 71.3.2	Exported Constants		27 27 27 27
71	71.1 71.2 71.3	Module Uses . Syntax 71.3.1 1 71.3.2 1 Semanti	Exported Constants		27 27 27 27 27
71	71.1 71.2 71.3	Module Uses Syntax 71.3.1 71.3.2 Semant: 71.4.1	Exported Constants		27 27 27 27 27 27 27 27
71	71.1 71.2 71.3	Module Uses . Syntax 71.3.1 1 71.3.2 1 Semanti 71.4.1 5 71.4.2 1	Exported Constants		27 27 27 27 27 27 27 27 27
71	71.1 71.2 71.3	Module Uses . Syntax 71.3.1 . The semants 71.4.1 . Semants 71.4.2 . The semants 71.4.3 . The semants 71.4 .	Exported Constants  Exported Access Programs  State Variables  Environment Variables		27 27 27 27 27 27 27 27 27
71	71.1 71.2 71.3	Module Uses . Syntax 71.3.1 . 71.3.2 . Semanti 71.4.1 . 5 71.4.2 . 71.4.3 . 71.4.4	Exported Constants  Exported Access Programs  Sics  State Variables  Environment Variables  Assumptions		27 27 27 27 27 27 27 27 27 27
	71.1 71.2 71.3 71.4	Module Uses . Syntax 71.3.1 . The semanting 71.4.1 . Semanting 71.4.2 . The semanting 71.4.3 . The semanting 71.4.4 . The semanting 71.4.5 . The semanting representation of the semanting rep	Exported Constants  Exported Access Programs  Cics  State Variables  Environment Variables  Assumptions  Access Routine Semantics		27 27 27 27 27 27 27 27 27 27
	71.1 71.2 71.3 71.4 MIS	Module Uses Syntax 71.3.1 Semanti 71.4.1 71.4.2 71.4.3 71.4.4 71.4.5 of pie 0	Exported Constants  Exported Access Programs  Sics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions		27 27 27 27 27 27 27 27 27 27 27 27
	71.1 71.2 71.3 71.4 MIS 72.1	Module Uses . Syntax 71.3.1 . The semanting 71.4.1 . The syntax 71.4.2 . The syntax 71.4.3 . The syntax 71.4.4 . The syntax 71.4.5 . The syntax of pieces of	Exported Constants  Exported Access Programs  Cics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  ChartButton (M67)		27 27 27 27 27 27 27 27 27 27 27
	71.1 71.2 71.3 71.4 MIS 72.1 72.2	Module Uses . Syntax 71.3.1 . The syntax 71.3.2 . Semant: 71.4.1 . The syntax 71.4.3 . The syntax 71.4.4 . The syntax 71.4.5 . The syntax for pieces . The syntax syntax is of pieces . The syntax is of	Exported Constants  Exported Access Programs  Sics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  ChartButton (M67)		27 27 27 27 27 27 27 27 27 27 27 27 27 2
	71.1 71.2 71.3 71.4 MIS 72.1 72.2	Module Uses . Syntax 71.3.1 . 71.3.2 . Semanti 71.4.1 . 71.4.2 . 71.4.3 . 71.4.4 . 71.4.5 . Sof pie C Module Uses . Syntax	Exported Constants Exported Access Programs  Sics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  ChartButton (M67)	15	27 27 27 27 27 27 27 27 27 27 27 27 27 2
	71.1 71.2 71.3 71.4 MIS 72.1 72.2	Module Uses . Syntax 71.3.1 . Semanti 71.4.1 . Semanti 71.4.2 . The syntax 71.4.5 . Sof pie Control of the Uses . Syntax 72.3.1 . Syntax .	Exported Constants  Exported Access Programs  Sics  State Variables  Environment Variables  Assumptions  Access Routine Semantics  Local Functions  ChartButton (M67)	1:	27 27 27 27 27 27 27 27 27 27 28 28 28 28
	71.1 71.2 71.3 71.4 MIS 72.1 72.2 72.3	Module Uses . Syntax 71.3.1 . Semanti 71.4.1 . Semanti 71.4.2 . The syntax 71.4.5 . Sof pie Constant Total 1 . Syntax 72.3.1 . The syntax 72.3.2 .	Exported Constants Exported Access Programs  Sics State Variables Environment Variables Assumptions Access Routine Semantics Local Functions  ChartButton (M67)  Exported Constants	15	27 27 27 27 27 27 27 27 27 27 27 27 27 2

7	72.4.2 Environment Variables	28
7	72.4.3 Assumptions	28
7	72.4.4 Access Routine Semantics	28
7	72.4.5 Local Functions	28
73 MIS	of TreeSwitchButton (M68)	26
73.1 N	Module	29
73.2 U	Jses	29
73.3 \$	$S_{ m yntax}$	29
	73.3.1 Exported Constants	
	73.3.2 Exported Access Programs	
	Semantics	
	73.4.1 State Variables	
	73.4.2 Environment Variables	
7	73.4.3 Assumptions	29
	73.4.4 Access Routine Semantics	
	73 4 5 Local Functions	

## 3 Introduction

The following document outlines the Module Interface Specifications for Digital Twin Forest, which is a virtual representation of the real world, including physical objects, processes, relationships, and behaviors. Components of a digital twin encompass data capture and integration, visualization, and advanced analysis including AI, automation, information sharing and collaboration. This project can benefit two groups of users: forest owners who can utilize the software for forest management and meteorologists who can use it for research purposes. Complementary documents include the System Requirement Specifications and Module Guide.

## 4 Notation

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol := is used for a multiple assignment statement and conditional rules follow the form  $(c_1 \Rightarrow r_1|c_2 \Rightarrow r_2|...|c_n \Rightarrow r_n)$ .

The following table summarizes the primitive data types used by Digital Twin Forest.

Data Type	Notation	Description
string	String	a sequence of characters
character	char	a single symbol or digit
integer	$\mathbb{Z}$	a number without a fractional component in $(-\infty, \infty)$
natural number	N	a number without a fractional component in $[1, \infty)$
real	$\mathbb{R}$	any number in $(-\infty, \infty)$
Boolean	Boolean	a value that takes either True or False

The specification of Digital Twin Forest uses some derived data types: sequences, strings, and tuples. Sequences are lists filled with elements of the same data type. Strings are sequences of characters. Tuples contain a list of values, potentially of different types. In addition, Digital Twin Forest uses functions, which are defined by the data types of their inputs and outputs. Local functions are described by giving their type signature followed by their specification.

# 5 Module Decomposition

Table 1: Module Hierarchy(First Controller Table)

Level 1	Level 2		
	M1: JsonFileReader		
	M2: JsonFileWriter		
	M3: PauseManager		
	M4: PlayerMovement		
	M5: NewDataInputBoxController		
Controller Modules	M6: StartButtonController		
	M7: InstructionButtonController		
	M8: UpdateDataButtonController		
	M9: ContactUsButtonController		
	M10: QuitButtonController		
	M11: BackButtonController		
	M12: PlotSelectionDropDownController		
	${\bf M13:\ TreeTypeSelectionDropDownController}$		
	M14: ShowEnvDataButtonController		
	M15: ShowTreeParamButtonController		
	M16: EnvDataSelectionButtonController		
	M17: DataTypeSelectionButtonsController		
	M18: SaveButtonController		

Table 2: Module Hierarchy(Second Controller Table)

Level 1	Level 2	
	M19: FileWriter	
	M20: FileReader	
	M21: SeasonChangeController	
	M22: movePanelController	
Controller Modules	M23: treePlantingController	
Controller Modules	M24: TreeSwitchButtonController	
	M25: pieChartButtonController	
	M26: pieChartController	
	M27: SeasonChangeButtonController	
	M28: TreeSwitchController	

Table 3: Module Hierarchy(Models)

Level 1	Level 2
	M29: ForestTrees
	M30: ForestSky
	M31: ForestTerrain
	M32: RedPine
Model Modules	M33: Oak
	M34: Beech
	M35: Birch
	M36: WhitePine
	M37: RedMaple
	M38: RedOak
	M39: EnvData
	M40: PlotData
	M41: FirstPersonPlayer
	M42: JsonFile

Table 4: Module Hierarchy(First Viewers Table)

Level 1	Level 2		
	M43: MainPageDisplay		
	M44: StartButton		
	M45: InstructionButton		
Viewer Modules	M46: ContactUsButton		
	M47: QuitButton		
	M48: InstructionInfoDisplay		
	M49: ContactUsInfoDisplay		
	M50: BackButton		
	M51: UpdateDataDisplay		
	M52: EnvDataSelectionButton		
	M53: DataTypeSelectionButtons		
	M54: NewDataInputBox		
	M55: SaveButton		

Table 5: Module Hierarchy(Second Viewers Table)

Level 1	Level 2
	M56: CurrentDataDisplay
	M57: PlotSelectionDropDown
Viewer Modules	M58: TreeTypeSelectionDropDown
	M59: UpdateDataButton
	M60: ForestDisplay
	M61: ShowEnvDataButton
	M62: ShowTreeParamButton
	M63: EnvDataDisplay
	M64: TreeParamDisplay
	M65: PauseIndicatorDisplay
	M66: SeasonChangeButton
	M67: pieChartButton
	M68: TreeSwitchButton

## 6 MIS of Json File Reader (M1)

#### 6.1 Module

JsonFileReader

### 6.2 Uses

 ${\bf Unity Engine}$ 

System.IO

UnityEngine.UI

M64

M63

M23

M26

M40

## 6.3 Syntax

#### 6.3.1 Exported Constants

None

#### 6.3.2 Exported Access Programs

Name	In	Out	Exceptions
Awake			
Start			
readfile	$\mathbb{Z}$		

#### 6.4 Semantics

#### 6.4.1 State Variables

 ${\it tree Param Display: Tree Param Display} \\ env Data Display: Env Data Display$ 

graphMaker: pieChartMaker treePlanter: treePlanting DataModelObj: DataModel JsonModelObj: JsonModel

plotNumber:  $\mathbb{Z}$  filePath: string plotJsonData: string

#### 6.4.2 Environment Variables

overalldata.json plot1data.json plot2data.json plot3data.json plot4data.json plot5data.json plot6data.json plot7data.json plot8data.json plot10data.json plot11data.json plot12data.json plot13data.json plot13data.json

#### 6.4.3 Assumptions

None

#### 6.4.4 Access Routine Semantics

#### Awake():

• transition: readfile(0)

• output: None

• exception: None

#### Start():

• transition: None

• output: None

• exception: None

#### readfile(value):

• transition: Open the JSON file according to value, read all the content from the JSON file, update tree parameters of treeParamDisplay, update environmental data in env-DataDisplay, invoke the markChart() function of graphMaker, and invoke plantTrees() function of treePlanter

• output: None

• exception: None

## 6.4.5 Local Functions

None

## 7 MIS of Json File Writer (M2)

## 7.1 Module

JsonFileWriter

### 7.2 Uses

UnityEngine TMPro Text UnityEngine.UI M1

## 7.3 Syntax

### 7.3.1 Exported Constants

None

#### 7.3.2 Exported Access Programs

Name	In	Out	Exceptions
Awake			
updateHandler			InvalidInputException
writeFile	String		
removeMsg			
isValid	String	Boolean	
isIN	char, List <char></char>	Boolean	

#### 7.4 Semantics

#### 7.4.1 State Variables

indicator: ValueIndicator inputField: TMP\_InputField

notify: Text FR: FileReader

#### 7.4.2 Environment Variables

overalldata.json plot1data.json plot2data.json plot3data.json plot4data.json plot5data.json plot6data.json plot7data.json plot8data.json plot9data.json plot10data.json plot11data.json plot12data.json plot13data.json plot13data.json

#### 7.4.3 Assumptions

None

#### 7.4.4 Access Routine Semantics

Awake():

• transition: Invoke removeMsg()

• output: None

• exception: None

updateHandler():

• transition: Validate the input of the text field and invoke writeFile function

• output: None

• exception: Throw InvalidInputException if the inputs are invalid

writeFile(newValue):

- transition: Import the data from the text field and use it to rewrite the data stored in the JSON files based on the attributes of the indicator
- output: None
- exception: None

removeMsg():

• transition: notify.text := ""

• output: None

• exception: None

### isValid(s):

• transition: Check whether all the characters in s are in the pool

• output: True if all the characters in s are in the pool. False otherwise

• exception: None

## isIN(target, pool):

• transition: Find an element of pool that matches target

• output: True if that element exists. False otherwise

• exception: None

#### 7.4.5 Local Functions

None

# 8 MIS of Pause Manager (M3)

## 8.1 Module

PauseManager

## 8.2 Uses

UnityEngine UnityEngine.UI

## 8.3 Syntax

## 8.3.1 Exported Constants

None

## 8.3.2 Exported Access Programs

Name	In	Out	Exceptions
Start			
Update			

## 8.4 Semantics

#### 8.4.1 State Variables

isPaused: Boolean pauseIndicator: Image

## 8.4.2 Environment Variables

None

## 8.4.3 Assumptions

None

#### 8.4.4 Access Routine Semantics

Start():

• transition: enable the visibility of the Pause image

• output: None

• exception: None

## Update():

• transition: Capture the event of pressing the K-key, change the value of isPaused, and enable or disable the visibility of the Pause image

• output: None

• exception: None

## 8.4.5 Local Functions

# 9 MIS of Player Movement(M4)

## 9.1 Module

PlayerMovement

## 9.2 Uses

UnityEngine

## 9.3 Syntax

## 9.3.1 Exported Constants

None

## 9.3.2 Exported Access Programs

Name	In	Out	Exceptions
Update			

## 9.4 Semantics

#### 9.4.1 State Variables

controller: Character Controller speed:  $\mathbb R$ 

#### 9.4.2 Environment Variables

None

## 9.4.3 Assumptions

None

#### 9.4.4 Access Routine Semantics

• transition: Change the position of the camera in each frame

• output: None

• exception: None

#### 9.4.5 Local Functions

# 10 MIS of New Data Input Box Controller (M5)

## 10.1 Module

New Data Input Box Controller

## 10.2 Uses

UnityEngine

## 10.3 Syntax

## 10.3.1 Exported Constants

None

## 10.3.2 Exported Access Programs

None

## 10.4 Semantics

## 10.4.1 State Variables

None

#### 10.4.2 Environment Variables

None

## 10.4.3 Assumptions

None

#### 10.4.4 Access Routine Semantics

None

#### 10.4.5 Local Functions

# 11 MIS of Start Button Controller (M6)

## 11.1 Module

 ${\bf Start Button Controller}$ 

## 11.2 Uses

UnityEngine

## 11.3 Syntax

## 11.3.1 Exported Constants

None

## 11.3.2 Exported Access Programs

Name	In	Out	Exceptions
OnClick			

## 11.4 Semantics

#### 11.4.1 State Variables

None

#### 11.4.2 Environment Variables

None

## 11.4.3 Assumptions

None

#### 11.4.4 Access Routine Semantics

OnClick():

• transition: Enable the visibility of M60

• output: None

# 11.4.5 Local Functions

# 12 MIS of Instruction Button Controller (M7)

## 12.1 Module

Instruction Button Controller

## 12.2 Uses

None

## 12.3 Syntax

## 12.3.1 Exported Constants

None

## 12.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick			

## 12.4 Semantics

#### 12.4.1 State Variables

None

#### 12.4.2 Environment Variables

None

## 12.4.3 Assumptions

None

#### 12.4.4 Access Routine Semantics

onClick():

• transition: Enable the visibility of M48

• output: None

## 12.4.5 Local Functions

# 13 MIS of Update Data Button Controller (M8)

## 13.1 Module

 ${\bf Update Data Button Controller}$ 

## 13.2 Uses

UnityEngine UnityEngine.UI Json File Reader Value Indicator M1

## 13.3 Syntax

## 13.3.1 Exported Constants

None

## 13.3.2 Exported Access Programs

Name	In	Out	Exceptions
UpdateEnvDataButtonHandle			
UpdateTreeParamHande			
onClick			

## 13.4 Semantics

## 13.4.1 State Variables

EnvDataOptions: Canvas TreeParamOptions: Canvas treeSelection: Dropdown indicator: ValueIndicator

FR: FileReader

## 13.4.2 Environment Variables

None

## 13.4.3 Assumptions

#### 13.4.4 Access Routine Semantics

## UpdateEnvDataButtonHandle():

- transition: Change the isEnvData and isTreeParam variables in the indicator.
- output: None
- exception: None

## UpdateTreeParamHande():

- transition: Change the isTreeParam and isEnvData, in the indicator, and also change the TreeType attribute in the indicator according to the value of the Dropdown class.
- output: None
- exception: None

## onClick():

- transition: Invoke UpdateEnvDataButtonHandle() and UpdateTreeParamHande()
- output: None
- exception: None

#### 13.4.5 Local Functions

# 14 MIS of Contact Us Button Controller (M9)

## 14.1 Module

Contact Us Button Controller

## 14.2 Uses

UnityEngine

## 14.3 Syntax

## 14.3.1 Exported Constants

None

## 14.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick			

## 14.4 Semantics

#### 14.4.1 State Variables

None

#### 14.4.2 Environment Variables

None

## 14.4.3 Assumptions

None

#### 14.4.4 Access Routine Semantics

onClick():

• transition: Enable the visibility of M49

• output: None

## 14.4.5 Local Functions

# 15 MIS of Quit Button Controller (M10)

## 15.1 Module

Quit Button Controller

## 15.2 Uses

UnityEngine

## 15.3 Syntax

## 15.3.1 Exported Constants

None

## 15.3.2 Exported Access Programs

Name	In	Out	Exceptions
QuitSoftware			
onClick			

## 15.4 Semantics

#### 15.4.1 State Variables

None

#### 15.4.2 Environment Variables

None

## 15.4.3 Assumptions

None

## 15.4.4 Access Routine Semantics

QuitSoftware():

• transition: Quit the software.

• output: None

# $\mathrm{onClick}():$

 $\bullet$ transition: Invoke QuitSoftware()

• output: None

• exception: None

## 15.4.5 Local Functions

# 16 MIS of Back Button Controller (M11)

## 16.1 Module

BackButtonController

## 16.2 Uses

UnityEngine UnityEngine.SceneManagement

## 16.3 Syntax

## 16.3.1 Exported Constants

None

## 16.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
Back			

## 16.4 Semantics

#### 16.4.1 State Variables

 $\begin{array}{c} {\rm viewState} \\ {\rm upperLevelPage} \end{array}$ 

#### 16.4.2 Environment Variables

Mouse

## 16.4.3 Assumptions

None

#### 16.4.4 Access Routine Semantics

Back():

- transition: upperLevelPage  $\implies$  (viewState := upperLevelPage)
- output: None

• exception: None

## 16.4.5 Local Functions

# 17 MIS of Plot Selection Drop Down Controller (M12)

#### 17.1 Module

 ${\bf Plot Selection Drop Down Controller}$ 

## 17.2 Uses

UnityEngine.UI UnityEngine.SceneManagement System.Threading

## 17.3 Syntax

## 17.3.1 Exported Constants

None

## 17.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
displayMenu			
extractTreeParam	s: int		

#### 17.4 Semantics

#### 17.4.1 State Variables

isActive: Boolean

s1: String s2: String

s3: String

s4: String

s5: String

curIndex: int

#### 17.4.2 Environment Variables

Mouse

DataModelObj: The gameobject of the current script EnvDisp: Interface that will be displayed in Unity

dropDown: Drop down menu to select plot

## 17.4.3 Assumptions

None

## 17.4.4 Access Routine Semantics

displayMenu():

• transition: isActive:= ¬ isActive

• output: None

• exception: None

extractTreeParam(s):

• transition: Get the mouse click, assign different values to s1,s2,s3,s4,s5 based on the value of curIndex

• output: None

• exception: None

## 17.4.5 Local Functions

# 18 MIS of Tree Type Selection Drop Down Controller (M13)

#### **18.1** Module

Tree Type Selection Drop Down Controller

## 18.2 Uses

UnityEngine.UI UnityEngine.SceneManagement System.Threading

## 18.3 Syntax

## 18.3.1 Exported Constants

None

#### 18.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
displayMenu			
extractTreeParam	s: int		

#### 18.4 Semantics

#### 18.4.1 State Variables

isActive: Boolean curIndex: int s1: String s2: String s3: String s4: String

#### 18.4.2 Environment Variables

Mouse

DataModelObj: The gameobject of the current script TreeParamDisp: Interface that will be displayed in Unity dropdown: The drop down menu to select tree type

## 18.4.3 Assumptions

None

## 18.4.4 Access Routine Semantics

displayMenu():

• transition: isActive:= ¬ isActive

• output: None

• exception: None

extractTreeParam(s):

 $\bullet$  transition: Get the mouse click, assign different values to s1,s2,s3,s4 based on the value of curIndex

• output: None

• exception: None

## 18.4.5 Local Functions

# 19 MIS of Show Environmental Data Button Controller (M14)

## 19.1 Module

Show Env Data But to Controller

## 19.2 Uses

UnityEngine UnityEngine.UI

## 19.3 Syntax

## 19.3.1 Exported Constants

None

## 19.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
EnvDataDispHandle			

## 19.4 Semantics

#### 19.4.1 State Variables

displayEnvData: Boolean

#### 19.4.2 Environment Variables

Mouse

## 19.4.3 Assumptions

None

#### 19.4.4 Access Routine Semantics

 ${\bf EnvDataDispHandle():}$ 

- transition: displayEnvData := ¬ displayEnvData
- output: None

• exception: None

## 19.4.5 Local Functions

# 20 MIS of Show Tree Parameter Button Controller (M15)

#### 20.1 Module

Show Tree Param Button Controller

## **20.2** Uses

UnityEngine UnityEngine.UI

## 20.3 Syntax

## 20.3.1 Exported Constants

None

## 20.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
TreeParamDispHandle			

## 20.4 Semantics

#### 20.4.1 State Variables

isActive: Boolean

## 20.4.2 Environment Variables

Mouse

## 20.4.3 Assumptions

None

#### 20.4.4 Access Routine Semantics

TreeParamDispHandle():

• transition: isActive :=  $\neg$  isActive

• output: None

# 20.4.5 Local Functions

# 21 MIS of Environmental Selection Button Controller (M16)

## 21.1 Module

 ${\bf EnvData Selection Button Controller}$ 

## **21.2** Uses

UnityEngine UnityEngine.UI

## 21.3 Syntax

## 21.3.1 Exported Constants

None

## 21.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
displayEnvSel			

## 21.4 Semantics

#### 21.4.1 State Variables

isActive: Boolean

## 21.4.2 Environment Variables

Mouse

## 21.4.3 Assumptions

None

#### 21.4.4 Access Routine Semantics

displayEnvSel():

• transition: is Active :=  $\neg$  is Active

• output: None

# 21.4.5 Local Functions

# 22 MIS of Data Type Selection Buttons Controller (M17)

#### **22.1** Module

 ${\bf Data Type Selection Buttons Controller}$ 

## 22.2 Uses

UnityEngine UnityEngine.UI

## 22.3 Syntax

## 22.3.1 Exported Constants

None

## 22.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
displayDataTypeSel			

## 22.4 Semantics

#### 22.4.1 State Variables

isActive: Boolean

## 22.4.2 Environment Variables

Mouse

## 22.4.3 Assumptions

None

#### 22.4.4 Access Routine Semantics

displayDataTypeSel():

• transition: is Active :=  $\neg$  is Active

• output: None

## 22.4.5 Local Functions

# 23 MIS of Save Button Controller(M18)

## 23.1 Module

Save Button Controller

## 23.2 Uses

UnityEngine UnityEngine.UI M19

## 23.3 Syntax

## 23.3.1 Exported Constants

None

## 23.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick	mouse click		
Save	updatedData: float		

## 23.4 Semantics

#### 23.4.1 State Variables

originalData: float updatedData: float

#### 23.4.2 Environment Variables

Mouse

## 23.4.3 Assumptions

None

#### 23.4.4 Access Routine Semantics

Save():

• transition: originalData := updatedData

• output: None

• exception: None

## 23.4.5 Local Functions

# 24 MIS of File Writer(M19)

## 24.1 Module

FileWriter

## 24.2 Uses

UnityEngine UnityEngine.UI TMPro System.IO Newtonsoft.Json

## 24.3 Syntax

## 24.3.1 Exported Constants

None

## 24.3.2 Exported Access Programs

Name	In	Out	Exceptions
Awake			
updateHandler			InvalidInput
writeFile	inputText: String		

## 24.4 Semantics

#### 24.4.1 State Variables

indicator: Forest data type of the input

inputField: Textbox of the input inputText: input to the textbox

notify: text FR: FileReader JSON file

## 24.4.2 Environment Variables

#### 24.4.3 Assumptions

None

#### 24.4.4 Access Routine Semantics

Awake():

- transition: notify := NULL
- output: None
- exception: None

updateHandler():

- transition: notify := "Updated" inputField := NULL Update the JSON file if the input is valid.
- output: None
- exception:  $inputText == NULL \lor inputText \in \{(a, A), (z, Z)\}$  writeFile(inputText):
  - transition: Use inputText to update the JSON files
  - output: None
  - exception:  $inputText == NULL \lor inputText \in \{(a, A), (z, Z)\}$

#### 24.4.5 Local Functions

removemsg():

- transition: notify := NULL
- output: None
- ullet exception: None

isValid(s: string):

• transition: None

• output: Boolean

• exception: None

isIN(target: char, pool: char[]):

• transition: None

• output: Boolean

# 25 MIS of File Reader(M20)

#### 25.1 Module

FileWriter

## 25.2 Uses

UnityEngine UnityEngine.UI TMPro System.IO Newtonsoft.Json

## 25.3 Syntax

## 25.3.1 Exported Constants

None

## 25.3.2 Exported Access Programs

Name	In	Out	Exceptions
readEnvData			
readTreeParam			
clearText			

## 25.4 Semantics

## 25.4.1 State Variables

indicator: Forest data type of the input

JsonModelObj:

currentValueDisp: Output shown JSON file

#### 25.4.2 Environment Variables

None

## 25.4.3 Assumptions

#### 25.4.4 Access Routine Semantics

## readEnvData():

- transition: filePath := "./dataCenter/plot" + plotNumber.ToString() + "data.json"; plotJsonData := File.ReadAllText(filePath); JsonModelObj := Newtonsoft.Json.JsonConvert.DeserializeObject;JsonModel¿(plotJsonData); EnvDataType := indicator.EnvDataType; currentValueDisp.text := currentValueDisp.text + JasonModelObj.envDataType.EnvDataType
- output: None
- exception: None

## readTreeParam():

- transition: filePath := "./dataCenter/plot" + plotNumber.ToString() + "data.json";
  plotJsonData := File.ReadAllText(filePath);
  JsonModelObj := Newtonsoft.Json.JsonConvert.DeserializeObject;JsonModel¿(plotJsonData);
  TreeType := indicator.TreeType;
  TreeParamType := indicator.TreeParamType;
  currentValueDisp.text := currentValueDisp.text + JasonModelObj.TreeType.TreeParamType
- output: None
- exception: None

## clearText():

- transition: currentValueDisp.text := None;
- output: None
- exception: None

#### 25.4.5 Local Functions

# 26 MIS of Season Change Controller(M21)

## 26.1 Module

 ${\bf Season Change Controller}$ 

## **26.2** Uses

UnityEngine UnityEngine.UI treePlantingController SeasonChangeButtonController

## 26.3 Syntax

## 26.3.1 Exported Constants

None

## 26.3.2 Exported Access Programs

Name	In	Out	Exceptions
Awake			
changeSeason			

## 26.4 Semantics

#### 26.4.1 State Variables

haveLeaves: If the trees have leaves

seasonChangeBut: Season Change button Snow: Particle System for snowing effects

#### 26.4.2 Environment Variables

None

## 26.4.3 Assumptions

None

#### 26.4.4 Access Routine Semantics

Awake():

• transition: seasonChangeBut.image.sprite := summerImage; Snow.gameObject.SetActive(false)

• output: None

• exception: None

# changeSeason():

transition: haveLeaves := !haveLeaves;
 (haveLeaves ⇒ Snow.gameObject.SetActive(false) ∧ (seasonChangeBut.image.sprite := summerImage));
 (!haveLeaves ⇒ Snow.gameObject.SetActive(true) ∧ (seasonChangeBut.image.sprite := winterImage))

• output: None

• exception: None

## 26.4.5 Local Functions

# 27 MIS of move Panel Controller(M22)

#### **27.1** Module

movePanelController

## 27.2 Uses

## 27.3 Syntax

## 27.3.1 Exported Constants

None

## 27.3.2 Exported Access Programs

Name	In	Out	Exceptions
myClick			
Update			

# 27.4 Semantics

#### 27.4.1 State Variables

#### 27.4.2 Environment Variables

```
float speed = 2000f;
float speed2 = -2000f;
bool isActive = false;
bool isShown = false;
bool isActive2 = false;
bool isShown2 = false;
int l_boundary = -400;
int r_boundary = 350;
int l_boundary2 = 3100;
int r_boundary2 = 3850;
GameObject go;
GameObject go2;
```

## 27.4.3 Assumptions

#### 27.4.4 Access Routine Semantics

myClick():

```
    transition: (atBoundary() ⇒ (isActive := true ∧ isShown := false))
    ∧(!atBoundary() ⇒ (isActive := false ∧ isShown := true))
```

• output: None

• exception: None

Update():

```
• transition: ((isActive \land !isShown) \Longrightarrow go.transform.Translate(speed * Time.deltaTime, 0, 0) \land ((go.transform.position.x \leqslant r_boundary) \Longrightarrow (isShown:=true)))
```

```
((!isActive \land !isShown) \implies go.transform.Translate(-speed * Time.deltaTime, 0, 0); \land ((go.transform.position.x \le l_boundary) \implies (isShown:=true)))
```

```
((isActive2 \land !isShown2) \implies go2.transform.Translate(speed2 * Time.deltaTime, 0, 0) \land ((go2.transform.position.x \leqslant l_boundary2) \implies (isShown:=true)))
```

```
 \begin{array}{ll} ((!isActive2 \land !isShown2) \implies go2.transform.Translate(-speed2 * Time.deltaTime, 0, 0); \land ((go2.transform.position.x \leqslant r\_boundary2) \implies (isShown:=true))) \end{array}
```

• output: None

• exception: None

#### 27.4.5 Local Functions

 ${\rm atBoundary}()\colon$ 

- transition: x := go.transform.position.x
- output:  $x \leq 1$ -boundary
- exception: None

# 28 MIS of Tree Planting Controller(M23)

## **28.1** Module

tree Planting Controller

## 28.2 Uses

UnityEngine UnityEngine.UI seasonController

# 28.3 Syntax

## 28.3.1 Exported Constants

None

## 28.3.2 Exported Access Programs

Name	In	Out	Exceptions
plantTrees	plotNumberIndex		
cleanTrees			

## 28.4 Semantics

#### 28.4.1 State Variables

#### 28.4.2 Environment Variables

#### Related measures in unity tree editor:

double redPineHSR = 25.0; double oakHSR = 17.2 / 2; double beechHSR = 35.47 / 2; double birchHSR = 22.18 / 2; double redMapleHSR = 14.12 / 2; double whitePineHSR = 64.4 / 2; double redOakHSR = 18.95 / 2

#### Plot Information:

double sideLength = 100.0; float startingCoordinate = 1f; float endingCoordinate = 99f

### Collection of tree positions:

Vector3[] treelocal

#### Treefabs with leaves:

List < GameObject > treeprefabsWL

#### Treefabs without leaves:

List < GameObject > treeprefabsWOL

ListOfCircles circles[plotNumberIndex]

#### 28.4.3 Assumptions

None

#### 28.4.4 Access Routine Semantics

plantTrees(plotNumberIndex):

- transition: generateCircleLocation(circles(plotNumberIndex),differentTreeNumbers.Sum());
  (seasonController.haceLeaves ⇒ treeprefabWL);
  (!seasonController.haveLeaves ⇒ treeprefabWOL);
  (∀ species ⇒ standardScale := data.species.Height/HSR ∧ lowerBound := 0.9 \* standardScale ∧ upperBound := 1.1 \* standardScale);
  (∀ species ⇒ trees.Add(Instantiate(treeprefabs | treeinstance.transform.localscale = Vectror3(randomScale, randomScale, randomScale)))
- output: None
- exception: None

cleanTrees():

- transition:  $\forall$  tree  $\in$  trees  $\Longrightarrow$  Destroy(tree);
- output: None
- exception: None

#### 28.4.5 Local Functions

calculatedTreeNumbers():

• transition: area := sideLength \*sideLength; (int) tree numbers =  $\sum_{species}$  density\*area • output: treenumbers

• exception: None

generateSquareLocation(numberOfPoints):

• transition: treelocal[i] = Vector3(UnityEngine.Random.Range(startingCoordinate, endingCoordinate), 0f, UnityEngine.Random.Range(startingCoordinate, endingCoordinate))

• output: None

• exception: None

generateCirculeLocation(List;Circle; circles, int numberOfPoints):

• transition: Point randomPoint := Point(UnityEngine.Random.Range(startingCoordinate, endingCoordinate), UnityEngine.Random.Range(startingCoordinate, endingCoordinate)); (isPointInCircle  $\implies$  treelocal[i] = Vector3((float)randomPoint.getX(),0f, (float) randomPoint.getY()));

• output: None

• exception: None

isPointInCircles(List< Circle > circles, Point point):

• transition: None

• output:  $(\exists \text{ circle} \in \text{circles} \mid \text{circle.isIn}(\text{point}) = \text{true})$ 

• exception: None

# 29 MIS of Tree Switch Button Controller(M24)

#### **29.1** Module

Tree Switch Button Controller

## 29.2 Uses

UnityEngine UnityEngine.UI

## 29.3 Syntax

## 29.3.1 Exported Constants

None

## 29.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick			

## 29.4 Semantics

#### 29.4.1 State Variables

isActive: Boolean value indicating if the leaf information page is active.

#### 29.4.2 Environment Variables

None

#### 29.4.3 Assumptions

None

#### 29.4.4 Access Routine Semantics

onClick():

• transition: isActive := !isActive

• output: None

• exception: None

# 29.4.5 Local Functions

# 30 MIS of Pie Chart Button Controller(M25)

## 30.1 Module

pie Chart Button Controller

## **30.2** Uses

UnityEngine UnityEngine.UI

## 30.3 Syntax

# 30.3.1 Exported Constants

None

# 30.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick			

## 30.4 Semantics

#### 30.4.1 State Variables

is Active: Boolean value indicating if the pie chart is active.

#### 30.4.2 Environment Variables

None

## 30.4.3 Assumptions

None

#### 30.4.4 Access Routine Semantics

onClick():

• transition: isActive := !isActive

• output: None

• exception: None

# 30.4.5 Local Functions

# 31 MIS of Pie Chart Controller(M26)

#### 31.1 Module

pieChartController

## 31.2 Uses

pieChartButtonController UnityEngine UnityEngine.UI

## 31.3 Syntax

# 31.3.1 Exported Constants

None

## 31.3.2 Exported Access Programs

Name	In	Out	Exceptions
ChangeView			
markChart			

## 31.4 Semantics

#### 31.4.1 State Variables

isActive: Boolean value indicating if the pie chart is active.

#### 31.4.2 Environment Variables

GameObject graph Image legend EnvDataDisp

## Data and Image for generating pieChart:

DataModel data

Image regPinePortion

Image oakPortion

Image beechPortion

Image birchPortion

Image redMaplePortion

Image whitePinePortion

Image redOakPortion

GameObject parentObject

### 31.4.3 Assumptions

None

### 31.4.4 Access Routine Semantics

ChangeView():

- transition: graph.gameObejct.SetActive(!isActive) ∧ legend.gameObject.SetActive(!isActive)
   ∧ EnvDataDisp.gameObject.SetActive(isActive);
   isActive := !isActive
- output: None
- exception: None

markChart():

- transition: calculateValues(); setImagePortions()
- output: None
- exception: None

#### 31.4.5 Local Functions

calculateValues():

- transition: percentage<sub>species</sub> := number<sub>species</sub> /  $\sum_{allspecies}$  number
- output: None
- exception: None

setImagePortions():

transition: pos := Vector3(150f,200f,0f);
size := Vector2(600f, 600f);
∀ species ⇒ (Portion<sub>species</sub>.transform.locakPosition := pos
∧ Portion<sub>species</sub>.rectTransform.sizeData := size
∧ Portion<sub>species</sub>.fillAmount:= percentage<sub>species</sub>
∧ Portion<sub>species</sub>.transform.rotation := Quaternion.Euler (Vector3 (0f, 0f, totalRot))
∧ totalRot := totalRot(percentage<sub>species</sub>))

• output: None

• exception: None

# 32 MIS of Season Change Button Controller (M27)

## 32.1 Module

Season Change Button Controller

**32.2** Uses

# 32.3 Syntax

# 32.3.1 Exported Constants

None

## 32.3.2 Exported Access Programs

Name	In	Out	Exceptions
onClick			

#### 32.4 Semantics

#### 32.4.1 State Variables

is Active: Boolean value indicating if the current season is summer.

#### 32.4.2 Environment Variables

None

#### 32.4.3 Assumptions

None

#### 32.4.4 Access Routine Semantics

onClick():

• transition: isActive := !isActive

• output: None

• exception: None

#### 32.4.5 Local Functions

# 33 MIS of Tree Switch Controller(M28)

### 33.1 Module

TreeSwitchController

### **33.2** Uses

UnityEngine
UnityEngine.UI
TreeSwitchButtonController

# 33.3 Syntax

#### 33.3.1 Exported Constants

None

### 33.3.2 Exported Access Programs

Name	In	Out	Exceptions
ChangeView			

## 33.4 Semantics

## 33.4.1 State Variables

isActive: Boolean value indicating if leaf information is active.

TreeParamDisplay: UI of Tree parameters display. LeafInfoDisplay: UI of Leaf information display.

#### 33.4.2 Environment Variables

None

## 33.4.3 Assumptions

None

#### 33.4.4 Access Routine Semantics

ChangeView():

• transition: (isActive  $\implies$  (LeafInfoDisplay.gameObject.SetActive(false)  $\land$  TreeParamDisplay.gameObject.SetActive(true);

 $(!isActive \implies (LeafInfoDisplay.gameObject.SetActive(true) \land TreeParamDisplay.gameObject.SetActive(true) \land TreePar$ 

isActive := !isActive

• output: None

• exception: None

# 33.4.5 Local Functions

# 34 MIS of Forest Trees (M29)

## 34.1 Module

ForestTrees

# **34.2** Uses

M32, M33, M34, M35, M36, M37, M38

# 34.3 Syntax

## 34.3.1 Exported Constants

None

# 34.3.2 Exported Access Programs

Name	In	Out	Exceptions
new ForestTrees		ForestTree	
addTree	GameObject(This is		
	unity built-in type)		
deleteTree			

## 34.4 Semantics

#### 34.4.1 State Variables

 $trees: GameObject\{\}$ 

### 34.4.2 Environment Variables

None

# 34.4.3 Assumptions

None

#### 34.4.4 Access Routine Semantics

new ForestTrees():

• transition: None

• output: out := self

• exception: None

# addTree(tree):

• transition:  $trees := trees \cup tree$ 

• output: None

• exception: None

# DeleteTree(s):

 $\bullet \ \ \text{transition:} \ \forall tree: GameObject| tree \in trees: tree.destory()$ 

• output: None

• exception: None

# 34.4.5 Local Functions

# 35 MIS of Forest Sky (M30)

### 35.1 Module

SkyBox

## 35.2 Uses

UnityLightning

# 35.3 Syntax

## 35.3.1 Exported Constants

None

## 35.3.2 Exported Access Programs

Name	In	Out	Exceptions
new ForestSky		ForestSky	
setSkyBox	Unity Texture		

## 35.4 Semantics

#### 35.4.1 State Variables

None

#### 35.4.2 Environment Variables

SkyTexture: imported picture of the skybox.

## 35.4.3 Assumptions

Unity only takes valid texture file type as input.

## 35.4.4 Access Routine Semantics

new ForestSky()

• transition: None

• output: None

• exception: None

# SetSkybox(s):

• transition: set the current skybox to the selected texture file.

• output: None

• exception: None

# 35.4.5 Local Functions

# 36 MIS of Forest Terrain (M31)

#### 36.1 Module

ForestTerrain

## 36.2 Uses

Unity Terrain Tool

# 36.3 Syntax

## 36.3.1 Exported Constants

None

# 36.3.2 Exported Access Programs

Name	In	Out	Exceptions
new ForestTer-		ForestTerrain	
rain			
setLength	Double		
setWidth	Double		

## 36.4 Semantics

#### 36.4.1 State Variables

None

### 36.4.2 Environment Variables

None

# 36.4.3 Assumptions

None

#### 36.4.4 Access Routine Semantics

new ForestTerrain():

- transition: Create a new terrain in unity using the terrain tool
- output: None

• exception: None

# setLenght(x):

• transition: set the length of the terrain to be x meters

• output: None

• exception: None

# setWidth(x):

• transition: set the width of the terrain to be x meters

• output: None

• exception: None

# 36.4.5 Local Functions

We want to address the following two points regarding creating different modules for different tree types:

- We created different modules for different types of trees because this is necessary when it comes to reading from JSON files by using the newtonsoft parser.
- Also, we deleted the "is ValidString" local function here since we will check the validity of the string when users input from the GUI

# 37 MIS of Red Pine (M32)

# 37.1 Module

RedPine

#### 37.2 Uses

None

# 37.3 Syntax

## 37.3.1 Exported Constants

None

## 37.3.2 Exported Access Programs

Name	In	Out	Exceptions
new RedPine		RedPine	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

## 37.4 Semantics

## 37.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

#### 37.4.2 Environment Variables

None

## 37.4.3 Assumptions

None

#### 37.4.4 Access Routine Semantics

new RedPine():

- transition: Treename, Density, DBH, Height, Age := "Red Pine", "", "", "", ""
- output: out := self
- exception: None

getTreeName():

- transition: None
- output: out := Treename
- exception: None

setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

getDensity():

• transition: None

- output: out := Density
- exception: None

# setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH
- exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

## setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

## getAge():

- transition: None
- output: out := Age
- exception: None

### 37.4.5 Local Functions

# 38 MIS of Oak (M33)

# 38.1 Module

Oak

# 38.2 Uses

None

# 38.3 Syntax

# 38.3.1 Exported Constants

None

# 38.3.2 Exported Access Programs

Name	In	Out	Exceptions
new Oak		Oak	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 38.4 Semantics

## 38.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 38.4.2 Environment Variables

#### 38.4.3 Assumptions

None

#### 38.4.4 Access Routine Semantics

new Oak():

- transition: Treename, Density, DBH, Height, Age := "Oak", "", "", "", ""
- output: out := self
- exception: None

getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

getDensity():

- transition: None
- output: out := Density
- exception: None

setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

### 38.4.5 Local Functions

# 39 MIS of Beech (M34)

# 39.1 Module

Beech

39.2 Uses

None

39.3 Syntax

39.3.1 Exported Constants

None

# 39.3.2 Exported Access Programs

Name	In	Out	Exceptions
new Beech		Beech	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 39.4 Semantics

# 39.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 39.4.2 Environment Variables

#### 39.4.3 Assumptions

None

#### 39.4.4 Access Routine Semantics

```
new Beech():
```

- transition: Treename, Density, DBH, Height, Age := "Beech", "", "", "", ""
- output: out := self
- exception: None

## getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

## setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

## getDensity():

- transition: None
- output: out := Density
- exception: None

#### setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

#### 39.4.5 Local Functions

# 40 MIS of Birch (M35)

# 40.1 Module

Birch

40.2 Uses

None

40.3 Syntax

40.3.1 Exported Constants

None

# 40.3.2 Exported Access Programs

Name	In	Out	Exceptions
new Birch		Birch	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 40.4 Semantics

## 40.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 40.4.2 Environment Variables

#### 40.4.3 Assumptions

None

#### 40.4.4 Access Routine Semantics

```
new Birch():
```

- transition: Treename, Density, DBH, Height, Age := "Birch", "", "", "", ""
- output: out := self
- exception: None

## getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

## setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

## getDensity():

- transition: None
- $\bullet$  output: out := Density
- exception: None

#### setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

#### 40.4.5 Local Functions

# 41 MIS of White Pine (M36)

## 41.1 Module

WhitePine

# 41.2 Uses

None

# 41.3 Syntax

## 41.3.1 Exported Constants

None

# 41.3.2 Exported Access Programs

Name	In	Out	Exceptions
new WhitePine		WhitePine	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 41.4 Semantics

#### 41.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 41.4.2 Environment Variables

#### 41.4.3 Assumptions

None

#### 41.4.4 Access Routine Semantics

```
new WhitePine():
```

- transition: Treename, Density, DBH, Height, Age := "White Pine", "", "", "", ""
- output: out := self
- exception: None

## getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

### setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

## getDensity():

- transition: None
- $\bullet$  output: out := Density
- exception: None

#### setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

### 41.4.5 Local Functions

# 42 MIS of Red Maple (M37)

# 42.1 Module

RedMaple

# **42.2** Uses

None

# 42.3 Syntax

# 42.3.1 Exported Constants

None

# 42.3.2 Exported Access Programs

Name	In	Out	Exceptions
new RedMaple		RedMaple	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 42.4 Semantics

## 42.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 42.4.2 Environment Variables

### 42.4.3 Assumptions

None

#### 42.4.4 Access Routine Semantics

```
new RedMaple():
```

- transition: Treename, Density, DBH, Height, Age := "Red Maple", "", "", "", ""
- output: out := self
- exception: None

# getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

## setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

## getDensity():

- transition: None
- output: out := Density
- exception: None

#### setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

#### 42.4.5 Local Functions

# 43 MIS of Red Oak (M38)

# 43.1 Module

RedOak

# 43.2 Uses

None

# 43.3 Syntax

# 43.3.1 Exported Constants

None

# 43.3.2 Exported Access Programs

Name	In	Out	Exceptions
new RedOak		RedOak	
getTreeName		String	
setDensity	String		
getDensity		String	
setDBH	String		
getDBH		String	
setHeight	String		
getHeight		String	
setAge	String		
getAge		String	

# 43.4 Semantics

## 43.4.1 State Variables

Treename: String
Density: String
DBH: String
Height: String
Age: String

## 43.4.2 Environment Variables

#### 43.4.3 Assumptions

None

#### 43.4.4 Access Routine Semantics

```
new RedOak():
```

- transition: Treename, Density, DBH, Height, Age := "Red Oak", "", "", "", ""
- output: out := self
- exception: None

# getTreeName():

- transition: None
- $\bullet$  output: out := Treename
- exception: None

## setDensity(newDensity):

- transition: Density := newDensity
- output: None
- exception: None

## getDensity():

- transition: None
- $\bullet$  output: out := Density
- exception: None

#### setDBH(newDBH):

- transition: DBH := newDBH
- output: None
- exception: None

# getDBH():

- transition: None
- output: out := DBH

• exception: None

# setHeight(newHeight):

- transition: Height := newHeight
- output: None
- exception: None

# getHeight():

- transition: None
- output: out := Height
- exception: None

# setAge(newAge):

- transition: Age := newAge
- output: None
- exception: None

# getAge():

- transition: None
- output: out := Age
- exception: None

### 43.4.5 Local Functions

We deleted "is ValidString" local function here because we will check the validity of string when users enter data from the GUI

# 44 MIS of Environmental Data (M39)

# 44.1 Module

EnvData

# 44.2 Uses

None

# 44.3 Syntax

# 44.3.1 Exported Constants

None

# 44.3.2 Exported Access Programs

Name	In	Out	Exceptions
new EnvData		EnvData	
setHumidity	String		
getHumidity		String	
setTemp	String		
getTemp		String	
setSC	String		
getSC		String	
setSN	String		
getSN		String	
setLAI	String		
getLAI		String	

## 44.4 Semantics

#### 44.4.1 State Variables

Humility: String
Temp: String
SC: String
SN: String
LAI: String

#### 44.4.2 Environment Variables

None

# 44.4.3 Assumptions

None

#### 44.4.4 Access Routine Semantics

new EnvData():

- transition: Humidity, Temp, SC, SN, LAI := "", "", "", "", ""
- output: out := self
- exception: None

getHumidity():

- transition: None
- output: out := Humidity
- exception: None

setHumidity(newHumidity):

- transition: Humidity := newHumidity
- output: None
- exception: None

getTemp():

- transition: None
- $\bullet$  output: out := Temp
- exception: None

setTemp(newTemp):

- transition: Temp := newTemp
- output: None
- exception: None

getSC():

- transition: None
- output: out := SC
- exception: None

# setSC(newSC):

- transition: SC := newSC
- output: None
- exception: None

# getSN():

- transition: None
- output: out := SN
- exception: None

# setSN(newSN):

- transition: SN := newSN
- output: None
- exception: None

# getLAI():

- transition: None
- output: out := LAI
- exception: None

# setLAI(newLAI):

- transition: LAI := newLAI
- output: None
- exception: None

#### 44.4.5 Local Functions

# 45 MIS of Plot Data (M40)

# 45.1 Module

PlotData

# 45.2 Uses

M32, M33, M34, M35, M36, M37, M38, M39

# 45.3 Syntax

# 45.3.1 Exported Constants

None

# 45.3.2 Exported Access Programs

Name	In	Out	Exceptions
new PlotData		PlotData	
setRedPineObj	RedPine		
getRedPineObj		RedPine	
setOakObj	Oak		
getOakObj		Oak	
setBeechObj	Beech		
getBeechObj		Beech	
setBirchObj	Birch		
getBirchObj		Birch	
setWhitePineObj	WhitePine		
getWhitePineObj		WhitePine	
setRedMapleObj	RedMaple		
getRedMapleObj		RedMaple	
setRedOakObj	RedOak		
getRedOakObj		RedOak	
setEnvDataObj	EnvData		
getEnvDataObj		EnvData	

# 45.4 Semantics

## 45.4.1 State Variables

RedPineObj: RedPine

OakObj : Oak BeechObj : Beech BirchObj : Birch

WhitePineObj: WhitePine RedMapleObj: RedMaple RedOakObj: RedOak EnvDataObj: EnvData

#### 45.4.2 Environment Variables

None

# 45.4.3 Assumptions

None

### 45.4.4 Access Routine Semantics

new PlotData():

- transition:
  - RedPineObj, OakObj, BeechObj, BirchObj := null, null, null, null
  - WhitePineObj, RedMapleObj, RedOakObj, EvnDataObj := null, null, null, null
- output: out := self
- exception: None

getRedPineObj():

- transition: None
- output: out := RedPineObj
- exception: None

setRedPineObj(newRedPineObj):

- transition: RedPineObj := newRedPineObj
- output: None

• exception: None

# getOakObj():

- transition: None
- output: out := OakObj
- exception: None

## setOakObj(newOakObj):

- transition: OakObj := newOakObj
- output: None
- exception: None

# getBeechObj():

- transition: None
- output: out := BeechObj
- exception: None

# setBeechObj(newBeechObj):

- transition: BeechObj := newBeechObj
- output: None
- exception: None

## getBirchObj():

- transition: None
- output: out := BirchObj
- exception: None

# setBirchObj(newBirchObj):

- transition: BirchObj := newBirchObj
- output: None
- exception: None

## getWhitePineObj():

- transition: None
- output: out := WhitePineObj
- exception: None

# setWhitePineObj(newWhitePineObj):

- $\bullet$  transition: WhitePineObj := newWhitePineObj
- output: None
- exception: None

# getRedMapleObj():

- transition: None
- output: out := RedMapleObj
- exception: None

## setRedMapleObj(newRedMapleObj):

- transition: RedMapleObj := newRedMapleObj
- output: None
- exception: None

# getRedOakObj():

- transition: None
- output: out := RedOakObj
- exception: None

# setRedOakObj(newRedOakObj):

- transition: RedOakObj := newRedOakObj
- output: None
- exception: None

## getEnvDataObj():

- transition: None
- output: out := EnvDataObj

• exception: None

setEnvDataObj (newEnvDataObj) :

• transition: EnvDataObj := newEnvDataObj

• output: None

• exception: None

# 45.4.5 Local Functions

# 46 MIS of First Person Player (M41)

# 46.1 Module

FirstPersonPlayer

# 46.2 Uses

Character Controller Module from Unity

# 46.3 Syntax

This is a module provided by UnityEngine.UI. Please click here to check offical document from Unity. We have designed a controller for this module. The controller is PlayerMovement(M4).

## 46.4 Semantics

This is a module provided by UnityEngine.UI. Please click here to check offical document from Unity. We have designed a controller for this module. The controller is PlayerMovement(M4).

# 47 MIS of Json File (M42)

## 47.1 Module

JsonFile. This is not a typical class. This section only aims to show how JSON files are organized formally.

# 47.2 Local Type

```
X = tuple(key : String, value : String) \land isValidString(value)
S : set \ of \ X
TreeANDEnvData = tuple(key : String, \ values : S)
```

#### 47.3 State Variables

 $JsonFile: set\ of\ TreeANDEnvData$ 

# 47.4 Example

• First, define all the tuples that have type X.

$$-x_{1} = ("DBH", "10") : X$$

$$-x_{2} = ("Age", "10") : X$$

$$-x_{3} = ("Height", "10") : X$$

$$-x_{4} = ("Density", "10") : X$$

$$-x_{5} = ("DBH", "20") : X$$

$$-x_{6} = ("Age", "20") : X$$

$$-x_{7} = ("Height", "20") : X$$

$$-x_{8} = ("Density", "20") : X$$

$$-x_{9} = ("DBH", "30") : X$$

$$-x_{10} = ("Age", "30") : X$$

$$-x_{11} = ("Height", "30") : X$$

$$-x_{12} = ("Density", "30") : X$$

$$-x_{13} = ("DBH", "40") : X$$

$$-x_{14} = ("Age", "40") : X$$

$$-x_{15} = ("Height", "40") : X$$

$$-x_{16} = ("Density", "40") : X$$

$$-x_{17} = ("DBH", "50") : X$$

$$-x_{18} = ("Age", "50") : X$$

$$-x_{19} = ("Height", "50") : X$$

$$-x_{20} = ("Density", "50") : X$$

$$-x_{21} = ("DBH", "60") : X$$

$$-x_{22} = ("Age", "60") : X$$

$$-x_{23} = ("Height", "60") : X$$

$$-x_{24} = ("Density", "60") : X$$

$$-x_{25} = ("DBH", "70") : X$$

$$-x_{26} = ("Age", "70") : X$$

$$-x_{27} = ("Height", "70") : X$$

$$-x_{28} = ("Density", "70") : X$$

$$-x_{29} = ("Humility", "10") : X$$

$$-x_{30} = ("Temperature", "20") : X$$

 $\bullet$  Second, define all the sets that have type S

 $-x_{31} = ("SC", "10") : X$   $-x_{32} = ("SN", "95") : X$   $-x_{33} = ("LAI", "95") : X$ 

 $- s_1 = \{x_1, x_2, x_3, x_4\} : S$   $- s_2 = \{x_5, x_6, x_7, x_8\} : S$   $- s_3 = \{x_9, x_{10}, x_{11}, x_{12}\} : S$   $- s_4 = \{x_{13}, x_{14}, x_{15}, x_{16}\} : S$   $- s_5 = \{x_{17}, x_{18}, x_{19}, x_{20}\} : S$   $- s_6 = \{x_{21}, x_{22}, x_{23}, x_{24}\} : S$   $- s_7 = \{x_{25}, x_{26}, x_{27}, x_{28}\} : S$   $- s_8 = \{x_{29}, x_{30}, x_{31}, x_{32}, x_{33}\} : S$ 

• Third, define all the tuples that have type TreeANDEnvData.

```
-d_1 = ("RedPineData", s_1) : TreeANDEnvData
-d_2 = ("OakData", s_2) : TreeANDEnvData
-d_3 = ("BeechData", s_3) : TreeANDEnvData
-d_4 = ("BirchData", s_4) : TreeANDEnvData
-d_5 = ("WhitePineData", s_5) : TreeANDEnvData
-d_6 = ("RedMapleData", s_6) : TreeANDEnvData
-d_7 = ("RedOakData", s_7) : TreeANDEnvData
-d_8 = ("EnvData", s_8) : TreeANDEnvData
```

• Finally,  $JsonFile = \{d_1, d_2, d_3, d_4, d_5, d_6, d_7, d_8\}.$ 

# 47.5 Local Functions

```
\label{eq:ValidCharacters} \begin{split} & \text{ValidCharacters} = \{\text{``1''}, \text{``2''}, \text{``3''}, \text{``4''}, \text{``5''}, \text{``6''}, \text{``7''}, \text{``8''}, \text{``9''}, \text{``0''}, \text{``.''}\} \\ & \text{isValidString}(\mathbf{S}) : \text{String} \to \mathbb{B} \\ & \text{isValidString}(\mathbf{S}) = \forall (i: \mathbb{Z}|0 \leq i < |S|: S[i] \in \text{ValidCharacters}) \end{split}
```

# 48 MIS of Main Page (M43)

## 48.1 Module

MainPageDisplay

## 48.2 Uses

M6, M7, M8, M9, M10, M44, M45, M46, M47 UnityEngine.UI

# 48.3 Syntax

## 48.3.1 Exported Constants

None

#### 48.3.2 Exported Access Programs

None

## 48.4 Semantics

This module is used to display the UI of the homepage. You can refer to Unity Canvas Documentation by clicking here.

#### 48.4.1 State Variables

None

#### 48.4.2 Environment Variables

None

#### 48.4.3 Assumptions

None

#### 48.4.4 Access Routine Semantics

None

#### 48.4.5 Local Functions

# 49 MIS of Start Button (M44)

#### **49.1** Module

StartButton

## 49.2 Uses

M6, UnityEngine.UI

# 49.3 Syntax

# 49.3.1 Exported Constants

None

#### 49.3.2 Exported Access Programs

None

## 49.4 Semantics

This module is used to display the UI of the StartButton. You can refer to Unity Button Documentation by clicking here.

#### 49.4.1 State Variables

None

#### 49.4.2 Environment Variables

windows: Computer screen used to display messages.

## 49.4.3 Assumptions

None

#### 49.4.4 Access Routine Semantics

None

#### 49.4.5 Local Functions

# 50 MIS of Instruction Button (M45)

## 50.1 Module

InstructionButton

## 50.2 Uses

M7, UnityEngine.UI

# 50.3 Syntax

## 50.3.1 Exported Constants

None

#### 50.3.2 Exported Access Programs

None

#### 50.4 Semantics

This module is used to display the UI of the InstructionButton. You can refer to Unity Button Documentation by clicking here.

#### 50.4.1 State Variables

None

#### 50.4.2 Environment Variables

windows: Computer screen used to display messages.

## 50.4.3 Assumptions

None

#### 50.4.4 Access Routine Semantics

None

#### 50.4.5 Local Functions

# 51 MIS of Contact Us Button (M46)

## 51.1 Module

ContactUsButton

## 51.2 Uses

M8, UnityEngine.UI

# 51.3 Syntax

## 51.3.1 Exported Constants

None

#### 51.3.2 Exported Access Programs

None

#### 51.4 Semantics

This module is used to display the UI of the ContactUsButton. You can refer to Unity Button Documentation by clicking here.

#### 51.4.1 State Variables

None

#### 51.4.2 Environment Variables

windows: Computer screen used to display messages.

## 51.4.3 Assumptions

None

#### 51.4.4 Access Routine Semantics

None

#### 51.4.5 Local Functions

# 52 MIS of Quit Button (M47)

#### 52.1 Module

QuitButton

## **52.2** Uses

M10 ,UnityEngine.UI

# 52.3 Syntax

# 52.3.1 Exported Constants

None

#### 52.3.2 Exported Access Programs

None

## 52.4 Semantics

This module is used to display the UI of the QuitButton. You can refer to Unity Button Documentation by clicking here.

#### 52.4.1 State Variables

None

#### 52.4.2 Environment Variables

windows: Computer screen used to display messages.

## 52.4.3 Assumptions

None

#### 52.4.4 Access Routine Semantics

None

#### 52.4.5 Local Functions

# 53 MIS of Instruction Page (M48)

## 53.1 Module

InstructionInfoDisplay

## **53.2** Uses

M7, UnityEngine.UI

# 53.3 Syntax

## 53.3.1 Exported Constants

None

#### 53.3.2 Exported Access Programs

None

## 53.4 Semantics

This module is used to display the UI of the instruction page. You can refer to Unity Canvas Documentation by clicking here.

#### 53.4.1 State Variables

None

#### 53.4.2 Environment Variables

windows: Computer screen used to display messages.

## 53.4.3 Assumptions

None

#### 53.4.4 Access Routine Semantics

None

#### 53.4.5 Local Functions

# 54 MIS of Contact Us Page (M49)

#### 54.1 Module

 ${\bf Contact Us In fo Display}$ 

## **54.2** Uses

M9 UnityEngine.UI

# 54.3 Syntax

# 54.3.1 Exported Constants

None

#### 54.3.2 Exported Access Programs

None

### 54.4 Semantics

This module is used to display the UI of the Contact Us page. You can refer to Unity Canvas Documentation by clicking here.

#### 54.4.1 State Variables

None

#### 54.4.2 Environment Variables

windows: Computer screen used to display messages.

## 54.4.3 Assumptions

None

#### 54.4.4 Access Routine Semantics

None

#### 54.4.5 Local Functions

# 55 MIS of Back Button (M50)

#### 55.1 Module

BackButton

## 55.2 Uses

M11, UnityEngine.UI

# 55.3 Syntax

# 55.3.1 Exported Constants

None

#### 55.3.2 Exported Access Programs

None

#### 55.4 Semantics

This module is used to display the UI of the BackButton. You can refer to Unity Button Documentation by clicking here.

#### 55.4.1 State Variables

None

#### 55.4.2 Environment Variables

windows: Computer screen used to display messages.

## 55.4.3 Assumptions

None

#### 55.4.4 Access Routine Semantics

None

#### 55.4.5 Local Functions

# 56 MIS of Update Data Page (M51)

## 56.1 Module

UpdateDataDisplay

## 56.2 Uses

M8 UnityEngine.UI

# 56.3 Syntax

# 56.3.1 Exported Constants

None

#### 56.3.2 Exported Access Programs

None

### 56.4 Semantics

This module is used to display the UI of the Update Data page. You can refer to Unity Canvas Documentation by clicking here.

#### 56.4.1 State Variables

None

#### 56.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 56.4.3 Assumptions

None

#### 56.4.4 Access Routine Semantics

None

#### 56.4.5 Local Functions

# 57 MIS of Environmental Data Selection Button (M52)

### 57.1 Module

EnvDataSelectionButton

## 57.2 Uses

M16, UnityEngine.UI

# 57.3 Syntax

## 57.3.1 Exported Constants

None

#### 57.3.2 Exported Access Programs

None

### 57.4 Semantics

This module is used to display the UI of the EnvDataSelectionButton. You can refer to Unity Button Documentation by clicking here.

#### 57.4.1 State Variables

None

#### 57.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 57.4.3 Assumptions

None

#### 57.4.4 Access Routine Semantics

None

#### 57.4.5 Local Functions

# 58 MIS of Data Type Selection Button (M53)

#### 58.1 Module

 ${\bf Data Type Selection Button}$ 

## 58.2 Uses

M17, UnityEngine.UI

# 58.3 Syntax

## 58.3.1 Exported Constants

None

#### 58.3.2 Exported Access Programs

None

#### 58.4 Semantics

This module is used to display the UI of the DataTypeSelectionButton. You can refer to Unity Button Documentation by clicking here.

#### 58.4.1 State Variables

None

#### 58.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 58.4.3 Assumptions

None

#### 58.4.4 Access Routine Semantics

None

#### 58.4.5 Local Functions

# 59 MIS of New Data Input Box (M54)

# 59.1 Module

New Data Input Box

## 59.2 Uses

, UnityEngine.UI

# 59.3 Syntax

## 59.3.1 Exported Constants

None

#### 59.3.2 Exported Access Programs

None

#### 59.4 Semantics

This module is used to display the UI of the new data input box. You can refer to Unity Input Field Documentation by clicking here

#### 59.4.1 State Variables

None

#### 59.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 59.4.3 Assumptions

None

#### 59.4.4 Access Routine Semantics

None

#### 59.4.5 Local Functions

# 60 MIS of Save Button (M55)

#### 60.1 Module

SaveButton

## 60.2 Uses

M18, UnityEngine.UI

# 60.3 Syntax

## 60.3.1 Exported Constants

None

#### 60.3.2 Exported Access Programs

None

#### 60.4 Semantics

This module is used to display the UI of the SaveButton. You can refer to Unity Button Documentation by clicking here.

#### 60.4.1 State Variables

None

#### 60.4.2 Environment Variables

windows: Computer screen used to display messages.

## 60.4.3 Assumptions

None

#### 60.4.4 Access Routine Semantics

None

#### 60.4.5 Local Functions

# 61 MIS of Current Data Dispaly (M56)

## 61.1 Module

CurrentDataDisplay

## 61.2 Uses

UnityEngine.UI

# 61.3 Syntax

# 61.3.1 Exported Constants

None

#### 61.3.2 Exported Access Programs

None

### 61.4 Semantics

This module is used to display the UI of the current data. You can refer to Unity Text Documentation by clicking here.

#### 61.4.1 State Variables

None

#### 61.4.2 Environment Variables

windows: Computer screen used to display messages.

## 61.4.3 Assumptions

None

#### 61.4.4 Access Routine Semantics

None

#### 61.4.5 Local Functions

# 62 MIS of Plot Selection Drop Down (M57)

#### 62.1 Module

PlotSelection

## 62.2 Uses

M12, UnityEngine.UI

# 62.3 Syntax

## 62.3.1 Exported Constants

None

#### 62.3.2 Exported Access Programs

None

### 62.4 Semantics

This module is used to display the dropdown box of plot selection. You can refer to Unity Drop Down Documentation by clicking here.

#### 62.4.1 State Variables

None

#### 62.4.2 Environment Variables

windows: Computer screen used to display messages.

## 62.4.3 Assumptions

None

#### 62.4.4 Access Routine Semantics

None

#### 62.4.5 Local Functions

# 63 MIS of Tree Type Selection Drop Down (M58)

#### 63.1 Module

 ${\bf Tree Type Selection}$ 

## 63.2 Uses

M13, UnityEngine.UI

# 63.3 Syntax

# 63.3.1 Exported Constants

None

#### 63.3.2 Exported Access Programs

None

## 63.4 Semantics

This module is used to display the dropdown box of the tree type selection. You can refer to Unity Drop Down Documentation by clicking here.

#### 63.4.1 State Variables

None

#### 63.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 63.4.3 Assumptions

None

#### 63.4.4 Access Routine Semantics

None

#### 63.4.5 Local Functions

# 64 MIS of Update Data Button (M59)

## 64.1 Module

UpdateDataButton

## 64.2 Uses

M8, UnityEngine.UI

# 64.3 Syntax

# 64.3.1 Exported Constants

None

## 64.3.2 Exported Access Programs

None

### 64.4 Semantics

The module is used to display the UI of UpdateDataButton. You can refer to Unity Button Documentation by clicking here.

#### 64.4.1 State Variables

None

#### 64.4.2 Environment Variables

windows: Computer screen used to display messages.

## 64.4.3 Assumptions

None

#### 64.4.4 Access Routine Semantics

None

#### 64.4.5 Local Functions

# 65 MIS of Forest Dispaly (M60)

#### 65.1 Module

ForestDisplay

# 65.2 Uses

UnityEngine.UI, M29, M30, M31

# 65.3 Syntax

## 65.3.1 Exported Constants

None

# 65.3.2 Exported Access Programs

None

## 65.4 Semantics

#### 65.4.1 State Variables

This module is used to display the forest models.

# 65.4.2 Environment Variables

windows: Computer screen used to display messages.

## 65.4.3 Assumptions

None

#### 65.4.4 Access Routine Semantics

None

#### 65.4.5 Local Functions

# 66 MIS of Show Environmental Data Button (M61)

# 66.1 Module

ShowEnvDataButton

## 66.2 Uses

M14, UnityEngine.UI

# 66.3 Syntax

# 66.3.1 Exported Constants

None

#### 66.3.2 Exported Access Programs

None

### 66.4 Semantics

This module is used to display the UI of the ShowEnvDataButton. You can refer to Unity Button Documentation by clicking here.

#### 66.4.1 State Variables

None

#### 66.4.2 Environment Variables

windows: Computer screen used to display messages.

#### 66.4.3 Assumptions

None

#### 66.4.4 Access Routine Semantics

None

#### 66.4.5 Local Functions

# 67 MIS of Show Tree Parameters Button (M62)

## 67.1 Module

ShowTreeParamButton

## 67.2 Uses

M15, UnityEngine.UI

# 67.3 Syntax

## 67.3.1 Exported Constants

None

#### 67.3.2 Exported Access Programs

None

#### 67.4 Semantics

This module is used to display the UI of the ShowTreeParamButton. You can refer to Unity Button Documentation by clicking here.

#### 67.4.1 State Variables

None

#### 67.4.2 Environment Variables

windows: Computer screen used to display messages.

## 67.4.3 Assumptions

None

#### 67.4.4 Access Routine Semantics

None

#### 67.4.5 Local Functions

# 68 MIS of Environment Data Display (M63)

### 68.1 Module

EnvDataDisplay

## 68.2 Uses

UnityEngine.UI

# 68.3 Syntax

## 68.3.1 Exported Constants

None

#### 68.3.2 Exported Access Programs

None

### 68.4 Semantics

This module is used to display the UI of the environment data. You can check Unity Text Documentation by clicking here.

#### 68.4.1 State Variables

None

#### 68.4.2 Environment Variables

windows: Computer screen used to display messages.

## 68.4.3 Assumptions

None

#### 68.4.4 Access Routine Semantics

None

#### 68.4.5 Local Functions

# 69 MIS of Tree Parameters Display (M64)

## 69.1 Module

TreeParamDisplay

## 69.2 Uses

UnityEngine.UI

# 69.3 Syntax

# 69.3.1 Exported Constants

None

#### 69.3.2 Exported Access Programs

None

## 69.4 Semantics

This module is used to display the UI of the tree parameters. You can check Unity Text Documentation by clicking here.

#### 69.4.1 State Variables

None

#### 69.4.2 Environment Variables

windows: Computer screen used to display messages.

## 69.4.3 Assumptions

None

#### 69.4.4 Access Routine Semantics

None

#### 69.4.5 Local Functions

# 70 MIS of Pause Indicator (M65)

### 70.1 Module

Pause Indicator Display

## **70.2** Uses

UnityEngine.UI

# 70.3 Syntax

## 70.3.1 Exported Constants

None

# 70.3.2 Exported Access Programs

None

#### 70.4 Semantics

This module is used to display the status of pausing. You can check Unity Text Documentation by clicking here.

#### 70.4.1 State Variables

None

#### 70.4.2 Environment Variables

windows: Computer screen used to display messages.

## 70.4.3 Assumptions

None

#### 70.4.4 Access Routine Semantics

None

#### 70.4.5 Local Functions

# 71 MIS of SeasonChangeButton (M66)

## 71.1 Module

SeasonChangeButton

## 71.2 Uses

UnityEngine.UI, M27

# 71.3 Syntax

# 71.3.1 Exported Constants

None

# 71.3.2 Exported Access Programs

None

## 71.4 Semantics

This module is used to display the seasonal change of the models of the forest

#### 71.4.1 State Variables

None

#### 71.4.2 Environment Variables

windows: Computer screen used to display messages.

## 71.4.3 Assumptions

None

#### 71.4.4 Access Routine Semantics

None

## 71.4.5 Local Functions

# 72 MIS of pieChartButton (M67)

#### **72.1** Module

pieChartButton

## **72.2** Uses

UnityEngine.UI

# 72.3 Syntax

## 72.3.1 Exported Constants

None

# 72.3.2 Exported Access Programs

None

### 72.4 Semantics

This module is providing a button GUI for users to switch between a pie chart and environmental data.

#### 72.4.1 State Variables

None

#### 72.4.2 Environment Variables

windows: Computer screen used to display messages.

## 72.4.3 Assumptions

None

#### 72.4.4 Access Routine Semantics

None

#### 72.4.5 Local Functions

# 73 MIS of TreeSwitchButton (M68)

#### 73.1 Module

TreeSwitchButton

# **73.2** Uses

UnityEngine.UI

# 73.3 Syntax

# 73.3.1 Exported Constants

None

# 73.3.2 Exported Access Programs

None

#### 73.4 Semantics

This module provides a button GUI for users to switch between tree parameters and leaf infor mation

#### 73.4.1 State Variables

None

#### 73.4.2 Environment Variables

windows: Computer screen used to display messages.

## 73.4.3 Assumptions

None

#### 73.4.4 Access Routine Semantics

None

#### 73.4.5 Local Functions

# References

Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. Fundamentals of Software Engineering. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.

Daniel M. Hoffman and Paul A. Strooper. Software Design, Automated Testing, and Maintenance: A Practical Approach. International Thomson Computer Press, New York, NY, USA, 1995. URL http://citeseer.ist.psu.edu/428727.html.