P2P-1

```
enable
conf t

router ospf 10
 auto-cost reference-bandwidth 10000
 network 10.0.0.12 0.0.0.3 area 0
 network 10.0.0.8 0.0.0.3 area 0
 network 10.0.0.0 0.0.0.3 area 0

interface s0/1/1
 ip ospf cost 50

interface s0/2/0
 ip ospf hello-interval 20
 ip ospf dead-interval 80

end
```

P2P-2

```
enable
conf t

router ospf 10
 auto-cost reference-bandwidth 10000
 passive-interface g0/0/0
 passive-interface g0/0/1
 network 192.168.2.0 0.0.0.255 area 0
 network 192.168.1.0 0.0.0.255 area 0
 network 10.0.0.4 0.0.0.3 area 0
 network 10.0.0.0 0.0.0.3 area 0

end
```

P2P-3

```
enable
conf t

router ospf 10
 auto-cost reference-bandwidth 10000
 passive-interface g0/0/0
 network 192.168.3.0 0.0.0.15 area 0
 network 10.0.0.8 0.0.0.3 area 0
 network 10.0.0.4 0.0.0.3 area 0
```

```
end
```

BC-1

```
enable
conf t

router ospf 10
 router-id 6.6.6.6
 auto-cost reference-bandwidth 10000
 passive-interface s0/1/1
 default-information originate

interface g0/0/0
 ip ospf 10 area 0
 ip ospf priority 255

interface s0/1/0
 ip ospf 10 area 0
 ip ospf hello-interval 20
 ip ospf dead-interval 80

ip route 0.0.0.0 0.0.0.0 s0/1/1

end
```

BC-2

```
enable
conf t

router ospf 10
 router-id 5.5.5.5
 auto-cost reference-bandwidth 10000
 passive-interface g0/0/0

interface g0/0/1
 ip ospf 10 area 0

interface g0/0/0
 ip ospf 10 area 0

end
```

BC-3

```
enable
conf t

router ospf 10
 router-id 4.4.4.4
 auto-cost reference-bandwidth 10000
 passive-interface g0/0/0

interface g0/0/1
 ip ospf 10 area 0

interface g0/0/0
 ip ospf 10 area 0

end
```

ตรวจ Requirement

OSPF Process ID 10

Headquarters ใช้ network statement + inverse mask

Data Service ใช้ ip ospf 10 area 0

Router ID: BC-1 = 6.6.6.6, BC-2 = 5.5.5.5, BC-3 = 4.4.4.4

Passive Interface

BC-1 OSPF priority = 255

Default route ผ่าน exit interface

default-information originate

auto-cost reference-bandwidth 10000

P2P-1 S0/1/1 cost = 50

Hello = 20 และ Dead = 80