MySQL Cluster

MySQL Cluster

Abstract

This is the MySQL Cluster extract from the MySQL 5.1 Reference Manual.

Document generated on: 2011-07-27 (revision: 26958)

Copyright © 1997, 2011, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. MySQL is a trademark of Oracle Corporation and/or its affiliates, and shall not be used without Oracle's express written authorization. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this material is subject to the terms and conditions of your Oracle Software License and Service Agreement, which has been executed and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle or as specifically provided below. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

This documentation is NOT distributed under a GPL license. Use of this documentation is subject to the following terms:

You may create a printed copy of this documentation solely for your own personal use. Conversion to other formats is allowed as long as the actual content is not altered or edited in any way. You shall not publish or distribute this documentation in any form or on any media, except if you distribute the documentation in a manner similar to how Oracle disseminates it (that is, electronically for download on a Web site with the software) or on a CD-ROM or similar medium, provided however that the documentation is disseminated together with the software on the same medium. Any other use, such as any dissemination of printed copies or use of this documentation, in whole or in part, in another publication, requires the prior written consent from an authorized representative of Oracle and/or its affiliates reserve any and all rights to this documentation not expressly granted above

For more information on the terms of this license, for details on how the MySQL documentation is built and produced, or if you are interested in doing a translation, please visit MySQL Contact & Questions.

For additional licensing information, including licenses for third-party libraries used by MySQL products, see Preface and Notes.

If you want help with using MySQL, please visit either the MySQL Forums or MySQL Mailing Lists where you can discuss your issues with other MySQL users.

For additional documentation on MySQL products, including translations of the documentation into other languages, and downloadable versions in variety of formats, including HTML and PDF formats, see the MySQL Documentation Library.



MySQL Cluster NDB 6.X/7.X

This chapter contains information about *MySQL Cluster*, which is a high-availability, high-redundancy version of MySQL adapted for the distributed computing environment. Current releases of MySQL Cluster use versions 6 and 7 of the NDBCLUSTER storage engine (also known as NDB) to enable running several computers with MySQL servers and other software in a cluster.

Beginning with MySQL 5.1.24, support for the NDBCLUSTER storage engine was removed from the standard MySQL server binaries built by MySQL. Instead, users of MySQL Cluster binaries built by MySQL should upgrade to the most recent binary release of MySQL Cluster NDB 7.0 or MySQL Cluster 7.1 for supported platforms—these include RPMs that should work with most Linux distributions. MySQL Cluster users who build from source should be aware that, also beginning with MySQL 5.1.24, NDB-CLUSTER sources in the standard MySQL 5.1 tree are no longer maintained; these users should use the sources provided for MySQL Cluster NDB 7.0 or later. (Locations where the sources can be obtained are listed later in this section.)

Note

MySQL Cluster NDB 6.1, 6.2, and 6.3 were formerly known as "MySQL Cluster Carrier Grade Edition". Beginning with MySQL Cluster NDB 6.2.15 and MySQL Cluster NDB 6.3.14, this term is no longer applied to the MySQL Cluster software—which is now known simply as "MySQL Cluster"—but rather to a commercial licensing and support package. You can learn more about available options for commercial licensing of MySQL Cluster from ht-tp://mysql.com/products/database/cluster/features.html, on the MySQL web site.

This chapter contains information about MySQL Cluster in MySQL 5.1 mainline releases through MySQL 5.1.23, MySQL Cluster NDB 6.2 releases through 5.1.51-ndb-6.2.19, MySQL Cluster NDB 6.3 releases through 5.1.56-ndb-6.3.45, MySQL Cluster NDB 7.0 releases through 5.1.56-ndb-7.1.16. Currently, the MySQL Cluster NDB 7.1 releases through 5.1.56-ndb-7.1.16. Currently, the MySQL Cluster NDB 7.0 (formerly known as "MySQL Cluster NDB 6.4") and MySQL Cluster NDB 7.1 release series are Generally Available (GA). MySQL Cluster NDB 6.2 and MySQL Cluster NDB 6.3 are previous GA release series; although these are still supported, we recommend that new deployments use MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1.

This chapter also contains historical information about MySQL Cluster NDB 6.1, although this release series is no longer in active development, and no longer supported for new deployments. You should upgrade to MySQL Cluster 6.3 or a MySQL Cluster NDB 7.x release series as soon as possible.

Supported Platforms. MySQL Cluster is currently available and supported on a number of platforms. For exact levels of support available for on specific combinations of operating system versions, operating system distributions, and hardware platforms, please refer to http://www.mysql.com/support/supportedplatforms/cluster.html.

Availability. MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, and MySQL Cluster NDB 7.1 binary and source packages are available for supported platforms from http://dev.mysql.com/downloads/cluster/.

Note

Binary releases and RPMs were not available for MySQL Cluster NDB 6.2 prior to MySQL Cluster NDB 6.2.15.

MySQL Cluster release numbers. Starting with MySQL Cluster NDB 6.1 and MySQL Cluster NDB 6.2, MySQL Cluster follows a somewhat different release pattern from the mainline MySQL 5.1 Cluster series of releases. In this *Manual* and other MySQL documentation, we identify these and later MySQL Cluster releases employing a version number that begins with "NDB". This version number is that of the NDBCLUSTER storage engine used in the release, and not of the MySQL server version on which the MySQL Cluster release is based.

Version strings used in MySQL Cluster NDB 6.x and 7.x software. The version string displayed by MySQL Cluster NDB 6.x and 7.x software uses this format:

```
mysql-mysql_server_version-ndb-ndbcluster_engine_version
```

mysql_server_version represents the version of the MySQL Server on which the MySQL Cluster release is based. For all MySQL Cluster NDB 6.x and 7.x releases, this is "5.1". ndbcluster_engine_version is the version of the NDBCLUSTER storage engine used by this release of the MySQL Cluster software. You can see this format used in the mysql client, as shown here:

This version string is also displayed in the output of the SHOW command in the ndb_mgm client:

The version string identifies the mainline MySQL version from which the MySQL Cluster release was branched and the version of the NDBCLUSTER storage engine used. For example, the full version string for MySQL Cluster NDB 7.0.5 (the first GA MySQL Cluster NDB 7.0 binary release) was mysql-5.1.32-ndb-7.0.5. From this we can determine the following:

- Since the portion of the version string preceding "-ndb-" is the base MySQL Server version, this means that MySQL Cluster NDB 7.0.5 derives from the MySQL 5.1.32, and contains all feature enhancements and bugfixes from MySQL 5.1 up to and including MySQL 5.1.32.
- Since the portion of the version string following "-ndb-" represents the version number of the NDB (or NDBCLUSTER) storage engine, MySQL Cluster NDB 7.0.5 uses version 7.0.5 of the NDBCLUSTER storage engine.

New MySQL Cluster releases are numbered according to updates in the NDB storage engine, and do not necessarily correspond in a linear fashion with mainline MySQL Server releases. For example, MySQL Cluster NDB 7.0.5 (as previously noted) is based on MySQL 5.1.32, and MySQL Cluster NDB 7.0.6 is based on MySQL 5.1.34 (version string: mysql-5.1.34-ndb-7.0.6).

Compatibility with standard MySQL 5.1 releases. While many standard MySQL schemas and applications can work using MySQL Cluster, it is also true that unmodified applications and database schemas may be slightly incompatible or have suboptimal performance when run using MySQL Cluster (see Section 1.6, "Known Limitations of MySQL Cluster"). Most of these issues can be overcome, but this also means that you are very unlikely to be able to switch an existing application datastore—that currently uses, for example, MyISAM or InnoDB—to use the NDB storage engine without allowing for the possibility of changes in schemas, queries, and applications. Moreover, from MySQL 5.1.24 onwards, the MySQL Server and MySQL Cluster codebases diverge considerably (and NDB storage engine support dropped from subsequent MySQL Server releases), so that the standard mysqld cannot function as a dropin replacement for the version of mysqld that is supplied with MySQL Cluster.

MySQL Cluster development source trees. MySQL Cluster development trees can also be accessed from https://code.launchpad.net/~mysql/:

```
• MySQL Cluster NDB 6.1 (ABANDONED—no longer maintained)
```

- MySQL Cluster NDB 6.2 (OBSOLETE—in maintenance mode)
- MySQL Cluster NDB 6.3 (PAST CURRENT—still maintained)
- MySQL Cluster NDB 7.0(CURRENT)
- MySQL Cluster NDB 7.1 (CURRENT)

The MySQL Cluster development sources maintained at https://code.launchpad.net/~mysql/ are licensed under the GPL. For information about obtaining MySQL sources using Bazaar and building them yourself, see Installing MySQL from a Development Source Tree.

Currently, MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, and MySQL Cluster NDB 7.1 releases are all Generally Available (GA), although we recommend that new deployments use MySQL Cluster NDB 7.1. MySQL Cluster NDB 6.1 is no longer in active development. For an overview of major features added in MySQL Cluster NDB 6.x and 7.x releases, see Section 1.4, "MySQL Cluster Development History".

This chapter represents a work in progress, and its contents are subject to revision as MySQL Cluster continues to evolve. Additional information regarding MySQL Cluster can be found on the MySQL Web site at ht-tp://www.mysql.com/products/cluster/.

Additional Resources. More information may be found in the following places:

- For answers to some commonly asked questions about MySQL Cluster, see Appendix A, MySQL 5.1 FAQ: MySQL Cluster.
- The MySQL Cluster mailing list: http://lists.mysql.com/cluster.

- The MySQL Cluster Forum: http://forums.mysql.com/list.php?25.
- Many MySQL Cluster users and developers blog about their experiences with MySQL Cluster, and make feeds of these available through PlanetMySQL.
- If you are new to MySQL Cluster, you may find our Developer Zone article *How to set up a MySQL Cluster for two servers* to be helpful.

Preface and Notes

This is an extract from the Reference Manual for the MySQL Database System, version 5.1. It contains information about MySQL Cluster releases, through MySQL Cluster NDB 6.3.45, MySQL Cluster NDB 7.0.27, and MySQL Cluster NDB 7.1.16. Differences between minor versions of MySQL Cluster covered in this extract are noted in the present text with reference to the NDBCLUSTER storage version number (6.3.x, 7.0.x, 7.1.x); differences between versions of the MySQL Server 5.1 software, on which MySQL Cluster is based, are noted with reference to MySQL 5.1 releases (5.1.x). For license information, see the legal notice. This product may contain third-party code. For license information on third-party code, see Appendix B, *Licenses for Third-Party Components*.

This extract also contains historical information about older versions of MySQL Cluster that were also based on version 5.1 of the MySQL database system (MySQL 5.1 Cluster, MySQL Cluster NDB 6.1, MySQL Cluster NDB 6.2), although these older versions are no longer supported, maintained, or recommended for new deployments. This extract is not intended for use with older versions of the MySQL Cluster software due to the many functional and other differences between current versions (MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, and MySQL Cluster NDB 7.1) and previous versions. This extract provides information that is specific to MySQL Cluster and is not intended to replace the *MySQL 5.1 Manual*, which provides additional information about MySQL 5.1 which may also be necessary for use of MySQL Cluster. If you are using MySQL Server 5.1 or an earlier release of the MySQL software, please refer to the appropriate manual. For example, *MySQL 5.0 Reference Manual*, covers the 5.0 series of MySQL software releases.

If you are using MySQL 5.5, please refer to the MySQL 5.5 Reference Manual.


Chapter 1. MySQL Cluster Overview

MySQL Cluster is a technology that enables clustering of in-memory databases in a shared-nothing system. The shared-nothing architecture enables the system to work with very inexpensive hardware, and with a minimum of specific requirements for hardware or software.

MySQL Cluster is designed not to have any single point of failure. In a shared-nothing system, each component is expected to have its own memory and disk, and the use of shared storage mechanisms such as network shares, network file systems, and SANs is not recommended or supported.

MySQL Cluster integrates the standard MySQL server with an in-memory clustered storage engine called NDB (which stands for "Network DataBase"). In our documentation, the term NDB refers to the part of the setup that is specific to the storage engine, whereas "MySQL Cluster" refers to the combination of one or more MySQL servers with the NDB storage engine.

A MySQL Cluster consists of a set of computers, known as *hosts*, each running one or more processes. These processes, known as *nodes*, may include MySQL servers (for access to NDB data), data nodes (for storage of the data), one or more management servers, and possibly other specialized data access programs. The relationship of these components in a MySQL Cluster is shown here:



All these programs work together to form a MySQL Cluster (see Chapter 4, *MySQL Cluster Programs*. When data is stored by the NDB storage engine, the tables (and table data) are stored in the data nodes. Such tables are directly accessible from all other MySQL servers (SQL nodes) in the cluster. Thus, in a payroll application storing data in a cluster, if one application updates the salary of an employee, all other MySQL servers that query this data can see this change immediately.

Although a MySQL Cluster SQL node uses the mysqld server damon, it differs in a number of critical respects from the mysqld binary supplied with the MySQL 5.1 distributions, and the two versions of mysqld are not interchangeable.

In addition, a MySQL server that is not connected to a MySQL Cluster cannot use the NDB storage engine and cannot access any MySQL Cluster data.

The data stored in the data nodes for MySQL Cluster can be mirrored; the cluster can handle failures of individual data nodes with no other impact than that a small number of transactions are aborted due to losing the transaction state. Because transactional applications are expected to handle transaction failure, this should not be a source of problems.

Individual nodes can be stopped and restarted, and can then rejoin the system (cluster). Rolling restarts (in which all nodes are restarted in turn) are used in making configuration changes and software upgrades (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster"). In MySQL Cluster NDB 7.0 and later, rolling restarts are also used as part of the process of adding new data nodes online (see Section 5.12, "Adding MySQL Cluster Data Nodes Online"). For more information about data nodes, how they are organized in a MySQL Cluster, and how they handle and store MySQL Cluster data, see Section 1.2, "MySQL Cluster Nodes,

Node Groups, Replicas, and Partitions".

Backing up and restoring MySQL Cluster databases can be done using the NDB native functionality found in the MySQL Cluster management client and the ndb_restore program included in the MySQL Cluster distribution. For more information, see Section 5.3, "Online Backup of MySQL Cluster", and Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup". You can also use the standard MySQL functionality provided for this purpose in mysqldump and the MySQL server. See mysqldump, for more information.

MySQL Cluster nodes can use a number of different transport mechanisms for inter-node communications, including TCP/IP using standard 100 Mbps or faster Ethernet hardware. It is also possible to use the high-speed *Scalable Coherent Interface* (SCI) protocol with MySQL Cluster, although this is not required to use MySQL Cluster. SCI requires special hardware and software; see Section 3.5, "Using High-Speed Interconnects with MySQL Cluster", for more about SCI and using it with MySQL Cluster.

1.1. MySQL Cluster Core Concepts

NDBCLUSTER (also known as NDB) is an in-memory storage engine offering high-availability and data-persistence features.

The NDBCLUSTER storage engine can be configured with a range of failover and load-balancing options, but it is easiest to start with the storage engine at the cluster level. MySQL Cluster's NDB storage engine contains a complete set of data, dependent only on other data within the cluster itself.

The "Cluster" portion of MySQL Cluster is configured independently of the MySQL servers. In a MySQL Cluster, each part of the cluster is considered to be a *node*.

Note

In many contexts, the term "node" is used to indicate a computer, but when discussing MySQL Cluster it means a *process*. It is possible to run multiple nodes on a single computer; for a computer on which one or more cluster nodes are being run we use the term *cluster host*.

There are three types of cluster nodes, and in a minimal MySQL Cluster configuration, there will be at least three nodes, one of each of these types:

- Management node: The role of this type of node is to manage the other nodes within the MySQL Cluster, performing such
 functions as providing configuration data, starting and stopping nodes, running backup, and so forth. Because this node type
 manages the configuration of the other nodes, a node of this type should be started first, before any other node. An MGM node
 is started with the command ndb_mgmd.
- Data node: This type of node stores cluster data. There are as many data nodes as there are replicas, times the number of fragments (see Section 1.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions"). For example, with two replicas, each having two fragments, you need four data nodes. One replica is sufficient for data storage, but provides no redundancy; therefore, it is recommended to have 2 (or more) replicas to provide redundancy, and thus high availability. A data node is started with the command ndbd (see Section 4.2, "ndbd The MySQL Cluster Data Node Daemon"). In MySQL Cluster NDB 7.0 and later, ndbmtd can also be used for the data node process; see Section 4.3, "ndbmtd The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

MySQL Cluster tables in MySQL 5.1 are normally stored completely in memory rather than on disk (this is why we refer to MySQL cluster as an *in-memory* database). In MySQL 5.1, MySQL Cluster NDB 6.X, and later, some MySQL Cluster data can be stored on disk; see Section 5.11, "MySQL Cluster Disk Data Tables", for more information.

SQL node: This is a node that accesses the cluster data. In the case of MySQL Cluster, an SQL node is a traditional MySQL server that uses the NDBCLUSTER storage engine. An SQL node is a mysqld process started with the --ndbcluster and --ndb-connectstring options, which are explained elsewhere in this chapter, possibly with additional MySQL server options as well.

An SQL node is actually just a specialized type of *API node*, which designates any application which accesses MySQL Cluster data. Another example of an API node is the ndb_restore utility that is used to restore a cluster backup. It is possible to write such applications using the NDB API. For basic information about the NDB API, see Getting Started with the NDB API.

Important

It is not realistic to expect to employ a three-node setup in a production environment. Such a configuration provides no redundancy; to benefit from MySQL Cluster's high-availability features, you must use multiple data and SQL nodes. The use of multiple management nodes is also highly recommended.

For a brief introduction to the relationships between nodes, node groups, replicas, and partitions in MySQL Cluster, see Section 1.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions".

Configuration of a cluster involves configuring each individual node in the cluster and setting up individual communication links

between nodes. MySQL Cluster is currently designed with the intention that data nodes are homogeneous in terms of processor power, memory space, and bandwidth. In addition, to provide a single point of configuration, all configuration data for the cluster as a whole is located in one configuration file.

The management server manages the cluster configuration file and the cluster log. Each node in the cluster retrieves the configuration data from the management server, and so requires a way to determine where the management server resides. When interesting events occur in the data nodes, the nodes transfer information about these events to the management server, which then writes the information to the cluster log.

In addition, there can be any number of cluster client processes or applications. These include standard MySQL clients, NDB-specific API programs, and management clients. These are described in the next few paragraphs.

Standard MySQL clients. MySQL Cluster can be used with existing MySQL applications written in PHP, Perl, C, C++, Java, Python, Ruby, and so on. Such client applications send SQL statements to and receive responses from MySQL servers acting as MySQL Cluster SQL nodes in much the same way that they interact with standalone MySQL servers.

MySQL clients using a MySQL Cluster as a data source can be modified to take advantage of the ability to connect with multiple MySQL servers to achieve load balancing and failover. For example, Java clients using Connector/J 5.0.6 and later can use jd-bc:mysql:loadbalance:// URLs (improved in Connector/J 5.1.7) to achieve load balancing transparently; for more information about using Connector/J with MySQL Cluster, see Using Connector/J with MySQL Cluster.

NDB client programs. Client programs can be written that access MySQL Cluster data directly from the NDBCLUSTER storage engine, bypassing any MySQL Servers that may connected to the cluster, using the NDB API, a high-level C++ API. Such applications may be useful for specialized purposes where an SQL interface to the data is not needed. For more information, see The NDB API.

Beginning with MySQL Cluster NDB 7.1, NDB-specific Java applications can also be written for MySQL Cluster, using the MySQL Cluster Connector for Java. This MySQL Cluster Connector includes ClusterJ, a high-level database API similar to object-relational mapping persistence frameworks such as Hibernate and JPA that connect directly to NDBCLUSTER, and so does not require access to a MySQL Server. Support is also provided in MySQL Cluster NDB 7.1 and later for ClusterJPA, an OpenJPA implementation for MySQL Cluster that leverages the strengths of ClusterJ and JDBC; ID lookups and other fast operations are performed using ClusterJ (bypassing the MySQL Server), while more complex queries that can benefit from MySQL's query optimizer are sent through the MySQL Server, using JDBC. See Java and MySQL Cluster, and The ClusterJ API and Data Object Model, for more information.

Management clients. These clients connect to the management server and provide commands for starting and stopping nodes gracefully, starting and stopping message tracing (debug versions only), showing node versions and status, starting and stopping backups, and so on. An example of this type of program is the ndb_mgm management client supplied with MySQL Cluster (see Section 4.5, "ndb_mgm — The MySQL Cluster Management Client"). Such applications can be written using the MGM API, a Clanguage API that communicates directly with one or more MySQL Cluster management servers. For more information, see The MGM API.

Oracle also makes available MySQL Cluster Manager, which provides an advanced command-line interface simplifying many complex MySQL Cluster management tasks, such restarting a MySQL Cluster with a large number of nodes. The MySQL Cluster Manager client also supports commands for getting and setting the values of most node configuration parameters as well as mysqld server options and variables relating to MySQL Cluster. MySQL Cluster Manager 1.1 provides support for adding data nodes online. See MySQLTM Cluster Manager 1.1 User Manual, for more information.

Event logs. MySQL Cluster logs events by category (startup, shutdown, errors, checkpoints, and so on), priority, and severity. A complete listing of all reportable events may be found in Section 5.5, "Event Reports Generated in MySQL Cluster". Event logs are of the two types listed here:

- Cluster log: Keeps a record of all desired reportable events for the cluster as a whole.
- Node log: A separate log which is also kept for each individual node.

Note

Under normal circumstances, it is necessary and sufficient to keep and examine only the cluster log. The node logs need be consulted only for application development and debugging purposes.

Checkpoint. Generally speaking, when data is saved to disk, it is said that a *checkpoint* has been reached. More specific to MySQL Cluster, a checkpoint is a point in time where all committed transactions are stored on disk. With regard to the NDB storage engine, there are two types of checkpoints which work together to ensure that a consistent view of the cluster's data is maintained. These are shown in the following list:

• Local Checkpoint (LCP): This is a checkpoint that is specific to a single node; however, LCP's take place for all nodes in the

cluster more or less concurrently. An LCP involves saving all of a node's data to disk, and so usually occurs every few minutes. The precise interval varies, and depends upon the amount of data stored by the node, the level of cluster activity, and other factors.

Global Checkpoint (GCP): A GCP occurs every few seconds, when transactions for all nodes are synchronized and the redo-log
is flushed to disk.

1.2. MySQL Cluster Nodes, Node Groups, Replicas, and Partitions

This section discusses the manner in which MySQL Cluster divides and duplicates data for storage.

A number of concepts central to an understanding of this topic are discussed in the next few paragraphs.

(**Data**) **Node.** An ndbd process, which stores a *replica* —that is, a copy of the *partition* (see below) assigned to the node group of which the node is a member.

Each data node should be located on a separate computer. While it is also possible to host multiple ndbd processes on a single computer, such a configuration is not supported.

It is common for the terms "node" and "data node" to be used interchangeably when referring to an ndbd process; where mentioned, management nodes (ndb_mgmd processes) and SQL nodes (mysqld processes) are specified as such in this discussion.

Node Group. A node group consists of one or more nodes, and stores partitions, or sets of *replicas* (see next item).

The number of node groups in a MySQL Cluster is not directly configurable; it is a function of the number of data nodes and of the number of replicas (NoofReplicas configuration parameter), as shown here:

[number_of_node_groups] = number_of_data_nodes / NoOfReplicas

Thus, a MySQL Cluster with 4 data nodes has 4 node groups if NoOfReplicas is set to 1 in the config.ini file, 2 node groups if NoOfReplicas is set to 2, and 1 node group if NoOfReplicas is set to 4. Replicas are discussed later in this section; for more information about NoOfReplicas, see Section 3.2.6, "Defining MySQL Cluster Data Nodes".

Note

All node groups in a MySQL Cluster must have the same number of data nodes.

Prior to MySQL Cluster NDB 7.0, it was not possible to add new data nodes to a MySQL Cluster without shutting down the cluster completely and reloading all of its data. In MySQL Cluster NDB 7.0 (beginning with MySQL Cluster version NDB 6.4.0), you can add new node groups (and thus new data nodes) to a running MySQL Cluster—see Section 5.12, "Adding MySQL Cluster Data Nodes Online", for information about how this can be done.

Partition. This is a portion of the data stored by the cluster. There are as many cluster partitions as nodes participating in the cluster. Each node is responsible for keeping at least one copy of any partitions assigned to it (that is, at least one replica) available to the cluster.

A replica belongs entirely to a single node; a node can (and usually does) store several replicas.

NDB and user-defined partitioning. MySQL Cluster normally partitions NDBCLUSTER tables automatically. However, in MySQL 5.1 and later MySQL Cluster releases, it is possible to employ user-defined partitioning with NDBCLUSTER tables. This is subject to the following limitations:

- 1. Only KEY and LINEAR KEY partitioning schemes can be used with NDBCLUSTER tables.
- 2. When using ndbd, the maximum number of partitions that may be defined explicitly for any NDBCLUSTER table is 8 * [number of node groups]. (The number of node groups in a MySQL Cluster is determined as discussed previously in this section.)


When using ndbmtd, this maximum is also affected by the number of local query handler threads, which is determined by the value of the MaxNoOfExecutionThreads configuration parameter. In such cases, the maxmimum number of partitions that may be defined explicitly for an NDB table is equal to 4 * MaxNoOfExecutionThreads * [number of node groups].

See Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

For more information relating to MySQL Cluster and user-defined partitioning, see Section 1.6, "Known Limitations of MySQL Cluster", and Partitioning Limitations Relating to Storage Engines.

Replica. This is a copy of a cluster partition. Each node in a node group stores a replica. Also sometimes known as a *partition replica*. The number of replicas is equal to the number of nodes per node group.

The following diagram illustrates a MySQL Cluster with four data nodes, arranged in two node groups of two nodes each; nodes 1 and 2 belong to node group 0, and nodes 3 and 4 belong to node group 1. Note that only data (ndbd) nodes are shown here; although a working cluster requires an ndb_mgm process for cluster management and at least one SQL node to access the data stored by the cluster, these have been omitted in the figure for clarity.




The data stored by the cluster is divided into four partitions, numbered 0, 1, 2, and 3. Each partition is stored—in multiple copies—on the same node group. Partitions are stored on alternate node groups as follows:

- Partition 0 is stored on node group 0; a *primary replica* (primary copy) is stored on node 1, and a *backup replica* (backup copy of the partition) is stored on node 2.
- Partition 1 is stored on the other node group (node group 1); this partition's primary replica is on node 3, and its backup replica is on node 4.
- Partition 2 is stored on node group 0. However, the placing of its two replicas is reversed from that of Partition 0; for Partition 2, the primary replica is stored on node 2, and the backup on node 1.

• Partition 3 is stored on node group 1, and the placement of its two replicas are reversed from those of partition 1. That is, its primary replica is located on node 4, with the backup on node 3.

What this means regarding the continued operation of a MySQL Cluster is this: so long as each node group participating in the cluster has at least one node operating, the cluster has a complete copy of all data and remains viable. This is illustrated in the next diagram.



In this example, where the cluster consists of two node groups of two nodes each, any combination of at least one node in node group 0 and at least one node in node group 1 is sufficient to keep the cluster "alive" (indicated by arrows in the diagram). However, if *both* nodes from *either* node group fail, the remaining two nodes are not sufficient (shown by the arrows marked out with an **X**); in either case, the cluster has lost an entire partition and so can no longer provide access to a complete set of all cluster data.

1.3. MySQL Cluster Hardware, Software, and Networking Requirements

One of the strengths of MySQL Cluster is that it can be run on commodity hardware and has no unusual requirements in this regard, other than for large amounts of RAM, due to the fact that all live data storage is done in memory. (It is possible to reduce this requirement using Disk Data tables—see Section 5.11, "MySQL Cluster Disk Data Tables", for more information about these.) Naturally, multiple and faster CPUs can enhance performance. Memory requirements for other MySQL Cluster processes are relatively small.

The software requirements for MySQL Cluster are also modest. Host operating systems do not require any unusual modules, services, applications, or configuration to support MySQL Cluster. For supported operating systems, a standard installation should be sufficient. The MySQL software requirements are simple: all that is needed is a production release of MySQL 5.1.56-ndb-7.0.27 or 5.1.56-ndb-7.1.16 to have MySQL Cluster support. It is not strictly necessary to compile MySQL yourself merely to be able to use MySQL Cluster. We assume that you are using the binaries appropriate to your platform, available from the MySQL Cluster software downloads page at http://dev.mysql.com/downloads/cluster/.

For communication between nodes, MySQL Cluster supports TCP/IP networking in any standard topology, and the minimum expected for each host is a standard 100 Mbps Ethernet card, plus a switch, hub, or router to provide network connectivity for the cluster as a whole. We strongly recommend that a MySQL Cluster be run on its own subnet which is not shared with machines not forming part of the cluster for the following reasons:

Security. Communications between MySQL Cluster nodes are not encrypted or shielded in any way. The only means of protecting transmissions within a MySQL Cluster is to run your MySQL Cluster on a protected network. If you intend to use MySQL Cluster for Web applications, the cluster should definitely reside behind your firewall and not in your network's De-Militarized Zone (DMZ) or elsewhere.

See Section 5.10.1, "MySQL Cluster Security and Networking Issues", for more information.

• Efficiency. Setting up a MySQL Cluster on a private or protected network enables the cluster to make exclusive use of bandwidth between cluster hosts. Using a separate switch for your MySQL Cluster not only helps protect against unauthorized access to MySQL Cluster data, it also ensures that MySQL Cluster nodes are shielded from interference caused by transmissions between other computers on the network. For enhanced reliability, you can use dual switches and dual cards to remove the network as a single point of failure; many device drivers support failover for such communication links.

Network communication and latency. MySQL Cluster requires communication between data nodes and API nodes (including SQL nodes), as well as between data nodes and other data nodes, to execute queries and updates. Communication latency between these processes can directly affect the observed performance and latency of user queries. In addition, to maintain consistency and service despite the silent failure of nodes, MySQL Cluster uses heartbeating and timeout mechanisms which treat an extended loss of communication from a node as node failure. This can lead to reduced redundancy. Recall that, to maintain data consistency, a MySQL Cluster shuts down when the last node in a node group fails. Thus, to avoid increasing the risk of a forced shutdown, breaks in communication between nodes should be avoided wherever possible.

The failure of a data or API node results in the abort of all uncommitted transactions involving the failed node. Data node recovery requires synchronization of the failed notde's data from a surviving data node, and re-establishment of disk-based redo and checkpoint logs, before the data node returns to service. This recovery can take some time, during which the Cluster operates with reduced redundancy.

Heartbeating relies on timely generation of heartbeat signals by all nodes. This may not be possible if the node is overloaded, has insufficient machine CPU due to sharing with other programs, or is experiencing delays due to swapping. If heartbeat generation is sufficiently delayed, other nodes treat the node that is slow to respond as failed.

This treatment of a slow node as a failed one may or may not be desireable in some circumstances, depending on the impact of the node's slowed operation on the rest of the cluster. When setting timeout values such as HeartbeatIntervalDbDb and HeartbeatIntervalDbApi for MySQL Cluster, care must be taken care to achieve quick detection, failover, and return to service, while avoiding potentially expensive false positives.

Where communication latencies between data nodes are expected to be higher than would be expected in a LAN environment (on the order of $100 \, \mu s$), timeout parameters must be increased to ensure that any allowed periods of latency periods are well within configured timeouts. Increasing timeouts in this way has a corresponding effect on the worst-case time to detect failure and therefore time to service recovery.

LAN environments can typically be configured with stable low latency, and such that they can provide redundancy with fast fail-over. Individual link failures can be recovered from with minimal and controlled latency visible at the TCP level (where MySQL Cluster normally operates). WAN environments may offer a range of latencies, as well as redundancy with slower failover times. Individual link failures may require route changes to propagate before end-to-end connectivity is restored. At the TCP level this can appear as large latencies on individual channels. The worst-case observed TCP latency in these scenarios is related to the worst-case time for the IP layer to reroute around the failures.

SCI support. It is also possible to use the high-speed Scalable Coherent Interface (SCI) with MySQL Cluster, but this is not a requirement. See Section 3.5, "Using High-Speed Interconnects with MySQL Cluster", for more about this protocol and its use with MySQL Cluster.

1.4. MySQL Cluster Development History

In this section, we discuss changes in the implementation of MySQL Cluster in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x, as compared to earlier MySQL Cluster releases.

There are a number of significant changes in the implementation of the NDBCLUSTER storage engine in mainline MySQL 5.1 releases up to and including MySQL 5.1.23 as compared to that in MySQL 5.0; MySQL Cluster NDB 6.x and 7.x make further changes and improvements in MySQL Cluster in addition to these. The changes and features most likely to be of interest are shown in the following tables:

MySQL Cluster NDB 7.2

Distribution of MySQL users and privileges across MySQL Cluster SQL nodes

Distributed pushed-down joins.

Improved default values for data node configuration parameters.

MySQL Cluster NDB 7.1

Production-level support for MySQL Cluster on Microsoft Windows platforms.

ndbinfo meta-information database

MySQL Cluster Connector for Java, including ClusterJ and OpenJPA (ClusterJPA) support

Native support for default column values

MySQL Cluster NDB 7.0

Multi-threaded data nodes (ndbmtd data node daemon)

Online addition of data nodes; online data redistribution

MySQL on Windows (alpha; source releases only)

Configuration cache

Backup snapshots (START BACKUP ... SNAPSHOTSTART, START BACKUP ... SNAPSHOTEND commands)

IPv6 support for geo-replication

Protected DDL operations

Dynamic buffering for NDB transporters

Increased flexibility in determining arbitration handling, using a new Arbitration data node configuration parameter

MySQL Cluster NDB 6.3

Conflict detection and resolution for multi-master replication

Compressed backups and local checkpoints

Support for OPTIMIZE TABLE

Parallel data node recovery

Enhanced transaction coordinator selection

Improved SQL statement performance metrics

Transaction batching

ndb_restore attribute promotion

Support for epoll (Linux only)

Distribution awareness

NDB thread locks; realtime extensions for multiple CPUs

MySQL Cluster NDB 6.2

Improved backup status reporting (BackupReportFrequency, REPORT BackupStatus)

Multiple connections per SQL node

Data access with NdbRecord (NDB API)

REPORT MemoryUsage command

Memory allocation improvements

Management client connection control

Micro-GCPs

Online ADD COLUMN; improved online index creation

MySQL Cluster NDB 6.1

Greater number of cluster nodes

MySQL Cluster NDB 6.1 Disabling of arbitration Additional DUMP commands Faster Disk Data backups Batched slave updates

MySQL 5.1 (through 5.1.23) MySQL Cluster Replication Disk Data storage Variable-size columns User-defined partitioning Autodiscovery of table schema changes

1.4.1. MySQL Cluster Development in MySQL Cluster NDB 7.2

Online adding and dropping of indexes

The following improvements to MySQL Cluster have been made in MySQL Cluster NDB 7.2.

• **Distribution of MySQL users and privileges.** Automatic distribution of MySQL users and privileges across all SQL nodes in a given MySQL Cluster is now supported. To enable this support, you must first import an SQL script share/
mysql/ndb_dist_priv.sql
that is included with the MySQL Cluster NDB 7.2 distribution. This script creates several stored procedures which you can use to enable privilege distribution and perform related tasks.

When a new MySQL Server joins a MySQL Cluster where privilege distribution is in effect, it also participates in the privilege distribution automatically.

Once privilege distribution is enabled, all changes to the grant tables made on any mysqld attached to the cluster are immediately available on any other attached MySQL Servers. This is true whether the changes are made using CREATE USER, GRANT, or any of the other statements described elsewhere in this Manual (see Account Management Statements.) This includes privileges relating to stored routines and views; however, automatic distribution of the views or stored routines themselves is not currently supported.

For more information, see Section 5.13, "Distributed MySQL Privileges for MySQL Cluster".

• **Distributed pushed-down joins.** Many joins can now be pushed down to the NDB kernel for processing on MySQL Cluster data nodes. Previously, a join was handled in MySQL Cluster by means of repeated accesses of NDB by the SQL node; however, when pushed-down joins are enabled, a pushable join is sent in its entirety to the data nodes, where it can be distributed among the data nodes and executed in parallel on multiple copies of the data, with a single, merged result being returned to mysqld. This can reduce greatly the number of round trips between an SQL node and the data nodes required to handle such a join, leading to greatly improved performance of join processing.

It is possible to determine when joins can be pushed down to the data nodes by examining the join with EXPLAIN. A number of new system status variables (Ndb_pushed_queries_defined, Ndb_pushed_queries_dropped, Ndb_pushed_queries_executed, and Ndb_pushed_reads) and additions to the counters table (in the ndbinfo information database) can also be helpful in determining when and how well joins are being pushed down.

More information and examples are available in the description of the ndb_join_pushdown server system variable. See also the description of the status variables referenced in the previous paragraph, as well as Section 5.9.3, "The ndbinfo counters Table".

- Improved default values for data node configuration parameters. In order to provide more resiliency to environmental issues and better handling of some potential failure scenarios, and to perform more reliably with increases in memory and other resource requirements brought about by recent improvements in join handling by NDB, the default values for a number of MySQL Cluster data node configuration parameters have been changed. The parameters and changes are described in the following list:
 - HeartbeatIntervalDbDb: Default increased from 1500 ms to 5000 ms.
 - ArbitrationTimeout: Default increased from 3000 ms to 7500 ms.
 - TimeBetweenEpochsTimeout: Now effectively disabled by default (default changed from 4000 ms to 0).

- SharedGlobalMemory: Default increased from 20 MB to 128 MB.
- MaxParallelScansPerFragment: Default increased from 32 to 256.

In addition, the value computed for MaxNoOfLocalScans when this parameter is not set in config.ini has been increased by a factor of 4.

1.4.2. MySQL Cluster Development in MySQL Cluster NDB 7.1

The following improvements to MySQL Cluster have been made in MySQL Cluster NDB 7.1.

• MySQL Cluster information database (ndbinfo). The ndbinfo information database makes it possible to obtain realtime characteristics of a MySQL Cluster by issuing queries from the mysql client or other MySQL client applications. ndbinfo provides metadata specific to MySQL Cluster similarly to how the INFORMATION_SCHEMA database provides metadata for the standard MySQL Server. This eliminates much of the need to read log files, issue REPORT or DUMP commands in the ndb_mgm client, or parse the output of ndb_config in order to get configuration and status information from a running MySQL Cluster.

For more information, see Section 5.9, "The ndbinfo MySQL Cluster Information Database".

• Java connectors for MySQL Cluster. The MySQL Cluster distribution now includes 2 new Java user APIs, ClusterJ and ClusterJPA. ClusterJ is an object-relational interface in a manner similar to that of Java persistence frameworks such as Hibernate. Cluster JPA is a reimplementation of OpenJPA. ClusterJ uses a backend library (NdbJTie) that provides access to the NDB storage engine without using a MySQL Server connection or JDBC. ClusterJPA also uses NdbJTie when it improves performance, but can also process complex queries using JDBC and a MySQL Server connection, where it can take advantage of the MySQL query optimizer.

Cluster J and Cluster JPA can also be made to work with recent MySQL Cluster NDB 7.0 releases although the necessary library and JAR files are included only in MySQL Cluster NDB 7.1.1 and later.

For more information about using ClusterJ and ClusterJPA, see MySQL Cluster Connector for Java.

• New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 7.1.0, the CHANGE MASTER TO statement supports an IGNORE_SERVER_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

Native support for default column values. Starting with MySQL Cluster NDB 7.1.4, default values for table columns are
stored in the NDB kernel rather than by the MySQL server as was done previously. This means that inserts on tables having
column value defaults can be smaller and faster than before, because less data must be sent from SQL nodes to NDBCLUSTER.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.1.4 and later; however, they do not support native default values until they are upgraded. You can upgrade a table with non-native default values to support native default values using an offline ALTER TABLE statement.

MySQL Cluster on Windows (*Production*). Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is available for production use on Microsoft Windows operating systems; MySQL Cluster NDB 7.1 binaries for Windows can be obtained from http://dev.mysql.com/downloads/cluster/.

Features and behavior are generally comparable to those found on previously supported platforms such as Linux and Solaris. However, you must install the binaries manually.

Beginning with MySQL Cluster NDB 7.1.5, MySQL Cluster processes can be run as Windows services.

If you wish to build MySQL Cluster from source on Windows, you must configure the build using the WITH_NDBCLUSTER_STORAGE_ENGINE option. For more information, see Installing MySQL from Source on Windows.

- --nowait-nodes option for management servers. It is now possible to configure a cluster with two management servers, but to start the cluster using only one of them by starting the management node daemon with the --nowait-nodes option. The other management server can then be started at a later time to join the running MySQL Cluster.
- Improved lock handling for primary key lookups on BLOB tables. A MySQL Cluster table stores all but the first 256 bytes of any BLOB or TEXT column values in a separate BLOB table; when executing queries against such tables, a shared lock is obtained. Prior to MySQL Cluster NDB 7.1.1, when the query used a primary key lookup and took place within a transaction, the lock was held for the duration of the transaction, even after no more data was being read from the NDB table. Now in such cases, the lock is released when all BLOB data associated with the table has been read. (Bug #49190)

Note

A shared lock is also taken for unique key lookups; it is still the case that this lock is held for the duration of the transaction.

- Heartbeat thread policy and priority. Beginning with MySQL Cluster NDB 7.1.2, a new configuration parameter Heart-beatThreadPriority makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 7.1.2, the --blob-info option causes this program to include partition information for BLOB tables in its output. Also beginning with MySQL Cluster NDB 7.1.2, the --extra-node-info option causes ndb_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 7.1.2.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster Replication
supports attribute promotion and demotion when replicating between columns of different but similar types on the master and
the slave. For example, it is possible to promote an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave_type_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Change in ndbinfo database. The experimental pools table was removed from ndbinfo in MySQL Cluster NDB 7.1.3. Applications which used this table can and should be rewritten to use other ndbinfo tables.
- Configuration caching control. Beginning with MySQL Cluster NDB 7.1.4, it is possible to disable the management server's configuration cache using the --config-cache option, which forces ndb_mgmd to read its configuration data from the config.ini configuration file every time it starts. For more information about configuration caching and this option, see Section 3.2, "MySQL Cluster Configuration Files", as well as Section 4.4, "ndb_mgmd The MySQL Cluster Management Server Daemon".
- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 7.1.4, DDL events are no longer reported on Event objects by default. Instead such event reporting must be enabled explicitly using the Event::setReport() method. For more information, see Event::setReport(), and The Event::EventReport Type.
- Number of table attributes. Beginning with MySQL Cluster NDB 7.1.4, the maximum number of attributes (columns plus indexes) per table has been increased from 128 to 512.
- InnobB support in commercial binaries. Beginning with MySQL Cluster NDB 7.1.4b, all commercial binary releases of MySQL Cluster provide support for the InnobB storage engine.
- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 7.1.5, it is possible to set a specific order for transmission of heartbeats between datat nodes, using the HeartbeatOrder data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb_restore column comparison rules. When restoring data, ndb_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 7.1.5, ndb_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
 - COLUMN_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
 - STORAGE setting (MEMORY or DISK)
 - · The default value
 - The distribution key

In such cases, ndb_restore reports any such differences to minimize any chance of user error.

- Storage of user data in anyValue. When writing NDB events to the binary log, MySQL Cluster uses OperationOptions::anyValue to store the server ID. Beginning with MySQL Cluster NDB 7.1.6, it is possible to store user data from an NDB API application in part of the anyValue when mysqld has been started with the --server-id-bits option set to a nondefault value. Also beginning with MySQL Cluster NDB 7.1.6, it is possible to view this data in the output of mysqlbinlog, for which its own --server-id-bits option is added.
- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 7.1.8, this option can be used to
 force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Forcing node shutdown and restart. In MySQL Cluster NDB 7.1.8 and later, it is possible using the ndb_mgm management client or the MGM API to force a data node shutdown or restart even if this would force the shutdown or restart of the entire cluster. In the management client, this is implemented through the addition of the -f (force) option to the STOP and RESTART commands. For more information, see Section 5.2, "Commands in the MySQL Cluster Management Client". The MGM API also adds two new methods for forcing such a node shutdown or restart; see ndb_mgm_stop4(), and ndb_mgm_restart4(), for more information about these methods.
- **Disk Data usage statistics** (**diskpagebuffer table**). MySQL Cluster 7.1.9 introduces a new table in the ndbinfo information database. The diskpagebuffer table provides real-time data on disk page buffer usage. These statistics can be used to monitor performance of MySQL Cluster Disk Data read and write operations, and can prove useful in the tuning of Disk Data parameters such as DiskPageBufferMemory.
- InnobB Plugin support. Beginning with MySQL Cluster NDB 7.1.9, the MySQL Server supplied with MySQL Cluster supports the InnobB Plugin. For more information about enabling the plugin if you are building MySQL Cluster from source, see Chapter 2, MySQL Cluster Installation.

Note

Due to a packaging issue, the InnobB plugin was not included in RPMs for MySQL Cluster NDB 7.1.9; this issue was corrected in MySQL Cluster NDB 7.1.9a. (Bug #58283)

- TimeBetweenEpochsTimeout and GCP stop control. Beginning with MySQL Cluster NDB 7.1.10, it is possible to disable GCP stops by setting TimeBetweenEpochsTimeout to 0. In addition, a warning is written to the cluster log whenever the time required for a GCP save exceeds 60 seconds or the time required for a GCP commit exceeds 10 seconds. This warning includes a report of the current value of TimeBetweenEpochsTimeout. For more information, see Disk Data and GCP Stop errors.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 7.1.10, you can cause ndb_restore to ignore tables that are corrupted due to missing blob parts tables by using the the --skip-broken-objects option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- BLOB read and write batching. Beginning with MySQL Cluster NDB 7.1.10, it possible to control batching of BLOB read and write operations. For SQL nodes, this can be done using the --ndb-blob-read-batch-bytes and --ndb-blob-write-batch-bytes options for mysqld. In NDB API applications, you can control batching of BLOB reads and writes using the NdbTransaction methods setMaxPendingBlobReadBytes(), getMaxPendingBlobReadBytes(), setMaxPendingBlobWriteBytes().
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 7.1.11 adds a new rewrite-database option to ndb_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup", for more information.

• Selective over-commit handling. Beginning with MySQL Cluster NDB 7.1.10, it is possible to exercise more direct control over uncommitted operations from transactions aborted due to timeouts flushing redo logs to disk. This is implemented using three configuration parameters added in this version of MySQL Cluster: the data node configuration parameters RedoOver-CommitCounter and RedoOverCommitLimit, and the API node configuration parameter DefaultOperationRedoProblemAction.

When an attempt to flush a given redo log takes longer than RedoOverCommitLimit seconds, and this occurs RedoOverCommitLimit times or more, the transactions contained within the redo log are aborted. Any operations left uncommitted as a result are either aborted or re-tried, according to the value of DefaultOperationRedoProblemAction.

For more information, see Redo log over-commit handling

INFORMATION_SCHEMA inprovements. Beginning with MySQL Cluster NDB 7.1.11, Beginning with MySQL Cluster NDB 7.0.22, INFORMATION_SCHEMA provides disk usage information for MySQL Cluster Disk Data tables. Previously, IN-

FORMATION_SCHEMA. TABLES showed only the space usage for the in-memory data part of the table. Now, it also shows the space allocated for and used by the disk_part data of that table as well.

In addition, the INFORMATION_SCHEMA. PARTITIONS table (which did not show any statistics for NDB tables) now shows correct values in this table's TABLE_ROWS, AVG_ROW_LENGTH, DATA_LENGTH, MAX_DATA_LENGTH, and DATA_FREE columns, for each partition.

ndb_restore attribute demotion. Beginning with MySQL Cluster NDB 7.1.11, it is possible to enable attribute demotion
when restoring a MySQL Cluster from a native backup running ndb_restore with a new --lossy-conversions option.

In general, the rules governing demotion are the same as for MySQL replication, although there are some exceptions that you may need to take into account being employing this option. See Replication of Columns Having Different Data Types, for information about type conversions currently supported by attribute promotion and demotion in MySQL Cluster.

- Improved multi-threaded order index building. Previously, it was not possible to enable multi-threaded building of ordered indexes during initial restarts. In MySQL Cluster NDB 7.1.11, this can now be done, using the new TwoPassInitial-NodeRestartCopy data node configuration parameter.
- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config_generation column which is added to the nodes table in MySQL Cluster NDB 7.1.13.
- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config_generation column which is added to the nodes table in MySQL Cluster NDB 7.1.13.
- Improvements in adding data nodes online. Begining with MySQL Cluster NDB 7.0.24, it is possible to add data nodes online to a running MySQL Cluster without performing a rolling restart of the cluster or starting data node processes with the -nowait-nodes option. This can be done by setting Nodegroup = 65536 in the config.ini file for any data nodes that should be started at a later time, when first starting the cluster. The amount of time the cluster waits before doing this can be controlled using the StartNoNodeGroupTimeout data node configuration parameter.
- Unique key updates in replication. It is possible in MySQL Cluster NDB 7.1.14 and later to employ operations that update unique keys when replicating NDB tables. Previously this could lead to duplicate key errors when trying to execute the binary log (due to the fact that row events in the binary log were ordered according to the partitioning of the base table, and could differ in order within the epoch for that in which they were executed).

Important

Master and slave tables must both be using the NDB storage engine for this to work.

MySQL Cluster NDB 7.1 (actually, MySQL Cluster NDB 6.3 and later) is also supported by MySQL Cluster Manager, which provides an advanced command-line interface that can simplify many complex MySQL Cluster management tasks. See MySQLTM Cluster Manager 1.1 User Manual, for more information.

1.4.3. MySQL Cluster Development in MySQL Cluster NDB 7.0

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 7.0. For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 7.0, see Changes in MySQL Cluster NDB 7.0.

Important

Early development versions of MySQL Cluster NDB 7.0 were known as "MySQL Cluster NDB 6.4", and the first four releases in this series were identified as MySQL Cluster NDB 6.4.0 through 6.4.3. Any information relating to these MySQL Cluster NDB 6.4.x releases appearing in this documentation apply to MySQL Cluster NDB 7.0.

MySQL Cluster NDB 7.0.4 is the fifth MySQL Cluster NDB 7.0 release; it is the successor to MySQL Cluster NDB 6.4.3.

• MySQL Cluster on Windows (alpha). MySQL Cluster NDB 7.0 is available on an experimental basis for Windows operating systems (for production use on Windows, you should use MySQL Cluster NDB 7.1.3 or later). Features and behavior comparable to those found on platforms that are already supported—such as Linux and Solaris—are planned for MySQL Cluster on Windows. In MySQL Cluster NDB 7.0, you must build from source (Windows binaries are available for MySQL Cluster NDB 7.1 releases). To enable MySQL Cluster support on Windows when building from source, you must configure the build using the WITH_NDBCLUSTER_STORAGE_ENGINE option. For more information, see Installing MySQL from Source on Windows.

- Ability to add nodes and node groups online. Beginning with MySQL Cluster NDB 6.4.0, it is possible to add new node groups (and thus new data nodes) to a running MySQL Cluster without shutting down and reloading the cluster. As part of enabling this feature, a new command CREATE NODEGROUP has been added to the cluster management client and the functionality of the ALTER ONLINE TABLE . . . REORGANIZE PARTITION SQL statement has been extended. For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".
- Data node multithreading support. Beginning with MySQL Cluster NDB 6.4.0, a multithreaded version of the data node daemon, named ndbmtd, is available for use on data node hosts with multiple CPU cores. This binary is built automatically when compiling with MySQL Cluster support; no additional options other than those needed to provide MySQL Cluster support are needed when configuring the build. In most respects, ndbmtd functions in the same way as ndbd, and can use the same command-line options and configuration parameters. In addition, the new MaxNoOfExecutionThreads configuration parameter can be used to determine the number of data node process threads for ndbmtd. For more information, see Section 4.3, "ndbmtd The MySQL Cluster Data Node Daemon (Multi-Threaded)".

Note

Disk Data tables are not yet supported for use with ndbmtd.

- Configuration cache. Formerly, MySQL Cluster configuration was stateless—that is, configuration information was reloaded from the cluster's global configuration file (usually config.ini) each time ndb_mgmd was started. Beginning with MySQL Cluster NDB 6.4.0, the cluster's configuration is cached internally, and the global configuration file is no longer automatically re-read when the management server is restarted. This behavior can be controlled using the management server options configdir, --initial, and --reload. In MySQL Cluster NDB 7.0.15 and later, the configuration cache can be disabled using the --config-cache option. For more information about these changes, see Section 3.2, "MySQL Cluster Configuration Files". For more information about the new management server options, see Section 4.4, "ndb_mgmd The MySQL Cluster Management Server Daemon".
- **Detection of NDB API client connection errors.** In MySQL Cluster NDB 7.0 (6.4.0 and later releases), the NDB API's Ndb_cluster_connection class adds the get_latest_error() and get_latest_error_msg() methods for catching and diagnosing problems with NDB API client connections.
- Snapshot options for backups. Beginning with MySQL Cluster NDB 6.4.0, you can determine when performing a cluster backup whether the backup matches the state of the data when the backup was started or when it was completed, using the new options SNAPSHOTSTART and SNAPSHOTEND for the management client's START BACKUP command. See Section 5.3.2, "Using The MySQL Cluster Management Client to Create a Backup", for more information.
- Dynamic NDB transporter send buffer memory allocation. Previously, the NDB kernel used a fixed-size send buffer for every data node in the cluster, which was allocated when the node started. Because the size of this buffer could not be changed after the cluster was started, it was necessary to make it large enough in advance to accommodate the maximum possible load on any transporter socket. However, this was an inefficient use of memory, since much of it often went unused. Beginning with MySQL Cluster NDB 6.4.0, send buffer memory is allocated dynamically from a memory pool shared between all transporters, which means that the size of the send buffer can be adjusted as necessary. This change is reflected by the addition of the configuration parameters TotalSendBufferMemory, ReservedSendBufferMemory, and OverLoadLimit, as well as a change in how the existing SendBufferMemory configuration parameter is used. For more information, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".
- Robust DDL operations. Beginning with MySQL Cluster NDB 6.4.0, DDL operations (such as CREATE TABLE or ALTER TABLE) are protected from data node failures; in the event of a data node failure, such operations are now rolled back gracefully. Previously, if a data node failed while trying to perform a DDL operation, the MySQL Cluster data dictionary became locked and no further DDL statements could be executed without restarting the cluster.
- IPv6 support in MySQL Cluster Replication. Beginning with MySQL Cluster NDB 6.4.1, IPv6 networking is supported
 between MySQL Cluster SQL nodes, which makes it possible to replicate between instances of MySQL Cluster using IPv6 addresses. However, IPv6 is supported only for direct connections between MySQL servers; all connections within an individual
 MySQL Cluster must use IPv4. For more information, see Section 6.3, "Known Issues in MySQL Cluster Replication".
- Restoring specific databases, tables, or columns from a MySQL Cluster backup. It is now possible to exercise more fine-grained control when restoring a MySQL Cluster from backup using ndb_restore. Beginning with MySQL Cluster NDB 6.4.3, you can choose to restore only specified tables or databases, or exclude specific tables or databases from being restored, using the new ndb_restore options --include-tables, --include-databases, --exclude-tables, and --exclude-databases. Beginning with MySQL Cluster NDB 7.0.7, it is also possible to restore to a table having fewer columns than the original using the --exclude-missing-columns option. For more information about all of these options, see Section 4.17, "ndb_restore Restore a MySQL Cluster Backup".
- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.4.3, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.

- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL Cluster NDB 6.4.3, using the data node configuration parameters InitialLogFileGroup and InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group, tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements are required to create these Disk Data objects. For more information, see *Disk Data object creation parameters*.
- Improved internal message passing and record handling. MySQL Cluster NDB 7.0 contains 2 changes that optimize the use of network connections by addressing the size and number of messages passed between data nodes, and between data nodes and API nodes, which can increase MySQL Cluster and application performance:
 - Packed reads. Formerly, each read request signal contained a list of columns to be retrieved, each of these column identifiers using 4 bytes within the message. This meant that the message size increased as the number of columns being fetched increased. In addition, in the response from the data node, each column result was packed to a 4-byte boundary, which resulted in wasted space. In MySQL Cluster NDB 7.0, messaging for read operations is optimized in both directions, using a bitmap in the read request to specify the columns to be fetched. Where many fields are requested, this can result in a significant message size reduction as compared with the old method. In addition, the 4-byte packing in responses is no longer used, which means that smaller fields consume less space.
 - Long signal transactions. This enhancement reduces the number of messages and signals that are sent to data nodes for complex requests. Prior to MySQL Cluster NDB 7.0, there was a 100 byte limit on the size of the request signal, which meant that complex requests had to be split up between multiple messages prior to transmission, then reassembled on the receiving end. In addition to actual payload data, each message required its own operating system and protocol overhead such as header information. This often wasted network bandwidth and data node CPU. The maximum size of the message is now 32 KB, which is sufficient to accommodate most queries.

Both of these optimizations are internal to the NDB API, and so is transparent to applications; this is true whether an application uses the NDB API directly or does so indirectly through an SQL node.

- Configuration parameter data dumps. Starting with MySQL Cluster NDB 7.0.6, the ndb_config utility supports a -configinfo option that causes it to dump a list of all configuration parameters supported by the cluster, along with brief
 descriptions, information about the parameters' default and permitted values, and the sections of the config.ini file in
 which the parameters apply. An additional --xml switch causes ndb_config to use XML rather than plaintext output. Using
 ndb_config --configinfo or ndb_config --configinfo --xml requires no access to a running MySQL
 Cluster, any other programs, or any files. For more information and examples, see Section 4.6, "ndb_config -- Extract
 MySQL Cluster Configuration Information".
- Per-table reporting of free space on disk. The INFORMATION_SCHEMA.FILES table shows information about used and free space in MySQL Cluster Disk Data data files, but this information is not applicable to individual tables. In MySQL Cluster NDB 7.0.8 and later, the ndb_desc utility provides two additional columns in its output that show the amount of space allocated on disk for a given NDB table as well the amount of space that remains available for additional storage of disk-based column data for that table. For more information, see Section 4.9, "ndb_desc Describe NDB Tables".
- Improved restart times. Optimizations in redo log handling and other file system operations introduced in MySQL Cluster NDB 7.0.9 have the potential to reduce considerably the time required for restarts. While actual performance benefits observed in production setups will naturally vary depending on database size, hardware, and other conditions, our own preliminary testing has shown that these improvements can yield startup times that are faster than those typical of previous MySQL Cluster NDB 7.0 releases by a factor of 50 or more.
- Native support for default column values. Starting with MySQL Cluster NDB 7.0.15, default values for table columns are
 stored in the NDB kernel rather than by the MySQL server as was done previously. This means that inserts on tables having
 column value defaults can be smaller and faster than before, because less data must be sent from SQL nodes to NDBCLUSTER.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.0.15 and later; however, they do not support native default values until they are upgraded. You can upgrade a table with non-native default values to support native default values using an offline ALTER TABLE statement.

- --nowait-nodes option for management servers. Starting with MySQL Cluster NDB 7.0.10, it is possible to configure a cluster with two management servers, but to start the cluster using only one of them by starting the management node daemon with the --nowait-nodes option. The other management server can then be started at a later time to join the running MySQL Cluster.
- Increased flexibility in online upgrade procedure. Previously, when performing an upgrade of a running MySQL cluster, the order in which the types of cluster nodes had to be upgraded was very strict. However, beginning with MySQL Cluster NDB 7.0.10, MySQL Cluster supports online upgrading of API nodes (including MySQL servers running as SQL nodes) online upgrading management nodes, data nodes, or both.

Important

Before attempting to use this new upgrade functionality, see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster", for additional information, especially if you are planning an online upgrade to MySQL Cluster NDB 7.0

- from MySQL Cluster NDB 6.3.
- New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 7.0.11, the CHANGE MASTER TO statement supports an IGNORE_SERVER_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

- New replication conflict resolution strategy. Beginning with MySQL Cluster NDB 7.0.11, the function NDB\$MAX_DELETE_WIN() is available to implement "greatest timestamp, delete wins" conflict resolution. See NDB\$MAX_DELETE_WIN(column_name), for more information.
- Improved lock handling for primary key lookups on BLOB tables. A MySQL Cluster table stores all but the first 256 bytes of any BLOB or TEXT column values in a separate BLOB table; when executing queries against such tables, a shared lock is obtained. Prior to MySQL Cluster NDB 7.0.12, when the query used a primary key lookup and took place within a transaction, the lock was held for the duration of the transaction, even after no more data was being read from the NDB table. Now in such cases, the lock is released when all BLOB data associated with the table has been read. (Bug #49190)

Note

A shared lock is also taken for unique key lookups; it is still the case that this lock is held for the duration of the transaction

- Heartbeat thread policy and priority. Beginning with MySQL Cluster NDB 7.0.13, a new configuration parameter HeartbeatThreadPriority makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 7.0.13, the --blob-info option causes this program to include partition information for BLOB tables in its output. Beginning with MySQL Cluster NDB 7.0.14, the --extra-node-info option causes ndb_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 7.0.14.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 7.0.14, MySQL Cluster Replication
supports attribute promotion and demotion when replicating between columns of different but similar types on the master and
the slave. For example, it is possible to promote an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave_type_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 7.0.15, DDL events are no longer reported on Event objects by default. Instead such event reporting must be enabled explicitly using the Event::setReport() method. For more information, see Event::setReport(), and The Event::EventReport Type.
- Number of table attributes. Beginning with MySQL Cluster NDB 7.0.15, the maximum number of attributes (columns plus indexes) per table has been increased from 128 to 512.
- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 7.0.16, it is possible to set a specific order for transmission of heartbeats between data nodes, using the HeartbeatOrder data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb_restore column comparison rules. When restoring data, ndb_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 7.0.16, ndb_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
 - COLUMN_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
 - STORAGE setting (MEMORY or DISK)
 - The default value

· The distribution key

In such cases, ndb_restore reports any such differences to minimize any chance of user error.

- Storage of user data in anyValue. When writing NDB events to the binary log, MySQL Cluster uses OperationOptions::anyValue to store the server ID. Beginning with MySQL Cluster NDB 7.0.17, it is possible to store user data from an NDB API application in part of the anyValue when mysqld has been started with the --server-id-bits option set to a nondefault value. Also beginning with MySQL Cluster NDB 7.0.17, it is possible to view this data in the output of mysql-binlog, for which its own --server-id-bits option is added.
- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 7.0.19, this option can be used to force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Forcing node shutdown and restart. In MySQL Cluster NDB 7.0.19 and later, it is possible using the ndb_mgm management client or the MGM API to force a data node shutdown or restart even if this would force the shutdown or restart of the entire cluster. In the management client, this is implemented through the addition of the -f (force) option to the STOP and RE-START commands. For more information, see Section 5.2, "Commands in the MySQL Cluster Management Client". The MGM API also adds two new methods for forcing such a node shutdown or restart; see ndb_mgm_stop4(), and ndb mgm restart4(), for more information about these methods.
- TimeBetweenEpochsTimeout and GCP stop control. Beginning with MySQL Cluster NDB 7.0.21, it is possible to disable GCP stops by setting TimeBetweenEpochsTimeout to 0. In addition, a warning is written to the cluster log whenever the time required for a GCP save exceeds 60 seconds or the time required for a GCP commit exceeds 10 seconds. This warning includes a report of the current value of TimeBetweenEpochsTimeout. For more information, see Disk Data and GCP Stop errors.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 7.0.21, you can cause ndb_restore to ignore tables that are corrupted due to missing blob parts tables by using the the --skip-broken-objects option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- BLOB read and write batching. Beginning with MySQL Cluster NDB 7.0.21, it possible to control batching of BLOB read and write operations. For SQL nodes, this can be done using the --ndb-blob-read-batch-bytes and --ndb-blob-write-batch-bytes options for mysqld. In NDB API applications, you can control batching of BLOB reads and writes using the NdbTransaction methods setMaxPendingBlobReadBytes(), getMaxPendingBlobReadBytes(), setMaxPendingBlobWriteBytes().
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 7.0.22 adds a new rewrite-database option to ndb_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup", for more information.

• INFORMATION_SCHEMA inprovements. Beginning with MySQL Cluster NDB 7.0.22, INFORMATION_SCHEMA provides disk usage information for MySQL Cluster Disk Data tables. Previously, INFORMATION_SCHEMA. TABLES showed only the space usage for the in-memory data part of the table. Now, it also shows the space allocated for and used by the disk_part data of that table as well.

In addition, the INFORMATION_SCHEMA. PARTITIONS table (which did not show any statistics for NDB tables) now shows correct values in this table's TABLE_ROWS, AVG_ROW_LENGTH, DATA_LENGTH, MAX_DATA_LENGTH, and DATA_FREE columns, for each partition.

- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config_generation column which is added to the nodes table in MySQL Cluster NDB 7.0.24.
- Improvements in adding data nodes online. Begining with MySQL Cluster NDB 7.0.24, it is possible to add data nodes online to a running MySQL Cluster without performing a rolling restart of the cluster or starting data node processes with the -nowait-nodes option. This can be done by setting Nodegroup = 65536 in the config.ini file for any data nodes that should be started at a later time, when first starting the cluster. The amount of time the cluster waits before doing this can be controlled using the StartNoNodeGroupTimeout data node configuration parameter.
- Unique key updates in replication. It is possible in MySQL Cluster NDB 7.0.25 and later to employ operations that update unique keys when replicating NDB tables. Previously this could lead to duplicate key errors when trying to execute the binary log (due to the fact that row events in the binary log were ordered according to the partitioning of the base table, and could differ in order within the epoch for that in which they were executed).

Important

Master and slave tables must both be using the NDB storage engine for this to work.

MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, and later are also supported by MySQL Cluster Manager, which provides an advanced command-line interface that can simplify many complex MySQL Cluster management tasks. See MySQLTM Cluster Manager 1.1 User Manual, for more information.

1.4.4. MySQL Cluster Development in MySQL Cluster NDB 6.3

The following list provides an overview of significant feature additions and changes first made in MySQL Cluster NDB 6.3. For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 6.3, see Changes in MySQL Cluster NDB 6.3.

- Conflict detection and resolution. It is now possible to detect and resolve conflicts that arise in multi-master replication scenarios, such as circular replication, when different masters may try to update the same row on the slave with different data. Both "greatest timestamp wins" and "same timestamp wins" scenarios are supported. For more information, see Section 6.11, "MySQL Cluster Replication Conflict Resolution".
- Recovery of "one master, many slaves" replication setups. Recovery of multi-way replication setups ("one master, many slaves") is now supported using the --ndb-log-orig server option and changes in the mysql.ndb_binlog_index table. See Section 6.4, "MySQL Cluster Replication Schema and Tables", for more information.
- Enhanced selection options for transaction coordinator. New values and behaviors are introduced for -ndb_optimized_node_selection, enabling greater flexibility when an SQL node chooses a transaction coordinator.
 For more information, see the description of ndb_optimized_node_selection in Section 3.4.3, "MySQL Cluster System Variables".
- **Replication heartbeats.** Replication heartbeats facilitate the task of monitoring and detecting failures in master-slave connections in real time. This feature is implemented using a new MASTER_HEARTBEAT_PERIOD = value clause for the CHANGE MASTER TO statement and the addition of two status variables Slave_heartbeat_period and Slave_received_heartbeats. For more information, see CHANGE MASTER TO Syntax.
- NDB thread locks. It is possible to lock NDB execution threads and maintenance threads (such as file system and other operating system threads) to specific CPUs on multiprocessor data node hosts, and to leverage real-time scheduling.
- Improved performance of updates using primary keys or unique keys. The number of unnecessary reads when performing a primary key or unique key update has been greatly reduced. Since it is seldom necessary to read a record prior to an update, this can yield a considerable improvement in performance. In addition, primary key columns are no longer written to when not needed during update operations.
- **Batching improvements.** Support of batched DELETE and UPDATE operations has been significantly improved. Batching of UPDATE WHERE... and multiple DELETE operations is also now implemented.
- Improved SQL statement performance metrics. The Ndb_execute_count system status variable measures the number of round trips made by SQL statements to the NDB kernel, providing an improved metric for determining efficiency with which statements are excuted. For more information, see MySQL Cluster Status Variables: Ndb_execute_count.
- Compressed LCPs and backups. Compressed local checkpoints and backups can save 50% or more of the disk space used by
 uncompressed LCPs and backups. These can be enabled using the two new data node configuration parameters CompressedLCP and CompressedBackup, respectively.
- OPTIMIZE TABLE support with NDBCLUSTER tables. OPTIMIZE TABLE is supported for dynamic columns of inmemory NDB tables. In such cases, it is no longer necessary to drop (and possibly to re-create) a table, or to perform a rolling restart, in order to recover memory from deleted rows for general re-use by Cluster. The performance of OPTIMIZE on Cluster tables can be tuned by adjusting the value of the ndb_optimization_delay system variable, which controls the number of milliseconds to wait between processing batches of rows by OPTIMIZE TABLE. In addition, OPTIMIZE TABLE on an NDBCLUSTER table can be interrupted by, for example, killing the SQL thread performing the OPTIMIZE operation.
- Batching of transactions. It is possible to cause statements occurring within the same transaction to be run as a batch by setting the session variable transaction_allow_batching to 1 or ON. To use this feature, autocommit must be set to 0 or OFF. Batch sizes can be controlled using the --ndb-batch-size option for mysqld. For additional information, see Section 3.4.2, "mysqld Command Options for MySQL Cluster", and Section 3.4.3, "MySQL Cluster System Variables".
- Attribute promotion with ndb_restore. It is possible using ndb_restore to restore data reliably from a column of a
 given type to a column that uses a "larger" type. This is sometimes referred to as attribute promotion. For example, MySQL
 Cluster backup data that originated in a SMALLINT column can be restored to a MEDIUMINT, INT, or BIGINT column. See

Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup", for more information.

- Parallel data node recovery. Recovery of multiple data nodes can now be done in parallel, rather than sequentially. In other words, several data nodes can be restored concurrently, which can often result in much faster recovery times than when they are restored one at a time.
- Increased local checkpoint efficiency. Only 2 local checkpoints are stored, rather than 3, lowering disk space requirements and the size and number of redo log files.
- NDBCLUSTER table persistence control. Persistence of NDB tables can be controlled using the session variables ndb_table_temporary and ndb_table_no_logging. ndb_table_no_logging causes NDB tables not to be checkpointed to disk; ndb_table_temporary does the same, and in addition, no schema files are created. See Section 3.4.1, "MySQL Cluster Server Option and Variable Reference".
- Epoll support (Linux only). Epoll is an improved method for handling file descriptors, which is more efficient than scanning
 to determine whether a file descriptor has data to be read. (The term epoll is specific to Linux and equivalent functionality is
 known by other names on other platforms such as Solaris and FreeBSD.) Currently, MySQL Cluster supports this functionality
 on Linux only.
- **Distribution awareness** (**SQL nodes**). In MySQL Cluster NDB 6.3, SQL nodes can take advantage of distribution awareness. Here we provide a brief example showing how to design a table to make a given class of queries distribution-aware. Suppose an NDBCLUSTER table t1 has the following schema:

```
CREATE TABLE t1 (
    userid INT NOT NULL,
    serviceid INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
    data VARCHAR(255)
) ENGINE=NDBCLUSTER;
```

Suppose further that most of the queries to be used in our application test values of the userid column of this table. The form of such a query looks something like this:

```
SELECT columns FROM t1
WHERE userid relation value;
```

In this query, relation represents some relational operator, such as =, <, >, and so on. Queries using IN and a list of values can also be used:

```
SELECT columns FROM t1
WHERE userid IN value_list;
```

To make use of distribution awareness, we need to make the userid column part of the table's primary key, then explicitly partition the table with this column being used as the partitioning key. (Recall that for a partitioned table having one or more unique keys, all columns of the table's partitioning key must also be part of all of the unique keys—for more information and examples, see Partitioning Keys, Primary Keys, and Unique Keys.) In other words, the table schema should be equivalent to the following CREATE TABLE statement:

```
CREATE TABLE t1 (
    userid INT NOT NULL,
    serviceid INT NOT NULL AUTO_INCREMENT,
    data VARCHAR(255),
    PRIMARY KEY p (userid, serviceid)
) ENGINE=NDBCLUSTER
    PARTITION BY KEY(userid);
```

When the table is partitioned in this way, all rows having the same userid value are found on the same node group, and the MySQL Server can immediately select the optimal node to use as the transaction coordinator.

- Realtime extensions for multiple CPUs. When running MySQL Cluster data nodes on hosts with multiple processors, the realtime extensions make it possible to give priority to the data node process and control on which CPU cores it should operate. This can be done using the data node configuration parameters RealtimeScheduler, SchedulerExecutionTimer, and SchedulerSpinTimer. Doing so properly can significantly lower response times and make them much more predictable response. For more information about using these parameters, see Defining Data Nodes: Realtime Performance Parameters
- Fully automatic database discovery. It is no longer a requirement for database autodiscovery that an SQL node already be connected to the cluster at the time that a database is created on another SQL node, or for a CREATE DATABASE or CREATE SCHEMA statement to be issued on the new SQL node after it joins the cluster.
- Detection of NDB API client connection errors. Beginning with MySQL Cluster NDB 6.3.20, the NDB API's Ndb_cluster_connection class adds the get_latest_error() and get_latest_error_msg() methods for catching and diagnosing problems with NDB API client connections.

- Restoring specific databases, tables, or columns from a MySQL Cluster backup. It is now possible to exercise more fine-grained control when restoring a MySQL Cluster from backup using ndb_restore. Beginning with MySQL Cluster NDB 6.3.22, you can choose to restore only specified tables or databases, or exclude specific tables or databases from being restored, using the new ndb_restore options --include-tables, --include-databases, --exclude-tables, and --exclude-databases. Beginning with MySQL Cluster NDB 6.3.26, it is also possible to restore to a table having fewer columns than the original using the --exclude-missing-columns option. For more information about all of these options, see Section 4.17, "ndb_restore Restore a MySQL Cluster Backup".
- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.3.22, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDDtaaFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.
- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL Cluster NDB 6.3.22, using the data node configuration parameters InitialLogFileGroup and InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group, tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements are required to create these Disk Data objects. For more information, see *Disk Data object creation parameters*.
- Configuration parameter data dumps. Starting with MySQL Cluster NDB 6.3.25, the ndb_config utility supports a --configinfo option that causes it to dump a list of all configuration parameters supported by the cluster, along with brief descriptions, information about the parameters' default and permitted values, and the sections of the config.ini file in which the parameters apply. An additional --xml switch causes ndb_config to use XML rather than plaintext output. Using ndb_config --configinfo or ndb_config --configinfo --xml requires no access to a running MySQL Cluster, any other programs, or any files. For more information and examples, see Section 4.6, "ndb_config Extract MySQL Cluster Configuration Information".
- Per-table reporting of free space on disk. The INFORMATION_SCHEMA.FILES table shows information about used and free space in MySQL Cluster Disk Data data files, but this information is not applicable to individual tables. In MySQL Cluster NDB 6.3.27 and later, the ndb_desc utility provides two additional columns in its output that show the amount of space allocated on disk for a given NDB table as well the amount of space that remains available for additional storage of disk-based column data for that table. For more information, see Section 4.9, "ndb_desc Describe NDB Tables".
- Improved restart times. Optimizations in redo log handling and other file system operations introduced in MySQL Cluster NDB 6.3.28 have the potential to reduce considerably the time required for restarts. While actual performance benefits observed in production setups will naturally vary depending on database size, hardware, and other conditions, our own preliminary testing has shown that these improvements can yield startup times that are faster than those typical of previous MySQL Cluster NDB 6.3 releases by a factor of 50 or more.
- Increased flexibility in online upgrade procedure. Previously, when performing an upgrade of a running MySQL cluster, the order in which the types of cluster nodes had to be upgraded was very strict. However, beginning with MySQL Cluster NDB 6.3.29, MySQL Cluster supports online upgrading of API nodes (including MySQL servers running as SQL nodes) before upgrading management nodes, data nodes, or both.

Important

Before attempting to use this new upgrade functionality, see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster", for additional information, especially if you are planning an online upgrade from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0.

- New replication conflict resolution strategy. Beginning with MySQL Cluster NDB 6.3.31, the function NDB\$MAX_DELETE_WIN() is available to implement "greatest timestamp, delete wins" conflict resolution. See NDB\$MAX_DELETE_WIN(column_name), for more information.
- New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 6.3.31, the CHANGE MASTER TO statement supports an IGNORE_SERVER_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

- Heartbeat thread policy and priority. Beginning with MySQL Cluster NDB 6.3.32, a new configuration parameter HeartbeatThreadPriority makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 6.3.32, the --blob-info option causes this program to include partition information for BLOB tables in its output. Beginning with MySQL Cluster NDB 6.3.33, the --extra-node-info option causes ndb_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 6.3.33.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 6.3.33, MySQL Cluster Replication
supports attribute promotion and demotion when replicating between columns of different but similar types on the master and
the slave. For example, it is possible to promote an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave_type_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 6.3.34, DDL events are no longer reported on Event objects by default. Instead such event reporting must be enabled explicitly using the Event::setReport() method. For more information, see Event::setReport(), and The Event::EventReport Type.
- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 6.3.35, it is possible to set a specific order for transmission of heartbeats between data nodes, using the HeartbeatOrder data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb_restore column comparison rules. When restoring data, ndb_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 6.3.35, ndb_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
 - COLUMN_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
 - STORAGE setting (MEMORY or DISK)
 - The default value
 - · The distribution key

In such cases, ndb_restore reports any such differences to minimize any chance of user error.

- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 6.3.38, this option can be used to force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 6.3.40, you can cause ndb_restore to ignore tables that are corrupted due to missing blob parts tables by using the the --skip-broken-objects option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 6.3.41 adds a new rewrite-database option to ndb_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup", for more information.

MySQL Cluster NDB 6.3 and later is also supported by MySQL Cluster Manager, which provides an advanced command-line interface that can simplify many complex MySQL Cluster management tasks. See MySQLTM Cluster Manager 1.1 User Manual, for more information.

1.4.5. MySQL Cluster Development in MySQL Cluster NDB 6.2

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 6.2. All of the changes in this list are also available in MySQL Cluster NDB 6.3 . For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 6.2, see Changes in MySQL Cluster NDB 6.2.

- Enhanced backup status reporting. Backup status reporting has been improved, aided in part by the introduction of a BackupReportFrequency configuration parameter.
- Multiple cluster connections per SQL node. A single MySQL server acting as a MySQL Cluster SQL node can employ multiple connections to the cluster using the --ndb-cluster-connection-pool startup option for mysqld. This option is described in MySQL Cluster-Related Command Options for mysqld: --ndb-cluster-connection-pool option.
- New data access interface. The NdbRecord interface provides a new and simplified data handler for use in NDB API applications.
- New reporting commands. The new management client REPORT BackupStatus and REPORT MemoryUsage commands provide better access to information about the status of MySQL Cluster backups and how much memory is being used by MySQL Cluster for data and index storage. See Section 5.2, "Commands in the MySQL Cluster Management Client", for more information about the REPORT commands. In addition, in-progress status reporting is provided by the ndb_restore utility; see Section 4.17, "ndb_restore Restore a MySQL Cluster Backup".
- Improved memory allocation and configuration. Memory is now allocated by the NDB kernel to tables on a page-by-page basis, which significantly reduces the memory overhead required for maintaining NDBCLUSTER tables. In addition, the Max-Allocate configuration parameter now makes it possible to set the maximum size of the allocation unit used for table memory.
- Choice of fixed-width or variable-width columns. You can control whether fixed-width or variable-width storage is used for a given column of an NDB table by employing of the COLUMN_FORMAT specifier as part of the column's definition in a CREATE TABLE or ALTER TABLE statement. In addition, the ability to control whether a given column of an NDB table is stored in memory or on disk, using the STORAGE specifier as part of the column's definition in a CREATE TABLE or ALTER TABLE Syntax.
- Controlling management client connections. The --bind-address cluster management server startup option makes it possible to restrict management client connections to ndb_mgmd to a single host (IP address or host name) and port, which can make MySQL Cluster management operations more secure. For more information about this option, see Section 4.4, "ndb_mgmd The MySQL Cluster Management Server Daemon".
- Micro-GCPs. Due to a change in the protocol for handling of global checkpoints (GCPs handled in this manner sometimes being referred to as "micro-GCPs"), it is now possible to control how often the GCI number is updated, and how often global checkpoints are written to disk, using the TimeBetweenEpochs and TimeBetweenEpochsTimeout configuration parameters. This improves the reliability and performance of MySQL Cluster Replication.
- Core online schema change support. Support for the online ALTER TABLE operations ADD COLUMN, ADD INDEX, and DROP INDEX is available. When the ONLINE keyword is used, the ALTER TABLE is noncopying, which means that indexes do not have to be re-created, which provides these benefits:
 - Single user mode is no longer required for ALTER TABLE operations that can be performed online.
 - Transactions can continue during ALTER TABLE operations that can be performed online.
 - Tables being altered online are not locked against access by other SQL nodes.

However, such tables are locked against other operations on the *same* SQL node for the duration of the ALTER TABLE. We are working to overcome this limitation in a future MySQL Cluster release.

Online CREATE INDEX and DROP INDEX statements are also supported. Online changes can be suppressed using the OFF-LINE key word. See ALTER TABLE Online Operations, CREATE INDEX Syntax, and DROP INDEX Syntax, for more detailed information.

- mysql.ndb_binlog_index improvements. More information has been added to the mysql.ndb_binlog_index table so that it is possible to determine which originating epochs have been applied inside an epoch. This is particularly useful for 3-way replication. See Section 6.4, "MySQL Cluster Replication Schema and Tables", for more information.
- Epoch lag control. The MaxBufferedEpochs data node configuration parameter provides a means to control the maximum number of unprocessed epochs by which a subscribing node can lag. Subscribers which exceed this number are disconnected and forced to reconnect.
- Fully automatic database discovery. It is no longer a requirement for database autodiscovery that an SQL node already be connected to the cluster at the time that a database is created on another SQL node, or for a CREATE DATABASE or CREATE SCHEMA statement to be issued on the new SQL node after it joins the cluster.
- Multiple data node processes per host. In earlier MySQL Cluster release series, we did not support MySQL Cluster deployments in production where more than one ndbd process was run on a single physical machine. However, beginning with MySQL Cluster NDB 6.2.0, you can use multiple data node processes on a single host.

Note

A multi-threaded version of ndbd tailored for use on hosts with multiple CPUs or cores was introduced in MySQL Cluster NDB 7.0. See Section 1.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.2.17, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.
- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL Cluster NDB 6.2.17, using the data node configuration parameters InitialLogFileGroup and InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group, tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements are required to create these Disk Data objects.
- Improved access to partitioning information. The ndb_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 6.2.19, the --extra-node-info option causes ndb_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). This option also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 6.2.19.

New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 6.2.19, the CHANGE
MASTER TO statement supports an IGNORE_SERVER_IDS option which takes a comma-separated list of server IDs and
causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

1.4.6. MySQL Cluster Development in MySQL Cluster NDB 6.1

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 6.1. All of the changes in this list are also available in MySQL Cluster NDB 6.2 and 6.3 releases. For detailed information about all changes made in MySQL Cluster NDB 6.1, see Changes in MySQL Cluster NDB 6.1.

- Increased number of cluster nodes. The maximum number of all nodes in a MySQL Cluster has been increased to 255. For more information, see Section 1.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".
- **Disabling arbitration.** It is now possible to disable arbitration by setting ArbitrationRank=0 on all cluster management and SQL nodes. For more information, see *Defining the Management Server:* ArbitrationRank and *Defining SQL and Other API Nodes:* ArbitrationRank.
- Additional DUMP commands. New management client DUMP commands provide help with tracking transactions, scan operations, and locks. See Section 5.2, "Commands in the MySQL Cluster Management Client", and DUMP Commands, for more information.
- Faster Disk Data backups. Improvements in backups of Disk Data tables can yield a 10 to 15% increase in backup speed of Disk Data tables
- Batched slave updates. Batching of updates on cluster replication slaves, enabled using the --slave-allow-batching option for mysqld, increases replication efficiency. For more information, see Section 6.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

1.4.7. Development History of MySQL Cluster in MySQL 5.1

A number of features for MySQL Cluster were implemented in MySQL 5.1 through MySQL 5.1.23, when support for MySQL Cluster was moved to MySQL Cluster NDB. All of the features in the following list are also available in all MySQL Cluster NDB (6.1 and later) releases.

• Integration of MySQL Cluster into MySQL Replication. MySQL Cluster Replication makes it possible to replicate from one MySQL Cluster to another. Updates on any SQL node (MySQL server) in the cluster acting as the master are replicated to the slave cluster; the state of the slave side remains consistent with the cluster acting as the master. This is sometimes referred to as asynchronous replication between clusters, providing geographic redundancy. It is also possible to replicate from a MySQL Cluster acting as the master to a standalone MySQL server acting as the slave, or from a standalone MySQL master server to to a slave cluster; in either of these cases, the standalone MySQL server uses a storage engine other than NDB-

CLUSTER. Multi-master replication setups such as circular replication are also supported.

See Chapter 6, MySQL Cluster Replication.

Support for storage of rows on disk. Storage of NDBCLUSTER table data on disk is now supported. Indexed columns, including the primary key hash index, must still be stored in RAM; however, all other columns can be stored on disk.

See Section 5.11, "MySQL Cluster Disk Data Tables".

- Variable-size columns. In MySQL 5.0, an NDBCLUSTER table column defined as VARCHAR (255) used 260 bytes of storage independent of what was stored in any particular record. In MySQL 5.1 Cluster tables, only the portion of the column actually taken up by the record is stored. This makes possible a significant reduction in space requirements for such columns as compared to previous release series—by a factor of up to 5 in many cases.
- User-defined partitioning. Users can define partitions based on columns that are part of the primary key. It is possible to partition NDB tables based on KEY and LINEAR KEY schemes. This feature is also available for many other MySQL storage engines, which support additional partitioning types that are not available with NDBCLUSTER tables.

For additional general information about user-defined partitioning in MySQL 5.1, see Partitioning. Specifics of partitioning types are discussed in Partitioning Types.

The MySQL Server can also determine whether it is possible to "prune away" some of the partitions from the WHERE clause, which can greatly speed up some queries. See Partition Pruning, for information about designing tables and queries to take advantage of partition pruning.

Autodiscovery of table schema changes. In MySQL 5.0, it was necessary to issue a FLUSH TABLES statement or a
"dummy" SELECT for new NDBCLUSTER tables or changes made to schemas of existing NDBCLUSTER tables on one SQL
node to be visible on the cluster's other SQL nodes. In MySQL 5.1, this is no longer necessary; new Cluster tables and changes
in the definitions of existing NDBCLUSTER tables made on one SQL node are immediately visible to all SQL nodes connected
to the cluster.

Note

When creating a new database, it is still necessary in MySQL 5.1 to issue a CREATE DATABASE or CREATE SCHEMA statement on each SQL node in the cluster.

- **Distribution awareness (NDB API).** *Distribution awareness* is a mechanism by which the best data node is automatically selected to be queried for information. (Conceptually, it is similar in some ways to partition pruning (see Partition Pruning). To take advantage of distribution awareness, you should do the following:
 - 1. Determine which table column is most likely to be used for finding matching records.
 - 2. Make this column part of the table's primary key.
 - 3. Explicitly partition the table by KEY, using this column as the table' partitioning key.

Following these steps causes records with the same value for the partitioning column to be stored on the same partition (that is, in the same node group). When reading data, transactions are begun on the data node actually having the desired rows instead of this node being determined by the usual round-robin mechanism.

Important

To see a measureable impact on performance, the cluster must have at least four data nodes, since, with only two data nodes, both data nodes have exactly the same data.

Using distribution awareness can yield performance increase of as great as 45% when using four data nodes, and possibly more when using a greater number of data nodes.

Note

In mainline MySQL 5.1 releases, distribution awareness was supported only when using the NDB API; support was added for SQL and API nodes in MySQL Cluster NDB 6.3 (see Section 1.4.4, "MySQL Cluster Development in MySQL Cluster NDB 6.3", which includes an example showing how to create a table to take advantage of distribution awareness).

Online adding and dropping of indexes. For ALTER TABLE statements, ADD INDEX and DROP INDEX operations for
dynamic (variable-width) columns on NDB tables are now performed as online operations (no table copying). This is also true
for CREATE INDEX and DROP INDEX. As a result, these operations are now performed much more quickly than previously.

For more information, see ALTER TABLE Online Operations, CREATE INDEX Syntax, and DROP INDEX Syntax.

See Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

1.5. MySQL Server using InnoDB Compared with MySQL Cluster

MySQL Server offers a number of choices in storage engines. Since both NDBCLUSTER and InnoDB can serve as transactional MySQL storage engines, users of MySQL Server sometimes become interested in MySQL Cluster. They see NDB as a possible alternative or upgrade to the default InnoDB storage engine in MySQL 5.5. While NDB and InnoDB share common characteristics, there are differences in architecture and implementation, so that some existing MySQL Server applications and usage scenarios can be a good fit for MySQL Cluster, but not all of them.

In this section, we discuss and compare some characteristics of the NDB storage engine used by MySQL Cluster with InnoDB used in MySQL 5.1 and MySQL 5.5. The next few sections provide a technical comparison. In many instances, decisions about when and where to use MySQL Cluster must be made on a case-by-case basis, taking all factors into consideration. While it is beyond the scope of this documentation to provide specifics for every conceivable usage scenario, we also attempt to offer some very general guidance on the relative suitability of some common types of applications for NDB as opposed to InnoDB backends.

While it is possible to use InnoDB tables with MySQL Cluster, such tables are not clustered. It is also not always possible to use the latest MySQL Cluster and InnoDB features and enhancements together due to availability issues. Currently, the latest MySQL Cluster NDB 7.1 releases use a mysqld based on MySQL 5.1; while the most recent InnoDB enhancements are available only in MySQL Server 5.5, where MySQL Cluster is not currently supported. It is also not possible to use programs or libraries from a MySQL Cluster NDB 6.x or MySQL Cluster NDB 7.x distribution with MySQL Server 5.1 or MySQL Server 5.5, or the reverse.

While it is also true that some types of common business applications can be run either on MySQL Cluster or on MySQL Server (most likely using the InnoDB storage engine), there are some important architectural and implementation differences. Section 1.5.1, "Differences Between the NDB and InnoDB Storage Engines", provides a summary of the these differences. Due to the differences, some usage scenarios are clearly more suitable for one engine or the other; see Section 1.5.2, "NDB and InnoDB Workloads". This in turn has an impact on the types of applications that better suited for use with NDB or InnoDB. See Section 1.5.3, "NDB and InnoDB Feature Usage Summary", for a comparison of the relative suitability of each for use in common types of database applications.

For information about the relative characteristics of the NDB and MEMORY storage engines, see MEMORY compared with MySQL Cluster.

See Storage Engines, for additional information about MySQL storage engines.

1.5.1. Differences Between the NDB and InnoDB Storage Engines

The MySQL Cluster NDB storage engine is implemented using a distributed, shared-nothing architecture, which causes it to behave differently from InnoDB in a number of ways. For those unaccustomed to working with NDB, unexpected behaviors can arise due to its distributed nature with regard to transactions, foreign keys, joins, and other characteristics. These are shown in the following table:

Feature	InnoDB	MySQL Cluster (NDB)
MySQL Server Availability	5.5 (in latest MySQL 5.5 GA release)	5.1 (SQL nodes currently based on MySQL 5.1.51 GA)
InnoDB Availability	InnoDB 1.1 plugin	NDB 6.3, 7.0: InnoDB storage engine
		NDB 7.1: InnoDB 1.0 plugin support, as of MySQL Cluster NDB 7.1.9a
Storage Limits	64TB	2TB
		(Practical upper limit for database size)
Foreign Keys	Yes	No
		(Foreign keys ignored, as with MyISAM)
Transactions	All standard types	Only READ COMMITTED supported
MVCC Non-Blocking Reads	Yes	No
	(Read concurrency without locks)	

Feature	InnoDB	MySQL Cluster (NDB)
Multi-Table Join Performance	Good	Poor
		(Push-down joins can improve MySQL Cluster performance, but InnoDB provides higher throughput)
Data Compression	Yes	No
		(MySQL Cluster checkpoint and backup files can be compressed)
Large Row Support (> 8K)	Supported for VARBINARY, VARCHAR, BLOB, and TEXT columns	Supported for BLOB and TEXT columns only
		(Using these types to store very large amounts of data can lower MySQL Cluster performance)
Virtualization	Yes	No
	(Can be deployed on both physical and virtual infrastructure)	(Not supported in virtual environments)
Minimum Number of Physical Hosts for Redundancy	2: 1 active, 1 passive	3: 2 data nodes, 1 management node
Availability (HA)	No	Yes (99.999%)
Node Failure Recovery and Failover	Requires additional software	Automatic
		(Key element in MySQL Cluster architecture)
Time for Node Failure Recovery	30 seconds to several hours	< 1 second
Real-Time Performance	No	Yes (Low latency)
In-Memory Storage	No	Yes
		(Some data can optionally be stored on disk; both in-memory and disk data storage are durable)
Direct (non-SQL) API Access to Storage	No	Yes
Engine		(Faster access possible when bypassing SQL interface to data)
Scalability	Poor	Good
	(Requires application-level partitioning)	(Data already partitioned by MySQL Cluster; schema and query optimization required to maximize scaling of writes)
Concurrent and Parallel Writes	Not supported	Up to 48 writers, optimized for concurrent writes
		(MySQL Cluster supports up to 48 data nodes for processing, with 24 nodes for storage, due to requirements for two-fold redundancy)

Feature	InnoDB	MySQL Cluster (NDB)
Conflict Detection and Resolution (Multiple Replication Masters)	No	Yes (True active-active geographic replication, in which each application node can read or write to its own local database)
Hash Indexes	No	Yes (Can provide fast access to key/value data)

1.5.2. NDB and InnoDB Workloads

MySQL Cluster has a range of unique attributes that make it ideal to serve applications requiring high availability, fast failover, high throughput, and low latency. Due to its real-time nature, distributed architecture, and multi-node implementation, MySQL Cluster also has specific constraints that may keep some workloads from performing well. A number of major differences in behavior between the NDB and InnobB storage engines with regard to some common types of database-driven application workloads are shown in the following table:

Workload	InnoDB	MySQL Cluster (NDB)
In-Network Telecoms Applications (HLR, HSS, SDP)	No	Yes
Packaged Applications	Yes	Access should be mostly by primary key
Custom Applications	Yes	Yes
OLTP Applications	Yes	Yes
DSS Applications (data marts, analytics)	Yes	No
Content Management	Yes	Limited support
Web Session Management	Yes	Yes
E-Commerce Applications	Yes	Yes
User Profile Management, AAA Protocol	Yes	Yes

1.5.3. NDB and InnoDB Feature Usage Summary

When comparing application feature requirements to the capabilities of InnoDB with NDB, some are clearly more compatible with one storage engine than the other. For example, since NDB does not support foreign keys, an application that requires them and cannot be re-engineered to remove this requirement is likely not to be a good match for MySQL Cluster.

The following table shows required supported features for applications according to which of these two storage engines each of them is usually better suited:

Application requirements better supported with InnoDB	Application requirements better supported with NDB	
Foreign keys	Real-time concurrency	
Large or complex joins	High availability, high-speed failover	
Very large datastores or transactions	Fast low-level APIs (see MySQL Cluster APIs: Overview	

Application requirements better supported with NDB
and Concepts)
Primary-key lookups, key/value data
Limited use of BLOB columns

1.6. Known Limitations of MySQL Cluster

In the sections that follow, we discuss known limitations in current releases of MySQL Cluster as compared with the features available when using the MyISAM and InnoDB storage engines. If you check the "Cluster" category in the MySQL bugs database at http://bugs.mysql.com, you can find known bugs in the following categories under "MySQL Server:" in the MySQL bugs database at http://bugs.mysql.com, which we intend to correct in upcoming releases of MySQL Cluster:

- MySQL Cluster
- Cluster Direct API (NDBAPI)
- Cluster Disk Data
- Cluster Replication
- · ClusterJ

This information is intended to be complete with respect to the conditions just set forth. You can report any discrepancies that you encounter to the MySQL bugs database using the instructions given in How to Report Bugs or Problems. If we do not plan to fix the problem in MySQL Cluster NDB 6.X or 7.X, we will add it to the list.

See Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x" for a list of issues in MySQL Cluster in MySQL 5.0 that have been resolved in the current version.

Note

Limitations and other issues specific to MySQL Cluster Replication are described in Section 6.3, "Known Issues in MySQL Cluster Replication".

1.6.1. Noncompliance with SQL Syntax in MySQL Cluster

Some SQL statements relating to certain MySQL features produce errors when used with NDB tables, as described in the following list:

- Temporary tables. Temporary tables are not supported. Trying either to create a temporary table that uses the NDB storage engine or to alter an existing temporary table to use NDB fails with the error Table Storage Engine 'NDBCLUSTER' DOES NOT SUPPORT THE CREATE OPTION 'TEMPORARY'.
- Indexes and keys in NDB tables. Keys and indexes on MySQL Cluster tables are subject to the following limitations:
 - Column width. Attempting to create an index on an NDB table column whose width is greater than 3072 bytes succeeds, but only the first 3072 bytes are actually used for the index. In such cases, a warning Specified key was too long; max key length is 3072 bytes is issued, and a SHOW CREATE TABLE statement shows the length of the index as 3072.
 - TEXT and BLOB columns. You cannot create indexes on NDB table columns that use any of the TEXT or BLOB data types.
 - FULLTEXT indexes. The NDB storage engine does not support FULLTEXT indexes, which are possible for MyISAM tables
 only.

However, you can create indexes on VARCHAR columns of NDB tables.

USING HASH keys and NULL. Using nullable columns in unique keys and primary keys means that queries using these
columns are handled as full table scans. To work around this issue, make the column NOT NULL, or re-create the index
without the USING HASH option.

- **Prefixes.** There are no prefix indexes; only entire columns can be indexed. (The size of an NDB column index is always the same as the width of the column in bytes, up to and including 3072 bytes, as described earlier in this section. Also see Section 1.6.6, "Unsupported or Missing Features in MySQL Cluster", for additional information.)
- BIT columns. A BIT column cannot be a primary key, unique key, or index, nor can it be part of a composite primary key, unique key, or index.
- AUTO_INCREMENT columns. Like other MySQL storage engines, the NDB storage engine can handle a maximum of one AUTO_INCREMENT column per table. However, in the case of a Cluster table with no explicit primary key, an AUTO_INCREMENT column is automatically defined and used as a "hidden" primary key. For this reason, you cannot define a table that has an explicit AUTO_INCREMENT column unless that column is also declared using the PRIMARY KEY option. Attempting to create a table with an AUTO_INCREMENT column that is not the table's primary key, and using the NDB storage engine, fails with an error.
- MySQL Cluster and geometry data types. Geometry data types (WKT and WKB) are supported in NDB tables in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1). However, spatial indexes are not supported.
- Character sets and binary log files. Currently, the ndb_apply_status and ndb_binlog_index tables are created using the latin1 (ASCII) character set. Because names of binary logs are recorded in this table, binary log files named using non-Latin characters are not referenced correctly in these tables. This is a known issue, which we are working to fix. (Bug #50226)

To work around this problem, use only Latin-1 characters when naming binary log files or setting any the --basedir, --log-bin, or --log-bin-index options.

• Creating NDBCLUSTER tables with user-defined partitioning. Support for user-defined partitioning for MySQL Cluster in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1) is restricted to [LINEAR] KEY partitioning. Beginning with MySQL 5.1.12, using any other partitioning type with ENGINE=NDB or ENGINE=NDBCLUSTER in a CREATE TABLE statement results in an error.

Default partitioning scheme. As of MySQL 5.1.6, all MySQL Cluster tables are by default partitioned by KEY using the table's primary key as the partitioning key. If no primary key is explicitly set for the table, the "hidden" primary key automatically created by the NDBCLUSTER storage engine is used instead. For additional discussion of these and related issues, see KEY Partitioning.

Beginning with MySQL Cluster NDB 6.2.18, MySQL Cluster NDB 6.3.25, and MySQL Cluster NDB 7.0.6, CREATE TABLE and ALTER TABLE statements that would cause a user-partitioned NDBCLUSTER table not to meet either or both of the following two requirements are not permitted, and fail with an error (Bug #40709):

- 1. The table must have an explicit primary key.
- 2. All columns listed in the table's partitioning expression must be part of the primary key.

Exception. If a user-partitioned NDBCLUSTER table is created using an empty column-list (that is, using PARTITION BY [LINEAR] KEY()), then no explicit primary key is required.

Maximum number of partitions for NDBCLUSTER tables. The maximum number of partitions that can defined for a NDBCLUSTER table when employing user-defined partitioning is 8 per node group. (See Section 1.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions", for more information about MySQL Cluster node groups.

DROP PARTITION not supported. It is not possible to drop partitions from NDB tables using ALTER TABLE ... DROP PARTITION. The other partitioning extensions to ALTER TABLE—ADD PARTITION, REORGANIZE PARTITION, and COALESCE PARTITION—are supported for Cluster tables, but use copying and so are not optimized. See Management of RANGE and LIST Partitions and ALTER TABLE Syntax.

• Row-based replication. When using row-based replication with MySQL Cluster, binary logging cannot be disabled. That is, the NDB storage engine ignores the value of sql_log_bin. (Bug #16680)

1.6.2. Limits and Differences of MySQL Cluster from Standard MySQL Limits

In this section, we list limits found in MySQL Cluster that either differ from limits found in, or that are not found in, standard MySQL.

Memory usage and recovery. Memory consumed when data is inserted into an NDB table is not automatically recovered when deleted, as it is with other storage engines. Instead, the following rules hold true:

· A DELETE statement on an NDB table makes the memory formerly used by the deleted rows available for re-use by inserts on

the same table only. However, this memory can be made available for general re-use by performing a rolling restart of the cluster. See Section 5.4, "Performing a Rolling Restart of a MySQL Cluster".

Beginning with MySQL Cluster NDB 6.3.7, this limitation can be overcome using OPTIMIZE TABLE. See Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

 A DROP TABLE or TRUNCATE TABLE operation on an NDB table frees the memory that was used by this table for re-use by any NDB table, either by the same table or by another NDB table.

Note

Recall that TRUNCATE TABLE drops and re-creates the table. See TRUNCATE TABLE Syntax.

- Limits imposed by the cluster's configuration. A number of hard limits exist which are configurable, but available main memory in the cluster sets limits. See the complete list of configuration parameters in Section 3.2, "MySQL Cluster Configuration Files". Most configuration parameters can be upgraded online. These hard limits include:
 - Database memory size and index memory size (DataMemory and IndexMemory, respectively).

DataMemory is allocated as 32KB pages. As each DataMemory page is used, it is assigned to a specific table; once allocated, this memory cannot be freed except by dropping the table.

See Section 3.2.6, "Defining MySQL Cluster Data Nodes", for more information.

The maximum number of operations that can be performed per transaction is set using the configuration parameters
 MaxNoOfConcurrentOperations and MaxNoOfLocalOperations.

Note

Bulk loading, TRUNCATE TABLE, and ALTER TABLE are handled as special cases by running multiple transactions, and so are not subject to this limitation.

- Different limits related to tables and indexes. For example, the maximum number of ordered indexes in the cluster is determined by MaxNoofOrderedIndexes, and the maximum number of ordered indexes per table is 16.
- Node and data object maximums. The following limits apply to numbers of cluster nodes and metadata objects:
 - The maximum number of data nodes is 48.
 - A data node must have a node ID in the range of 1 to 48, inclusive. (Previous to MySQL Cluster NDB 6.1.1, management and API nodes were restricted to the range 1 to 63 inclusive as a node ID; starting with MySQL Cluster NDB 6.1.1, management and API nodes may use node IDs in the range 1 to 255, inclusive.)
 - Prior to MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster was 63. Beginning with MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster is 255. In either case, this number includes all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers.
 - The maximum number of metadata objects in current versions of MySQL Cluster is 20320. This limit is hard-coded.

See Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

1.6.3. Limits Relating to Transaction Handling in MySQL Cluster

A number of limitations exist in MySQL Cluster with regard to the handling of transactions. These include the following:

- Transaction isolation level. The NDBCLUSTER storage engine supports only the READ COMMITTED transaction isolation level. (InnoDB, for example, supports READ COMMITTED, READ UNCOMMITTED, REPEATABLE READ, and SERIALIZABLE.) See Section 5.3.4, "MySQL Cluster Backup Troubleshooting", for information on how this can affect backing up and restoring Cluster databases.)
- Transactions and BLOB or TEXT columns. NDBCLUSTER stores only part of a column value that uses any of MySQL's BLOB or TEXT data types in the table visible to MySQL; the remainder of the BLOB or TEXT is stored in a separate internal table that is not accessible to MySQL. This gives rise to two related issues of which you should be aware whenever executing SELECT statements on tables that contain columns of these types:

- 1. For any SELECT from a MySQL Cluster table: If the SELECT includes a BLOB or TEXT column, the READ COMMITTED transaction isolation level is converted to a read with read lock. This is done to guarantee consistency.
- Prior to MySQL Cluster NDB 7.0.12, for any SELECT which used a primary key lookup or unique key lookup to retrieve
 any columns that used any of the BLOB or TEXT data types and that was executed within a transaction, a shared read lock
 was held on the table for the duration of the transaction—that is, until the transaction was either committed or aborted.

In MySQL Cluster NDB 7.0.12 and later, for primary key lookups, the lock is released as soon as all BLOB or TEXT data has been read. (Bug #49190) However, for unique key lookups, the shared lock continues to be held for the lifetime of the transaction.

This issue does not occur for queries that use index or table scans, even against NDB tables having BLOB or TEXT columns.

For example, consider the table t defined by the following CREATE TABLE statement:

```
CREATE TABLE t (
a INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
b INT NOT NULL,
c INT NOT NULL,
d TEXT,
INDEX i(b),
UNIQUE KEY u(c)
) ENGINE = NDB,
```

Either of the following queries on t causes a shared read lock, because the first query uses a primary key lookup and the second uses a unique key lookup:

```
SELECT * FROM t WHERE a = 1;
SELECT * FROM t WHERE c = 1;
```

However, none of the four queries shown here causes a shared read lock:

```
SELECT * FROM t WHERE b 1;

SELECT * FROM t WHERE d = '1';

SELECT * FROM t;

SELECT b,c WHERE a = 1;
```

This is because, of these four queries, the first uses an index scan, the second and third use table scans, and the fourth, while using a primary key lookup, does not retrieve the value of any BLOB or TEXT columns.

You can help minimize issues with shared read locks by avoiding queries that use unique key lookups (or primary key lookups in MySQL Cluster NDB 7.0.11 and earlier) that retrieve BLOB or TEXT columns, or, in cases where such queries are not avoidable, by committing transactions as soon as possible afterward.

• Rollbacks. There are no partial transactions, and no partial rollbacks of transactions. A duplicate key or similar error causes the entire transaction to be rolled back.

This behavior differs from that of other transactional storage engines such as InnoDB that may roll back individual statements.

- Transactions and memory usage. As noted elsewhere in this chapter, MySQL Cluster does not handle large transactions well; it is better to perform a number of small transactions with a few operations each than to attempt a single large transaction containing a great many operations. Among other considerations, large transactions require very large amounts of memory. Because of this, the transactional behavior of a number of MySQL statements is effected as described in the following list:
 - TRUNCATE TABLE is not transactional when used on NDB tables. If a TRUNCATE TABLE fails to empty the table, then it must be re-run until it is successful.
 - DELETE FROM (even with no WHERE clause) is transactional. For tables containing a great many rows, you may find that
 performance is improved by using several DELETE FROM ... LIMIT ... statements to "chunk" the delete operation.
 If your objective is to empty the table, then you may wish to use TRUNCATE TABLE instead.
 - LOAD DATA statements. LOAD DATA INFILE is not transactional when used on NDB tables.

Important

When executing a LOAD DATA INFILE statement, the NDB engine performs commits at irregular intervals that enable better utilization of the communication network. It is not possible to know ahead of time when such commits take place.

LOAD DATA FROM MASTER is not supported in MySQL Cluster.

- ALTER TABLE and transactions. When copying an NDB table as part of an ALTER TABLE, the creation of the copy is nontransactional. (In any case, this operation is rolled back when the copy is deleted.)
- Transactions and the COUNT() function. When using MySQL Cluster Replication, it is not possible to guarantee the transactional consistency of the COUNT() function on the slave. In other words, when performing on the master a series of statements (INSERT, DELETE, or both) that changes the number of rows in a table within a single transaction, executing SELECT COUNT(*) FROM table queries on the slave may yield intermediate results. This is due to the fact that SELECT COUNT(...) may perform dirty reads, and is not a bug in the NDB storage engine. (See Bug #31321 for more information.)

1.6.4. MySQL Cluster Error Handling

Starting, stopping, or restarting a node may give rise to temporary errors causing some transactions to fail. These include the following cases:

- Temporary errors. When first starting a node, it is possible that you may see Error 1204 TEMPORARY FAILURE, DISTRIBUTION CHANGED and similar temporary errors.
- Errors due to node failure. The stopping or failure of any data node can result in a number of different node failure errors. (However, there should be no aborted transactions when performing a planned shutdown of the cluster.)

In either of these cases, any errors that are generated must be handled within the application. This should be done by retrying the transaction.

See also Section 1.6.2, "Limits and Differences of MySOL Cluster from Standard MySOL Limits".

1.6.5. Limits Associated with Database Objects in MySQL Cluster

Some database objects such as tables and indexes have different limitations when using the NDBCLUSTER storage engine:

Table names containing special characters. NDB tables whose names contain characters other than letters, numbers, dashes, and underscores and which are created on one SQL node were not always discovered correctly by other SQL nodes. (Bug #31470)

Note

This issue was fixed in MySQL 5.1.23, MySQL Cluster NDB 6.2.7, and MySQL Cluster NDB 6.3.4.

- Number of database objects. The maximum number of *all* NDB database objects in a single MySQL Cluster—including databases, tables, and indexes—is limited to 20320.
- Attributes per table. Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the maximum number of attributes (that is, columns and indexes) per table is limited to 128.

Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this limit is increased to 512.

- Attributes per key. The maximum number of attributes per key is 32.
- Row size. The maximum permitted size of any one row is 8052 bytes. Each BLOB or TEXT column contributes 256 + 8 = 264 bytes to this total.
- Number of rows per partition. A single MySQL Cluster partition can hold a maximum of 46137488 rows. Since the number of partitions is the same as the number of data nodes in the cluster (see Section 1.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions"), you can increase the available space for data storage by using more data nodes.

In MySQL Cluster NDB 7.0 and later MySQL Cluster release series, you can increase the number of data nodes in the cluster while the cluster remains in operation. See Section 5.12, "Adding MySQL Cluster Data Nodes Online", for more information.

It is also possible to increase the number of partitions for NDB tables by using explicit KEY or LINEAR KEY partitioning (see KEY Partitioning).

1.6.6. Unsupported or Missing Features in MySQL Cluster

A number of features supported by other storage engines are not supported for NDB tables. Trying to use any of these features in MySQL Cluster does not cause errors in or of itself; however, errors may occur in applications that expects the features to be sup-

ported or enforced:

- Foreign key constraints. The foreign key construct is ignored, just as it is in MyISAM tables.
- Index prefixes. Prefixes on indexes are not supported for NDBCLUSTER tables. If a prefix is used as part of an index specification in a statement such as CREATE TABLE, ALTER TABLE, or CREATE INDEX, the prefix is ignored.
- **OPTIMIZE operations.** OPTIMIZE operations are not supported.

Beginning with MySQL Cluster NDB 6.3.7, this limitation has been lifted. See Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

- LOAD TABLE ... FROM MASTER. LOAD TABLE FROM MASTER is not supported.
- Savepoints and rollbacks. Savepoints and rollbacks to savepoints are ignored as in MyISAM.
- Durability of commits. There are no durable commits on disk. Commits are replicated, but there is no guarantee that logs are flushed to disk on commit.
- Replication. Statement-based replication is not supported. Use --binlog-format=ROW (or --binlog-format=MIXED) when setting up cluster replication. See Chapter 6, MySQL Cluster Replication, for more information.

Note

See Section 1.6.3, "Limits Relating to Transaction Handling in MySQL Cluster", for more information relating to limitations on transaction handling in NDB.

1.6.7. Limitations Relating to Performance in MySQL Cluster

The following performance issues are specific to or especially pronounced in MySQL Cluster:

- Range scans. There are query performance issues due to sequential access to the NDB storage engine; it is also relatively more expensive to do many range scans than it is with either MyISAM or InnoDB.
- Reliability of Records in range. The Records in range statistic is available but is not completely tested or officially supported. This may result in nonoptimal query plans in some cases. If necessary, you can employ USE INDEX or FORCE INDEX to alter the execution plan. See Index Hint Syntax, for more information on how to do this.
- Unique hash indexes. Unique hash indexes created with USING HASH cannot be used for accessing a table if NULL is given as part of the key.

1.6.8. Issues Exclusive to MySQL Cluster

The following are limitations specific to the NDBCLUSTER storage engine:

- Machine architecture. All machines used in the cluster must have the same architecture. That is, all machines hosting nodes must be either big-endian or little-endian, and you cannot use a mixture of both. For example, you cannot have a management node running on a PowerPC which directs a data node that is running on an x86 machine. This restriction does not apply to machines simply running mysql or other clients that may be accessing the cluster's SQL nodes.
- Binary logging. MySQL Cluster has the following limitations or restrictions with regard to binary logging:
 - sql_log_bin has no effect on data operations; however, it is supported for schema operations.
 - MySQL Cluster cannot produce a binary log for tables having BLOB columns but no primary key.
 - Only the following schema operations are logged in a cluster binary log which is not on the mysqld executing the statement:
 - CREATE TABLE
 - ALTER TABLE
 - DROP TABLE

- CREATE DATABASE/CREATE SCHEMA
- DROP DATABASE / DROP SCHEMA
- CREATE TABLESPACE
- ALTER TABLESPACE
- DROP TABLESPACE
- CREATE LOGFILE GROUP
- ALTER LOGFILE GROUP
- DROP LOGFILE GROUP

See also Section 1.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

1.6.9. Limitations Relating to MySQL Cluster Disk Data Storage

Disk Data object maxmimums and minimums. Disk data objects are subject to the following maximums and minimums:

- Maximum number of tablespaces: 2³² (4294967296)
- Maximum number of data files per tablespace: 2¹⁶ (65536)
- The theoretical maximum number of extents per tablespace data file is 2^{16} (65536); however, for practical purposes, the recommended maximum number of extents per data file is 2^{15} (32768).
- Maximum data file size: The theoretical limit is 64G; however, in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the practical upper limit is 32G. This is equivalent to 32768 extents of 1M each.

The minimum and maximum possible sizes of extents for tablespace data files are 32K and 2G, respectively. See CREATE TABLESPACE Syntax, for more information.

Disk Data tables and diskless mode. Use of Disk Data tables is not supported when running the cluster in diskless mode. Beginning with MySQL 5.1.12, it is prohibited altogether. (Bug #20008)

1.6.10. Limitations Relating to Multiple MySQL Cluster Nodes

Multiple SQL nodes. The following are issues relating to the use of multiple MySQL servers as MySQL Cluster SQL nodes, and are specific to the NDBCLUSTER storage engine:

- No distributed table locks. A LOCK TABLES works only for the SQL node on which the lock is issued; no other SQL node in the cluster "sees" this lock. This is also true for a lock issued by any statement that locks tables as part of its operations. (See next item for an example.)
- ALTER TABLE operations. ALTER TABLE is not fully locking when running multiple MySQL servers (SQL nodes). (As discussed in the previous item, MySQL Cluster does not support distributed table locks.)

Multiple management nodes. When using multiple management servers:

- You must give nodes explicit IDs in connectstrings because automatic allocation of node IDs does not work across multiple
 management servers.
- You must take extreme care to have the same configurations for all management servers. No special checks for this are performed by the cluster.

Multiple network addresses. Multiple network addresses per data node are not supported. Use of these is liable to cause problems: In the event of a data node failure, an SQL node waits for confirmation that the data node went down but never receives it because another route to that data node remains open. This can effectively make the cluster inoperable.

Note

It is possible to use multiple network hardware *interfaces* (such as Ethernet cards) for a single data node, but these must be bound to the same address. This also means that it not possible to use more than one [tcp] section per connection in the config.ini file. See Section 3.2.8, "MySQL Cluster TCP/IP Connections", for more information.

1.6.11. Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x

A number of limitations and related issues existing in earlier versions of MySQL Cluster have been resolved:

 Variable-length column support. The NDBCLUSTER storage engine now supports variable-length column types for inmemory tables.

Previously, for example, any Cluster table having one or more VARCHAR fields which contained only relatively small values, much more memory and disk space were required when using the NDBCLUSTER storage engine than would have been the case for the same table and data using the MyISAM engine. In other words, in the case of a VARCHAR column, such a column required the same amount of storage as a CHAR column of the same size. In MySQL 5.1, this is no longer the case for in-memory tables, where storage requirements for variable-length column types such as VARCHAR and BINARY are comparable to those for these column types when used in MyISAM tables (see Data Type Storage Requirements).

Important

For MySQL Cluster Disk Data tables, the fixed-width limitation continues to apply. See Section 5.11, "MySQL Cluster Disk Data Tables".

 Replication with MySQL Cluster. It is now possible to use MySQL replication with Cluster databases. For details, see Chapter 6, MySQL Cluster Replication.

Circular Replication. Circular replication is also supported with MySQL Cluster, beginning with MySQL 5.1.18. See Section 6.10, "MySQL Cluster Replication: Multi-Master and Circular Replication".

- auto_increment_increment and auto_increment_offset. The auto_increment_increment and auto_increment_offset server system variables are supported for Cluster replication beginning with MySQL 5.1.20, MySQL Cluster NDB 6.2.5, and MySQL Cluster 6.3.2.
- Database autodiscovery and online schema changes. Autodiscovery of databases is now supported for multiple MySQL servers accessing the same MySQL Cluster. Formerly, autodiscovery in MySQL Cluster 5.1 and MySQL Cluster NDB 6.x releases required that a given mysqld was already running and connected to the cluster at the time that the database was created on a different mysqld—in other words, when a mysqld process connected to the cluster after a database named db_name was created, it was necessary to issue a CREATE DATABASE db_name or CREATE SCHEMA db_name statement on the "new" MySQL server when it first accessed that MySQL Cluster. Beginning with MySQL Cluster NDB 6.2.16 and MySQL Cluster NDB 6.3.18, such a CREATE statement is no longer required. (Bug #39612)

This also means that online schema changes in NDB tables are now possible. That is, the result of operations such as ALTER TABLE and CREATE INDEX performed on one SQL node in the cluster are now visible to the cluster's other SQL nodes without any additional action being taken.

- Backup and restore between architectures. Beginning with MySQL 5.1.10, it is possible to perform a Cluster backup and restore between different architectures. Previously—for example—you could not back up a cluster running on a big-endian platform and then restore from that backup to a cluster running on a little-endian system. (Bug #19255)
- Character set directory. Beginning with MySQL 5.1.10, it is possible to install MySQL with Cluster support to a nondefault location and change the search path for font description files using either the --basedir or --character-sets-dir options. (Previously, ndbd in MySQL 5.1 searched only the default path—typically / usr/local/mysql/share/mysql/charsets—for character sets.)
- Multiple management servers. In MySQL 5.1 (including all MySQL Cluster NDB 6.x and later versions), it is no longer necessary, when running multiple management servers, to restart all the cluster's data nodes to enable the management nodes to see one another.

Also, when using multiple management servers and starting concurrently several API nodes (possibly including one or more SQL nodes) whose connectstrings listed the management servers in different order, it was possible for 2 API nodes to be assigned the same node ID. This issue is resolved in MySQL Cluster NDB 6.2.17, 6.3.23, and 6.4.3. (Bug #42973)

• Multiple data node processes per host. Beginning with MySQL Cluster NDB 6.2.0, you can use multiple data node processes on a single host. (In MySQL Cluster NDB 6.1, MySQL 5.1, and earlier release series, we did not support production MySQL Cluster deployments in which more than one ndbd process was run on a single physical machine.)

In addition, MySQL Cluster NDB 7.0 introduces support for multi-threaded data nodes (ndbmtd). See Section 1.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

- Identifiers. Formerly (in MySQL 5.0 and earlier), database names, table names and attribute names could not be as long for NDB tables as tables using other storage engines, because attribute names were truncated internally. In MySQL 5.1 and later, names of MySQL Cluster databases, tables, and table columns follow the same rules regarding length as they do for any other storage engine.
- Length of CREATE TABLE statements. CREATE TABLE statements may be no more than 4096 characters in length. *This limitation affects MySQL 5.1.6, 5.1.7, and 5.1.8 only.* (See Bug #17813)
- IGNORE and REPLACE functionality. In MySQL 5.1.7 and earlier, INSERT IGNORE, UPDATE IGNORE, and REPLACE were supported only for primary keys, but not for unique keys. It was possible to work around this issue by removing the constraint, then dropping the unique index, performing any inserts, and then adding the unique index again.

This limitation was removed for INSERT IGNORE and REPLACE in MySQL 5.1.8. (See Bug #17431.)

 AUTO_INCREMENT columns. In MySQL 5.1.10 and earlier versions, the maximum number of tables having AUTO_INCREMENT columns—including those belonging to hidden primary keys—was 2048.

This limitation was lifted in MySQL 5.1.11.

Maximum number of cluster nodes. Prior to MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster was 63, including all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers.

Starting with MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster is 255, including all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers. The total number of data nodes and management nodes beginning with this version is 63, of which up to 48 can be data nodes.

Note

The limitation that a data node cannot have a node ID greater than 49 continues to apply.

- Recovery of memory from deleted rows. Beginning with MySQL Cluster NDB 6.3.7, memory can be reclaimed from an NDB table for reuse with any NDB table by employing OPTIMIZE TABLE, subject to the following limitations:
 - Only in-memory tables are supported; the OPTIMIZE TABLE statement still has no effect on MySQL Cluster Disk Data tables.
 - Only variable-length columns (such as those declared as VARCHAR, TEXT, or BLOB) are supported.

However, you can force columns defined using fixed-length data types (such as CHAR) to be dynamic using the ROW_FORMAT or COLUMN_FORMAT option with a CREATE TABLE or ALTER TABLE statement.

See CREATE TABLE Syntax, and ALTER TABLE Syntax, for information on these options.

You can regulate the effects of OPTIMIZE on performance by adjusting the value of the global system variable ndb_optimization_delay, which sets the number of milliseconds to wait between batches of rows being processed by OPTIMIZE. The default value is 10 milliseconds. It is possible to set a lower value (to a minimum of 0), but not recommended. The maximum is 100000 milliseconds (that is, 100 seconds).

• Implicit Rollbacks. Prior to MySQL Cluster NDB 6.2.17 and MySQL Cluster NDB 6.3.19, MySQL Cluster did not automtically roll back a transaction that was aborted by a duplicate key or similar error, and subsequent statements raised ERROR 1296 (HY000): Got error 4350 'Transaction already aborted' from NDBCLUSTER. In such cases, it was necessary to issue an explicit ROLLBACK statement first, and then to retry the entire transaction.

Beginning with MySQL Cluster NDB 6.2.17 and MySQL Cluster NDB 6.3.19, this limitation has been removed; now, an error which causes a transaction to be aborted generates an implicit rollback of the entire transaction. This is logged with the warning Storage engine NDB does not support rollback for this statement. Transaction rolled back and must be restarted. A statement subsequent to this starts a new transaction. (Bug #32656)

Note

The NDBCLUSTER storage engine does not support partial transactions or partial rollbacks of transactions in any version of MySQL Cluster.

• Number of tables. Previously, the maximum number of NDBCLUSTER tables in a single MySQL Cluster was 1792, but this is

no longer the case in MySQL 5.1 and later MySQL Cluster releases. However, the number of tables is still included in the total maximum number of NDBCLUSTER database objects (20320). (See Section 1.6.5, "Limits Associated with Database Objects in MySQL Cluster".)

- DDL operations. Beginning with MySQL Cluster NDB 6.4.0, DDL operations (such as CREATE TABLE or ALTER TABLE)
 are protected from data node failures. Previously, if a data node failed while trying to perform one of these, the data dictionary
 became locked and no further DDL statements could be executed without restarting the cluster (Bug #36718).
- Adding and dropping of data nodes. In MySQL Cluster NDB 6.3 and previous versions of MySQL Cluster, the online
 adding or dropping of data nodes was not possible; such operations required a complete shutdown and restart of the entire
 cluster. In MySQL Cluster NDB 7.0 (beginning with MySQL Cluster NDB 6.4.0) and later MySQL Cluster release series, it is
 possible to add new data nodes to a running MySQL Cluster by performing a rolling restart, so that the cluster and the data
 stored in it remain available to applications.

When planning to increase the number of data nodes in the cluster online in MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1, you should be aware of and take into account the following issues:

- · New data nodes can be added online to a MySQL Cluster only as part of a new node group.
- New data nodes can be added online, but cannot yet be dropped online. Reducing the number of data nodes still requires a system restart of the cluster.
- As in previous MySQL Cluster releases, it is not possible to change online either the number of replicas (NoOfReplicas configuration parameter) or the number of data nodes per node group. These changes require a system restart.
- Redistribution of existing cluster data using the new data nodes is not automatic; however, this can be accomplished using simple SQL statements in the mysql client or other MySQL client application once the nodes have been added. During this procedure, it is not possible to perform DDL operations, although DML operations can continue as normal.

The distribution of new cluster data (that is, data stored in the cluster *after* the new nodes have been added) uses the new nodes without manual intervention.

For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".

• Native support for default column values. Starting with MySQL Cluster NDB 7.1.0, default values for table columns are stored by NDBCLUSTER, rather than by the MySQL server as was previously the case. Because less data must be sent from an SQL node to the data nodes, inserts on tables having column value defaults can be performed more efficiently than before.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.1.0 and later, although they do not support native default values and continue to use defaults supplied by the MySQL server until they are upgraded. This can be done by means of an offline ALTER TABLE statement.

Important

You cannot set or change a table column's default value using an online ALTER TABLE operation

- InnoDB plugin support. Previously, InnoDB support in MySQL Cluster was limited to the version built in to the MySQl Server. Beginning with MySQL Cluster NDB 7.1.9, MySQL Cluster also provides support for the InnoDB Plugin. See Chapter 2, MySQL Cluster Installation, for information about enabling InnoDB storage engine and plugin support with MySQL Cluster.
- Distribution of MySQL users and privileges. Previously, MySQL users and privileges created on one SQL node were unique
 to that SQL node, due to the fact that the MySQL grant tables were restricted to using the MyISAM storage engine. Beginning
 with MySQL Cluster NDB 7.2.0, it is possible, following installation of the MySQL Cluster software and setup of the desired
 users and privileges on one SQL node, to convert the grant tables to use NDB and thus to distribute the users and privileges
 across all SQL nodes connected to the cluster. You can do this by loading and making use of a set of stored procedures defined
 in an SQL script supplied with the MySQL Cluster distribution. For more information, see Section 5.13, "Distributed MySQL
 Privileges for MySQL Cluster".

Chapter 2. MySQL Cluster Installation

This section describes the basics for planning, installing, configuring, and running a MySQL Cluster. Whereas the examples in Chapter 3, MySQL Cluster Configuration provide more in-depth information on a variety of clustering options and configuration, the result of following the guidelines and procedures outlined here should be a usable MySQL Cluster which meets the minimum requirements for availability and safeguarding of data.


This section covers hardware and software requirements; networking issues; installation of MySQL Cluster; configuration issues; starting, stopping, and restarting the cluster; loading of a sample database; and performing queries.

Assumptions. The following sections make a number of assumptions regarding the cluster's physical and network configuration. These assumptions are discussed in the next few paragraphs.

Cluster nodes and host computers. The cluster consists of four nodes, each on a separate host computer, and each with a fixed network address on a typical Ethernet network as shown here:

Node	IP Address
Management node (mgmd)	192.168.0.10
SQL node (mysqld)	192.168.0.20
Data node "A" (ndbd)	192.168.0.30
Data node "B" (ndbd)	192.168.0.40

This may be made clearer by the following diagram:



Network addressing. In the interest of simplicity (and reliability), this *How-To* uses only numeric IP addresses. However, if DNS resolution is available on your network, it is possible to use host names in lieu of IP addresses in configuring Cluster. Alternatively, you can use the hosts file (typically /etc/hosts for Linux and other Unix-like operating systems, C:\WINDOWS\system32\drivers\etc\hosts on Windows, or your operating system's equivalent) for providing a means

to do host lookup if such is available.

Potential hosts file issues. A common problem when trying to use host names for Cluster nodes arises because of the way in which some operating systems (including some Linux distributions) set up the system's own host name in the /etc/hosts during installation. Consider two machines with the host names ndb1 and ndb2, both in the cluster network domain. Red Hat Linux (including some derivatives such as CentOS and Fedora) places the following entries in these machines' /etc/hosts files:

```
# ndb1 /etc/hosts:
127.0.0.1 ndb1.cluster ndb1 localhost.localdomain localhost

# ndb2 /etc/hosts:
127.0.0.1 ndb2.cluster ndb2 localhost.localdomain localhost
```

 $SUSE\ Linux\ (including\ OpenSUSE)\ places\ these\ entries\ in\ the\ machines'\ /\verb|etc/hosts| files:$

```
127.0.0.1 localhost
127.0.0.2 ndb1.cluster ndb1

# ndb2 /etc/hosts:
127.0.0.1 localhost
127.0.0.2 ndb2.cluster ndb2
```

In both instances, ndb1 routes ndb1.cluster to a loopback IP address, but gets a public IP address from DNS for ndb2.cluster, while ndb2 routes ndb2.cluster to a loopback address and obtains a public address for ndb1.cluster. The result is that each data node connects to the management server, but cannot tell when any other data nodes have connected, and so the data nodes appear to hang while starting.

Caution

ndb1 /etc/hosts:

You cannot mix localhost and other host names or IP addresses in config.ini. For these reasons, the solution in such cases (other than to use IP addresses for *all* config.ini HostName entries) is to remove the fully qualified host names from /etc/hosts and use these in config.ini for all cluster hosts.

Host computer type. Each host computer in our installation scenario is an Intel-based desktop PC running a supported operating system installed to disk in a standard configuration, and running no unnecessary services. The core operating system with standard TCP/IP networking capabilities should be sufficient. Also for the sake of simplicity, we also assume that the file systems on all hosts are set up identically. In the event that they are not, you should adapt these instructions accordingly.

Network hardware. Standard 100 Mbps or 1 gigabit Ethernet cards are installed on each machine, along with the proper drivers for the cards, and that all four hosts are connected through a standard-issue Ethernet networking appliance such as a switch. (All machines should use network cards with the same throughout. That is, all four machines in the cluster should have 100 Mbps cards *or* all four machines should have 1 Gbps cards.) MySQL Cluster works in a 100 Mbps network; however, gigabit Ethernet provides better performance.

Important

MySQL Cluster is *not* intended for use in a network for which throughput is less than 100 Mbps or which experiences a high degree of latency. For this reason (among others), attempting to run a MySQL Cluster over a wide area network such as the Internet is not likely to be successful, and is not supported in production.

Sample data. We use the world database which is available for download from the MySQL Web site (see http://dev.mysql.com/doc/index-other.html). We assume that each machine has sufficient memory for running the operating system, required MySQL Cluster processes, and (on the data nodes) storing the database.

For general information about installing MySQL, see Installing and Upgrading MySQL. For information about installation of MySQL Cluster on Linux and other Unix-like operating systems, see Section 2.1, "Installing MySQL Cluster on Linux". For information about installation of MySQL Cluster on Windows operating systems, see Section 2.2, "Installing MySQL Cluster on Windows".

For general information about MySQL Cluster hardware, software, and networking requirements, see Section 1.3, "MySQL Cluster Hardware, Software, and Networking Requirements".

2.1. Installing MySQL Cluster on Linux

This section covers installation of MySQL Cluster on Linux and other Unix-like operating systems. While the next few sections refer to a Linux operating system, the instructions and procedures given there should be easily adaptable to other supported Unix-like platforms.

Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported for production use on Windows operating systems;

for installation and setup instructions specific to Windows, see Section 2.2, "Installing MySQL Cluster on Windows".

Each MySQL Cluster host computer must have the correct executable programs installed. A host running an SQL node must have installed on it a MySQL Server binary (mysqld). Management nodes require the management server daemon (ndb_mgmd); data nodes require the data node daemon (ndbd; in MySQL Cluster NDB 7.0 and later, you can use ndbmtd instead. It is not necessary to install the MySQL Server binary on management node hosts and data node hosts. It is recommended that you also install the management client (ndb_mgm) on the management server host.

Installation of MySQL Cluster on Linux can be done using precompiled binaries from Oracle (downloaded as a .tar.gz archive), with RPM packages (also available from Oracle), or from source code. All three of these installation methods are described in the section that follow.

Regardless of the method used, it is still necessary following installation of the MySQL Cluster binaries to create configuration files for all cluster nodes, before you can start the cluster. See Section 2.3, "Initial Configuration of MySQL Cluster".

2.1.1. Installing a MySQL Cluster Binary Release on Linux

This section covers the steps necessary to install the correct executables for each type of Cluster node from precompiled binaries supplied by Oracle.

For setting up a cluster using precompiled binaries, the first step in the installation process for each cluster host is to download the latest MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, or MySQL Cluster NDB 7.1 binary archive (mysql-

```
cluster-gpl-6.3.45-linux-i686-glibc23.tar.gz, mysql-cluster-gpl-7.0.27-linux-i686-glibc23.tar.gz, or mysql-cluster-gpl-7.1.16-linux-i686-glibc23.tar.gz, respectively) from the MySQL Cluster downloads area. We assume that you have placed this file in each machine's /var/tmp directory. (If you do require a custom binary, see Installing MySQL from a Development Source Tree.)
```

Note

After completing the installation, do not yet start any of the binaries. We show you how to do so following the configuration of the nodes (see Section 2.3, "Initial Configuration of MySQL Cluster").

Data nodes and SQL nodes. On each of the machines designated to host data nodes or SQL nodes, perform the following steps as the system root user:

1. Check your /etc/passwd and /etc/group files (or use whatever tools are provided by your operating system for managing users and groups) to see whether there is already a mysql group and mysql user on the system. Some OS distributions create these as part of the operating system installation process. If they are not already present, create a new mysql user group, and then add a mysql user to this group:

```
shell> groupadd mysql shell> useradd -g mysql mysql
```

The syntax for useradd and groupadd may differ slightly on different versions of Unix, or they may have different names such as adduser and addgroup.

2. Change location to the directory containing the downloaded file, unpack the archive, and create a symbolic link named mysql to the mysql directory. Note that the actual file and directory names vary according to the MySQL Cluster version number.

```
shell> cd /var/tmp
shell> tar -C /usr/local -xzvf mysql-cluster-gpl-7.1.16-linux-i686-glibc23.tar.gz
shell> ln -s /usr/local/mysql-cluster-gpl-7.1.16-linux-i686-glibc23 /usr/local/mysql
```

3. Change location to the mysql directory and run the supplied script for creating the system databases:

```
shell> cd mysql
shell> scripts/mysql_install_db --user=mysql
```

4. Set the necessary permissions for the MySQL server and data directories:

```
shell> chown -R root .
shell> chown -R mysql data
shell> chgrp -R mysql .
```

Note that the data directory on each machine hosting a data node is /usr/local/mysql/data. This piece of information is essential when configuring the management node. (See Section 2.3, "Initial Configuration of MySQL Cluster".)

5. Copy the MySQL startup script to the appropriate directory, make it executable, and set it to start when the operating system is

booted up:

```
shell> cp support-files/mysql.server /etc/rc.d/init.d/
shell> chmod +x /etc/rc.d/init.d/mysql.server
shell> chkconfig --add mysql.server
```

(The startup scripts directory may vary depending on your operating system and version—for example, in some Linux distributions, it is /etc/init.d.)

Here we use Red Hat's chkconfig for creating links to the startup scripts; use whatever means is appropriate for this purpose on your operating system and distribution, such as update-rc.d on Debian.

Remember that the preceding steps must be repeated on each machine where an SQL node is to reside.

Management nodes. Installation of the management node does not require the mysqld binary. Only the MySQL Cluster management server (ndb_mgmd) is required; you most likely want to install the management client (ndb_mgm) as well. Both of these binaries also be found in the .tar.gz archive. Again, we assume that you have placed this archive in /var/tmp.

As system root (that is, after using sudo, su root, or your system's equivalent for temporarily assuming the system administrator account's privileges), perform the following steps to install ndb_mgmd and ndb_mgm on the Cluster management node host:

1. Change location to the /var/tmp directory, and extract the ndb_mgm and ndb_mgmd from the archive into a suitable directory such as /usr/local/bin:

```
shell> cd /var/tmp
shell> tar -zxvf mysql-5.1.56-ndb-7.1.16-linux-i686-glibc23.tar.gz
shell> cd mysql-5.1.56-ndb-7.1.16-linux-i686-glibc23
shell> cp bin/ndb_mgm* /usr/local/bin
```

(You can safely delete the directory created by unpacking the downloaded archive, and the files it contains, from /var/tmp once ndb_mgm and ndb_mgmd have been copied to the executables directory.)

2. Change location to the directory into which you copied the files, and then make both of them executable:

```
shell> cd /usr/local/bin shell> chmod +x ndb_mgm*
```

In Section 2.3, "Initial Configuration of MySQL Cluster", we create configuration files for all of the nodes in our example MySQL Cluster.

2.1.2. Installing MySQL Cluster from RPM

This section covers the steps necessary to install the correct executables for each type of MySQL Cluster node using RPM packages supplied by Oracle.

RPMs are available for both 32-bit and 64-bit Linux platforms. For a MySQL Cluster, three RPMs are required:

• The Server RPM (for example, MySQL-Cluster-gpl-server-6.3.45-0.sles10.i586.rpm, MySQL-Cluster-gpl-server-7.0.27-0.sles10.i586.rpm, or MySQL-Cluster-gpl-server-7.1.16-0.sles10.i586.rpm), which supplies the core files needed to run a MySQL Server with NDBCLUSTER storage engine support (that is, as a MySQL Cluster SQL node).

```
If you do not have your own client application capable of administering a MySQL server, you should also obtain and install the Client RPM (for example, MySQL-Cluster-gpl-client-6.3.45-0.sles10.i586.rpm, MySQL-Cluster-gpl-client-7.0.27-0.sles10.i586.rpm, or MySQL-Cluster-gpl-client-7.1.16-0.sles10.i586.rpm).
```

- The Cluster storage engine RPM (for example, MySQL-Cluster-gpl-storage-6.3.45-0.sles10.i586.rpm, MySQL-Cluster-gpl-storage-7.0.27-0.sles10.i586.rpm, or MySQL-Cluster-gpl-storage-7.1.16-0.sles10.i586.rpm), which supplies the MySQL Cluster data node binary (ndbd).
- The Cluster storage engine management RPM (for example, MySQL-Cluster-gpl-management-6.3.45-0.sles10.i586.rpm, MySQL-Cluster-gpl-management-7.0.27-0.sles10.i586.rpm, or MySQL-Cluster-gpl-management-7.1.16-0.sles10.i586.rpm) which provides the MySQL Cluster management server binary (ndb_mgmd).

In addition, you should also obtain the NDB Cluster - Storage engine basic tools RPM (for example, MySQL-

```
Cluster-gpl-tools-6.3.45-0.sles10.i586.rpm, MySQL-
```

Cluster-gpl-tools-7.0.27-0.sles10.i586.rpm, or MySQL-

Cluster-gpl-tools-7.1.16-0.sles10.i586.rpm), which supplies several useful applications for working with a MySQL Cluster. The most important of these is the MySQL Cluster management client (ndb_mgm). The NDB Cluster - Storage engine extra tools RPM (for example, MySQL-Cluster-gpl-extra-6.3.45-0.sles10.i586.rpm, MySQL-

Cluster-gpl-extra-7.0.27-0.sles10.i586.rpm, or MySQL-

Cluster-gpl-extra-7.1.16-0.sles10.i586.rpm) contains some additional testing and monitoring programs, but is not required to install a MySQL Cluster. (For more information about these additional programs, see Chapter 4, MySQL Cluster Programs.)

The MySQL Cluster version number in the RPM file names (shown here as 6.3.45, 7.0.27, or 7.1.16) can vary according to the version which you are actually using. It is very important that all of the Cluster RPMs to be installed have the same version number. The glibc version number (if present), and architecture designation (shown here as i586) should be appropriate to the machine on which the RPM is to be installed.

Data nodes. On a computer that is to host a cluster data node it is necessary to install only the **NDB Cluster - Storage engine** RPM. To do so, copy this RPM to the data node host, and run the following command as the system root user, replacing the name shown for the RPM as necessary to match that of the RPM downloaded from the MySQL web site:

```
shell> rpm -Uhv MySQL-Cluster-gpl-storage-7.1.16-0.sles10.i586.rpm
```

The previous command installs the MySQL Cluster data node binary (ndbd) in the /usr/sbin directory.

SQL nodes. On each machine to be used for hosting a cluster SQL node, install the **Server** RPM by executing the following command as the system root user, replacing the name shown for the RPM as necessary to match the name of the RPM downloaded from the MySQL web site:

```
shell> rpm -Uhv MySQL-Cluster-gpl-server-7.1.16-0.sles10.i586.rpm
```

This installs the MySQL server binary (mysqld) in the /usr/sbin directory, as well as all needed MySQL Server support files. It also installs the mysql.server and mysqld_safe startup scripts in /usr/share/mysql and /usr/bin, respectively. The RPM installer should take care of general configuration issues (such as creating the mysql user and group, if needed) automatically.

Note

To administer the SQL node (MySQL server), you should also install the Client RPM, as shown here:

```
shell> rpm -Uhv MySQL-Cluster-gpl-client-7.1.16-0.sles10.i586.rpm
```

This installs the mysql client program.

Management nodes. To install the MySQL Cluster management server, it is necessary only to use the **NDB Cluster - Storage engine management** RPM. Copy this RPM to the computer intended to host the management node, and then install it by running the following command as the system root user (replace the name shown for the RPM as necessary to match that of the **Storage engine management** RPM downloaded from the MySQL web site):

```
shell> rpm -Uhv MySQL-Cluster-gpl-management-7.1.16-0.sles10.i586.rpm
```

This installs the management server binary (ndb_mgmd) to the /usr/sbin directory.

You should also install the NDB management client, which is supplied by the **Storage engine basic tools** RPM. Copy this RPM to the same computer as the management node, and then install it by running the following command as the system root user (again, replace the name shown for the RPM as necessary to match that of the **Storage engine basic tools** RPM downloaded from the MySQL web site):

```
shell> rpm -Uhv MySQL-Cluster-gpl-tools-7.1.16-0.sles10.i586.rpm
```

The Storage engine basic tools RPM installs the MySQL Cluster management client (ndb_mgm) to the /usr/bin directory.

Note

You can also install the Cluster storage engine extra tools RPM, if you wish, as shown here:

```
shell> rpm -Uhv MySQL-Cluster-gpl-extra-7.1.16-0.sles10.i586.rpm
```

You may find the extra tools useful; however the Cluster storage engine extra tools RPM is not required to install a

working MySQL Cluster.

See Installing MySQL from RPM Packages on Linux, for general information about installing MySQL using RPMs supplied by Oracle.

After installing from RPM, you still need to configure the cluster as discussed in Section 2.3, "Initial Configuration of MySQL Cluster".

2.1.3. Building MySQL Cluster from Source on Linux

This section provides information about compiling MySQL Cluster on Linux and other Unix-like platforms. Building MySQL Cluster from source is similar to building the standard MySQL Server, although it differs in a few key respects discussed here. For general information about building MySQL from source, see Installing MySQL from Source. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported on Windows platforms, and can be built on Windows from source. For information about compiling MySQL Cluster on Windows platforms, see Section 2.2.2, "Compiling and Installing MySQL Cluster from Source on Windows".

Building MySQL Cluster requires using the MySQL Cluster sources. These are available from the MySQL Cluster downloads page at http://dev.mysql.com/downloads/cluster/. The archived source file should have a name similar to mysql-cluster-gpl-6.3.45.tar.gz, mysql-cluster-gpl-7.0.27.tar.gz, or mysql-cluster-gpl-7.1.16.tar.gz. You can also obtain MySQL development sources from launchpad.net. Attempting to build MySQL Cluster from standard MySQL 5.1 sources is not supported.

In addition to any other configure options you wish to use, be sure to include --with-plugins=ndbcluster, --with-plugins=max, or, or --with-plugins=max-no-innodb. Either of these options causes the binaries for the management nodes, data nodes, and other MySQL Cluster programs to be built; it also causes mysqld to be compiled with NDB storage engine support.

After you have run make && make install (or your system's equivalent), the result is similar to what is obtained by unpacking a precompiled binary to the same location. However, the layout can differ. These differences are covered in the next few paragraphs.

Prior to MySQL Cluster NDB 7.1.9, MySQL Cluster was not compatible with the InnoDB Plugin; in earlier MySQL Cluster releases, only the version of InnoDB supplied with the MySQL Server could be used. Beginning with MySQL Cluster NDB 7.1.9, you can build MySQL Cluster with InnoDB storage engine or plugin support using the appropriate --with-plugins option for configure.

Management nodes. When building from source and running the default make install, the management server binary (ndb_mgmd) is placed in /usr/local/mysql/libexec, while the management client binary (ndb_mgm) can be found in / usr/local/mysql/bin. Only ndb_mgmd is required to be present on a management node host; however, it is also a good idea to have ndb_mgm present on the same host machine. Neither of these executables requires a specific location on the host machine's file system.

Data nodes. The only executable required on a data node host is ndbd (mysqld, for example, does not have to be present on the host machine). By default when doing a source build, this file is placed in the directory /usr/local/mysql/libexec. For installing on multiple data node hosts, only ndbd need be copied to the other host machine or machines. (This assumes that all data node hosts use the same architecture and operating system; otherwise you may need to compile separately for each different platform.) ndbd need not be in any particular location on the host's file system, as long as the location is known.

When compiling MySQL Cluster NDB 7.0 or later from source, no special options are required for building multi-threaded data node binaries. On Unix platforms, configuring the build with any of the options --with-plugins=ndbcluster, -with-plugins=max, or --with-plugins=max-no-innodb causes ndbmtd to be built automatically; make install places the ndbmtd binary in the libexec directory along with mysqld, ndbd, and ndb_mgm.

SQL nodes. If you compile MySQL with clustering support, and perform the default installation (using make install as the system root user), mysqld is placed in /usr/local/mysql/bin. Follow the steps given in Installing MySQL from Source to make mysqld ready for use. If you want to run multiple SQL nodes, you can use a copy of the same mysqld executable and its associated support files on several machines. The easiest way to do this is to copy the entire /usr/local/mysql directory and all directories and files contained within it to the other SQL node host or hosts, then repeat the steps from Installing MySQL from Source on each machine. If you configure the build with a nondefault --prefix, you need to adjust the directory accordingly.

In Section 2.3, "Initial Configuration of MySQL Cluster", we create configuration files for all of the nodes in our example MySQL Cluster

2.2. Installing MySQL Cluster on Windows

Experimental support for MySQL Cluster on Microsoft Windows operating systems was introduced in MySQL Cluster NDB 7.0. Beginning with MySQL Cluster NDB 7.1.3, production support is provided for MySQL Cluster on Windows, and MySQL Cluster binaries for Windows can be obtained from http://dev.mysql.com/downloads/cluster/. For information about installing MySQL Cluster on Windows from a binary release provided by Oracle, see Section 2.2.1, "Installing MySQL Cluster on Windows from a

Binary Release".

It is also possible to compile and install MySQL Cluster from source on Windows using Microsoft Visual Studio. For more information, see Section 2.2.2, "Compiling and Installing MySQL Cluster from Source on Windows".

2.2.1. Installing MySQL Cluster on Windows from a Binary Release

This section describes a basic installation of MySQL Cluster on Windows using a binary no-install MySQL Cluster release provided by Oracle, using the same 4-node setup outlined in the beginning of this section (see Chapter 2, MySQL Cluster Installation), as shown in the following table:

Node	IP Address
Management (MGMD) node	192.168.0.10
MySQL server (SQL) node	192.168.0.20
Data (NDBD) node "A"	192.168.0.30
Data (NDBD) node "B"	192.168.0.40

As on other platforms, the MySQL Cluster host computer running an SQL node must have installed on it a MySQL Server binary (mysqld.exe). You should also have the MySQL client (mysql.exe) on on this host. For management nodes and data nodes, it is not necessary to install the MySQL Server binary; however, each management node requires the management server daemon (ndb_mgmd.exe); each data node requires the data node daemon (ndbd.exe or ndbmtd.exe). For this example, we refer to ndbd.exe as the data node executable, but you can install ndbmtd.exe, the multi-threaded version of this program, instead, in exactly the same way. You should also install the management client (ndb_mgm.exe) on the management server host. This section covers the steps necessary to install the correct Windows binaries for each type of MySQL Cluster node.

ndbmtd.exe was not included in MySQL Cluster NDB 7.1.3 binary releases for Windows, due to a problem with make_win_bin_dist. This issue was corrected in MySQL Cluster NDB 7.1.5.

Note

As with other Windows programs, MySQL Cluster executables are named with the .exe file extension. However, it is not necessary to include the .exe extension when invoking these programs from the command line. Therefore, we often simply refer to these programs in this documentation as mysqld, mysql, ndb_mgmd, and so on. You should understand that, whether we refer (for example) to mysqld or mysqld.exe, either name means the same thing (the MySQL Server program).

For setting up a MySQL Cluster using Oracles's no-install binaries, the first step in the installation process is to download the latest MySQL Cluster Windows binary archive from http://dev.mysql.com/downloads/cluster/. This archive has a filename of the form mysql-cluster-gpl-noinstall-ver-winarch.zip, where ver is the NDB storage engine version (such as 7.1.3), and arch is the architecture (32 for 32-bit binaries, and 64 for 64-bit binaries). For example, the MySQL Cluster NDB 7.1.3 no-install archive for 32-bit Windows systems is named mysql-cluster-gpl-noinstall-7.1.3-win32.zip.

You can run 32-bit MySQL Cluster binaries on both 32-bit and 64-bit versions of Windows; however, 64-bit MySQL Cluster binaries can be used only on 64-bit versions of Windows. If you are using a 32-bit version of Windows on a computer that has a 64-bit CPU, then you must use the 32-bit MySQL Cluster binaries.

To minimize the number of files that need to be downloaded from the Internet or copied between machines, we start with the computer where you intend to run the SQL node.

SQL node. We assume that you have placed a copy of the no-install archive in the directory C:\Documents and Settings\username\My Documents\Downloads on the computer having the IP address 192.168.0.20, where username is the name of the current user. (You can obtain this name using ECHO %USERNAME% on the command line.) To install and run MySQL Cluster executables as Windows services, this user should be a member of the Administrators group.

Extract all the files from the archive. The Extraction Wizard integrated with Windows Explorer is adequate for this task. (If you use a different archive program, be sure that it extracts all files and directories from the archive, and that it preserves the archive's directory structure.) When you are asked for a destination directory, enter C:\, which causes the Extraction Wizard to extract the archive to the directory C:\mysgl-cluster-gpl-noinstall-ver-winarch. Rename this directory to C:\mysgl.

It is possible to install the MySQL Cluster binaries to directories other than C:\mysql\bin; however, if you do so, you must modify the paths shown in this procedure accordingly. In particular, if the MySQL Server (SQL node) binary is installed to a location other than C:\mysql or C:\Program Files\MySQL\MySQL Server 5.1, or if the SQL node's data directory is in a location other than C:\mysql\data or C:\Program Files\MySQL\MySQL Server 5.1\data, extra configuration options must be used on the command line or added to the my.ini or my.cnf file when starting the SQL node. For more information about configuring a MySQL Server to run in a nonstandard location, see Installing MySQL on Microsoft Windows Using a noinstall Zip Archive.

For a MySQL Server with MySQL Cluster support to run as part of a MySQL Cluster, it must be started with the options - -ndbcluster and --ndb-connectstring. While you can specify these options on the command line, it is usually more convenient to place them in an option file. To do this, create a new text file in Notepad or another text editor. Enter the following configuration information into this file:

You can add other options used by this MySQL Server if desired (see Creating an Option File), but the file must contain the options shown, at a minimum. Save this file as C:\mysql\my.ini. This completes the installation and setup for the SQL node.

Data nodes. A MySQL Cluster data node on a Windows host requires only a single executable, one of either ndbd.exe or ndb-mtd.exe. For this example, we assume that you are using ndbd.exe, but the same instructions apply when using ndbmtd.exe. On each computer where you wish to run a data node (the computers having the IP addresses 192.168.0.30 and 192.168.0.40), create the directories C:\mysql\bin, and C:\mysql\bin, and C:\mysql\cluster-data; then, on the computer where you downloaded and extracted the no-install archive, locate ndbd.exe in the C:\mysql\bin directory. Copy this file to the C:\mysql\bin directory on each of the two data node hosts.

To function as part of a MySQL Cluster, each data node must be given the address or hostname of the management server. You can supply this information on the command line using the --ndb-connectstring or -c option when starting each data node process. However, it is usually preferable to put this information in an option file. To do this, create a new text file in Notepad or another text editor and enter the following text:

```
[mysql_cluster]
# Options for data node process:
ndb-connectstring=192.168.0.10 # location of management server
```

Save this file as C:\mysql\my.ini on the data node host. Create another text file containing the same information and save it on as C:mysql\my.ini on the other data node host, or copy the my.ini file from the first data node host to the second one, making sure to place the copy in the second data node's C:\mysql directory. Both data node hosts are now ready to be used in the MySQL Cluster, which leaves only the management node to be installed and configured.

Management node. The only executable program required on a computer used for hosting a MySQL Cluster management node is the management server program ndb_mgmd.exe. However, in order to administer the MySQL Cluster once it has been started, you should also install the MySQL Cluster management client program ndb_mgm.exe on the same machine as the management server. Locate these two programs on the machine where you downloaded and extracted the no-install archive; this should be the directory C:\mysql\bin on the SQL node host. Create the directory C:\mysql\bin on the computer having the IP address 192.168.0.10, then copy both programs to this directory.

You should now create two configuration files for use by ndb_mgmd.exe:

1. A local configuration file to supply configuration data spcific to the management node itself. Typically, this file needs only to supply the location of the MySQL Cluster global configuration file (see item 2).

To create this file, start a new text file in Notepad or another text editor, and enter the following information:

```
[mysql_cluster]
# Options for management node process
config-file=C:/mysql/bin/config.ini
```

Save this file as the plaintext file C:\mysql\bin\my.ini.

- 2. A global configuration file from which the management node can obtain configuration information governing the MySQL Cluster as a whole. At a minimum, this file must contain a section for each node in the MySQL Cluster, and the IP addresses or hostnames for the management node and all data nodes (HostName configuration parameter). It is also advisable to include the following additional information:
 - The IP address or hostname of any SQL nodes
 - The data memory and index memory allocated to each data node (DataMemory and IndexMemory configuration parameters)
 - The number of replicas, using the NoOfReplicas configuration parameter (see Section 1.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions")
 - The directory where each data node stores it data and log file, and the directory where the management node keeps its log files (in both cases, the DataDir configuration parameter)

Create a new text file using a text editor such as Notepad, and input the following information:

```
[ndbd default]
  Options affecting ndbd processes on all data nodes:
                                                  Number of replicas
Directory for each data node's data files
NoOfReplicas=2
DataDir=C:/mysql/bin/cluster-data
                                                  Forward slashes used in directory path, rather than backslashes. This is correct;
                                                  see Important note in text
                        # Memory allocated to data storage
# Memory allocated to index storage
DataMemory=80M
IndexMemory=18M
                        # For DataMemory and IndexMemory, we have used the # default values. Since the "world" database takes
                          only about 500KB, this should be more than enough for
                        # this example Cluster setup.
[ndb mqmd]
# Management process options:
HostName=192.168.0.10
                                               # Hostname or IP address of management node
# Directory for management node log files
DataDir=C:/mysql/bin/cluster-logs
# Options for data node "A":
                                          # (one [ndbd] section per data node)
# Hostname or IP address
HostName=192.168.0.30
[ndbd]
# Options for data node "B":
HostName=192.168.0.40
                                          # Hostname or IP address
[mysqld]
  SQL node options:
HostName=192.168.0.20
                                          # Hostname or IP address
```

Save this file as the plaintext file C:\mysql\bin\config.ini.

Important

A single backslash character (\) cannot be used when specifying directory paths in program options or configuration files used by MySQL Cluster on Windows. Instead, you must either escape each backslash character with a second backslash (\\), or replace the backslash with a forward slash character (/). For example, the following line from the [ndb_mgmd] section of a MySQL Cluster config.ini file does not work:

```
DataDir=C:\mysql\bin\cluster-logs

Instead, you may use either of the following:

DataDir=C:\mysql\bin\cluster-logs  # Escaped backslashes

DataDir=C:/mysql/bin/cluster-logs  # Forward slashes
```

For reasons of brevity and legibility, we recommend that you use forward slashes in directory paths used in MySQL Cluster program options and configuration files on Windows.

2.2.2. Compiling and Installing MySQL Cluster from Source on Windows

Oracle provides precompiled MySQL Cluster binaries for Windows which should be adequate for most users. However, if you wish, it is also possible to compile MySQL Cluster for Windows from source code. The procedure for doing this is almost identical to the procedure used to compile the standard MySQL Server binaries for Windows, and uses the same tools. However, there are two major differences:

 To build MySQL Cluster, you must use the MySQL Cluster sources, which you can obtain from http://dev.mysql.com/downloads/cluster/.

Attempting to build MySQL Cluster from the source code for the standard MySQL Server is likely not to be successful, and is not supported by Oracle.

You must configure the build using the WITH_NDBCLUSTER_STORAGE_ENGINE option in addition to any other build options you wish to use before creating the Visual Studio project files. Once you have run configure.js with the desired options, you can create the project files and build from them in the same manner as you do when compiling the standard MySQL Server. For more information, see Installing MySQL from Source on Windows.

Prior to MySQL Cluster NDB 7.1.9, MySQL Cluster was not compatible with the InnoDB Plugin; in earlier MySQL Cluster releases, only the version of InnoDB supplied with the MySQL Server could be used. Beginning with MySQL Cluster NDB 7.1.9, you can build MySQL Cluster with InnoDB storage engine or plugin support on Windows using

```
WITH_INNOBASE_STORAGE_ENGINE with configure.js-
```

Once the build process is complete, you can create a Zip archive containing the compiled binaries by running make_win_bin_dist. The MySQL Cluster binaries can be found in the bin directory of the resulting archive, which is equivalent to the no-install archive, and which can be installed and configured in the same manner. For basic information about how to accomplish these tasks, see Section 2.2.1, "Installing MySQL Cluster on Windows from a Binary Release".

On Windows, beginning with MySQL Cluster NDB 7.0.11, using WITH_NDBCLUSTER_STORAGE_ENGINE with configure.js causes ndbmtd.exe to be built automatically, and to be found in the bin directory of the archive created by make_win_bin_dist. (It was not possible to build ndbmtd.exe on Windows prior to MySQL Cluster NDB 7.0.11.)

2.2.3. Initial Startup of MySQL Cluster on Windows

Once the MySQL Cluster executables and needed configuration files are in place, performing an initial start of the cluster is simply a matter of starting the MySQL Cluster executables for all nodes in the cluster. Each cluster node process must be started separately, and on the host computer where it resides. The management node should be started first, followed by the data nodes, and then finally by any SQL nodes.

1. On the management node host, issue the following command from the command line to start the management node process:

```
C:\mysql\bin> ndb_mgmd
2010-06-23 07:53:34 [MgmtSrvr] INFO -- NDB Cluster Management Server. mysql-5.1.56-ndb-7.1.16
2010-06-23 07:53:34 [MgmtSrvr] INFO -- Reading cluster configuration from 'config.ini'
```

The management node process continues to print logging output to the console. This is normal, because the management node is not running as a Windows service. (If you have used MySQL Cluster on a Unix-like platform such as Linux, you may notice that the management node's default behavior in this regard on Windows is effectively the opposite of its behavior on Unix systems, where it runs by default as a Unix daemon process. This behavior is also true of MySQL Cluster data node processes running on Windows.) For this reason, do not close the window in which ndb_mgmd.exe is running; doing so kills the management node process. (See Section 2.2.4, "Installing MySQL Cluster Processes as Windows Services", where we show how to install and run MySQL Cluster processes as Windows services.)

The required -f option tells the management node where to find the global configuration file (config.ini). The long form of this option is --config-file.

Important

A MySQL Cluster management node caches the configuration data that it reads from config.ini; once it has created a configuration cache, it ignores the config.ini file on subsequent starts unless forced to do otherwise. This means that, if the management node fails to start due to an error in this file, you must make the management node reread config.ini after you have corrected any errors in it. You can do this by starting ndb_mgmd.exe with the -reload or --initial option on the command line. Either of these options works to refresh the configuration cache.

It is not necessary or advisable to use either of these options in the management node's my.ini file.

For additional information about options which can be used with ndb_mgmd, see Section 4.4, "ndb_mgmd — The MySQL Cluster Management Server Daemon", as well as Section 4.23, "Options Common to MySQL Cluster Programs".

2. On each of the data node hosts, run the command shown here to start the data node processes:

```
C:\mysql\bin> ndbd
2010-06-23 07:53:46 [ndbd] INFO -- Configuration fetched from 'localhost:1186', generation: 1
```

In each case, the first line of output from the data node process should resemble what is shown in the preceding example, and is followed by additional lines of logging output. As with the management node process, this is normal, because the data node is not running as a Windows service. For this reason, do not close the console window in which the data node process is running; doing so kills ndbd.exe. (For more information, see Section 2.2.4, "Installing MySQL Cluster Processes as Windows Services".)

3. Do not start the SQL node yet; it cannot connect to the cluster until the data nodes have finished starting, which may take some time. Instead, in a new console window on the management node host, start the MySQL Cluster management client ndb_mgm.exe, which should be in C:\mysql\bin on the management node host. (Do not try to re-use the console window where ndb_mgmd.exe is running by typing CTRL+C, as this kills the management node.) The resulting output should look like this:

```
C:\mysql\bin> ndb_mgm
-- NDB Cluster -- Management Client --
ndb_mgm>
```

When the prompt ndb_mgm> appears, this indicates that the management client is ready to receive MySQL Cluster management commands. You can observe the status of the data nodes as they start by entering ALL STATUS at the management client prompt. This command causes a running report of the data nodes's startup sequence, which should look something like this:

```
ndb_mgm> ALL STATUS

Connected to Management Server at: localhost:1186

Node 2: starting (Last completed phase 3) (mysql-5.1.56-ndb-7.1.16)

Node 3: starting (Last completed phase 3) (mysql-5.1.56-ndb-7.1.16)

Node 2: starting (Last completed phase 4) (mysql-5.1.56-ndb-7.1.16)

Node 3: starting (Last completed phase 4) (mysql-5.1.56-ndb-7.1.16)

Node 2: Started (version 7.1.16)

Node 3: Started (version 7.1.16)

ndb_mgm>
```

Note

Commands issued in the management client are not case-sensitive; we use uppercase as the canonical form of these commands, but you are not required to observe this convention when inputting them into the ndb_mgm client. For more information, see Section 5.2, "Commands in the MySQL Cluster Management Client".

The output produced by ALL STATUS is likely to vary from what is shown here, according to the speed at which the data nodes are able to start, the release version number of the MySQL Cluster software you are using, and other factors. What is significant is that, when you see that both data nodes have started, you are ready to start the SQL node.

You can leave ndb_mgm.exe running; it has no negative impact on the performance of the MySQL Cluster, and we use it in the next step to verify that the SQL node is connected to the cluster after you have started it.

4. On the computer designated as the SQL node host, open a console window and navigate to the directory where you unpacked the MySQL Cluster binaries (if you are following our example, this is C:\mysql\bin).

Start the SQL node by invoking mysqld.exe from the command line, as shown here:

```
C:\mysql\bin> mysqld --console
```

The --console option causes logging information to be written to the console, which can be helpful in the event of problems. (Once you are satisfied that the SQL node is running in a satisfactory manner, you can stop it and restart it out without the --console option, so that logging is performed normally.)

In the console window where the management client (ndb_mgm.exe) is running on the management node host, enter the SHOW command, which should produce output similar to what is shown here:

You can also verify that the SQL node is connected to the MySQL Cluster in the mysql client (mysql.exe) using the SHOW ENGINE NDB STATUS statement.

You should now be ready to work with database objects and data using MySQL Cluster's NDBCLUSTER storage engine. See Section 2.5, "MySQL Cluster Example with Tables and Data", for more information and examples.

Beginning with MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, you can install ndb_mgmd.exe, ndbd.exe, and ndbmtd.exe as Windows services. For information on how to do this, see Section 2.2.4, "Installing MySQL Cluster Processes as Windows Services").

2.2.4. Installing MySQL Cluster Processes as Windows Services

Once you are satisfied that MySQL Cluster is running as desired, you can—beginning with MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5—install the management nodes and data nodes as Windows services, so that these processes are started and stopped automatically whenever Windows is started or stopped. This also makes it possible to control these processes from the command line with the appropriate NET START or NET STOP command, or using the Windows graphical Services utility.

Installing programs as Windows services usually must be done using an account that has Administrator rights on the system.

To install the management node as a service on Windows, invoke ndb_mgmd.exe from the command line on the machine hosting the management node, using the --install option, as shown here:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --install
Installing service 'MySQL Cluster Management Server' as '"C:\mysql\bin\ndbd.exe" "--service=ndb_mgmd"'
Service successfully installed.
```

Important

When installing a MySQL Cluster program as a Windows service, you should always specify the complete path; otherwise the service installation may fail with the error The System Cannot find the file specified.

The --install option must be used first, ahead of any other options that might be specified for ndb_mgmd.exe. However, it is preferable to specify such options in an options file instead. If your options file is not in one of the default locations as shown in the output of ndb_mgmd.exe --help, you can specify the location using the --config-file option.

Now you should be able to start and stop the management server like this:

```
C:\> NET START ndb_mgmd
The MySQL Cluster Management Server service is starting.
The MySQL Cluster Management Server service was started successfully.
C:\> NET STOP ndb_mgmd
The MySQL Cluster Management Server service is stopping.
The MySQL Cluster Management Server service was stopped successfully.
```

You can also start or stop the management server as a Windows service using the descriptive name, as shown here:

```
C:\> NET START 'MySQL Cluster Management Server'
The MySQL Cluster Management Server service is starting.
The MySQL cluster Management Server service was started successfully.
C:\> NET STOP 'MySQL Cluster Management Server'
The MySQL Cluster Management Server service is stopping..
The MySQL Cluster Management Server service was stopped successfully.
```

However, it is usually simpler to specify a short service name or to permit the default service name to be used when installing the service, and then reference that name when starting or stopping the service. To specify a service name other than ndb_mgmd, append it to the --install option, as shown in this example:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --install=mgmd1
Installing service 'MySQL Cluster Management Server' as '"C:\mysql\bin\ndb_mgmd.exe" "--service=mgmd1"'
Service successfully installed.
```

Now you should be able to start or stop the service using the name you have specified, like this:

```
C:\> NET START mgmd1
The MySQL Cluster Management Server service is starting.
The MySQL cluster Management Server service was started successfully.
C:\> NET STOP mgmd1
The MySQL Cluster Management Server service is stopping..
The MySQL Cluster Management Server service was stopped successfully.
```

To remove the management node service, invoke ndb_mgmd.exe with the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --remove
Removing service 'MySQL Cluster Management Server'
Service successfully removed.
```

If you installed the service using a service name other than the default, you can remove the service by passing this name as the value of the --remove option, like this:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --remove=mgmd1
Removing service 'mgmd1'
Service successfully removed.
```

Installation of a MySQL Cluster data node processs as a Windows service can be done in a similar fashion, using the --install option for ndbd.exe (or ndbmtd.exe), as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --install
Installing service 'MySQL Cluster Data Node Daemon' as '"C:\mysql\bin\ndbd.exe" "--service=ndbd"'
Service successfully installed.
```

Now you can start or stop the data node using either the default service name or the descriptive name with net start or net stop, as shown in the following example:

```
C:\> NET START ndbd

The MySQL Cluster Data Node Daemon service is starting.

The MySQL Cluster Data Node Daemon service was started successfully.

C:\> NET STOP ndbd

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service was stopped successfully.

C:\> NET START 'MySQL Cluster Data Node Daemon'

The MySQL Cluster Data Node Daemon service is starting.

The MySQL Cluster Data Node Daemon service was started successfully.

C:\> NET STOP 'MySQL Cluster Data Node Daemon service was started successfully.

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service was stopped successfully.
```

To remove the data node service, invoke ndbd. exe with the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --remove
Removing service 'MySQL Cluster Data Node Daemon'
Service successfully removed.
```

As with ndb_mgmd.exe (and mysqld.exe), when installing ndbd.exe as a Windows service, you can also specify a name for the service as the value of --install, and then use it when starting or stopping the service, like this:

```
C:\> C:\mysql\bin\ndbd.exe --install=dnode1
Installing service 'dnode1' as '"C:\mysql\bin\ndbd.exe" "--service=dnode1"'
Service successfully installed.
C:\> NET START dnode1
The MySQL Cluster Data Node Daemon service is starting.
The MySQL Cluster Data Node Daemon service was started successfully.
C:\> NET STOP dnode1
The MySQL Cluster Data Node Daemon service is stopping.
The MySQL Cluster Data Node Daemon service is stopping.
The MySQL Cluster Data Node Daemon service was stopped successfully.
```

If you specified a service name when installing the data node service, you can use this name when removing it as well, by passing it as the value of the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --remove=dnode1
Removing service 'dnode1'
Service successfully removed.
```

Installation of the SQL node as a Windows service, starting the service, stopping the service, and removing the service are done in a similar fashion, using mysqld --install, NET START, NET STOP, and mysqld --remove. For additional information, see Starting MySQL Server as a Microsoft Windows Service.

2.3. Initial Configuration of MySQL Cluster

For our four-node, four-host MySQL Cluster, it is necessary to write four configuration files, one per node host.

Each data node or SQL node requires a my.cnf file that provides two pieces of information: a connectstring that tells the node
where to find the management node, and a line telling the MySQL server on this host (the machine hosting the data node) to enable the NDBCLUSTER storage engine.

For more information on connectstrings, see Section 3.2.3, "The MySQL Cluster Connectstring".

• The management node needs a config.ini file telling it how many replicas to maintain, how much memory to allocate for data and indexes on each data node, where to find the data nodes, where to save data to disk on each data node, and where to find any SQL nodes.

Configuring the data nodes and SQL nodes. The my.cnf file needed for the data nodes is fairly simple. The configuration file should be located in the /etc directory and can be edited using any text editor. (Create the file if it does not exist.) For example:

```
shell> vi /etc/my.cnf
```

Note

We show vi being used here to create the file, but any text editor should work just as well.

For each data node and SQL node in our example setup, my.cnf should look like this:

```
ndb-connectstring=192.168.0.10 # location of management server
```

After entering the preceding information, save this file and exit the text editor. Do this for the machines hosting data node "A", data node "B", and the SQL node.

Important

Once you have started a mysqld process with the NDBCLUSTER and ndb-connectstring parameters in the [mysqld] in the my.cnf file as shown previously, you cannot execute any CREATE TABLE or ALTER TABLE statements without having actually started the cluster. Otherwise, these statements will fail with an error. This is by design.

Configuring the management node. The first step in configuring the management node is to create the directory in which the configuration file can be found and then to create the file itself. For example (running as root):

```
shell> mkdir /var/lib/mysql-cluster
shell> cd /var/lib/mysql-cluster
shell> vi config.ini
```

For our representative setup, the config.ini file should read as follows:

```
[ndbd default]
   Options affecting ndbd processes on all data nodes:
NoOfReplicas=2
                                    Number of replicas
                                 # How much memory to allocate for data storage
# How much memory to allocate for index storage
# For DataMemory and IndexMemory, we have used the
# default values. Since the "world" database takes up
# only about 500KB, this should be more than enough for
IndexMemory=18M
                                  # this example Cluster setup.
[tcp default]
# TCP/IP options:
portnumber=2202
                                 # This the default; however, you can use any
# port that is free for all the hosts in the cluster
# Note: It is recommended that you do not specify the port
# number at all and simply allow the default value to be used
                                  # instead
[ndb_mgmd]
# Management process options:
hostname=192.168.0.10
datadir=/var/lib/mysql-cluster
                                                          # Hostname or IP address of MGM node
# Directory for MGM node log files
# Options for data node "A":
                                                           # (one [ndbd] section per data node)
hostname=192.168.0.30
datadir=/usr/local/mysql/data
                                                           # Hostname or IP address
                                                           # Directory for this data node's data files
[ndbd]
# Options for data node "B":
hostname=192.168.0.40
datadir=/usr/local/mysql/data
                                                           # Hostname or IP address
# Directory for this data node's data files
[mysqld]
 # SQL node options:
                                                           # Hostname or IP address
# (additional mysqld connections can be
# specified for this node for various
hostname=192.168.0.20
                                                           # purposes such as running ndb_restore
```

Note

The world database can be downloaded from http://dev.mysql.com/doc/, where it can be found listed under "Examples".

After all the configuration files have been created and these minimal options have been specified, you are ready to proceed with starting the cluster and verifying that all processes are running. We discuss how this is done in Section 2.4, "Initial Startup of MySQL Cluster".

For more detailed information about the available MySQL Cluster configuration parameters and their uses, see Section 3.2, "MySQL Cluster Configuration Files", and Chapter 3, MySQL Cluster Configuration. For configuration of MySQL Cluster as relates to making backups, see Section 5.3.3, "Configuration for MySQL Cluster Backups".

Note

The default port for Cluster management nodes is 1186; the default port for data nodes is 2202. However, the cluster can automatically allocate ports for data nodes from those that are already free.

2.4. Initial Startup of MySQL Cluster

Starting the cluster is not very difficult after it has been configured. Each cluster node process must be started separately, and on

the host where it resides. The management node should be started first, followed by the data nodes, and then finally by any SQL nodes:

1. On the management host, issue the following command from the system shell to start the management node process:

```
shell> ndb_mgmd -f /var/lib/mysql-cluster/config.ini
```

ndb_mgmd must be told where to find its configuration file, using the -f or --config-file option. (See Section 4.4, "ndb_mgmd — The MySQL Cluster Management Server Daemon", for details.)

For additional options which can be used with ndb_mgmd, see Section 4.23, "Options Common to MySQL Cluster Programs".

2. On each of the data node hosts, run this command to start the ndbd process:

```
shell> ndbd
```

3. If you used RPM files to install MySQL on the cluster host where the SQL node is to reside, you can (and should) use the supplied startup script to start the MySQL server process on the SQL node.

If all has gone well, and the cluster has been set up correctly, the cluster should now be operational. You can test this by invoking the ndb_mgm management node client. The output should look like that shown here, although you might see some slight differences in the output depending upon the exact version of MySQL that you are using:

The SQL node is referenced here as [mysqld(API)], which reflects the fact that the mysqld process is acting as a MySQL Cluster API node.

Note

The IP address shown for a given MySQL Cluster SQL or other API node in the output of SHOW is the address used by the SQL or API node to connect to the cluster data nodes, and not to any management node.

You should now be ready to work with databases, tables, and data in MySQL Cluster. See Section 2.5, "MySQL Cluster Example with Tables and Data", for a brief discussion.

2.5. MySQL Cluster Example with Tables and Data

Note

The information in this section applies to MySQL Cluster running on both Unix and Windows platforms.

Working with database tables and data in MySQL Cluster is not much different from doing so in standard MySQL. There are two key points to keep in mind:

• For a table to be replicated in the cluster, it must use the NDBCLUSTER storage engine. To specify this, use the ENGINE=NDBCLUSTER or ENGINE=NDB option when creating the table:

```
CREATE TABLE tbl_name (col_name column_definitions) ENGINE=NDBCLUSTER;
```

Alternatively, for an existing table that uses a different storage engine, use ALTER TABLE to change the table to use NDB-CLUSTER:

```
ALTER TABLE tbl_name ENGINE=NDBCLUSTER;
```

 Every NDBCLUSTER table has a primary key. If no primary key is defined by the user when a table is created, the NDB-CLUSTER storage engine automatically generates a hidden one. Such a key takes up space just as does any other table index. (It is not uncommon to encounter problems due to insufficient memory for accommodating these automatically created indexes.)

If you are importing tables from an existing database using the output of mysqldump, you can open the SQL script in a text editor and add the ENGINE option to any table creation statements, or replace any existing ENGINE options. Suppose that you have the world sample database on another MySQL server that does not support MySQL Cluster, and you want to export the City table:

```
shell> mysqldump --add-drop-table world City > city_table.sql
```

The resulting city_table.sql file will contain this table creation statement (and the INSERT statements necessary to import the table data):

You need to make sure that MySQL uses the NDBCLUSTER storage engine for this table. There are two ways that this can be accomplished. One of these is to modify the table definition *before* importing it into the Cluster database. Using the City table as an example, modify the ENGINE option of the definition as follows:

```
DROP TABLE IF EXISTS `City`;

CREATE TABLE `City` (
   `ID` int(11) NOT NULL auto_increment,
   `Name` char(35) NOT NULL default '',
   `CountryCode` char(3) NOT NULL default '',
   `District` char(20) NOT NULL default '',
   `Population` int(11) NOT NULL default '0',
   PRIMARY KEY (`ID`)
) ENGINE=NDBCLUSTER DEFAULT CHARSET=latin1;
INSERT INTO `City` VALUES (1,'Kabul','AFG','Kabol',1780000);
INSERT INTO `City` VALUES (2,'Qandahar','AFG','Qandahar',237500);
INSERT INTO `City` VALUES (3,'Herat','AFG','Herat',186800);
(remaining INSERT statements omitted)
```

This must be done for the definition of each table that is to be part of the clustered database. The easiest way to accomplish this is to do a search-and-replace on the file that contains the definitions and replace all instances of TYPE=engine_name or ENGINE=engine_name with ENGINE=NDBCLUSTER. If you do not want to modify the file, you can use the unmodified file to create the tables, and then use ALTER TABLE to change their storage engine. The particulars are given later in this section.

Assuming that you have already created a database named world on the SQL node of the cluster, you can then use the mysql command-line client to read city_table.sql, and create and populate the corresponding table in the usual manner:

```
shell> mysql world < city_table.sql
```

It is very important to keep in mind that the preceding command must be executed on the host where the SQL node is running (in this case, on the machine with the IP address 192.168.0.20).

To create a copy of the entire world database on the SQL node, use mysqldump on the noncluster server to export the database to a file named world.sql; for example, in the /tmp directory. Then modify the table definitions as just described and import the file into the SQL node of the cluster like this:

```
shell> mysql world < /tmp/world.sql
```

If you save the file to a different location, adjust the preceding instructions accordingly.

Running SELECT queries on the SQL node is no different from running them on any other instance of a MySQL server. To run queries from the command line, you first need to log in to the MySQL Monitor in the usual way (specify the root password at the Enter password: prompt):

```
shell> mysql -u root -p
Enter password:
Welcome to the MySQL monitor. Commands end with ; or \g.
Your MySQL connection id is 1 to server version: 5.1.56-ndb-7.1.16
Type 'help;' or '\h' for help. Type '\c' to clear the buffer.
mysql>
```

We simply use the MySQL server's root account and assume that you have followed the standard security precautions for installing a MySQL server, including setting a strong root password. For more information, see Securing the Initial MySQL Accounts

It is worth taking into account that Cluster nodes do *not* make use of the MySQL privilege system when accessing one another. Setting or changing MySQL user accounts (including the root account) effects only applications that access the SQL node, not interaction between nodes. See Section 5.10.2, "MySQL Cluster and MySQL Privileges", for more information.

If you did not modify the ENGINE clauses in the table definitions prior to importing the SQL script, you should run the following statements at this point:

```
mysql> USE world;
mysql> ALTER TABLE City ENGINE=NDBCLUSTER;
mysql> ALTER TABLE Country ENGINE=NDBCLUSTER;
mysql> ALTER TABLE CountryLanguage ENGINE=NDBCLUSTER;
```

Selecting a database and running a SELECT query against a table in that database is also accomplished in the usual manner, as is exiting the MySQL Monitor:

Applications that use MySQL can employ standard APIs to access NDB tables. It is important to remember that your application must access the SQL node, and not the management or data nodes. This brief example shows how we might execute the SELECT statement just shown by using the PHP 5.X mysqli extension running on a Web server elsewhere on the network:

```
<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.01 Transitional//EN"
   "http://www.w3.org/TR/html4/loose.dtd">
<html>
<head>
  <title>SIMPLE mysqli SELECT</title>
</head>
<body>
# connect to SQL node:
    $link = new mysqli('192.168.0.20', 'root', 'root_password', 'world');
# parameters for mysqli odstrabose
# boot was reserved adstabase
  # parameters for mysql1 constructor are:
# host, user, password, database
if( mysql1_connect_errno() )
   die("Connect failed: " . mysql1_connect_error());
$query = "SELECT Name, Population
              FROM City
ORDER BY Population DESC
              LIMIT 5";
    if no errors.
  if( $result = $link->query($query) )
City
     Population
  <?
     # then display the results..
     while($row = $result->fetch_object())
printf("\n %s%d\n\n",
                $row->Name, $row->Population);
  </tbody
# ...and verify the number of rows that were retrieved
printf("Affected rows: %d\n", $link->affected_rows);
     # otherwise, tell us what went wrong
     echo mysqli_error();
  # free the result set and the mysqli connection object
$result->close();
```

```
$link->close();
?>
</body>
</html>
```

We assume that the process running on the Web server can reach the IP address of the SQL node.

In a similar fashion, you can use the MySQL C API, Perl-DBI, Python-mysql, or MySQL Connectors to perform the tasks of data definition and manipulation just as you would normally with MySQL.

2.6. Safe Shutdown and Restart of MySQL Cluster

To shut down the cluster, enter the following command in a shell on the machine hosting the management node:

```
shell> ndb_mgm -e shutdown
```

The -e option here is used to pass a command to the ndb_mgm client from the shell. (See Section 4.23, "Options Common to MySQL Cluster Programs", for more information about this option.) The command causes the ndb_mgm, ndb_mgmd, and any ndbd or ndbmtd processes to terminate gracefully. Any SQL nodes can be terminated using mysqladmin shutdown and other means. On Windows platforms, assuming that you have installed the SQL node as a Windows service, you can use NET STOP MYSQL.

To restart the cluster on Unix platforms, run these commands:

• On the management host (192.168.0.10 in our example setup):

```
shell> ndb_mgmd -f /var/lib/mysql-cluster/config.ini
```

• On each of the data node hosts (192.168.0.30 and 192.168.0.40):

```
shell> ndbd
```

- Use the ndb_mgm client to verify that both data nodes have started successfully.
- On the SQL host (192.168.0.20):

```
shell> mysqld_safe &
```

On Windows platforms, assuming that you have installed all MySQL Cluster processes as Windows services using the default service names (see Section 2.2.4, "Installing MySQL Cluster Processes as Windows Services"), you can restart the cluster as follows:

On the management host (192.168.0.10 in our example setup), execute the following command:

```
C:\> NET START ndb_mgmd
```

• On each of the data node hosts (192.168.0.30 and 192.168.0.40), execute the following command:

```
C:\> NET START ndbd
```

- On the management node host, use the ndb_mgm client to verify that the management node and both data nodes have started successfully (see Section 2.2.3, "Initial Startup of MySQL Cluster on Windows").
- On the SQL node host (192.168.0.20), execute the following command:

```
C:\> NET START mysql
```

In a production setting, it is usually not desirable to shut down the cluster completely. In many cases, even when making configuration changes, or performing upgrades to the cluster hardware or software (or both), which require shutting down individual host machines, it is possible to do so without shutting down the cluster as a whole by performing a *rolling restart* of the cluster. For more information about doing this, see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster".

2.7. Upgrading and Downgrading MySQL Cluster

This section provides information about MySQL Cluster software and table file compatibility between MySQL 5.1.23 and earlier,

MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x releases with regard to performing upgrades and downgrades as well as compatibility matrices and notes. You are expected already to be familiar with installing and configuring a MySQL Cluster prior to attempting an upgrade or downgrade. See Chapter 3, MySQL Cluster Configuration.

Important

Only compatibility between MySQL versions with regard to NDBCLUSTER is taken into account in this section, and there are likely other issues to be considered. As with any other MySQL software upgrade or downgrade, you are strongly encouraged to review the relevant portions of the MySQL Manual for the MySQL versions from which and to which you intend to migrate, before attempting an upgrade or downgrade of the MySQL Cluster software. See Upgrading MySQL.

For information about upgrades and downgrades to, from, and between different releases of MySQL Cluster NDB 7.0 and MySQL Cluster NDB 7.1, see Section 2.7.1, "Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x".

For information about upgrades and downgrades to, from, and between different releases of MySQL Cluster NDB 6.1, MySQL Cluster NDB 6.2, and MySQL Cluster NDB 6.3, see Section 2.7.2, "Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x".


For information about upgrades and downgrades to, from, and between different editions of MySQL Cluster as found in standard MySQL 5.1.23 and earlier releases, see Section 2.7.3, "Upgrade and downgrade compatibility: MySQL 5.1".

Important

Only compatibility between MySQL versions with regard to NDBCLUSTER is taken into account in this section, and there are likely other issues to be considered. As with any other MySQL software upgrade or downgrade, you are strongly encouraged to review the relevant portions of the MySQL Manual for the MySQL versions from which and to which you intend to migrate, before attempting an upgrade or downgrade of the MySQL Cluster software. See Upgrading MySQL.

2.7.1. Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL Cluster NDB 7.0 and 7.1. Additional notes about upgrades and downgrades to, from, or within the MySQL Cluster NDB 7.x release series can be found immediately following the table.



Notes: MySQL Cluster NDB 7.x

Versions supported. Online upgrades from any MySQL Cluster NDB 7.0 release up to and including MySQL Cluster NDB 7.0.4 (as well as all early releases numbered NDB 6.4.x) to MySQL Cluster NDB 7.0.5 or later are not possible. Upgrades to MySQL Cluster NDB 7.0.6 or later from MySQL Cluster NDB 6.3.8 or a later MySQL Cluster NDB 6.3 release, or from MySQL Cluster NDB 7.0.5 or later, are supported. (Bug #44294)

Upgrading ndbd to ndbmtd. When upgrading online from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0 release, you should not try to upgrade the data nodes from ndbd to ndbmtd at the same time. Instead, perform the upgrade using the new ndbd executable (from the MySQL Cluster NDB 7.0.x distribution to which you are upgrading) to replace the one in use on the data nodes. Once the version upgrade is complete, you can perform a second (online) upgrade to replace the data node executables with ndbmtd from the MySQL Cluster NDB 7.0.x distribution.

Changes in default values. In MySQL Cluster NDB 7.0.4, the default values for a number of MySQL Cluster configuration parameters relating to memory usage and buffering changed (see Changes in MySQL Cluster NDB 7.0.4 (5.1.32-ndb-7.0.4), for a list of the parameters whose defaults changed). For this reason, you may encounter issues if you try to use a configuration that does not explicitly define each of these buffers (because it was developed for a previous version of MySQL Cluster), SendBuffer-Memory and ReceiveBufferMemory in particular.

Other known issues include the following:

- Prior to MySQL Cluster NDB 7.0.7, DML statements failed if executed while performing an online upgrade from a MySQL Cluster NDB 6.3 release. (Bug #45917)
- Following an upgrade from any MySQL Cluster NDB 6.3.x release to MySQL Cluster NDB 7.0.6, DDL and backup operations failed. This issue was resolved in MySQL Cluster NDB 7.0.7. (Bug #46494, Bug #46563)
- In some cases, there could be problems with online upgrades from MySQL Cluster NDB 6.3 releases to MySQL Cluster NDB 7.0 releases due to a previous change in the signalling format used between nodes. This issue was corrected in MySQL Cluster NDB 7.0.9.
- Once an NDB table had an ALTER ONLINE TABLE operation performed on it using a MySQL Cluster NDB 6.3.x release, it could not be upgraded online to MySQL Cluster NDB 7.0. This issue was resolved in MySQL Cluster NDB 7.0.8. (See Bug #47542.)
- Following an upgrade from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0, if there were any tables having unique indexes prior to the upgrade, attempts to create unique indexes failed. This could also occur when performing offline ALTER TABLE operations on tables having indexes that were not dropped as a result of the ALTER TABLE. This issue was due to a change in the way that NDB tracked unique indexes internally, and was resolved in MySQL Cluster NDB 7.0.9. (Bug #48416)
 - For upgrades to MySQL Cluster NDB 7.0 releases prior to version 7.0.9, a workaround is available: Following the upgrade, execute a *second* rolling restart of the cluster before before performing any ALTER TABLE operations involving indexes.
- Due to an issue discovered after the release of MySQL Cluster NDB 7.0.10 (Bug #50433), it is not possible to perform an online upgrade from MySQL Cluster NDB 7.0.9b and earlier MySQL Cluster NDB 7.0 releases to MySQL Cluster NDB 7.0.10. Instead, you should upgrade your MySQL Cluster NDB 7.0 installation directly to MySQL Cluster NDB 7.0.11 or later.
 - This issue did not appear to affect MySQL Cluster NDB 6.3, and it should be possible to upgrade online from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0.10 without any problems other than those noted previously.
- It was not possible to perform an online upgrade from a MySQL Cluster NDB 6.3 or 7.0 release to MySQL Cluster NDB 7.1.0 or 7.1.1. This issue was fixed in MySQL Cluster NDB 7.1.2 (see Bug #51429).
- Following an upgrade to MySQL Cluster NDB 7.0.15 or later (MySQL Cluster NDB 7.0), or to MySQL Cluster NDB 7.1.4 or later (MySQL Cluster NDB 7.1), a table created in a previous version of MySQL Cluster does *not* automatically support NDB-native default values. Such a table continues to use default values supplied by the MySQL server until it is upgraded by performing an offline ALTER TABLE on it.

When upgrading to a MySQL Cluster release that supports native default values from a MySQL Cluster release that does not, you should not attempt to create any new tables until all data nodes are using the new ndbd or ndbmtd binaries. This is because the older binaries do not provide support for native default values.

Important

Tables created with native default value support cannot be used with versions of MySQL Cluster that do not support native default values.

Due to issues discovered shortly after release, MySQL Cluster NDB 7.0.20 was withdrawn and replaced with MySQL Cluster NDB 7.0.20a. Users of MySQL Cluster NDB 7.0.19 and previous MySQL Cluster NDB 7.0 releases should upgrade to MySQL Cluster NDB 7.0.20a, or to a later MySQL Cluster NDB 7.0 release. See Changes in MySQL Cluster NDB 7.0.20a

(5.1.51-ndb-7.0.20a), for more information.


Due to issues discovered shortly after release, MySQL Cluster NDB 7.1.9 was withdrawn and replaced with MySQL Cluster NDB 7.1.9a. Users of MySQL Cluster NDB 7.1.8 and previous MySQL Cluster NDB 7.1 releases should upgrade to MySQL Cluster NDB 7.1.9a, or to a later MySQL Cluster NDB 7.1 release. See Changes in MySQL Cluster NDB 7.1.9a (5.1.51-ndb-7.1.9a), for more information.

• When performing an online upgrade or downgrade between MySQL Cluster NDB 7.1.8 or earlier and a later release up to and including MySQL Cluster NDB 7.1.14, you must upgrade or downgrade the data nodes before upgrading or downgrading any SQL nodes; otherwise mysql_upgrade fails on the SQL nodes due to differences between ndbinfo tables used in the "old" and "new" versions of the MySQL Cluster software. You should also upgrade or downgrade the data nodes prior to the SQL nodes when performing an online upgrade or downgrade between MySQL Cluster NDB 7.1 releases where either of the versions involved is MySQL Cluster NDB 7.1.14 or earlier, and where one or more ndbinfo tables has more, fewer, or differing columns between the two versions.

This issue is resolved in MySQL Cluster NDB 7.1.15. (Bug #11885602)

2.7.2. Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL Cluster NDB 6.1, 6.2, and 6.3. Additional notes about upgrades and downgrades to, from, or within the MySQL Cluster NDB 6.x release series can be found immediately following the table.



Notes: MySQL Cluster NDB 6.1

Availability of older releases. MySQL Cluster NDB 6.1 is no longer in production; information about this series of releases is of historical interest only. MySQL Cluster NDB 6.2 is still available, but is no longer supported in new deployments. If you are still using a MySQL Cluster NDB 6.1 or MySQL Cluster NDB 6.2 release, you should upgrade to the most recent MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1 release as soon as possible.

- It is not possible to upgrade from MySQL Cluster NDB 6.1.2 (or an older 6.1 release) directly to 6.1.4 or a newer NDB 6.1 release, or to downgrade from 6.1.4 (or a newer 6.1 release) directly to 6.1.2 or an older NDB 6.1 release; in either case, you must upgrade or downgrade to MySQL Cluster NDB 6.1.3 first.
- It is not possible to perform an online downgrade from MySQL Cluster NDB 6.1.8 (or a newer 6.1 release) to MySQL Cluster NDB 6.1.7 (or an older 6.1 release).
- MySQL Cluster NDB 6.1.6 and 6.1.18 were not released.
- It is not possible to perform an online upgrade or downgrade between MySQL Cluster NDB 6.2 and any previous release series
 (including mainline MySQL 5.1 and MySQL Cluster NDB 6.1); it is necessary to perform a dump and reload. However, it
 should be possible to perform online upgrades or downgrades between any MySQL Cluster NDB 6.2 release and any MySQL
 Cluster NDB 6.3 release up to and including 6.3.7.

Notes: MySQL Cluster NDB 6.2 and MySQL Cluster NDB 6.3

Internal column specification changes. The internal specifications for columns in NDB tables changed in MySQL Cluster NDB 6.1.17 and 6.2.1 to enable compatibility with later MySQL Cluster releases implementing online adding and dropping of columns (MySQL 5.1.17 through MySQL 5.1.23; MySQL Cluster NDB 6.2.3 and later; MySQL Cluster NDB 6.3.2 and later). This change is not backward-compatible with earlier MySQL Server or MySQL Cluster releases.

To make tables created in earlier versions compatible with online adding and dropping of columns in later versions, it is necessary to force MySQL Cluster to convert the tables to the new format by following this procedure following an upgrade:

- 1. Upgrade the MySQL Cluster software on all data, management, and SQL nodes
- 2. Back up all NDB tables
- 3. Shut down the cluster (all data, management, and SQL nodes)
- 4. Restart the cluster, starting all data nodes with the --initial option (to clear and rebuild the data node file systems)
- 5. Restore the tables from backup

To minimize possible later difficulties, it is strongly advised that the procedure outlined above be followed as soon as possible after to upgrading between the versions indicated. The procedure is *not* necessary for NDBCLUSTER tables created in any of the following versions:

- MySQL Cluster NDB 6.1.8 or a later MySQL Cluster NDB 6.1 release
- MySQL Cluster 6.2.1 or a later MySQL Cluster NDB 6.2 release
- Any MySQL Cluster NDB 6.3 release (or later MySQL Cluster release series)


Tables created in the versions listed previously (or later versions, as indicated) are already compatible with adding and dropping of columns online (as implemented beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2).

Additional issues encountered when upgrading or downgrading to or from MySQL Cluster NDB 6.2 and MySQL Cluster NDB 6.3 releases are listed here:

- It was not possible to perform an online upgrade between any MySQL Cluster NDB 6.2 release and MySQL Cluster NDB 6.3.8 and later MySQL Cluster 6.3 releases. This issue was fixed in MySQL Cluster NDB 6.3.21. (Bug #41435)
- Online downgrades between MySQL Cluster NDB 6.2.5 and earlier releases are not supported.
- Online downgrades between MySQL Cluster NDB 6.3.8 and earlier releases are not supported.

2.7.3. Upgrade and downgrade compatibility: MySQL 5.1

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL 5.1 prior to MySQL 5.1.24. Additional notes about upgrades and downgrades to, from, or within the MySQL 5.1 release series can be found immediately following the table.



Notes: MySQL 5.1

- MySQL 5.1.3 was the first public release in this series.
- Direct upgrades or downgrades between MySQL Cluster 5.0 and 5.1 are not supported; you must dump all NDBCLUSTER tables using mysqldump, install the new version of the software, and then reload the tables from the dump.
- You cannot downgrade a MySQL Cluster based on MySQL 5.1.6 or later and using Disk Data tables to MySQL 5.1.5 or earlier
 unless you convert all such tables to in-memory NDB tables first.
- MySQL 5.1.8, MySQL 5.1.10, and MySQL 5.1.13 were not released.
- Online cluster upgrades and downgrades between MySQL 5.1.11 (or an earlier version) and 5.1.12 (or a later version) are not possible due to major changes in the cluster file system. In such cases, you must perform a backup or dump, upgrade (or downgrade) the software, start each data node with --initial, and then restore from the backup or dump. You can use native NDB backup and restore, or mysqldump and LOAD DATA INFILE for this purpose.
- Online downgrades from MySQL 5.1.14 or later to versions previous to 5.1.14 are not supported due to incompatible changes in the cluster system tables.

MySQL Cluster Replication: changes in ndb_apply_status. Online upgrades from MySQL 5.1.17 and earlier to 5.1.18 and later MySQL 5.1.x releases are not supported for clusters using replication due to incompatible changes in the mysql.ndb_apply_status table. (Online upgrades from MySQL 5.1 to MySQL Cluster NDB 6.2 and later are not supported, as discussed elsewhere in this section.) However, it should not be necessary to shut down the cluster entirely, if you follow this modified rolling restart procedure:

- 1. Stop the management server, update the management server software, then start the management server again. For multiple management servers, repeat this step for each management server in turn.
- 2. For each data node in turn: Stop the data node, update the data node daemon (in MySQL Cluster NDB 7.0 and later, this can be either ndbd or ndbmtd) with the new version, then restart the data node. It should not be necessary to use --initial when restarting any of the data nodes after updating the software.
- 3. Stop *all* SQL nodes. Upgrade the existing MySQL server installations to the new version on all SQL nodes, then restart them. It is not necessary to start them one at a time after upgrading the MySQL server software, but *there must be a time when none of them is running before starting any of them again using the 5.1.18 (or later) mysqld*. Otherwise—due to the fact that mysql.ndb_apply_status uses the NDB storage engine and is thus shared between all SQL nodes—there may be conflicts between the old and new versions of the table on different SQL nodes.

You can find more information about the changes to ndb_apply_status in Section 6.4, "MySQL Cluster Replication Schema and Tables".

Note

You should upgrade the MySQL Cluster software on each node using the same method by which it was originally installed. See Chapter 2, MySQL Cluster Installation, for more information.

As with any other MySQL Cluster version upgrade, you should also update the MySQL Cluster management client (ndb_mgm) and other MySQL Cluster client programs such as ndb_config and ndb_error_reporter; however, this does not have to be done in any particular order.

Internal column specification changes. The internal specifications for columns in NDBCLUSTER tables changed in MySQL 5.1.18 to enable compatibility with later MySQL Cluster releases that permit online adding and dropping of columns. *This change is not backward-compatible with earlier MySQL versions*.

To make tables created in MySQL 5.1.17 and earlier compatible with online adding and dropping of columns (available beginning with beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2—see ALTER TABLE Syntax, for more information), it is necessary to force MySQL 5.1.18 and later to convert the tables to the new format by following this procedure:

- 1. Back up all NDBCLUSTER tables.
- 2. Upgrade the MySQL Cluster software on all data, management, and SQL nodes.
- 3. Shut down the cluster completely (this includes all data, management, and API or SQL nodes).
- 4. Restart the cluster, starting all data nodes with the --initial option (to clear and rebuild the data node file systems).

5. Restore the NDBCLUSTER tables from backup.

It is not necessary to follow this procedure for NDBCLUSTER tables created in MySQL 5.1.18 and later; such tables are already compatible with online adding and dropping of columns (as implemented beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2).

To minimize possible later difficulties, it is strongly advised that the procedure outlined above be followed as soon as possible after to upgrading from MySQL 5.1.17 or earlier to MySQL 5.1.18 or later.

Information about how this change effects users of MySQL Cluster NDB 6.x and 7.x is provided later in this section.

MySQL Cluster not supported in MySQL Server 5.1.24 and later. MySQL Cluster is not supported in standard MySQL 5.1 releases beginning with MySQL 5.1.24. If you are using MySQL Cluster in a standard MySQL 5.1 release, you should upgrade to the most recent MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1 release.

Chapter 3. MySQL Cluster Configuration

A MySQL server that is part of a MySQL Cluster differs in one chief respect from a normal (nonclustered) MySQL server, in that it employs the NDBCLUSTER storage engine. This engine is also referred to simply as NDB, and the two forms of the name are synonymous.

To avoid unnecessary allocation of resources, the server is configured by default with the NDB storage engine disabled. To enable NDB, you must modify the server's my.cnf configuration file, or start the server with the --ndbcluster option.

For more information about --ndbcluster and other MySQL server options specific to MySQL Cluster, see Section 3.4.2, "mysqld Command Options for MySQL Cluster".

The MySQL server is a part of the cluster, so it also must know how to access an MGM node to obtain the cluster configuration data. The default behavior is to look for the MGM node on localhost. However, should you need to specify that its location is elsewhere, this can be done in my.cnf or on the MySQL server command line. Before the NDB storage engine can be used, at least one MGM node must be operational, as well as any desired data nodes.

NDB, the MySQL Cluster storage engine, is available in binary distributions for Linux, Mac OS X, Solaris. and Windows. We are working to support MySQL Cluster on all operating systems supported by the MySQL Server. For information about installing MySQL Cluster, see Chapter 2, MySQL Cluster Installation.

3.1. Quick Test Setup of MySQL Cluster

To familiarize you with the basics, we will describe the simplest possible configuration for a functional MySQL Cluster. After this, you should be able to design your desired setup from the information provided in the other relevant sections of this chapter.

First, you need to create a configuration directory such as /var/lib/mysql-cluster, by executing the following command as the system root user:

```
shell> mkdir /var/lib/mysql-cluster
```

In this directory, create a file named config.ini that contains the following information. Substitute appropriate values for HostName and DataDir as necessary for your system.

```
# file "config.ini" - showing minimal setup consisting of 1 data node,
# 1 management server, and 3 MySQL servers.
# The empty default sections are not required, and are shown only for
# the sake of completeness.
# Data nodes must provide a hostname but MySQL Servers are not required
# to do so.
# If you don't know the hostname for your machine, use localhost.
# The DataDir parameter also has a default value, but it is recommended to
# set it explicitly.
# Note: [db], [api], and [mgm] are aliases for [ndbd], [mysqld], and [ndb_mgmd],
# respectively. [db] is deprecated and should not be used in new installations.
[ndbd default]
NoOfReplicas= 1
[mysqld default]
[tcp default]
[tcp default]
[tcp default]
[hostName= myhost.example.com
[ndbd]
HostName= myhost.example.com
DataDir= /var/lib/mysql-cluster
[mysqld]
[mysqld]
[mysqld]
[mysqld]
```

You can now start the ndb_mgmd management server. By default, it attempts to read the config.ini file in its current working directory, so change location into the directory where the file is located and then invoke ndb_mgmd:

```
shell> cd /var/lib/mysql-cluster shell> ndb_mgmd
```

Then start a single data node by running ndbd:

```
shell> ndbd
```

For command-line options which can be used when starting ndbd, see Section 4.23, "Options Common to MySQL Cluster Programs".

By default, ndbd looks for the management server at localhost on port 1186.

Note

If you have installed MySQL from a binary tarball, you will need to specify the path of the ndb_mgmd and ndbd servers explicitly. (Normally, these will be found in /usr/local/mysql/bin.)

Finally, change location to the MySQL data directory (usually $\ver/lib/mysql$ or $\ver/local/mysql/data$), and make sure that the my.cnf file contains the option necessary to enable the NDB storage engine:

```
[mysqld]
ndbcluster
```

You can now start the MySQL server as usual:

```
shell> mysqld_safe --user=mysql &
```

Wait a moment to make sure the MySQL server is running properly. If you see the notice mysql ended, check the server's .err file to find out what went wrong.

If all has gone well so far, you now can start using the cluster. Connect to the server and verify that the NDBCLUSTER storage engine is enabled:

The row numbers shown in the preceding example output may be different from those shown on your system, depending upon how your server is configured.

Try to create an NDBCLUSTER table:

To check that your nodes were set up properly, start the management client:

```
shell> ndb_mgm
```

Use the SHOW command from within the management client to obtain a report on the cluster's status:

At this point, you have successfully set up a working MySQL Cluster. You can now store data in the cluster by using any table created with ENGINE=NDBCLUSTER or its alias ENGINE=NDB.

3.2. MySQL Cluster Configuration Files

Configuring MySQL Cluster requires working with two files:

- my.cnf: Specifies options for all MySQL Cluster executables. This file, with which you should be familiar with from previous work with MySQL, must be accessible by each executable running in the cluster.
- config.ini: This file, sometimes known as the *global configuration file*, is read only by the MySQL Cluster management server, which then distributes the information contained therein to all processes participating in the cluster. config.ini contains a description of each node involved in the cluster. This includes configuration parameters for data nodes and configuration parameters for connections between all nodes in the cluster. For a quick reference to the sections that can appear in this file, and what sorts of configuration parameters may be placed in each section, see Sections of the config.ini File.

Caching of configuration data. Beginning with MySQL Cluster NDB 6.4.0, MySQL Cluster uses *stateful configuration*. The global configuration file is no longer read every time the management server is restarted. Instead, the management server caches the configuration the first time it is started, and thereafter, the global configuration file is read only when one of the following items is true:

- The management server is started using the --initial option. In this case, the global configuration file is re-read, any existing cache files are deleted, and the management server creates a new configuration cache.
- The management server is started using the --reload option. In this case, the management server compares its cache with the global configuration file. If they differ, the management server creates a new configuration cache; any existing configuration cache is preserved, but not used. If the management server's cache and the global configuration file contain the same configuration data, then the existing cache is used, and no new cache is created.
- The management server is started using a --config-cache option. Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option can be used to force the management server to bypass configuration caching altogether. In this case, the management server ignores any configuration files that may be present, always reading its configuration data from the config.ini file instead.
- No configuration cache is found. In this case, the management server reads the global configuration file and creates a cache containing the same configuration data as found in the file.

Configuration cache files. Beginning with MySQL Cluster 6.4.0, the management server by default creates configuration cache files in a directory named mysql-cluster in the MySQL installation directory. (If you build MySQL Cluster from source on a Unix system, the default location is /usr/local/mysql-cluster.) This can be overridden at run time by starting the management server with the --configdir option. Configuration cache files are binary files named according to the pattern ndb_node_id_config.bin.seq_id, where node_id is the management server's node ID in the cluster, and seq_id is a cache identifier. Cache files are numbered sequentially using seq_id, in the order in which they are created. The management server uses the latest cache file as determined by the seq_id.

Note

It is possible to roll back to a previous configuration by deleting later configuration cache files, or by renaming an earlier cache file so that it has a higher seq_id . However, since configuration cache files are written in a binary format, you should not attempt to edit their contents by hand.

For more information about the --configdir, --initial, and --reload options for the MySQL Cluster management server, see Section 4.4, "ndb_mgmd — The MySQL Cluster Management Server Daemon".

We are continuously making improvements in Cluster configuration and attempting to simplify this process. Although we strive to maintain backward compatibility, there may be times when introduce an incompatible change. In such cases we will try to let Cluster users know in advance if a change is not backward compatible. If you find such a change and we have not documented it, please report it in the MySQL bugs database using the instructions given in How to Report Bugs or Problems.

3.2.1. MySQL Cluster Configuration: Basic Example

To support MySQL Cluster, you will need to update my.cnf as shown in the following example. You may also specify these parameters on the command line when invoking the executables.

Note

The options shown here should not be confused with those that are used in config.ini global configuration files. Global configuration options are discussed later in this section.

```
# my.cnf
# example additions to my.cnf for MySQL Cluster
# (valid in MySQL 5.1)
```

```
# enable ndbcluster storage engine, and provide connectstring for
# management server host (default port is 1186)
[mysqld]
ndbcluster
ndb-connectstring=ndb_mgmd.mysql.com
# provide connectstring for management server host (default port: 1186)
[ndbd]
connect-string=ndb_mgmd.mysql.com
# provide connectstring for management server host (default port: 1186)
[ndb_mgm]
connect-string=ndb_mgmd.mysql.com
# provide location of cluster configuration file
[ndb_mgmd]
config-file=/etc/config.ini
```

(For more information on connectstrings, see Section 3.2.3, "The MySQL Cluster Connectstring".)

```
# my.cnf
# example additions to my.cnf for MySQL Cluster
# (will work on all versions)
# enable ndbcluster storage engine, and provide connectstring for management
# server host to the default port 1186
[mysqld]
ndbcluster
ndb-connectstring=ndb_mgmd.mysql.com:1186
```

Important

Once you have started a mysqld process with the NDBCLUSTER and ndb-connectstring parameters in the [mysqld] in the my.cnf file as shown previously, you cannot execute any CREATE TABLE or ALTER TABLE statements without having actually started the cluster. Otherwise, these statements will fail with an error. This is by design.

You may also use a separate [mysql_cluster] section in the cluster my.cnf file for settings to be read and used by all executables:

```
# cluster-specific settings
[mysql_cluster]
ndb-connectstring=ndb_mgmd.mysql.com:1186
```

For additional NDB variables that can be set in the my. cnf file, see Section 3.4.3, "MySQL Cluster System Variables".

The MySQL Cluster global configuration file is named <code>config.ini</code> by default. It is read by ndb_mgmd at startup and can be placed anywhere. Its location and name are specified by using <code>--config-file=path_name</code> on the ndb_mgmd command line. If the configuration file is not specified, ndb_mgmd by default tries to read a file named <code>config.ini</code> located in the current working directory.

The global configuration file for MySQL Cluster uses INI format, which consists of sections preceded by section headings (surrounded by square brackets), followed by the appropriate parameter names and values. One deviation from the standard INI format is that the parameter name and value can be separated by a colon (":") as well as the equal sign ("="); however, the equal sign is preferred. Another deviation is that sections are not uniquely identified by section name. Instead, unique sections (such as two different nodes of the same type) are identified by a unique ID specified as a parameter within the section.

Default values are defined for most parameters, and can also be specified in config.ini. (Prior to MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, there was no default value for NoofReplicas, which always had to be specified explicitly in the [ndbd default] section. Beginning with versions just stated, the default value is 2, which is the recommended setting in most common usage scenarios.) To create a default value section, simply add the word default to the section name. For example, an [ndbd] section contains parameters that apply to a particular data node, whereas an [ndbd default] section contains parameters that apply to all data nodes. Suppose that all data nodes should use the same data memory size. To configure them all, create an [ndbd default] section that contains a DataMemory line to specify the data memory size.

The global configuration file must define the computers and nodes involved in the cluster and on which computers these nodes are located. An example of a simple configuration file for a cluster consisting of one management server, two data nodes and two MySQL servers is shown here:

```
# file "config.ini" - 2 data nodes and 2 SQL nodes
# This file is placed in the startup directory of ndb_mgmd (the
# management server)
# The first MySQL Server can be started from any host. The second
# can be started only on the host mysqld_5.mysql.com
[ndbd default]
NoOfReplicas= 2
DataDir= /var/lib/mysql-cluster
[ndb_mgmd]
Hostname= ndb_mgmd.mysql.com
DataDir= /var/lib/mysql-cluster
[ndbd]
HostName= ndbd_2.mysql.com
[ndbd]
```

HostName= ndbd_3.mysql.com
[mysqld]
[mysqld]
HostName= mysqld_5.mysql.com

Note

The preceding example is intended as a minimal starting configuration for purposes of familiarization with MySQL Cluster, and is almost certain not to be sufficient for production settings. See Section 3.2.2, "Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later", which provides more complete example starting configurations for use with MySQL Cluster NDB 6.2 and newer versions of MySQL Cluster.

Each node has its own section in the config.ini file. For example, this cluster has two data nodes, so the preceding configuration file contains two [ndbd] sections defining these nodes.

Note

Do not place comments on the same line as a section heading in the config.ini file; this causes the management server not to start because it cannot parse the configuration file in such cases.

Sections of the config.ini File

There are six different sections that you can use in the config.ini configuration file, as described in the following list:

- [computer]: Defines cluster hosts. This is not required to configure a viable MySQL Cluster, but be may used as a convenience when setting up a large cluster. See Section 3.2.4, "Defining Computers in a MySQL Cluster", for more information.
- [ndbd]: Defines a cluster data node (ndbd process). See Section 3.2.6, "Defining MySQL Cluster Data Nodes", for details.
- [mysqld]: Defines the cluster's MySQL server nodes (also called SQL or API nodes). For a discussion of SQL node configuration, see Section 3.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".
- [mgm] or [ndb_mgmd]: Defines a cluster management server (MGM) node. For information concerning the configuration of MGM nodes, see Section 3.2.5, "Defining a MySQL Cluster Management Server".
- [tcp]: Defines a TCP/IP connection between cluster nodes, with TCP/IP being the default connection protocol. Normally, [tcp] or [tcp default] sections are not required to set up a MySQL Cluster, as the cluster handles this automatically; however, it may be necessary in some situations to override the defaults provided by the cluster. See Section 3.2.8, "MySQL Cluster TCP/IP Connections", for information about available TCP/IP configuration parameters and how to use them. (You may also find Section 3.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections" to be of interest in some cases.)
- [shm]: Defines shared-memory connections between nodes. In MySQL 5.1, it is enabled by default, but should still be considered experimental. For a discussion of SHM interconnects, see Section 3.2.10, "MySQL Cluster Shared-Memory Connections".
- [sci]:Defines Scalable Coherent Interface connections between cluster data nodes. Such connections require software which, while freely available, is not part of the MySQL Cluster distribution, as well as specialized hardware. See Section 3.2.11, "SCI Transport Connections in MySQL Cluster" for detailed information about SCI interconnects.

You can define default values for each section. All Cluster parameter names are case-insensitive, which differs from parameters specified in my.cnf or my.ini files.

3.2.2. Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later

Achieving the best performance from a MySQL Cluster depends on a number of factors including the following:

- MySQL Cluster software version
- Numbers of data nodes and SQL nodes
- Hardware
- · Operating system
- · Amount of data to be stored

• Size and type of load under which the cluster is to operate

Therefore, obtaining an optimum configuration is likely to be an iterative process, the outcome of which can vary widely with the specifics of each MySQL Cluster deployment. Changes in configuration are also likely to be indicated when changes are made in the platform on which the cluster is run, or in applications that use the MySQL Cluster's data. For these reasons, it is not possible to offer a single configuration that is ideal for all usage scenarios. However, in this section, we provide recommended base configurations for MySQL Cluster NDB 6.2 and 6.3 that can serve as reasonable starting points.

Starting configuration for MySQL Cluster NDB 6.2. The following is a recommended starting point for configuring a cluster running MySQL Cluster NDB 6.2.

```
TCP PARAMETERS
 [tcp default]
 SendBufferMer
ReceiveBufferMemory=2M
# Increasing the sizes of these 2 buffers beyond the default values
 # helps prevent bottlenecks due to slow disk I/O.
     MANAGEMENT NODE PARAMETERS
[ndb_mgmd default]
DataDir=path/to/management/server/data/directory
# It is possible to use a different data directory for each management
# server, but for ease of administration it is preferable to be
# consistent.
 [ndb_mgmd]
 HostName=management-server-1-hostname
# NodeId=management-server-1-nodeid
 [ndb_mgmd]
 HostName=management-server-2-hostname
HostName=management-server-2-hostname
# Using 2 management servers helps guarantee that there is always an
# arbitrator in the event of network partitioning, and so is
# recommended for high availability. Each management server must be
# identified by a HostName. You may for the sake of convenience specify
# a node ID for any management server, although one will be allocated
# for it automatically; if you do so, it must be in the range 1-255
# inclusive and must be unique among all IDs specified for cluster
# nodes
     nodes.
     DATA NODE PARAMETERS
 [ndbd default]
 NoOfReplicas=2
# Using 2 replicas is recommended to guarantee availability of data;
# using only 1 replica does not provide any redundancy, which means
# that the failure of a single data node causes the entire cluster to
# shut down. We do not recommend using more than 2 replicas, since 2 is
# sufficient to provide high availability, and we do not currently test
# with greater values for this parameter.
LockPagesInMainMemory=1
# On Linux and Solaris systems, setting this parameter locks data node # processes into memory. Doing so prevents them from swapping to disk, # which can severely degrade cluster performance.
DataMemory=3072M
IndexMemory=384M
    The values provided for DataMemory and IndexMemory assume 4 GB RAM per data node. However, for best results, you should first calculate the memory that would be used based on the data you actually plan to store (you may find the ndb_size.pl utility helpful in estimating this), then allow an extra 20% over the calculated values. Naturally,
    you should ensure that each data node host has at least as much physical memory as the sum of these two values.
      ODirect=1
     Enabling this parameter causes NDBCLUSTER to try using O_DIRECT
# Enabling this parameter causes NDBCLUSTER to try using O_DIRECT
# writes for local checkpoints and redo logs; this can reduce load on
# CPUs. We recommend doing so when using MySQL Cluster NDB 6.2.3 or
# newer on systems running Linux kernel 2.6 or later.
NoOfFragmentLogFiles=300
DataDir=path/to/data/node/data/directory
MaxNoOfConcurrentOperations=100000
TimeBetweenGlobalCheckpoints=1000
TimeBetweenFrochs=200
TimeBetweenEpochs=200
DiskCheckpointSpeed=10M
DiskCheckpointSpeedInRestart=100M
RedoBuffer=32M
# MaxNoOfLocalScans=64
MaxNoOfTables=1024
 MaxNofOfOrderedIndexes=256
HostName=data-node-A-hostname
# NodeId=data-node-A-nodeid
 [ndbd]
 HostName=data-node-B-hostname
# NodeId=data-node-B-nodeid
# You must have an [ndbd] section for every data node in the cluster;
    each of these sections must include a HostName. Each section may optionally include an Id for convenience, but in most cases, it is sufficient to allow the cluster to allocate node IDs dynamically. If you do specify the node ID for a data node, it must be in the range 1
     to 48 inclusive and must be unique among all IDs specified for
    cluster nodes.
SQL NODE / API NODE PARAMETERS
 [mysqld]
                       ne=SOL-node-1-hostname
 # NodeId=sql-node-A-nodeid
```

```
[mysqld]
[mysqld]
# Each API or SQL node that connects to the cluster requires a [mysqld]
# or [api] section of its own. Each such section defines a connection
# "slot"; you should have at least as many of these sections in the
# config.ini file as the total number of API nodes and SQL nodes that
# you wish to have connected to the cluster at any given time. There is
# no performance or other penalty for having extra slots available in
# case you find later that you want or need more API or SQL nodes to
# connect to the cluster at the same time.
# If no HostName is specified for a given [mysqld] or [api] section,
# then any API or SQL node may use that slot to connect to the
# cluster. You may wish to use an explicit HostName for one connection slot
# to guarantee that an API or SQL node from that host can always
# connect to the cluster. If you wish to prevent API or SQL nodes from
# connecting from other than a desired host or hosts, then use a
# HostName for every [mysqld] or [api] section in the config.ini file.
# You can if you wish define a node ID (Id parameter) for any API or
# SQL node, but this is not necessary; if you do so, it must be in the
# range 1 to 255 inclusive and must be unique among all IDs specified
# for cluster nodes.
```

Starting configuration for MySQL Cluster NDB 6.3. The following is a recommended starting point for configuring a cluster running MySQL Cluster NDB 6.3. It is similar to the recommendation for MySQL Cluster NDB 6.2, with the addition of parameters for better control of NDBCLUSTER process threads.

```
# TCP PARAMETERS
[tcp default]
SendBufferMemory=2M
ReceiveBufferMemory=2M
      Increasing the sizes of these 2 buffers beyond the default values
     helps prevent bottlenecks due to slow disk I/O. MANAGEMENT NODE PARAMETERS
 [ndb_mgmd default]
 DataDir=path/to/management/server/data/directory
# It is possible to use a different data directory for each management # server, but for ease of administration it is preferable to be # consistent.
 [ndb mqmd]
HostName=management-server-A-hostname
# NodeId=management-server-A-nodeid
  [ndb_mgmd]
HostName=management-server-B-hostname
# NodeId=management-server-B-nodeid
# NodeId=management-server_B-nodeid
# NodeId=management-server_B-nodeid
# Using 2 management servers helps guarantee that there is always an
# arbitrator in the event of network partitioning, and so is
# recommended for high availability. Each management server must be
# identified by a HostName. You may for the sake of convenience specify
# a NodeId for any management server, although one will be allocated
# for it automatically; if you do so, it must be in the range 1-255
# inclusive and must be unique among all IDs specified for cluster
     DATA NODE PARAMETERS
 [ndbd default]
NoOfReplicas=2
# Using 2 replicas is recommended to guarantee availability of data;
     using 2 replicas is recommended to guarantee availability of data, using only 1 replica does not provide any redundancy, which means that the failure of a single data node causes the entire cluster to shut down. We do not recommend using more than 2 replicas, since 2 is sufficient to provide high availability, and we do not currently test
      with greater values for this parameter
LockPagesInMainMemory=1
# On Linux and Solaris systems, setting this parameter locks data node # processes into memory. Doing so prevents them from swapping to disk, # which can severely degrade cluster performance.
DataMemory=3072M
IndexMemory=384M
# The values provided for DataMemory and IndexMemory assume 4 GB RAM # per data node. However, for best results, you should first calculate # the memory that would be used based on the data you actually plan to # store (you may find the ndb_size.pl utility helpful in estimating # this), then allow an extra 20% over the calculated values. Naturally, # you should ensure that each data node host has at least as much # physical memory as the sum of these two values.
      ODirect=1
# UDIFECT=1
# Enabling this parameter causes NDBCLUSTER to try using O_DIRECT
# writes for local checkpoints and redo logs; this can reduce load on
# CPUs. We recommend doing so when using MySQL Cluster NDB 6.2.3 or
# newer on systems running Linux kernel 2.6 or later.
NOOFFragmentLogFiles=300
DataDir=path/to/data/node/data/directory
MaxNoofConcurrentOperations=100000
SchedularSpininger=400
SchedulerSpinTimer=400
SchedulerExecutionTimer=100
RealTimeScheduler=1
# Setting these parameters allows you to take advantage of real-time scheduling # of NDBCLUSTER threads (introduced in MySQL Cluster NDB 6.3.4) to get higher
# throughput.
TimeBetweenGlobalCheckpoints=1000
TimeBetweenEpochs=200
DiskCheckpointSpeed=10M
DiskCheckpointSpeedInRestart=100M
RedoBuffer=32M
# CompressedLCP=1
 # CompressedBackup=1
```

```
# Enabling CompressedLCP and CompressedBackup causes, respectively, local
# Embling CompressedLCP and Compressedackup causes, respectively, local checkpoint files and backup files to be compressed, which can result in a space savings of up to 50% over noncompressed LCPs and backups.

# MaxNoOfLocalScans=64
MaxNoOfTables=1024
 MaxNofOfOrderedIndexes=256
 [ndbd]
 HostName=data-node-A-hostname
 # NodeId=data-node-A-nodeid
# On systems with multiple CPUs, these parameters can be used to lock NDBCLUSTER
 # threads to specific CPUs
 [ndbd]
HostName=data-node-B-hostname
# NodeId=data-node-B-nodeid
LockExecuteThreadToCPU=1
LockMaintThreadsToCPU=0
# You must have an [ndbd] section for every data node in the cluster; # each of these sections must include a HostName. Each section may
     optionally include a NodeId for convenience, but in most cases, it is sufficient to allow the cluster to allocate node IDs dynamically. If you do specify the node ID for a data node, it must be in the range 1 to 48 inclusive and must be unique among all IDs specified for
 # cluster nodes.
# SQL NODE / API NODE PARAMETERS
 [mysqld]
      HostName=sql-node-A-hostname
    NodeId=sql-node-A-nodeid
 [mysqld]
 [mysqld]
[mysqld]
# Each API or SQL node that connects to the cluster requires a [mysqld]
# or [api] section of its own. Each such section defines a connection
# "slot"; you should have at least as many of these sections in the
# config.ini file as the total number of API nodes and SQL nodes that
# you wish to have connected to the cluster at any given time. There is
# no performance or other penalty for having extra slots available in
# case you find later that you want or need more API or SQL nodes to
# connect to the cluster at the same time.
    connect to the cluster at the same time.

If no HostName is specified for a given [mysqld] or [api] section, then any API or SQL node may use that slot to connect to the cluster. You may wish to use an explicit HostName for one connection slot to guarantee that an API or SQL node from that host can always connect to the cluster. If you wish to prevent API or SQL nodes from connecting from other than a desired host or hosts, then use a HostName for every [mysqld] or [api] section in the config.ini file. You can if you wish define a node ID (NodeId parameter) for any API or SQL node, but this is not necessary; if you do so, it must be in the range 1 to 255 inclusive and must be unique among all IDs specified for cluster nodes.
```

Recommended my.cnf options for SQL nodes. MySQL Servers acting as MySQL Cluster SQL nodes must always be started with the --ndbcluster and --ndb-connectstring options, either on the command line or in my.cnf. In addition, set the following options for all mysqld processes in the cluster, unless your setup requires otherwise:

```
• --ndb-use-exact-count=0
```

- --ndb-index-stat-enable=0
- --ndb-force-send=1
- --engine-condition-pushdown=1

3.2.3. The MySQL Cluster Connectstring

With the exception of the MySQL Cluster management server (ndb_mgmd), each node that is part of a MySQL Cluster requires a *connectstring* that points to the management server's location. This connectstring is used in establishing a connection to the management server as well as in performing other tasks depending on the node's role in the cluster. The syntax for a connectstring is as follows:

```
[nodeid=node_id, ]host-definition[, host-definition[, ...]]
host-definition:
   host_name[:port_number]
```

node_id is an integer larger than 1 which identifies a node in config.ini. host_name is a string representing a valid Internet host name or IP address. port_number is an integer referring to a TCP/IP port number.

```
example 1 (long): "nodeid=2,myhost1:1100,myhost2:1100,192.168.0.3:1200" example 2 (short): "myhost1"
```

localhost: 1186 is used as the default connectstring value if none is provided. If port_num is omitted from the connectstring, the default port is 1186. This port should always be available on the network because it has been assigned by IANA for this pur-

pose (see http://www.iana.org/assignments/port-numbers for details).

By listing multiple host definitions, it is possible to designate several redundant management servers. A MySQL Cluster data or API node attempts to contact successive management servers on each host in the order specified, until a successful connection has been established.

Beginning with MySQL Cluster NDB 6.3.19, it is also possible in a connectstring to specify one or more bind addresses to be used by nodes having multiple network interfaces for connecting to management servers. A bind address consists of a hostname or network address and an optional port number. This enhanced syntax for connectstrings is shown here:

```
[nodeid=node_id, ]
    [bind-address=host-definition, ]
    host-definition[; bind-address=host-definition]
    host-definition[; bind-address=host-definition]
    [, ...]]
host-definition:
    host_name[:port_number]
```

If a single bind address is used in the connectstring *prior* to specifying any management hosts, then this address is used as the default for connecting to any of them (unless overridden for a given management server; see later in this section for an example). For example, the following connectstring causes the node to use 192.168.178.242 regardless of the management server to which it connects:

```
bind-address=192.168.178.242, poseidon:1186, perch:1186
```

If a bind address is specified *following* a management host definition, then it is used only for connecting to that management node. Consider the following connectstring:

```
poseidon:1186;bind-address=localhost, perch:1186;bind-address=192.168.178.242
```

In this case, the node uses localhost to connect to the management server running on the host named poseidon and 192.168.178.242 to connect to the management server running on the host named perch.

You can specify a default bind address and then override this default for one or more specific management hosts. In the following example, localhost is used for connecting to the management server running on host poseidon; since 192.168.178.242 is specified first (before any management server definitions), it is the default bind address and so is used for connecting to the management servers on hosts perch and orca:

```
bind-address=192.168.178.242,poseidon:1186;bind-address=localhost,perch:1186,orca:2200
```

There are a number of different ways to specify the connectstring:

- Each executable has its own command-line option which enables specifying the management server at startup. (See the documentation for the respective executable.)
- It is also possible to set the connectstring for all nodes in the cluster at once by placing it in a [mysql_cluster] section in the management server's my.cnf file.
- For backward compatibility, two other options are available, using the same syntax:
 - Set the NDB_CONNECTSTRING environment variable to contain the connectstring.
 - 2. Write the connectstring for each executable into a text file named Ndb.cfg and place this file in the executable's startup directory.

However, these are now deprecated and should not be used for new installations.

The recommended method for specifying the connectstring is to set it on the command line or in the my. cnf file for each executable.

Previous to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the maximum length of a connectstring was 1024 characters.

3.2.4. Defining Computers in a MySQL Cluster

The [computer] section has no real significance other than serving as a way to avoid the need of defining host names for each node in the system. All parameters mentioned here are required.

Id

Restart Type	initial, node	
	Permitted Values	
	Type	string
	Default	
	Range	-

This is a unique identifier, used to refer to the host computer elsewhere in the configuration file.

Important

The computer ID is *not* the same as the node ID used for a management, API, or data node. Unlike the case with node IDs, you cannot use NodeId in place of Id in the [computer] section of the config.ini file.

HostName

Restart Type	system	system	
	Permitted	Values	
	Type	string	
	Default		
	Range	-	

This is the computer's hostname or IP address.

3.2.5. Defining a MySQL Cluster Management Server

The [ndb_mgmd] section is used to configure the behavior of the management server. [mgm] can be used as an alias; the two section names are equivalent. All parameters in the following list are optional and assume their default values if omitted.

Note

If neither the ExecuteOnComputer nor the HostName parameter is present, the default value localhost will be assumed for both.

Id

Version Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Restart Type	node	node	
	Permitted Values		
	Type	Type numeric	
	Default	Default	
	Range	Range 1-63	

Each node in the cluster has a unique identity. For a management node, this is represented by an integer value in the range 1 to 63 inclusive (previous to MySQL Cluster NDB 6.1.1), or in the range 1 to 255 inclusive (MySQL Cluster NDB 6.1.1 and later). This ID is used by all internal cluster messages for addressing the node, and so must be unique for each MySQL Cluster node, regardless of the type of node.

Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for management nodes (and API nodes) to values greater than 48

The use of the Id parameter for identifying management nodes is deprecated in favor of NodeId beginning with MySQL

Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it now generates a warning.

• NodeId

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	1-63	

Each node in the cluster has a unique identity. For a management node, this is represented by an integer value in the range 1 to 63 inclusive (previous to MySQL Cluster NDB 6.1.1), or in the range 1 to 255 inclusive (MySQL Cluster NDB 6.1.1 and later). This ID is used by all internal cluster messages for addressing the node, and so must be unique for each MySQL Cluster node, regardless of the type of node.

Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for management nodes (and API nodes) to values greater than 48.

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

• ExecuteOnComputer

Restart Type	system	system	
	Permitted Values		
	Type	string	
	Default		
	Range	-	

This refers to the Id set for one of the computers defined in a [computer] section of the config.ini file.

PortNumber

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1186	
	Range	0-64K	

This is the port number on which the management server listens for configuration requests and management commands.

• HostName

Restart Type	system	
	Permitted Values	
	Type	string
	Default	
	Range	-

Specifying this parameter defines the hostname of the computer on which the management node is to reside. To specify a hostname other than localhost, either this parameter or ExecuteOnComputer is required.

• LogDestination

Restart Type	node	node	
	Permitted	l Values	
	Type	string	
	Default	<pre>FILE:filename=ndb_nodeid_cluster.log,maxsize=1000000,ma xfiles=6</pre>	
	Range	-	

This parameter specifies where to send cluster logging information. There are three options in this regard—CONSOLE, SYS-LOG, and FILE—with FILE being the default:

CONSOLE outputs the log to stdout:

CONSOLE

• SYSLOG sends the log to a syslog facility, possible values being one of auth, authpriv, cron, daemon, ftp, kern, lpr, mail, news, syslog, user, uucp, local0, local1, local2, local3, local4, local5, local6, or local7.

Note

Not every facility is necessarily supported by every operating system.

SYSLOG: facility=syslog

- · FILE pipes the cluster log output to a regular file on the same machine. The following values can be specified:
 - filename: The name of the log file.
 - maxsize: The maximum size (in bytes) to which the file can grow before logging rolls over to a new file. When this occurs, the old log file is renamed by appending . N to the file name, where N is the next number not yet used with this name.
 - maxfiles: The maximum number of log files.

FILE:filename=cluster.log,maxsize=1000000,maxfiles=6

The default value for the FILE parameter is FILE: filename=ndb_node_id_cluster.log, maxsize=1000000, maxfiles=6, where node_id is the ID of the node.

It is possible to specify multiple log destinations separated by semicolons as shown here:

CONSOLE;SYSLOG:facility=local0;FILE:filename=/var/log/mgmd

• ArbitrationRank

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1	
	Range	0-2	

This parameter is used to define which nodes can act as arbitrators. Only management nodes and SQL nodes can be arbitrators. ArbitrationRank can take one of the following values:

- 0: The node will never be used as an arbitrator.
- 1: The node has high priority; that is, it will be preferred as an arbitrator over low-priority nodes.
- 2: Indicates a low-priority node which be used as an arbitrator only if a node with a higher priority is not available for that purpose.

Normally, the management server should be configured as an arbitrator by setting its ArbitrationRank to 1 (the default for management nodes) and those for all SQL nodes to 0 (the default for SQL nodes).

Beginning with MySQL 5.1.16 and MySQL Cluster NDB 6.1.3, it is possible to disable arbitration completely by setting ArbitrationRank to 0 on all management and SQL nodes. In MySQL Cluster NDB 7.0.7 and later releases, you can also control arbitration by overriding this parameter; to do this, set the Arbitration parameter in the [ndbd default] section of the config.ini global configuration file.

• ArbitrationDelay

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-4G	

An integer value which causes the management server's responses to arbitration requests to be delayed by that number of milliseconds. By default, this value is 0; it is normally not necessary to change it.

• DataDir

Restart Type	node	node	
	Permitted	Values	
	Type	string	
	Default	•	
	Range	-	

This specifies the directory where output files from the management server will be placed. These files include cluster log files, process output files, and the daemon's process ID (PID) file. (For log files, this location can be overridden by setting the FILE parameter for LogDestination as discussed previously in this section.)

The default value for this parameter is the directory in which ndb_mgmd is located.

HeartbeatThreadPriority

Beginning with MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2, it is possible to use this parameter to set the scheduling policy and priority of heartbeat threads for management and API nodes.

The syntax for setting this parameter is shown here:

```
HeartbeatThreadPriority = policy[, priority]
policy:
{FIFO | RR}
```

When setting this parameter, you must specify a policy. This is one of FIFO (first in, first out) or RR (round robin). The policy value is followed optionally by the priority (an integer).

• TotalSendBufferMemory

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039. For more detailed information about the behavior and use of TotalSendBufferMemory and configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

Note

After making changes in a management node's configuration, it is necessary to perform a rolling restart of the cluster for the new configuration to take effect.

To add new management servers to a running MySQL Cluster, it is also necessary to perform a rolling restart of all cluster nodes after modifying any existing config.ini files. For more information about issues arising when using

multiple management nodes, see Section 1.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

3.2.6. Defining MySQL Cluster Data Nodes

The [ndbd] and [ndbd default] sections are used to configure the behavior of the cluster's data nodes.

[ndbd] and [ndbd_default] are always used as the section names whether you are using ndbd or (in MySQL Cluster NDB 6.4.0 and later) ndbmtd binaries for the data node processes.

There are many parameters which control buffer sizes, pool sizes, timeouts, and so forth. The only mandatory parameters are:

- Either ExecuteOnComputer or HostName, which must be defined in the local [ndbd] section.
- The parameter NoOfReplicas, which must be defined in the [ndbd default] section, as it is common to all Cluster data

Note

It is no longer strictly necessary to set NoofReplicas starting with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, where it acquires a default value (2). However, it remains good practice to set it explicitly.

Most data node parameters are set in the [ndbd default] section. Only those parameters explicitly stated as being able to set local values are permitted to be changed in the [ndbd] section. Where present, HostName, NodeId and ExecuteOnComputer must be defined in the local [ndbd] section, and not in any other section of config.ini. In other words, settings for these parameters are specific to one data node.

For those parameters affecting memory usage or buffer sizes, it is possible to use K, M, or G as a suffix to indicate units of 1024, $1024 \times 1024 \times$

Information about configuration parameters specific to MySQL Cluster Disk Data tables can be found later in this section.

Beginning with MySQL Cluster NDB 6.4.0, all of these parameters also apply to ndbmtd (the multi-threaded version of ndbd). An additional data node configuration parameter MaxNoOfExecutionThreads applies to ndbmtd only, and has no effect when used with ndbd. For more information, see Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

Identifying data nodes. The NodeId or Id value (that is, the data node identifier) can be allocated on the command line when the node is started or in the configuration file.

• Id

Version Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Restart Type	node	node	
	Permitted Values		
	Type	Type numeric	
	Default	Default	
	Range	Range 1-48	

A unique node ID is used as the node's address for all cluster internal messages. For data nodes, this is an integer in the range 1 to 48 inclusive. Each node in the cluster must have a unique identifier.

NodeId is the preferred parameter name to use when identifying data nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

• NodeId

Restart Type	node
--------------	------

Permitted Values	
Type	numeric
Default	
Range	1-48

A unique node ID is used as the node's address for all cluster internal messages. For data nodes, this is an integer in the range 1 to 48 inclusive. Each node in the cluster must have a unique identifier.

NodeId is the preferred parameter name to use when identifying data nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

• ExecuteOnComputer

Restart Type	system	system	
	Permitted	Permitted Values	
	Type	string	
	Default		
	Range	-	

This refers to the Id set for one of the computers defined in a [computer] section.

• HostName

Restart Type	system	system	
	Permitted	Permitted Values	
	Type	string	
	Default	localhost	
	Range	-	

Specifying this parameter defines the hostname of the computer on which the data node is to reside. To specify a hostname other than localhost, either this parameter or ExecuteOnComputer is required.

• ServerPort

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	1-64K	

Each node in the cluster uses a port to connect to other nodes. By default, this port is allocated dynamically in such a way as to ensure that no two nodes on the same host computer receive the same port number, so it should normally not be necessary to specify a value for this parameter.

However, if you need to be able to open specific ports in a firewall to permit communication between data nodes and API nodes (including SQL nodes), you can set this parameter to the number of the desired port in an <code>[ndbd]</code> section or (if you need to do this for multiple data nodes) the <code>[ndbd]</code> default] section of the <code>config.ini</code> file, and then open the port having that number for incoming connections from SQL nodes, API nodes, or both.

Note

Connections from data nodes to management nodes is done using the ndb_mgmd management port (the management server's PortNumber; see Section 3.2.5, "Defining a MySQL Cluster Management Server") so outgoing connections to that port from any data nodes should always be permitted.

TcpBind_INADDR_ANY

Setting this parameter to TRUE or 1 binds IP_ADDR_ANY so that connections can be made from anywhere (for autogenerated connections). The default is FALSE (0).

This parameter was added in MySQL Cluster NDB 6.2.0.

NodeGroup

Version Introduced	5.1.30-ndb	5.1.30-ndb-6.4.0	
Restart Type	initial, syst	initial, system	
	Permitted	Permitted Values	
	Type	numeric	
	Default		
	Range	0-65536	

This parameter can be used to assign a data node to a specific node group. It is read only when the cluster is started for the first time, and cannot be used to reassign a data node to a different node group online. It is generally not desirable to use this parameter in the [ndbd default] section of the config.ini file, and care must be taken not to assign nodes to node groups in such a way that an invalid numbers of nodes are assigned to any node groups.

The NodeGroup parameter is chiefly intended for use in adding a new node group to a running MySQL Cluster without having to perform a rolling restart. For this purpose, you should set it to 65536 (the maximum value). You are not required to set a NodeGroup value for all cluster data nodes, only for those nodes which are to be started and added to the cluster as a new node group at a later time. For more information, see Section 5.12.3, "Adding MySQL Cluster Data Nodes Online: Detailed Example".

This parameter was added in MySQL Cluster NDB 6.4.0.

• NoOfReplicas

Restart Type	initial, system		
	Permitted Values		
	Type	numeric	
	Default	None	
	Range	1-4	
	Permitted	Values	
	Type	numeric	
	Default	None	
	Range	1-4	
	Permitted Values		
	Type	numeric	
	Default	2	
	Range	1-4	
	Permitted Values		
	Type	numeric	
	Default	2	
	Range	1-4	

This global parameter can be set only in the [ndbd default] section, and defines the number of replicas for each table stored in the cluster. This parameter also specifies the size of node groups. A node group is a set of nodes all storing the same information.

Node groups are formed implicitly. The first node group is formed by the set of data nodes with the lowest node IDs, the next node group by the set of the next lowest node identities, and so on. By way of example, assume that we have 4 data nodes and that NoOfReplicas is set to 2. The four data nodes have node IDs 2, 3, 4 and 5. Then the first node group is formed from nodes 2 and 3, and the second node group by nodes 4 and 5. It is important to configure the cluster in such a manner that nodes in the same node groups are not placed on the same computer because a single hardware failure would cause the entire cluster to fail.

If no node IDs are provided, the order of the data nodes will be the determining factor for the node group. Whether or not explicit assignments are made, they can be viewed in the output of the management client's SHOW command.

Prior to MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, there was no default value for NoOfReplicas; beginning with these versions, the default value is 2, which is the recommended setting in most common usage scenarios. (Bug #44746)

The maximum possible value is 4; currently, only the values 1 and 2 are actually supported.

Important

Setting NoOfReplicas to 1 means that there is only a single copy of all Cluster data; in this case, the loss of a single data node causes the cluster to fail because there are no additional copies of the data stored by that node.

The value for this parameter must divide evenly into the number of data nodes in the cluster. For example, if there are two data nodes, then NoOfReplicas must be equal to either 1 or 2, since 2/3 and 2/4 both yield fractional values; if there are four data nodes, then NoOfReplicas must be equal to 1, 2, or 4.

DataDir

Restart Type	initial, node	
	Permitted Values	
	Type	string
	Default	•
	Range	-

This parameter specifies the directory where trace files, log files, pid files and error logs are placed.

The default is the data node process working directory.

• FileSystemPath

Version Introduced	5.1.15-ndb	5.1.15-ndb-6.1.1		
Restart Type	initial, nod	initial, node		
	Permitted	Permitted Values		
	Type	string		
	Default DataDir			
	Range	-		

This parameter specifies the directory where all files created for metadata, REDO logs, UNDO logs (for Disk Data tables), and data files are placed. The default is the directory specified by DataDir.

Note

This directory must exist before the ndbd process is initiated.

The recommended directory hierarchy for MySQL Cluster includes /var/lib/mysql-cluster, under which a directory for the node's file system is created. The name of this subdirectory contains the node ID. For example, if the node ID is 2, this subdirectory is named ndb_2_fs.

BackupDataDir

Restart Type	initial, nod	initial, node	
	Permitted	Permitted Values	
	Type	string	
	Default	FileSystemPath	
	Range	-	

This parameter specifies the directory in which backups are placed.

Important

The string '/BACKUP' is always appended to this value. For example, if you set the value of BackupDataDir to /var/lib/cluster-data, then all backups are stored under /var/lib/cluster-data/BACKUP. This also means that the *effective* default backup location is the directory named BACKUP under the location specified by the FileSystemPath parameter.

Data Memory, Index Memory, and String Memory

DataMemory and IndexMemory are [ndbd] parameters specifying the size of memory segments used to store the actual records and their indexes. In setting values for these, it is important to understand how DataMemory and IndexMemory are used, as they usually need to be updated to reflect actual usage by the cluster:

DataMemory

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	80M	
	Range	1M-1024G	

This parameter defines the amount of space (in bytes) available for storing database records. The entire amount specified by this value is allocated in memory, so it is extremely important that the machine has sufficient physical memory to accommodate it

The memory allocated by <code>DataMemory</code> is used to store both the actual records and indexes. There is a 16-byte overhead on each record; an additional amount for each record is incurred because it is stored in a 32KB page with 128 byte page overhead (see below). There is also a small amount wasted per page due to the fact that each record is stored in only one page.

For variable-size table attributes in MySQL 5.1, the data is stored on separate datapages, allocated from DataMemory. Variable-length records use a fixed-size part with an extra overhead of 4 bytes to reference the variable-size part. The variable-size part has 2 bytes overhead plus 2 bytes per attribute.

The maximum record size is currently 8052 bytes.

The memory space defined by <code>DataMemory</code> is also used to store ordered indexes, which use about 10 bytes per record. Each table row is represented in the ordered index. A common error among users is to assume that all indexes are stored in the memory allocated by <code>IndexMemory</code>, but this is not the case: Only primary key and unique hash indexes use this memory; ordered indexes use the memory allocated by <code>DataMemory</code>. However, creating a primary key or unique hash index also creates an ordered index on the same keys, unless you specify <code>USING HASH</code> in the index creation statement. This can be verified by running <code>ndb_desc -d db_name table_name</code> in the management client.

The memory space allocated by <code>DataMemory</code> consists of 32KB pages, which are allocated to table fragments. Each table is normally partitioned into the same number of fragments as there are data nodes in the cluster. Thus, for each node, there are the same number of fragments as are set in <code>NoofReplicas</code>.

In addition, due to the way in which new pages are allocated when the capacity of the current page is exhausted, there is an additional overhead of approximately 18.75%. When more <code>DataMemory</code> is required, more than one new page is allocated, according to the following formula:

```
number of new pages = FLOOR(number of current pages × 0.1875) + 1
```

For example, if 15 pages are currently allocated to a given table and an insert to this table requires additional storage space, the number of new pages allocated to the table is $FLOOR(15 \times 0.1875) + 1 = FLOOR(2.8125) + 1 = 2 + 1 = 3$. Now 15 + 3 = 18 memory pages are allocated to the table. When the last of these 18 pages becomes full, $FLOOR(18 \times 0.1875) + 1 = FLOOR(3.3750) + 1 = 3 + 1 = 4$ new pages are allocated, so the total number of pages allocated to the table is now 22.

Note

The "18.75% + 1" overhead is no longer required beginning with MySQL Cluster NDB 6.2.3 and MySQL Cluster NDB 6.3.0.

Once a page has been allocated, it is currently not possible to return it to the pool of free pages, except by deleting the table.

(This also means that DataMemory pages, once allocated to a given table, cannot be used by other tables.) Performing a node recovery also compresses the partition because all records are inserted into empty partitions from other live nodes.

The <code>DataMemory</code> memory space also contains UNDO information: For each update, a copy of the unaltered record is allocated in the <code>DataMemory</code>. There is also a reference to each copy in the ordered table indexes. Unique hash indexes are updated only when the unique index columns are updated, in which case a new entry in the index table is inserted and the old entry is deleted upon commit. For this reason, it is also necessary to allocate enough memory to handle the largest transactions performed by applications using the cluster. In any case, performing a few large transactions holds no advantage over using many smaller ones, for the following reasons:

- · Large transactions are not any faster than smaller ones
- · Large transactions increase the number of operations that are lost and must be repeated in event of transaction failure
- · Large transactions use more memory

The default value for <code>DataMemory</code> is 80MB; the minimum is 1MB. There is no maximum size, but in reality the maximum size has to be adapted so that the process does not start swapping when the limit is reached. This limit is determined by the amount of physical RAM available on the machine and by the amount of memory that the operating system may commit to any one process. 32-bit operating systems are generally limited to 2–4GB per process; 64-bit operating systems can use more. For large databases, it may be preferable to use a 64-bit operating system for this reason.

• IndexMemory

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	18M	
	Range	1M-1T	

This parameter controls the amount of storage used for hash indexes in MySQL Cluster. Hash indexes are always used for primary key indexes, unique indexes, and unique constraints. Note that when defining a primary key and a unique index, two indexes will be created, one of which is a hash index used for all tuple accesses as well as lock handling. It is also used to enforce unique constraints.

The size of the hash index is 25 bytes per record, plus the size of the primary key. For primary keys larger than 32 bytes another 8 bytes is added.

The default value for IndexMemory is 18MB. The minimum is 1MB.

StringMemory

Restart Type	system	
	Permitted Values (>= 5.1.6)	
	Type	numeric
	Default	5
	Range	0-4G

This parameter determines how much memory is allocated for strings such as table names, and is specified in an <code>[ndbd]</code> or <code>[ndbd]</code> default] section of the <code>config.ini</code> file. A value between 0 and 100 inclusive is interpreted as a percent of the maximum default value, which is calculated based on a number of factors including the number of tables, maximum table name size, maximum size of <code>.FRM</code> files, <code>MaxNoOfTriggers</code>, maximum column name size, and maximum default column value. In general it is safe to assume that the maximum default value is approximately 5 MB for a MySQL Cluster having 1000 tables.

A value greater than 100 is interpreted as a number of bytes.

Beginning with MySQL Cluster NDB 6.2.18, MySQL Cluster NDB 6.3.24, and MySQL Cluster NDB 7.0.5, the default value is 25—that is, 25 percent of the default maximum, or approximately 25 KB. (Previously, the default value was 5 beginning with MySQL 5.1.6; prior to MySQL 5.1.6, the default was 0.)

Under most circumstances, the default value should be sufficient, but when you have a great many Cluster tables (1000 or more), it is possible to get Error 773 Out of String Memory, please modify StringMemory config parameter: Permanent error: Schema error, in which case you should increase this value. 25 (25 percent) is not excessive, and should

prevent this error from recurring in all but the most extreme conditions.

The following example illustrates how memory is used for a table. Consider this table definition:

```
CREATE TABLE example (
a INT NOT NULL,
b INT NOT NULL,
c INT NOT NULL,
PRIMARY KEY(a),
UNIQUE(b)
) ENGINE-NDBCLUSTER;
```

For each record, there are 12 bytes of data plus 12 bytes overhead. Having no nullable columns saves 4 bytes of overhead. In addition, we have two ordered indexes on columns a and b consuming roughly 10 bytes each per record. There is a primary key hash index on the base table using roughly 29 bytes per record. The unique constraint is implemented by a separate table with b as primary key and a as a column. This other table consumes an additional 29 bytes of index memory per record in the example table as well 8 bytes of record data plus 12 bytes of overhead.

Thus, for one million records, we need 58MB for index memory to handle the hash indexes for the primary key and the unique constraint. We also need 64MB for the records of the base table and the unique index table, plus the two ordered index tables.

You can see that hash indexes takes up a fair amount of memory space; however, they provide very fast access to the data in return. They are also used in MySQL Cluster to handle uniqueness constraints.

Currently, the only partitioning algorithm is hashing and ordered indexes are local to each node. Thus, ordered indexes cannot be used to handle uniqueness constraints in the general case.

An important point for both IndexMemory and DataMemory is that the total database size is the sum of all data memory and all index memory for each node group. Each node group is used to store replicated information, so if there are four nodes with two replicas, there will be two node groups. Thus, the total data memory available is $2 \times DataMemory$ for each data node.

It is highly recommended that DataMemory and IndexMemory be set to the same values for all nodes. Data distribution is even over all nodes in the cluster, so the maximum amount of space available for any node can be no greater than that of the smallest node in the cluster.

DataMemory and IndexMemory can be changed, but decreasing either of these can be risky; doing so can easily lead to a node or even an entire MySQL Cluster that is unable to restart due to there being insufficient memory space. Increasing these values should be acceptable, but it is recommended that such upgrades are performed in the same manner as a software upgrade, beginning with an update of the configuration file, and then restarting the management server followed by restarting each data node in turn.

Updates do not increase the amount of index memory used. Inserts take effect immediately; however, rows are not actually deleted until the transaction is committed.

Transaction parameters. The next few [ndbd] parameters that we discuss are important because they affect the number of parallel transactions and the sizes of transactions that can be handled by the system. MaxNoOfConcurrentTransactions sets the number of parallel transactions possible in a node. MaxNoOfConcurrentOperations sets the number of records that can be in update phase or locked simultaneously.

Both of these parameters (especially MaxNoOfConcurrentOperations) are likely targets for users setting specific values and not using the default value. The default value is set for systems using small transactions, to ensure that these do not use excessive memory.

MaxDMLOperationsPerTransaction, added in MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.15, sets the maximum number of DML operations that can be performed in a given transaction.

• MaxNoOfConcurrentTransactions

Restart Type	system	system	
	Permitted Values		
	Type	numeric	
	Default	4096	
	Range	32-4G	

Each cluster data node requires a transaction record for each active transaction in the cluster. The task of coordinating transactions is distributed among all of the data nodes. The total number of transaction records in the cluster is the number of transactions in any given node times the number of nodes in the cluster.

Transaction records are allocated to individual MySQL servers. Each connection to a MySQL server requires at least one transaction record, plus an additional transaction object per table accessed by that connection. This means that a reasonable minimum for this parameter is

```
MaxNoOfConcurrentTransactions =
  (maximum number of tables accessed in any single transaction + 1)
  * number of cluster SQL nodes
```

Suppose that there are 4 SQL nodes using the cluster. A single join involving 5 tables requires 6 transaction records; if there are 5 such joins in a transaction, then 5 * 6 = 30 transaction records are required for this transaction, per MySQL server, or 30 * 4 = 120 transaction records total.

This parameter must be set to the same value for all cluster data nodes. This is due to the fact that, when a data node fails, the oldest surviving node re-creates the transaction state of all transactions that were ongoing in the failed node.

Changing the value of MaxNoOfConcurrentTransactions requires a complete shutdown and restart of the cluster.

The default value is 4096.

MaxNoOfConcurrentOperations

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	32K	
	Range	32-4G	

It is a good idea to adjust the value of this parameter according to the size and number of transactions. When performing transactions of only a few operations each and not involving a great many records, there is no need to set this parameter very high. When performing large transactions involving many records need to set this parameter higher.

Records are kept for each transaction updating cluster data, both in the transaction coordinator and in the nodes where the actual updates are performed. These records contain state information needed to find UNDO records for rollback, lock queues, and other purposes.

This parameter should be set to the number of records to be updated simultaneously in transactions, divided by the number of cluster data nodes. For example, in a cluster which has four data nodes and which is expected to handle 1,000,000 concurrent updates using transactions, you should set this value to 1000000 / 4 = 250000.

Read queries which set locks also cause operation records to be created. Some extra space is allocated within individual nodes to accommodate cases where the distribution is not perfect over the nodes.

When queries make use of the unique hash index, there are actually two operation records used per record in the transaction. The first record represents the read in the index table and the second handles the operation on the base table.

The default value is 32768.

This parameter actually handles two values that can be configured separately. The first of these specifies how many operation records are to be placed with the transaction coordinator. The second part specifies how many operation records are to be local to the database.

A very large transaction performed on an eight-node cluster requires as many operation records in the transaction coordinator as there are reads, updates, and deletes involved in the transaction. However, the operation records of the are spread over all eight nodes. Thus, if it is necessary to configure the system for one very large transaction, it is a good idea to configure the two parts separately. MaxNoOfConcurrentOperations will always be used to calculate the number of operation records in the transaction coordinator portion of the node.

It is also important to have an idea of the memory requirements for operation records. These consume about 1KB per record.

• MaxNoOfLocalOperations

Restart Type	node

Permitted Values	
Type	numeric
Default	UNDEFINED
Range	32-4G

By default, this parameter is calculated as $1.1 \times \texttt{MaxNoofConcurrentOperations}$. This fits systems with many simultaneous transactions, none of them being very large. If there is a need to handle one very large transaction at a time and there are many nodes, it is a good idea to override the default value by explicitly specifying this parameter.

• MaxDMLOperationsPerTransaction

Version Introduced	5.1.56-ndb	5.1.56-ndb-7.0.26, 5.1.56-ndb-7.1.15	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	4294967295	
	Range	32-4294967295	
	Permitted	Values	
	Type	numeric	
	Default	4294967295	
	Range	32-4294967295	

Added in MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.15, this parameter limits the size of a transaction. The transaction is aborted if it requires more than this many DML operations. The minimum number of operations per transaction is 32; however, you can set MaxDMLOperationsPerTransaction to 0 to disable any limitation on the number of DML operations per transaction. The maximum (and default) is 4294967295.

Transaction temporary storage. The next set of [ndbd] parameters is used to determine temporary storage when executing a statement that is part of a Cluster transaction. All records are released when the statement is completed and the cluster is waiting for the commit or rollback.

The default values for these parameters are adequate for most situations. However, users with a need to support transactions involving large numbers of rows or operations may need to increase these values to enable better parallelism in the system, whereas users whose applications require relatively small transactions can decrease the values to save memory.

• MaxNoOfConcurrentIndexOperations

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	8K	
	Range	0-4G	

For queries using a unique hash index, another temporary set of operation records is used during a query's execution phase. This parameter sets the size of that pool of records. Thus, this record is allocated only while executing a part of a query. As soon as this part has been executed, the record is released. The state needed to handle aborts and commits is handled by the normal operation records, where the pool size is set by the parameter MaxNoOfConcurrentOperations.

The default value of this parameter is 8192. Only in rare cases of extremely high parallelism using unique hash indexes should it be necessary to increase this value. Using a smaller value is possible and can save memory if the DBA is certain that a high degree of parallelism is not required for the cluster.

• MaxNoOfFiredTriggers

Restart Type node	
-------------------	--

Permitted Values	
Type	numeric
Default	4000
Range	0-4G

The default value of MaxNoOfFiredTriggers is 4000, which is sufficient for most situations. In some cases it can even be decreased if the DBA feels certain the need for parallelism in the cluster is not high.

A record is created when an operation is performed that affects a unique hash index. Inserting or deleting a record in a table with unique hash indexes or updating a column that is part of a unique hash index fires an insert or a delete in the index table. The resulting record is used to represent this index table operation while waiting for the original operation that fired it to complete. This operation is short-lived but can still require a large number of records in its pool for situations with many parallel write operations on a base table containing a set of unique hash indexes.

• TransactionBufferMemory

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1M	
	Range	1K-4G	

The memory affected by this parameter is used for tracking operations fired when updating index tables and reading unique indexes. This memory is used to store the key and column information for these operations. It is only very rarely that the value for this parameter needs to be altered from the default.

The default value for TransactionBufferMemory is 1MB.

Normal read and write operations use a similar buffer, whose usage is even more short-lived. The compile-time parameter ZATTRBUF_FILESIZE (found in ndb/src/kernel/blocks/Dbtc/Dbtc.hpp) set to 4000×128 bytes (500KB). A similar buffer for key information, ZDATABUF_FILESIZE (also in Dbtc.hpp) contains $4000 \times 16 = 62.5$ KB of buffer space. Dbtc is the module that handles transaction coordination.

Scans and buffering. There are additional <code>[ndbd]</code> parameters in the <code>Dblqh</code> module (in <code>ndb/src/kernel/blocks/Dblqh/Dblqh.hpp)</code> that affect reads and updates. These include <code>ZATTRINBUF_FILESIZE</code>, set by default to <code>10000 × 128</code> bytes (<code>1250KB</code>) and <code>ZDATABUF_FILE_SIZE</code>, set by default to <code>10000*16</code> bytes (roughly <code>156KB</code>) of buffer space. To date, there have been neither any reports from users nor any results from our own extensive tests suggesting that either of these compile-time limits should be increased.

• MaxNoOfConcurrentScans

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	256	
	Range	2–500	

This parameter is used to control the number of parallel scans that can be performed in the cluster. Each transaction coordinator can handle the number of parallel scans defined for this parameter. Each scan query is performed by scanning all partitions in parallel. Each partition scan uses a scan record in the node where the partition is located, the number of records being the value of this parameter times the number of nodes. The cluster should be able to sustain MaxNoOfConcurrentScans scans concurrently from all nodes in the cluster.

Scans are actually performed in two cases. The first of these cases occurs when no hash or ordered indexes exists to handle the query, in which case the query is executed by performing a full table scan. The second case is encountered when there is no hash index to support the query but there is an ordered index. Using the ordered index means executing a parallel range scan. The order is kept on the local partitions only, so it is necessary to perform the index scan on all partitions.

The default value of MaxNoOfConcurrentScans is 256. The maximum value is 500.

MaxNoOfLocalScans

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	UNDEFINED
	Range	32-4G

Specifies the number of local scan records if many scans are not fully parallelized. In MySQL Cluster NDB 7.2.0 and later, when the number of local scan records is not provided, it is calculated as 4 times the product of MaxNoOfConcurrentS-cans and the number of data nodes in the system. (Previously, it was calculated as the product of MaxNoOfConcurrentS-cans and the number of data nodes.) The minimum value is 32.

• BatchSizePerLocalScan

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	64	
	Range	1-992	

This parameter is used to calculate the number of lock records used to handle concurrent scan operations.

The default value is 64; this value has a strong connection to the BatchSize defined in the SQL nodes.

• LongMessageBuffer

Restart Type	node		
	Permitted	Permitted Values	
	Type	numeric	
	Default	1M	
	Range	512K-4G	
	Permitted Values		
	Type	numeric	
	Default	4M	
	Range	512K-4G	

This is an internal buffer used for passing messages within individual nodes and between nodes. In MySQL Cluster NDB 6.4.3 and earlier, the default is 1MB; beginning with MySQL Cluster NDB 7.0.4, it is 4MB.

This parameter seldom needs to be changed from the default. However, when replicating a MySQL Cluster using ndbmtd for the data nodes, you may need to increase this value to 8MB (or possibly more) to prevent data node instability, because ndbmtd uses much more of this resource than ndbd does. Beginning with MySQL Cluster NDB 7.0.13 and MySQL Cluster NDB 7.1.2, this should no longer be necessary when using ndbmtd with MySQL Cluster Replication (Bug #46914).

• MaxParallelScansPerFragment

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.0.23, 5.1.51-ndb-7.1.21	
Restart Type	node		
	Permitted Values		
	Type	numeric	
	Default	32	
	Range	1-1G	

Permitted Values	
Type	numeric
Default	32
Range	1-1G
Permitted Values	
Type	numeric
Default	256
Range	1-1G

Beginning with MySQL Cluster NDB 7.0.23 and MySQL Cluster NDB 7.1.12, it is possible to copnfigure the maximum number of parallel scans (TUP scans and TUX scans) allowed before they begin queuing for serial handling. (Previously, the maximum number of parallel scans per fragment was fixed at 32.) You can increase this to take advantage of any unused CPU when performing large number of scans in parallel and improve their performance.

Beginning with MySQL Cluster NDB 7.2.0, the default value for this parameter is increased from 32 to 256.

Memory Allocation

MaxAllocate

This is the maximum size of the memory unit to use when allocating memory for tables. In cases where NDB gives OUT OF MEMORY errors, but it is evident by examining the cluster logs or the output of DUMP 1000 (see DUMP 1000) that all available memory has not yet been used, you can increase the value of this parameter (or MaxNoOfTables, or both) to cause NDB to make sufficient memory available.

This parameter was introduced in MySQL 5.1.20, MySQL Cluster NDB 6.1.12 and MySQL Cluster NDB 6.2.3.

Logging and checkpointing. The following [ndbd] parameters control log and checkpoint behavior.

• NoOfFragmentLogFiles

Restart Type	initial, node	
	Permitted Values (>= 5.1.0)	
	Type	numeric
	Default	16
	Range	3-4G

This parameter sets the number of REDO log files for the node, and thus the amount of space allocated to REDO logging. Because the REDO log files are organized in a ring, it is extremely important that the first and last log files in the set (sometimes referred to as the "head" and "tail" log files, respectively) do not meet. When these approach one another too closely, the node begins aborting all transactions encompassing updates due to a lack of room for new log records.

A REDO log record is not removed until the required number of local checkpoints has been completed since that log record was inserted (prior to MySQL Cluster NDB 6.3.8, this was 3 local checkpoints; in later versions of MySQL Cluster, only 2 local checkpoints are necessary). Checkpointing frequency is determined by its own set of configuration parameters discussed elsewhere in this chapter.

How these parameters interact and proposals for how to configure them are discussed in Section 3.2.12, "Configuring MySQL Cluster Parameters for Local Checkpoints".

The default parameter value is 16, which by default means 16 sets of 4 16MB files for a total of 1024MB. Beginning with MySQL Cluster NDB 6.1.1, the size of the individual log files is configurable using the FragmentLogFileSize parameter. In scenarios requiring a great many updates, the value for NoOfFragmentLogFiles may need to be set as high as 300 or even higher to provide sufficient space for REDO logs.

If the checkpointing is slow and there are so many writes to the database that the log files are full and the log tail cannot be cut without jeopardizing recovery, all updating transactions are aborted with internal error code 410 (Out of log file space temporarily). This condition prevails until a checkpoint has completed and the log tail can be moved forward.

Important

This parameter cannot be changed "on the fly"; you must restart the node using <code>--initial</code>. If you wish to change this value for all data nodes in a running cluster, you can do so using a rolling node restart (using <code>--initial</code> when starting each data node).

• FragmentLogFileSize

Version Introduced	5.1.15-ndb	5.1.15-ndb-6.1.11	
Restart Type	initial, nod	initial, node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	16M	
	Range	4M-1G	

Setting this parameter enables you to control directly the size of redo log files. This can be useful in situations when MySQL Cluster is operating under a high load and it is unable to close fragment log files quickly enough before attempting to open new ones (only 2 fragment log files can be open at one time); increasing the size of the fragment log files gives the cluster more time before having to open each new fragment log file. The default value for this parameter is 16M. FragmentLogFileSize was added in MySQL Cluster NDB 6.1.11.

For more information about fragment log files, see the description for NoOfFragmentLogFiles.

• InitFragmentLogFiles

Version Introduced	5.1.29-nd	5.1.29-ndb-6.3.19	
Restart Type	initial, no	initial, node	
	Permittee	Permitted Values	
	Type	string	
	Default		
	Range	-	

By default, fragment log files are created sparsely when performing an initial start of a data node—that is, depending on the operating system and file system in use, not all bytes are necessarily written to disk. Beginning with MySQL Cluster NDB 6.3.19, it is possible to override this behavior and force all bytes to be written regardless of the platform and file system type being used by mean of this parameter.

InitFragmentLogFiles takes one of two values:

- SPARSE. Fragment log files are created sparsely. This is the default value.
- FULL. Force all bytes of the fragment log file to be written to disk.

Depending on your operating system and file system, setting InitFragmentLogFiles=FULL may help eliminate I/O errors on writes to the REDO log.

• MaxNoOfOpenFiles

Restart Type	node	
	Permitted Values (<= 5.1.15)	
	Type	numeric
	Default	40
	Range	20-4G
	Permitted	Values (>= 5.1.16)
	Type	numeric
	Default	0
	Range	20-4G

This parameter sets a ceiling on how many internal threads to allocate for open files. Any situation requiring a change in this

parameter should be reported as a bug.

The default value is 0. (Prior to MySQL 5.1.16, the default was 40.) However, the minimum value to which this parameter can be set is 20.

• InitialNoOfOpenFiles

Version Introduced	5.1.9	5.1.9	
Restart Type	node	node	
	Permitted Values (>= 5.1.9)		
	Type	numeric	
	Default	27	
	Range	20-4G	

This parameter sets the initial number of internal threads to allocate for open files.

The default value is 27.

• MaxNoOfSavedMessages

Restart Type	node	
	Permitted	Values
	Type	numeric
	Default	25
	Range	0-4G

This parameter sets the maximum number of trace files that are kept before overwriting old ones. Trace files are generated when, for whatever reason, the node crashes.

The default is 25 trace files.

• MaxLCPStartDelay

Version Introduced	5.1.32-ndb	5.1.32-ndb-6.3.23, 5.1.32-ndb-6.4.3	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	Type numeric	
	Default	0	
	Range	0-600	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-600	

In parallel data node recovery (supported in MySQL Cluster NDB 6.3.8 and later), only table data is actually copied and synchronized in parallel; synchronization of metadata such as dictionary and checkpoint information is done in a serial fashion. In addition, recovery of dictionary and checkpoint information cannot be executed in parallel with performing of local checkpoints. This means that, when starting or restarting many data nodes concurrently, data nodes may be forced to wait while a local checkpoint is performed, which can result in longer node recovery times.

Beginning with MySQL Cluster NDB 6.3.23 and MySQL Cluster NDB 6.4.3, it is possible to force a delay in the local checkpoint to permit more (and possibly all) data nodes to complete metadata synchronization; once each data node's metadata synchronization is complete, all of the data nodes can recover table data in parallel, even while the local checkpoint is being executed

To force such a delay, you can set MaxLCPStartDelay, which determines the number of seconds the cluster can wait to begin a local checkpoint while data nodes continue to synchronize metadata. This parameter should be set in the [ndbd default] section of the config. ini file, so that it is the same for all data nodes. The maximum value is 600; the default is 0.

Metadata objects. The next set of <code>[ndbd]</code> parameters defines pool sizes for metadata objects, used to define the maximum number of attributes, tables, indexes, and trigger objects used by indexes, events, and replication between clusters. Note that these act merely as "suggestions" to the cluster, and any that are not specified revert to the default values shown.

• MaxNoOfAttributes

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	1000
	Range	32-4G

This parameter sets a suggested maximum number of attributes that can be defined in the cluster; like MaxNoOfTables, it is not intended to function as a hard upper limit.

Prior to MySQL Cluster NDB 6.3.45, MySQL Cluster NDB 7.0.26, and MySQL Cluster NDB 7.1.15, this parameter was sometimes treated as a hard limit for certain operations. This caused problems with MySQL Cluster Replication, when it was possible to create more tables than could be replicated, and sometimes led to confusion when it was possible (or not possible, depending on the circumstances) to create more than MaxNoOfAttributes attributes. (Bug #61684)

The default value is 1000, with the minimum possible value being 32. The maximum is 4294967039. Each attribute consumes around 200 bytes of storage per node due to the fact that all metadata is fully replicated on the servers.

When setting MaxNoOfAttributes, it is important to prepare in advance for any ALTER TABLE statements that you might want to perform in the future. This is due to the fact, during the execution of ALTER TABLE on a Cluster table, 3 times the number of attributes as in the original table are used, and a good practice is to permit double this amount. For example, if the MySQL Cluster table having the greatest number of attributes (greatest_number_of_attributes) has 100 attributes, a good starting point for the value of MaxNoOfAttributes would be 6 * greatest_number_of_attributes = 600

You should also estimate the average number of attributes per table and multiply this by MaxNoOfTables. If this value is larger than the value obtained in the previous paragraph, you should use the larger value instead.

Assuming that you can create all desired tables without any problems, you should also verify that this number is sufficient by trying an actual ALTER TABLE after configuring the parameter. If this is not successful, increase MaxNoOfAttributes by another multiple of MaxNoOfTables and test it again.

• MaxNoOfTables

Restart Type	node	
	Permitted	Values
	Type	numeric
	Default	128
	Range	8-20320

A table object is allocated for each table and for each unique hash index in the cluster. This parameter sets a suggested maximum number of table objects for the cluster as a whole; like MaxNoOfAttributes, it is not intended to function as a hard upper limit.

Prior to MySQL Cluster NDB 6.3.45, MySQL Cluster NDB 7.0.26, and MySQL Cluster NDB 7.1.15, this parameter was sometimes treated as a hard limit for certain operations. This caused problems with MySQL Cluster Replication, when it was possible to create more tables than could be replicated, and sometimes led to confusion when it was possible (or not possible, depending on the circumstances) to create more than MaxNoOfTables tables.

For each attribute that has a BLOB data type an extra table is used to store most of the BLOB data. These tables also must be taken into account when defining the total number of tables.

The default value of this parameter is 128. The minimum is 8 and the maximum is 20320. Each table object consumes approximately 20KB per node.

Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not

exceed $2^{32} - 2(4294967294)$.

• MaxNoOfOrderedIndexes

Restart Type	node	node	
	Permitted	Values	
	Type	numeric	
	Default	128	
	Range	0-4G	

For each ordered index in the cluster, an object is allocated describing what is being indexed and its storage segments. By default, each index so defined also defines an ordered index. Each unique index and primary key has both an ordered index and a hash index. MaxNoOfOrderedIndexes sets the total number of hash indexes that can be in use in the system at any one time.

The default value of this parameter is 128. Each hash index object consumes approximately 10KB of data per node.

Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not exceed $2^{32} - 2$ (4294967294).

• MaxNoOfUniqueHashIndexes

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	64
	Range	0-4G

For each unique index that is not a primary key, a special table is allocated that maps the unique key to the primary key of the indexed table. By default, an ordered index is also defined for each unique index. To prevent this, you must specify the USING HASH option when defining the unique index.

The default value is 64. Each index consumes approximately 15KB per node.

Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not exceed $2^{32} - 2$ (4294967294).

• MaxNoOfTriggers

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	768
	Range	0-4G

Internal update, insert, and delete triggers are allocated for each unique hash index. (This means that three triggers are created for each unique hash index.) However, an *ordered* index requires only a single trigger object. Backups also use three trigger objects for each normal table in the cluster.

Replication between clusters also makes use of internal triggers.

This parameter sets the maximum number of trigger objects in the cluster.

The default value is 768.

• MaxNoOfIndexes

This parameter is deprecated in MySQL Cluster 5.1 and later; you should use MaxNoOfOrderedIndexes and MaxNoOfUniqueHashIndexes instead.

This parameter is used only by unique hash indexes. There needs to be one record in this pool for each unique hash index defined in the cluster.

The default value of this parameter is 128.

• MaxNoOfSubscriptions

Version Introduced	5.1.23-ndb	5.1.23-ndb-6.2.10, 5.1.23-ndb-6.3.7	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	

Each NDB table in a MySQL Cluster requires a subscription in the NDB kernel. For some NDB API applications, it may be necessary or desirable to change this parameter, which became available in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7. However, for normal usage with MySQL servers acting as SQL nodes, there is not any need to do so.

The default value for MaxNoOfSubscriptions is 0, which is treated as equal to MaxNoOfTables.

• MaxNoOfSubscribers

Version Introduced	5.1.23-ndb-	5.1.23-ndb-6.2.10, 5.1.23-ndb-6.3.7	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	

This parameter, added in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7, is of interest only when using MySQL Cluster Replication. The default value is 0, which is treated as 2 * MaxNoOfTables; that is, there is one subscription per NDB table for each of two MySQL servers (one acting as the replication master and the other as the slave).

When using circular replication, multi-master replcation, and other replication setups involving more than 2 MySQL servers, you should increase this parameter to the number of mysqld processes included in replication (this is often, but not always, the same as the number of clusters). For example, if you have a circular replication setup using three MySQL Clusters, with one mysqld attached to each cluster, and each of these mysqld processes acts as a master and as a slave, you should set MaxNoOfSubscribers equal to 3 * MaxNoOfTables.

For more information, see Chapter 6, MySQL Cluster Replication.

MaxNoOfConcurrentSubOperations

Version Introduced	5.1.23-ndb-6.2.10, 5.1.23-ndb-6.3.7	
Restart Type	node	

Permitted	Values
Type	numeric
Default	256
Range	0-4G
Permitted Values	
Type	numeric
Default	256
Range	0-4G

This parameter sets a ceiling on the number of operations that can be performed by all API nodes in the cluster at one time. The default value (256) is sufficient for normal operations, and might need to be adjusted only in scenarios where there are a great many API nodes each performing a high volume of operations concurrently.

This parameter was added in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7.

Boolean parameters. The behavior of data nodes is also affected by a set of [ndbd] parameters taking on boolean values. These parameters can each be specified as TRUE by setting them equal to 1 or Y, and as FALSE by setting them equal to 0 or N.

• LockPagesInMainMemory

Restart Type	node	
	Permitted	Values (>= 5.1.0, <= 5.1.14)
	Type	boolean
	Default	0
	Range	0-1
	Permitted Values (>= 5.1.15)	
	Type	numeric
	Default	0
	Range	0-2

For a number of operating systems, including Solaris and Linux, it is possible to lock a process into memory and so avoid any swapping to disk. This can be used to help guarantee the cluster's real-time characteristics.

Beginning with MySQL 5.1.15 and MySQL Cluster NDB 6.1.1, this parameter takes one of the integer values 0, 1, or 2, which act as follows:

- 0: Disables locking. This is the default value.
- 1: Performs the lock after allocating memory for the process.
- 2: Performs the lock before memory for the process is allocated.

Previously, this parameter was a Boolean. 0 or false was the default setting, and disabled locking. 1 or true enabled locking of the process after its memory was allocated.

Important

Beginning with MySQL 5.1.15 and MySQL Cluster NDB 6.1.1, it is no longer possible to use true or false for the value of this parameter; when upgrading from a previous version, you must change the value to 0, 1, or 2.

Prior to MySQL Cluster NDB 6.3.31 and MySQL Cluster NDB 7.0.11, setting this parameter did not cause the stated memory to be allocated when the node was started, but rather only when the memory was used by the data node process for other reasons. (Bug #37430)

Note

If the operating system is not configured to permit unprivileged users to lock pages, then the data node process making use of this parameter may have to be run as system root. (LockPagesInMainMemory uses the mlockall

function. From Linux kernel 2.6.9, unprivileged users can lock memory as limited by max locked memory. For more information, see ulimit -1 and http://linux.die.net/man/2/mlock).

• StopOnError

Restart Type	node	node	
	Permitted Values		
	Type	boolean	
	Default	true	
	Range	-	

This parameter specifies whether an ndbd process should exit or perform an automatic restart when an error condition is encountered.

This feature is enabled by default.

Diskless

Restart Type	initial, system	
	Permitted Values	
	Type	boolean
	Default	0
	Range	0-1

It is possible to specify MySQL Cluster tables as *diskless*, meaning that tables are not checkpointed to disk and that no logging occurs. Such tables exist only in main memory. A consequence of using diskless tables is that neither the tables nor the records in those tables survive a crash. However, when operating in diskless mode, it is possible to run ndbd on a diskless computer.

Important

This feature causes the *entire* cluster to operate in diskless mode.

When this feature is enabled, Cluster online backup is disabled. In addition, a partial start of the cluster is not possible.

Diskless is disabled by default.

ODirect

Version Introduced	5.1.15-ndb-6.1.11, 5.1.19-ndb-6.2.3, 5.1.19-ndb-6.3.0		
Restart Type	node		
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-1	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-1	
	Permitted	Values	
	Type	numeric	
	Default	0	
	Range	0-1	

Enabling this parameter causes NDB to attempt using O_DIRECT writes for LCP, backups, and redo logs, often lowering kswapd and CPU usage. When using MySQL Cluster on Linux, enable ODirect if you are using a 2.6 or later kernel.

This parameter was added in MySQL 5.1.20, MySQL Cluster NDB 6.1.11, MySQL Cluster NDB 6.2.3, and MySQL Cluster

NDB 6.3.0.

ODirect is disabled by default.

• RestartOnErrorInsert

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	2	
	Range	0-4	

This feature is accessible only when building the debug version where it is possible to insert errors in the execution of individual blocks of code as part of testing.

This feature is disabled by default.

• CompressedBackup

Version Introduced	5.1.23-ndb	5.1.23-ndb-6.3.7	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	boolean	
	Default	false	
	Range	-	

Setting this parameter to 1 causes backup files to be compressed. The compression used is equivalent to gzip --fast, and can save 50% or more of the space required on the data node to store uncompressed backup files. Compressed backups can be enabled for individual data nodes, or for all data nodes (by setting this parameter in the [ndbd default] section of the config.ini file).

Important

You cannot restore a compressed backup to a cluster running a MySQL version that does not support this feature.

The default value is 0 (disabled).

This parameter was introduced in MySQL Cluster NDB 6.3.7.

• CompressedLCP

Version Introduced	5.1.23-ndb-	5.1.23-ndb-6.3.7	
Restart Type	node	node	
	Permitted Values		
	Type	boolean	
	Default	false	
	Range	-	

Setting this parameter to 1 causes local checkpoint files to be compressed. The compression used is equivalent to gzip --fast, and can save 50% or more of the space required on the data node to store uncompressed checkpoint files. Compressed LCPs can be enabled for individual data nodes, or for all data nodes (by setting this parameter in the [ndbd default] section of the config.ini file).

Important

You cannot restore a compressed local checkpoint to a cluster running a MySQL version that does not support this feature.

The default value is 0 (disabled).

This parameter was introduced in MySQL Cluster NDB 6.3.7.

Controlling Timeouts, Intervals, and Disk Paging

There are a number of [ndbd] parameters specifying timeouts and intervals between various actions in Cluster data nodes. Most of the timeout values are specified in milliseconds. Any exceptions to this are mentioned where applicable.

• TimeBetweenWatchDogCheck

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	6000	
	Range	70-4G	

To prevent the main thread from getting stuck in an endless loop at some point, a "watchdog" thread checks the main thread. This parameter specifies the number of milliseconds between checks. If the process remains in the same state after three checks, the watchdog thread terminates it.

This parameter can easily be changed for purposes of experimentation or to adapt to local conditions. It can be specified on a per-node basis although there seems to be little reason for doing so.

The default timeout is 6000 milliseconds (6 seconds).

• TimeBetweenWatchDogCheckInitial

Version Introduced	5.1.20	5.1.20	
Restart Type	node	node	
	Permitted Values (>= 5.1.20)		
	Type	numeric	
	Default	6000	
	Range	70-4G	

This is similar to the TimeBetweenWatchDogCheck parameter, except that TimeBetweenWatchDogCheckInitial controls the amount of time that passes between execution checks inside a database node in the early start phases during which memory is allocated.

The default timeout is 6000 milliseconds (6 seconds).

This parameter was added in MySQL 5.1.20.

StartPartialTimeout

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	30000
	Range	0-4G

This parameter specifies how long the Cluster waits for all data nodes to come up before the cluster initialization routine is invoked. This timeout is used to avoid a partial Cluster startup whenever possible.

This parameter is overridden when performing an initial start or initial restart of the cluster.

The default value is 30000 milliseconds (30 seconds). 0 disables the timeout, in which case the cluster may start only if all nodes are available.

StartPartitionedTimeout

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	60000	
	Range	0-4G	

If the cluster is ready to start after waiting for StartPartialTimeout milliseconds but is still possibly in a partitioned state, the cluster waits until this timeout has also passed. If StartPartitionedTimeout is set to 0, the cluster waits indefinitely.

This parameter is overridden when performing an initial start or initial restart of the cluster.

The default timeout is 60000 milliseconds (60 seconds).

• StartFailureTimeout

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	0
	Range	0-4G

If a data node has not completed its startup sequence within the time specified by this parameter, the node startup fails. Setting this parameter to 0 (the default value) means that no data node timeout is applied.

For nonzero values, this parameter is measured in milliseconds. For data nodes containing extremely large amounts of data, this parameter should be increased. For example, in the case of a data node containing several gigabytes of data, a period as long as 10–15 minutes (that is, 600000 to 1000000 milliseconds) might be required to perform a node restart.

• StartNoNodeGroupTimeout

Version Introduced	5.1.56-ndb	5.1.56-ndb-7.0.24,5.1.56-ndb-7.1.13	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	15000	
	Range	0-4294967039	

When a data node is configured with Nodegroup = 65536, is regarded as not being assigned to any node group. When that is done, the cluster waits StartNoNodegroupTimeout milliseconds, then treats such nodes as though they had been added to the list passed to the --nowait-nodes option, and starts. The default value is 15000 (that is, the management server waits 15 seconds). Setting this parameter equal to 0 means that the cluster waits indefinitely.

StartNoNodegroupTimeout must be the same for all data nodes in the cluster; for this reason, you should always set it in the [ndbd default] section of the config.ini file, rather than for individual data nodes.

This parameter was added in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13. See Section 5.12, "Adding MySQL Cluster Data Nodes Online", for more information.

HeartbeatIntervalDbDb

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	1500
	Range	10-4G

One of the primary methods of discovering failed nodes is by the use of heartbeats. This parameter states how often heartbeat signals are sent and how often to expect to receive them. After missing three heartbeat intervals in a row, the node is declared dead. Thus, the maximum time for discovering a failure through the heartbeat mechanism is four times the heartbeat interval.

In MySQL Cluster NDB 7.2.0 and later, the default heartbeat interval is 5000 milliseconds (5 seconds). Previously, the default was 1500 milliseconds (1.5 seconds). This parameter must not be changed drastically and should not vary widely between nodes. If one node uses 5000 milliseconds and the node watching it uses 1000 milliseconds, obviously the node will be declared dead very quickly. This parameter can be changed during an online software upgrade, but only in small increments.

See also Network communication and latency.

• HeartbeatIntervalDbApi

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1500	
	Range	100-4G	

Each data node sends heartbeat signals to each MySQL server (SQL node) to ensure that it remains in contact. If a MySQL server fails to send a heartbeat in time it is declared "dead," in which case all ongoing transactions are completed and all resources released. The SQL node cannot reconnect until all activities initiated by the previous MySQL instance have been completed. The three-heartbeat criteria for this determination are the same as described for HeartbeatIntervalDbDb.

The default interval is 1500 milliseconds (1.5 seconds). This interval can vary between individual data nodes because each data node watches the MySQL servers connected to it, independently of all other data nodes.

For more information, see Network communication and latency.

• HeartbeatOrder

Version Introduced	5.1.47-ndb-	5.1.47-ndb-6.3.35, 5.1.47-ndb-7.0.16, 5.1.47-ndb-7.1.5	
Restart Type	system	system	
	Permitted Values Type numeric Default 0		
	Range	0-65535	

Data nodes send heartbeats to one another in a circular fashion whereby each data node monitors the previous one. If a heartbeat is not detected by a given data node, this node declares the previous data node in the circle "dead" (that is, no longer accessible by the cluster). The determination that a data node is dead is done globally; in other words; once a data node is declared dead, it is regarded as such by all nodes in the cluster.

It is possible for heartbeats between data nodes residing on different hosts to be too slow compared to heartbeats between other pairs of nodes (for example, due to a very low heartbeat interval or temporary connection problem), such that a data node is declared dead, even though the node can still function as part of the cluster.

In this type of situation, it may be that the order in which heartbeats are transmitted between data nodes makes a difference as to whether or not a particular data node is declared dead. If this declaration occurs unnecessarily, this can in turn lead to the unnecessary loss of a node group and as thus to a failure of the cluster.

Consider a setup where there are 4 data nodes A, B, C, and D running on 2 host computers host1 and host2, and that these data nodes make up 2 node groups, as shown in the following table:

	host1	host2
Node Group 0:	Node A	Node B
Node Group 1:	Node C	Node D

Suppose the heartbeats are transmitted in the order A->B->C->D->A. In this case, the loss of the heartbeat between the hosts causes node B to declare node A dead and node C to declare node B dead. This results in loss of Node Group 0, and so the

cluster fails. On the other hand, if the order of transmission is A->B->D->C->A (and all other conditions remain as previously stated), the loss of the heartbeat causes nodes A and D to be declared dead; in this case, each node group has one surviving node, and the cluster survives.

Priot to MySQL Cluster NDB 6.3.35, MySQL Cluster NDB 7.0.16, and MySQL Cluster NDB 7.1.5, the order of of heartbeat transmission between data nodes was always automatically determined by NDB. However, beginning with these versions, the Heartbeat order configuration parameter makes the order of heartbeat transmission user-configurable.

The default value for HeartbeatOrder is zero; allowing the default value to be used on all data nodes causes the order of heartbeat transmission to be determined by NDB. If this parameter is used, it must be set to a nonzero value (maximum 65535) for every data node in the cluster, and this value must be unique for each data node; this causes the heartbeat transmission to proceed from data node to data node in the order of their HeartbeatOrder values from lowest to highest (and then directly from the data node having the highest HeartbeatOrder to the data node having the lowest value, to complete the circle). The values need not be consecutive; for example, to force the heartbeat transmission order A->B->D->C->A in the scenario outlined previously, you could set the HeartbeatOrder values as shown here:

Node	HeartbeatOrder
A	10
В	20
С	30
D	25

To use this parameter to change the heartbeat transmission order in a running MySQL Cluster, you must first set Heartbeat-Order for each data node in the cluster in the global configuration (config.ini) file (or files). To cause the change to take effect, you must perform either of the following:

- A complete shutdown and restart of the entire cluster.
- 2 rolling restarts of the cluster in succession. All nodes must be restarted in the same order in both rolling restarts.

You can use DUMP 908 to observe the effect of this parameter in the data node logs.

• TimeBetweenLocalCheckpoints

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	20	
	Range	0-31	

This parameter is an exception in that it does not specify a time to wait before starting a new local checkpoint; rather, it is used to ensure that local checkpoints are not performed in a cluster where relatively few updates are taking place. In most clusters with high update rates, it is likely that a new local checkpoint is started immediately after the previous one has been completed.

The size of all write operations executed since the start of the previous local checkpoints is added. This parameter is also exceptional in that it is specified as the base-2 logarithm of the number of 4-byte words, so that the default value 20 means 4MB (4×2^{20}) of write operations, 21 would mean 8MB, and so on up to a maximum value of 31, which equates to 8GB of write operations.

All the write operations in the cluster are added together. Setting TimeBetweenLocalCheckpoints to 6 or less means that local checkpoints will be executed continuously without pause, independent of the cluster's workload.

• TimeBetweenGlobalCheckpoints

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	2000	
	Range	10-32000	

When a transaction is committed, it is committed in main memory in all nodes on which the data is mirrored. However, transaction log records are not flushed to disk as part of the commit. The reasoning behind this behavior is that having the transaction safely committed on at least two autonomous host machines should meet reasonable standards for durability.

It is also important to ensure that even the worst of cases—a complete crash of the cluster—is handled properly. To guarantee that this happens, all transactions taking place within a given interval are put into a global checkpoint, which can be thought of as a set of committed transactions that has been flushed to disk. In other words, as part of the commit process, a transaction is placed in a global checkpoint group. Later, this group's log records are flushed to disk, and then the entire group of transactions is safely committed to disk on all computers in the cluster.

This parameter defines the interval between global checkpoints. The default is 2000 milliseconds.

• TimeBetweenEpochs

Version Introduced	5.1.22-ndb-6.2.5, 5.1.22-ndb-6.3.2		
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	100	
	Range	0-32000	
	Permitted	Permitted Values	
	Type	numeric	
	Default	100	
	Range	0-32000	

This parameter defines the interval between synchronisation epochs for MySQL Cluster Replication. The default value is 100 milliseconds.

TimeBetweenEpochs is part of the implementation of "micro-GCPs", which can be used to improve the performance of MySQL Cluster Replication. This parameter was introduced in MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2.

• TimeBetweenEpochsTimeout

Version Introduced	5.1.22-ndb-6.2.7, 5.1.22-ndb-6.3.4	
Restart Type	node	
	Permitted	Values
	Type	numeric
	Default	4000
	Range	0-32000
	Permitted	Values
	Type	numeric
	Default	4000
	Range	0-32000
	Permitted Values	
	Type	numeric
	Default	4000
	Range	0-32000
	Permitted Values	
	Type	numeric
	Default	4000
	Range	0-256000
	Permitted Values	
	Type	numeric
	Default	4000
	Range	0-32000

Permitted Values	
Type	numeric
Default	4000
Range	0-256000
Permitted Values	
Type	numeric
Default	0
Range	0-256000

This parameter defines a timeout for synchronization epochs for MySQL Cluster Replication. If a node fails to participate in a global checkpoint within the time determined by this parameter, the node is shut down. In MySQL Cluster NDB 7.2.0 and later, the default value is 0; in other words, the timeout is disabled. This represents a change from previous versions of MySQL Cluster, in which the default value was 4000 milliseconds (4 seconds).

TimeBetweenEpochsTimeout is part of the implementation of "micro-GCPs", which can be used to improve the performance of MySQL Cluster Replication. This parameter was introduced in MySQL Cluster NDB 6.2.7 and MySQL Cluster NDB 6.3.4.

The following changes regarding this parameter were made in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10:

- The maximum possible value for this parameter was increased from 32000 milliseconds to 256000 milliseconds.
- · Setting this parameter to zero now has the effect of disabling GCP stops caused by save timeouts, commit timeouts, or both.
- The current value of this parameter and a warning are now written to the cluster log whenever a GCP save takes longer than 1 minute or a GCP save takes longer than 10 seconds.
- MaxBufferedEpochs

Version Introduced	5.1.23-ndb-	5.1.23-ndb-6.2.14	
Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	100	
	Range	0-100000	

The number of unprocessed epochs by which a subscribing node can lag behind. Exceeding this number causes a lagging subscriber to be disconnected.

The default value of 100 is sufficient for most normal operations. If a subscribing node does lag enough to cause disconnections, it is usually due to network or scheduling issues with regard to processes or threads. (In rare circumstances, the problem may be due to a bug in the NDB client.) It may be desirable to set the value lower than the default when epochs are longer.

Disconnection prevents client issues from affecting the data node service, running out of memory to buffer data, and eventually shutting down. Instead, only the client is affected as a result of the disconnect (by, for example gap events in the binlog), forcing the client to reconnect or restart the process.

• TimeBetweenInactiveTransactionAbortCheck

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	1000	
	Range	1000-4G	

Timeout handling is performed by checking a timer on each transaction once for every interval specified by this parameter. Thus, if this parameter is set to 1000 milliseconds, every transaction will be checked for timing out once per second.

The default value is 1000 milliseconds (1 second).

• TransactionInactiveTimeout

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	4G	
	Range	0-4G	

This parameter states the maximum time that is permitted to lapse between operations in the same transaction before the transaction is aborted.

The default for this parameter is 4G (also the maximum). For a real-time database that needs to ensure that no transaction keeps locks for too long, this parameter should be set to a relatively small value. The unit is milliseconds.

• TransactionDeadlockDetectionTimeout

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	1200	
	Range	50-4G	

When a node executes a query involving a transaction, the node waits for the other nodes in the cluster to respond before continuing. A failure to respond can occur for any of the following reasons:

- The node is "dead"
- The operation has entered a lock queue
- The node requested to perform the action could be heavily overloaded.

This timeout parameter states how long the transaction coordinator waits for query execution by another node before aborting the transaction, and is important for both node failure handling and deadlock detection. In MySQL 5.1.10 and earlier versions, setting it too high could cause undesirable behavior in situations involving deadlocks and node failure. Beginning with MySQL 5.1.11, active transactions occurring during node failures are actively aborted by the MySQL Cluster Transaction Coordinator, and so high settings are no longer an issue with this parameter.

The default timeout value is 1200 milliseconds (1.2 seconds).

Prior to MySQL Cluster NDB versions 6.2.18, 6.3.24, and 7.0.5, the effective minimum for this parameter was 100 milliseconds. (Bug #44099) Beginning with these versions, the actual minimum is 50 milliseconds.

DiskSyncSize

Version Introduced	5.1.12	5.1.12	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	4M	
	Range	32K-4G	

This is the maximum number of bytes to store before flushing data to a local checkpoint file. This is done to prevent write buffering, which can impede performance significantly. This parameter is *not* intended to take the place of TimeBetweenLocalCheckpoints.

Note

When ODirect is enabled, it is not necessary to set DiskSyncSize; in fact, in such cases its value is simply ig-

nored.

The default value is 4M (4 megabytes).

This parameter was added in MySQL 5.1.12.

• DiskCheckpointSpeed

Version Introduced	5.1.12	5.1.12	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	10M	
	Range	1M-4G	

The amount of data,in bytes per second, that is sent to disk during a local checkpoint. This allocation is shared by DML operations and backups (but not backup logging), which means that backups started during times of intensive DML may be impaired by flooding of the redo log buffer and may fail altogether if the contention is sufficiently severe.

The default value is 10M (10 megabytes per second).

This parameter was added in MySQL 5.1.12.

• DiskCheckpointSpeedInRestart

Version Introduced	5.1.12	5.1.12	
Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	100M	
	Range	1M-4G	

The amount of data,in bytes per second, that is sent to disk during a local checkpoint as part of a restart operation.

The default value is 100M (100 megabytes per second).

This parameter was added in MySQL 5.1.12.

• NoOfDiskPagesToDiskAfterRestartTUP

Version Removed	5.1.6	
Restart Type	node	
]	Permitted Values (<= 5.1.6) Type numeric Default 40	
7		
	Range	1-4G

When executing a local checkpoint, the algorithm flushes all data pages to disk. Merely doing so as quickly as possible without any moderation is likely to impose excessive loads on processors, networks, and disks. To control the write speed, this parameter specifies how many pages per 100 milliseconds are to be written. In this context, a "page" is defined as 8KB. This parameter is specified in units of 80KB per second, so setting NoOfDiskPagesToDiskAfterRestartTUP to a value of 20 entails writing 1.6MB in data pages to disk each second during a local checkpoint. This value includes the writing of UNDO log records for data pages. That is, this parameter handles the limitation of writes from data memory. (See the entry for IndexMemory for information about index pages.)

In short, this parameter specifies how quickly to execute local checkpoints. It operates in conjunction with NoOfFragment-LogFiles, DataMemory, and IndexMemory.

For more information about the interaction between these parameters and possible strategies for choosing appropriate values for them, see Section 3.2.12, "Configuring MySQL Cluster Parameters for Local Checkpoints".

The default value is 40 (3.2MB of data pages per second).

Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use DiskCheckpointSpeed and DiskSyncSize instead.

NoOfDiskPagesToDiskAfterRestartACC

Version Removed	5.1.6	5.1.6	
Restart Type	node	node	
	Permitted Values (<= 5.1.6) Type numeric		
	Default	20	
	Range	1-4G	

This parameter uses the same units as NoOfDiskPagesToDiskAfterRestartTUP and acts in a similar fashion, but limits the speed of writing index pages from index memory.

The default value of this parameter is 20 (1.6MB of index memory pages per second).

Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use DiskCheckpointSpeed and DiskSyncSize.

• NoOfDiskPagesToDiskDuringRestartTUP (DEPRECATED)

Version Removed	5.1.6	5.1.6	
Restart Type	node	node	
	Permitted	Permitted Values (<= 5.1.6)	
	Type	numeric	
	Default	40	
	Range	1-4G	

This parameter is used in a fashion similar to NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC, only it does so with regard to local checkpoints executed in the node when a node is restarting. A local checkpoint is always performed as part of all node restarts. During a node restart it is possible to write to disk at a higher speed than at other times, because fewer activities are being performed in the node.

This parameter covers pages written from data memory.

The default value is 40 (3.2MB per second).

Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use DiskCheckpoint-SpeedInRestart and DiskSyncSize.

NoOfDiskPagesToDiskDuringRestartACC (DEPRECATED)

Version Removed	5.1.6	5.1.6	
Restart Type	node	node	
	Permitted Values (<= 5.1.6) Type numeric		
	Default	20	
	Range	1-4G	

Controls the number of index memory pages that can be written to disk during the local checkpoint phase of a node restart.

As with NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC, values for this parameter are expressed in terms of 8KB pages written per 100 milliseconds (80KB/second).

The default value is 20 (1.6MB per second).

Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use DiskCheckpointSpeedIn-Restart and DiskSyncSize.

• ArbitrationTimeout

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	3000	
	Range	10-4G	

This parameter specifies how long data nodes wait for a response from the arbitrator to an arbitration message. If this is exceeded, the network is assumed to have split.

In MySQL Cluster NDB 7.2.0 and later, the default value is 7500 milliseconds (7.5 seconds). Previously, this was 3000 milliseconds (3 seconds).

• Arbitration

Version Introduced	5.1.35-ndb-	5.1.35-ndb-7.0.7	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	enumeration	
	Default	Default	
	, aracs	Default Disabled	
		WaitExternal	

The Arbitration parameter, added in MySQL Cluster NDB 7.0.7, enables a choice of arbitration schemes, corresponding to one of 3 possible values for this parameter:

- **Default.** This enables arbitration to proceed normally, as determined by the ArbitrationRank settings for the management and API nodes. This is the default value.
- **Disabled.** Previously, it was possible to disable arbitration only by setting ArbitrationRank to 0 on all management and API nodes. Now, you can now use Arbitration = Disabled in the [ndbd default] section of the config.ini file to accomplish this task. In this case, any ArbitrationRank settings are ignored.
- WaitExternal. The Arbitration parameter also makes it possible to configure arbitration in such a way that the cluster waits until after the time determined by ArbitrationTimeout has passed for an external cluster manager application to perform arbitration instead of handling arbitration internally. This can be done by setting Arbitration = WaitExternal in the [ndbd default] section of the config.ini file. For best results with the WaitExternal setting, it is recommended that ArbitrationTimeout be 2 times as long as the interval required by the external cluster manager to perform arbitration.

Important

This parameter should be used only in the [ndbd default] section of the cluster configuration file. The behavior of the cluster is unspecified when Arbitration is set to different values for individual data nodes.

Buffering and logging. Several [ndbd] configuration parameters enable the advanced user to have more control over the resources used by node processes and to adjust various buffer sizes at need.

These buffers are used as front ends to the file system when writing log records to disk. If the node is running in diskless mode, these parameters can be set to their minimum values without penalty due to the fact that disk writes are "faked" by the NDB storage engine's file system abstraction layer.

• UndoIndexBuffer

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	2M	
	Range	1M-4G	

The UNDO index buffer, whose size is set by this parameter, is used during local checkpoints. The NDB storage engine uses a recovery scheme based on checkpoint consistency in conjunction with an operational REDO log. To produce a consistent checkpoint without blocking the entire system for writes, UNDO logging is done while performing the local checkpoint. UNDO logging is activated on a single table fragment at a time. This optimization is possible because tables are stored entirely in main memory.

The UNDO index buffer is used for the updates on the primary key hash index. Inserts and deletes rearrange the hash index; the NDB storage engine writes UNDO log records that map all physical changes to an index page so that they can be undone at system restart. It also logs all active insert operations for each fragment at the start of a local checkpoint.

Reads and updates set lock bits and update a header in the hash index entry. These changes are handled by the page-writing algorithm to ensure that these operations need no UNDO logging.

This buffer is 2MB by default. The minimum value is 1MB, which is sufficient for most applications. For applications doing extremely large or numerous inserts and deletes together with large transactions and large primary keys, it may be necessary to increase the size of this buffer. If this buffer is too small, the NDB storage engine issues internal error code 677 (Index UNDO buffers overloaded).

Important

It is not safe to decrease the value of this parameter during a rolling restart.

UndoDataBuffer

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	16M	
	Range	1M-4G	

This parameter sets the size of the UNDO data buffer, which performs a function similar to that of the UNDO index buffer, except the UNDO data buffer is used with regard to data memory rather than index memory. This buffer is used during the local checkpoint phase of a fragment for inserts, deletes, and updates.

Because UNDO log entries tend to grow larger as more operations are logged, this buffer is also larger than its index memory counterpart, with a default value of 16MB.

This amount of memory may be unnecessarily large for some applications. In such cases, it is possible to decrease this size to a minimum of 1MB.

It is rarely necessary to increase the size of this buffer. If there is such a need, it is a good idea to check whether the disks can actually handle the load caused by database update activity. A lack of sufficient disk space cannot be overcome by increasing the size of this buffer.

If this buffer is too small and gets congested, the NDB storage engine issues internal error code 891 (DATA UNDO BUFFERS OVERLOADED).

Important

It is not safe to decrease the value of this parameter during a rolling restart.

• RedoBuffer

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	8M	
	Range	1M-4G	

All update activities also need to be logged. The REDO log makes it possible to replay these updates whenever the system is restarted. The NDB recovery algorithm uses a "fuzzy" checkpoint of the data together with the UNDO log, and then applies the REDO log to play back all changes up to the restoration point.

RedoBuffer sets the size of the buffer in which the REDO log is written. In MySQL Cluster NDB 6.4.3 and earlier, the default value is 8MB; beginning with MySQL Cluster NDB 7.0.4, the default is 32MB. The minimum value is 1MB.

If this buffer is too small, the NDB storage engine issues error code 1221 (REDO LOG BUFFERS OVERLOADED). For this reason, you should exercise care if you attempt to decrease the value of RedoBuffer as part of an online change in the cluster's configuration.

Controlling log messages. In managing the cluster, it is very important to be able to control the number of log messages sent for various event types to stdout. For each event category, there are 16 possible event levels (numbered 0 through 15). Setting event reporting for a given event category to level 15 means all event reports in that category are sent to stdout; setting it to 0 means that there will be no event reports made in that category.

By default, only the startup message is sent to stdout, with the remaining event reporting level defaults being set to 0. The reason for this is that these messages are also sent to the management server's cluster log.

An analogous set of levels can be set for the management client to determine which event levels to record in the cluster log.

• LogLevelStartup

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1	
	Range	0-15	

The reporting level for events generated during startup of the process.

The default level is 1.

• LogLevelShutdown

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-15	

The reporting level for events generated as part of graceful shutdown of a node.

The default level is 0.

LogLevelStatistic

Restart Type	node

Permitt	ed Values
Туре	numeric
Default	0
Range	0-15

The reporting level for statistical events such as number of primary key reads, number of updates, number of inserts, information relating to buffer usage, and so on.

The default level is 0.

• LogLevelCheckpoint

Restart Type	initial, node	
	Permitted Values	
	Type	numeric
	Default	0
	Range	0-15

The reporting level for events generated by local and global checkpoints.

The default level is 0.

• LogLevelNodeRestart

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	0
	Range	0-15

The reporting level for events generated during node restart.

The default level is 0.

• LogLevelConnection

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	0
	Range	0-15

The reporting level for events generated by connections between cluster nodes.

The default level is 0.

• LogLevelError

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-15	

The reporting level for events generated by errors and warnings by the cluster as a whole. These errors do not cause any node failure but are still considered worth reporting.

The default level is 0.

• LogLevelCongestion

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-15	

The reporting level for events generated by congestion. These errors do not cause node failure but are still considered worth reporting.

The default level is 0.

• LogLevelInfo

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-15	

The reporting level for events generated for information about the general state of the cluster.

The default level is 0.

• MemReportFrequency

Version Introduced	5.1.14-ndb-6.1.0, 5.1.16	
Restart Type	node	
	Permitted Values (>= 5.1.16) Type numeric Default 0 Range 0-4G	

This parameter controls how often data node memory usage reports are recorded in the cluster log; it is an integer value representing the number of seconds between reports.

Each data node's data memory and index memory usage is logged as both a percentage and a number of 32 KB pages of the DataMemory and IndexMemory, respectively, set in the config.ini file. For example, if DataMemory is equal to 100 MB, and a given data node is using 50 MB for data memory storage, the corresponding line in the cluster log might look like this:

```
2006-12-24 01:18:16 [MgmSrvr] INFO -- Node 2: Data usage is 50%(1280 32K pages of total 2560)
```

MemReportFrequency is not a required parameter. If used, it can be set for all cluster data nodes in the [ndbd default] section of config.ini, and can also be set or overridden for individual data nodes in the corresponding [ndbd] sections of the configuration file. The minimum value—which is also the default value—is 0, in which case memory reports are logged only when memory usage reaches certain percentages (80%, 90%, and 100%), as mentioned in the discussion of statistics events in Section 5.5.2, "MySQL Cluster Log Events".

This parameter was added in MySQL Cluster 5.1.16 and MySQL Cluster NDB 6.1.0.

• StartupStatusReportFrequency

Version Introduced	5.1.30-ndb-	5.1.30-ndb-6.4.0		
Restart Type	node			
	Permitted Values			
	Type	numeric		

When a data node is started with the <code>--initial</code>, it initializes the redo log file during Start Phase 4 (see Section 5.1, "Summary of MySQL Cluster Start Phases"). When very large values are set for <code>NoOfFragmentLogFiles</code>, <code>FragmentLogFiles</code> initialization can take a long time. Previous to MySQL Cluster NDB 6.4.0, only the beginning and end of the redo log file initialization process were logged. Beginning with this version, it is possible to force reports on the progress of this process to be logged periodically, by means of the <code>StartupStatusReportFrequency</code> configuration parameter. In this case, progress is reported in the cluster log, in terms of both the number of files and the amount of space that have been initialized, as shown here:

```
2009-06-20 16:39:23 [MgmSrvr] INFO -- Node 1: Local redo log file initialization status: #Total files: 80, Completed: 60 #Total MBytes: 20480, Completed: 15557 2009-06-20 16:39:23 [MgmSrvr] INFO -- Node 2: Local redo log file initialization status: #Total files: 80, Completed: 60 #Total MBytes: 20480, Completed: 15570
```

These reports are logged each StartupStatusReportFrequency seconds during Start Pahe 4. If StartupStatusReportFrequency is 0 (the default), then reports are written to the cluster log only when at the beginning and at the completion of the redo log file initialization process.

Debugging Parameters. Beginning with MySQL Cluster NDB 6.3.36, MySQL Cluster NDB 7.0.17, and MySQL Cluster NDB 7.1.6, it is possible to cause logging of traces for events generated by creating and dropping tables using <code>DictTrace</code>. This parameter is useful only in debugging NDB kernel code. <code>DictTrace</code> takes an integer value; currently, 0 (default - no logging) and 1 (logging enabled) are the only supported values.

Backup parameters. The [ndbd] parameters discussed in this section define memory buffers set aside for execution of online backups.

• BackupDataBufferSize

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	2M
	Range	0-4G

In creating a backup, there are two buffers used for sending data to the disk. The backup data buffer is used to fill in data recorded by scanning a node's tables. Once this buffer has been filled to the level specified as <code>BackupWriteSize</code>, the pages are sent to disk. While flushing data to disk, the backup process can continue filling this buffer until it runs out of space. When this happens, the backup process pauses the scan and waits until some disk writes have completed freed up memory so that scanning may continue.

In MySQL Cluster NDB 6.4.3 and earlier, the default value is 2MB; in MySQL Cluster NDB 7.0.4 and later, it is 16MB.

• BackupLogBufferSize

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	2M
	Range	0-4G

The backup log buffer fulfills a role similar to that played by the backup data buffer, except that it is used for generating a log of all table writes made during execution of the backup. The same principles apply for writing these pages as with the backup data buffer, except that when there is no more space in the backup log buffer, the backup fails. For that reason, the size of the

backup log buffer must be large enough to handle the load caused by write activities while the backup is being made. See Section 5.3.3, "Configuration for MySQL Cluster Backups".

The default value for this parameter should be sufficient for most applications. In fact, it is more likely for a backup failure to be caused by insufficient disk write speed than it is for the backup log buffer to become full. If the disk subsystem is not configured for the write load caused by applications, the cluster is unlikely to be able to perform the desired operations.

It is preferable to configure cluster nodes in such a manner that the processor becomes the bottleneck rather than the disks or the network connections.

In MySQL Cluster NDB 6.4.3 and earlier, the default value is 2MB; in MySQL Cluster NDB 7.0.4 and later, it is 16MB.

BackupMemory

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	4M
	Range	0-4G

This parameter is simply the sum of BackupDataBufferSize and BackupLogBufferSize.

In MySQL Cluster NDB 6.4.3 and earlier, the default value was 2MB + 2MB = 4MB; in MySQL Cluster NDB 7.0.4 and later, it is 16MB + 16MB = 32MB.

Important

If BackupDataBufferSize and BackupLogBufferSize taken together exceed the default value for BackupMemory, then this parameter must be set explicitly in the config.ini file to their sum.

• BackupReportFrequency

Version Introduced	5.1.19-ndb-6.2.3		
Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-4G	

This parameter controls how often backup status reports are issued in the management client during a backup, as well as how often such reports are written to the cluster log (provided cluster event logging is configured to permit it—see Logging and checkpointing). BackupReportFrequency represents the time in seconds between backup status reports.

The default value is 0.

This parameter was added in MySQL Cluster NDB 6.2.3.

BackupWriteSize

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	32K
	Range	2K-4G

This parameter specifies the default size of messages written to disk by the backup log and backup data buffers.

In MySQL Cluster 6.4.3 and earlier, the default value for this parameter was 32KB; beginning with MySQL Cluster NDB 7.0.4, it is 256KB.

• BackupMaxWriteSize

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	256K	
	Range	2K-4G	

This parameter specifies the maximum size of messages written to disk by the backup log and backup data buffers.

In MySQL Cluster 6.4.3 and earlier, the default value for this parameter was 256KB; beginning with MySQL Cluster NDB 7.0.4, it is 1MB.

Important

When specifying these parameters, the following relationships must hold true. Otherwise, the data node will be unable to start.

- BackupDataBufferSize >= BackupWriteSize + 188KB
- BackupLogBufferSize >= BackupWriteSize + 16KB
- BackupMaxWriteSize >= BackupWriteSize

MySQL Cluster Realtime Performance Parameters

The [ndbd] parameters discussed in this section are used in scheduling and locking of threads to specific CPUs on multiprocessor data node hosts. They were introduced in MySQL Cluster NDB 6.3.4.

Note

To make use of these parameters, the data node process must be run as system root.

LockExecuteThreadToCPU

Version Introduced	5.1.19-ndb-6.3.4		
Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	64K	
	Range	0-64K	

Previous to MySQL Cluster NDB 7.0. This parameter specifies the ID of the CPU assigned to handle the NDBCLUSTER execution thread. The value of this parameter is an integer in the range 0 to 65535 (inclusive). The default is 65535.

MySQL Cluster NDB 7.0 and later (beginning with MySQL Cluster NDB 6.4.0). When used with ndbd, this parameter (now a string) specifies the ID of the CPU assigned to handle the NDBCLUSTER execution thread. When used with ndbmtd, the value of this parameter is a comma-separated list of CPU IDs assigned to handle execution threads. Each CPU ID in the list should be an integer in the range 0 to 65535 (inclusive). The number of IDs specified should match the number of execution threads determined by MaxNoOfExecutionThreads. There is no default value.

Prior to MySQL Cluster NDB 7.0.18 and MySQL Cluster NDB 7.1.7, the effective maximum value recognized by this parameter as a valid CPU ID was 255; using a greater value caused thread locking to be disabled. (Bug #56185)

• LockMaintThreadsToCPU

Version Introduced	5.1.19-ndb-6.3.4		
Restart Type	node		

Permitted Values	
Type	numeric
Default	64K
Range	0-64K

This parameter specifies the ID of the CPU assigned to handle NDBCLUSTER maintenance threads.

The value of this parameter is an integer in the range 0 to 65535 (inclusive). This parameter was added in MySQL Cluster NDB 6.3.4. Prior to MySQL Cluster NDB 6.4.0, the default is 65535; in MySQL Cluster NDB 7.0 and later MySQL Cluster release series, there is no default value.

RealtimeScheduler

Version Introduced	5.1.19-ndb-	5.1.19-ndb-6.3.4	
Restart Type	node		
	Permitted Values		
	Type	boolean	
	Default	false	
	Range	-	

Setting this parameter to 1 enables real-time scheduling of NDBCLUSTER threads.

The default is 0 (scheduling disabled).

• SchedulerExecutionTimer

Version Introduced	5.1.22-ndb	5.1.22-ndb-6.3.4	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	50	
	Range	0-11000	

This parameter specifies the time in microseconds for threads to be executed in the scheduler before being sent. Setting it to 0 minimizes the response time; to achieve higher throughput, you can increase the value at the expense of longer response times.

The default is $50 \mu sec$, which our testing shows to increase throughput slightly in high-load cases without materially delaying requests.

This parameter was added in MySQL Cluster NDB 6.3.4.

• SchedulerSpinTimer

Version Introduced	5.1.22-ndb-6.3.4	
Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	0
	Range	0-500

This parameter specifies the time in microseconds for threads to be executed in the scheduler before sleeping.

The default value is 0.

BuildIndexThreads

Version Introduced	5.1.39-ndb-	5.1.39-ndb-6.3.30, 5.1.39-ndb-7.0.11	
Restart Type			
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-128	

This parameter determines the number of threads to create when rebuilding indexes during a system or node start. It is supported only when there is more than one fragment for the table per data node (for example, when the MAX_ROWS option has been used with CREATE TABLE).

Setting this parameter to 0 (which is also the default value) disables multi-threaded building of ordered indexes. The maximum allowed value is 128.

This parameter was added in MySQL Cluster NDB 6.3.30 and MySQL Cluster NDB 7.0.11. Prior to MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, it was supported only when using ndbd; in these and later MySQL Cluster releases, BuildIndexThreads is also supported for data nodes running ndbmtd (see Bug #54521).

Prior to MySQL Cluster NDB 7.1.11, multi-threaded building of ordered indexes was not supported during node initial restarts. Starting with MySQL Cluster NDB 7.1.11, you can enable multi-threaded builds during data node initial restarts by setting the TwoPassInitialNodeRestartCopy data node configuration parameter to TRUE.

• TwoPassInitialNodeRestartCopy

In MySQL Cluster NDB 7.1.11 and later, multi-threaded building of ordered indexes can be enabled for initial restarts of data nodes by setting this configuration parameter to TRUE, which enables two-pass copying of data during initial node restarts.

You must also set BuildIndexThreads to a nonzero value.

Numa

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.0.20, 5.1.51-ndb-7.1.9	
Restart Type	node	node	
	Permitted Values		
	Type (linux)	boolean	
	Default	0	

NDB is extremely sensitive to Non-Uniform Memory Access settings and multi-CPU systems due to timeouts that it can cause. Due to this fact, and because most MySQL Cluster users do not employ numactl, support for NUMA is ignored by default by ndbd when running on a Linux system, beginning with MySQL Cluster NDB 7.0.20 and MySQL Cluster 7.1.9. If your Linux system provides NUMA support and you wish for data node memory to be subject to NUMA control, you can set this parameter equal to 0.

The Numa configuration parameter is supported only on Linux systems where libnuma.so is installed.

Disk Data Configuration Parameters. Configuration parameters affecting Disk Data behavior include the following:

DiskPageBufferMemory

Version Introduced	5.1.6	5.1.6	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	64M	
	Range	4M-1T	

This determines the amount of space used for caching pages on disk, and is set in the [ndbd] or [ndbd default] section

of the config. ini file. It is measured in bytes. Each page takes up 32 KB. This means that Cluster Disk Data storage always uses N * 32 KB memory where N is some nonnegative integer.

The default value for this parameter is 64M (2000 pages of 32 KB each).

This parameter was added in MySQL 5.1.6.

Beginning with MySQL Cluster NDB 7.1.9, you can query the ndbinfo.diskpagebuffer table to help determine whether the value for this parameter should be increased to minimize unnecessary disk seeks. See Section 5.9.4, "The ndbinfo diskpagebuffer Table", for more information.

SharedGlobalMemory

Version Introduced	5.1.6	5.1.6	
Restart Type	node	node	
	Permitted Values (>= 5.1.6)		
	Type	numeric	
	Default	20M	
	Range	0-64T	

This parameter determines the amount of memory that is used for log buffers, disk operations (such as page requests and wait queues), and metadata for tablespaces, log file groups, UNDO files, and data files. The shared global memory pool also provides memory used for satisfying the memory requirements of the INITIAL_SIZE and UNDO_BUFFER_SIZE options used with CREATE LOGFILE GROUP and ALTER LOGFILE GROUP statements, including any default value implied for these options by the setting of the InitialLogFileGroup data node configuration parameter. SharedGlobalMemory can be set in the [ndbd] or [ndbd default] section of the config.ini configuration file, and is measured in bytes.

As of MySQL Cluster NDB 7.2.0, the default value is 128M. (Previously, this was 20M.)

This parameter was added in MySQL 5.1.6.

• DiskIOThreadPool

Version Introduced	5.1.30-ndb-6.4.0	
Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	8
	Range	0-4G
	Permitted Values	
	Type	numeric
	Default	2
	Range	0-4G
	Permitted Values	
	Type	numeric
	Default	2
	Range	0-4G

This parameter determines the number of unbound threads used for Disk Data file access. Before <code>DiskIOThreadPool</code> was introduced, exactly one thread was spawned for each Disk Data file, which could lead to performance issues, particularly when using very large data files. With <code>DiskIOThreadPool</code>, you can—for example—access a single large data file using several threads working in parallel.

Currently, this parameter applies to Disk Data I/O threads only, but we plan in the future to make the number of such threads configurable for in-memory data as well.

The optimum value for this parameter depends on your hardware and configuration, and includes these factors:

• Physical distribution of Disk Data files. You can obtain better performance by placing data files, undo log files, and the data node file system on separate physical disks. If you do this with some or all of these sets of files, then you can set

DiskIOThreadPool higher to enable separate threads to handle the files on each disk.

• **Disk performance and types.** The number of threads that can be accommodated for Disk Data file handling is also dependent on the speed and throughput of the disks. Faster disks and higher throughput allow for more disk I/O threads. Our test results indicate that solid-state disk drives can handle many more disk I/O threads than conventional disks, and thus higher values for <code>DiskIOThreadPool</code>.

This parameter was added in MySQL Cluster NDB 6.4.0. Previous to MySQL Cluster NDB 6.4.3, it was named ThreadPool. Previous to MySQL Cluster NDB 7.0.7, the default value was 8. Beginning with MySQL Cluster NDB 7.0.7 and MySQL Cluster NDB 7.1.0, the default is 2.

- **Disk Data file system parameters.** The parameters in the following list were added in MySQL Cluster NDB 6.2.17, 6.3.22, and 6.4.3 to make it possible to place MySQL Cluster Disk Data files in specific directories without the need for using symbolic links
 - FileSystemPathDD

Version Introduced	5.1.32-ndb-	5.1.32-ndb-6.2.17, 5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Restart Type	initial, node	initial, node	
	Permitted Values Type file name Default FileSystemPath Range -		

If this parameter is specified, then MySQL Cluster Disk Data data files and undo log files are placed in the indicated directory. This can be overridden for data files, undo log files, or both, by specifying values for FileSystemPathData-Files, FileSystemPathUndoFiles, or both, as explained for these parameters. It can also be overridden for data files by specifying a path in the ADD DATAFILE clause of a CREATE TABLESPACE or ALTER TABLESPACE statement, and for undo log files by specifying a path in the ADD UNDOFILE clause of a CREATE LOGFILE GROUP or ALTER LOGFILE GROUP statement. If FileSystemPathDD is not specified, then FileSystemPath is used.

If a FileSystemPathDD directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

• FileSystemPathDataFiles

Version Introduced	5.1.32-ndb	5.1.32-ndb-6.2.17, 5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Restart Type	initial, nod	initial, node	
	Permitted	Permitted Values	
	Type	file name	
	Default	FileSystemPathDD	
	Range	Range -	

If this parameter is specified, then MySQL Cluster Disk Data data files are placed in the indicated directory. This overrides any value set for FileSystemPathDD. This parameter can be overridden for a given data file by specifying a path in the ADD DATAFILE clause of a CREATE TABLESPACE or ALTER TABLESPACE statement used to create that data file. If FileSystemPathDataFiles is not specified, then FileSystemPathDD is used (or FileSystemPath, if FileSystemPathDD has also not been set).

If a FileSystemPathDataFiles directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

FileSystemPathUndoFiles

Version Introduced	5.1.32-ndb-6.2.17, 5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Restart Type	initial, node	

Permitted	Values
Type	file name
Default	FileSystemPathDD
Range	-

If this parameter is specified, then MySQL Cluster Disk Data undo log files are placed in the indicated directory. This overrides any value set for FileSystemPathDD. This parameter can be overridden for a given data file by specifying a path in the ADD UNDO clause of a CREATE LOGFILE GROUP or CREATE LOGFILE GROUP statement used to create that data file. If FileSystemPathUndoFiles is not specified, then FileSystemPathDD is used (or FileSystemPathDD has also not been set).

If a FileSystemPathUndoFiles directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

For more information, see Section 5.11.1, "MySQL Cluster Disk Data Objects".

- **Disk Data object creation parameters.** The next two parameters enable you—when starting the cluster for the first time—to cause a Disk Data log file group, tablespace, or both, to be created without the use of SQL statements.
 - InitialLogFileGroup

Version Introduced	5.1.32-ndb	5.1.32-ndb-6.2.17, 5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Restart Type	system	system	
	Permitted	Permitted Values	
	Type	string	
	Default	[see documentation]	
	Range	Range -	

This parameter can be used to specify a log file group that is created when performing an initial start of the cluster. InitialLogFileGroup is specified as shown here:

```
InitialLogFileGroup = [name=name;] [undo_buffer_size=size;] file-specification-list
file-specification[; file-specification[; ...]]
file-specification:
    filename:size
```

The name of the log file group is optional and defaults to DEFAULT-LG. The undo_buffer_size is also optional; if omitted, it defaults to 64M. Each file-specification corresponds to an undo log file, and at least one must be specified in the file-specification-list. Undo log files are placed according to any values that have been set for FileSystemPath, FileSystemPathDD, and FileSystemPathUndoFiles, just as if they had been created as the result of a CREATE LOGFILE GROUP or ALTER LOGFILE GROUP statement.

Consider the following:

```
InitialLogFileGroup = name=LG1; undo_buffer_size=128M; undo1.log:250M; undo2.log:150M
```

This is equivalent to the following SQL statements:

```
CREATE LOGFILE GROUP LG1
ADD UNDOFILE 'undo1.log'
INITIAL_SIZE 250M
UNDO_BUFFER_SIZE 128M
ENGINE NDBCLUSTER;
ALTER LOGFILE GROUP LG1
ADD UNDOFILE 'undo2.log'
INITIAL_SIZE 150M
ENGINE NDBCLUSTER;
```

This logfile group is created when the data nodes are started with --initial.

Resources for the initial log file group are taken from the global memory pool whose size is determined by the value of the SharedGlobalMemory data node configuration parameter; if this parameter is set too low and the values set in Ini-

tialLogFileGroup for the logfile group's initial size or undo buffer size are too high, the cluster may fail to create the default log file group when starting, or fail to start altogether.

This parameter, if used, should always be set in the [ndbd default] section of the config.ini file. The behavior of a MySQL Cluster when different values are set on different data nodes is not defined.

• InitialTablespace

Version Introduced	5.1.32-ndb-6.2.17, 5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Restart Type	system	
	Permitted Values Type string Default [see documentation] Range -	

This parameter can be used to specify a MySQL Cluster Disk Data tablespace that is created when performing an initial start of the cluster. InitialTablespace is specified as shown here:

```
InitialTablespace = [name=name;] [extent_size=size;] file-specification-list
```

The name of the tablespace is optional and defaults to DEFAULT-TS. The extent_size is also optional; it defaults to 1M. The <code>file-specification-list</code> uses the same syntax as shown with the <code>InitialLogfileGroup</code> parameter, the only difference being that each <code>file-specification</code> used with <code>InitialTablespace</code> corresponds to a data file. At least one must be specified in the <code>file-specification-list</code>. Data files are placed according to any values that have been set for <code>FileSystemPath</code>, <code>FileSystemPathDD</code>, and <code>FileSystemPathDataFiles</code>, just as if they had been created as the result of a <code>CREATE TABLESPACE</code> or <code>ALTER TABLESPACE</code> statement.

For example, consider the following line specifying InitialTablespace in the [ndbd default] section of the config.ini file (as with InitialLogfileGroup, this parameter should always be set in the [ndbd default] section, as the behavior of a MySQL Cluster when different values are set on different data nodes is not defined):

```
InitialTablespace = name=TS1; extent_size=8M; data1.dat:2G; data2.dat:4G
```

This is equivalent to the following SQL statements:

```
CREATE TABLESPACE TS1

ADD DATAFILE 'data1.dat'

EXTENT_SIZE 8M

INITIAL_SIZE 2G

ENGINE NDBCLUSTER;

ALTER TABLESPACE TS1

ADD UNDOFILE 'data2.dat'

INITIAL_SIZE 4G

ENGINE NDBCLUSTER;
```

This tablespace is created when the data nodes are started with --initial, and can be used whenever creating MySQL Cluster Disk Data tables thereafter.

Disk Data and GCP STOP errors. Errors encountered when using Disk Data tables such as Node Nodeld killed this node Because GCP stop was detected (error 2303) are often referred to as "GCP stop errors". Such errors occur when the redo log is not flushed to disk quickly enough; this is usually due to slow disks and insufficient disk throughput.

You can help prevent these errors from occurring by using faster disks, and by placing Disk Data files on a separate disk from the data node file system. Reducing the value of TimeBetweenGlobalCheckpoints tends to decrease the amount of data to be written for each global checkpoint, and so may provide some protection against redo log buffer overflows when trying to write a global checkpoint; however, reducing this value also permits less time in which to write the GCP, so this must be done with caution

In addition, adjusting the cluster configuration as discussed here can also help:

MySQL Cluster NDB 6.2 and 6.3. When working with large amounts of data on disk under high load, the default value for DiskPageBufferMemory may not be large enough. In such cases, you should increase its value to include most of the memory available to the data nodes after accounting for index memory, data memory, internal buffers, and memory needed by the data node host operating system.

You can use this formula as a guide:

```
DiskPageBufferMemory
= 0.8
    x (
       [total memory]
       - ([operating system memory] + [buffer memory] + DataMemory + IndexMemory)
)
```

Once you have established that sufficient memory is reserved for <code>DataMemory</code>, <code>IndexMemory</code>, NDB internal buffers, and operating system overhead, it is possible (and sometimes desirable) to allocate more than the above amount of the remainder to <code>DiskPageBufferMemory</code>.

• MySQL Cluster NDB 7.X. In addition to the considerations given for DiskPageBufferMemory as explained previously, it is also very important that the DiskIOThreadPool configuration parameter be set correctly; having DiskIOThreadPool set too high is very likely to cause GCP stop errors (Bug #37227).

GCP stops can be caused by save or commit timeouts; the <u>TimeBetweenEpochsTimeout</u> data node configuration parameter determines the timeout for commits. However, beginning with MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10, it is possible to disable both types of timeouts by setting this parameter to 0.

Parameters for configuring send buffer memory allocation (MySQL Cluster NDB 7.0 and later). Beginning with MySQL Cluster NDB 6.4.0, send buffer memory is allocated dynamically from a memory pool shared between all transporters, which means that the size of the send buffer can be adjusted as necessary. (Previously, the NDB kernel used a fixed-size send buffer for every node in the cluster, which was allocated when the node started and could not be changed while the node was running.) The following data node configuration parameters were added in MySQL Cluster NDB 6.4.0 to permit the setting of limits on this memory allocation; this change is reflected by the addition of the configuration parameters TotalSendBufferMemory and OverLoadLimit, as well as a change in how the existing SendBufferMemory configuration parameter is used. For more information, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

TotalSendBufferMemory

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039.

ReservedSendBufferMemory

This parameter is present in NDBCLUSTER source code beginning with MySQL Cluster NDB 6.4.0. However, it is not currently enabled.

For more detailed information about the behavior and use of TotalSendBufferMemory and about configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

Note

Previous to MySQL Cluster NDB 7.0, to add new data nodes to a MySQL Cluster, it was necessary to shut down the cluster completely, update the config.ini file, and then restart the cluster (that is, you had to perform a system restart). All data node processes had to be started with the --initial option.

Beginning with MySQL Cluster NDB 7.0, it is possible to add new data node groups to a running cluster online. See Section 5.12, "Adding MySQL Cluster Data Nodes Online", for more information.

Redo log over-commit handling. Beginning with MySQL Cluster NDB 7.1.10, it is possible to control the data node's handling of operations when too much time is taken flushing redo logs to disk. This occurs when a given redo log flush takes longer than RedooverCommitLimit seconds, more than RedooverCommitCounter times, causing any pending transactions to be aborted. When this happens, the API node that sent the transaction can handle the operations that should have been committed either by queuing the operations and re-trying them, or by aborting them, as determined by DefaultOperationRedoProblemAction. The data node configuration parameters for setting the timeout and number of

DefaultOperationRedoProblemAction. The data node configuration parameters for setting the timeout and number of times it may be exceeded before the API node takes this action are described in the following list:

• RedoOverCommitCounter

Version Introduced	5.1.51-ndb-7.1.10
--------------------	-------------------

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	3	
	Range	0-4G	

When RedoOverCommitLimit is exceeded when trying to write a given redo log to disk this many times or more, any transactions that were not committed as a result are aborted, and an API node where any of these transactions originated handles the operations making up those transactions according to its value for DefaultOperationRedoProblemAction (by either queuing the operations to be re-tried, or aborting them).

RedoOverCommitCounter defaults to 3. Set it to 0 to disable the limit. This parameter was added in MySQL Cluster NDB 7.1.10.

• RedoOverCommitLimit

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.1.10	
Restart Type	node	node	
	Permitted Values Type numeric		
	Default	20	
	Range	0-4G	

This parameter sets an upper limit in seconds for trying to write a given redo log to disk before timing out. The number of times the data node tries to flush this redo log, but takes longer than RedoOverCommitLimit, is kept and compared with RedoOverCommitCounter, and when flushing takes too long more times than the value of that parameter, any transactions that were not committed as a result of the flush timeout are aborted. When this occurs, the API node where any of these transactions originated handles the operations making up those transactions according to its DefaultOperationRedoProblemAction setting (it either queues the operations to be re-tried, or aborts them).

By default, RedoOverCommitLimit is 20 seconds. Set to 0 to disable checking for redo log flush timeouts. This parameter was added in MySQL Cluster NDB 7.1.10.

Controlling restart attempts. Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to exercise more finely-grained control over restart attempts by data nodes when they fail to start using two data node configuration parameters added in these releases. MaxStartFailRetries limits the total number of retries made before giving up on starting the data node; StartFailRetryDelay sets the number of seconds between retry attempts, as described in the following list:

• StartFailRetryDelay

Version Introduced	5.1.51-ndb-6.2.19, 5.1.47-ndb-6.3.37, 5.1.47-ndb-7.0.18, 5.1.47-ndb-7.1.7		
Restart Type	node		
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-4G	
	Permitted	Permitted Values	
	Type	numeric	
	Default	0	
	Range	0-4G	

Permitted Values	
Type	numeric
Default	0
Range	0-4G

Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to set the number of seconds between restart attempts by the data node in the event on failure on startup. The default is 0 (no delay).

Note

This parameter is ignored unless StartOnError is equal to 0.

• MaxStartFailRetries

Version Introduced	5.1.51-ndb-6.2.19, 5.1.47-ndb-6.3.37, 5.1.47-ndb-7.0.18, 5.1.47-ndb-7.1.7	
Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	3
	Range	0-4G
	Permitted Values	
	Туре	numeric
	Default	3
	Range	0-4G
	Permitted Values	
	Type	numeric
	Default	3
	Range	0-4G
	Permitted Values	
	Type	numeric
	Default	3
	Range	0-4G

Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to limit the number restart attempts made by the data node in the event that it fails on startup. The default is 3 attempts.

Note

This parameter is ignored unless StopOnError is equal to 0.

3.2.7. Defining SQL and Other API Nodes in a MySQL Cluster

The [mysqld] and [api] sections in the config.ini file define the behavior of the MySQL servers (SQL nodes) and other applications (API nodes) used to access cluster data. None of the parameters shown is required. If no computer or host name is provided, any host can use this SQL or API node.

Generally speaking, a [mysqld] section is used to indicate a MySQL server providing an SQL interface to the cluster, and an [api] section is used for applications other than mysqld processes accessing cluster data, but the two designations are actually synonomous; you can, for instance, list parameters for a MySQL server acting as an SQL node in an [api] section.

Note

For a discussion of MySQL server options for MySQL Cluster, see Section 3.4.2, "mysqld Command Options for MySQL Cluster"; for information about MySQL server system variables relating to MySQL Cluster, see Sec-

tion 3.4.3, "MySQL Cluster System Variables".

• Id

Version Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Deprecated	5.1.51-ndb-	5.1.51-ndb-7.1.9	
Restart Type	node	node	
	Permitted Values		
	Type	Type numeric	
	Default	Default Default	
	Range	Range 1-63	

The Id is an integer value used to identify the node in all cluster internal messages. Prior to MySQL Cluster NDB 6.1.1, the permitted range of values for this parameter was 1 to 63 inclusive. Beginning with MySQL Cluster NDB 6.1.1, the permitted range is 1 to 255 inclusive. This value must be unique for each node in the cluster, regardless of the type of node.

Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for API nodes (and management nodes) to values greater than 48

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

• NodeId

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	1-63	

The NodeId is an integer value used to identify the node in all cluster internal messages. Prior to MySQL Cluster NDB 6.1.1, the permitted range of values for this parameter was 1 to 63 inclusive. Beginning with MySQL Cluster NDB 6.1.1, the permitted range is 1 to 255 inclusive. This value must be unique for each node in the cluster, regardless of the type of node.

Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for API nodes (and management nodes) to values greater than 48

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

• ExecuteOnComputer

Restart Type	system	
	Permitted Values	
	Type	string
	Default	
	Range	-

This refers to the Id set for one of the computers (hosts) defined in a [computer] section of the configuration file.

HostName

Restart Type	system	system	
	Permitted Values		
	Type	string	
	Default		
	Range	-	

Specifying this parameter defines the hostname of the computer on which the SQL node (API node) is to reside. To specify a hostname, either this parameter or ExecuteOnComputer is required.

If no HostName or ExecuteOnComputer is specified in a given [mysql] or [api] section of the config.ini file, then an SQL or API node may connect using the corresponding "slot" from any host which can establish a network connection to the management server host machine. This differs from the default behavior for data nodes, where localhost is assumed for HostName unless otherwise specified.

• ArbitrationRank

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-2	

This parameter defines which nodes can act as arbitrators. Both MGM nodes and SQL nodes can be arbitrators. A value of 0 means that the given node is never used as an arbitrator, a value of 1 gives the node high priority as an arbitrator, and a value of 2 gives it low priority. A normal configuration uses the management server as arbitrator, setting its ArbitrationRank to 1 (the default for management nodes) and those for all SQL nodes to 0 (the default for SQL nodes).

Beginning with MySQL 5.1.16 and MySQL Cluster NDB 6.1.3, it is possible to disable arbitration completely by setting ArbitrationRank to 0 on all management and SQL nodes. In MySQL Cluster NDB 7.0.7 and later releases, you can also control arbitration by overriding this parameter; to do this, set the Arbitration parameter in the [ndbd default] section of the config.ini global configuration file.

• ArbitrationDelay

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-4G	

Setting this parameter to any other value than 0 (the default) means that responses by the arbitrator to arbitration requests will be delayed by the stated number of milliseconds. It is usually not necessary to change this value.

BatchByteSize

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	32K	
	Range	1024-1M	

For queries that are translated into full table scans or range scans on indexes, it is important for best performance to fetch records in properly sized batches. It is possible to set the proper size both in terms of number of records (BatchSize) and in terms of bytes (BatchByteSize). The actual batch size is limited by both parameters.

The speed at which queries are performed can vary by more than 40% depending upon how this parameter is set. In future releases, MySQL Server will make educated guesses on how to set parameters relating to batch size, based on the query type.

This parameter is measured in bytes and by default is equal to 32KB.

• BatchSize

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	64	
	Range	1-992	

This parameter is measured in number of records and is by default set to 64. The maximum size is 992.

• HeartbeatThreadPriority

Beginning with MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2, it is possible to use this parameter to set the scheduling policy and priority of heartbeat threads for management and API nodes.

The syntax for setting this parameter is shown here:

```
HeartbeatThreadPriority = policy[, priority]
policy:
{FIFO | RR}
```

When setting this parameter, you must specify a policy. This is one of FIFO (first in, first in) or RR (round robin). This followed optionally by the priority (an integer).

• MaxScanBatchSize

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	256K	
	Range	32K-16M	

The batch size is the size of each batch sent from each data node. Most scans are performed in parallel to protect the MySQL Server from receiving too much data from many nodes in parallel; this parameter sets a limit to the total batch size over all nodes.

The default value of this parameter is set to 256KB. Its maximum size is 16MB.

• TotalSendBufferMemory

Version Introduced	5.1.30-ndb-	5.1.30-ndb-6.4.0	
Restart Type	node	node	
	Permitted	Permitted Values	
	Type numeric Default 256K Range 0-4G		

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039. For more detailed information about the behavior and use of TotalSendBufferMemory and configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

• AutoReconnect

Version Introduced	5.1.35-ndb-6.3.26, 5.1.35-ndb-7.0.7	
Restart Type	node	

Permitted Values	
Type	boolean
Default	false
Range	false-true

This parameter is available beginning with MySQL Cluster NDB 6.3.26 and MySQL Cluster NDB 7.0.7. By default, its value is false, which forces disconnected API nodes (including MySQL Servers acting as SQL nodes) the use a new connection to the cluster rather than attempting to re-use an existing one, which can cause problems when using dynamically-allocated node IDs. (Bug #45921)

Note

```
This parameter can be overridden using the NDB API. For more information, see Ndb_cluster_connection::set_auto_reconnect(), and Ndb_cluster_connection::get_auto_reconnect().
```

• DefaultOperationRedoProblemAction

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.1.10	
Restart Type			
	Permitted Values		
	Type	enumeration	
	Default		
	Valid Values	ABORT	
		QUEUE	

This parameter was introduced in MySQL Cluster NDB 7.1.10 (along with RedoOverCommitLimit and RedoOverCommitCounter) for controlling the data node's handling of operations when too much time is taken flushing redo logs to disk. This occurs when a given redo log flush takes longer than RedoOverCommitLimit seconds, more than RedoOverCommitCounter times, causing any pending transactions to be aborted.

When this happens, the node can respond in either of two ways, according to the value of DefaultOperationRedoProblemAction, listed here:

- ABORT: Any pending operations from aborted transactions are also aborted.
- QUEUE: Pending operations from transactions that were aborted are queued up to be re-tried.

You can obtain some information from a MySQL server running as a Cluster SQL node using SHOW STATUS in the mysql client, as shown here:

For information about these Cluster system status variables, see Server Status Variables.

Note

To add new SQL or API nodes to the configuration of a running MySQL Cluster, it is necessary to perform a rolling restart of all cluster nodes after adding new [mysqld] or [api] sections to the config.ini file (or files, if you are using more than one management server). This must be done before the new SQL or API nodes can connect to the cluster.

It is not necessary to perform any restart of the cluster if new SQL or API nodes can employ previously unused API

slots in the cluster configuration to connect to the cluster.

3.2.8. MySQL Cluster TCP/IP Connections

TCP/IP is the default transport mechanism for all connections between nodes in a MySQL Cluster. Normally it is not necessary to define TCP/IP connections; MySQL Cluster automatically sets up such connections for all data nodes, management nodes, and SQL or API nodes.

Note

For an exception to this rule, see Section 3.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections".

To override the default connection parameters, it is necessary to define a connection using one or more [tcp] sections in the config.ini file. Each [tcp] section explicitly defines a TCP/IP connection between two MySQL Cluster nodes, and must contain at a minimum the parameters NodeIdl and NodeIdl, as well as any connection parameters to override.

It is also possible to change the default values for these parameters by setting them in the [tcp default] section.

Important

Any [tcp] sections in the config.ini file should be listed *last*, following all other sections in the file. However, this is not required for a [tcp default] section. This requirement is a known issue with the way in which the config.ini file is read by the MySQL Cluster management server.

Connection parameters which can be set in [tcp] and [tcp default] sections of the config.ini file are listed here:

NodeId1

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default		
	Range	-	

NodeId2

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default		
	Range	-	

To identify a connection between two nodes it is necessary to provide their node IDs in the [tcp] section of the configuration file. These are the same unique NodeId (or Id) values for each of these nodes as described in Section 3.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

HostName1

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	string	
	Default		
	Range	-	

HostName2

Restart Type	node
--------------	------

P	Permitted Values	
T	Гуре	string
D	Default	
R	Range	-

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given TCP connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

OverloadLimit

Beginning in MySQL Cluster NDB 6.4.0, this parameter can be used to determine the amount of unsent data that must be present in the send buffer before the connection is considered overloaded. See Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters", for more information.

Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, the effective value of this parameter was limited by the size of SendBufferMemory; beginning with these releases, the actual value for OverloadLimit (up to the stated maximum of 4G) is used instead.

• SendBufferMemory

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	numeric	
	Default	256K	
	Range	64K-4G	

TCP transporters use a buffer to store all messages before performing the send call to the operating system. When this buffer reaches 64KB its contents are sent; these are also sent when a round of messages have been executed. To handle temporary overload situations it is also possible to define a bigger send buffer.

Prior to MySQL Cluster NDB 7.0, this parameter determines a fixed amount of memory allocated at startup for each configured TCP connection. Beginning with MySQL Cluster NDB 6.4.0, if this parameter is set explicitly, then the memory is not dedicated to each transporter; instead, the value used denotes the hard limit for how much memory (out of the total available memory—that is, TotalSendBufferMemory) that may be used by a single transporter. For more information about configuring dynamic transporter send buffer memory allocation in MySQL Cluster NDB 7.0 and later, see Section 3.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

In MySQL Cluster NDB 6.4.3 and earlier, the default size of the send buffer was 256 KB; in MySQL Cluster NDB 7.0.4 and later, it is 2MB, which is the size recommended in most situations. The minimum size is 64 KB; the theoretical maximum is 4 GB.

• SendSignalId

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	boolean	
	Default	false (debug builds: true)	
	Range	_	

To be able to retrace a distributed message datagram, it is necessary to identify each message. When this parameter is set to Y, message IDs are transported over the network. This feature is disabled by default in production builds, and enabled in -debug builds.

• Checksum

Restart Type	node

Permitted Values	
Type	boolean
Default	false
Range	-

This parameter is a boolean parameter (enabled by setting it to Y or 1, disabled by setting it to Y or 0). It is disabled by default. When it is enabled, checksums for all messages are calculated before they placed in the send buffer. This feature ensures that messages are not corrupted while waiting in the send buffer, or by the transport mechanism.

PortNumber (OBSOLETE)

This formerly specified the port number to be used for listening for connections from other nodes. This parameter should no longer be used; use the ServerPort data node configuration parameter for this purpose instead.

ReceiveBufferMemory

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	64K	
	Range	16K-4G	

Specifies the size of the buffer used when receiving data from the TCP/IP socket.

In MySQL Cluster NDB 6.4.3 and earlier, the default value of this parameter was 64 KB; beginning with MySQL Cluster NDB 7.0.4, 2MB is the default. The minimum possible value is 16KB; the theoretical maximum is 4GB.

3.2.9. MySQL Cluster TCP/IP Connections Using Direct Connections

Setting up a cluster using direct connections between data nodes requires specifying explicitly the crossover IP addresses of the data nodes so connected in the [tcp] section of the cluster config.ini file.

In the following example, we envision a cluster with at least four hosts, one each for a management server, an SQL node, and two data nodes. The cluster as a whole resides on the 172.23.72.* subnet of a LAN. In addition to the usual network connections, the two data nodes are connected directly using a standard crossover cable, and communicate with one another directly using IP addresses in the 1.1.0.* address range as shown:

```
# Management Server
[ndb_mgmd]
Id=1
HostName=172.23.72.20
# SQL Node
[mysqld]
Id=2
HostName=172.23.72.21
# Data Nodes
[ndbd]
Id=3
HostName=172.23.72.22
[ndbd]
Id=4
HostName=172.23.72.23
# TCP/IP Connections
[tcp]
NodeId1=3
NodeId1=3
NodeId2=4
HostName=172.23.72.23
# TOSTANAME=172.23.72.23
```

The HostName1 and HostName2 parameters are used only when specifying direct connections.

The use of direct TCP connections between data nodes can improve the cluster's overall efficiency by enabling the data nodes to bypass an Ethernet device such as a switch, hub, or router, thus cutting down on the cluster's latency. It is important to note that to take the best advantage of direct connections in this fashion with more than two data nodes, you must have a direct connection between each data node and every other data node in the same node group.

3.2.10. MySQL Cluster Shared-Memory Connections

MySQL Cluster attempts to use the shared memory transporter and configure it automatically where possible. [shm] sections in the config.ini file explicitly define shared-memory connections between nodes in the cluster. When explicitly defining shared memory as the connection method, it is necessary to define at least NodeId1, NodeId2, and ShmKey. All other parameters have default values that should work well in most cases.

Important

SHM functionality is considered experimental only. It is not officially supported in any current MySQL Cluster release, and testing results indicate that SHM performance is not appreciably greater than when using TCP/IP for the transporter.

For these reasons, you must determine for yourself or by using our free resources (forums, mailing lists) whether SHM can be made to work correctly in your specific case.

• NodeId1

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	_	

NodeId2

Restart Type	node	
	Permitted Values	
	Type	numeric
	Default	
	Range	-

To identify a connection between two nodes it is necessary to provide node identifiers for each of them, as NodeId1 and NodeId2.

HostName1

Restart Type	node	node	
	Permitted Values		
	Type	string	
	Default		
	Range	-	

HostName2

Restart Type	node	
	Permitted Values	
	Type	string
	Default	
	Range	-

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given SHM connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

• ShmKey

Restart Type	node
--------------	------

Permitted Values	
Type	numeric
Default	
Range	0-4G

When setting up shared memory segments, a node ID, expressed as an integer, is used to identify uniquely the shared memory segment to use for the communication. There is no default value.

• ShmSize

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	1M	
	Range	64K-4G	

Each SHM connection has a shared memory segment where messages between nodes are placed by the sender and read by the reader. The size of this segment is defined by ShmSize. The default value is 1MB.

• SendSignalId

Restart Type	node	node	
	Permitted Values		
	Type	boolean	
	Default	false	
	Range	-	

To retrace the path of a distributed message, it is necessary to provide each message with a unique identifier. Setting this parameter to Y causes these message IDs to be transported over the network as well. This feature is disabled by default in production builds, and enabled in -debug builds.

• Checksum

Restart Type	node	node	
	Permitted Values		
	Type	boolean	
	Default	true	
	Range	-	

This parameter is a boolean (Y/N) parameter which is disabled by default. When it is enabled, checksums for all messages are calculated before being placed in the send buffer.

This feature prevents messages from being corrupted while waiting in the send buffer. It also serves as a check against data being corrupted during transport.

• SigNum

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	0-4G	

When using the shared memory transporter, a process sends an operating system signal to the other process when there is new

data available in the shared memory. Should that signal conflict with with an existing signal, this parameter can be used to change it. This is a possibility when using SHM due to the fact that different operating systems use different signal numbers.

The default value of SigNum is 0; therefore, it must be set to avoid errors in the cluster log when using the shared memory transporter. Typically, this parameter is set to 10 in the [shm default] section of the config.ini file.

3.2.11. SCI Transport Connections in MySQL Cluster

[sci] sections in the config.ini file explicitly define SCI (Scalable Coherent Interface) connections between cluster nodes. Using SCI transporters in MySQL Cluster is supported only when the MySQL binaries are built using --with-ndb-sci=/your/path/to/SCI. The path should point to a directory that contains at a minimum lib and include directories containing SISCI libraries and header files. (See Section 3.5, "Using High-Speed Interconnects with MySQL Cluster" for more information about SCI.)

In addition, SCI requires specialized hardware.

It is strongly recommended to use SCI Transporters only for communication between ndbd processes. Note also that using SCI Transporters means that the ndbd processes never sleep. For this reason, SCI Transporters should be used only on machines having at least two CPUs dedicated for use by ndbd processes. There should be at least one CPU per ndbd process, with at least one CPU left in reserve to handle operating system activities.

• NodeId1

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	-	

NodeId2

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	-	

To identify a connection between two nodes it is necessary to provide node identifiers for each of them, as NodeId1 and NodeId2.

• Host1SciId0

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	0-4G	

This identifies the SCI node ID on the first Cluster node (identified by NodeId1).

• Host1SciId1

Restart Type	node

Permitted Values	
Type	numeric
Default	0
Range	0-4G

It is possible to set up SCI Transporters for failover between two SCI cards which then should use separate networks between the nodes. This identifies the node ID and the second SCI card to be used on the first node.

Host2SciId0

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default		
	Range	0-4G	

This identifies the SCI node ID on the second Cluster node (identified by NodeId2).

• Host2SciId1

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	0	
	Range	0-4G	

When using two SCI cards to provide failover, this parameter identifies the second SCI card to be used on the second node.

• HostName1

Restart Type	node	node	
	Permitted Values		
	Type	string	
	Default		
	Range	-	

HostName2

Restart Type	node	node	
	Permitted	Permitted Values	
	Type	string	
	Default		
	Range	-	

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given SCI connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

• SharedBufferSize

Restart Type	node

Pe	ermitted	Values
T	`ype	numeric
De	efault	10M
R	Range	64K-4G

Each SCI transporter has a shared memory segment used for communication between the two nodes. Setting the size of this segment to the default value of 1MB should be sufficient for most applications. Using a smaller value can lead to problems when performing many parallel inserts; if the shared buffer is too small, this can also result in a crash of the ndbd process.

SendLimit

Restart Type	node	node	
	Permitted Values		
	Type	numeric	
	Default	8K	
	Range	128-32K	

A small buffer in front of the SCI media stores messages before transmitting them over the SCI network. By default, this is set to 8KB. Our benchmarks show that performance is best at 64KB but 16KB reaches within a few percent of this, and there was little if any advantage to increasing it beyond 8KB.

• SendSignalId

Restart Type	node	
	Permitted Values	
	Type	boolean
	Default	true
	Range	-

To trace a distributed message it is necessary to identify each message uniquely. When this parameter is set to Y, message IDs are transported over the network. This feature is disabled by default in production builds, and enabled in -debug builds.

• Checksum

Restart Type	node	
	Permitted Values	
	Type	boolean
	Default	false
	Range	-

This parameter is a boolean value, and is disabled by default. When Checksum is enabled, checksums are calculated for all messages before they are placed in the send buffer. This feature prevents messages from being corrupted while waiting in the send buffer. It also serves as a check against data being corrupted during transport.

3.2.12. Configuring MySQL Cluster Parameters for Local Checkpoints

The parameters discussed in Logging and Checkpointing and in Data Memory, Index Memory, and String Memory that are used to configure local checkpoints for a MySQL Cluster do not exist in isolation, but rather are very much interdepedent on each other. In this section, we illustrate how these parameters—including DataMemory, IndexMemory, NoOfDiskPagesToDiskAfter-RestartTUP, NoOfDiskPagesToDiskAfterRestartACC, and NoOfFragmentLogFiles—relate to one another in a working Cluster.

Important

The parameters NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC were deprecated in MySQL 5.1.6. From MySQL 5.1.6 through 5.1.11, disk writes during LCPs took

place at the maximum speed possible. Beginning with MySQL 5.1.12, the speed and throughput for LCPs are controlled using the parameters <code>DiskSyncSize</code>, <code>DiskCheckpointSpeed</code>, and <code>DiskCheckpointSpeedInRestart</code>. See Section 3.2.6, "Defining MySQL Cluster Data Nodes".

In this example, we assume that our application performs the following numbers of types of operations per hour:

- 50000 selects
- 15000 inserts
- 15000 updates
- 15000 deletes

We also make the following assumptions about the data used in the application:

- We are working with a single table having 40 columns.
- Each column can hold up to 32 bytes of data.
- A typical UPDATE run by the application affects the values of 5 columns.
- No NULL values are inserted by the application.

A good starting point is to determine the amount of time that should elapse between local checkpoints (LCPs). It is worth noting that, in the event of a system restart, it takes 40-60 percent of this interval to execute the REDO log—for example, if the time between LCPs is 5 minutes (300 seconds), then it should take 2 to 3 minutes (120 to 180 seconds) for the REDO log to be read.

The maximum amount of data per node can be assumed to be the size of the <code>DataMemory</code> parameter. In this example, we assume that this is 2 GB. The <code>NoOfDiskPagesToDiskAfterRestartTUP</code> parameter represents the amount of data to be checkpointed per unit time—however, this parameter is actually expressed as the number of 8K memory pages to be checkpointed per 100 milliseconds. 2 GB per 300 seconds is approximately 6.8 MB per second, or 700 KB per 100 milliseconds, which works out to roughly 85 pages per 100 milliseconds.

Similarly, we can calculate NoOfDiskPagesToDiskAfterRestartACC in terms of the time for local checkpoints and the amount of memory required for indexes—that is, the IndexMemory. Assuming that we permit 512 MB for indexes, this works out to approximately 20 8-KB pages per 100 milliseconds for this parameter.

Next, we need to determine the number of REDO log files required—that is, fragment log files—the corresponding parameter being NoOfFragmentLogFiles. We need to make sure that there are sufficient REDO log files for keeping records for at least 3 local checkpoints (in MySQL Cluster NDB 6.3.8 and later, we need only allow for 2 local checkpoints). In a production setting, there are always uncertainties—for instance, we cannot be sure that disks always operate at top speed or with maximum throughput. For this reason, it is best to err on the side of caution, so we double our requirement and calculate a number of fragment log files which should be enough to keep records covering 6 local checkpoints (in MySQL Cluster NDB 6.3.8 and later, a number of fragment log files accommodating 4 local checkpoints should be sufficient).

It is also important to remember that the disk also handles writes to the REDO log, so if you find that the amount of data being written to disk as determined by the values of NoOfDiskPagesToDiskAfterRestartACC and NoOfDiskPagesToDiskAfterRestartTUP is approaching the amount of disk bandwidth available, you may wish to increase the time between local checkpoints.

Given 5 minutes (300 seconds) per local checkpoint, this means that we need to support writing log records at maximum speed for 6*300 = 1800 seconds (*MySQL Cluster NDB 6.3.8 and later*: 4*300 = 1200 seconds). The size of a REDO log record is 72 bytes plus 4 bytes per updated column value plus the maximum size of the updated column, and there is one REDO log record for each table record updated in a transaction, on each node where the data reside. Using the numbers of operations set out previously in this section, we derive the following:

- 50000 select operations per hour yields 0 log records (and thus 0 bytes), since SELECT statements are not recorded in the REDO log.
- 15000 DELETE statements per hour is approximately 5 delete operations per second. (Since we wish to be conservative in our estimate, we round up here and in the following calculations.) No columns are updated by deletes, so these statements consume only 5 operations * 72 bytes per operation = 360 bytes per second.
- 15000 UPDATE statements per hour is roughly the same as 5 updates per second. Each update uses 72 bytes, plus 4 bytes per column * 5 columns updated, plus 32 bytes per column * 5 columns—this works out to 72 + 20 + 160 = 252 bytes per operation, and multiplying this by 5 operation per second yields 1260 bytes per second.

• 15000 INSERT statements per hour is equivalent to 5 insert operations per second. Each insert requires REDO log space of 72 bytes, plus 4 bytes per record * 40 columns, plus 32 bytes per column * 40 columns, which is 72 + 160 + 1280 = 1512 bytes per operation. This times 5 operations per second yields 7560 bytes per second.

So the total number of REDO log bytes being written per second is approximately 0 + 360 + 1260 + 7560 = 9180 bytes. Multiplied by 1800 seconds, this yields 16524000 bytes required for REDO logging, or approximately 15.75 MB. The unit used for NoOf-FragmentLogFiles represents a set of 4 16-MB log files—that is, 64 MB. Thus, the minimum value (3) for this parameter is sufficient for the scenario envisioned in this example, since 3 times 64 = 192 MB, or about 12 times what is required; the default value of 8 (or 512 MB) is more than ample in this case.

3.2.13. Configuring MySQL Cluster Send Buffer Parameters

Formerly, the NDB kernel used a send buffer whose size was fixed at 2MB for every node in the cluster, which was allocated when the node started. Because the size of this buffer could not be changed after the cluster was started, it was necessary to make it large enough in advance to accommodate the maximum possible load on any transporter socket. However, this was an inefficient use of memory, since much of it often went unused, and could result in large amounts of resources being wasted when scaling up to many API nodes.

Beginning with MySQL Cluster NDB 7.0, this problem is solved by employing a unified send buffer whose memory is allocated dynamically from a pool shared by all transporters. This means that the size of the send buffer can be adjusted as necessary. Configuration of the unified send buffer can accomplished by setting the following parameters:

• TotalSendBufferMemory. This parameter can be set for all types of MySQL Cluster nodes—that is, it can be set in the [ndbd], [mgm], and [api] (or [mysql]) sections of the config.ini file. It represents the total amount of memory (in bytes) to be allocated by each node for which it is set for use among all configured transporters. If set, its minimum is 256KB; the maximum is 4294967039.

To be backward-compatible with existing configurations, this parameter takes as its default value the sum of the maximum send buffer sizes of all configured transporters, plus an additional 32KB (one page) per transporter. The maximum depends on the type of transporter, as shown in the following table:

Transporter	Iaxmimum Send Buffer Size (bytes)			
TCP	SendBufferMemory (default = 2M)			
SCI	SendLimit (default = 8K) plus 16K			
SHM	20K			

This enables existing configurations to function in close to the same way as they did with MySQL Cluster NDB 6.3 and earlier, with the same amount of memory and send buffer space available to each transporter. However, memory that is unused by one transporter is not available to other transporters.

- OverloadLimit. This parameter is used in the config.ini file [tcp] section, and denotes the amount of unsent data (in bytes) that must be present in the send buffer before the connection is considered overloaded. When such an overload condition occurs, transactions that affect the overloaded connection fail with NDB API Error 1218 (SEND BUFFERS OVERLOADED IN NDB KERNEL) until the overload status passes. The default value is 0, in which case the effective overload limit is calculated as SendBufferMemory * 0.8 for a given connection. The maximum value for this parameter is 4G.
- SendBufferMemory. In MySQL Cluster NDB 6.3 and earlier, this TCP configuration parameter represented the amount of memory allocated at startup for each configured TCP connection. Beginning with MySQL Cluster NDB 7.0, this value denotes a hard limit for the amount of memory that may be used by a single transporter out of the entire pool specified by TotalSendBufferMemory. However, the sum of SendBufferMemory for all configured transporters may be greater than the TotalSendBufferMemory that is set for a given node. This is a way to save memory when many nodes are in use, as long as the maximum amount of memory is never required by all transporters at the same time.

3.3. Overview of MySQL Cluster Configuration Parameters

The next four sections provide summary tables of MySQL Cluster configuration parameters used in the config.ini file to govern the cluster's functioning. Each table lists the parameters for one of the Cluster node process types (ndbd, ndb_mgmd, and mysqld), and includes the parameter's type as well as its default, minimum, and maximum values as applicable.

These tables also indicate what type of restart is required (node restart or system restart)—and whether the restart must be done with --initial—to change the value of a given configuration parameter.

When performing a node restart or an initial node restart, all of the cluster's data nodes must be restarted in turn (also referred to as

a *rolling restart*). It is possible to update cluster configuration parameters marked as node online—that is, without shutting down the cluster—in this fashion. An initial node restart requires restarting each ndbd process with the --initial option.

A system restart requires a complete shutdown and restart of the entire cluster. An initial system restart requires taking a backup of the cluster, wiping the cluster file system after shutdown, and then restoring from the backup following the restart.

In any cluster restart, all of the cluster's management servers must be restarted for them to read the updated configuration parameter values.

Important

Values for numeric cluster parameters can generally be increased without any problems, although it is advisable to do so progressively, making such adjustments in relatively small increments. Many of these can be increased online, using a rolling restart.

However, decreasing the values of such parameters—whether this is done using a node restart, node initial restart, or even a complete system restart of the cluster—is not to be undertaken lightly; it is recommended that you do so only after careful planning and testing. This is especially true with regard to those parameters that relate to memory usage and disk space, such as MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes. In addition, it is the generally the case that configuration parameters relating to memory and disk usage can be raised using a simple node restart, but they require an initial node restart to be lowered.

Because some of these parameters can be used for configuring more than one type of cluster node, they may appear in more than one of the tables.

Note

4294967039 often appears as a maximum value in these tables. This value is defined in the NDBCLUSTER sources as MAX INT RNIL and is equal to $0 \times FFFFFEFF$, or $2^{32} - 2^8 - 1$.

3.3.1. MySQL Cluster Data Node Configuration Parameters

The summary table in this section provides information about parameters used in the [ndbd] or [ndbd default] sections of a config.ini file for configuring MySQL Cluster data nodes. For detailed descriptions and other additional information about each of these parameters, see Section 3.2.6, "Defining MySQL Cluster Data Nodes".

Beginning with MySQL Cluster NDB 6.4.0, these parameters also apply to ndbmtd, which is a multi-threaded version of ndbd. For more information, see Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

Restart types. Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

For more information about restart types, see Section 3.3, "Overview of MySQL Cluster Configuration Parameters".

Table 3.1. Data Node Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Arbitration	{Disabled Default WaitEx ternal}	Default			N
ArbitrationTimeout	milliseconds	3000	10	4G	N
BackupDataBufferSize	bytes	2M		4G	N
BackupDataDir	path	FileSystemPath			IN
BackupLogBufferSize	bytes	2M		4G	N
BackupMaxWriteSize	bytes	256K	2K	4G	N
BackupMemory	bytes	4M		4G	N
BackupReportFrequency	seconds			4G	N
BackupWriteSize	bytes	32K	2K	4G	N

Name	Type/Units	Default	Min Value	Max Value	Restart Type
BatchSizePerLocalScan	integer	64	1	992	N
BuildIndexThreads				128	
CompressedBackup		false			N
CompressedLCP		false			N
DataDir	path				IN
DataMemory	bytes	80M	1M	1024G	N
DictTrace	bytes	undefined		100	N
DiskCheckpointSpeed	bytes	10M	1M	4G	N
DiskCheckpointSpeedIn- Restart	bytes	100M	1M	4G	N
DiskIOThreadPool	threads	8		4G	N
Diskless	true false (1 0)			1	IS
DiskPageBufferMemory	bytes	64M	4M	1T	N
DiskSyncSize	bytes	4M	32K	4G	N
ExecuteOnComputer	name				S
FileSystemPath	path	DataDir			IN
FileSystemPathDataFiles		FileSystemPath- DD			IN
FileSystemPathDD		FileSystemPath			IN
FileSystemPathUndoFiles		FileSystemPath-DD			IN
FragmentLogFileSize	bytes	16M	4M	1G	IN
HeartbeatIntervalDbApi	milliseconds	1500	100	4G	N
HeartbeatIntervalDbDb	milliseconds	1500	10	4G	N
HeartbeatOrder				65535	S
HostName	name or IP address	localhost			S
Id	unsigned		1	48	N
IndexMemory	bytes	18M	1M	1T	N
InitFragmentLogFiles	sparse full				IN
InitialLogFileGroup		[see documenta-tion]			S
InitialNoOfOpenFiles	files	27	20	4G	N
InitialTablespace		[see documentation]			S
IOThreadPool	threads	8		4G	N
LockEx- ecuteThreadToCPU	CPU ID	64K		64K	N
LockMaintThread-sToCPU	CPU ID	64K		64K	N
LockPagesInMain- Memory	true false (1 0)			1	N
LogLevelCheckpoint	log level			15	IN
LogLevelCongestion	levelr			15	N
LogLevelConnection	integer			15	N
LogLevelError	integer			15	N
LogLevelInfo	integer			15	N
LogLevelNodeRestart	integer			15	N
LogLevelShutdown	integer			15	N
LogLevelStartup	integer	1		15	N
LogLevelStatistic	integer			15	N

Name	Type/Units	Default	Min Value	Max Value	Restart Type
LongMessageBuffer	bytes	1M	512K	4G	N
MaxAllocate	unsigned	32M	1M	1G	N
MaxBufferedEpochs	epochs	100		100000	N
MaxDMLOperationsPer- Transaction	operations (DML)	4294967295	32	4294967295	N
MaxLCPStartDelay	seconds			600	N
MaxNoOfAttributes	integer	1000	32	4G	N
MaxNoOfConcurrentIn- dexOperations	integer	8K		4G	N
MaxNoOfConcurrent- Operations	integer	32K	32	4G	N
MaxNoOfConcurrentS- cans	integer	256	2	500	N
MaxNoOfConcurrentSub- Operations	unsigned	256		4G	N
MaxNoOfConcurrent- Transactions	integer	4096	32	4G	S
MaxNoOfFiredTriggers	integer	4000		4G	N
MaxNoOfLocalOperations	integer	UNDEFINED	32	4G	N
MaxNoOfLocalScans	integer	UNDEFINED	32	4G	N
MaxNoOfOpenFiles	integer	40	20	4G	N
MaxNoOfOrderedIndexes	integer	128		4G	N
MaxNoOfSavedMessages	integer	25		4G	N
MaxNoOfSubscribers	unsigned			4G	N
MaxNoOfSubscriptions	unsigned			4G	N
MaxNoOfTables	integer	128	8	20320	N
MaxNoOfTriggers	integer	768		4G	N
MaxNoOfUnique- HashIndexes	integer	64		4G	N
MaxParallelScansPer- Fragment	bytes	32	1	1G	N
MaxStartFailRetries	unsigned	3		4G	N
MemReportFrequency	unsigned			4G	N
NodeGroup				65536	IS
NodeId	unsigned		1	48	N
NoOf- DiskPagesToDiskAfter- RestartACC	8K pages/100 milli- seconds	20	1	4G	N
NoOf- DiskPagesToDiskAfter- RestartTUP	8K pages/100 milli- seconds	40	1	4G	N
NoOfDiskPagesToDisk- DuringRestartACC	8K pages/100 milli- seconds	20	1	4G	N
NoOfDiskPagesToDisk- DuringRestartTUP	8K pages/100 milli- seconds	40	1	4G	N
NoOfFragmentLogFiles	integer	16	3	4G	IN
NoOfReplicas	integer	None	1	4	IS
Numa					N
ODirect	boolean			1	N
RealtimeScheduler		false			N
RedoBuffer	bytes	8M	1M	4G	N
RedoOverCommit-		3		4G	N

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Counter					
RedoOverCommitLimit	seconds	20		4G	N
ReservedSendBuffer- Memory	bytes	256K		4G	N
RestartOnErrorInsert	error code	2		4	N
SchedulerExecutionTimer	μsec	50		11000	N
SchedulerSpinTimer	μsec			500	N
ServerPort	unsigned		1	64K	N
SharedGlobalMemory	bytes	20M		64T	N
StartFailRetryDelay	unsigned			4G	N
StartFailureTimeout	milliseconds			4G	N
StartNoNodeGroup- Timeout	milliseconds	15000		4294967039	N
StartPartialTimeout	milliseconds	30000		4G	N
StartPartitionedTimeout	milliseconds	60000		4G	N
StartupStatusReportFrequency	seconds				N
StopOnError	true false (1 0)	true			N
StringMemory	% or bytes	5		4G	S
Tcp- Bind_INADDR_ANY		false			N
TimeBetweenEpochs	milliseconds	100		32000	N
TimeBetweenEpochs- Timeout	milliseconds	4000		32000	N
TimeBetweenGlobal-Checkpoints	milliseconds	2000	10	32000	N
TimeBetweenInactiv- eTransactionAbortCheck	milliseconds	1000	1000	4G	N
TimeBetweenLocal-Checkpoints	number of 4-byte words, as a base-2 logarithm	20		31	N
TimeBetweenWatchDo- gCheck	milliseconds	6000	70	4G	N
TimeBetweenWatchDo- gCheckInitial	milliseconds	6000	70	4G	N
TotalSendBufferMemory	bytes	256K		4G	N
TransactionBuffer- Memory	bytes	1M	1K	4G	N
TransactionDeadlockDetectionTimeout	milliseconds	1200	50	4G	N
TransactionInactive- Timeout	milliseconds	4G		4G	N
TwoPassInitialNodeRestart		FALSE			N
UndoDataBuffer	unsigned	16M	1M	4G	N
UndoIndexBuffer	unsigned	2M	1M	4G	N

Note

Prior to MySQL Cluster NDB 7.0, to add new data nodes to a MySQL Cluster, it is necessary to shut down the cluster completely, update the config.ini file, and then restart the cluster, starting all data node processes using the --initial option—that is, you must perform a system restart.

Beginning in MySQL Cluster NDB 7.0, it is possible to add new data node groups to a running cluster online. For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".

3.3.2. MySQL Cluster Management Node Configuration Parameters

The summary table in this section provides information about parameters used in the <code>[ndb_mgmd]</code> or <code>[mgm]</code> sections of a config.ini file for configuring MySQL Cluster management nodes. For detailed descriptions and other additional information about each of these parameters, see Section 3.2.5, "Defining a MySQL Cluster Management Server".

Restart types. Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

For more information about restart types, see Section 3.3, "Overview of MySQL Cluster Configuration Parameters".

Table 3.2. Management Node Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
ArbitrationDelay	milliseconds			4G	N
ArbitrationRank	0-2	1		2	N
DataDir	path				N
ExecuteOnComputer	name				S
HeartbeatThreadPriority		none			
HostName	name or IP address				S
Id	unsigned		1	63	N
LogDestination	{CONSOLE SYSLOG FI LE}	FILE:filename=n db_nodeid_cluste r.log,maxsize=10 00000,maxfiles= 6			N
MaxNoOfSavedEvents	unsigned	100		4G	N
NodeId	unsigned		1	63	N
PortNumber	unsigned	1186		64K	N
PortNumberStats	unsigned			64K	N
wan		false			N

Note

After making changes in a management node's configuration, it is necessary to perform a rolling restart of the cluster for the new configuration to take effect. See Section 3.2.5, "Defining a MySQL Cluster Management Server", for more information.

To add new management servers to a running MySQL Cluster, it is also necessary perform a rolling restart of all cluster nodes after modifying any existing config.ini files. For more information about issues arising when using multiple management nodes, see Section 1.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

3.3.3. MySQL Cluster SQL Node and API Node Configuration Parameters

The summary table in this section provides information about parameters used in the [mysqld] and [api] sections of a config.ini file for configuring MySQL Cluster SQL nodes and API nodes. For detailed descriptions and other additional information about each of these parameters, see Section 3.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

Note

For a discussion of MySQL server options for MySQL Cluster, see Section 3.4.2, "mysqld Command Options for MySQL Cluster"; for information about MySQL server system variables relating to MySQL Cluster, see Section 3.4.3, "MySQL Cluster System Variables".

Restart types. Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

For more information about restart types, see Section 3.3, "Overview of MySQL Cluster Configuration Parameters".

Table 3.3. SQL Node/API Node Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
ArbitrationDelay	milliseconds			4G	N
ArbitrationRank	0-2			2	N
AutoReconnect		false	false	true	N
BatchByteSize	bytes	32K	1024	1M	N
BatchSize	records	64	1	992	N
ConnectionMap					N
DefaultOperationRedo- ProblemAction					
ExecuteOnComputer	name				S
HeartbeatThreadPriority		none			
HostName	name or IP address				S
Id	unsigned		1	63	N
MaxScanBatchSize	bytes	256K	32K	16M	N
NodeId	unsigned		1	63	N
TotalSendBufferMemory	bytes	256K		4G	N
wan		false			N

Note

To add new SQL or API nodes to the configuration of a running MySQL Cluster, it is necessary to perform a rolling restart of all cluster nodes after adding new [mysqld] or [api] sections to the config.ini file (or files, if you are using more than one management server). This must be done before the new SQL or API nodes can connect to the cluster.

It is *not* necessary to perform any restart of the cluster if new SQL or API nodes can employ previously unused API slots in the cluster configuration to connect to the cluster.

3.3.4. Other MySQL Cluster Configuration Parameters

The summary tables in this section provide information about parameters used in the <code>[computer]</code>, <code>[tcp]</code>, <code>[shm]</code>, and <code>[sci]</code> sections of a <code>config.ini</code> file for configuring MySQL Cluster management nodes. For detailed descriptions and other additional information about individual parameters, see Section 3.2.8, "MySQL Cluster TCP/IP Connections", Section 3.2.10, "MySQL Cluster Shared-Memory Connections", or Section 3.2.11, "SCI Transport Connections in MySQL Cluster", as appropriate.

Restart types. Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary tables as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

For more information about restart types, see Section 3.3, "Overview of MySQL Cluster Configuration Parameters".

Table 3.4. COMPUTER Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
HostName	name or IP address				S
Id	string				IN

Table 3.5. TCP Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Checksum		false			N
Group	unsigned	55		200	N
NodeId1					N
NodeId2					N
NodeIdServer					N
OverloadLimit	bytes			4G	N
PortNumber	unsigned			64K	N
Proxy					N
ReceiveBufferMemory	bytes	64K	16K	4G	N
SendBufferMemory	unsigned	256K	64K	4G	N
SendSignalId		false (debug builds: true)			N
TCP_MAXSEG_SIZE	unsigned			2G	N
TCP_RCV_BUF_SIZE	unsigned	70080	1	2G	N
TCP_SND_BUF_SIZE	unsigned	71540	1	2G	N
Tcp- Bind_INADDR_ANY		false			N

Table 3.6. SHM Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Checksum		true			N
Group	unsigned	35		200	N
NodeId1					N
NodeId2					N
NodeIdServer					N
OverloadLimit	bytes			4G	N
PortNumber	unsigned			64K	N
SendSignalId		false			N
ShmKey	unsigned			4G	N
ShmSize	bytes	1M	64K	4G	N
Signum	unsigned			4G	N

Table 3.7. SCI Configuration Parameters

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Checksum		false			N
Group	unsigned	15		200	N
Host1SciId0	unsigned			4G	N

Name	Type/Units	Default	Min Value	Max Value	Restart Type
Host1SciId1	unsigned			4G	N
Host2SciId0	unsigned			4G	N
Host2SciId1	unsigned			4G	N
NodeId1					N
NodeId2					N
NodeIdServer					N
OverloadLimit	bytes			4G	N
PortNumber	unsigned			64K	N
SendLimit	unsigned	8K	128	32K	N
SendSignalId		true			N
SharedBufferSize	unsigned	10M	64K	4G	N

3.4. MySQL Server Options and Variables for MySQL Cluster

This section provides information about MySQL server options, server and status variables that are specific to MySQL Cluster. For general information on using these, and for other options and variables not specific to MySQL Cluster, see The MySQL Server.

For MySQL Cluster configuration parameters used in the cluster confiuration file (usually named config.ini), see Chapter 3, MySQL Cluster Configuration.

3.4.1. MySQL Cluster Server Option and Variable Reference

The following table provides a list of the command-line options, server and status variables applicable within mysqld when it is running as an SQL node in a MySQL Cluster. For a table showing *all* command-line options, server and status variables available for use with mysqld, see Server Option and Variable Reference.

Table 3.8. Command Options for MySQL Cluster

Name	Cmd-Line	Option file	System Var	Status Var	Var Scope	Dynamic
Handler_discover				Yes	Both	No
have_ndbcluster			Yes		Global	No
ndb_autoincrement_pr efetch_sz	Yes	Yes	Yes		Both	Yes
ndb-batch-size	Yes	Yes	Yes		Global	No
ndb- blob-read-batch-bytes	Yes	Yes	Yes		Both	Yes
ndb- blob-write-batch-bytes	Yes	Yes	Yes		Both	Yes
ndb_cache_check_tim e	Yes	Yes	Yes		Global	Yes
ndb- cluster-connec- tion-pool	Yes	Yes	Yes	Yes	Global	No
Ndb_cluster_node_id				Yes	Both	No
Ndb_config_from_hos t				Yes	Both	No
Ndb_config_from_por t				Yes	Both	No
Ndb_conflict_fn_max				Yes	Global	No
Ndb_conflict_fn_old				Yes	Global	No
ndb-connectstring	Yes	Yes				
ndb_execute_count				Yes	Global	No
ndb_extra_logging	Yes	Yes	Yes		Global	Yes
ndb_force_send	Yes	Yes	Yes		Both	Yes

Name	Cmd-Line	Option file	System Var	Status Var	Var Scope	Dynamic
ndb_index_stat_cache _entries	Yes	Yes				
ndb_index_stat_enabl e	Yes	Yes				
ndb_index_stat_updat e_freq	Yes	Yes				
ndb_join_pushdown			Yes		Global	No
ndb-log-apply-status	Yes	Yes			Global	No
- Variable: ndb_log_apply_status			Yes		Global	No
ndb_log_bin	Yes		Yes		Both	Yes
ndb_log_binlog_index	Yes		Yes		Global	Yes
ndb_log_empty_epoc hs	Yes	Yes	Yes		Global	Yes
ndb_log_orig			Yes		Global	No
ndb- log-update-as-write	Yes	Yes	Yes		Global	Yes
ndb_log_updated_onl y	Yes	Yes	Yes		Global	Yes
ndb-mgmd-host	Yes	Yes				
ndb-nodeid	Yes	Yes		Yes	Global	No
Ndb_number_of_data _nodes				Yes	Global	No
ndb_optimization_del ay			Yes		Global	Yes
ndb_optimized_node_ selection	Yes	Yes				
ndb_pruned_scan_cou nt				Yes	Global	No
ndb_pushed_queries_ defined				Yes	Global	No
ndb_pushed_queries_ dropped				Yes	Global	No
ndb_pushed_queries_ executed				Yes	Global	No
ndb_pushed_reads				Yes	Global	No
ndb_report_thresh_bin log_epoch_slip	Yes	Yes				
ndb_report_thresh_bin log_mem_usage	Yes	Yes				
ndb_scan_count				Yes	Global	No
ndb_table_no_logging			Yes		Session	Yes
ndb_table_temporary			Yes		Session	Yes
ndb_use_copying_alte r_table			Yes		Both	No
ndb_use_exact_count			Yes		Both	Yes
ndb_use_transactions	Yes	Yes	Yes		Both	Yes
ndb-wait-connected	Yes	Yes	Yes		Global	No
ndb-wait-setup	Yes	Yes	Yes		Global	No
ndbcluster	Yes	Yes				
- Variable: have_ndbcluster						
ndbinfo_database			Yes		Global	No

Name	Cmd-Line	Option file	System Var	Status Var	Var Scope	Dynamic
ndbinfo_max_bytes	Yes		Yes		Both	Yes
ndbinfo_max_rows	Yes		Yes		Both	Yes
ndbinfo_show_hidden	Yes		Yes		Both	Yes
ndbinfo_table_prefix	Yes		Yes		Both	Yes
ndbinfo_version			Yes		Global	No
server-id-bits	Yes	Yes			Global	No
- <i>Variable</i> : serv- er_id_bits			Yes		Global	No
skip-ndbcluster	Yes	Yes				
slave_allow_batching	Yes	Yes	Yes		Global	Yes

3.4.2. mysqld Command Options for MySQL Cluster

This section provides descriptions of mysqld server options relating to MySQL Cluster. For information about mysqld options not specific to MySQL Cluster, and for general information about the use of options with mysqld, see Server Command Options.

For information about command-line options used with other MySQL Cluster processes (ndbd, ndb_mgmd, and ndb_mgm), see Section 4.23, "Options Common to MySQL Cluster Programs". For information about command-line options used with NDB utility programs (such as ndb_desc, ndb_size.pl, and ndb_show_tables), see Chapter 4, MySQL Cluster Programs.

--ndb-batch-size=#

Version Introduced	5.1.23-ndb	5.1.23-ndb-6.3.8		
Command-Line Format	ndb-b	ndb-batch-size		
Option-File Format	ndb-bat	ch-size		
Variable Name	ndb_bat	ndb_batch_size		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitted	Values		
	Type	numeric		
	Default	Default 32768 Range 0-31536000		
	Range			

This sets the size in bytes that is used for NDB transaction batches.

• --ndb-cluster-connection-pool=#

Version Introduced	5.1.19-ndb-	5.1.19-ndb-6.2.2		
Command-Line Format	ndb-cl	ndb-cluster-connection-pool		
Option-File Format	ndb-clus	db-cluster-connection-pool		
Variable Name	ndb_clus	ster_connection_pool		
Variable Scope	Global	Global		
Dynamic Variable	No			
	Permitted	Values		
	Type	Type numeric		
	Default 1			
	Range	Range 1-63		

By setting this option to a value greater than 1 (the default), a mysqld process can use multiple connections to the cluster, effectively mimicking several SQL nodes. Each connection requires its own [api] or [mysqld] section in the cluster configuration (config.ini) file, and counts against the maximum number of API connections supported by the cluster.

Suppose that you have 2 cluster host computers, each running an SQL node whose mysqld process was started with - -ndb-cluster-connection-pool=4; this means that the cluster must have 8 API slots available for these connections (instead of 2). All of these connections are set up when the SQL node connects to the cluster, and are allocated to threads in a round-robin fashion.

This option is useful only when running mysqld on host machines having multiple CPUs, multiple cores, or both. For best results, the value should be smaller than the total number of cores available on the host machine. Setting it to a value greater than this is likely to degrade performance severely.

Important

Because each SQL node using connection pooling occupies multiple API node slots—each slot having its own node ID in the cluster—you must *not* use a node ID as part of the cluster connectstring when starting any mysqld process that employs connection pooling.

Setting a node ID in the connectstring when using the --ndb-cluster-connection-pool option causes node ID allocation errors when the SQL node attempts to connect to the cluster.

This option was introduced in MySQL Cluster NDB 6.2.2. Beginning with MySQL Cluster NDB 6.2.16 and MySQL Cluster NDB 6.3.13, the value used for this option is available as a system variable (Bug #35573).

Prior to MySQL Cluster NDB 7.0.23 and MySQL Cluster NDB 7.1.12, there was also a status variable corresponding to this option; however, the status variable was removed as redundant as of these versions. (Bug #60119)

• --ndb-blob-read-batch-bytes=bytes

Version Introduced	5.1.51-ndb	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10		
Command-Line Format	ndb-b	ndb-blob-read-batch-bytes		
Option-File Format	ndb-blol	ndb-blob-read-batch-bytes		
Variable Name	ndb_blol	ndb_blob_read_batch_bytes		
Variable Scope	Global, Ses	Global, Session		
Dynamic Variable	Yes	Yes		
	Permitted	Values		
	Type	numeric		
	Default	Default 65535		
	Range	0-4294967295		

This option can be used to set the size (in bytes) for batching of BLOB data reads in MySQL Cluster applications. When this batch size is exceeded by the amount of BLOB data to be read within the current transaction, any pending BLOB read operations are immediately executed.

The maximum value for this option is 4294967295; the default is 65535. Setting it to 0 has the effect of disabling BLOB read batching.

Note

In NDB API applications, you can control BLOB write batching with the setMaxPendingBlobReadBytes() and getMaxPendingBlobReadBytes() methods.

This option was introduced in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

• --ndb-blob-write-batch-bytes=bytes

Version Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10
Command-Line Format	ndb-blob-write-batch-bytes
Option-File Format	ndb-blob-write-batch-bytes
Variable Name	ndb_blob_write_batch_bytes
Variable Scope	Global, Session
Dynamic Variable	Yes

Permitted	Values
Type	numeric
Default	65535
Range	0-4294967295

This option can be used to set the size (in bytes) for batching of BLOB data writes in MySQL Cluster applications. When this batch size is exceeded by the amount of BLOB data to be written within the current transaction, any pending BLOB write operations are immediately executed.

The maximum value for this option is 4294967295; the default is 65535. Setting it to 0 has the effect of disabling BLOB write batching.

Note

In NDB API applications, you can control BLOB write batching with the setMaxPendingBlobWriteBytes() and getMaxPendingBlobWriteBytes() methods.

This option was introduced in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

--ndb-connectstring=connect_string

Command-Line Format	ndb-cc	ndb-connectstring		
Option-File Format	ndb-conn	ndb-connectstring		
	Permitted Values			
	Type	string		

When using the NDBCLUSTER storage engine, this option specifies the management server that distributes cluster configuration data. See Section 3.2.3, "The MySQL Cluster Connectstring", for syntax.

• --ndbcluster

Command-Line Format	ndbclu	ndbcluster		
Option-File Format	ndbclust	dbcluster		
Option Sets Variable	Yes, have	Yes, have_ndbcluster		
Disabled by	skip-ndk	skip-ndbcluster		
	Permitted Values			
	Type	Type boolean		
	Default	FALSE		

The NDBCLUSTER storage engine is necessary for using MySQL Cluster. If a mysqld binary includes support for the NDB-CLUSTER storage engine, the engine is disabled by default. Use the --ndbcluster option to enable it. Use --skip-ndbcluster to explicitly disable the engine.

• --ndb-log-apply-status

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10		
Command-Line Format	ndb-lo	ndb-log-apply-status		
Option-File Format	ndb-log-	ndb-log-apply-status		
Option Sets Variable	Yes, ndb_	log_apply_status		
Variable Name	ndb_log_apply_status			
Variable Scope	Global	Global		
Dynamic Variable	No			
	Permitted	Permitted Values		
	Type boolean			
	Default	ON		

Causes a slave mysqld to log any updates received from its immediate master to the mysql.ndb_apply_status table in its own binary log using its own server ID rather than the server ID of the master. In a circular or chain replication setting, this allows such updates to propagate to the mysql.ndb_apply_status tables of any MySQL servers configured as slaves of the current mysqld.

In a chain replication setup, using this option allows downstream (slave) clusters to be aware of their positions relative to all of their upstream contributors (masters).

In a circular replication setup, this option causes changes to ndb_apply_status tables to complete the entire circuit, eventually propagating back to the originating MySQL Cluster. This also allows a cluster acting as a master to see when its changes (epochs) have been applied to the other clusters in the circle.

This option was added in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10. It has no effect unless the MySQL server is started with the --ndbcluster option.

• --ndb-nodeid=#

Version Introduced	5.1.15	5.1.15		
Command-Line Format	ndb-1	ndb-nodeid=#		
Option-File Format	ndb-noo	ndb-nodeid		
Variable Name	Ndb_cl	Ndb_cluster_node_id		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitte	d Values (>= 5.1.5)		
	Type	Type numeric		
	Range	1-255		

Set this MySQL server's node ID in a MySQL Cluster.

Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option can be used *instead* of specifying the node ID as part of the connectstring or in the config.ini file, or permitting the cluster to determine an arbitrary node ID. If you use this option, then --ndb-nodeid must be specified *before* --ndb-connectstring. If --ndb-nodeid is used *and* a node ID is specified in the connectstring, then the MySQL server cannot connect to the cluster.

Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the --ndb-nodeid option *overrides* any node ID set with --ndb-connectstring, regardless of the order in which the two options are used.

In addition (regardless of the MySQL Cluster version), if --ndb-nodeid is used, then either a matching node ID must be found in a [mysqld] or [api] section of config.ini, or there must be an "open" [mysqld] or [api] section in the file (that is, a section without a NodeId or Id parameter specified). This is also true if the node ID is specified as part of the connectstring.

Regardless of how the node ID is determined, its is shown as the value of the global status variable Ndb_cluster_node_id in the output of SHOW STATUS, and as cluster_node_id in the connection row of the output of SHOW ENGINE NDBCLUSTER STATUS.

For more information about node IDs for MySQL Cluster SQL nodes, see Section 3.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

--server-id-bits=#

Version Introduced	5.1.47-ndb-7.0.17, 5.1.47-ndb-7.1.6		
Command-Line Format	server-id-bits=#		
Option-File Format	server-id-bits		
Option Sets Variable	Yes, server_id_bits		
Variable Name	server_id_bits		
Variable Scope	Global		
Dynamic Variable	No		

	Permitted	Values
	Type	numeric
	Default	32
	Range	7–32

This option indicates the number of least significant bits within the 32-bit server_id which actually identify the server. Indicating that the server is actually identified by fewer than 32 bits makes it possible for some of the remaining bits to be used for other purposes, such as storing user data generated by applications using the NDB API's Event API within the AnyValue of an OperationOptions structure (MySQL Cluster uses the AnyValue to store the server ID).

When extracting the effective server ID from server_id for purposes such as detection of replication loops, the server ignores the remaining bits. The --server-id-bits option is used to mask out any irrelevant bits of server_id in the IO and SQL threads when deciding whether an event should be ignored based on the server ID.

This data can be read from the binary log by mysqlbinlog, provided that it is run with its own --server-id-bits option set to 32 (the default).

The value of server_id must be less than 2 ^ server_id_bits; otherwise, mysqld refuses to start.

This system variable was added in MySQL Cluster NDB 7.0.17 and MySQL Cluster NDB 7.1.6; it is supported only in these and later releases of MySQL Cluster. It is not supported by the standard MySQL Server.

• --skip-ndbcluster

Command-Line Format	skip-ndbcluster			
Option-File Format	skip-ndbcluster			

Disable the NDBCLUSTER storage engine. This is the default for binaries that were built with NDBCLUSTER storage engine support; the server allocates memory and other resources for this storage engine only if the --ndbcluster option is given explicitly. See Section 3.1, "Quick Test Setup of MySQL Cluster", for an example.

• --ndb-wait-connected=seconds

Version Introduced	5.1.16-ndb	5.1.16-ndb-6.2.0		
Command-Line Format	ndb-wa	ait-connected=#		
Option-File Format	ndb-wait	t-connected		
Variable Name	ndb-wait	ndb-wait-connected		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitted	Permitted Values		
	Type	Type numeric		
	Default 0 Range 0-31536000			

This option sets the period of time that the MySQL server waits for connections to MySQL Cluster management and data nodes to be established before accepting MySQL client connections. The time is specified in seconds. The default value is 0.

• --ndb-wait-setup=seconds

Version Introduced	5.1.39-ndb-6.2.19, 5.1.39-ndb-6.3.28, 5.1.39-ndb-7.0.9		
Command-Line Format	ndb-wait-setup=#		
Option-File Format	ndb-wait-setup		
Variable Name	ndb-wait-setup		
Variable Scope	Global		
Dynamic Variable	No		

	Permitted	Values
	Type	numeric
	Default	15
	Range	0-31536000

This variable shows the period of time that the MySQL server waits for the NDB storage engine to complete setup before timing out and treating NDB as unavailable. The time is specified in seconds. The default value is 15.

3.4.3. MySQL Cluster System Variables

This section provides detailed information about MySQL server system variables that are specific to MySQL Cluster and the NDB storage engine. For system variables not specific to MySQL Cluster, see Server System Variables. For general information on using system variables, see Using System Variables.

• have_ndbcluster

Variable Name	have_ndbcluster		
Variable Scope	Global		
Dynamic Variable	No		
	Permitted Values		
	Type	boolean	

YES if mysqld supports NDBCLUSTER tables. DISABLED if --skip-ndbcluster is used.

This variable is deprecated and is removed in MySQL 5.6. Use SHOW ENGINES instead.

• multi_range_count

Command-Line Format	multi	multi_range_count=#		
Option-File Format	multi_ra	ange_count		
Option Sets Variable	Yes, mult	i_range_count		
Variable Name	multi_ra	multi_range_count		
Variable Scope	Global, Sea	Global, Session		
Dynamic Variable	Yes	Yes		
	Permitted	Permitted Values		
	Type	Type numeric		
	Default			
	Range			

The maximum number of ranges to send to a table handler at once during range selects. The default value is 256. Sending multiple ranges to a handler at once can improve the performance of certain selects dramatically. This is especially true for the NDBCLUSTER table handler, which needs to send the range requests to all nodes. Sending a batch of those requests at once reduces communication costs significantly.

This variable is deprecated in MySQL 5.1, and is no longer supported in MySQL 5.5, in which arbitrarily long lists of ranges can be processed.

ndb_autoincrement_prefetch_sz

Command-Line Format	ndb_autoincrement_prefetch_sz		
Option-File Format	ndb_autoincrement_prefetch_sz		
Option Sets Variable	Yes, ndb_autoincrement_prefetch_sz		
Variable Name	ndb_autoincrement_prefetch_sz		
Variable Scope	Global, Session		

Dynamic Variable	Yes	
	Permitted	Values (<= 5.1.22)
	Type	numeric
	Default	32
	Range	1-256
	Permitted Values (>= 5.1.23)	
	Type	numeric
	Default	1
	Range	1-256

Determines the probability of gaps in an autoincremented column. Set it to 1 to minimize this. Setting it to a high value for optimization—makes inserts faster, but decreases the likelihood that consecutive autoincrement numbers will be used in a batch of inserts. Default value: 32. Minimum value: 1.

Beginning with MySQL Cluster NDB 6.2.10, MySQL Cluster NDB 6.3.7, and MySQL 5.1.23, this variable affects the number of AUTO_INCREMENT IDs that are fetched between statements only. Within a statement, at least 32 IDs are now obtained at a time. The default value for ndb_autoincrement_prefetch_sz is now 1, to increase the speed of statements inserting single rows. (Bug #31956)

Beginning with MySQL Cluster NDB 6.3.31 and MySQL CLuster NDB 7.0.11, the maximum value for ndb_autoincrement_prefetch_sz is increased, from 256 to 65536. (Bug #50621)

• ndb_cache_check_time

Command-Line Format	ndb_cache_check_time			
Option-File Format	ndb_cach	ndb_cache_check_time		
Option Sets Variable	Yes, ndb_e	Yes, ndb_cache_check_time		
Variable Name	ndb_cach	ndb_cache_check_time		
Variable Scope	Global			
Dynamic Variable	Yes			
	Permitted Values			
	Type numeric			
	Default 0			

The number of milliseconds that elapse between checks of MySQL Cluster SQL nodes by the MySQL query cache. Setting this to 0 (the default and minimum value) means that the query cache checks for validation on every query.

The recommended maximum value for this variable is 1000, which means that the check is performed once per second. A larger value means that the check is performed and possibly invalidated due to updates on different SQL nodes less often. It is generally not desirable to set this to a value greater than 2000.

ndb_extra_logging

Version Introduced	5.1.6			
Command-Line Format	ndb_extr	ra_logging=#		
Option-File Format	ndb_extr	ra_logging		
Variable Name	ndb_extr	ndb_extra_logging		
Variable Scope	Global	Global		
Dynamic Variable	Yes			
	Permitted	Permitted Values		
	Type	Type numeric		
	Default 0			

This variable can be used to enable recording in the MySQL error log of information specific to the NDB storage engine. It is

normally of interest only when debugging NDB storage engine code.

The default value is 0, which means that the only NDB-specific information written to the MySQL error log relates to transaction handling. If the value is greater than 0 but less than 10, NDB table schema and connection events are also logged, as well as whether or not conflict resolution is in use, and other NDB errors and information. If the value is set to 10 or more, information about NDB internals, such as the progress of data distribution among cluster nodes, is also written to the MySQL error log.

This variable was added in MySQL 5.1.6.

• ndb_force_send

Command-Line Format	ndb-force-send		
Option-File Format	ndb_force_send		
Option Sets Variable	Yes, ndb_force_send		
Variable Name	ndb_force_send		
Variable Scope	Global, Session		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default TRUE		

Forces sending of buffers to NDB immediately, without waiting for other threads. Defaults to ON.

• ndb_index_stat_cache_entries

Version Removed	5.1.14			
Command-Line Format	ndb_ir	ndb_index_stat_cache_entries		
Option-File Format	ndb_index_stat_cache_entries			
	Permitted Values			
	Type	Type numeric		
	Default	Default 32		
	Range 0-4294967295			

Sets the granularity of the statistics by determining the number of starting and ending keys to store in the statistics memory cache. Zero means no caching takes place; in this case, the data nodes are always queried directly. Default value: 32.

Note

If $ndb_index_stat_enable$ is OFF, then setting this variable has no effect.

• ndb_index_stat_enable

Version Removed	5.1.19		
Command-Line Format	ndb_ir	ndb_index_stat_enable	
Option-File Format	ndb_inde	ndb_index_stat_enable	
	Permitted	Permitted Values	
	Type	Type boolean	
	Default	Default OFF	

Use NDB index statistics in query optimization. Defaults to ON.

ndb_index_stat_update_freq

Version Removed	5.1.14	
Command-Line Format	ndb_index_stat_update_freq	
Option-File Format	ndb_index_stat_update_freq	

Permitted Values	
Type	numeric
Default	20
Range	0-4294967295

How often to query data nodes instead of the statistics cache. For example, a value of 20 (the default) means to direct every 20th query to the data nodes.

Note

If ndb_index_stat_cache_entries is 0, then setting this variable has no effect; in this case, every query is sent directly to the data nodes.

• ndb join pushdown

Version Introduced	5.1.51-ndb	5.1.51-ndb-7.2.0		
Variable Name	ndb_joi	ndb_join_pushdown		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitted	Permitted Values		
	Type	**		
	Default			

Added in MySQL Cluster NDB 7.2.0, this variable controls whether joins on NDB tables are pushed down to the NDB kernel (data nodes). Previously, a join was handled using multiple accesses of NDB by the SQL node; however, when ndb_join_pushdown is enabled, a pushable join is sent in its entirety to the data nodes, where it can be distributed among the data nodes and executed in parallel on multiple copies of the data, with a single, merged result being returned to mysqld. This can reduce greatly the number of round trips between an SQL node and the data nodes required to handle such a join.

By default, ndb_join_pushdown is enabled.

In order for a join to be pushable, it must meet the following conditions:

- Any columns to be joined must use *exactly* the same data type. (For example, if an INT and a BIGINT column are joined, the join cannot be pushed down.)
- Queries referencing BLOB or TEXT columns are not supported.
- Explicit locking is not supported; however, the NDB storage engine's characteristic implicit row-based locking is enforced.

 This means that a join using FOR UPDATE cannot be pushed down.
- In order for a join to be pushed down, child tables in the join must be accessed using one of the ref, eq_ref, or const access methods, or some combination of these methods.
- Joins referencing tables explicitly partitioned by [LINEAR] HASH, LIST, or RANGE currently cannot be pushed down.

You can see whether a given join can be pushed down by checking it with EXPLAIN; when the join can be pushed down, you can see references to the pushed join in the Extra column of the output, as shown in this example:

```
id: 1
select_type: SIMPLE
table: de
            type: ref
possible_keys: PRIMARY,emp_no,dept_no
key: dept_no
       key_len: 4
          id: 1
  select_type: SIMPLE table: e
type: eq_ref
possible_keys: PRIMARY
       key: PRIMARY
key_len: 4
             ref: employees.de.emp_no
           rows: 1
          rows: 1
Extra: Child of 'de' in pushed join@1
******************* 4. row *********
              id: 1
  select_type: SIMPLE table: t
type: ref
possible_keys: PRIMARY,emp_no
       key: emp_no
key_len: 4
           ref: employees.de.emp_no rows: 19
Extra: Child of 'e' in pushed join@1 4 rows in set (0.00 sec)
```

Two additional sources of information about pushed join performance are available:

- The status variables Ndb_pushed_queries_defined, Ndb_pushed_queries_dropped, Ndb_pushed_queries_executed, and Ndb_pushed_reads (all introduced in MySQL Cluster NDB 7.2.0).
- 2. The counters in the ndbinfo.counters table that belong to the DBSPJ kernel block. (These counters and the DBSPJ block were also introduced in MySQL Cluster NDB 7.2.0). See Section 5.9.3, "The ndbinfo counters Table", for information about these counters. See also The DBSPJ Block, in the MySQL Cluster API Developer Guide.
- ndb_log_apply_status

Version Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10			
Command-Line Format	ndb-l	ndb-log-apply-status		
Option-File Format	ndb-log	ndb-log-apply-status		
Option Sets Variable	Yes, ndb_	Yes, ndb_log_apply_status		
Variable Name	ndb_log	ndb_log_apply_status		
Variable Scope	Global			
Dynamic Variable	No			
	Permitted	Permitted Values		
	Type boolean			
	Default ON			

A read-only variable which shows whether the server was started with the --ndb-log-apply-status option.

This variable was added in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

ndb_log_bin

Version Introduced	5.1.6		
Command-Line Format	ndb-log-bin={1 0}		
Option Sets Variable	Yes, ndb_log_bin		
Variable Name	ndb_log_bin		
Variable Scope	Global, Session		
Dynamic Variable	Yes		

Permitted Values	
Type	boolean
Default	ON

Causes updates to NDB tables to be written to the binary log. Setting this variable has no effect if binary logging is not already enabled for the server using log_bin.ndb_log_bin defaults to 1 (ON); normally, there is never any need to change this value in a production environment.

This variable was added in MySQL 5.1.6.

• ndb_log_binlog_index

Version Introduced	5.1.6			
Command-Line Format	ndb-log-binlog-index={1 0}			
Option Sets Variable	Yes, ndb_log_binlog_index			
Variable Name	ndb_log_	ndb_log_binlog_index		
Variable Scope	Global			
Dynamic Variable	Yes			
	Permitted Values			
	Type boolean			
	Default ON			

Causes a mapping of epochs to positions in the binary log to be inserted into the ndb_binlog_index table. Setting this variable has no effect if binary logging is not already enabled for the server using log_bin. (In addition, ndb_log_bin must not be disabled.) ndb_log_binlog_index defaults to 1 (ON); normally, there is never any need to change this value in a production environment.

This variable was added in MySQL 5.1.6.

ndb_optimized_node_selection

Command-Line Format	- ndb- optim- ized- node- selec- tion	4.1.9-5.1. 22-ndb-6. 33	
	ndb-or	ptimized-r	node-selection=#
Option-File Format	ndb_opti	imized_noo	de_selection
	Permitted	Values (<= 5	5.1.22-ndb-6.33)
	Type	boolean	
	Default	ON	

Prior to MySQL Cluster NDB 6.3.4. Causes an SQL node to use the "closest" data node as transaction coordinator. Enabled by default. Set to 0 or OFF to disable, in which case the SQL node uses each data node in the cluster in succession. When this option is disabled each SQL thread attempts to use a given data node 8 times before proceeding to the next one.

Beginning with MySQL Cluster NDB 6.3.4. There are two forms of optimized node selection, described here:

- 1. The SQL node uses *promixity* to determine the transaction coordinator; that is, the "closest" data node to the SQL node is chosen as the transaction coordinator. For this purpose, a data node having a shared memory connection with the SQL node is considered to be "closest" to the SQL node; the next closest (in order of decreasing proximity) are: TCP connection to localhost; SCI connection; TCP connection from a host other than localhost.
- 2. The SQL thread uses *distribution awareness* to select the data node. That is, the data node housing the cluster partition accessed by the first statement of a given transaction is used as the transaction coordinator for the entire transaction. (This is

effective only if the first statement of the transaction accesses no more than one cluster partition.)

This option takes one of the integer values 0, 1, 2, or 3. 3 is the default. These values affect node selection as follows:

- 0: Node selection is not optimized. Each data node is employed as the transaction coordinator 8 times before the SQL thread proceeds to the next data node. (This is the same "round-robin" behavior as caused by setting this option to 0 or OFF in previous versions of MySQL Cluster.)
- 1: Proximity to the SQL node is used to determine the transaction coordinator. (This is the same behavior as caused by setting this option to 1 or ON in previous MySQL versions.)
- 2: Distribution awareness is used to select the transaction coordinator. However, if the first statement of the transaction accesses more than one cluster partition, the SQL node reverts to the round-robin behavior seen when this option is set to 0.
- 3: If distribution awareness can be employed to determine the transaction coordinator, then it is used; otherwise proximity is used to select the transaction coordinator. (This is the default behavior in MySQL Cluster NDB 6.3.4 and later.)

Important

Beginning with MySQL Cluster NDB 6.3.4, it is no longer possible to set - -ndb_optimized_node_selection to ON or OFF; attempting to do so causes mysqld to abort with an error.

ndb_report_thresh_binlog_epoch_slip

Command-Line Format	ndb_report_thresh_binlog_epoch_slip			
Option-File Format	ndb_report_thresh_binlog_epoch_slip			
	Permitted	Permitted Values		
	Type	Type numeric		
	Default 3			
	Range 0-256			

This is a threshold on the number of epochs to be behind before reporting binlog status. For example, a value of 3 (the default) means that if the difference between which epoch has been received from the storage nodes and which epoch has been applied to the binlog is 3 or more, a status message will be sent to the cluster log.

ndb_report_thresh_binlog_mem_usage

Command-Line Format	ndb_report_thresh_binlog_mem_usage		
Option-File Format	ndb_repo	ndb_report_thresh_binlog_mem_usage	
	Permitted Values		
	Type numeric		
	Default 10		
	Range 0-10		

This is a threshold on the percentage of free memory remaining before reporting binlog status. For example, a value of 10 (the default) means that if the amount of available memory for receiving binlog data from the data nodes falls below 10%, a status message will be sent to the cluster log.

slave_allow_batching

Version Introduced	5.1.19-ndb-6.2.3		
Command-Line Format	slave-allow-batching		
Option-File Format	slave_allow_batching		
Option Sets Variable	Yes, slave_allow_batching		
Variable Name	slave_allow_batching		
Variable Scope	Global		
Dynamic Variable	Yes		

Permit	Permitted Values	
Type	boolean	
Defaul	off	

Whether or not batched updates are enabled on MySQL Cluster replication slaves.

This variable is available beginning with MySQL Cluster NDB 6.2.3. Currently, it is available for mysqld only as supplied with MySQL Cluster or built from the MySQL Cluster sources. For more information, see Section 6.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

• ndb_table_no_logging

Version Introduced	5.1.23-ndb-6.3.8		
Variable Name	ndb_tabl	ndb_table_no_logging	
Variable Scope	Session		
Dynamic Variable	Yes		
	Permitted	Permitted Values	
	Type	Type boolean	
	Default FALSE		

When this variable is set to ON or 1, it causes NDB tables not to be checkpointed to disk. More specifically, this setting applies to tables which are created or altered using ENGINE NDB when ndb_table_no_logging is enabled, and continues to apply for the lifetime of the table, even if ndb_table_no_logging is later changed. Suppose that A, B, C, and D are tables that we create (and perhaps also alter), and that we also change the setting for ndb_table_no_logging as shown here:

```
SET @@ndb_table_no_logging = 1;
CREATE TABLE A ... ENGINE NDB;
CREATE TABLE B ... ENGINE MYISAM;
CREATE TABLE C ... ENGINE MYISAM;
ALTER TABLE B ENGINE NDB;
SET @@ndb_table_no_logging = 0;
CREATE TABLE D ... ENGINE NDB;
ALTER TABLE C ENGINE NDB;
SET @@ndb_table_no_logging = 1;
```

After the previous sequence of events, tables A and B are not checkpointed; A was created with ENGINE NDB and B was altered to use NDB, both while ndb_table_no_logging was enabled. However, tables C and D are logged; C was altered to use NDB and D was created using ENGINE NDB, both while ndb_table_no_logging was disabled. Setting ndb_table_no_logging back to 1 or ON does *not* cause table C or D to be checkpointed.

Note

ndb_table_no_logging has no effect on the creation of NDB table schema files; to suppress these, use ndb_table_temporary instead.

• ndb_table_temporary

Version Introduced	5.1.23-ndb-	5.1.23-ndb-6.3.8		
Variable Name	ndb_tabl	ndb_table_temporary		
Variable Scope	Session	Session		
Dynamic Variable	Yes			
	Permitted	Permitted Values		
	Type boolean			
	Default FALSE			

When set to ON or 1, this variable causes NDB tables not to be written to disk: This means that no table schema files are created, and that the tables are not logged.

Note

Setting this variable currently has no effect in MySQL Cluster NDB 7.0 and later. This is a known issue; see

BUG#34036.

• ndb_use_copying_alter_table

Version Introduced	5.1.12		
Variable Name	ndb_use_copying_alter_table		
Variable Scope	Global, Session		
Dynamic Variable	No		

Forces NDB to use copying of tables in the event of problems with online ALTER TABLE operations. The default value is OFF. This variable was added in MySQL 5.1.12.

ndb_use_exact_count

Variable Name	ndb_use_	ndb_use_exact_count	
Variable Scope	Global, Ses	Global, Session	
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default ON		

Forces NDB to use a count of records during SELECT COUNT(*) query planning to speed up this type of query. The default value is ON. For faster queries overall, disable this feature by setting the value of ndb_use_exact_count to OFF.

• ndb_use_transactions

Command-Line Format	ndb_us	ndb_use_transactions		
Option-File Format	ndb_use_	ndb_use_transactions		
Variable Name	ndb_use_	ndb_use_transactions		
Variable Scope	Global, Session			
Dynamic Variable	Yes			
	Permitted	Permitted Values		
	Type boolean			
	Default ON			

You can disable NDB transaction support by setting this variable's values to OFF (not recommended). The default is ON.

Note

The setting for this variable was not honored in MySQL Cluster NDB 6.4.3 and MySQL Cluster NDB 7.0.4. (Bug #43236)

The system variables in the following list all relate to the ndbinfo information database. They were added in MySQL Cluster NDB 7.1.1.

• ndbinfo_database

Version Introduced	5.1.41-ndb-7.1.1		
Variable Name	ndbinfo_database		
Variable Scope	Global		
Dynamic Variable	No		

	Permitted	Values
	Type	string
	Default	ndbinfo

Shows the name used for the NDB information database; the default is ndbinfo. This is a read-only variable whose value is determined at compile time; you can set it by starting the server using --ndbinfo-database=name, which sets the value shown for this variable but does not actually change the name used for the NDB information database.

ndbinfo_max_bytes

Version Introduced	5.1.41-ndb	5.1.41-ndb-7.1.1		
Command-Line Format	ndbin	ndbinfo-max-bytes=#		
Option Sets Variable	Yes, ndbi	Yes, ndbinfo_max_bytes		
Variable Name	ndbinfo_	ndbinfo_max_bytes		
Variable Scope	Global, Sea	Global, Session		
Dynamic Variable	Yes	Yes		
	Permitted	Permitted Values		
	Type	Type numeric		
	Default	0		

Used in testing and debugging only.

• ndbinfo_max_rows

Version Introduced	5.1.41-ndb-7.1.1			
Command-Line Format	ndbinf	ndbinfo-max-rows=#		
Option Sets Variable	Yes, ndbi	Yes, ndbinfo_max_rows		
Variable Name	ndbinfo_	ndbinfo_max_rows		
Variable Scope	Global, Session			
Dynamic Variable	Yes			
	Permitted Values			
	Type numeric			
	Default	10		

Used in testing and debugging only.

• ndbinfo_show_hidden

Version Introduced	5.1.41-ndb	5.1.41-ndb-7.1.1		
Command-Line Format	ndbin	ndbinfo-show-hidden={0 1}		
Option Sets Variable	Yes, ndbi	Yes, ndbinfo_show_hidden		
Variable Name	ndbinfo_	ndbinfo_show_hidden		
Variable Scope	Global, Sea	Global, Session		
Dynamic Variable	Yes	Yes		
	Permitted	Permitted Values		
	Type	boolean		
	Default	no		

Whether or not the ndbinfo database's underlying internal tables are shown in the mysql client. The default is OFF.

• ndbinfo_table_prefix

Version Introduced	5.1.41-ndb-7.1.1			
Command-Line Format	ndbinf	ndbinfo-table-prefix=name		
Option Sets Variable	Yes, ndbi:	Yes, ndbinfo_table_prefix		
Variable Name	ndbinfo_table_prefix			
Variable Scope	Global, Session			
Dynamic Variable	Yes			
	Permitted Values			
	Type string			
	Default ndb\$			

The prefix used in naming the ndbinfo database's base tables (normally hidden, unless exposed by setting nd-binfo_show_hidden). This is a read-only variable whose default value is "ndb\$". You can start the server with the --ndbinfo-table-prefix option, but this merely sets the variable and does not change the actual prefix used to name the hidden base tables; the prefix itself is determined at compile time.

• ndbinfo_version

Version Introduced	5.1.41-ndb	5.1.41-ndb-7.1.1		
Variable Name	ndbinfo	ndbinfo_version		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitted	Permitted Values		
	Type	string		
	Default			

Shows the version of the ndbinfo engine in use; read-only.

server_id_bits

Version Introduced	5.1.47-ndb	5.1.47-ndb-7.0.17, 5.1.47-ndb-7.1.6		
Command-Line Format	serve	server-id-bits=#		
Option-File Format	server-	server-id-bits		
Option Sets Variable	Yes, serv	Yes, server_id_bits		
Variable Name	server_	server_id_bits		
Variable Scope	Global	Global		
Dynamic Variable	No	No		
	Permitted	Permitted Values		
	Type	numeric		
	Default	32		
	Range	Range 7-32		

The effective value of server_id if the server was started with the --server-id-bits option set to a nondefault value.

If the value of server_id greater than or equal to 2 to the power of server_id_bits, mysqld refuses to start.

This system variable was added in MySQL Cluster NDB 7.0.17 and MySQL Cluster NDB 7.1.6; it is supported only in these and later releases of MySQL Cluster. server_id_bits is not supported by the standard MySQL Server.

3.4.4. MySQL Cluster Status Variables

This section provides detailed information about MySQL server status variables that relate to MySQL Cluster and the NDB storage engine. For status variables not specific to MySQL Cluster, and for general information on using status variables, see Server Status Variables.

• Handler discover

The MySQL server can ask the NDBCLUSTER storage engine if it knows about a table with a given name. This is called discovery. Handler_discover indicates the number of times that tables have been discovered using this mechanism.

• Ndb_cluster_node_id

If the server is acting as a MySQL Cluster node, then the value of this variable its node ID in the cluster.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

• Ndb_config_from_host

If the server is part of a MySQL Cluster, the value of this variable is the host name or IP address of the Cluster management server from which it gets its configuration data.

If the server is not part of a MySQL Cluster, then the value of this variable is an empty string.

Prior to MySQL 5.1.12, this variable was named Ndb_connected_host.

• Ndb_config_from_port

If the server is part of a MySQL Cluster, the value of this variable is the number of the port through which it is connected to the Cluster management server from which it gets its configuration data.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

Prior to MySQL 5.1.12, this variable was named Ndb_connected_port.

• Ndb_conflict_fn_max

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of times that a row was not applied on the current SQL node due to "greatest timestamp wins" conflict resolution since the last time that this mysqld was started.

This variable was added in MySQL Cluster NDB 6.3.3. For more information, see Section 6.11, "MySQL Cluster Replication Conflict Resolution".

Ndb_conflict_fn_old

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of times that a row was not applied as the result of "same timestamp wins" conflict resolution on a given mysqld since the last time it was restarted.

This variable was added in MySQL Cluster NDB 6.3.4. For more information, see Section 6.11, "MySQL Cluster Replication Conflict Resolution".

• Ndb_execute_count

Provides the number of round trips to the NDB kernel made by operations. Added in MySQL Cluster NDB 6.3.6.

• Ndb_number_of_data_nodes

If the server is part of a MySQL Cluster, the value of this variable is the number of data nodes in the cluster.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

Prior to MySQL 5.1.12, this variable was named Ndb_number_of_storage_nodes.

• Ndb_pushed_queries_defined

The total number of joins pushed down to the NDB kernel for distributed handling on the data nodes. Note that joins tested using EXPLAIN that can be pushed down contribute to this number. Added in MySQL Cluster NDB 7.2.0.

• Ndb_pushed_queries_dropped

The number of joins that were pushed down to the NDB kernel but that could not be handled there. Added in MySQL Cluster NDB 7.2.0.

• Ndb_pushed_queries_executed

The number of joins successfully pushed down to NDB and executed there. Added in MySOL Cluster NDB 7.2.0.

• Ndb_pushed_reads

The number of rows returned to mysqld from the NDB kernel by joins that were pushed down. Note that executing EXPLAIN on joins that can be pushed down to NDB does not add to this number. Added in MySQL Cluster NDB 7.2.0.

• Slave_heartbeat_period

Shows the replication heartbeat interval (in seconds) on a replication slave.

This variable was added in MySQL Cluster NDB 6.3.4.

• Slave_received_heartbeats

This counter increments with each replication heartbeat received by a replication slave since the last time that the slave was restarted or reset, or a CHANGE MASTER TO statement was issued.

This variable was added in MySQL Cluster NDB 6.3.4.

• Ndb_pruned_scan_count

This variable holds a count of the number of scans executed by NDBCLUSTER since the MySQL Cluster was last started where NDBCLUSTER was able to use partition pruning.

Using this variable together with Ndb_scan_count can be helpful in schema design to maximize the ability of the server to prune scans to a single table partition, thereby involving only a single data node.

This variable was added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.5.

• Ndb_scan_count

This variable holds a count of the total number of scans executed by NDBCLUSTER since the MySQL Cluster was last started.

This variable was added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.5.

3.5. Using High-Speed Interconnects with MySQL Cluster

Even before design of NDBCLUSTER began in 1996, it was evident that one of the major problems to be encountered in building parallel databases would be communication between the nodes in the network. For this reason, NDBCLUSTER was designed from the very beginning to permit the use of a number of different data transport mechanisms. In this Manual, we use the term *transporter* for these.

The MySQL Cluster codebase provides for four different transporters:

- TCP/IP using 100 Mbps or gigabit Ethernet, as discussed in Section 3.2.8, "MySQL Cluster TCP/IP Connections".
- Direct (machine-to-machine) TCP/IP; although this transporter uses the same TCP/IP protocol as mentioned in the previous item, it requires setting up the hardware differently and is configured differently as well. For this reason, it is considered a separate transport mechanism for MySQL Cluster. See Section 3.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections", for details.
- Shared memory (SHM). For more information about SHM, see Section 3.2.10, "MySQL Cluster Shared-Memory Connections".

Note

SHM is considered experimental only, and is not officially supported.

 Scalable Coherent Interface (SCI), as described in the next section of this chapter, Section 3.2.11, "SCI Transport Connections in MySQL Cluster".

Most users today employ TCP/IP over Ethernet because it is ubiquitous. TCP/IP is also by far the best-tested transporter for use with MySQL Cluster.

We are working to make sure that communication with the ndbd process is made in "chunks" that are as large as possible because this benefits all types of data transmission.

For users who desire it, it is also possible to use cluster interconnects to enhance performance even further. There are two ways to achieve this: Either a custom transporter can be designed to handle this case, or you can use socket implementations that bypass the TCP/IP stack to one extent or another. We have experimented with both of these techniques using the SCI (Scalable Coherent Interface) technology developed by Dolphin Interconnect Solutions.

3.5.1. Configuring MySQL Cluster to use SCI Sockets

It is possible employing Scalable Coherent Interface (SCI) technology to achieve a significant increase in connection speeds and throughput between MySQL Cluster data and SQL nodes. To use SCI, it is necessary to obtain and install Dolphin SCI network cards and to use the drivers and other software supplied by Dolphin. You can get information on obtaining these, from Dolphin Interconnect Solutions. SCI SuperSocket or SCI Transporter support is available for 32-bit and 64-bit Linux, Solaris, Windows, and other platforms. See the Dolphin documentation referenced later in this section for more detailed information regarding platforms supported for SCI.

Note

Prior to MySQL 5.1.20, there were issues with building MySQL Cluster with SCI support (see Bug #25470), but these have been resolved due to work contributed by Dolphin. SCI Sockets are now correctly supported for MySQL Cluster hosts running recent versions of Linux using the <code>-max</code> builds, and versions of MySQL Cluster with SCI Transporter support can be built using either of <code>compile-amd64-max-sci</code> or <code>compile-pentium64-max-sci</code>. Both of these build scripts can be found in the <code>BUILD</code> directory of the MySQL Cluster source trees; it should not be difficult to adapt them for other platforms. Generally, all that is necessary is to compile MySQL Cluster with SCI Transporter support is to configure the MySQL Cluster build using <code>--with-ndb-sci=/opt/DIS</code>.

Once you have acquired the required Dolphin hardware and software, you can obtain detailed information on how to adapt a MySQL Cluster configured for normal TCP/IP communication to use SCI from the *Dolphin Express for MySQL Installation and Reference Guide*, available for download at http://docsrva.mysql.com/public/DIS_install_guide_book.pdf (PDF file, 94 pages, 753 KB). This document provides instructions for installing the SCI hardware and software, as well as information concerning network topology and configuration.

3.5.2. MySQL Cluster Interconnects and Performance

The ndbd process has a number of simple constructs which are used to access the data in a MySQL Cluster. We have created a very simple benchmark to check the performance of each of these and the effects which various interconnects have on their performance.

There are four access methods:

- Primary key access. This is access of a record through its primary key. In the simplest case, only one record is accessed at a
 time, which means that the full cost of setting up a number of TCP/IP messages and a number of costs for context switching are
 borne by this single request. In the case where multiple primary key accesses are sent in one batch, those accesses share the cost
 of setting up the necessary TCP/IP messages and context switches. If the TCP/IP messages are for different destinations, additional TCP/IP messages need to be set up.
- Unique key access. Unique key accesses are similar to primary key accesses, except that a unique key access is executed as a read on an index table followed by a primary key access on the table. However, only one request is sent from the MySQL Server, and the read of the index table is handled by ndbd. Such requests also benefit from batching.
- Full table scan. When no indexes exist for a lookup on a table, a full table scan is performed. This is sent as a single request to the ndbd process, which then divides the table scan into a set of parallel scans on all cluster ndbd processes. In future versions of MySQL Cluster, an SQL node will be able to filter some of these scans.
- Range scan using ordered index. When an ordered index is used, it performs a scan in the same manner as the full table scan, except that it scans only those records which are in the range used by the query transmitted by the MySQL server (SQL node). All partitions are scanned in parallel when all bound index attributes include all attributes in the partitioning key.

With benchmarks developed internally by MySQL for testing simple and batched primary and unique key accesses, we have found that using SCI sockets improves performance by approximately 100% over TCP/IP, except in rare instances when communication performance is not an issue. This can occur when scan filters make up most of processing time or when very large batches of primary key accesses are achieved. In that case, the CPU processing in the ndbd processes becomes a fairly large part of the overhead.

Using the SCI transporter instead of SCI Sockets is only of interest in communicating between ndbd processes. Using the SCI transporter is also only of interest if a CPU can be dedicated to the ndbd process because the SCI transporter ensures that this process will never go to sleep. It is also important to ensure that the ndbd process priority is set in such a way that the process does not lose priority due to running for an extended period of time, as can be done by locking processes to CPUs in Linux 2.6. If such a configuration is possible, the ndbd process will benefit by 10–70% as compared with using SCI sockets. (The larger figures will be seen when performing updates and probably on parallel scan operations as well.)

There are several other optimized socket implementations for computer clusters, including Myrinet, Gigabit Ethernet, Infiniband and the VIA interface. However, we have tested MySQL Cluster so far only with SCI sockets. See Section 3.5.1, "Configuring MySQL Cluster to use SCI Sockets", for information on how to set up SCI sockets using ordinary TCP/IP for MySQL Cluster.

Chapter 4. MySQL Cluster Programs

Using and managing a MySQL Cluster requires several specialized programs, which we describe in this chapter. We discuss the purposes of these programs in a MySQL Cluster, how to use the programs, and what startup options are available for each of them.

These programs include the MySQL Cluster data, management, and SQL node processes (ndbd, ndbmtd, ndb_mgmd, and mysqld) and the management client (ndb_mgm).

Other NDB utility, diagnostic, and example programs are included with the MySQL Cluster distribution. These include ndb_restore, ndb_show_tables, and ndb_config. These programs are covered later in this chapter.

The last two sections of this chapter contain tables of options used, respectively, with mysqld and with the various MySQL Cluster programs.

4.1. MySQL Server Usage for MySQL Cluster

mysqld is the traditional MySQL server process. To be used with MySQL Cluster, mysqld needs to be built with support for the NDBCLUSTER storage engine, as it is in the precompiled binaries available from http://dev.mysql.com/downloads/. If you build MySQL from source, you must invoke configure with one of the options to enable NDBCLUSTER storage engine support:

- --with-plugins=ndbcluster
- --with-plugins=max
- --with-plugins=max-no-innodb

(--with-ndbcluster also works to enable NDBCLUSTER support, but is deprecated and so produces a configure warning as of MySQL 5.1.9.)

For information about other MySQL server options and variables relevant to MySQL Cluster in addition to those discussed in this section, see Section 3.4, "MySQL Server Options and Variables for MySQL Cluster".

If the mysqld binary has been built with Cluster support, the NDBCLUSTER storage engine is still disabled by default. You can use either of two possible options to enable this engine:

- Use --ndbcluster as a startup option on the command line when starting mysqld.
- Insert a line containing ndbcluster in the [mysqld] section of your my.cnf file.

An easy way to verify that your server is running with the NDBCLUSTER storage engine enabled is to issue the SHOW ENGINES statement in the MySQL Monitor (mysql). You should see the value YES as the Support value in the row for NDBCLUSTER. If you see NO in this row or if there is no such row displayed in the output, you are not running an NDB-enabled version of MySQL. If you see DISABLED in this row, you need to enable it in either one of the two ways just described.

To read cluster configuration data, the MySQL server requires at a minimum three pieces of information:

- · The MySQL server's own cluster node ID
- The host name or IP address for the management server (MGM node)
- The number of the TCP/IP port on which it can connect to the management server

Node IDs can be allocated dynamically, so it is not strictly necessary to specify them explicitly.

The mysqld parameter ndb-connectstring is used to specify the connectstring either on the command line when starting mysqld or in my.cnf. The connectstring contains the host name or IP address where the management server can be found, as well as the TCP/IP port it uses.

In the following example, ndb_mgmd.mysql.com is the host where the management server resides, and the management server listens for cluster messages on port 1186:

shell> mysqld --ndbcluster --ndb-connectstring=ndb_mgmd.mysql.com:1186

See Section 3.2.3, "The MySQL Cluster Connectstring", for more information on connectstrings.

Given this information, the MySQL server will be a full participant in the cluster. (We often refer to a mysqld process running in this manner as an SQL node.) It will be fully aware of all cluster data nodes as well as their status, and will establish connections to all data nodes. In this case, it is able to use any data node as a transaction coordinator and to read and update node data.

You can see in the mysql client whether a MySQL server is connected to the cluster using SHOW PROCESSLIST. If the MySQL server is connected to the cluster, and you have the PROCESS privilege, then the first row of the output is as shown here:

Important

To participate in a MySQL Cluster, the mysqld process must be started with both the options --ndbcluster and --ndb-connectstring (or their equivalents in my.cnf). If mysqld is started with only the --ndbcluster option, or if it is unable to contact the cluster, it is not possible to work with NDB tables, nor is it possible to create any new tables regardless of storage engine. The latter restriction is a safety measure intended to prevent the creation of tables having the same names as NDB tables while the SQL node is not connected to the cluster. If you wish to create tables using a different storage engine while the mysqld process is not participating in a MySQL Cluster, you must restart the server without the --ndbcluster option.

4.2. ndbd — The MySQL Cluster Data Node Daemon

ndbd is the process that is used to handle all the data in tables using the NDB Cluster storage engine. This is the process that empowers a data node to accomplish distributed transaction handling, node recovery, checkpointing to disk, online backup, and related tasks.

In a MySQL Cluster, a set of ndbd processes cooperate in handling data. These processes can execute on the same computer (host) or on different computers. The correspondences between data nodes and Cluster hosts is completely configurable.

The following table includes command options specific to the MySQL Cluster data node program ndbd. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.1. ndbd Command Line Options	Table 4.1	ndbd	Command	Line	Options
--------------------------------------	-----------	------	---------	------	----------------

Format	Description	Introduc- tion	Deprec- ated	Removed
bind-address=name	Local bind address	5.1.12		
daemon	Start ndbd as daemon (default); override withnodaemon			
foreground	Run ndbd in foreground, provided for debugging purposes (impliesnodaemon)			
initial	Perform initial start of ndbd, including cleaning the file system. Consult the documentation before using this option			
initial-start	Perform partial initial start (requiresnowait-nodes)	5.1.11		
install[=name]	Used to install the data node process as a Windows service. Does not apply on non-Windows platforms.	5.1.47-ndb- 7.0.16, 5.1.47-ndb- 7.1.5		
nodaemon	Do not start ndbd as daemon; provided for testing purposes			
nostart	Don't start ndbd immediately; ndbd waits for command to start from ndb_mgmd			
nowait-nodes=list	Do not wait for these data nodes to start (takes comma-separated list of node IDs). Also requiresndb-nodeid to be used.	5.1.9		
remove[=name]	Used to remove a data node process that was previously installed as a Windows service. Does not apply on non-Windows platforms.	5.1.47-ndb- 7.0.16, 5.1.47-ndb-		

Format	_ <u>*</u>		Deprec- ated	Removed
		7.1.5		

Note

All of these options also apply to the multi-threaded version of this program (ndbmtd, available in MySQL Cluster NDB 7.0 and later) and you may substitute "ndbmtd" for "ndbd" wherever the latter occurs in this section.

For options common to all NDBCLUSTER programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

--bind-address

Version Introduced	5.1.12	5.1.12	
Command-Line Format	bind-a	-bind-address=name	
	Permitted	Permitted Values	
	Type	string	
	Default		

Causes ndbd to bind to a specific network interface (host name or IP address). This option has no default value.

This option was added in MySQL 5.1.12.

• --daemon, -d

Command-Line Format	daemor	-daemon		
	-d	đ		
	Permitted Values			
	Type	boolean		
	Default	TRUE		

Instructs ndbd to execute as a daemon process. This is the default behavior. --nodaemon can be used to prevent the process from running as a daemon.

This option has no effect when running ndbd or ndbmtd on Windows platforms.

• --initial

Command-Line Format	initia	initial	
	Permitted	Values	
	Type	boolean	
	Default	FALSE	

Instructs ndbd to perform an initial start. An initial start erases any files created for recovery purposes by earlier instances of ndbd. It also re-creates recovery log files. Note that on some operating systems this process can take a substantial amount of time

An --initial start is to be used *only* when starting the ndbd process under very special circumstances; this is because this option causes all files to be removed from the MySQL Cluster file system and all redo log files to be re-created. These circumstances are listed here:

- When performing a software upgrade which has changed the contents of any files.
- When restarting the node with a new version of ndbd.
- As a measure of last resort when for some reason the node restart or system restart repeatedly fails. In this case, be aware that this node can no longer be used to restore data due to the destruction of the data files.

Use of this option prevents the StartPartialTimeout and StartPartitionedTimeout configuration parameters from having any effect.

Important

This option does *not* affect either of the following types of files:

- · Backup files that have already been created by the affected node
- MySQL Cluster Disk Data files (see Section 5.11, "MySQL Cluster Disk Data Tables").

This option also has no effect on recovery of data by a data node that is just starting (or restarting) from data nodes that are already running. This recovery of data occurs automatically, and requires no user intervention in a MySQL Cluster that is running normally.

It is permissible to use this option when starting the cluster for the very first time (that is, before any data node files have been created); however, it is *not* necessary to do so.

• --initial-start

Version Introduced	5.1.11	.1.11		
Command-Line Format	initia	-initial-start		
	Permitted	Permitted Values		
	Type boolean			
	Default	FALSE		

This option is used when performing a partial initial start of the cluster. Each node should be started with this option, as well as --nowait-nodes.

Suppose that you have a 4-node cluster whose data nodes have the IDs 2, 3, 4, and 5, and you wish to perform a partial initial start using only nodes 2, 4, and 5—that is, omitting node 3:

```
shell> ndbd --ndb-nodeid=2 --nowait-nodes=3 --initial-start
shell> ndbd --ndb-nodeid=4 --nowait-nodes=3 --initial-start
shell> ndbd --ndb-nodeid=5 --nowait-nodes=3 --initial-start
```

Prior to MySQL 5.1.19, it was not possible to perform DDL operations involving Disk Data tables on a partially started cluster. (See Bug #24631.)

When using this option, you must also specify the node ID for the data node being started with the --ndb-nodeid option.

This option was added in MySQL 5.1.11.

Important

Do not confuse this option with the --nowait-nodes option added for ndb_mgmd in MySQL Cluster NDB 7.0.10, which can be used to enable a cluster configured with multiple management servers to be started without all management servers being online.

• --nowait-nodes=node_id_1[, node_id_2[, ...]]

Version Introduced	5.1.9	1.9	
Command-Line Format	nowait	-nowait-nodes=list	
	Permitted	ermitted Values	
	Type	string	
	Default		

This option takes a list of data nodes which for which the cluster will not wait for before starting.

This can be used to start the cluster in a partitioned state. For example, to start the cluster with only half of the data nodes (nodes 2, 3, 4, and 5) running in a 4-node cluster, you can start each ndbd process with --nowait-nodes=3, 5. In this case, the cluster starts as soon as nodes 2 and 4 connect, and does not wait StartPartitionedTimeout milliseconds for nodes 3 and 5 to connect as it would otherwise.

If you wanted to start up the same cluster as in the previous example without one ndbd (say, for example, that the host machine for node 3 has suffered a hardware failure) then start nodes 2, 4, and 5 with --nowait-nodes=3. Then the cluster will

start as soon as nodes 2, 4, and 5 connect and will not wait for node 3 to start.

This option was added in MySQL 5.1.9.

--nodaemon

Command-Line Format	nodaemon	
	Permitted	Values
	Type	boolean
	Default	FALSE
	Permitted	Values
	Type (windows)	boolean
	Default	TRUE

Instructs ndbd not to start as a daemon process. This is useful when ndbd is being debugged and you want output to be redirected to the screen.

As of MySQL Cluster NDB 7.0.8, the default behavior for ndbd and ndbmtd on Windows is to run in the foreground, making this option unnecessary on Windows platforms. (Bug #45588)

• --nostart, -n

Command-Line Format	nostart	
	-n	
	Permitted Values	
	Type	boolean
	Default	FALSE

Instructs ndbd not to start automatically. When this option is used, ndbd connects to the management server, obtains configuration data from it, and initializes communication objects. However, it does not actually start the execution engine until specifically requested to do so by the management server. This can be accomplished by issuing the proper START command in the management client (see Section 5.2, "Commands in the MySQL Cluster Management Client").

• --install[=name]

Version Introduced	5.1.47-ndb-7.0.16, 5.1.47-ndb-7.1.5	
Command-Line Format	install[=name]	
	Permitted Values	
	Type (windows)	string
	Default	ndbd

Causes ndbd to be installed as a Windows service. Optionally, you can specify a name for the service; if not set, the service name defaults to ndbd. Although it is preferable to specify other ndbd program options in a my.ini or my.cnf configuration file, it is possible to use together with --install. However, in such cases, the --install option must be specified first, before any other options are given, for the Windows service installation to succeed.

It is generally not advisable to use this option together with the <code>--initial</code> option, since this causes the data node file system to be wiped and rebuilt every time the service is stopped and started. Extreme care should also be taken if you intend to use any of the other ndbd options that affect the starting of data nodes—including <code>--initial-start</code>, <code>--nostart</code>, and <code>--nowait-nodes</code>—together with <code>--install</code>, and you should make absolutely certain you fully understand and allow for any possible consequences of doing so.

The --install option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

--remove[=name]

Version Introduced	5.1.47-ndb-7.0.16, 5.1.47-ndb-7.1.5	
Command-Line Format	remove[=name]	
	Permitted Values	
	Type (windows)	string
	Default	ndbd

Causes an ndbd process that was previously installed as a Windows service to be removed. Optionally, you can specify a name for the service to be uninstalled; if not set, the service name defaults to ndbd.

The --remove option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

ndbd generates a set of log files which are placed in the directory specified by DataDir in the config.ini configuration file.

These log files are listed below. node_id is the node's unique identifier. Note that node_id represents the node's unique identifier. For example, ndb_2_error.log is the error log generated by the data node whose node ID is 2.

• ndb_node_id_error.log is a file containing records of all crashes which the referenced ndbd process has encountered. Each record in this file contains a brief error string and a reference to a trace file for this crash. A typical entry in this file might appear as shown here:

```
Date/Time: Saturday 30 July 2004 - 00:20:01
Type of error: error
Message: Internal program error (failed ndbrequire)
Fault ID: 2341
Problem data: DbtupFixAlloc.cpp
Object of reference: DBTUP (Line: 173)
ProgramName: NDB Kernel
ProcessID: 14909
TraceFile: ndb_2_trace.log.2
***EDM***
```

Listings of possible ndbd exit codes and messages generated when a data node process shuts down prematurely can be found in ndbd Error Messages.

Important

The last entry in the error log file is not necessarily the newest one (nor is it likely to be). Entries in the error log are not listed in chronological order; rather, they correspond to the order of the trace files as determined in the ndb_node_id_trace.log.next file (see below). Error log entries are thus overwritten in a cyclical and not sequential fashion.

• ndb_node_id_trace.log.trace_id is a trace file describing exactly what happened just before the error occurred. This information is useful for analysis by the MySQL Cluster development team.

It is possible to configure the number of these trace files that will be created before old files are overwritten. <code>trace_id</code> is a number which is incremented for each successive trace file.

- ndb_node_id_trace.log.next is the file that keeps track of the next trace file number to be assigned.
- ndb_node_id_out.log is a file containing any data output by the ndbd process. This file is created only if ndbd is started as a daemon, which is the default behavior.
- ndb_node_id.pid is a file containing the process ID of the ndbd process when started as a daemon. It also functions as a lock file to avoid the starting of nodes with the same identifier.
- ndb_node_id_signal.log is a file used only in debug versions of ndbd, where it is possible to trace all incoming, outgoing, and internal messages with their data in the ndbd process.

It is recommended not to use a directory mounted through NFS because in some environments this can cause problems whereby the lock on the .pid file remains in effect even after the process has terminated.

To start ndbd, it may also be necessary to specify the host name of the management server and the port on which it is listening. Optionally, one may also specify the node ID that the process is to use.

shell> ndbd --connect-string="nodeid=2;host=ndb_mgmd.mysql.com:1186"

See Section 3.2.3, "The MySQL Cluster Connectstring", for additional information about this issue. Section 4.2, "ndbd — The MySQL Cluster Data Node Daemon", describes other options for ndbd.

When ndbd starts, it actually initiates two processes. The first of these is called the "angel process"; its only job is to discover when the execution process has been completed, and then to restart the ndbd process if it is configured to do so. Thus, if you attempt to kill ndbd using the Unix kill command, it is necessary to kill both processes, beginning with the angel process. The preferred method of terminating an ndbd process is to use the management client and stop the process from there.

The execution process uses one thread for reading, writing, and scanning data, as well as all other activities. This thread is implemented asynchronously so that it can easily handle thousands of concurrent actions. In addition, a watch-dog thread supervises the execution thread to make sure that it does not hang in an endless loop. A pool of threads handles file I/O, with each thread able to handle one open file. Threads can also be used for transporter connections by the transporters in the ndbd process. In a multi-processor system performing a large number of operations (including updates), the ndbd process can consume up to 2 CPUs if permitted to do so.

For a machine with many CPUs it is possible to use several ndbd processes which belong to different node groups; however, such a configuration is still considered experimental and is not supported for MySQL 5.1 in a production setting. See Section 1.6, "Known Limitations of MySQL Cluster".

4.3. ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)

ndbmtd is a multi-threaded version of ndbd, the process that is used to handle all the data in tables using the NDBCLUSTER storage engine. ndbmtd is intended for use on host computers having multiple CPU cores. Except where otherwise noted, ndbmtd functions in the same way as ndbd; therefore, in this section, we concentrate on the ways in which ndbmtd differs from ndbd, and you should consult Section 4.2, "ndbd — The MySQL Cluster Data Node Daemon", for additional information about running MySQL Cluster data nodes that apply to both the single-threaded and multi-threaded versions of the data node process.

Command-line options and configuration parameters used with ndbd also apply to ndbmtd. For more information about these options and parameters, see Section 4.2, "ndbd — The MySQL Cluster Data Node Daemon", and Section 3.2.6, "Defining MySQL Cluster Data Nodes", respectively.

ndbmtd is also file system-compatible with ndbd. In other words, a data node running ndbd can be stopped, the binary replaced with ndbmtd, and then restarted without any loss of data. (However, when doing this, you must make sure that MaxNoofExecutionThreads is set to an appriate value before restarting the node if you wish for ndbmtd to run in multi-threaded fashion.) Similarly, an ndbmtd binary can be replaced with ndbd simply by stopping the node and then starting ndbd in place of the multi-threaded binary. It is not necessary when switching between the two to start the data node binary using --initial.

Prior to MySQL Cluster NDB 7.0.6, there were known issues when using ndbmtd with MySQL Cluster Disk Data tables. If you wish to use multi-threaded data nodes with disk-based NDB tables, you should ensure that you are running MySQL Cluster NDB 7.0.6 or later (see Bug #41915 and Bug #44915)

Using ndbmtd differs from using ndbd in two key respects:

- 1. You must set an appropriate value for the MaxNoOfExecutionThreads configuration parameter in the config.ini file. If you do not do so, ndbmtd runs in single-threaded mode; that is, it behaves like ndbd.
- 2. Trace files are generated by critical errors in ndbmtd processes in a somewhat different fashion from how these are generated by ndbd failures.

These differences are discussed in more detail in the next few paragraphs.

Number of execution threads. The MaxNoOfExecutionThreads configuration parameter is used to determine the number of local query handler (LQH) threads spawned by ndbmtd. Although this parameter is set in [ndbd] or [ndbd default] sections of the config.ini file, it is exclusive to ndbmtd and does not apply to ndbd.

This parameter takes an integer value from 2 to 8 inclusive. Generally, you should set this parameter equal to the number of CPU cores on the data node host, as shown in the following table:

Number of Cores	Recommended MaxNoOfExecutionThreads Value
2	2
4	4
8 or more	8

(It is possible to set this parameter to other values within the permitted range, but these are automatically rounded as shown in the **Value Used** column of the next table in this section.)

The multi-threaded data node process always spawns at least 4 threads, listed here:

- 1 local query handler (LQH) thread
- 1 transaction coordinator (TC) thread
- 1 transporter thread
- · 1 subscription manager (SUMA) thread

Setting this parameter to a value between 4 and 8 inclusive causes additional LQH threads to be used by ndbmtd (up to a maximum of 4 LQH threads), as shown in the following table:

config.ini Value	Value Used	Number of LQH Threads Used
3	2	1
5 or 6	4	2
7	8	4

Setting this parameter outside the permitted range of values causes the management server to abort on startup with the error Error Line Number: Illegal value Value for Parameter MaxNoOfExecutionThreads.

Note

In MySQL Cluster NDB 6.4.0, it is not possible to set MaxNoOfExecutionThreads to 2. You can safely use the value 3 instead (it is treated as 2 internally). This issue is resolved in MySQL Cluster NDB 6.4.1.

In MySQL Cluster NDB 6.4.0 through 6.4.3, the default value for this parameter was undefined, although the default behavior for ndbmtd was to use 1 LQH thread, as though MaxNoOfExecutionThreads had been set to 2. Beginning with MySQL Cluster NDB 7.0.4, this parameter has an explcit default value of 2, thus guaranteeing this default behavior.

In MySQL Cluster NDB 7.0, it is not possible to cause ndbmtd to use more than 1 TC thread, although we plan to introduce this capability in a future MySQL Cluster release series.

Like ndbd, ndbmtd generates a set of log files which are placed in the directory specified by DataDir in the config.ini configuration file. Except for trace files, these are generated in the same way and have the same names as those generated by ndbd.

In the event of a critical error, ndbmtd generates trace files describing what happened just prior to the error' occurrence. These files, which can be found in the data node's DataDir, are useful for analysis of problems by the MySQL Cluster Development and Support teams. One trace file is generated for each ndbmtd thread. The names of these files have the following pattern:

```
ndb_node_id_trace.log.trace_id_tthread_id,
```

In this pattern, node_id stands for the data node's unique node ID in the cluster, trace_id is a trace sequence number, and thread_id is the thread ID. For example, in the event of the failure of an ndbmtd process running as a MySQL Cluster data node having the node ID 3 and with MaxNoOfExecutionThreads equal to 4, four trace files are generated in the data node's data directory. If the is the first time this node has failed, then these files are named ndb_3_trace.log.1_t1, ndb_3_trace.log.1_t2, ndb_3_trace.log.1_t3, and ndb_3_trace.log.1_t4. Internally, these trace files follow the same format as ndbd trace files.

The ndbd exit codes and messages that are generated when a data node process shuts down prematurely are also used by ndbmtd. See ndbd Error Messages, for a listing of these.

Note

It is possible to use ndbd and ndbmtd concurrently on different data nodes in the same MySQL Cluster. However, such configurations have not been tested extensively; thus, we cannot not recommend doing so in a production setting at this time.

4.4. ndb_mgmd — The MySQL Cluster Management Server Daemon

The management server is the process that reads the cluster configuration file and distributes this information to all nodes in the cluster that request it. It also maintains a log of cluster activities. Management clients can connect to the management server and check the cluster's status.

The following table includes options that are specific to the MySQL Cluster management server program ndb_mgmd. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.2. ndb_mgmd Command Line Options

Format	Description	Introduc- tion	Deprec- ated	Removed
bind-address	Local bind address	5.1.22-ndb- 6.2.5, 5.1.22-ndb- 6.3.2		
config-cache=value	Enable the management server configuration cache; ON by default.	5.1.44-ndb- 7.0.15, 5.1.44-ndb- 7.1.4		
-с	Specify the cluster configuration file; in NDB-6.4.0 and later, needsreload orinitial to override configuration cache if present			
configdir=directory	Specify the cluster management server's configuration cache directory	5.1.30-ndb- 6.4.0		
daemon	Run ndb_mgmd in daemon mode (default)			
initial	Causes the management server reload its configuration data from the configuration file, bypassing the configuration cache	5.1.30-ndb- 6.4.0		
install[=name]	Used to install the management server process as a Windows service. Does not apply on non-Windows platforms.	5.1.47-ndb- 7.0.16, 5.1.47-ndb- 7.1.5		
interactive	Run ndb_mgmd in interactive mode (not officially supported in production; for testing purposes only)			
log-name=	A name to use when writing messages applying to this node in the cluster log.	5.1.37-ndb- 7.0.8		
mycnf	Read cluster configuration data from the my.cnf file			
no-nodeid-checks	Do not provide any node id checks			
nodaemon	Do not run ndb_mgmd as a daemon			
nowait-nodes=list	Do not wait for these management nodes when starting this management server. Also requiresndb-nodeid to be used.	5.1.39-ndb- 7.0.10, 5.1.39-ndb- 7.1.0		
print-full-config	Print full configuration and exit			
reload	Causes the management server to compare the configuration file with its configuration cache	5.1.30-ndb- 6.4.0		
remove[=name]	Used to remove a management server process that was previously installed as a Windows service, optionally specifying the name of the service to be removed. Does not apply on non-Windows platforms.	5.1.47-ndb- 7.0.16, 5.1.47-ndb- 7.1.5		

• --bind-address=host[:port]

Version Introduced	5.1.22-ndb-	5.1.22-ndb-6.2.5, 5.1.22-ndb-6.3.2	
Command-Line Format	bind-a	bind-address	
	Permitted Values		
	Type	Type string	
	Default	Default [none]	

When specified, this option limits management server connections by management clients to clients at the specified host name or IP address (and possibly port, if this is also specified). In such cases, a management client attempting to connect to the management server from any other address fails with the error UNABLE TO SETUP PORT: HOST: PORT!

If the *port* is not specified, the management client attempts to use port 1186.

This option was added in MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2.

• --configdir=directory

Version Introduced	5.1.30-ndb	5.1.30-ndb-6.4.0		
Command-Line Format	config	configdir=directory		
	- config- dir=dir ectory			
	Permitted	Permitted Values		
	Type	file name		
	Default \$INSTALLDIR/mysql-cluster			

Beginning with MySQL Cluster NDB 6.4.0, configuration data is cached internally rather than being read from the cluster global configuration file each time the management server is started (see Section 3.2, "MySQL Cluster Configuration Files"). This option instructs the management server to its configuration cache in the <code>directory</code> indicated. By default, this is a directory named <code>mysql-cluster</code> in the MySQL installation directory—for example, if you compile and install MySQL Cluster on a Unix system using the default location, this is <code>/usr/local/mysql-cluster</code>.

This behavior can be overridden using the <code>--initial</code> or <code>--reload</code> option for <code>ndb_mgmd</code>. Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, it can also be overridden using the <code>--config-cache</code> option. Each of these options is described elsewhere in this section.

This option is available beginning with MySQL Cluster NDB 6.4.0.

Beginning with MySQL Cluster NDB 7.0.8, --config-dir is accepted as an alias for --configdir.

- This option, whose default value is 1 (or TRUE, or ON), can be used to disable the management server's configuration cache, so that it reads its configuration from config.ini every time it starts (see Section 3.2, "MySQL Cluster Configuration Files"). You can do this by starting the ndb_mgmd process with any one of the following options:
 - --config-cache=0
 - --config-cache=FALSE
 - --config-cache=OFF
 - --skip-config-cache

Using one of the options just listed is effective only if the management server has no stored configuration at the time it is started. If the management server finds any configuration cache files, then the <code>--config-cache</code> option or the <code>--skip-config-cache</code> option is ignored. Therefore, to disable configuration caching, the option should be used the *first* time that the management server is started. Otherwise—that is, if you wish to disable configuration caching for a management server that has *already* created a configuration cache—you must stop the management server, delete any existing configuration cache files manually, then restart the management server with <code>--skip-config-cache</code> (or with <code>--config-cache</code> set equal to 0, OFF, or FALSE).

Configuration cache files are normally created in a directory named mysql-cluster under the installation directory (unless this location has been overridden using the --configdir option). Each time the management server updates its configuration data, it writes a new cache file. The files are named sequentially in order of creation using the following format:

ndb_node-id_config.bin.seq-number

node-id is the management server's node ID; seq-number is a sequence number, beginning with 1. For example, if the management server's node ID is 5, then the first three configuration cache files would, when they are created, be named ndb_5_config.bin.1, ndb_5_config.bin.2, and ndb_5_config.bin.3.

If your intent is to purge or reload the configuration cache without actually disabling caching, you should start ndb_mgmd with

one of the options --reload or --initial instead of --skip-config-cache.

To re-enable the configuration cache, simply restart the management server, but without the --config-cache or --skip-config-cache option that was used previously to disable the configuration cache.

This option was added in MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4.

• --config-file=filename, -f filename

Command-Line Format	config	config-file	
	-f	f	
	-C	-c	
	Permitted	Permitted Values	
	Type	file name	
	Default ./config.ini		

Instructs the management server as to which file it should use for its configuration file. By default, the management server looks for a file named config.ini in the same directory as the ndb_mgmd executable; otherwise the file name and location must be specified explicitly.

Beginning with MySQL Cluster NDB 6.4.0, this option is ignored unless the management server is forced to read the configuration file, either because ndb_mgmd was started with the --reload or --initial option, or because the management server could not find any configuration cache. Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option is also read if ndb_mgmd was started with --config-cache=OFF. See Section 3.2, "MySQL Cluster Configuration Files", for more information.

• --daemon, -d

Command-Line Format	daemor	daemon		
	-d	-d		
	Permitted Values Type boolean			
	Default TRUE			

Instructs ndb_mgmd to start as a daemon process. This is the default behavior.

This option has no effect when running ndb_mgmd on Windows platforms.

--initial

Version Introduced	5.1.30-ndb-	5.1.30-ndb-6.4.0		
Command-Line Format	initia	initial		
	Permitted Values			
	Type	boolean		
	Default	FALSE		

Beginning with MySQL Cluster NDB 6.4.0, configuration data is cached internally rather than being read from the cluster global configuration file each time the management server is started (see Section 3.2, "MySQL Cluster Configuration Files"). Using this option overrides this behavior, by forcing the management server to delete any existing cache files, and then to re-read the configuration data from the cluster configuration file and to build a new cache.

This differs in two ways from the <code>--reload</code> option. First, <code>--reload</code> forces the server to check the configuration file against the cache and reload its data only if the contents of the file are different from the cache. Second, <code>--reload</code> does not delete any existing cache files.

If ndb_mgmd is invoked with --initial but cannot find a global configuration file, the management server cannot start.

This option was introduced in MySQL Cluster NDB 6.4.0.

• --log-name=*name*

Version Introduced	5.1.37-ndb-	5.1.37-ndb-7.0.8		
Command-Line Format	log-na	log-name=		
	Permitted Values			
	Type	string		
	Default	Default MgmtSrvr		

Provides a name to be used for this node in the cluster log.

This option was added in MySQL Cluster NDB 7.0.8.

--nodaemon

Command-Line Format	nodaen	nodaemon	
	Permitted	Values	
	Type	boolean	
	Default	FALSE	
	Permitted	Values	
	Type (windows)	boolean	
	Default	TRUE	

Instructs ndb_mgmd not to start as a daemon process.

As of MySQL Cluster NDB 7.0.8, the default behavior for ndb_mgmd on Windows is to run in the foreground, making this option unnecessary on Windows platforms. (Bug #45588)

• --print-full-config, -P

Command-Line Format	print-	print-full-config		
	-P	-P		
	Permitted Values			
	Type	boolean		
	Default	Default FALSE		

Shows extended information regarding the configuration of the cluster. With this option on the command line the ndb_mgmd process prints information about the cluster setup including an extensive list of the cluster configuration sections as well as parameters and their values. Normally used together with the --config-file(-f) option.

--reload

Version Introduced	5.1.30-ndb-	5.1.30-ndb-6.4.0	
Command-Line Format	reload	reload	
	Permitted	Permitted Values	
	Type	Type boolean	
	Default	Default FALSE	

Beginning with MySQL Cluster NDB 6.4.0, configuration data is stored internally rather than being read from the cluster global configuration file each time the management server is started (see Section 3.2, "MySQL Cluster Configuration Files"). Using this option forces the management server to check its internal data store against the cluster configuration file and to reload the configuration if it finds that the configuration file does not match the cache. Existing configuration cache files are preserved, but not used

This differs in two ways from the --initial option. First, --initial causes all cache files to be deleted. Second, --initial forces the management server to re-read the global configuration file and construct a new cache.

If the management server cannot find a global configuration file, then the --reload option is ignored.

This option was introduced in MySQL Cluster NDB 6.4.0.

• --nowait-nodes

Version Introduced	5.1.39-ndb-	5.1.39-ndb-7.0.10, 5.1.39-ndb-7.1.0	
Command-Line Format	nowait	nowait-nodes=list	
	Permitted	Permitted Values	
	Type	numeric	
	Default	Default	
	Range	Range 1-255	

When starting a MySQL Cluster is configured with two management nodes and running MySQL Cluster NDB 7.0 and later, each management server normally checks to see whether the other ndb_mgmd is also operational and whether the other management server's configuration is identical to its own. However, it is sometimes desirable to start the cluster with only one management node (and perhaps to allow the other ndb_mgmd to be started later). This option causes the management node to bypass any checks for any other management nodes whose node IDs are passed to this option, permitting the cluster to start as though configured to use only the management node that was started.

For purposes of illustration, consider the following portion of a config.ini file (where we have omitted most of the configuration parameters that are not relevant to this example):

```
NodeId = 1
HostName = 192.168.0.101
[ndbd]
NodeId = 2
HostName = 192.168.0.102
[ndbd]
NodeId = 3
HostName = 192.168.0.103
[ndbd]
NodeId = 4
Nodeld = 192.168.0.104

[ndb_mgmd]

Nodeld = 10

HostName = 192.168.0.150
[ndb_mgmd]
NodeId = 11
HostName = 192.168.0.151
[api]
NodeId = 20
HostName = 192.168.0.200
[api]
NodeId = 21
HostName = 192.168.0.201
```

Assume that you wish to start this cluster using only the management server having node ID 10 and running on the host having the IP address 192.168.0.150. (Suppose, for example, that the host computer on which you intend to the other management server is temporarily unavailable due to a hardware failure, and you are waiting for it to be repaired.) To start the cluster in this way, use a command line on the machine at 192.168.0.150 to enter the following command:

```
shell> ndb_mgmd --ndb-nodeid=10 --nowait-nodes=11
```

As shown in the preceding example, when using --nowait-nodes, you must also use the --ndb-nodeid option to specify the node ID of this ndb_mgmd process.

You can then start each of the cluster's data nodes in the usual way. If you wish to start and use the second management server in addition to the first management server at a later time without restarting the data nodes, you must start each data node with a connectstring that references both management servers, like this:

```
shell> ndbd -c 192.168.0.150,192.168.0.151
```

The same is true with regard to the connectstring used with any mysqld processes that you wish to start as MySQL Cluster SQL nodes connected to this cluster. See Section 3.2.3, "The MySQL Cluster Connectstring", for more information.

When used with ndb_mgmd, this option affects the behavior of the management node with regard to other management nodes only. Do not confuse it with the --nowait-nodes option used with ndbd (or ndbmtd in MySQL Cluster NDB 7.0 and later) to permit a cluster to start with fewer than its full complement of data nodes; when used with data nodes, this option affects their behavior only with regard to other data nodes.

Multiple management node IDs may be passed to this option as a comma-separated list. Each node ID must be no less than 1

and no greater than 255. In practice, it is quite rare to use more than two management servers for the same MySQL Cluster (or to have any need for doing so); in most cases you need to pass to this option only the single node ID for the one management server that you do not wish to use when starting the cluster.

Note

When you later start the "missing" management server, its configuration must match that of the management server that is already in use by the cluster. Otherwise, it fails the configuration check performed by the existing management server, and does not start.

This option was introduced in MySQL Cluster NDB 7.0.10 and MySQL Cluster NDB 7.1.0.

It is not strictly necessary to specify a connectstring when starting the management server. However, if you are using more than one management server, a connectstring should be provided and each node in the cluster should specify its node ID explicitly.

See Section 3.2.3, "The MySQL Cluster Connectstring", for information about using connectstrings. Section 4.4, "ndb_mgmd — The MySQL Cluster Management Server Daemon", describes other options for ndb_mgmd.

The following files are created or used by ndb_mgmd in its starting directory, and are placed in the DataDir as specified in the config.ini configuration file. In the list that follows, node_id is the unique node identifier.

- config. ini is the configuration file for the cluster as a whole. This file is created by the user and read by the management server. Chapter 3, MySQL Cluster Configuration, discusses how to set up this file.
- ndb_node_id_cluster.log is the cluster events log file. Examples of such events include checkpoint startup and completion, node startup events, node failures, and levels of memory usage. A complete listing of cluster events with descriptions may be found in Chapter 5, Management of MySQL Cluster.

When the size of the cluster log reaches one million bytes, the file is renamed to ndb_node_id_cluster.log.seq_id, where seq_id is the sequence number of the cluster log file. (For example: If files with the sequence numbers 1, 2, and 3 already exist, the next log file is named using the number 4.)

- ndb_node_id_out.log is the file used for stdout and stderr when running the management server as a daemon.
- ndb_node_id.pid is the process ID file used when running the management server as a daemon.
- --install[=name]

Version Introduced	5.1.47-ndb-	5.1.47-ndb-7.0.16, 5.1.47-ndb-7.1.5	
Command-Line Format	instal	install[=name]	
	Permitted Values		
	Type (windows)	string	
	Default	ndb_mgmd	

Causes ndb_mgmd to be installed as a Windows service. Optionally, you can specify a name for the service; if not set, the service name defaults to ndb_mgmd. Although it is preferable to specify other ndb_mgmd program options in a my.ini or my.cnf configuration file, it is possible to use them together with --install. However, in such cases, the --install option must be specified first, before any other options are given, for the Windows service installation to succeed.

It is generally not advisable to use this option together with the --initial option, since this causes the configuration cache to be wiped and rebuilt every time the service is stopped and started. Care should also be taken if you intend to use any other ndb_mgmd options that affect the starting of the management server, and you should make absolutely certain you fully understand and allow for any possible consequences of doing so.

The --install option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

• --remove[=*name*]

Version Introduced	5.1.47-ndb-7.0.16, 5.1.47-ndb-7.1.5	
Command-Line Format	remove[=name]	

	Permitted	Values
	Type (windows)	string
	Default	ndb_mgmd

Causes an ndb_mgmd process that was previously installed as a Windows service to be removed. Optionally, you can specify a name for the service to be uninstalled; if not set, the service name defaults to ndb_mgmd.

The --remove option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

4.5. ndb_mgm — The MySQL Cluster Management Client

The ndb_mgm management client process is actually not needed to run the cluster. Its value lies in providing a set of commands for checking the cluster's status, starting backups, and performing other administrative functions. The management client accesses the management server using a C API. Advanced users can also employ this API for programming dedicated management processes to perform tasks similar to those performed by ndb_mgm.

To start the management client, it is necessary to supply the host name and port number of the management server:

```
shell> ndb_mgm [host_name [port_num]]
```

For example:

```
shell> ndb_mgm ndb_mgmd.mysql.com 1186
```

The default host name and port number are localhost and 1186, respectively.

The following table includes options that are specific to the MySQL Cluster management client program ndb_mgm. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.3. ndb_mgm Command Line Options

Format	_ <u>*</u>	Introduc- tion	Deprecated	Removed
execute=name	Execute command and exit			
try-reconnect=#	Specify number of tries for connecting to ndb_mgmd (0 = infinite)			

• --execute=command, -e command

Command-Line Format	execute=name	
	-е	

This option can be used to send a command to the MySQL Cluster management client from the system shell. For example, either of the following is equivalent to executing SHOW in the management client:

```
shell> ndb_mgm -e "SHOW"
shell> ndb_mgm --execute="SHOW"
```

This is analogous to how the --execute or -e option works with the mysql command-line client. See Using Options on the Command Line.

Note

If the management client command to be passed using this option contains any space characters, then the command *must* be enclosed in quotation marks. Either single or double quotation marks may be used. If the management client

- command contains no space characters, the quotation marks are optional.
- --try-reconnect=number

Command-Line Format	try-reconnect=#		
	-t	-t	
	Permitted Values		
	Type	boolean	
	Default	TRUE	

If the connection to the management server is broken, the node tries to reconnect to it every 5 seconds until it succeeds. By using this option, it is possible to limit the number of attempts to number before giving up and reporting an error instead.

Additional information about using ndb_mgm can be found in Section 5.2, "Commands in the MySQL Cluster Management Client"

4.6. ndb_config — Extract MySQL Cluster Configuration Information

This tool extracts current configuration information for data nodes, SQL nodes, and API nodes from a cluster management node (and possibly its config.ini file). Beginning with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, it can also provide an offline dump (in text or XML format) of all configuration parameters which can be used, along with their default, maximum, and minimum values and other information (see the discussion of the --configinfo and --xml options later in this section).

The following table includes options that are specific to ndb_config. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.4. ndb config Command Line Options

Format	Description	Introduc- tion	Deprec- ated	Removed
configinfo	Dumps information about all NDB configuration parameters in text format with default, maximum, and minimum values. Use withxml to obtain XML output.	5.1.34-ndb- 6.3.25, 5.1.34-ndb- 7.0.6		
connections	Print connection information only			
fields=string	Field separator			
host=name	Specify host			
mycnf	Read configuration data from my.cnf file			
nodeid	Get configuration of node with this ID			
nodes	Print node information only			
	Short form forndb-connectstring	5.1.12		
config-file=path	Set the path to config.ini file			
query=string	One or more query options (attributes)			
rows=string	Row separator			
type=name	Specify node type			
configinfoxml	Use withconfiginfo to obtain a dump of all NDB configuration parameters in XML format with default, maximum, and minimum values.	5.1.34-ndb- 6.3.25, 5.1.34-ndb- 7.0.6		

• --usage, --help, or -?

Command-Line Format	help	
	usage	

1= 5

Causes ndb_config to print a list of available options, and then exit.

• --version, -V

Command-Line Format	-V
	version

Causes ndb_config to print a version information string, and then exit.

• --ndb-connectstring=connect_string

Command-Line Format	ndb-co	ndb-connectstring=name	
	connec	connect-string=name	
	-c		
	Permitted Values		
	Type	string	
	Default	localhost:1186	

Specifies the connectstring to use in connecting to the management server. The format for the connectstring is the same as described in Section 3.2.3, "The MySQL Cluster Connectstring", and defaults to localhost:1186.

The use of -c as a short version for this option is supported for ndb_config beginning with MySQL 5.1.12.

• --config-file=path-to-file

Gives the path to the management server's configuration file (config.ini). This may be a relative or absolute path. If the management node resides on a different host from the one on which ndb_config is invoked, then an absolute path must be used

• --query=query-options, -q query-options

Command-Line Format	query=string		
	-d	-q	
	Permitted Values		
	Type	string	
	Default		

This is a comma-delimited list of *query options*—that is, a list of one or more node attributes to be returned. These include id (node ID), type (node type—that is, ndbd, mysqld, or ndb_mgmd), and any configuration parameters whose values are to be obtained.

For example, -query=id, type, indexmemory, datamemory returns the node ID, node type, DataMemory, and IndexMemory for each node.

Note

If a given parameter is not applicable to a certain type of node, than an empty string is returned for the corresponding value. See the examples later in this section for more information.

• --host=hostname

Command-Line Format	host=r	-host=name		
	Permitted	mitted Values		
	Type	string		
	Default			

Specifies the host name of the node for which configuration information is to be obtained.

Note

While the hostname localhost usually resolves to the IP address 127.0.0.1, this may not necessarily be true for all operating platforms and configurations. This means that it is possible, when localhost is used in config.ini, for ndb_config --host=localhost to fail if ndb_config is run on a different host where localhost resolves to a different address (for example, on some versions of SUSE Linux, this is 127.0.0.2). In general, for best results, you should use numeric IP addresses for all MySQL Clustewr configuration values relating to hosts, or verify that all MySQL Cluster hosts handle localhost in the same fashion.

- --id=node_id,
 - --nodeid=node_id

Either of these options can be used to specify the node ID of the node for which configuration information is to be obtained. – nodeid is the preferred form.

• --nodes

Command-Line Format	nodes	
	Permitted	Values
	Type	boolean
	Default	FALSE

Tells ndb_config to print information from parameters defined in [ndbd] sections only. Currently, using this option has no affect, since these are the only values checked, but it may become possible in future to query parameters set in [tcp] and other sections of cluster configuration files.

• --type=node_type

Command-Line Format	type=	type=name			
	Permittee	d Values			
	Type	enumeration			
	Default				
	Valid Values	ndbd			
		mysqld			
		ndb_mgmd			

Filters results so that only configuration values applying to nodes of the specified *node_type* (ndbd, mysqld, or ndb_mgmd) are returned.

• --fields=delimiter, -f delimiter

Command-Line Format	fields	fields=string	
	-f		
	Permitted	Values	
	Type	string	
	Default		

Specifies a delimiter string used to separate the fields in the result. The default is "," (the comma character).

Note

If the delimiter contains spaces or escapes (such as \n for the linefeed character), then it must be quoted.

• --rows=separator, -r separator

Command-Line Format	rows=s	-rows=string		
	-r			
	Permitted	Values		
	Type	string		
	Default			

Specifies a *separator* string used to separate the rows in the result. The default is a space character.

Note

If the separator contains spaces or escapes (such as \n for the linefeed character), then it must be quoted.

--configinfo

The --configinfo option, added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, causes ndb_config to dump a list of each MySQL Cluster configuration parameter supported by the MySQL Cluster distribution of which ndb_config is a part, including the following information:

- A brief description of each parameter's purpose, effects, and usage
- The section of the config.ini file where the parameter may be used
- The parameter's data type or unit of measurement
- · Where applicable, the parameter's default, minimum, and maximum values
- · A brief description of the parameter's purpose, effects, and usage
- · MySQL Cluster release version and build information

By default, this output is in text format. Part of this output is shown here:

```
shell> ndb_config --configinfo
******* SYSTEM ******
Name (String)
Name of system (NDB Cluster)
MANDATORY
PrimaryMGMNode (Non-negative Integer)
Node id of Primary ndb_mgmd(MGM) node
Default: 0 (Min: 0, Max: 4294967039)
ConfigGenerationNumber (Non-negative Integer)
Configuration generation number
Default: 0 (Min: 0, Max: 4294967039)
***********
MaxNoOfSubscriptions (Non-negative Integer)
Max no of subscriptions (default 0 == MaxNoOfTables)
Default: 0 (Min: 0, Max: 4294967039)
MaxNoOfSubscribers (Non-negative Integer)
Max no of subscribers (Non-negative Integer)
Max no of subscribers (default 0 == 2 * MaxNoOfTables)
Default: 0 (Min: 0, Max: 4294967039)
...
```

--configinfo --xml

Version Introduced	5.1.34-ndb-	1.34-ndb-6.3.25, 5.1.34-ndb-7.0.6		
Command-Line Format	config	-configinfoxml		
	Permitted	ermitted Values		
	Type	e boolean		
	Default	fault false		

You can obtain the output of ndb_config --configinfo as XML by adding the --xml option (like the --configinfo option, available beginning with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6). A portion of the resulting output is shown in this example:

Note

Normally, the XML output produced by ndb_config --configinfo --xml is formatted using one line per element; we have added extra whitespace in the previous example, as well as the next one, for reasons of legibility. This should not make any difference to applications using this output, since most XML processors either ignore nonessential whitespace as a matter of course, or can be instructed to do so.

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, the XML output also indicates when changing a given parameter requires that data nodes be restarted using the <code>--initial</code> option. This is shown by the presence of an <code>ini-tial="true"</code> attribute in the corresponding <code><param></code> element. In addition (also beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10), the restart type (<code>system</code> or node) is also shown; if a given parameter requires a system restart, this is indicated by the presence of a <code>restart="system"</code> attribute in the corresponding <code><param></code> element. For example, changing the value set for the <code>Diskless</code> parameter requires a system initial restart, as shown here (with the <code>restart</code> and <code>initial</code> attributes highlighted for visibility):

```
<param name="Diskless" comment="Run wo/ disk" type="bool" default="false"
    restart="system" initial="true"/>
```

Important

The --xml option can be used only with the --configinfo option. Using --xml without --configinfo fails with an error.

Unlike the options used with this program to obtain current configuration data, --configinfo and --xml use information obtained from the MySQL Cluster sources when ndb_config was compiled. For this reason, no connection to a running MySQL Cluster or access to a config.ini or my.cnf file is required for these two options.

Combining other ndb_config options (such as --query or --type) with --configinfo or --xml is not supported. Currently, if you attempt to do so, the usual result is that all other options besides --configinfo or --xml are simply ignored. However, this behavior is not guaranteed and is subject to change at any time. In addition, since ndb_config, when used with the --configinfo option, does not access the MySQL Cluster or read any files, trying to specify additional options such as --ndb-connectstring or --config-file with --configinfo serves no purpose.

Examples

1. To obtain the node ID and type of each node in the cluster:

```
shell> ./ndb_config --query=id,type --fields=':' --rows='\n'
1:ndbd
2:ndbd
3:ndbd
4:ndbd
5:ndb_mgmd
6:mysqld
7:mysqld
8:mysqld
9:mysqld
```

In this example, we used the --fields options to separate the ID and type of each node with a colon character (:), and the --rows options to place the values for each node on a new line in the output.

2. To produce a connectstring that can be used by data, SQL, and API nodes to connect to the management server:

```
shell> ./ndb_config --config-file=usr/local/mysql/cluster-data/config.ini --query=hostname,portnumber --fields=: 192.168.0.179:1186
```

3. This invocation of ndb_config checks only data nodes (using the --type option), and shows the values for each node's ID and host name, as well as the values set for its DataMemory, IndexMemory, and DataDir parameters:

```
shell> ./ndb_config --type=ndbd --query=id,host,datamemory,indexmemory,datadir -f ' : ' -r '\n'
1 : 192.168.0.193 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
2 : 192.168.0.112 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
3 : 192.168.0.176 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
4 : 192.168.0.119 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
```

In this example, we used the short options -f and -r for setting the field delimiter and row separator, respectively.

4. To exclude results from any host except one in particular, use the --host option:

```
shell> ./ndb_config --host=192.168.0.176 -f : -r '\n' -q id,type
3:ndbd
5:ndb_mgmd
```

In this example, we also used the short form -q to determine the attributes to be queried.

Similarly, you can limit results to a node with a specific ID using the --id or --nodeid option.

4.7. ndb_cpcd — Automate Testing for NDB Development

This utility is found in the libexec directory. It is part of an internal automated test framework used in testing and debugging MySQL Cluster. Because it can control processes on remote systems, it is not advisable to use ndb_cpcd in a production cluster.

The source files for ndb_cpcd may be found in the directory storage/ndb/src/cw/cpcd, in the MySQL Cluster source tree

4.8. ndb delete all — Delete All Rows from an NDB Table

 ${\tt ndb_delete_all} \ \ deletes \ all \ rows \ from \ the \ given \ {\tt NDB} \ table. \ In \ some \ cases, this \ can be \ much \ faster \ than \ {\tt DELETE} \ or \ even \ TRUNCATE \ \ TABLE.$

Usage

```
ndb_delete_all -c connect_string tbl_name -d db_name
```

This deletes all rows from the table named tbl_name in the database named db_name . It is exactly equivalent to executing TRUNCATE db_name in MySQL.

Additional Options

• --transactional, -t

Use of this option causes the delete operation to be performed as a single transaction.

Warning

With very large tables, using this option may cause the number of operations available to the cluster to be exceeded.

4.9. ndb_desc — Describe NDB Tables

ndb_desc provides a detailed description of one or more NDB tables.

Usage

```
ndb_desc -c connect_string tbl_name -d db_name [-p]
```

Sample Output

MySQL table creation and population statements:

```
USE test;

CREATE TABLE fish (
    id INT(11) NOT NULL AUTO_INCREMENT,
    name VARCHAR(20) NOT NULL,
    length_mm INT(11) NOT NULL,
    weight_gm INT(11) NOT NULL,
    PRIMARY KEY pk (id),
    UNIQUE KEY uk (name)
) ENGINE=NDB;
INSERT INTO fish VALUES
    ('','guppy', 35, 2), ('','tuna', 2500, 150000),
    ('','shark', 3000, 110000), ('','manta ray', 1500, 50000),
    (''','grouper', 900, 125000), (''','puffer', 250, 2500);
```

Output from ndb_desc:

```
shell> ./ndb_desc -c localhost fish -d test -p
  - fish
Version: 2
Fragment type: 9
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 4
Number of primary keys: 1
Length of frm data: 311
Row Checksum: 1
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 2
TableStatus: Retrieved
-- Attributes -- id Int PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
name Varchar(20;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY length_mm Int NOT NULL AT=FIXED ST=MEMORY
weight_gm Int NOT NULL AT=FIXED ST=MEMORY
-- Indexes --
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
uk$unique(name) - UniqueHashIndex
uk(name) - OrderedIndex
          partition info
Partition Row count Commit count
                                                    Frag fixed memory Frag varsized memory Extent_space 32768 0
                                                                                                                                      Free extent space
                                                                                                                  0
                                                                                                                                       0
                                                     32768
                                                                                  32768
NDBT_ProgramExit: 0 - OK
```

Information about multiple tables can be obtained in a single invocation of ndb_desc by using their names, separated by spaces. All of the tables must be in the same database.

The Extent_space and Free extent_space columns were added in MySQL Cluster NDB 6.3.27 and MySQL Cluster NDB 7.0.8. They are applicable only to NDB tables having columns on disk; for tables having only in-memory columns, these columns always contain the value 0.

To illustrate their use, we modify the previous example. First, we must create the necessary Disk Data objects, as shown here:

```
CREATE LOGFILE GROUP lg_1

ADD UNDOFILE 'undo_1.log'
INITIAL_SIZE 16M
UNDO_BUFFER_SIZE 2M
ENGINE NDB;

ALTER LOGFILE GROUP lg_1

ADD UNDOFILE 'undo_2.log'
INITIAL_SIZE 12M
ENGINE NDB;

CREATE TABLESPACE ts_1

ADD DATAFILE 'data_1.dat'
USE LOGFILE GROUP lg_1
INITIAL_SIZE 32M
ENGINE NDB;

ALTER TABLESPACE ts_1

ADD DATAFILE 'data_2.dat'
INITIAL_SIZE 34M
ENGINE NDB;
```

(For more information on the statements just shown and the objects created by them, see Section 5.11.1, "MySQL Cluster Disk Data Objects", as well as CREATE LOGFILE GROUP Syntax, and CREATE TABLESPACE Syntax.)

Now we can create and populate a version of the fish table that stores 2 of its columns on disk (deleting the previous version of the table first, if it already exists):

```
CREATE TABLE fish (
    id INT(11) NOT NULL AUTO_INCREMENT,
    name VARCHAR(20) NOT NULL,
    length_mm INT(11) NOT NULL,
    weight_gm INT(11) NOT NULL,
    weight_gm INT(11) NOT NULL,
    PRIMARY KEY pk (id),
    UNIQUE KEY uk (name)
) TABLESPACE ts_1 STORAGE DISK
ENGINE=NDB;
INSERT INTO fish VALUES
    ('','guppy', 35, 2), ('','tuna', 2500, 150000),
    (''','shark', 3000, 110000), ('','manta ray', 1500, 50000),
    (''','grouper', 900, 125000), (''','puffer', 250, 2500);
```

When run against this version of the table, ndb desc displays the following output:

```
shell> ./ndb_desc -c localhost fish -d test -p
     fish
Version:
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 4
Number of primary keys:
Length of frm data: 321
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount:
TableStatus: Retrieved
    Attributes
-- Attributes --
id Int PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
name Varchar(20;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
length_mm Int NOT NULL AT=FIXED ST=DISK
weight_gm Int NOT NULL AT=FIXED ST=DISK
-- Indexes --
PRIMARY KEY(id) - UniqueHashIndex
DDTMAPV(id) - OrderedIndex
PRIMARY(id)
                    - OrderedIndex
uk$unique(name) - UniqueHashIndex
uk(name) - OrderedIndex
     Per partition info
Partition Row count Commit count
                                                             Frag fixed memory
                                                                                              Frag varsized memory
                                                                                                                                    Extent_space
                                                                                                                                                            Free extent_space
                                                              32768
                                                                                              32768
                                                                                                                                    1048576
                                                                                                                                                            1044440
                                                              32768
                                                                                              32768
                                                                                                                                    1048576
                                                                                                                                                            1044400
NDBT_ProgramExit: 0 - OK
```

This means that 1048576 bytes are allocated from the tablespace for this table on each partition, of which 1044440 bytes remain free for additional storage. In other words, 1048576 - 1044440 = 4136 bytes per partition is currently being used to store the data from this table's disk-based columns. The number of bytes shown as Free extent_space is available for storing on-disk column data from the fish table only; for this reason, it is not visible when selecting from the INFORMATION_SCHEMA.FILES table.

Additional Options

--extra-partition-info,-p

Print additional information about the table's partitions.

• --blob-info, -b

Include information about subordinate BLOB and TEXT columns.

Use of this option also requires the use of the --extra-partition-info (-p) option.

This option was added in MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2.

• --extra-node-info,-n

Include information about the mappings between table partitions and the data nodes upon which they reside. This information can be useful for verifying distribution awareness mechanisms and supporting more efficient application access to the data stored in MySQL Cluster.

Use of this option also requires the use of the --extra-partition-info (-p) option.

This option was added in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.33, MySQL Cluster NDB 7.0.14, and MySQL Cluster NDB 7.1.2.

4.10. ndb_drop_index — Drop Index from an NDB Table

ndb_drop_index drops the specified index from an NDB table. It is recommended that you use this utility only as an example for writing NDB API applications—see the Warning later in this section for details.

Usage

```
ndb_drop_index -c connect_string table_name index -d db_name
```

The statement shown above drops the index named index from the table in the database.

Additional Options

None that are specific to this application.

Warning

Operations performed on Cluster table indexes using the NDB API are not visible to MySQL and make the table unusable by a MySQL server. If you use this program to drop an index, then try to access the table from an SQL node, an error results, as shown here:

In such a case, your *only* option for making the table available to MySQL again is to drop the table and re-create it. You can use either the SQL statementDROP TABLE or the ndb_drop_table utility (see Section 4.11, "ndb_drop_table — Drop an NDB Table") to drop the table.

4.11. ndb_drop_table — Drop an NDB Table

ndb_drop_table drops the specified NDB table. (If you try to use this on a table created with a storage engine other than NDB, the attempt fails with the error 723: NO SUCH TABLE EXISTS.) This operation is extremely fast; in some cases, it can be an order of magnitude faster than using a MySQL DROP TABLE statement on an NDB table.

Usage

```
ndb_drop_table -c connect_string tbl_name -d db_name
```

Additional Options

None.

4.12. ndb_error_reporter — NDB Error-Reporting Utility

ndb_error_reporter creates an archive from data node and management node log files that can be used to help diagnose bugs or other problems with a cluster. It is highly recommended that you make use of this utility when filing reports of bugs in MySQL Cluster.

Usage

ndb_error_reporter path/to/config-file [username] [--fs]

This utility is intended for use on a management node host, and requires the path to the management host configuration file (config.ini). Optionally, you can supply the name of a user that is able to access the cluster's data nodes using SSH, to copy the data node log files. ndb_error_reporter then includes all of these files in archive that is created in the same directory in which it is run. The archive is named ndb_error_report_YYYYMMDDHHMMSS.tar.bz2, where YYYYMMDDHHMMSS is a datetime string.

If the --fs is used, then the data node file systems are also copied to the management host and included in the archive that is produced by this script. As data node file systems can be extremely large even after being compressed, we ask that you please do *not* send archives created using this option to Oracle unless you are specifically requested to do so.

Command-Line Format	fs	
	Permitted	Values
	Type	boolean
	Default	FALSE

4.13. ndb_print_backup_file — Print NDB Backup File Contents

ndb_print_backup_file obtains diagnostic information from a cluster backup file.

Usage

ndb_print_backup_file file_name

file_name is the name of a cluster backup file. This can be any of the files (.Data, .ctl, or .log file) found in a cluster backup directory. These files are found in the data node's backup directory under the subdirectory BACKUP-#, where # is the sequence number for the backup. For more information about cluster backup files and their contents, see Section 5.3.1, "MySQL Cluster Backup Concepts".

Like ndb_print_schema_file and ndb_print_sys_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb_print_backup_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

Additional Options

None.

4.14. ndb_print_schema_file — Print NDB Schema File Contents

ndb_print_schema_file obtains diagnostic information from a cluster schema file.

Usage

ndb_print_schema_file file_name

file_name is the name of a cluster schema file. For more information about cluster schema files, see Cluster Data Node FileSystemDir Files.

Like ndb_print_backup_file and ndb_print_sys_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb_schema_backup_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

Additional Options

None.

4.15. ndb_print_sys_file — Print NDB System File Contents

 ${\tt ndb_print_sys_file}\ obtains\ diagnostic\ information\ from\ a\ MySQL\ Cluster\ system\ file.$

Usage

ndb_print_sys_file file_name

file_name is the name of a cluster system file (sysfile). Cluster system files are located in a data node's data directory (DataDir); the path under this directory to system files matches the pattern ndb_#_fs/D#/DBDIH/P#.sysfile. In each case, the # represents a number (not necessarily the same number). For more information, see Cluster Data Node FileSystem-Dir Files

Like ndb_print_backup_file and ndb_print_schema_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb_print_backup_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

Additional Options

None.

4.16. ndbd_redo_log_reader — Check and Print Content of Cluster Redo Log

Reads a redo log file, checking it for errors, printing its contents in a human-readable format, or both. nd-bd_redo_log_reader is intended for use primarily by MySQL developers and support personnel in debugging and diagnosing problems.

This utility was made available as part of default builds beginning with MySQL Cluster NDB 6.1.3. It remains under development, and its syntax and behavior are subject to change in future releases. For this reason, it should be considered experimental at this time.

The C++ source files for ndbd_redo_log_reader can be found in the directory /storage/ndb/src/kernel/blocks/dblqh/redoLogReader.

The following table includes options that are specific to the MySQL Cluster program ndbd_redo_log_reader. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.5. ndbd_redo_log_reader Command Line Options

Format	Description	 Deprec- ated	Removed
-nocheck	Do not check records for errors		
-noprint	Do not print records		

Usage

ndbd_redo_log_reader file_name [options]

file_name is the name of a cluster redo log file. redo log files are located in the numbered directories under the data node's data directory (DataDir); the path under this directory to the redo log files matches the pattern ndb_#_fs/D#/LCP/#/T#F#.Data. In each case, the # represents a number (not necessarily the same number). For more information, see Cluster Data Node FileSystemDir Files.

The name of the file to be read may be followed by one or more of the options listed here:

Command-Line Format	-noprint	noprint	
	Permitted	Values	
	Type	boolean	
	Default	FALSE	

-noprint: Do not print the contents of the log file.

Command-Line Format	-nochec	nocheck		
	Permitted	Values		
	Type	boolean		
	Default	FALSE		

⁻nocheck: Do not check the log file for errors.

Like ndb_print_backup_file and ndb_print_schema_file (and unlike most of the NDB utilities that are intended to be run on a management server host or to connect to a management server) ndbd_redo_log_reader must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

4.17. ndb_restore — Restore a MySQL Cluster Backup

The cluster restoration program is implemented as a separate command-line utility ndb_restore, which can normally be found in the MySQL bin directory. This program reads the files created as a result of the backup and inserts the stored information into the database

ndb_restore must be executed once for each of the backup files that were created by the START BACKUP command used to create the backup (see Section 5.3.2, "Using The MySQL Cluster Management Client to Create a Backup"). This is equal to the number of data nodes in the cluster at the time that the backup was created.

Note

Before using ndb_restore, it is recommended that the cluster be running in single user mode, unless you are restoring multiple data nodes in parallel. See Section 5.7, "MySQL Cluster Single User Mode", for more information.

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb_restore. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.6. ndb restore Command Line Options

Format	Description	Introduc- tion	Deprec- ated	Removed
append	Append data to a tab-delimited file	5.1.18		
backup_path=path	Path to backup files directory	5.1.15-ndb- 6.1.5, 5.1.17		
backupid=#	Restore from the backup with the given ID			
connect	Same as connectstring			
restore_data	Restore table data and logs into NDB Cluster using the NDB API			
disable-indexes	Causes indexes from a backup to be ignored; may decrease time needed to restore data.	5.1.41-ndb- 6.3.31, 5.1.41-ndb- 7.0.11, 5.1.41-ndb- 7.1.2		
dont_ignore_systab_0	Do not ignore system table during restore. Experimental only; not for production use			
- -ex- clude-databases=db-list	List of one or more databases to exclude (includes those not named)	5.1.31-ndb- 6.3.22, 5.1.32-ndb- 6.4.3		
- -ex- clude-missing-columns	Causes columns from the backup version of a table that are missing from the version of the table in the database to be ignored.	5.1.35-ndb- 6.3.26, 5.1.35-ndb- 7.0.7		
-	List of one or more tables to exclude (includes those in same	5.1.31-ndb-		

Format	Description	Introduc- tion	Deprecated	Removed
-ex- clude-tables=table-list	database that are not not named); each table reference must include the database name	6.3.22, 5.1.32-ndb- 6.4.3		
- -fields-enclosed-by=char	Fields are enclosed with the indicated character	5.1.18		
- fields-option- ally-enclosed-by	Fields are optionally enclosed with the indicated character	5.1.18		
- - fields-termin- ated-by=char	Fields are terminated by the indicated character	5.1.18		
hex	Print binary types in hexadecimal format	5.1.18		
in- clude-databases=db-list	List of one or more databases to restore (excludes those not named)	5.1.31-ndb- 6.3.22, 5.1.32-ndb- 6.4.3		
- -include-tables=table-list	List of one or more tables to restore (excludes those in same database that are not named); each table reference must include the database name	5.1.31-ndb- 6.3.22, 5.1.32-ndb- 6.4.3		
- - lines-termin-	Lines are terminated by the indicated character	5.1.18		
ated-by=char				
lossy-conversions	Allow lossy conversions of column values (type demotions or changes in sign) when restoring data from backup	5.1.51-ndb- 7.1.11		
restore_meta	Restore metadata to NDB Cluster using the NDB API			
- - ndb-node- group-map=map	Nodegroup map for NDBCLUSTER storage engine. Syntax: list of (source_nodegroup, destination_nodegroup)			
no-binlog	If a mysqld is connected and using binary logging, do not log the restored data	5.1.24-ndb- 6.2.16, 5.1.24-ndb- 6.3.16		
no-restore-disk-objects	Do not restore Disk Data objects such as tablespaces and log file groups			
no-upgrade	Do not upgrade array type for varsize attributes which do not already resize VAR data, and do not change column attributes	5.1.19		
nodeid=#	Back up files from node with this ID			
parallelism=#	Number of parallel transactions during restoration of data			
- -preserve-trailing-spaces	Allow preservation of tailing spaces (including padding) when CHAR is promoted to VARCHAR or BINARY is promoted to VARBINARY	5.1.23-ndb- 6.3.8		
print	Print metadata, data and log to stdout (equivalent to - -print_metaprint_dataprint_log)			
print_data	Print data to stdout			
print_log	Print to stdout			
print_metadata	Print metadata to stdout			
progress-frequency=#	Print status of restoration each given number of seconds			
promote-attributes	Allow attributes to be promoted when restoring data from backup	5.1.23-ndb- 6.3.8		
rebuild-indexes	Causes multi-threaded ordered index rebuilding of indexes found in the backup.	5.1.41-ndb- 6.3.31, 5.1.41-ndb- 7.0.11,		

Format	Description	Introduc- tion	Deprecated	Removed
		5.1.41-ndb- 7.1.2		
restore_epoch	Restore epoch info into the status table. Convenient on a MySQL Cluster replication slave for starting replication. The row in mysql.ndb_apply_status with id 0 will be updated/inserted.			
- -re- write-data- base=old_dbname,new_ dbname	Restores to a database with a different name than the original	5.1.51-ndb- 6.3.41, 5.1.51-ndb- 7.0.22, 5.1.51-ndb- 7.1.11		
skip-broken-objects	Causes missing blob tables in the backup file to be ignored.	5.1.51-ndb- 6.3.40, 5.1.51-ndb- 7.0.21, 5.1.51-ndb- 7.1.10		
skip-table-check	Skip table structure check during restoring of data	5.1.17		
skip-unknown-objects	Causes schema objects not recognized by ndb_restore to be ignored when restoring a backup made from a newer MySQL Cluster version to an older version.	5.1.41-ndb- 6.3.34, 5.1.41-ndb- 7.0.15, 5.1.41-ndb- 7.1.4		
tab=path	Creates a tab-separated .txt file for each table in the given path	5.1.18		
verbose=#	Control level of verbosity in output			

Typical options for this utility are shown here:

```
ndb_restore [-c connectstring] -n node_id [-m] -b backup_id \
-r --backup_path=/path/to/backup/files
```

The -c option is used to specify a connectstring which tells ndb_restore where to locate the cluster management server. (See Section 3.2.3, "The MySQL Cluster Connectstring", for information on connectstrings.) If this option is not used, then ndb_restore attempts to connect to a management server on localhost:1186. This utility acts as a cluster API node, and so requires a free connection "slot" to connect to the cluster management server. This means that there must be at least one [api] or [mysqld] section that can be used by it in the cluster config.ini file. It is a good idea to keep at least one empty [api] or [mysqld] section in config.ini that is not being used for a MySQL server or other application for this reason (see Section 3.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster").

You can verify that ndb_restore is connected to the cluster by using the SHOW command in the ndb_mgm management client. You can also accomplish this from a system shell, as shown here:

```
shell> ndb_mgm -e "SHOW"
```

-n is used to specify the node ID of the data node on which the backups were taken.

The first time you run the ndb_restore restoration program, you also need to restore the metadata. In other words, you must recreate the database tables—this can be done by running it with the -m option. Note that the cluster should have an empty database when starting to restore a backup. (In other words, you should start ndbd with --initial prior to performing the restore. You should also remove manually any Disk Data files present in the data node's DataDir.)

It is possible to restore data without restoring table metadata. Prior to MySQL 5.1.17, ndb_restore did not perform any checks of table schemas; if a table was altered between the time the backup was taken and when ndb_restore was run, ndb_restore would still attempt to restore the data to the altered table.

Beginning with MySQL 5.1.17, the default behavior is for ndb_restore to fail with an error if table data do not match the table schema; this can be overridden using the --skip-table-check or -s option. Prior to MySQL 5.1.21, if this option is used, then ndb_restore attempts to fit data into the existing table schema, but the result of restoring a backup to a table schema that does not match the original is unspecified.

Beginning with MySQL Cluster NDB 6.3.35, MySQL Cluster NDB 7.0.16, and MySQL Cluster NDB 7.1.5, some of the restric-

tions on mismatches in column definitions when restoring data using ndb_restore are relaxed; when one of these types of mismatches is encountered, ndb_restore does not stop with an error as it did previously, but rather accepts the data and inserts it into the target table while issuing a warning to the user that this is being done. This behavior occurs whether or not either of the options --skip-table-check or --promote-attributes is in use. These differences in column definitions are of the following types:

- Different COLUMN_FORMAT settings (FIXED, DYNAMIC, DEFAULT)
- Different STORAGE settings (MEMORY, DISK)
- · Different default values
- Different distribution key settings

Beginning with MySQL Cluster NDB 6.3.8, ndb_restore supports limited attribute promotion in much the same way that it is supported by MySQL replication; that is, data backed up from a column of a given type can generally be restored to a column using a "larger, similar" type. For example, data from a CHAR(20) column can be restored to a column declared as VARCHAR(20), VARCHAR(30), or CHAR(30); data from a MEDIUMINT column can be restored to a column of type INT or BIGINT. See Replication of Columns Having Different Data Types, for a table of type conversions currently supported by attribute promotion.

Attribute promotion by ndb_restore must be enabled explicitly, as follows:

- 1. Prepare the table to which the backup is to be restored. ndb_restore cannot be used to re-create the table with a different definition from the original; this means that you must either create the table manually, or alter the columns which you wish to promote using ALTER TABLE after restoring the table metadata but before restoring the data.
- 2. Invoke ndb_restore with the --promote-attributes option (short form -A) when restoring the table data. Attribute promotion does not occur if this option is not used; instead, the restore operation fails with an error.

--lossy-conversions, -L

Version Introduced	5.1.51-ndb-	5.1.51-ndb-7.1.11	
Command-Line Format	lossy-	lossy-conversions	
	-L		
	Permitted Values Type boolean Default FALSE		

This option is intended to complement the --promote-attributes option. Using --lossy-conversions allows lossy conversions of column values (type demotions or changes in sign) when restoring data from backup. With some exceptions, the rules governing demotion are the same as for MySQL replication; see Replication of Columns Having Different Data Types, for information about specific type conversions currently supported by attribute demotion.

ndb_restore reports any truncation of data that it performs during lossy conversions once per attribute and column.

This option was added in MySQL Cluster NDB 7.1.11.

The --preserve-trailing-spaces option is also available beginning with MySQL Cluster NDB 6.3.8. This option (short form -R) causes trailing spaces to be preserved when promoting a CHAR column to VARCHAR or a BINARY column to VARBIN-ARY. Otherwise, any trailing spaces are dropped from column values when they are inserted into the new columns.

Note

Although you can promote CHAR columns to VARCHAR and BINARY columns to VARBINARY, you cannot promote VARCHAR columns to CHAR or VARBINARY columns to BINARY.

The -b option is used to specify the ID or sequence number of the backup, and is the same number shown by the management client in the Backup <code>backup_id</code> completed message displayed upon completion of a backup. (See Section 5.3.2, "Using The MySQL Cluster Management Client to Create a Backup".)

Important

When restoring cluster backups, you must be sure to restore all data nodes from backups having the same backup ID.

Using files from different backups will at best result in restoring the cluster to an inconsistent state, and may fail altogether.

--epoch (short form: -e) adds (or restores) epoch information to the cluster replication status table. This is useful for starting replication on a MySQL Cluster replication slave. When this option is used, the row in the mysql.ndb_apply_status having 0 in the id column is updated if it already exists; such a row is inserted if it does not already exist. (See Section 6.9, "MySQL Cluster Backups With MySQL Cluster Replication".)

The path to the backup directory is required; this is supplied to ndb_restore using the --backup_path option, and must include the subdirectory corresponding to the ID backup of the backup to be restored. For example, if the data node's DataDir is / var/lib/mysql-cluster, then the backup directory is /var/lib/mysql-cluster/BACKUP, and the backup files for the backup with the ID 3 can be found in /var/lib/mysql-cluster/BACKUP/BACKUP-3. The path may be absolute or relative to the directory in which the ndb_restore executable is located, and may be optionally prefixed with backup_path=.

Note

Previous to MySQL 5.1.17 and MySQL Cluster NDB 6.1.5, the path to the backup directory was specified as shown here, with backup_path= being optional:

[backup_path=]/path/to/backup/files

Beginning with MySQL 5.1.17 and MySQL Cluster NDB 6.1.5, this syntax changed to --backup_path=/path/to/backup/files, to conform more closely with options used by other MySQL programs; --backupid is required, and there is no short form for this option.

It is possible to restore a backup to a database with a different configuration than it was created from. For example, suppose that a backup with backup ID 12, created in a cluster with two database nodes having the node IDs 2 and 3, is to be restored to a cluster with four nodes. Then ndb_restore must be run twice—once for each database node in the cluster where the backup was taken. However, ndb_restore cannot always restore backups made from a cluster running one version of MySQL to a cluster running a different MySQL version. See Section 2.7, "Upgrading and Downgrading MySQL Cluster", for more information.

Important

It is not possible to restore a backup made from a newer version of MySQL Cluster using an older version of ndb_restore. You can restore a backup made from a newer version of MySQL to an older cluster, but you must use a copy of ndb_restore from the newer MySQL Cluster version to do so.

For example, to restore a cluster backup taken from a cluster running MySQL Cluster NDB 7.1.8 to a cluster running MySQL Cluster NDB 7.0.16, you must use the ndb_restore that comes with the MySQL Cluster NDB 7.1.8 distribution.

For more rapid restoration, the data may be restored in parallel, provided that there is a sufficient number of cluster connections available. That is, when restoring to multiple nodes in parallel, you must have an <code>[api]</code> or <code>[mysqld]</code> section in the cluster <code>config.ini</code> file available for each concurrent <code>ndb_restore</code> process. However, the data files must always be applied before the logs.

Formerly, when using ndb_restore to restore a backup made from a MySQL 5.0 cluster to a 5.1 cluster, VARCHAR columns were not resized and were recreated using the 5.0 fixed format. Beginning with MySQL 5.1.19, ndb_restore recreates such VARCHAR columns using MySQL Cluster 5.1's variable-width format. Also beginning with MySQL 5.1.19, this behavior can be overridden using the --no-upgrade option (short form: -u) when running ndb_restore.

The --print_data option causes ndb_restore to direct its output to stdout.

TEXT and BLOB column values are always truncated to the first 256 bytes in the output; this cannot currrently be overridden when using --print_data.

Beginning with MySQL 5.1.18, several additional options are available for use with the --print_data option in generating data dumps, either to stdout, or to a file. These are similar to some of the options used with mysqldump, and are shown in the following list:

--tab, -T

Version Introduced	5.1.18
Command-Line Format	tab=path
	-T

This option causes --print_data to create dump files, one per table, each named tbl name.txt. It requires as its argu-

ment the path to the directory where the files should be saved; use . for the current directory.

• --fields-enclosed-by=string

Version Introduced	5.1.18	5.1.18	
Command-Line Format	fields	fields-enclosed-by=char	
	Permitted Values		
	Type string		
	Default		

Each column values are enclosed by the string passed to this option (regardless of data type; see next item).

• --fields-optionally-enclosed-by=string

Version Introduced	5.1.18		
Command-Line Format	fields	fields-optionally-enclosed-by	
	Permitted Values		
	Type	Type string	
	Default		

The string passed to this option is used to enclose column values containing character data (such as CHAR, VARCHAR, BINARY, TEXT, or ENUM).

• --fields-terminated-by=string

Version Introduced	5.1.18		
Command-Line Format	fields-terminated-by=char		
	Permitted Values		
	Type	Type string	
	Default \t (tab)		

The string passed to this option is used to separate column values. The default value is a tab character (\t).

• --hex

Version Introduced	5.1.18
Command-Line Format	hex

If this option is used, all binary values are output in hexadecimal format.

• --fields-terminated-by=string

Version Introduced	5.1.18		
Command-Line Format	fields	fields-terminated-by=char	
	Permitted Values		
	Type string		
	Default \t (tab)		

This option specifies the string used to end each line of output. The default is a linefeed character (\n).

--append

Version Introduced	5.1.18
Command-Line Format	append

When used with the --tab and --print_data options, this causes the data to be appended to any existing files having the same names.

Note

If a table has no explicit primary key, then the output generated when using the --print_data option includes the table's hidden primary key.

Beginning with MySQL 5.1.18, it is possible to restore selected databases, or to restore selected tables from a given database using the syntax shown here:

```
ndb_restore other_options db_name,[db_name[,...] | tbl_name[,tbl_name][,...]]
```

In other words, you can specify either of the following to be restored:

- · All tables from one or more databases
- One or more tables from a single database

--include-databases=db_name[,db_name][,...]

Version Introduced	5.1.31-ndb-	5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Command-Line Format	include-databases=db-list		
	Permitted Values Type string		
	Default		

--include-tables=db_name.tbl_name[,db_name.tbl_name][,...]

Version Introduced	5.1.31-ndb-	5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3	
Command-Line Format	include-tables=table-list		
	Permitted Values		
	Type string		
	Default		

Beginning with MySQL Cluster NDB 6.3.22 and MySQL Cluster NDB 6.4.3, you can (and should) use instead the --include-databases option or the --include-tables option for restoring only specific databases or tables, respectively. --include-databases takes a comma-delimited list of databases to be restored. --include-tables takes a comma-delimited list of tables (in database.table format) to be restored.

When --include-databases or --include-tables is used, only those databases or tables named by the option are restored; all other databases and tables are excluded by ndb_restore, and are not restored.

The following table shows several invocations of ndb_restore using --include-* options (other options possibly required have been omitted for clarity), and the effects these have on restoring from a MySQL Cluster backup:

Option Used	Result
include-databases=db1	Only tables in database db1 are restored; all tables in all other databases are ignored
include-databases=db1,db2(orinclude-databases=db1include-databases=db2)	Only tables in databases db1 and db2 are restored; all tables in all other databases are ignored
include-tables=db1.t1	Only table t1 in database db1 is restored; no other tables in db1 or in any other database are restored
include-tables=db1.t2,db2.t1(or- -include-tables=db1.t2- -include-tables=db2.t1)	Only the table t2 in database db1 and the table t1 in database db2 are restored; no other tables in db1, db2, or any other database are restored

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use these two options together. For example, the following causes all tables in databases db1 and db2, together with the tables t1 and t2 in database db3, to be restored (and no other databases or tables):

```
shell> ndb_restore [...] --include-databases=db1,db2 --include-tables=db3.t1,db3.t2
```

(Again we have omitted other, possibly required, options in the example just shown.)

Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, multiple <code>--include-*</code> options were not handled correctly, and the result of the options shown in the previous example was that only the tables <code>db3.t1</code> and <code>db3.t2</code> were actually restored. (Bug #48907)

--exclude-databases=db_name[,db_name][,...]

Version Introduced	5.1.31-ndb-	5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3		
Command-Line Format	exclude-databases=db-list			
	Permitted Values			
	Type	Type string		
	Default			

--exclude-tables=db_name.tbl_name[,db_name.tbl_name][,...]

Version Introduced	5.1.31-ndb-	5.1.31-ndb-6.3.22, 5.1.32-ndb-6.4.3		
Command-Line Format	exclude-tables=table-list			
	Permitted	Permitted Values		
	Type string			
	Default			

Beginning with MySQL Cluster NDB 6.3.22 and MySQL Cluster NDB 6.4.3, it is possible to prevent one or more databases or tables from being restored using the ndb_restore options --exclude-databases and --exclude-tables. --exclude-databases takes a comma-delimited list of one or more databases which should not be restored. --exclude-tables takes a comma-delimited list of one or more tables (using database.table format) which should not be restored.

When --exclude-databases or --exclude-tables is used, only those databases or tables named by the option are excluded; all other databases and tables are restored by ndb_restore.

This table shows several invocations of ndb_restore usng --exclude-* options (other options possibly required have been omitted for clarity), and the effects these options have on restoring from a MySQL Cluster backup:

Option Used	Result
exclude-databases=db1	All tables in all databases except db1 are restored; no tables in db1 are restored
exclude-databases=db1,db2(or- -exclude-databases=db1- -exclude-databases=db2)	All tables in all databases except db1 and db2 are restored; no tables in db1 or db2 are restored
exclude-tables=db1.t1	All tables except t1 in database db1 are restored; all other tables in db1 are restored; all tables in all other databases are restored
exclude-tables=db1.t2,db2.t1(or- -exclude-tables=db1.t2- -exclude-tables=db2.t1)	All tables in database db1 except for t2 and all tables in database db2 except for table t1 are restored; no other tables in db1 or db2 are restored; all tables in all other databases are restored

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use these two options together. For example, the following causes all tables in all databases *except for* databases db1 and db2, along with the tables t1 and t2 in database db3, *not* to be restored:

```
shell> ndb_restore [...] --exclude-databases=db1,db2 --exclude-tables=db3.t1,db3.t2
```

(Again, we have omitted other possibly necessary options in the interest of clarity and brevity from the example just shown.)

Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, multiple --exclude-* options were not handled correctly, with the result that the options shown in the previous example caused ndb_restore to exclude only the tables db3.t1 and db3.t2. (Bug #48907)

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use --include-* and --exclude-* options together, subject to the following rules:

- The actions of all --include-* and --exclude-* options are cumulative.
- All --include-* and --exclude-* options are evaluated in the order passed to ndb_restore, from right to left.
- In the event of conflicting options, the first (rightmost) option takes precedence. In other words, the first option (going from right to left) that matches against a given database or table "wins".

For example, the following set of options causes ndb_restore to restore all tables from database db1 except db1.t1, while restoring no other tables from any other databases:

```
--include-databases=db1 --exclude-tables=db1.t1
```

However, reversing the order of the options just given simply causes all tables from database db1 to be restored (including db1.t1, but no tables from any other database), because the --include-databases option, being farthest to the right, is the first match against database db1 and thus takes precedence over any other option that matches db1 or any tables in db1:

```
--exclude-tables=db1.t1 --include-databases=db1
```

Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, it was not possible to use --include-databases or --include-tables together with --exclude-databases or --exclude-tables, as these combinations were evaluated inconsistently. (Bug #48907)

--exclude-missing-columns

Version Introduced	5.1.35-ndb-6.3.26, 5.1.35-ndb-7.0.7
Command-Line Format	exclude-missing-columns

Beginning with MySQL Cluster NDB 6.3.26 and MySQL Cluster NDB 7.0.7, it is also possible to restore only selected table columns using the <code>--exclude-missing-columns</code> option. When this option is used, <code>ndb_restore</code> ignores any columns missing from tables being restored as compared to the versions of those tables found in the backup. This option applies to all tables being restored. If you wish to apply this option only to selected tables or databases, you can use it in combination with one or more of the options described in the previous paragraph to do so, then restore data to the remaining tables using a complementary set of these options.

--disable-indexes

Version Introduced	5.1.41-ndb-6.3.31, 5.1.41-ndb-7.0.11, 5.1.41-ndb-7.1.2
Command-Line Format	disable-indexes

Beginning with MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL CLuster NDB 7.1.2, you can use this option with ndb_restore to disable restoration of indexes during restoration of the data from a native NDB backup. Afterwards, you can restore indexes for all tables at once with multi-threaded building of indexes using --rebuild-indexes, which should be faster than rebuilding indexes concurrently for very large tables.

--rebuild-indexes

Version Introduced	5.1.41-ndb-6.3.31, 5.1.41-ndb-7.0.11, 5.1.41-ndb-7.1.2
Command-Line Format	rebuild-indexes

Beginning with MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL CLuster NDB 7.1.2, you can use this option with ndb_restore to cause multi-threaded rebuilding of the ordered indexes while restoring a native NDB backup.

--skip-broken-objects

Version Introduced	5.1.51-ndb-6.3.40, 5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10
Command-Line Format	skip-broken-objects

This option causes ndb_restore to ignore corrupt tables while reading a native NDB backup, and to continue restoring any remaining tables (that are not also corrupted). Currently, the --skip-broken-objects option works only in the case of missing blob parts tables.

This option was added in MySQL Cluster NDB 6.3.40, MySQL Cluster NDB 7.0.21, and MySQL CLuster NDB 7.1.10.

--skip-unknown-objects

Version Introduced	5.1.41-ndb-6.3.34, 5.1.41-ndb-7.0.15, 5.1.41-ndb-7.1.4
Command-Line Format	skip-unknown-objects

This option causes ndb_restore to ignore any schema objects it does not recgnize while reading a native NDB backup. This can be used for restoring a backup made from a cluster running MySQL Cluster NDB 7.0 to a cluster running MySQL Cluster NDB 6.3

This option was added in MySQL Cluster NDB 6.3.34, MySQL Cluster NDB 7.0.15, and MySQL CLuster NDB 7.1.4.

--rewrite-database=old_dbname,new_dbname

Version Introduced	5.1.51-ndb-	5.1.51-ndb-6.3.41, 5.1.51-ndb-7.0.22, 5.1.51-ndb-7.1.11		
Command-Line Format	rewrite-database=old_dbname,new_dbname			
	Permitted Values			
	Type string			
	Default			

This option makes it possible to restore to a database having a different name from that used in the backup. For example, if a backup is made of a database named products, you can restore the data it contains to a database named inventory, use this option as shown here (omitting any other options that might be required):

```
shell> ndb_restore --rewrite-database=product,inventory
```

The option can be employed multiple times in a single invocation of ndb_restore. Thus it is possible to restore simultaneously from a database named db1 to a database named db2 and from a database named db3 to one named db4 using - -rewrite-database=db1, db2 --rewrite-database=db3, db4. Other ndb_restore options may be used between multiple occurrences of --rewrite-database.

In the event of conflicts between multiple --rewrite-database options, the last --rewrite-database option used, reading from left to right, is the one that takes effect. For example, if --rewrite-database=db1,db2 - -rewrite-database=db1,db3 is used, only --rewrite-database=db1,db3 is honored, and --rewrite-database=db1,db2 is ignored. It is also possible to restore from multiple databases to a single database, so that --rewrite-database=db1,db3 --rewrite-database=db2,db3 restores all tables and data from databases db1 and db2 into database db3.

Important

When restoring from multiple backup databases into a single target database using --rewrite-database, no check is made for collisions between table or other object names, and the order in which rows are restored is not guaranteed. This means that it is possible in such cases for rows to be overwritten and updates to be lost.

This option was added in MySQL Cluster NDB 6.3.41, MySQL Cluster NDB 7.0.22, and MySQL Cluster NDB 7.1.11.

Error reporting. ndb_restore reports both temporary and permanent errors. In the case of temporary errors, it may able to recover from them. Beginning with MySQL 5.1.12, it reports Restore successful, but encountered temporary error, please look at configuration in such cases.

Important

After using ndb_restore to initialize a MySQL Cluster for use in circular replication, binary logs on the SQL node acting as the replication slave are not automatically created, and you must cause them to be created manually. To cause the binary logs to be created, issue a SHOW TABLES statement on that SQL node before running START SLAVE. This is a known issue in MySQL Cluster.

4.18. ndb select all — Print Rows from an NDB Table

ndb_select_all prints all rows from an NDB table to stdout.

Usage

ndb_select_all -c connect_string tbl_name -d db_name [> file_name]

Additional Options

• --lock=lock_type, -l lock_type

Employs a lock when reading the table. Possible values for *lock_type* are:

- · 0: Read lock
- · 1: Read lock with hold
- 2: Exclusive read lock

There is no default value for this option.

• --order=index_name, -o index_name

Orders the output according to the index named <code>index_name</code>. Note that this is the name of an index, not of a column, and that the index must have been explicitly named when created.

--descending, -z

Sorts the output in descending order. This option can be used only in conjunction with the -o (--order) option.

• --header=FALSE

Excludes column headers from the output.

--useHexFormat -x

Causes all numeric values to be displayed in hexadecimal format. This does not affect the output of numerals contained in strings or datetime values.

--delimiter=character, -D character

Causes the character to be used as a column delimiter. Only table data columns are separated by this delimiter.

The default delimiter is the tab character.

• --disk

Adds a disk reference column to the output. The column is nonempty only for Disk Data tables having nonindexed columns.

--rowid

Adds a ROWID column providing information about the fragments in which rows are stored.

• --gci

Adds a column to the output showing the global checkpoint at which each row was last updated. See Chapter 1, *MySQL Cluster Overview*, and Section 5.5.2, "MySQL Cluster Log Events", for more information about checkpoints.

• --tupscan, -t

Scan the table in the order of the tuples.

• --nodata

Causes any table data to be omitted.

Sample Output

Output from a MySQL SELECT statement:

Output from the equivalent invocation of ndb_select_all:

```
shell> ./ndb_select_all -c localhost fish -d ctest1
id    name
3     [shark]
6     [puffer]
2     [tuna]
4     [manta ray]
5     [grouper]
1     [guppy]
6 rows returned
NDBT_ProgramExit: 0 - OK
```

Note that all string values are enclosed by square brackets ("[...]") in the output of ndb_select_all. For a further example, consider the table created and populated as shown here:

```
CREATE TABLE dogs (
   id INT(11) NOT NULL AUTO_INCREMENT,
   name VARCHAR(25) NOT NULL,
   breed VARCHAR(50) NOT NULL,
   primary KEY pk (id),
   KEY ix (name)
)

TABLESPACE ts STORAGE DISK
ENGINE=NDBCLUSTER;
INSERT INTO dogs VALUES
   ('', 'Lassie', 'collie'),
   ('', 'Scooby-Doo', 'Great Dane'),
   ('', 'Rin-Tin-Tin', 'Alsatian'),
   ('', 'Rosscoe', 'Mutt');
```

This demonstrates the use of several additional ndb_select_all options:

```
shell> ./ndb_select_all -d ctest1 dogs -o ix -z --gci --disk
GCI
834461
         id name
2 [Scooby-Doo]
                              breed    DISK_REF
[Great Dane] [ m_file_no: 0 m_page: 98 m_page_idx: 0 ]
834878
              [Rosscoe]
                               [Mutt]
                                              [ m_file_no: 0 m_page: 98 m_page_idx: 16 ]
[ m_file_no: 0 m_page: 34 m_page_idx: 0 ]
             [Rin-Tin-Tin]
                               [Alsatian]
834463
835657 1
             [Lassie]
                               [Collie]
                                               [ m_file_no: 0 m_page: 66 m_page_idx: 0 ]
4 rows returned
NDBT_ProgramExit: 0 - OK
```

Note

In earlier MySQL Cluster NDB 7.0 and 7.1 releases, ndb_select_all did not print any output for NULL values as it did in MySQL Cluster NDB 6.3 and earlier release series. This issue was fixed in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. (Bug #60045)

4.19. ndb_select_count — Print Row Counts for NDB Tables

ndb_select_count prints the number of rows in one or more NDB tables. With a single table, the result is equivalent to that obtained by using the MySQL statement SELECT COUNT(*) FROM tbl_name.

Usage

```
ndb_select_count [-c connect_string] -ddb_name tbl_name[, tbl_name2[, ...]]
```

Additional Options

None that are specific to this application. However, you can obtain row counts from multiple tables in the same database by listing the table names separated by spaces when invoking this command, as shown under **Sample Output**.

Sample Output

```
shell> ./ndb_select_count -c localhost -d ctest1 fish dogs
6 records in table fish
4 records in table dogs
NDBT_ProgramExit: 0 - OK
```

4.20. ndb_show_tables — Display List of NDB Tables

ndb_show_tables displays a list of all NDB database objects in the cluster. By default, this includes not only both user-created tables and NDB system tables, but NDB-specific indexes, internal triggers, and MySQL Cluster Disk Data objects as well.

The following table includes options that are specific to the MySQL Cluster program ndb_show_tables. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.7. ndb_show_tables Command Line Options

Format	Description	Introduc- tion	Deprec- ated	Removed
database=string	Specifies the database in which the table is found			
loops=#	Number of times to repeat output			
parsable	Return output suitable for MySQL LOAD DATA INFILE statement			
show-temp-status	Show table temporary flag			
type=#	Limit output to objects of this type			
unqualified	Do not qualify table names			

Usage

ndb_show_tables [-c connect_string]

--database, -d

Specifies the name of the database in which the tables are found.

--loops, -l

Specifies the number of times the utility should execute. This is 1 when this option is not specified, but if you do use the option, you must supply an integer argument for it.

• --parsable, -p

Using this option causes the output to be in a format suitable for use with LOAD DATA INFILE.

• --show-temp-status

If specified, this causes temporary tables to be displayed.

--type, -t

Can be used to restrict the output to one type of object, specified by an integer type code as shown here:

• 1: System table

- 2: User-created table
- 3: Unique hash index

Any other value causes all NDB database objects to be listed (the default).

--unqualified, -u

If specified, this causes unqualified object names to be displayed.

Note

Only user-created MySQL Cluster tables may be accessed from MySQL; system tables such as SYSTAB_0 are not visible to mysqld. However, you can examine the contents of system tables using NDB API applications such as ndb_select_all (see Section 4.18, "ndb_select_all — Print Rows from an NDB Table").

4.21. ndb size.pl — NDBCLUSTER Size Requirement Estimator

This is a Perl script that can be used to estimate the amount of space that would be required by a MySQL database if it were converted to use the NDBCLUSTER storage engine. Unlike the other utilities discussed in this section, it does not require access to a MySQL Cluster (in fact, there is no reason for it to do so). However, it does need to access the MySQL server on which the database to be tested resides.

Requirements

- A running MySQL server. The server instance does not have to provide support for MySQL Cluster.
- A working installation of Perl.
- The DBI module, which can be obtained from CPAN if it is not already part of your Perl installation. (Many Linux and other operating system distributions provide their own packages for this library.)
- Previous to MySQL 5.1.18, ndb_size.pl also required the HTML::Template module and an associated template file share/mysql/ndb_size.tmpl. Beginning with MySQL 5.1.18, ndb_size.tmpl is no longer needed (or included).
- A MySQL user account having the necessary privileges. If you do not wish to use an existing account, then creating one using
 GRANT USAGE ON db_name.*—where db_name is the name of the database to be examined—is sufficient for this purpose.

ndb_size.pl can also be found in the MySQL sources in storage/ndb/tools. If this file is not present in your MySQL installation, you can obtain it from the MySQL Forge project page.

The following table includes options that are specific to the MySQL Cluster program ndb_size.pl. Additional descriptions follow the table. For options common to all MySQL Cluster programs, see Section 4.23, "Options Common to MySQL Cluster Programs".

Table 4.8. ndb	_size.p	1 Command	Line Options
----------------	---------	-----------	--------------

Format	Description	Introduc- tion	Deprec- ated	Removed
database=dbname	The database or databases to examine; accepts a comma-delimited list; the default is ALL (use all databases found on the server)			
excludedbs=db-list	Skip any databases in a comma-separated list of databases			
excludetables=tbl-list	Skip any tables in a comma-separated list of tables			
format=string	Set output format (text or HTML)			
hostname[:port]	Specify host and optional port as host[:port]			
loadqueries=file	Loads all queries from the file specified; does not connect to a database			
password=string	Specify a MySQL user password			
real_table_name=table	Designates a table to handle unique index size calculations	5.1.22-ndb- 6.2.5		

Format	Description		Deprec- ated	Removed
savequeries=file	Saves all queries to the database into the file specified			
socket=file	Specify a socket to connect to	5.1.22-ndb- 6.2.5		
user=string	Specify a MySQL user name			

Usage

By default, this utility attempts to analyze all databases on the server. You can specify a single database using the --database option; the default behavior can be made explicit by using ALL for the name of the database. You can also exclude one or more databases by using the --excludedbs with a comma-separated list of the names of the databases to be skipped. Similarly, you can cause specific tables to be skipped by listing their names, separated by commas, following the optional --excludetables option. A host name (and possibly a port as well) can be specified using --hostname; the default is localhost: 3306. If necessary, you can also specify a socket; the default is /var/lib/mysql.sock. A MySQL user name and password can be specified the corresponding options shown. It also possible to control the format of the output using the --format option; this can take either of the values html or text, with text being the default. An example of the text output is shown here:

```
shell> ndb_size.pl --database=test --socket=/tmp/mysql.sock
ndb_size.pl report for database: 'test' (1 tables)
Connected to: DBI:mysql:host=localhost;mysql_socket=/tmp/mysql.sock
Including information for versions: 4.1,
test.t1
DataMemory for Columns (* means varsized DataMemory)
           Column Name
HIDDEN_NDB_PKEY
                                            Type
bigint
                                                      Varsized
                                                                              4.1
                                                                                          5.0
                                                                  PRI
                                       varchar(50)
                                                                               52
                                                                                           52
                                                                                                        4
                                           int(11)
                                                                                4
                                                                                            4
                         c1
Fixed Size Columns DM/Row
                                                                               64
                                                                                           64
   Varsize Columns DM/Row
DataMemory for Indexes:
                 Index Name
                                                                                     5.1
16
                    PRIMARY
                                              BTREE
                                                              16
                                                                          16
                                                                          16
                                                                                      16
       Total Index DM/Row
                                                              16
IndexMemory for Indexes:
                Index Name
PRIMARY
                                                 5.0
16
                                     4.1
                                                              5.1
                                      33
                                                               16
            Indexes IM/Row
                                      33
                                                  16
                                                               16
Summary (for THIS table):
                                                 5.0
                                                              5.1
                                      12
4
    Fixed Overhead DM/Row
                                                  12
            NULL Bytes/Row
            DataMemory/Row
                                      96
                                                  96
                                                               48
                                                                   (Includes overhead, bitmap and indexes)
  Varsize Overhead DM/Row
                                       0
                                                   0
                                       0
                                                    0
   Varsize NULL
                 Bytes/Row
                                                              16
       Avg Varside DM/Row
                                       0
                                                   0
                  No. Rows
        Rows/32kb DM Page
                                     340
                                                 340
                                                              680
Fixedsize DataMemory
                       (KB)
                                                   0
Rows/32kb Varsize DM Page
                                       Ω
                                                   Ω
                                                             2040
  Varsize DataMemory (KB)
          Rows/8kb IM Page
                                     248
                                                 512
                                                              512
          IndexMemory (KB)
Parameter Minimum Requirements
* indicates greater than default
                                       Default
                                                              4.1
                                                                                 5.0
                                                                                                    5.1
                 Parameter
       DataMemory (KB)
NoOfOrderedIndexes
                                         81920
128
                                                                0
                                                                                                      0
                                            128
                NoOfTables
    IndexMemory (KB)
NoOfUniqueHashIndexes
                                         18432
                                                                0
                                                                                   0
                                                                                                      0
                                                                0
                                                                                   0
                                                                                                      0
                                           1000
            NoOfAttributes
              NoOfTriggers
```

For debugging purposes, the Perl arrays containing the queries run by this script can be read from the file specified using can be saved to a file using --savequeries; a file containing such arrays to be read in during script execution can be specified using --loadqueries. Neither of these options has a default value.

To produce output in HTML format, use the --format option and redirect the output to a file, as shown in this example:

```
shell> ndb_size.pl --database=test --socket=/tmp/mysql.sock --format=html > ndb_size.html
```



MySQL Cluster analysis for world

This is an automated analysis of the DBI:mysql:database=world;host=192.168.0.176 database for migration into MySQL Cluster. No warranty is made to the accuracy of the information.

This information should be valid for MySQL 4.1 and 5.0. Since 5.1 is not a final release yet, the numbers should be used as a guide only.

Parameter Settings

NOTE the configuration parameters below do not take into account system tables and other requirements.

Parameter	4.1	5.0	5.1
DataMemory (kb)	544	544	544
IndexMemory (kb)	192	136	136
MaxNoOfTables	3	3	3
MaxNoOfAttributes	24	24	24
MaxNoOfOrderedIndexes	3	3	3
MaxNoOfUniqueHashIndexes	3	3	3
MaxNoOfTriggers	12	12	12

Memory usage because of parameters

Usage is in kilobytes. Actual usage will vary as you should set the parameters larger than those listed in the table above.

Parameter	4.1	5.0	5.1
Attributes	5	5	5
Tables	60	60	60
Ordered Indexes	30	30	30
UniqueHashIndexes	45	45	45

Table List

- City
- Country
- CountryLanguage

City

Column	Туре	Size	Key	4.1 NDB Size	5.0 NDB Size	5.1 NDB Size
ID	int	11	PRI	4	4	4
District	char	20		20	20	20
Name	char	35		36	36	36
Population	int	11		4	4	4
Country Code	char	3		4	4	4

Indexes

We assume that indexes are ORDERED (not created USING HASH). If order is not required, 10 bytes of data memory can be saved per row if the index is created USING HASH

Index	Туре	Columns	4.1 IdxMem	5.0 IdxMem	5.1 IdxMem	4.1 DatMem	5.0 DatMem	5.1 DatMem
PRIMAR	Y BTREE	ID	29	25	25	10	10	10

DataMemory Usage

	4.1	5.0	5.1
Row Overhead	16	16	16
Column DataMemory/Row	68	68	68
Index DataMemory/Row	10	10	10
Total DataMemory/Row	94	94	94
Rows per 32kb page	347	347	347
Current number of rows	4079	4079	4079
Total DataMemory (kb)	384	384	384

IndexMemory Usage

	4.1	5.0	5.1
IndexMemory/Row	29	25	25
Rows per 8kb page	282	327	327
Current number of rows	4079	4079	4079
Total IndexMemory (kb)	120	104	104

The output from this script includes the following information:

- Minimum values for the DataMemory, IndexMemory, MaxNoOfTables, MaxNoOfAttributes, MaxNoOfOrderedIndexes, MaxNoOfUniqueHashIndexes, and MaxNoOfTriggers configuration parameters required to accommodate the tables analyzed.
- · Memory requirements for all of the tables, attributes, ordered indexes, and unique hash indexes defined in the database.
- The IndexMemory and DataMemory required per table and table row.

Note

Prior to MySQL 5.1.23, MySQL Cluster NDB 6.2.5, and MySQL Cluster NDB 6.3.7, ndb_size.pl was invoked as shown here:

perl ndb_size.pl db_name hostname username password > file_name.html

For more information about this change, see Bug #28683 and Bug #28253.

4.22. ndb_waiter — Wait for MySQL Cluster to Reach a Given Status

ndb_waiter repeatedly (each 100 milliseconds) prints out the status of all cluster data nodes until either the cluster reaches a given status or the --timeout limit is exceeded, then exits. By default, it waits for the cluster to achieve STARTED status, in which all nodes have started and connected to the cluster. This can be overridden using the --no-contact and --not-started options (see Additional Options).

The node states reported by this utility are as follows:

- NO_CONTACT: The node cannot be contacted.
- UNKNOWN: The node can be contacted, but its status is not yet known. Usually, this means that the node has received a START
 or RESTART command from the management server, but has not yet acted on it.
- NOT_STARTED: The node has stopped, but remains in contact with the cluster. This is seen when restarting the node using the
 management client's RESTART command.
- STARTING: The node's ndbd process has started, but the node has not yet joined the cluster.
- STARTED: The node is operational, and has joined the cluster.
- SHUTTING_DOWN: The node is shutting down.
- SINGLE USER MODE: This is shown for all cluster data nodes when the cluster is in single user mode.

Usage

ndb_waiter [-c connect_string]

Additional Options

• --no-contact, -n

Instead of waiting for the STARTED state, ndb_waiter continues running until the cluster reaches NO_CONTACT status before exiting.

--not-started

Instead of waiting for the STARTED state, ndb_waiter continues running until the cluster reaches NOT_STARTED status before exiting.

• --timeout=seconds, -t seconds

Time to wait. The program exits if the desired state is not achieved within this number of seconds. The default is 120 seconds (1200 reporting cycles).

• --single-user

The program waits for the cluster to enter single user mode.

• --nowait-nodes=list

When this option is used, ndb_waiter does not wait for the nodes whose IDs are listed. The list is comma-delimited; ranges can be indicated by dashes, as shown here:

```
shell> ndb_waiter --nowait-nodes=1,3,7-9
```

Important

Do not use this option together with the --wait-nodes option.

This option was added in MySQL Cluster NDB 6.2.1.

• --wait-nodes=list,-w list

When this option is used, ndb_waiter waits only for the nodes whose IDs are listed. The list is comma-delimited; ranges can be indicated by dashes, as shown here:

```
shell> ndb_waiter --wait-nodes=2,4-6,10
```

Important

Do not use this option together with the --nowait-nodes option.

This option was added in MySQL Cluster NDB 6.3.34, 7.0.15, and 7.1.4.

Sample Output. Shown here is the output from ndb_waiter when run against a 4-node cluster in which two nodes have been shut down and then started again manually. Duplicate reports (indicated by "...") are omitted.

```
shell> ./ndb_waiter -c localhost
Connecting to mgmsrv at (localhost)
State node 1 STARTED
State node 2 NO_CONTACT
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 1 STARTED
State node 2 UNKNOWN
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 UNKNOWN
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 STARTING
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTED State node 3 STARTED
State node 4 STARTING
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 1 STARTED
State node 2 STARTED
State node 3 STARTED
State node 4 STARTED
Waiting for cluster enter state STARTED
NDBT_ProgramExit: 0 - OK
```

Note

If no connectstring is specified, then ndb_waiter tries to connect to a management on localhost, and reports Connecting to mgmsrv at (null).

4.23. Options Common to MySQL Cluster Programs

All MySQL Cluster programs (except for mysqld) take the options described in this section. Users of earlier MySQL Cluster versions should note that some of these options have been changed to make them consistent with one another as well as with mysqld. You can use the --help option with any MySQL Cluster program to view a list of the options which it supports.

The options in the following table are common to all MySQL Cluster executables.

Table 4.9. Common MySQL Cluster Command Line Options

Format	Description	Introduc- tion	Deprec- ated	Removed
character-sets-dir=path	Directory where character sets are			
- - ndb-connectstring=name	Set connect string for connecting to ndb_mgmd. Syntax: [nodeid= <id>;][host=]<hostname>[:<port>]. Overrides specifying entries in NDB_CONNECTSTRING and my.cnf</port></hostname></id>			
core-file	Write core on errors (defaults to TRUE in debug builds)			
debug=options	Enable output from debug calls. Can be used only for versions compiled with debugging enabled			
help	Display help message and exit			
ndb-mgmd-host=name	Set host and port for connecting to ndb_mgmd. Syntax: <hostname>[:<port>]. Overrides specifying entries in NDB_CONNECTSTRING and my.cnf</port></hostname>			
ndb-nodeid=#	Set node id for this node			
- ndb-optim- ized-node-selection	Select nodes for transactions in a more optimal way			
ndb-shm	Allow optimizing using shared memory connections when available (was EXPERIMENTAL; REMOVED in later versions)			5.1.47-ndb- 7.1.5
-V	Output version information and exit			

For options specific to individual MySQL Cluster programs, see Chapter 4, MySQL Cluster Programs.

See Section 3.4.2, "mysqld Command Options for MySQL Cluster", for mysqld options relating to MySQL Cluster.

• --help --usage, -?

Command-Line Format	help
	usage
	-?

Prints a short list with descriptions of the available command options.

• --character-sets-dir=name

Command-Line Format	character-sets-dir=path		
	Permitted	Values	
	Type	file name	
	Default		

Tells the program where to find character set information.

• --connect-string=connect_string,-c connect_string

Command-Line Format	ndb-cd	ndb-connectstring=name		
	connect-string=name			
	-c			
	Permitted Values Type string Default localhost:1186			

connect_string sets the connectstring to the management server as a command option.

shell> ndbd --connect-string="nodeid=2;host=ndb_mgmd.mysql.com:1186"

For more information, see Section 3.2.3, "The MySQL Cluster Connectstring".

• --core-file

Command-Line Format	core-file		
	Permitted Values		
	Type	boolean	
	Default	FALSE	

Write a core file if the program dies. The name and location of the core file are system-dependent. (For MySQL Cluster programs nodes running on Linux, the default location is the program's working directory—for a data node, this is the node's <code>DataDir.</code>) For some systems, there may be restrictions or limitations; for example, it might be necessary to execute <code>ulimit-c unlimited</code> before starting the server. Consult your system documentation for detailed information.

If MySQL Cluster was built using the --debug option for configure, then --core-file is enabled by default. For regular builds, --core-file is disabled by default.

• --debug[=options]

Command-Line Format	debug=options		
	Permitted Values		
	Type string		
	Default d:t:0,/tmp/ndb_restore.trace		

This option can be used only for versions compiled with debugging enabled. It is used to enable output from debug calls in the same manner as for the mysqld process.

--ndb-mgmd-host=host[:port]

Can be used to set the host and port number of the management server to connect to.

• --ndb-nodeid=#

Command-Line Format	ndb-nodeid=#		
	Permitted	Values	
	Type	numeric	
	Default	0	

Sets this node's MySQL Cluster node ID. The range of permitted values depends on the node's type (data, management, or API) and the MySQL Cluster software version. See Section 1.6.2, "Limits and Differences of MySQL Cluster from Standard MySQL Limits", for more information.

• --ndb-optimized-node-selection

Command-Line Format	ndb-optimized-node-selection		
	Permitted Values		
	Type	boolean	
	Default	TRUE	

Optimize selection of nodes for transactions. Enabled by default.

• --version, -V

Command-Line Format	-V
	version

Prints the MySQL Cluster version number of the executable. The version number is relevant because not all versions can be used together, and the MySQL Cluster startup process verifies that the versions of the binaries being used can co-exist in the same cluster. This is also important when performing an online (rolling) software upgrade or downgrade of MySQL Cluster.

See Section 5.4, "Performing a Rolling Restart of a MySQL Cluster"), for more information.

Chapter 5. Management of MySQL Cluster

Managing a MySQL Cluster involves a number of tasks, the first of which is to configure and start MySQL Cluster. This is covered in Chapter 3, MySQL Cluster Configuration, and Chapter 4, MySQL Cluster Programs.

The next few sections cover the management of a running MySQL Cluster.

For information about security issues relating to management and deployment of a MySQL Cluster, see Section 5.10, "MySQL Cluster Security Issues".

There are essentially two methods of actively managing a running MySQL Cluster. The first of these is through the use of commands entered into the management client whereby cluster status can be checked, log levels changed, backups started and stopped, and nodes stopped and started. The second method involves studying the contents of the cluster log ndb_node_id_cluster.log; this is usually found in the management server's DataDir directory, but this location can be overridden using the LogDestination option. (Recall that node_id represents the unique identifier of the node whose activity is being logged.) The cluster log contains event reports generated by ndbd. It is also possible to send cluster log entries to a Unix system log.

Some aspects of the cluster's operation can be also be monitored from an SQL node using the SHOW ENGINE NDB STATUS statement.

In MySQL Cluster NDB 7.1.1 and later, detailed information about cluster operations is available in real time through an SQL interface using the ndbinfo database. For more information, see Section 5.9, "The ndbinfo MySQL Cluster Information Database".

MySQL Enterprise Monitor can also be used to monitor MySQL Servers that are part of a MySQL Cluster deployment. MySQL Enterprise Monitor 2.3, added a MySQL Cluster advisor, including a set of graphs providing information on MySQL Cluster resources, and defining rules for alerts on key information from data nodes such as DataMemory usage. This information is made available to MySQL Enterprise Monitor 2.3 or later by any MySQL Server which is connected to the MySQL Cluster, using ndbinfo. The advisor could be run against a single MySQL Server in the Cluster, or against a pair in order to provide a higher level of availability for the monitoring service. For more information, see the MySQL Enterprise Monitor 2.3 Manual.

MySQL Cluster Manager provides an advanced command-line interface that simplifies many otherwise complex MySQL Cluster management tasks, such as starting, stoppping, or restarting a MySQL Cluster with a large number of nodes. The MySQL Cluster Manager client also supports commands for getting and setting the values of most node configuration parameters as well as mysqld server options and variables relating to MySQL Cluster. MySQL Cluster Manager 1.1 provides support for adding data nodes online. See the MySQL Cluster Manager 1.1 User Manual, for more information.

5.1. Summary of MySQL Cluster Start Phases

This section provides a simplified outline of the steps involved when MySQL Cluster data nodes are started. More complete information can be found in MySQL Cluster Start Phases, in the NDB Internals Guide.

These phases are the same as those reported in the output from the node_id_STATUS command in the management client (see Section 5.2, "Commands in the MySQL Cluster Management Client"). In MySQL Cluster NDB 7.1.1 and later, these start phases are also reported in the start_phase column of the ndbinfo.nodes table.

Start types. There are several different startup types and modes, as shown in the following list:

• **Initial start.** The cluster starts with a clean file system on all data nodes. This occurs either when the cluster started for the very first time, or when all data nodes are restarted using the --initial option.



Disk Data files are not removed when restarting a node using --initial.

- System restart. The cluster starts and reads data stored in the data nodes. This occurs when the cluster has been shut down
 after having been in use, when it is desired for the cluster to resume operations from the point where it left off.
- Node restart. This is the online restart of a cluster node while the cluster itself is running.
- Initial node restart. This is the same as a node restart, except that the node is reinitialized and started with a clean file system.

Setup and initialization (phase -1). Prior to startup, each data node (ndbd process) must be initialized. Initialization consists of the following steps:

- 1. Obtain a node ID
- 2. Fetch configuration data
- 3. Allocate ports to be used for inter-node communications
- 4. Allocate memory according to settings obtained from the configuration file

When a data node or SQL node first connects to the management node, it reserves a cluster node ID. To make sure that no other node allocates the same node ID, this ID is retained until the node has managed to connect to the cluster and at least one ndbd reports that this node is connected. This retention of the node ID is guarded by the connection between the node in question and ndb_mgmd.

Normally, in the event of a problem with the node, the node disconnects from the management server, the socket used for the connection is closed, and the reserved node ID is freed. However, if a node is disconnected abruptly—for example, due to a hardware failure in one of the cluster hosts, or because of network issues—the normal closing of the socket by the operating system may not take place. In this case, the node ID continues to be reserved and not released until a TCP timeout occurs 10 or so minutes later.

To take care of this problem, you can use PURGE STALE SESSIONS. Running this statement forces all reserved node IDs to be checked; any that are not being used by nodes actually connected to the cluster are then freed.

Beginning with MySQL 5.1.11, timeout handling of node ID assignments is implemented. This performs the ID usage checks automatically after approximately 20 seconds, so that PURGE STALE SESSIONS should no longer be necessary in a normal Cluster start.

After each data node has been initialized, the cluster startup process can proceed. The stages which the cluster goes through during this process are listed here:

- Phase 0. The NDBFS and NDBCNTR blocks start (see NDB Kernel Blocks). Data node file systems are cleared on those data nodes that were started with --initial option.
- Phase 1. In this stage, all remaining NDB kernel blocks are started. MySQL Cluster connections are set up, inter-block communications are established, and heartbeats are started. In the case of a node restart, API node connections are also checked.

Note

When one or more nodes hang in Phase 1 while the remaining node or nodes hang in Phase 2, this often indicates network problems. One possible cause of such issues is one or more cluster hosts having multiple network interfaces. Another common source of problems causing this condition is the blocking of TCP/IP ports needed for communications between cluster nodes. In the latter case, this is often due to a misconfigured firewall.

- Phase 2. The NDBCNTR kernel block checks the states of all existing nodes. The master node is chosen, and the cluster schema file is initialized.
- Phase 3. The DBLQH and DBTC kernel blocks set up communications between them. The startup type is determined; if this is a restart, the DBDIH block obtains permission to perform the restart.
- Phase 4. For an initial start or initial node restart, the redo log files are created. The number of these files is equal to NoOf-FragmentLogFiles.

For a system restart:

- Read schema or schemas.
- Read data from the local checkpoint.
- Apply all redo information until the latest restorable global checkpoint has been reached.

For a node restart, find the tail of the redo log.

- Phase 5. Most of the database-related portion of a data node start is performed during this phase. For an initial start or system restart, a local checkpoint is executed, followed by a global checkpoint. Periodic checks of memory usage begin during this phase, and any required node takeovers are performed.
- Phase 6. In this phase, node groups are defined and set up.
- Phase 7. The arbitrator node is selected and begins to function. The next backup ID is set, as is the backup disk write speed. Nodes reaching this start phase are marked as Started. It is now possible for API nodes (including SQL nodes) to connect to the cluster.

- Phase 8. If this is a system restart, all indexes are rebuilt (by DBDIH).
- Phase 9. The node internal startup variables are reset.
- Phase 100 (OBSOLETE). Formerly, it was at this point during a node restart or initial node restart that API nodes could connect to the node and begin to receive events. Currently, this phase is empty.
- **Phase 101.** At this point in a node restart or initial node restart, event delivery is handed over to the node joining the cluster. The newly-joined node takes over responsibility for delivering its primary data to subscribers. This phase is also referred to as **SUMA** handover phase.

After this process is completed for an initial start or system restart, transaction handling is enabled. For a node restart or initial node restart, completion of the startup process means that the node may now act as a transaction coordinator.

5.2. Commands in the MySQL Cluster Management Client

In addition to the central configuration file, a cluster may also be controlled through a command-line interface available through the management client ndb_mgm. This is the primary administrative interface to a running cluster.

Commands for the event logs are given in Section 5.5, "Event Reports Generated in MySQL Cluster"; commands for creating backups and restoring from them are provided in Section 5.3, "Online Backup of MySQL Cluster".

The management client has the following basic commands. In the listing that follows, node_id denotes either a database node ID or the keyword ALL, which indicates that the command should be applied to all of the cluster's data nodes.

HELP

Displays information on all available commands.

SHOW

Displays information on the cluster's status. Possible node status values include UNKNOWN, NO_CONTACT, NOT_STARTED, STARTING, STARTED, SHUTTING_DOWN, and RESTARTING.

Beginning with MySQL Cluster NDB 6.2.8 and MySQL Cluster NDB 6.3.6, the output from this command indicates when the cluster is in single user mode (status SINGLE USER MODE).

Prior to MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.5, in a cluster having multiple management nodes, this command displayed information only for data nodes that were actually connected to the current management server; in addition, management servers could not find each other until all nodes had been started. Beginning with these versions, such issues are fixed (see Bug #12352191), and management nodes can be additionally be reported with status RESUME or CONNECTED.

node_id START

Brings online the data node identified by node_id (or all data nodes).

ALL START works on all data nodes only, and does not affect management nodes.

Important

To use this command to bring a data node online, the data node must have been started using ndbd --nostart or ndbd -n.

• node_id STOP [-a] [-f]

Stops the data or management node identified by node_id. Note that ALL STOP works to stop all data nodes only, and does not affect management nodes.

A node affected by this command disconnects from the cluster, and its associated ndbd or ndb_mgmd process terminates.

The -a option causes the node to be stopped immediately, without waiting for the completion of any pending transactions.

Normally, STOP fails if the result would cause an incomplete cluster. The -f option, added in MySQL Cluster NDB 7.0.19 and MySQL Cluster NDB 7.1.8, forces the node to shut down without checking for this. If this option is used and the result is an incomplete cluster, the cluster immediately shuts down.

Warning

Use of the -a option also disables the safety check otherwise performed when STOP is invoked to insure that stopping the node does not cause an incomplete cluster. In other words, you should exercise extreme care when using the -a option with the STOP command, due to the fact that this option makes it possible for the cluster to undergo a forced shutdown because it no longer has a complete copy of all data stored in NDB.

• node_id RESTART [-n] [-i] [-a] [-f]

Restarts the data node identified by node_id (or all data nodes).

Using the -i option with RESTART causes the data node to perform an initial restart; that is, the node's file system is deleted and recreated. The effect is the same as that obtained from stopping the data node process and then starting it again using ndbd --initial from the system shell. Note that backup files and Disk Data files are not removed when this option is used.

Using the -n option causes the data node process to be restarted, but the data node is not actually brought online until the appropriate START command is issued. The effect of this option is the same as that obtained from stopping the data node and then starting it again using ndbd --nostart or ndbd -n from the system shell.

Using the -a causes all current transactions relying on this node to be aborted. No GCP check is done when the node rejoins the cluster.

Normally, RESTART fails if taking the node offline would result in an incomplete cluster. The -f option, added in MySQL Cluster NDB 7.0.19 and MySQL Cluster NDB 7.1.8, forces the node to restart without checking for this. If this option is used and the result is an incomplete cluster, the entire cluster is restarted.

node_id STATUS

Displays status information for the data node identified by node_id (or for all data nodes).

Beginning with MySQL Cluster NDB 6.2.8 and MySQL Cluster NDB 6.3.6, the output from this command indicates when the cluster is in single user mode.

node_id REPORT report-type

Displays a report of type report-type for the data node identified by node_id, or for all data nodes using ALL.

Currently, there are two accepted values for report-type:

- BackupStatus provides a status report on a cluster backup in progress
- MemoryUsage displays how much data memory and index memory is being used by each data node as shown in this example:

```
ndb_mgm> ALL REPORT MEMORY
Node 1: Data usage is 5%(177 32K pages of total 3200)
Node 1: Index usage is 0%(108 8K pages of total 12832)
Node 2: Data usage is 5%(177 32K pages of total 3200)
Node 2: Index usage is 0%(108 8K pages of total 12832)
```

In MySQL Cluster NDB 7.1.1 and later, this information is also available from the ndbinfo.memoryusage table.

report-type is case-insensitive and "fuzzy"; for MemoryUsage, you can use MEMORY (as shown in the prior example), memory, or even simply MEM (or mem). You can abbreviate BackupStatus in a similar fashion.

The REPORT command was introduced in MySQL Cluster NDB 6.2.3 and MySQL Cluster NDB 6.3.0.

ENTER SINGLE USER MODE node_id

Enters single user mode, whereby only the MySQL server identified by the node ID node_id is permitted to access the database.

Currently, it is not possible for data nodes to join a MySQL Cluster while it is running in single user mode. (Bug #20395)

• EXIT SINGLE USER MODE

Exits single user mode, enabling all SQL nodes (that is, all running mysqld processes) to access the database.

Note

It is possible to use EXIT SINGLE USER MODE even when not in single user mode, although the command has no effect in this case.

• OUIT, EXIT

Terminates the management client.

This command does not affect any nodes connected to the cluster.

SHUTDOWN

Shuts down all cluster data nodes and management nodes. To exit the management client after this has been done, use EXIT or OUIT.

This command does not shut down any SQL nodes or API nodes that are connected to the cluster.

CREATE NODEGROUP nodeid[, nodeid, ...]

Creates a new MySQL Cluster node group and causes data nodes to join it.

This command is used after adding new data nodes online to a MySQL Cluster, and causes them to join a new node group and thus to begin participating fully in the cluster. The command takes as its sole parameter a comma-separated list of node IDs—these are the IDs of the nodes just added and started that are to join the new node group. The number of nodes must be the same as the number of nodes in each node group that is already part of the cluster (each MySQL Cluster node group must have the same number of nodes). In other words, if the MySQL Cluster has 2 node groups of 2 data nodes each, then the new node group must also have 2 data nodes.

The node group ID of the new node group created by this command is determined automatically, and always the next highest unused node group ID in the cluster; it is not possible to set it manually.

This command was introduced in MySQL Cluster NDB 6.4.0. For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".

DROP NODEGROUP nodegroup_id

Drops the MySQL Cluster node group with the given nodegroup_id.

This command can be used to drop a node group from a MySQL Cluster. DROP NODEGROUP takes as its sole argument the node group ID of the node group to be dropped.

DROP NODEGROUP acts only to remove the data nodes in the effected node group from that node group. It does not stop data nodes, assign them to a different node group, or remove them from the cluster's configuration. A data node that does not belong to a node group is indicated in the output of the management client SHOW command with no nodegroup in place of the node group ID, like this (indicated using bold text):

```
id=3 @10.100.2.67 (5.1.56-ndb-7.1.16, no nodegroup)
```

Prior to MySOL Cluster NDB 7.0.4, the SHOW output was not updated correctly following DROP NODEGROUP. (Bug #43413)

DROP NODEGROUP works only when all data nodes in the node group to be dropped are completely empty of any table data and table definitions. Since there is currently no way using ndb_mgm or the mysql client to remove all data from a specific data node or node group, this means that the command succeeds only in the two following cases:

- 1. After issuing CREATE NODEGROUP in the ndb_mgm client, but before issuing any ALTER ONLINE TABLE ... REORGANIZE PARTITION statements in the mysql client.
- 2. After dropping all NDBCLUSTER tables using DROP TABLE.

TRUNCATE TABLE does not work for this purpose because this removes only the table data; the data nodes continue to store an NDBCLUSTER table's definition until a DROP TABLE statement is issued that causes the table metadata to be dropped.

DROP NODEGROUP was introduced in MySQL Cluster NDB 6.4.0. For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".

5.3. Online Backup of MySQL Cluster

The next few sections describe how to prepare for and then to create a MySQL Cluster backup using the functionality for this purpose found in the ndb_mgm management client. To distinguish this type of backup from a backup made using mysqldump, we sometimes refer to it as a "native" MySQL Cluster backup. (For information about the creation of backups with mysqldump, see mysqldump.) Restoration of MySQL Cluster backups is done using the ndb_restore utility provided with the MySQL Cluster distribution; for information about ndb_restore and its use in restoring MySQL Cluster backups, see Section 4.17,

ndb_restore — Restore a MySQL Cluster Backup".

5.3.1. MySQL Cluster Backup Concepts

A backup is a snapshot of the database at a given time. The backup consists of three main parts:

- Metadata. The names and definitions of all database tables
- Table records. The data actually stored in the database tables at the time that the backup was made
- Transaction log. A sequential record telling how and when data was stored in the database

Each of these parts is saved on all nodes participating in the backup. During backup, each node saves these three parts into three files on disk:

• BACKUP-backup_id.node_id.ctl

A control file containing control information and metadata. Each node saves the same table definitions (for all tables in the cluster) to its own version of this file.

• BACKUP-backup_id-0.node_id.data

A data file containing the table records, which are saved on a per-fragment basis. That is, different nodes save different fragments during the backup. The file saved by each node starts with a header that states the tables to which the records belong. Following the list of records there is a footer containing a checksum for all records.

BACKUP-backup_id.node_id.log

A log file containing records of committed transactions. Only transactions on tables stored in the backup are stored in the log. Nodes involved in the backup save different records because different nodes host different database fragments.

In the listing above, <code>backup_id</code> stands for the backup identifier and <code>node_id</code> is the unique identifier for the node creating the file.

5.3.2. Using The MySQL Cluster Management Client to Create a Backup

Before starting a backup, make sure that the cluster is properly configured for performing one. (See Section 5.3.3, "Configuration for MySQL Cluster Backups".)

The START BACKUP command is used to create a backup:

```
START BACKUP [backup_id] [wait_option] [snapshot_option]
wait_option:
WAIT {STARTED | COMPLETED} | NOWAIT
snapshot_option:
SNAPSHOTSTART | SNAPSHOTEND
```

Successive backups are automatically identified sequentially, so the <code>backup_id</code>, an integer greater than or equal to 1, is optional; if it is omitted, the next available value is used. If an existing <code>backup_id</code> value is used, the backup fails with the error <code>Backup_id</code> must follow <code>START BACKUP</code> immediately, before any other options are used.

Prior to MySQL Cluster NDB 6.2.17, 6.3.23, and 6.4.3, backup IDs greater than $2147483648 (2^{31})$ were not supported correctly. (Bug #43042) Beginning with these versions, the maximum possible backup ID is $4294967296 (2^{32})$.

Note

Prior to MySQL Cluster NDB 7.0.5, when starting a backup using ndb_mgm -e "START BACKUP", the backup_id was required. (Bug #31754)

The wait_option can be used to determine when control is returned to the management client after a START BACKUP command is issued, as shown in the following list:

• If NOWAIT is specified, the management client displays a prompt immediately, as seen here:

```
ndb_mgm> START BACKUP NOWAIT ndb_mgm>
```

In this case, the management client can be used even while it prints progress information from the backup process.

 With WAIT STARTED the management client waits until the backup has started before returning control to the user, as shown here:

```
ndb_mgm> START BACKUP WAIT STARTED
Waiting for started, this may take several minutes
Node 2: Backup 3 started from node 1
ndb_mgm>
```

WAIT COMPLETED causes the management client to wait until the backup process is complete before returning control to the
user.

WAIT COMPLETED is the default.

Beginning with MySQL Cluster NDB 6.4.0, a <code>snapshot_option</code> can be used to determine whether the backup matches the state of the cluster when <code>START BACKUP</code> was issued, or when it was completed. <code>SNAPSHOTSTART</code> causes the backup to match the state of the cluster when the backup began; <code>SNAPSHOTEND</code> causes the backup to reflect the state of the cluster when the backup was finished. <code>SNAPSHOTEND</code> is the default, and matches the behavior found in previous <code>MySQL</code> Cluster releases.

Note

If you use the SNAPSHOTSTART option with START BACKUP, and the CompressedBackup parameter is enabled, only the data and control files are compressed—the log file is not compressed.

If both a wait_option and a snapshot_option are used, they may be specified in either order. For example, all of the following commands are valid, assuming that there is no existing backup having 4 as its ID:

```
START BACKUP WAIT STARTED SNAPSHOTSTART
START BACKUP SNAPSHOTSTART WAIT STARTED
START BACKUP 4 WAIT COMPLETED SNAPSHOTSTART
START BACKUP SNAPSHOTEND WAIT COMPLETED
START BACKUP 4 NOWAIT SNAPSHOTSTART
```

The procedure for creating a backup consists of the following steps:

- 1. Start the management client (ndb_mgm), if it not running already.
- Execute the START BACKUP command. This produces several lines of output indicating the progress of the backup, as shown here:

```
ndb_mgm> START BACKUP
Waiting for completed, this may take several minutes
Node 2: Backup 1 started from node 1
Node 2: Backup 1 started from node 1 completed
StartGCP: 177 StopGCP: 180
#Records: 7362 #LogRecords: 0
Data: 453648 bytes Log: 0 bytes
ndb_mgm>
```

3. When the backup has started the management client displays this message:

```
Backup backup_id started from node node_id
```

backup_id is the unique identifier for this particular backup. This identifier is saved in the cluster log, if it has not been configured otherwise. node_id is the identifier of the management server that is coordinating the backup with the data nodes. At this point in the backup process the cluster has received and processed the backup request. It does not mean that the backup has finished. An example of this statement is shown here:

```
Node 2: Backup 1 started from node 1
```

4. The management client indicates with a message like this one that the backup has started:

```
Backup backup_id started from node node_id completed
```

As is the case for the notification that the backup has started, <code>backup_id</code> is the unique identifier for this particular backup, and <code>node_id</code> is the node ID of the management server that is coordinating the backup with the data nodes. This output is accompanied by additional information including relevant global checkpoints, the number of records backed up, and the size of

the data, as shown here:

```
Node 2: Backup 1 started from node 1 completed
StartGCP: 177 StopGCP: 180
#Records: 7362 #LogRecords: 0
Data: 453648 bytes Log: 0 bytes
```

It is also possible to perform a backup from the system shell by invoking ndb_mgm with the -e or --execute option, as shown in this example:

```
shell> ndb_mgm -e "START BACKUP 6 WAIT COMPLETED SNAPSHOTSTART"
```

When using START BACKUP in this way, you must specify the backup ID.

Cluster backups are created by default in the BACKUP subdirectory of the DataDir on each data node. This can be overridden for one or more data nodes individually, or for all cluster data nodes in the config.ini file using the BackupDataDir configuration parameter. The backup files created for a backup with a given backup_id are stored in a subdirectory named BACKUP-backup_id in the backup directory.

To abort a backup that is already in progress:

- 1. Start the management client.
- 2. Execute this command:

```
ndb_mgm> ABORT BACKUP backup_id
```

The number backup_id is the identifier of the backup that was included in the response of the management client when the backup was started (in the message Backup backup_id started from node management_node_id).

3. The management client will acknowledge the abort request with Abort of backup backup_id ordered.

Note

At this point, the management client has not yet received a response from the cluster data nodes to this request, and the backup has not yet actually been aborted.

4. After the backup has been aborted, the management client will report this fact in a manner similar to what is shown here:

```
Node 1: Backup 3 started from 5 has been aborted. Error: 1321 - Backup aborted by user request: Permanent error: U Node 3: Backup 3 started from 5 has been aborted. Error: 1323 - 1323: Permanent error: Internal error Node 2: Backup 3 started from 5 has been aborted. Error: 1323 - 1323: Permanent error: Internal error Node 4: Backup 3 started from 5 has been aborted. Error: 1323 - 1323: Permanent error: Internal error
```

In this example, we have shown sample output for a cluster with 4 data nodes, where the sequence number of the backup to be aborted is 3, and the management node to which the cluster management client is connected has the node ID 5. The first node to complete its part in aborting the backup reports that the reason for the abort was due to a request by the user. (The remaining nodes report that the backup was aborted due to an unspecified internal error.)

Note

There is no guarantee that the cluster nodes respond to an ABORT BACKUP command in any particular order.

The Backup <code>backup_id</code> started from node <code>management_node_id</code> has been aborted messages mean that the backup has been terminated and that all files relating to this backup have been removed from the cluster file system.

It is also possible to abort a backup in progress from a system shell using this command:

```
shell> ndb_mgm -e "ABORT BACKUP backup_id"
```

Note

If there is no backup having the ID backup_id running when an ABORT BACKUP is issued, the management client makes no response, nor is it indicated in the cluster log that an invalid abort command was sent.

5.3.3. Configuration for MySQL Cluster Backups

Five configuration parameters are essential for backup:

BackupDataBufferSize

The amount of memory used to buffer data before it is written to disk.

• BackupLogBufferSize

The amount of memory used to buffer log records before these are written to disk.

BackupMemory

The total memory allocated in a data node for backups. This should be the sum of the memory allocated for the backup data buffer and the backup log buffer.

• BackupWriteSize

The default size of blocks written to disk. This applies for both the backup data buffer and the backup log buffer.

BackupMaxWriteSize

The maximum size of blocks written to disk. This applies for both the backup data buffer and the backup log buffer.

More detailed information about these parameters can be found in Backup Parameters.

5.3.4. MySQL Cluster Backup Troubleshooting

If an error code is returned when issuing a backup request, the most likely cause is insufficient memory or disk space. You should check that there is enough memory allocated for the backup.

Important

If you have set BackupDataBufferSize and BackupLogBufferSize and their sum is greater than 4MB, then you must also set BackupMemory as well.

You should also make sure that there is sufficient space on the hard drive partition of the backup target.

NDB does not support repeatable reads, which can cause problems with the restoration process. Although the backup process is "hot", restoring a MySQL Cluster from backup is not a 100% "hot" process. This is due to the fact that, for the duration of the restore process, running transactions get nonrepeatable reads from the restored data. This means that the state of the data is inconsistent while the restore is in progress.

5.4. Performing a Rolling Restart of a MySQL Cluster

This section discusses how to perform a *rolling restart* of a MySQL Cluster installation, so called because it involves stopping and starting (or restarting) each node in turn, so that the cluster itself remains operational. This is often done as part of a *rolling upgrade* or *rolling downgrade*, where high availability of the cluster is mandatory and no downtime of the cluster as a whole is permissible. Where we refer to upgrades, the information provided here also generally applies to downgrades as well.

There are a number of reasons why a rolling restart might be desirable. These are described in the next few paragraphs.

Configuration change. To make a change in the cluster's configuration, such as adding an SQL node to the cluster, or setting a configuration parameter to a new value.

MySQL Cluster software upgrade or downgrade. To upgrade the cluster to a newer version of the MySQL Cluster software (or to downgrade it to an older version). This is usually referred to as a "rolling upgrade" (or "rolling downgrade", when reverting to an older version of MySQL Cluster).

Change on node host. To make changes in the hardware or operating system on which one or more MySQL Cluster node processes are running.

System reset (cluster reset). To reset the cluster because it has reached an undesirable state. In such cases it is often desirable to reload the data and metadata of one or more data nodes. This can be done in any of three ways:

Start each data node process (ndbd, or possibly ndbmtd in MySQL Cluster NDB 7.0 and later) with the --initial option, which forces the data node to clear its file system and to reload all MySQL Cluster data and metadata from the other data nodes.

• Create a backup using the ndb_mgm client BACKUP command prior to performing the restart. Following the upgrade, restore the node or nodes using ndb_restore.

See Section 5.3, "Online Backup of MySQL Cluster", and Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup", for more information.

• Use mysqldump to create a backup prior to the upgrade; afterward, restore the dump using LOAD DATA INFILE.

Resource Recovery. To free memory previously allocated to a table by successive INSERT and DELETE operations, for re-use by other MySQL Cluster tables.

The process for performing a rolling restart may be generalized as follows:

- 1. Stop all cluster management nodes (ndb_mgmd processes), reconfigure them, then restart them.
- 2. Stop, reconfigure, then restart each cluster data node (ndbd process) in turn.
- 3. Stop, reconfigure, then restart each cluster SQL node (mysqld process) in turn.

The specifics for implementing a given rolling upgrade depend upon the changes being made. A more detailed view of the process is presented here:

RESTART TYPE:					
Cluster Configuration Change		Cluster Software Upgrade or Downgrade	Change on Node Host	Cluster Reset	
	A. Manag	gement node	nab_mgma) pro	cesses	
1. Stop all ndb_mgmd processes 2. Make changes in global configuration file(s) 3. Start all ndb_mgmd processes		1. Stop all ndb_mgmd processes 2. Replace each ndb_mgmd binary with new version 3. Start ndb_mgmd processes	1. Stop all ndb_mqmd processes 2. Make desired changes in hardware, operating system, or both 3. Start all ndb_mqmd processes	1. Stop all ndb_mqmd processes 2. Start all ndb_mqmd processes	Restart all ndb_mgmd processes (option al)
	B. For	each data no	de (nābā) prod	ess	
(01	R)		1. Stop ndbd	(OF	?)
Stop ndbd Start ndbd	Restart ndbd	Stop ndbd Replace ndbd binary with new version Start ndbd	2. Make desired changes in hardware, operating system, or both 3. Start ndbd	1. Stop ndbd 2. Start ndbd	Restart ndbd
	C For	anch SOL mad			
(01		each SQL nod	1. Stop	(OF	2.1
1. Stop mysqld 2. Start mysqld	Restart mysgld	1. Stop mysqld 2. Replace mysqld binary with new version 3. Start mysqld	2. Make desired changes in hardware, operating system, or both 3. Start mysqld	1.Stop mysqld 2.Start mysqld	Restart mysqld

In the previous diagram, the **Stop** and **Start** steps indicate that the process must be stopped completely using a shell command (such as kill on most Unix systems) or the management client STOP command, then started again from a system shell by invoking the ndbd or ndb_mgmd executable as appropriate. On Windows (MySQL Cluster NDB 7.1.3 and later), you can also use the system NET START and NET STOP commands or the Windows Service Manager to start and stop nodes which have been installed as Windows services (see Section 2.2.4, "Installing MySQL Cluster Processes as Windows Services").

Restart indicates that the process may be restarted using the ndb_mgm management client RESTART command (see Section 5.2, "Commands in the MySQL Cluster Management Client").

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10. When performing an upgrade or downgrade of the cluster software, you must upgrade or downgrade the management nodes first, then the data nodes, and finally the SQL nodes. Doing so in any other order may leave the cluster in an unusable state.

MySQL Cluster NDB 6.3.29 and later; MySQL Cluster NDB 7.0.10 and later. MySQL Cluster supports a more flexible order

for upgrading the cluster nodes. When upgrading a cluster running MySQL Cluster NDB 6.3.29 or later, or a cluster that is running MySQL Cluster NDB 7.0.10 or later, you may upgrade API nodes (including SQL nodes) before upgrading the management nodes, data nodes, or both. In other words, you are permitted to upgrade the API and SQL nodes in any order. This is subject to the following provisions:

- This functionality is intended for use as part of an online upgrade only. A mix of node binaries from different MySQL Cluster releases is neither intended nor supported for constant, long-term use in a production setting.
- All management nodes must be upgraded before any data nodes are upgraded. This remains true regardless of the order in which you upgrade the cluster's API and SQL nodes.
- For MySQL Cluster NDB 6.3, the ability to upgrade API nodes in any order relative to upgading management nodes and data nodes is supported only for MySQL Cluster NDB 6.3.29 and later; for MySQL Cluster NDB 7.0, it supported only for MySQL Cluster NDB 7.0.10 and later. This means that, if you are upgrading from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0 release, the "old" NDB engine version must be 6.3.29 or later, and the "new" NDB engine version must be 7.0.10 or later.
- When upgrading the cluster from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0 release: Once you have started upgrading the API nodes, you should not perform DDL operations until all management nodes and data nodes have been upgraded. DML operations should be unaffected, and can continue while the upgrade is in progress.

However, it is possible to perform DDL from an "old" (NDB 6.3 version) API node as long as the master data node is also running the "old" version of MySQL Cluster. You should keep in mind that a data node restart could result in the master node running a "new" (NDB 7.0 version) binary while one or more data nodes are still using the "old" (NDB 6.3) version; in this situation, no DDL can be performed from *any* API node, because the master data node is no longer using an NDB 6.3 binary, but the cluster still contains nodes which are not yet using NDB 7.0. For this reason, we recommend that you avoid performing DDL at any time while the upgrade is in progress.

· Features specific to the "new" version must not be used until all management nodes and data nodes have been upgraded.

This also applies to any MySQL Server version change that may apply, in addition to the NDB engine version change, so do not forget to take this into account when planning the upgrade. (This is true for online upgrades of MySQL Cluster in general.)

See also Bug #48528 and Bug #49163.

MySQL Cluster NDB 7.0.24 and later; MySQL Cluster NDB 7.1.13 and later. When performing a rolling restart to update the cluster's configuration, you can use the config_generation column of the ndbinfo.nodes table to keep track of which data nodes have been successfully restarted with the new configuration. See Section 5.9.8, "The ndbinfo nodes Table".

5.5. Event Reports Generated in MySQL Cluster

In this section, we discuss the types of event logs provided by MySQL Cluster, and the types of events that are logged.

MySQL Cluster provides two types of event log:

• The *cluster log*, which includes events generated by all cluster nodes. The cluster log is the log recommended for most uses because it provides logging information for an entire cluster in a single location.

By default, the cluster log is saved to a file named ndb_node_id_cluster.log, (where node_id is the node ID of the management server) in the same directory where the ndb_mgm binary resides.

Cluster logging information can also be sent to stdout or a syslog facility in addition to or instead of being saved to a file, as determined by the values set for the DataDir and LogDestination configuration parameters. See Section 3.2.5, "Defining a MySQL Cluster Management Server", for more information about these parameters.

• Node logs are local to each node.

Output generated by node event logging is written to the file ndb_node_id_out.log (where node_id is the node's node ID) in the node's DataDir. Node event logs are generated for both management nodes and data nodes.

Node logs are intended to be used only during application development, or for debugging application code.

Both types of event logs can be set to log different subsets of events.

Each reportable event can be distinguished according to three different criteria:

- Category: This can be any one of the following values: STARTUP, SHUTDOWN, STATISTICS, CHECKPOINT, NODERESTART, CONNECTION, ERROR, or INFO.
- *Priority*: This is represented by one of the numbers from 1 to 15 inclusive, where 1 indicates "most important" and 15 "least important."
- Severity Level: This can be any one of the following values: ALERT, CRITICAL, ERROR, WARNING, INFO, or DEBUG.

Both the cluster log and the node log can be filtered on these properties.

The format used in the cluster log is as shown here:

```
Data usage is 2%(60 32K pages of total 2560)
Index usage is 1%(24 8K pages of total 2336)
Resource 0 min: 0 max: 639 curr: 0
Data usage is 2%(76 32K pages of total 2560)
Index usage is 1%(24 8K pages of total 2336)
2007-01-26 19:35:55
2007-01-26 19:35:55
                                                     [MgmSrvr
[MgmSrvr
                                                                                                            Node 1:
Node 1:
                                                                              INFO
2007-01-26 19:35:55
2007-01-26 19:35:55
                                                     [MgmSrvr
[MgmSrvr
                                                                             INFO
INFO
                                                                                                            Node
Node
                                                                                                                         1:
                                                                                                                         2:
2007-01-26 19:35:55
2007-01-26 19:35:55
                                                                                                            Node 2:
Node 2:
                                                      MgmSrvr
                                                                                                                                Index usage is 1%(24 8K pages of total 2336) Resource 0 min: 0 max: 639 curr: 0
Data usage is 2%(58 32K pages of total 2560) Index usage is 1%(25 8K pages of total 2336) Resource 0 min: 0 max: 639 curr: 0
Data usage is 2%(74 32K pages of total 2560) Index usage is 1%(25 8K pages of total 2336) Resource 0 min: 0 max: 639 curr: 0
                                                     [MamSrvr
                                                                              INFO
2007-01-26 19:35:55
2007-01-26 19:35:55
                                                                                                            Node
                                                                                                                         3:
                                                      [MgmSrvr
                                                     [MgmSrvr
                                                                              INFO
                                                                                                            Node 3:
                                                                                                    -- Node 3:

-- Node 4:

-- Node 4:

-- Node 4:

-- Node 4:
2007-01-26 19:35:55
2007-01-26 19:35:55
                                                      [MgmSrvr
                                                     [MgmSrvr
[MgmSrvr
                                                                              INFO
2007-01-26 19:35:55
2007-01-26 19:35:55
2007-01-26 19:39:42
                                                                              INFO
                                                     [MqmSrvr
                                                                             INFO
                                                                                                                                 Node 9
Node 9
2007-01-26
2007-01-26
                                                                                                    --
                                                      MgmSrvr
                                                                                                                                                   Connected
                           19:39:42
19:39:42
                                                     [MgmSrvr
                                                                              INFO
                                                                                                            Node
Node
                                                                                                                         1:
1:
                                                                                                                                                   Connected: API 5.1.56-ndb-7.1.16
2007-01-26 19:39:42
2007-01-26 19:39:42
2007-01-26 19:39:42
2007-01-26 19:39:42
                                                     [MgmSrvr
                                                                              INFO
                                                                                                                                 Node
                                                                                                                               Node 9 Connected
Node 9: API 5.1.56-ndb-7.1.16
Node 9: API 5.1.56-ndb-7.1.16
Node 9: API 5.1.56-ndb-7.1.16
Node 7 Disconnected
Node 7 Disconnected
                                                     [MgmSrvr
[MgmSrvr
                                                                                                            Node
Node
                                                                                                                         2:
2:
                                                                              INFO
                                                                              INFO
2007-01-26 19:39:42
2007-01-26 19:39:42
                                                    [MgmSrvr
[MgmSrvr
                                                                             INFO
INFO
                                                                                                            Node
Node
                                                                                                                         3:
2007-01-26 19:39:42
2007-01-26 19:59:22
                                                    [MgmSrvr
[MgmSrvr
                                                                                                                         4:
2:
                                                                              INFO
                                                                                                            Node
                                                                             ALERT
                                                                                                            Node
2007-01-26 19:59:22
                                                                                                                          2:
```

Each line in the cluster log contains the following information:

- A timestamp in YYYY-MM-DD HH:MM:SS format.
- The type of node which is performing the logging. In the cluster log, this is always [MgmSrvr].
- The severity of the event.
- The ID of the node reporting the event.
- A description of the event. The most common types of events to appear in the log are connections and disconnections between
 different nodes in the cluster, and when checkpoints occur. In some cases, the description may contain status information.

5.5.1. MySQL Cluster Logging Management Commands

The following management commands are related to the cluster log:

• CLUSTERLOG ON

Turns the cluster log on.

• CLUSTERLOG OFF

Turns the cluster log off.

CLUSTERLOG INFO

Provides information about cluster log settings.

• node_id CLUSTERLOG category=threshold

Logs category events with priority less than or equal to threshold in the cluster log.

CLUSTERLOG FILTER severity_level

Toggles cluster logging of events of the specified severity_level.

The following table describes the default setting (for all data nodes) of the cluster log category threshold. If an event has a priority with a value lower than or equal to the priority threshold, it is reported in the cluster log.

Note that events are reported per data node, and that the threshold can be set to different values on different nodes.

Category	Default threshold (All data nodes)		
STARTUP	7		
SHUTDOWN	7		
STATISTICS	7		
CHECKPOINT	7		
NODERESTART	7		
CONNECTION	7		
ERROR	15		
INFO	7		

The STATISTICS category can provide a great deal of useful data. See Section 5.5.3, "Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client", for more information.

Thresholds are used to filter events within each category. For example, a STARTUP event with a priority of 3 is not logged unless the threshold for STARTUP is set to 3 or higher. Only events with priority 3 or lower are sent if the threshold is 3.

The following table shows the event severity levels.

Note

These correspond to Unix syslog levels, except for LOG_EMERG and LOG_NOTICE, which are not used or mapped.

1	ALERT	A condition that should be corrected immediately, such as a corrupted system database
2	CRITICAL	Critical conditions, such as device errors or insufficient resources
3	ERROR	Conditions that should be corrected, such as configuration errors
4	WARNING	Conditions that are not errors, but that might require special handling
5	INFO	Informational messages
6	DEBUG	Debugging messages used for NDBCLUSTER development

Event severity levels can be turned on or off (using CLUSTERLOG FILTER—see above). If a severity level is turned on, then all events with a priority less than or equal to the category thresholds are logged. If the severity level is turned off then no events belonging to that severity level are logged.

Important

Cluster log levels are set on a per ndb_mgmd, per subscriber basis. This means that, in a MySQL Cluster with multiple management servers, using a CLUSTERLOG command in an instance of ndb_mgm connected to one management server affects only logs generated by that management server but not by any of the others. This also means that, should one of the management servers be restarted, only logs generated by that management server are affected by the resetting of log levels caused by the restart.

5.5.2. MySQL Cluster Log Events

An event report reported in the event logs has the following format:

```
datetime [string] severity -- message
```

For example:

```
09:19:30 2005-07-24 [NDB] INFO -- Node 4 Start phase 4 completed
```

This section discusses all reportable events, ordered by category and severity level within each category.

In the event descriptions, GCP and LCP mean "Global Checkpoint" and "Local Checkpoint", respectively.

CONNECTION Events

These events are associated with connections between Cluster nodes.

Event	Priority	Severity Level	Description
data nodes connected	8	INFO	Data nodes connected
data nodes disconnected	8	INFO	Data nodes disconnected
Communication closed	8	INFO	SQL node or data node connection closed
Communication opened	8	INFO	SQL node or data node connection opened

CHECKPOINT Events

The logging messages shown here are associated with checkpoints.

Event	Priority	Severity Level	Description
LCP stopped in calc keep GCI	0	ALERT	LCP stopped
Local checkpoint fragment completed	11	INFO	LCP on a fragment has been completed
Global checkpoint completed	10	INFO	GCP finished
Global checkpoint started	9	INFO	Start of GCP: REDO log is written to disk
Local checkpoint completed	8	INFO	LCP completed normally
Local checkpoint started	7	INFO	Start of LCP: data written to disk

STARTUP Events

The following events are generated in response to the startup of a node or of the cluster and of its success or failure. They also provide information relating to the progress of the startup process, including information concerning logging activities.

Event	Priority	Severity Level	Description
Internal start signal received STTORRY	15	INFO	Blocks received after completion of restart
New REDO log started	10	INFO	GCI keep X, newest restorable GCI Y
New log started	10	INFO	Log part X, start MB Y, stop MB Z
Node has been refused for inclusion in the cluster	8	INFO	Node cannot be included in cluster due to misconfigura- tion, inability to establish communication, or other prob- lem
data node neighbors	8	INFO	Shows neighboring data nodes
data node start phase X completed	4	INFO	A data node start phase has been completed
Node has been successfully included into the cluster	3	INFO	Displays the node, managing node, and dynamic ID
data node start phases initiated	1	INFO	NDB Cluster nodes starting
data node all start phases completed	1	INFO	NDB Cluster nodes started
data node shutdown initiated	1	INFO	Shutdown of data node has commenced
data node shutdown aborted	1	INFO	Unable to shut down data node normally

NODERESTART Events

The following events are generated when restarting a node and relate to the success or failure of the node restart process.

Event	Priority	Severity Level	Description
Node failure phase completed	8	ALERT	Reports completion of node failure phases
Node has failed, node state was X	8	ALERT	Reports that a node has failed
Report arbitrator results	2	ALERT	There are eight different possible results for arbitration attempts:
	2:	29	

Event	Priority	Severity Level	Description
			 Arbitration check failed—less than 1/2 nodes left Arbitration check succeeded—node group majority Arbitration check failed—missing node group Network partitioning—arbitration required Arbitration succeeded—affirmative response from node <i>X</i> Arbitration failed - negative response from node <i>X</i> Network partitioning - no arbitrator available Network partitioning - no arbitrator configured
Completed copying a fragment	10	INFO	
Completed copying of dictionary information	8	INFO	
Completed copying distribution information	8	INFO	
Starting to copy fragments	8	INFO	
Completed copying all fragments	8	INFO	
GCP takeover started	7	INFO	
GCP takeover completed	7	INFO	
LCP takeover started	7	INFO	
LCP takeover completed (state = <i>X</i>)	7	INFO	
Report whether an arbitrator is found or not	6	INFO	There are seven different possible outcomes when seeking an arbitrator:
			 Management server restarts arbitration thread [state=X] Prepare arbitrator node X [ticket=Y] Receive arbitrator node X [ticket=Y] Started arbitrator node X [ticket=Y] Lost arbitrator node X - process failure [state=Y] Lost arbitrator node X - process exit [state=Y] Lost arbitrator node X < error msg> [state=Y]

STATISTICS Events

The following events are of a statistical nature. They provide information such as numbers of transactions and other operations, amount of data sent or received by individual nodes, and memory usage.

Event	Priority	Severity Level	Description
Report job scheduling statistics	9	INFO	Mean internal job scheduling statistics
Sent number of bytes	9	INFO	Mean number of bytes sent to node X
Received # of bytes	9	INFO	Mean number of bytes received from node X
Report transaction statistics	8	INFO	Numbers of: transactions, commits, reads, simple reads, writes, concurrent operations, attribute information, and aborts

Event	Priority	Severity Level	Description
Report operations	8	INFO	Number of operations
Report table create	7	INFO	
Memory usage	5	INFO	Data and index memory usage (80%, 90%, and 100%)

ERROR Events

These events relate to Cluster errors and warnings. The presence of one or more of these generally indicates that a major malfunction or failure has occurred.

Event	Priority	Severity	Description
Dead due to missed heartbeat	8	ALERT	Node X declared "dead" due to missed heartbeat
Transporter errors	2	ERROR	
Transporter warnings	8	WARNING	
Missed heartbeats	8	WARNING	Node X missed heartbeat #Y
General warning events	2	WARNING	

INFO Events

These events provide general information about the state of the cluster and activities associated with Cluster maintenance, such as logging and heartbeat transmission.

Event	Priority	Severity	Description
Sent heartbeat	12	INFO	Heartbeat sent to node <i>X</i>
Create log bytes	11	INFO	Log part, log file, MB
General information events	2	INFO	

5.5.3. Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client

The NDB management client's CLUSTERLOG STATISTICS command can provide a number of useful statistics in its output. Counters providing information about the state of the cluster are updated at 5-second reporting intervals by the transaction coordinator (TC) and the local query handler (LQH), and written to the cluster log.

Transaction coordinator statistics. Each transaction has one transaction coordinator, which is chosen by one of the following methods:

- In a round-robin fashion
- By communication proximity
- (Beginning with MySQL Cluster NDB 6.3.4:) By supplying a data placement hint when the transaction is started

Note

You can determine which TC selection method is used for transactions started from a given SQL node using the ndb_optimized_node_selection system variable.

All operations within the same transaction use the same transaction coordinator, which reports the following statistics:

• Trans count. This is the number transactions started in the last interval using this TC as the transaction coordinator. Any of these transactions may have committed, have been aborted, or remain uncommitted at the end of the reporting interval.

Note

Transactions do not migrate between TCs.

- Commit count. This is the number of transactions using this TC as the transaction coordinator that were committed in the last reporting interval. Because some transactions committed in this reporting interval may have started in a previous reporting interval, it is possible for Commit count to be greater than Trans count.
- Read count. This is the number of primary key read operations using this TC as the transaction coordinator that were started in the last reporting interval, including simple reads. This count also includes reads performed as part of unique index operations. A unique index read operation generates 2 primary key read operations—1 for the hidden unique index table, and 1 for the table on which the read takes place.
- Simple read count. This is the number of simple read operations using this TC as the transaction coordinator that were started in the last reporting interval. This is a subset of Read count. Because the value of Simple read count is incremented at a different point in time from Read count, it can lag behind Read count slightly, so it is conceivable that Simple read count is not equal to Read count for a given reporting interval, even if all reads made during that time were in fact simple reads.
- Write count. This is the number of primary key write operations using this TC as the transaction coordinator that were started in the last reporting interval. This includes all inserts, updates, writes and deletes, as well as writes performed as part of unique index operations.

Note

A unique index update operation can generate multiple PK read and write operations on the index table and on the base table.

• AttrInfoCount. This is the number of 32-bit data words received in the last reporting interval for primary key operations using this TC as the transaction coordinator. For reads, this is proportional to the number of columns requested. For inserts and updates, this is proportional to the number of columns written, and the size of their data. For delete operations, this is usually zero.

Unique index operations generate multiple PK operations and so increase this count. However, data words sent to describe the PK operation itself, and the key information sent, are *not* counted here. Attribute information sent to describe columns to read for scans, or to describe ScanFilters, is also not counted in AttrInfoCount.

Concurrent Operations. This is the number of primary key or scan operations using this TC as the transaction coordinator that were started during the last reporting interval but that were not completed. Operations increment this counter when they are started and decrement it when they are completed; this occurs after the transaction commits. Dirty reads and writes—as well as failed operations—decrement this counter.

The maximum value that Concurrent Operations can have is the maximum number of operations that a TC block can support; currently, this is (2 * MaxNoOfConcurrentOperations) + 16 + MaxNoOfConcurrentTransactions. (For more information about these configuration parameters, see the *Transaction Parameters* section of Section 3.2.6, "Defining MySQL Cluster Data Nodes".)

- Abort count. This is the number of transactions using this TC as the transaction coordinator that were aborted during the last reporting interval. Because some transactions that were aborted in the last reporting interval may have started in a previous reporting interval, Abort count can sometimes be greater than Trans count.
- Scans. This is the number of table scans using this TC as the transaction coordinator that were started during the last reporting interval. This does not include range scans (that is, ordered index scans).
- Range scans. This is the number of ordered index scans using this TC as the transaction coordinator that were started in the last reporting interval.

Local query handler statistics (Operations). There is 1 cluster event per local query handler block (that is, 1 per data node process). Operations are recorded in the LQH where the data they are operating on resides.

Note

A single transaction may operate on data stored in multiple LQH blocks.

The Operations statistic provides the number of local operations performed by this LQH block in the last reporting interval, and includes all types of read and write operations (insert, update, write, and delete operations). This also includes operations used to replicate writes. For example, in a 2-replica cluster, the write to the primary replica is recorded in the primary LQH, and the write to the backup will be recorded in the backup LQH. Unique key operations may result in multiple local operations; however, this does *not* include local operations generated as a result of a table scan or ordered index scan, which are not counted.

Process scheduler statistics. In addition to the statistics reported by the transaction coordinator and local query handler, each ndbd process has a scheduler which also provides useful metrics relating to the performance of a MySQL Cluster. This scheduler

runs in an infinite loop; during each loop the scheduler performs the following tasks:

- 1. Read any incoming messages from sockets into a job buffer.
- 2. Check whether there are any timed messages to be executed; if so, put these into the job buffer as well.
- 3. Execute (in a loop) any messages in the job buffer.
- 4. Send any distributed messages that were generated by executing the messages in the job buffer.
- 5. Wait for any new incoming messages.

Process scheduler statistics include the following:

- Mean Loop Counter. This is the number of loops executed in the third step from the preceding list. This statistic increases
 in size as the utilization of the TCP/IP buffer improves. You can use this to monitor changes in performance as you add new
 data node processes.
- Mean send size and Mean receive size. These statistics enable you to gauge the efficiency of, respectively writes
 and reads between nodes. The values are given in bytes. Higher values mean a lower cost per byte sent or received; the maximum value is 64K.

To cause all cluster log statistics to be logged, you can use the following command in the NDB management client:

ndb_mgm> ALL CLUSTERLOG STATISTICS=15

Note

Setting the threshold for STATISTICS to 15 causes the cluster log to become very verbose, and to grow quite rapidly in size, in direct proportion to the number of cluster nodes and the amount of activity in the MySQL Cluster.

For more information about MySQL Cluster management client commands relating to logging and reporting, see Section 5.5.1, "MySQL Cluster Logging Management Commands".

5.6. MySQL Cluster Log Messages

This section contains information about the messages written to the cluster log in response to different cluster log events. It provides additional, more specific information on NDB transporter errors.

5.6.1. MySQL Cluster: Messages in the Cluster Log

The following table lists the most common NDB cluster log messages. For information about the cluster log, log events, and event types, see Section 5.5, "Event Reports Generated in MySQL Cluster". These log messages also correspond to log event types in the MGM API; see The Ndb_logevent_type Type, for related information of interest to Cluster API developers.

nected Description. The data node having node ID node_id has connected to the management server (node mgm_node_id).	Event Name. Connected Event Type. Connection Priority. 8 Severity. INFO
Connected Description. The data node having node ID data_node_id has disconnected from the management server (node mgm_node_id).	Event Name. Disconnected Event Type. Connection Priority. 8 Severity. ALERT
api_node_id closed	Event Name. CommunicationClosed Event Type. Connection

no longer communicating with data node data_node_id.	
no tonger community with and note adod_itodo_ito	Priority. 8
	Severity. INFO
Log Message. Node data_node_id: Communication to Node	Event Name. CommunicationOpened
api_node_id opened	Event Type. Connection
Description. The API node or SQL node having node ID <code>api_node_id</code> is now communicating with data node <code>data_node_id</code> .	Priority. 8
-	Severity. INFO
Log Message. Node mgm_node_id: Node api_node_id: API	Event Name. ConnectedApiVersion
version	Event Type. Connection
Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version	Priority. 8
(generally the same as the MySQL version number).	Severity. INFO
Log Message. Node <i>node_id</i> : Global checkpoint <i>gci</i> started	Event Name. GlobalCheckpointStarted
Description. A global checkpoint with the ID gci has been started; node	Event Type. Checkpoint
node_id is the master responsible for this global checkpoint.	Priority. 9
	Severity. INFO
Log Message. Node node_id: Global checkpoint gci completed	Event Name. GlobalCheckpointCompleted
Description. The global checkpoint having the ID gci has been completed;	Event Type. Checkpoint
node node_id was the master responsible for this global checkpoint.	Priority. 10
	Severity. INFO
Log Message. Node node_id: Local checkpoint lcp star-	Event Name. LocalCheckpointStarted
<pre>ted. Keep GCI = current_gci oldest restorable GCI = old_gci</pre>	Event Type. Checkpoint
Description. The local checkpoint having sequence ID 1cp has been started	Priority. 7
on node node_id. The most recent GCI that can be used has the index current gci, and the oldest GCI from which the cluster can be restored	Severity. INFO
has the index old_gci.	·
Log Message. Node node_id: Local checkpoint lcp com-	Event Name. LocalCheckpointCompleted
pleted	Event Type. Checkpoint
Description. The local checkpoint having sequence ID 1cp on node node_id has been completed.	Priority. 8
	Severity. INFO
Log Message. Node node_id: Local Checkpoint stopped in	Event Name. LCPStoppedInCalcKeepGci
CALCULATED_KEEP_GCI	Event Type. Checkpoint
Description. The node was unable to determine the most recent usable GCI.	Priority. 0
	Severity. ALERT
	-
<pre>Log Message. Node node_id: Table ID = table_id, frag- ment ID = fragment_id has completed LCP on Node</pre>	Event Name. LCPFragmentCompleted
<pre>node_id maxGciStarted: started_gci maxGciCompleted: completed_gci</pre>	Event Type. Checkpoint
• • • • • • • • • • • • • • • • • • • •	Priority. 11

node_id. The GCI in progress has the index started_gci, and the most received CI to have been completed than the index completed_gci. Log Message. Node node_id: ACC Blocked num_1 and TUP Blocked num_2 times last second Description. Undo logging is blocked because the log buffer is close to overflowing. Log Message. Node node_id: Start initiated version Description. Data node node_id. running NDB version version, is beginning is startup process. Log Message. Node node_id: Started version Description. Data node node_id. running NDB version version, has started successfully. Log Message. Node node_id: Started version Description. Data node node_id: Started version Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase of a type start. Shart Phases, it (ype is one of initial, system, node, initial node, or offinknown). Log Message. Node node_id: CM_REGCONF president = president_id, own Node = cwn_id, our dynamic_id = dynamic_id; own Node node_id: CM_REGCONF president_id now Node prosident_id has been selected as "president_" com_id and dynamic_id for exporting node to the problem is given as one of Boxy, Election with wait = false, Not president_Election with wait = false, Not president_lection with out = false Not president in cluster Log Message. Node node_id: We are Node own_id with dynamic_id, our right is Node id_lection in the cluster Priority. 8 Severity. INFO Event Name. UndoLogBlocked Event Type. StartUp Priority. 1 Sevent Yupe. StartUp Priority. 2 Priority. 3 Sevent Yupe. StartUp Priority. 8 Seve		
Description. Undo logging is blocked because the log buffer is close to overflowing. Log Message. Node node_id: Start initiated version Description. Data node node_id. running NDB version version, is beginning its startup process. Log Message. Node node_id: Started version Description. Data node node_id: Started version Description. Data node node_id: Tunning NDB version version, has started successfully. Log Message. Node node_id: Started version Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySOL Cluster Start Phases", (type is one of initial, system, node, initial node, or *Unknown-b. Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id dynamic_id Description. The reporting node (ID node_id) was unable to accept node president_id, own Node node_id: CM_REGREF from Node president_id, own Node node_id: CM_REGREF from Node president_id as president, is false, Not president_sleer—tion with wait = false, Not p	Description. A table fragment has been checkpointed to disk on node node_id. The GCI in progress has the index started_gci, and the most recent GCI to have been completed has the index completed_gci.	Severity. INFO
Description. Undo logging is blocked because the log buffer is close to overflowing. Priority. 7 Severity. INFO	Log Message. Node node_id: ACC Blocked num_1 and TUP Blocked num_2 times last second	
Severity. INFO	Description. Undo logging is blocked because the log buffer is close to overflowing.	
Description. Data node node_id: Started version version, is beginning its startup process. Log Message. Node node_id: Started version Description. Data node node_id, running NDB version version, has started successfully. Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases", (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id should always be the same as the ID Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID Com Message. Node node_id: CM_REGREF from Node president_own_id and dynamic_id should always be the same as the ID Description. The reporting node. Log Message. Node node_id: CM_REGREF from Node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president_Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id_, our left neighbour is Node id_2_1, our right is Node id_2_1 our left neighbour is Node id_2_1, our right is Node id_2_1 our left neighbour is Node id_2_1, our right is Node id_2_1. Description. The node has discovered its neighboring nodes in the cluster Description. The node has discovered its neighboring nodes in the cluster</unknown>		Severity. INFO
Priority. 1 Severity. INFO Log Message. Node node_id: Started version version, has started successfully. Log Message. Node node_id: strorrer received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic_id = dynamic_id. Description. Node president_id has been selected as "president". own_id and dynamic_id, own Node = own_id, our dynamic_id = dynamic_id own Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president_Election with wait = false, Not presiden</unknown>	Log Message. Node node_id: Start initiated version	Event Name. NDBStartStarted
Log Message. Node node_id: Started version Description. Data node node_id: punning NDB version version, has started successfully. Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases", (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_RECCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_RECREE from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Ele</unknown>	Description. Data node <i>node_id</i> , running NDB version <i>version</i> , is beginning its startup process.	
Log Message. Node node_id: Started version Description. Data node node_id, running NDB version version, has started successfully. Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases", (type is one of initial, system, node, initial node, or <unknown>) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id, own Node president_id has been selected as "president". own id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id as president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president_election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1. Our right is Node id_2. Description. The node has discovered its neighboring nodes in the cluster</unknown>		
Description. Data node node_id, running NDB version version, has started successfully. Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases." (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Onde_id) of the reporting node. Log Message. Node node_id: CM_REGCONF president". own_id and dynamic_id should always be the same as the ID Onde_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president". own_id and dynamic_id should always be the same as the ID Description. The root node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president_Election with wait = false, Not president_Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id our left neighbour is Node id_1, our right is Node id_2. Description. The node has discovered its neighboring nodes in the cluster</unknown>	Log Mossago Nodo nodo id: Started vergion	
Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1. "Summary of MySQL Cluster Start Phases." (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id and dynamic_id should always be the same as the ID Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID Log Message. Node node_id: CM_REGREF from Node president". own_id and dynamic_id our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2. Description. The node has discovered its neighboring nodes in the cluster Priority. 1 Sevent Name. STTORRYRecieved Event Type. StartUp Priority. 15 Severity. INFO Event Name. CM_REGCOMF Event Name. CM_REGCONF Event Name. CM_REGREF Event Name. STTORRYRecieved Event Type. StartUp Priority. 15 Severity. INFO Event Name. CM_REGREF Event Name. CM_REGREF Event Name. CM_REGREF Event Name. STTORRYRecieved Event Name. StartUp Priority. 15 Severity. INFO Event Name. CM_REGREF Event Name. CM_REGREF Event Name. StartUp Priority. 15 Severity. INFO Event Name. StartUp Priority. 15 Severity. INFO Event Name. StartUp Event Name.</unknown>		-
Log Message. Node node_id: STTORRY received after restart finished Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases", (type is one of initial, system, node, initial node, or <unknown>-) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president_Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Name. STTORRYRecieved Event Type. StartUp Priority. 15 Severity. INFO Event Name. CM_REGCONF Event Name. CM_REGREF Event Type. StartUp Priority. 8 Severity. INFO Severity. INFO Event Name. CM_REGREF Event Type. StartUp Event Type. StartUp Priority. 8 Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8 Event Type. StartUp</unknown>	started successfully.	
Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown-) "president".="" (id="" (node_id)="" 15="" 8="" accept="" always="" and="" are="" as="" be="" been="" busy,="" candidate,="" cause="" cause.="" cluster="" cm_regconf="" cm_regref="" description.="" discovered="" dynamic="" dynamic_id="" dynamic_id,="" election="" event="" from="" given="" has="" id="" id_1,="" id_2="" in="" info="" is="" its="" left="" log="" message.="" name.="" neighboring="" neighbour="" new="" no="" node="" node.="" node_id)="" node_id.="" node_id:="" nodes="" not="" of="" one="" or="" our="" own="" own_id="" president="president_id," president,="" president.="" president_id="" priority.="" problem="" reporting="" right="" same="" selected="" selecting="" severity.="" should="" startup="" startup<="" such="" td="" the="" to="" type.="" unable="" wait="false," was="" we="" with="" without=""><td></td><td>Severity. INFO</td></unknown-)>		Severity. INFO
Description. The node has received a signal indicating that a cluster restart has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGCEF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Type. StartUp Priority. 15 Severity. INFO Event Name. CM_REGCONF Event Name. CM_REGREF Event Name. CM_REGREF Event Type. StartUp Priority. 8 Severity. INFO Event Name. FIND_NEIGHBOURS Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8</unknown>	Log Message. Node node_id: STTORRY received after re-	Event Name. STTORRYRecieved
has completed. Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster</unknown>		Event Type. StartUp
Log Message. Node node_id: Start phase phase completed (type) Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Name. StartPhaseCompleted Event Type. StartUp Priority. 4 Severity. INFO Event Name. CM_REGCONF Event Name. CM_REGCONF Event Name. CM_REGREF Event Name. StartUp Priority. 4 Severity. INFO Event Name. StartUp</unknown>	has completed.	
Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases", (type is one of initial, system, node, initial node, or <unknown>,) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election with</unknown>		Severity. INFO
Description. The node has completed start phase phase of a type start. For a listing of start phases, see Section 5.1, "Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Priority. 4 Severity. INFO Event Name. CM_REGREF Event Name. CM_REGREF Event Type. StartUp Priority. 8 Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8 Event Type. StartUp Priority. 8</unknown>	<pre>Log Message. Node node_id: Start phase phase completed (type)</pre>	
Start Phases". (type is one of initial, system, node, initial node, or <unknown>.) Log Message. Node node_id: CM_REGCONF president = president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Priority. Severity. INFO Event Name. CM_REGREF Event Type. StartUp Priority. 8 Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp</unknown>	Description. The node has completed start phase phase of a type start.	
president_id, own Node = own_id, our dynamic id = dynamic_id Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Type. StartUp Event Name. CM_REGREF Event Type. StartUp Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8	Start Phases". (<i>type</i> is one of initial, system, node, initial node, or <unknown>.)</unknown>	
Description. Node president_id has been selected as "president". own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Type. StartUp Event Name. CM_REGREF Event Type. StartUp Priority. 8 Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp	Log Message. Node node_id: CM_REGCONF president =	Event Name. CM_REGCONF
own_id and dynamic_id should always be the same as the ID (node_id) of the reporting node. Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Priority. 8 Event Name. CM_REGREF Event Type. StartUp Priority. 8 Event Name. FIND_NEIGHBOURS Event Type. StartUp	<pre>president_id, own Node = own_id, our dynamic id = dynamic_id</pre>	Event Type. StartUp
Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic_ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Severity. INFO Event Name. CM_REGREF Event Type. StartUp Event Name. FIND_NEIGHBOURS Event Name. Severity. INFO Event Name. Severity. INFO Event Name. Severity. INFO Event Name. Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8	Description. Node <i>president_id</i> has been selected as "president".	Priority. 3
<pre>ent_id to our Node node_id. Cause = cause Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster</pre> Event Type. StartUp Event Type. StartUp Priority. 8	(node_id) of the reporting node.	Severity. INFO
Description. The reporting node (ID node_id) was unable to accept node president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Type. StartUp Priority. 8 Event Type. StartUp Priority. 8 Event Type. StartUp	Log Message. Node node_id: CM_REGREF from Node president id to our Node node id. Cause = cause	Event Name. CM_REGREF
Busy, Election with wait = false, Not president, Election without selecting new candidate, or No such cause. Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Severity. INFO Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8	Description. The reporting node (ID node_id) was unable to accept node	
Log Message. Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Description. The node has discovered its neighboring nodes in the cluster Event Name. FIND_NEIGHBOURS Event Type. StartUp Priority. 8	<pre>president_id as president. The cause of the problem is given as one of Busy, Election with wait = false, Not president, Elec-</pre>	
namic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2 Event Type. StartUp Description. The node has discovered its neighboring nodes in the cluster Priority. 8		Severity. INFO
id_1, our right is Node id_2Event Type. StartUpPriority. 8	Log Message. Node node_id: We are Node own_id with dy-	Event Name. FIND_NEIGHBOURS
	<pre>namic ID dynamic_id, our left neighbour is Node id_1, our right is Node id_2</pre>	Event Type. StartUp
(node id_1 and node id_2). node_id, own_id, and dynamic_id	Description. The node has discovered its neighboring nodes in the cluster (node id_1 and node id_2). $node_id$, own_id , and $dynamic_id$	Priority. 8

	1
should always be the same; if they are not, this indicates a serious misconfiguration of the cluster nodes.	Severity. INFO
Log Message. Node node_id: type shutdown initiated	Event Name. NDBStopStarted
Description. The node has received a shutdown signal. The <i>type</i> of shut-	Event Type. StartUp
down is either Cluster or Node.	Priority. 1
	Severity. INFO
Log Message. Node node_id: Node shutdown completed [, action][Initiated by signal signal.]	Event Name. NDBStopCompleted
Description. The node has been shut down. This report may include an ac-	Event Type. StartUp
tion, which if present is one of restarting, no start, or initial. The report may also include a reference to an NDB Protocol signal; for	Priority. 1
possible signals, refer to Operations and Signals.	Severity. INFO
Log Message. Node node_id: Forced node shutdown com-	Event Name. NDBStopForced
pleted [, action]. [Occurred during startphase start_phase.][Initiated by signal.] [Caused by error	Event Type. StartUp
<pre>error_code: 'error_message(error_classification). error_status'.[(extra info extra_code)]]</pre>	Priority. 1
Description. The node has been forcibly shut down. The <i>action</i> (one of restarting, no start, or initial) subsequently being taken, if any, is also reported. If the shutdown occurred while the node was starting, the re-	Severity. ALERT
port includes the <code>start_phase</code> during which the node failed. If this was a result of a <code>signal</code> sent to the node, this information is also provided (see Operations and Signals, for more information). If the error causing the failure is known, this is also included; for more information about NDB error messages and classifications, see MySQL Cluster API Errors.	
Log Message. Node node_id: Node shutdown aborted	Event Name. NDBStopAborted
Description. The node shutdown process was aborted by the user.	Event Type. StartUp
	Priority. 1
	Severity. INFO
Log Message. Node node_id: StartLog: [GCI Keep:	Event Name. StartREDOLog
<pre>keep_pos LastCompleted: last_pos NewestRestorable: restore_pos]</pre>	Event Type. StartUp
Description. This reports global checkpoints referenced during a node start.	Priority. 4
The redo log prior to <code>keep_pos</code> is dropped. <code>last_pos</code> is the last global checkpoint in which data node the participated; <code>restore_pos</code> is the global checkpoint which is actually used to restore all data nodes.	Severity. INFO
Log Message. startup_message [Listed separately; see below.]	Event Name. StartReport
Description. There are a number of possible startup messages that can be	Event Type. StartUp
logged under different circumstances.	Priority. 4
	Severity. INFO
Log Message. Node node_id: Node restart completed copy	Event Name. NR_CopyDict
of dictionary information	Event Type. NodeRestart
Description. Copying of data dictionary information to the restarted node has been completed.	Priority. 8
•	Severity. INFO
Log Message. Node node_id: Node restart completed copy	Event Name. NR_CopyDistr
	1

		T		
of distribution information Description. Copying of data distribution information to the restarted node		Event Type. NodeRestart		
	been completed.	Priority. 8		
		Severity. INFO		
	g Message. Node node_id: Node restart starting to	Event Name. NR_CopyFragsStarted		
	by the fragments to Node node_id	Event Type. NodeRestart		
Des	scription. Copy of fragments to starting data node node_id has begun	Priority. 8		
		Severity. INFO		
	g Message. Node node_id: Table ID = table_id, frag-	Event Name. NR_CopyFragDone		
	nt ID = fragment_id have been copied to Node de_id	Event Type. NodeRestart		
Des	scription. Fragment fragment_id from table table_id has been	Priority. 10		
	ied to data node node_id	Severity. INFO		
Lac	g Message. Node node_id: Node restart completed	Event Name. NR_CopyFragsCompleted		
	bying the fragments to Node node_id	Event Type. NodeRestart		
	scription. Copying of all table fragments to restarting data node	Priority. 8		
ПОС	de_id has been completed	Severity. INFO		
Log	g Message. Any of the following:	Event Name. NodeFailCompleted		
1.	Node node_id: Node node1_id completed failure of	Event Type. NodeRestart		
	Node node2_id	Priority. 8		
2.	All nodes completed failure of Node node_id	Severity. ALERT		
3.	Node failure of node_idblock completed			
	scription. One of the following (each corresponding to the same- nbered message listed above):			
1.	Data node node1_id has detected the failure of data node node2_id			
2.	All (remaining) data nodes have detected the failure of data node node_id			
3.	The failure of data node <code>node_id</code> has been detected in the <code>blockNDB</code> kernel block, where block is 1 of <code>DBTC</code> , <code>DBDICT</code> , <code>DBDIH</code> , or <code>DBLQH</code> ; for more information, see <code>NDB Kernel Blocks</code>			
	g Message. Node mgm_node_id: Node data_node_id has iled. The Node state at failure was state_code	Event Name. NODE_FAILREP		
	scription. A data node has failed. Its state at the time of failure is de-	Event Type. NodeRestart		
scribed by an arbitration state code state_code: possible state code values can be found in the file include/ker-		Priority. 8		
	l/signaldata/ArbitSignalData.hpp.	Severity. ALERT		
Log	g Message. President restarts arbitration thread	Event Name. ArbitState		
[st	tate=state_code] or Prepare arbitrator node node_id icket=ticket_id] or Receive arbitrator node node_id	Event Type. NodeRestart		
[t:	<pre>icket=ticket_id] or Started arbitrator node node_id icket=ticket_id] or Lost arbitrator node node_id -</pre>	Priority. 6		

<pre>process failure [state=state_code] or Lost arbitrator node node_id - process exit [state=state_code] or Lost arbitrator node node_id - error_message [state=state_code]</pre>	Severity. INFO
Description. This is a report on the current state and progress of arbitration in the cluster. $node_id$ is the node ID of the management node or SQL node selected as the arbitrator. $state_code$ is an arbitration state code, as found in $include/kernel/signaldata/ArbitSignalData.hpp$. When an error has occurred, an $error_message$, also defined in $Arbit-SignalData.hpp$, is provided. $ticket_id$ is a unique identifier handed out by the arbitrator when it is selected to all the nodes that participated in its selection; this is used to ensure that each node requesting arbitration was one of the nodes that took part in the selection process.	
Log Message. Arbitration check lost - less than 1/2 nodes left or Arbitration check won - all node groups and more than 1/2 nodes left or Arbitration check won - node group majority or Arbitration check lost - missing node group or Network partitioning - arbitration required or Arbitration won - positive reply from node node_id or Arbitration lost - negative reply from node node_id or Network partitioning - no arbitrator available or Network partitioning - no arbitrator configured or Arbitration failure - error_message [state=state_code]	Event Name. ArbitResult Event Type. NodeRestart Priority. 2 Severity. ALERT
Description. This message reports on the result of arbitration. In the event of arbitration failure, an <i>error_message</i> and an arbitration <i>state_code</i> are provided; definitions for both of these are found in include/kernel/signaldata/ArbitSignalData.hpp.	
Log Message. Node node_id: GCP Take over started	Event Name. GCP_TakeoverStarted
Description. This node is attempting to assume responsibility for the next	Event Type. NodeRestart
Description. This node is attempting to assume responsibility for the next global checkpoint (that is, it is becoming the master node)	Event Type. NodeRestart Priority. 7
	Priority. 7
global checkpoint (that is, it is becoming the master node) Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibil-	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted
global checkpoint (that is, it is becoming the master node) Log Message. Node node_id: GCP Take over completed	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted
global checkpoint (that is, it is becoming the master node) Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibil-	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart
global checkpoint (that is, it is becoming the master node) Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibil-	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart Priority. 7
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next set of local checkpoints (that is, it is becoming the master node) Log Message. Node node_id: LCP Take over completed Description. This node has become the master, and has assumed responsibility.	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart Priority. 7 Severity. INFO
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next set of local checkpoints (that is, it is becoming the master node) Log Message. Node node_id: LCP Take over completed	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next set of local checkpoints (that is, it is becoming the master node) Log Message. Node node_id: LCP Take over completed Description. This node has become the master, and has assumed responsibility.	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverCompleted Event Type. NodeRestart
Log Message. Node node_id: GCP Take over completed Description. This node has become the master, and has assumed responsibility for the next global checkpoint Log Message. Node node_id: LCP Take over started Description. This node is attempting to assume responsibility for the next set of local checkpoints (that is, it is becoming the master node) Log Message. Node node_id: LCP Take over completed Description. This node has become the master, and has assumed responsibility.	Priority. 7 Severity. INFO Event Name. GCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverStarted Event Type. NodeRestart Priority. 7 Severity. INFO Event Name. LCP_TakeoverCompleted Event Type. NodeRestart Priority. 7 Severity. INFO

rent Operations = concurrent_operations, Abort Count			
= aborts, Scans = scans, Range scans = range_scans	Priority. 8 Severity. INFO		
Description. This report of transaction activity is given approximately once every 10 seconds	Seventy. INFO		
Log Message. Node node_id: Operations=operations	Event Name. OperationReportCounters		
Description. Number of operations performed by this node, provided ap-	Event Type. Statistic		
proximately once every 10 seconds	Priority. 8		
	Severity. INFO		
Log Message. Node node_id: Table with ID = table_id	Event Name. TableCreated		
created Description Aville is death ID to the last of	Event Type. Statistic		
Description. A table having the table ID shown has been created	Priority. 7		
	Severity. INFO		
Log Message. Node node_id: Mean loop Counter in doJob	Event Name. JobStatistic		
last 8192 times = count	Event Type. Statistic		
Description.	Priority. 9		
	Severity. INFO		
Log Message. Mean send size to Node = node_id last 4096 sends = bytes bytes	Event Name. SendBytesStatistic		
Description. This node is sending an average of bytes bytes per send to	Event Type. Statistic		
node node_id	Priority. 9		
	Severity. INFO		
<pre>Log Message. Mean receive size to Node = node_id last 4096 sends = bytes bytes</pre>	Event Name. ReceiveBytesStatistic		
Description. This node is receiving an average of <i>bytes</i> of data each time	Event Type. Statistic		
it receives data from node node_id	Priority. 9		
	Severity. INFO		
Log Message. Node node_id: Data usage is	Event Name. MemoryUsage		
<pre>data_memory_percentage% (data_pages_used 32K pages of total data_pages_total)/Node node_id: Index us-</pre>	Event Type. Statistic		
<pre>age is index_memory_percentage% (index_pages_used 8K pages of total index_pages_total)</pre>	Priority. 5		
Description. This report is generated when a DUMP 1000 command is issued in the cluster management client; for more information, see DUMP 1000, in MySQL Cluster Internals	Severity. INFO		
Log Message. Node node1_id: Transporter to node	Event Name. TransporterError		
node2_id reported error error_code: error_message	Event Type. Error		
Description. A transporter error occurred while communicating with node node2_id; for a listing of transporter error codes and messages, see NDB	Priority. 2		
Transporter Errors, in MySQL Cluster Internals	Severity. ERROR		
Log Massage Nade made 7 dd Turan and			
Log Message. Node node1_id: Transporter to node node2_id reported error error_code: error_message	Event Name. TransporterWarning		
Description. A warning of a potential transporter problem while communic-	Event Type. Error		

ating with node $node2_id$; for a listing of transporter error codes and messages, see NDB Transporter Errors, for more information	Priority. 8		
	Severity. WARNING		
Log Message. Node node1_id: Node node2_id missed heartbeat heartbeat_id	Event Name. MissedHeartbeat		
Description. This node missed a heartbeat from node <i>node2_id</i>	Event Type. Error		
Description: This node missed a nearboar from node node 2_14	Priority. 8		
	Severity. WARNING		
Log Message. Node node1_id: Node node2_id declared dead due to missed heartbeat	Event Name. DeadDueToHeartbeat		
Description. This node has missed at least 3 heartbeats from node	Event Type. Error		
node2_id, and so has declared that node "dead"	Priority. 8		
	Severity. ALERT		
<pre>Log Message. Node node1_id: Node Sent Heartbeat to node = node2_id</pre>	Event Name. SentHeartbeat		
Description. This node has sent a heartbeat to node <i>node2_id</i>	Event Type. Info		
Description. This node has sent a heartbeat to hode hode2_1d	Priority. 12		
	Severity. INFO		
<pre>Log Message. Node node_id: Event buffer status: used=bytes_used (percent_used%)</pre>	Event Name. EventBufferStatus		
alloc=bytes_allocated (percent_available%)	Event Type. Info		
<pre>max=bytes_available apply_gci=latest_restorable_GCI latest_gci=latest_GCI</pre>	Priority. 7		
Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints	Severity. INFO		
Log Message. Node node_id: Entering single user mode,	Event Name. SingleUser		
Node node_id: Entered single user mode Node API_node_id has exclusive access, Node node_id: En-	Event Type. Info		
tering single user mode	Priority. 7		
Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 5.7, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation	Severity. INFO		
Log Message. Node node_id: Backup backup_id started from node mgm_node_id	Event Name. BackupStarted		
Description. A backup has been started using the management node having	Event Type. Backup		
mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information,	Priority. 7		
see Section 5.3.2, "Using The MySQL Cluster Management Client to Create a Backup"	Severity. INFO		
Log Message. Node node_id: Backup backup_id started	Event Name. BackupCompleted		
<pre>from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords:</pre>	Event Type. Backup		
log_records Data: data_bytes bytes Log: log_bytes bytes	Priority. 7		

Description. The backup having the ID <code>backup_id</code> has been completed; for more information, see Section 5.3.2, "Using The MySQL Cluster Management Client to Create a Backup"	Severity. INFO
Log Message. Node node_id: Backup request from mgm_node_id failed to start. Error: error_code Description. The backup failed to start; for error codes, see MGM API Errors	Event Name. BackupFailedToStart Event Type. Backup Priority. 7 Severity. ALERT
Log Message. Node node_id: Backup backup_id started from mgm_node_id has been aborted. Error: error_code Description. The backup was terminated after starting, possibly due to user intervention	Event Name. BackupAborted Event Type. Backup Priority. 7 Severity. ALERT

5.6.2. MySQL Cluster: NDB Transporter Errors

This section lists error codes, names, and messages that are written to the cluster log in the event of transporter errors.

Error Code	Error Name	Error Text		
0x00	TE_NO_ERROR	No error		
0x01	TE_ERROR_CLOSING_SOCKET	ERROR FOUND DURING CLOSING OF SOCKET		
0x02	TE_ERROR_IN_SELECT_BEFORE_ACCEPT	ERROR FOUND BEFORE ACCEPT. THE TRANSPORTER WILL RETRY		
0x03	TE_INVALID_MESSAGE_LENGTH	ERROR FOUND IN MESSAGE (INVALID MESSAGE LENGTH)		
0x04	TE_INVALID_CHECKSUM	ERROR FOUND IN MESSAGE (CHECK-SUM)		
0x05	TE_COULD_NOT_CREATE_SOCKET	ERROR FOUND WHILE CREATING SOCKET(CAN'T CREATE SOCKET)		
0x06	TE_COULD_NOT_BIND_SOCKET	ERROR FOUND WHILE BINDING SERVER SOCKET		
0x07	TE_LISTEN_FAILED	ERROR FOUND WHILE LISTENING TO SERVER SOCKET		
0x08	TE_ACCEPT_RETURN_ERROR	ERROR FOUND DURING ACCEPT (ACCEPT RETURN ERROR)		
0x0b	TE_SHM_DISCONNECT	THE REMOTE NODE HAS DISCONNECTED		
0x0c	TE_SHM_IPC_STAT	Unable to check shm segment		
0x0d	TE_SHM_UNABLE_TO_CREATE_SEGMENT	Unable to create shm segment		
0x0e	TE_SHM_UNABLE_TO_ATTACH_SEGMENT	Unable to attach shm segment		
0x0f	TE_SHM_UNABLE_TO_REMOVE_SEGMENT	Unable to remove shm segment		
0x10	TE_TOO_SMALL_SIGID	SIG ID TOO SMALL		
0x11	TE_TOO_LARGE_SIGID	SIG ID TOO LARGE		
0x12	TE_WAIT_STACK_FULL	Wait stack was full		
0x13	TE_RECEIVE_BUFFER_FULL	RECEIVE BUFFER WAS FULL		
0x14	TE_SIGNAL_LOST_SEND_BUFFER_FULL	SEND BUFFER WAS FULL, AND TRY- ING TO FORCE SEND FAILS		
0x15	TE_SIGNAL_LOST SEND FAILED FOR UNKNOWN REASON(SIGNAL LOST)			

Error Code	Error Name	Error Text
0x16	TE_SEND_BUFFER_FULL	THE SEND BUFFER WAS FULL, BUT SLEEPING FOR A WHILE SOLVED
0x0017	TE_SCI_LINK_ERROR	THERE IS NO LINK FROM THIS NODE TO THE SWITCH
0x18	TE_SCI_UNABLE_TO_START_SEQUENCE	COULD NOT START A SEQUENCE, BECAUSE SYSTEM RESOURCES ARE EXUMED OR NO SEQUENCE HAS BEEN CREATED
0x19	TE_SCI_UNABLE_TO_REMOVE_SEQUENCE	COULD NOT REMOVE A SEQUENCE
0x1a	TE_SCI_UNABLE_TO_CREATE_SEQUENCE	COULD NOT CREATE A SEQUENCE, BECAUSE SYSTEM RESOURCES ARE EXEMPTED. MUST REBOOT
0x1b	TE_SCI_UNRECOVERABLE_DATA_TFX_ERROR	TRIED TO SEND DATA ON REDUND- ANT LINK BUT FAILED
0x1c	TE_SCI_CANNOT_INIT_LOCALSEGMENT	CANNOT INITIALIZE LOCAL SEGMENT
0x1d	TE_SCI_CANNOT_MAP_REMOTESEGMENT	CANNOT MAP REMOTE SEGMENT
0x1e	TE_SCI_UNABLE_TO_UNMAP_SEGMENT	CANNOT FREE THE RESOURCES USED BY THIS SEGMENT (STEP 1)
0x1f	TE_SCI_UNABLE_TO_REMOVE_SEGMENT	CANNOT FREE THE RESOURCES USED BY THIS SEGMENT (STEP 2)
0x20	TE_SCI_UNABLE_TO_DISCONNECT_SEGMENT	CANNOT DISCONNECT FROM A RE- MOTE SEGMENT
0x21	TE_SHM_IPC_PERMANENT	SHM IPC PERMANENT ERROR
0x22	TE_SCI_UNABLE_TO_CLOSE_CHANNEL	UNABLE TO CLOSE THE SCI CHAN- NEL AND THE RESOURCES ALLOCATED

5.7. MySQL Cluster Single User Mode

Single user mode enables the database administrator to restrict access to the database system to a single API node, such as a MySQL server (SQL node) or an instance of ndb_restore. When entering single user mode, connections to all other API nodes are closed gracefully and all running transactions are aborted. No new transactions are permitted to start.

Once the cluster has entered single user mode, only the designated API node is granted access to the database.

You can use the ALL STATUS command in the ndb_mgm client to see when the cluster has entered single user mode. Beginning with MySQL Cluster NDB 7.1.1, you can also check the status column of the ndbinfo.nodes table (see Section 5.9.8, "The ndbinfo nodes Table", for more information).

Example:

ndb_mgm> ENTER SINGLE USER MODE 5

After this command has executed and the cluster has entered single user mode, the API node whose node ID is 5 becomes the cluster's only permitted user.

The node specified in the preceding command must be an API node; attempting to specify any other type of node will be rejected.

Note

When the preceding command is invoked, all transactions running on the designated node are aborted, the connection is closed, and the server must be restarted.

The command EXIT SINGLE USER MODE changes the state of the cluster's data nodes from single user mode to normal mode. API nodes—such as MySQL Servers—waiting for a connection (that is, waiting for the cluster to become ready and available), are again permitted to connect. The API node denoted as the single-user node continues to run (if still connected) during and after the state change.

Example:

ndb_mgm> EXIT SINGLE USER MODE

There are two recommended ways to handle a node failure when running in single user mode:

- Method 1:
 - 1. Finish all single user mode transactions
 - 2. Issue the EXIT SINGLE USER MODE command
 - Restart the cluster's data nodes
- Method 2:

Restart database nodes prior to entering single user mode.

5.8. Quick Reference: MySQL Cluster SQL Statements

This section discusses several SQL statements that can prove useful in managing and monitoring a MySQL server that is connected to a MySQL Cluster, and in some cases provide information about the cluster itself.

• SHOW ENGINE NDB STATUS, SHOW ENGINE NDBCLUSTER STATUS

The output of this statement contains information about the server's connection to the cluster, creation and usage of MySQL Cluster objects, and binary logging for MySQL Cluster replication.

See SHOW ENGINE Syntax, for a usage example and more detailed information.

SHOW ENGINES

This statement can be used to determine whether or not clustering support is enabled in the MySQL server, and if so, whether it is active.

See SHOW ENGINES Syntax, for more detailed information.

Note

In MySQL 5.1 and later, this statement does not support a LIKE clause. However, you can use LIKE to filter queries against the INFORMATION_SCHEMA.ENGINES, as discussed in the next item.

SELECT * FROM INFORMATION SCHEMA.ENGINES [WHERE ENGINE LIKE 'NDB%']

This is the equivalent of SHOW ENGINES, but uses the ENGINES table of the INFORMATION_SCHEMA database (available beginning with MySQL 5.1.5). Unlike the case with the SHOW ENGINES statement, it is possible to filter the results using a LIKE clause, and to select specific columns to obtain information that may be of use in scripts. For example, the following query shows whether the server was built with NDB support and, if so, whether it is enabled:

See The INFORMATION_SCHEMA ENGINES Table, for more information.

• SHOW VARIABLES LIKE 'NDB%'

This statement provides a list of most server system variables relating to the NDB storage engine, and their values, as shown here:

See Server System Variables, for more information.

SELECT * FROM INFORMATION_SCHEMA.GLOBAL_VARIABLES WHERE VARIABLE_NAME LIKE 'NDB%';

This statement is the equivalent of the SHOW command described in the previous item, and provides almost identical output, as shown here:

```
mysql> SELECT * FROM INFORMATION_SCHEMA.GLOBAL_VARIABLES
         WHERE VARIABLE_NAME LIKE 'NDB%';
 VARIABLE_NAME
                                              VARIABLE_VALUE
  NDB_AUTOINCREMENT_PREFETCH_SZ
                                               32
  NDB_CACHE_CHECK_TIME
                                              0
  NDB_EXTRA_LOGGING
                                              ON
  NDB FORCE SEND
  NDB_INDEX_STAT_CACHE_ENTRIES
  NDB INDEX STAT ENABLE
                                              OFF
  NDB_INDEX_STAT_UPDATE_FREQ
                                              20
  NDB_REPORT_THRESH_BINLOG_EPOCH_SLIP
NDB_REPORT_THRESH_BINLOG_MEM_USAGE
                                              10
  NDB_USE_COPYING_ALTER_TABLE NDB_USE_EXACT_COUNT
                                              OFF
                                              ON
  NDB_USE_TRANSACTIONS
                                              ON
```

Unlike the case with the SHOW command, it is possible to select individual columns. For example:

See The INFORMATION_SCHEMA GLOBAL_VARIABLES and SESSION_VARIABLES Tables, and Server System Variables, for more information.

SHOW STATUS LIKE 'NDB%'

This statement shows at a glance whether or not the MySQL server is acting as a cluster SQL node, and if so, it provides the MySQL server's cluster node ID, the host name and port for the cluster management server to which it is connected, and the number of data nodes in the cluster, as shown here:

```
mysql> SHOW STATUS LIKE 'NDB%';

Variable_name | Value |

Ndb_cluster_node_id | 10
Ndb_config_from_host | 192.168.0.103
Ndb_config_from_port | 1186
Ndb_number_of_data_nodes | 4
```

If the MySQL server was built with clustering support, but it is not connected to a cluster, all rows in the output of this statement contain a zero or an empty string:

See also SHOW STATUS Syntax.

SELECT * FROM INFORMATION_SCHEMA.GLOBAL_STATUS WHERE VARIABLE_NAME LIKE 'NDB%';

Beginning with MySQL 5.1.12, this statement provides similar output to the SHOW command discussed in the previous item.

However, unlike the case with SHOW STATUS, it is possible using the SELECT to extract values in SQL for use in scripts for monitoring and automation purposes.

See The INFORMATION_SCHEMA GLOBAL_STATUS and SESSION_STATUS Tables, for more information.

Beginning with MySQL Cluster NDB 7.1.1, you can also query the tables in the ndbinfo information database for real-time data about many MySQL Cluster operations. See Section 5.9, "The ndbinfo MySQL Cluster Information Database".

5.9. The ndbinfo MySQL Cluster Information Database

ndbinfo is a database storing containing information specific to MySQL Cluster, available beginning with MySQL Cluster NDB 7.1.1.

This database contains a number of tables, each providing a different sort of data about MySQL Cluster node status, resource usage, and operations. You can find more detailed information about each of these tables in the next several sections.

ndbinfo is included with MySQL Cluster support in the MySQL Server; no special compilation or configuration steps are required; the tables are created by the MySQL Server when it connects to the cluster. You can verify that ndbinfo support is active in a given MySQL Server instance using SHOW PLUGINS; if ndbinfo support is enabled, you should see a row containing ndbinfo in the Name column and ACTIVE in the Status column, as shown here (emphasized text):

Name	Status	Type	Library	License
	ACTIVE	STORAGE ENGINE	NULL	GPL
partition	ACTIVE	STORAGE ENGINE	NULL	GPL
ARCHIVE	ACTIVE	STORAGE ENGINE	NULL	GPL
BLACKHOLE	ACTIVE	STORAGE ENGINE	NULL	GPL
CSV	ACTIVE	STORAGE ENGINE	NULL	GPL
FEDERATED	DISABLED	STORAGE ENGINE	NULL	GPL
MEMORY	ACTIVE	STORAGE ENGINE	NULL	GPL
InnoDB	ACTIVE	STORAGE ENGINE	NULL	GPL
MyISAM	ACTIVE	STORAGE ENGINE	NULL	GPL
MRG_MYISAM	ACTIVE	STORAGE ENGINE	NULL	GPL
ndbcluster	ACTIVE	STORAGE ENGINE	NULL	GPL
ndbinfo	ACTIVE	STORAGE ENGINE	NULL	GPL

You can also do this by checking the output of SHOW ENGINES for a line including ndbinfo in the Engine column and YES in the Support column, as shown here (emphasized text):

mysql> SHOW ENGINES;					
Engine	Support	Comment	Transactions	XA	Savepo
ndbcluster MRG_MYISAM / ndbinfo CSV MEMORY FEDERATED ARCHIVE InnoDB MyISAM BLACKHOLE	YES YES YES YES YES NO YES YES YES DEFAULT YES	Clustered, fault-tolerant tables Collection of identical MyISAM tables MySQL Cluster system information storage engine CSV storage engine Hash based, stored in memory, useful for temporary tables Federated MySQL storage engine Archive storage engine Supports transactions, row-level locking, and foreign keys Default engine as of MySQL 3.23 with great performance /dev/null storage engine (anything you write to it disappears)	YES NO NO NO NO NULL NO YES NO NO	NO NO NO NO NO NULL NO YES NO NO	NO NO NO NO NO NO NULL NO YES NO
10 rows in set (0.00 sec)					+

If ndbinfo support is enabled, then you can access ndbinfo using SQL statements in mysql or another MySQL client. For example, you can see ndbinfo listed in the output of SHOW DATABASES, as shown here:

If the mysqld process was not started with the --ndbcluster option, ndbinfo is not available and is not displayed by SHOW DATABASES. If mysqld was formerly connected to a MySQL Cluster but the cluster becomes unavailable (due to events such as cluster shutdown, loss of network connectivity, and so forth), ndbinfo and its tables remain visible, but an attempt to access any tables (other than blocks or config_params) fails with Got error 157 'Connection to NDB FAILED' FROM ND-BINFO.

Note

With the exception of the blocks and config_params tables, what we refer to as ndbinfo "tables" are actually views generated from internal NDB tables not visible to the MySQL Server.

All ndbinfo tables are read-only.

Beginning with MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11, ndbinfo tables are not included in the query cache. (Bug #59831)

You can select the ndbinfo database with a USE statement, and then issue a SHOW TABLES statement to obtain a list of tables, just as for any other database, like this:

The diskpagebuffer table was added in MySQL Cluster NDB 7.1.9.

In early versions of MySQL Cluster NDB 7.1, there was an additional pools table in the ndbinfo database; however, this table was removed in MySQL Cluster NDB 7.1.3.

You can execute SELECT statements against these tables, just as you would normally expect:

More complex queries, such as the two following SELECT statements using the memoryusage table, are possible:

ndbinfo table and column names are case sensitive (as is the name of the ndbinfo database itself). These identifiers are in lowercase. Trying to use the wrong lettercase results in an error, as shown in this example:

Important

Beginning with MySQL Cluster NDB 7.1.7, mysqldump ignores ndbinfo entirely, and excludes it from any output. This is true even when using the --databases or --all-databases option.

5.9.1. The ndbinfo blocks Table

The blocks table is a static table which simply contains the names and internal IDs of all NDB kernel blocks (see NDB Kernel Blocks). It is for use by the other ndbinfo tables (most of which are actually views) in mapping block numbers to block names for producing human-readable output.

The following table provides information about the columns in the blocks table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
block_number	integer	Block number
block_name	string	Block name

Although this is a static table, its content could possibly vary between different MySQL Cluster releases.

5.9.2. The ndbinfo config params Table

The config_params table is a static table which provides the names and internal ID numbers of all MySQL Cluster configuration parameters.

The following table provides information about the columns in the config_params table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
param_number	integer	The parameter's internal ID number
param_name	string	The name of the parameter

Although this is a static table, its content can vary between MySQL Cluster installations, since supported parameters can vary due to differences between software releases, cluster hardware configurations, and other factors.

5.9.3. The ndbinfo counters Table

The counters table provides running totals of events such as reads and writes for specific kernel blocks and data nodes. Counts are kept from the most recent node start or restart; a node start or restart resets all counters on that node. Not all kernel blocks have all types of counters.

The following table provides information about the columns in the counters table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Type	Remarks
node_id	integer	The data node ID
block_name	string	Name of the associated NDB kernel block (see NDB Kernel Blocks).
block_instance	integer	_REMARK_
counter_id	integer	The counter's internal ID number; normally an integer between 1 and 10, inclusive.
counter_name	string	The name of the counter. See text for names of individual counters and the NDB kernel block with which each counter is associated.
val	integer	The counter's value

Each counter is associated with a particular NDB kernel block. Prior to MySQL Cluster NDB 7.2.0, this was limited to either the DBLQH kernel block or the DBTC kernel block.

The OPERATIONS counter is associated with the DBLQH (local query handler) kernel block (see The DBLQH Block).

The ATTRINFO, TRANSACTIONS, COMMITS, READS, SIMPLE_READS, WRITES, ABORTS, TABLE_SCANS, and RANGE_SCANS counters are associated with the DBTC (transaction co-ordinator) kernel block (see The DBTC Block).

MySQL Cluster NDB 7.2.0, as part of its implementation of distributed pushed-down joins, adds the LOC-AL_TABLE_SCANS_SENT, READS_RECEIVED, PRUNED_RANGE_SCANS_RECEIVED, RANGE_SCANS_RECEIVED, LOC-AL_READS_SENT, CONST_PRUNED_RANGE_SCANS_RECEIVED, LOCAL_RANGE_SCANS_SENT, REMOTE_READS_SENT, REMOTE_READS_SENT, REMOTE_READS_NOT_FOUND, SCAN_BATCHES_RETURNED, TABLE_SCANS_RECEIVED, and SCAN_ROWS_RETURNED counters. These counters are associated with the DBSPJ (select push-down join) kernel block (see The DBSPJ Block).

5.9.4. The ndbinfo diskpagebuffer Table

The diskpagebuffer table provides stastistics about disk page buffer usage by MySQL Cluster Disk Data tables.

The following table provides information about the columns in the diskpagebuffer table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
node_id	integer	The data node ID
block_instance	integer	_REMARK_
pages_written	integer	Number of pages written to disk.
pages_written_lcp	integer	Number of pages written by local checkpoints.
pages_read	integer	Number of pages read from disk
log_waits	integer	Number of page writes waiting for log to be written to disk
page_requests_direct_return	integer	Number of requests for pages that were available in buffer
page_requests_wait_queue	integer	Number of requests that had to wait for pages to become available in buffer
page_requests_wait_io	integer	Number of requests that had to be read from pages on disk (pages were unavailable in buffer)

You can use this table with MySQL Cluster Disk Data tables to determine whether <code>DiskPageBufferMemory</code> is sufficiently large to allow data to be read from the buffer rather from disk; minimizing disk seeks can help improve performance of such tables.

You can determine the proportion of reads from DiskPageBufferMemory to the total number of reads using a query such as this one, which obtains this ratio as a percentage:

The result from this query should be similar to what is shown here, with one row for each data node in the cluster (in this example, the cluster has 4 data nodes):

hit_ratio values approaching 100% indicate that only a very small number of reads are being made from disk rather than from the buffer, which means that Disk Data read performance is approaching an optimum level. If any of these values are less than 95%, this is a strong indicator that the setting for <code>DiskPageBufferMemory</code> needs to be increased in the <code>config.ini</code> file.

Note

A change in DiskPageBufferMemory requires a rolling restart of all of the cluster's data nodes before it takes ef-

fect.

5.9.5. The ndbinfo logbuffers Table

The logbuffer table provides information on MySQL Cluster log buffer usage.

The following table provides information about the columns in the logbuffers table. For each column, the table shows the name, data type, and a brief description.

Column Name	Туре	Remarks
node_id	integer	The ID of this data node.
log_type	string	Type of log; one of: REDO or DD-UNDO.
log_id	integer	The log ID.
log_part	integer	The log part number.
total	integer	Total space available for this log.
used	integer	Space used by this log.

5.9.6. The ndbinfo logspaces Table

This table provides information about MySQL Cluster log space usage.

The following table provides information about the columns in the logspaces table. For each column, the table shows the name, data type, and a brief description.

Column Name	Туре	Remarks
node_id	integer	The ID of this data node.
log_type	string	Type of log; one of: REDO or DD-UNDO.
log_id	integer	The log ID.
log_part	integer	The log part number.
total	integer	Total space available for this log.
used	integer	Space used by this log.

5.9.7. The ndbinfo memoryusage Table

Querying this table provides information similar to that provided by the ALL REPORT MemoryUsage command in the ndb_mgm client, or logged by ALL DUMP 1000.

The following table provides information about the columns in the memoryusage table in MySQL Cluster NDB 7.1.3 and later. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
node_id	integer	The node ID of this data node.
memory_type	string	One of DATA_MEMORY or INDEX_MEMORY.
used	integer	Number of bytes currently used for data memory or index memory by this data node.
used_pages	integer	Number of pages currently used for data memory or index memory by this data node; see text.
total	integer	Total number of bytes of data memory or index memory available for this data node; see text.
total_pages	integer	Total number of memory pages available for data memory or index memory on this data node; see text.

The total column represents the total amount of memory in bytes available for the given resource (data memory or index memory) on a particular data node. This number should be approximately equal to the setting of the corresponding configuration parameter in the config.ini file.

Suppose that the cluster has 2 data nodes having node IDs 1 and 2, and the config.ini file contains the following:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
```

The following query shows approximately the same values:

In this case, the total column values for index memory are slightly higher than the value set of IndexMemory due to internal rounding.

For the used_pages and total_pages columns, resources are measured in pages, which are 32K in size for DataMemory and 8K for IndexMemory.

MySQL Cluster NDB 7.1.2 and earlier. The the remainder of this section provides information about the memoryusage table as implemented prior to MySQL Cluster NDB 7.1.3. (If you are using MySQL Cluster NDB 7.1.3 or later, refer to the beginning of this section.) For each column, the table shown here provides the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
node_id	integer	The node ID of this data node.
memory_type	string	One of DATA_MEMORY or INDEX_MEMORY
used	integer	Number of memory pages used; see text.
max	integer	Total number of memory pages available; see text.

For the used and max columns, resources are measured in pages, which (in MySQL Cluster NDB 7.1.2 and earlier) are 16K in size for DataMemory and 8K for IndexMemory. This example shows how to use this information in obtaining totals for DataMemory, IndexMemory, or both, which you can do by summing across data nodes and table columns, like this:

(We use DIV rather than / in both queries so that the results in all of the output columns are integers.)

 $Prior\ to\ MySQL\ Cluster\ NDB\ 7.1.2,\ the\ {\tt memory_type}\ column\ was\ named\ {\tt DATA_MEMORY}.\ (Bug\ {\tt\#50926})$

5.9.8. The ndbinfo nodes Table

This table contains information on the status of data nodes. For each data node that is running in the cluster, a corresponding row in this table provides the node's node ID, status, and uptime. For nodes that are starting, it also shows the current start phase.

The following table provides information about the columns in the nodes table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
node_id	integer	The data node's unique node ID in the cluster.
uptime	integer	Time since the node was last started, in seconds.
status	string	Current status of the data node; see text for possible values.
start_phase	integer	If the data node is starting, the current start phase.
config_generation	integer	The version of the cluster configuration file in use on this data node.

The uptime column shows the time in seconds that this node has been running since it was last started or restarted. This is a BIGINT value. This figure includes the time actually needed to start the node; in other words, this counter starts running the moment that ndbd or ndbmtd is first invoked; thus, even for a node that has not yet finished starting, uptime may show a non-zero value.

The status column shows the node's current status. This is one of: NOTHING, CMVMI, STARTING, STARTED, SINGLEUSER, STOPPING_1, STOPPING_2, STOPPING_3, or STOPPING_4. When the status is STARTING, you can see the current start phase in the start_phase column (see later in this section). SINGLEUSER is displayed in the status column for all data nodes when the cluster is in single user mode (see Section 5.7, "MySQL Cluster Single User Mode"). Seeing one of the STOPPING states does not necessarily mean that the node is shutting down but can mean rather that it is entering a new state; for example, if you put the cluster in single user mode, you can sometimes see data nodes report their state briefly as STOPPING_2 before the status changes to SINGLEUSER.

The start_phase column uses the same range of values as those used in the output of the ndb_mgm client node_id STATUS command (see Section 5.2, "Commands in the MySQL Cluster Management Client"). If the node is not currently starting, then this column shows 0. For a listing of MySQL Cluster start phases with descriptions, see Section 5.1, "Summary of MySQL Cluster Start Phases".

The config_generation column was added in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13. This column shows which version of the cluster configuration is in effect on each data node. This can be useful when performing a rolling restart of the cluster in order to make changes in configuration parameters. For example, from the output of the following SELECT statement, you can see that node 3 is not yet using the latest version of the cluster configuration (6) although nodes 1, 2, and 4 are doing so:

mysql> USE Database cl mysql> SELI	hanged	I nodes;		
node_id	uptime	status	start_phase	config_generation
1 2 3 4 +2 2 rows in (10462 10460 10457 10455 +set (0.04	STARTED STARTED STARTED STARTED sec)	0 0 0 0	6 6 5 6

Therefore, for the case just shown, you should restart node 3 to complete the rolling restart of the cluster.

Note

When upgrading to MySQL Cluster NDB 7.0.24 or MySQL Cluster NDB 7.1.13 from a previous version of MySQL Cluster, you should run mysql_upgrade on all MySQL Servers that should connect to the cluster, in order to enable support for the new config_generation column. Otherwise, when you attempt to access this table, you get the warning Table 'ndb\$nodes' is defined differently in NDB, there are more columns available...

Nodes that are stopped are not accounted for in this table. Suppose that you have a MySQL Cluster with 4 data nodes (node IDs 1, 2, 3 and 4), and all nodes are running normally, then this table contains 4 rows, 1 for each data node:

```
mysql> USE ndbinfo;
Database changed
mysql> SELECT * FROM nodes;
+-----+
| node_id | uptime | status | start_phase | config_generation |
+------+
```

```
1 | 11776 | STARTED | 0 | 6 |
2 | 11774 | STARTED | 0 | 6 |
3 | 11771 | STARTED | 0 | 6 |
4 | 11769 | STARTED | 0 | 6 |

4 rows in set (0.04 sec)
```

If you shut down one of the nodes, only the nodes that are still running are represented in the output of this SELECT statement, as shown here:

```
ndb_mgm> 2 STOP
Node 2: Node shutdown initiated
Node 2: Node shutdown completed.
Node 2 has shutdown.
```

	ysql> SELECT * FROM nodes;				
node_id	uptime			config_generation	
1 3 4	11807 11802 11800	STARTED STARTED STARTED	0 0 0	6 6 6	
3 rows in s					

5.9.9. The ndbinfo pools Table

Important

This table was part of the original ndbinfo implementation, but was later removed (in MySQL Cluster NDB 7.1.3). The information in this section is now obsolete, and subject to removal in a future version of the documentation.

The pools table was originally intended to provide information about NDB memory pool usage, but was later removed.

For each column, this table shows the name, data type, and a brief description of each ndbinfo.pools column (as it appeared prior to MySQL Cluster NDB 7.1.3). Additional information can be found in the notes afterward.

Column Name	Туре	Remarks
node_id	integer	The data node's node ID.
block_name	string	Name of the NDB kernel block using this pool.
block_instance	integer	Kernel block instance ID.
pool_name	string	The name of the pool.
used	integer	Amount of the pool in use.
total	integer	Total size of the pool.
high	integer	The maximum used from this pool (since the node was last started).
entry_size	integer	The size of each object, in bytes.
param_name1	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name2	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name3	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name4	string	Name of a configuration parameter associated with this pool (or NULL); see text.

The columns param_name1, param_name2, param_name3, and param_name4 contain names of configuration parameters that are associated with a given pool. If no parameters are associated with the pool, then all 4 of these columns are NULL. For pools that are associated with configuration parameters, these columns are not filled with non-NULL values in any particular order, as shown in this example:

You can use a query such as the one shown here to generate a table showing the associations of pools, NDB kernel blocks, and (where applicable) configuration parameters:

You may also find the following stored procedure useful. It returns a list of pools associated with a given configuration parameter, along with the kernel blocks to which these pools belong. You can see here the statement used to create this stored procedure along with sample output for some typical parameters:

```
mysql> DELIMITER |
mysql> CREATE PROCEDURE get_pools (p VARCHAR(50))
-> BEGIN
     ->
             SELECT
                  DISTINCT(pool_name) as Pool,
             block_name as Block FROM ndbinfo.pools
     ->
             WHERE p
IN (param_name1, param_name2, param_name3, param_name4)
     ->
             ORDER BY Pool;
     -> END
Query OK, 0 rows affected (0.02 sec)
mysql > DELIMITER ;
mysql> CALL get_pools('MaxNoOfTables');
  pool name
                       block name
  Table Record
DictObject
                        DBDICT
                        DBDICT
  Index
Table
                        DBTC
BACKUP
  Trigger
                        BACKUP
                        BACKUP
  Fragment
  Subscriber
                        SUMA
                        SUMA
  Table
  Subscription
                        SUMA
  Index
                        DBTUX
  Descriptor page
                        DBTUX
11 rows in set (0.30 sec)
Query OK, 0 rows affected (0.30 sec)
mysql> CALL get_pools('MaxNoOfOrderedIndexes');
  pool_name
                        block_name
  DictObject
                        DBDICT
                        DBTC
BACKUP
  Index
  Table
  Trigger
                        BACKUP
                        BACKUP
  Fragment
  Index
                        DBTUX
  Fragment
                        DBTUX
  Descriptor page
                        DBTUX
8 rows in set (0.29 sec)
```

5.9.10. The ndbinfo resources Table

This table provides information about data node resource availability and usage.

These resources are sometimes known as super-pools.

The following table provides information about the columns in the resources table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Type	Remarks
node_id	integer	The unique node ID of this data node.
resource_name	string	Name of the resource; see text.
reserved	integer	The amount reserved for this resource.
used	integer	The amount actually used by this resource.
max	integer	The maximum amount of this resource used, since the node was last started.

The resource_name can be one of RESERVED, DISK_OPERATIONS, DISK_RECORDS, DATA_MEMORY, JOBBUFFER, FILE_BUFFERS, or TRANSPORTER_BUFFERS.

5.9.11. The ndbinfo transporters Table

This table contains information about NDB transporters.

The following table provides information about the columns in the transporters table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Remarks
node_id	integer	This data node's unique node ID in the cluster.
remote_node_id	integer	The remote data node's node ID.
status	string	Status of the connection.

For each running data node in the cluster, the transporters table displays a row showing the status of each of that node's connections with all nodes in the cluster, *including itself*. This information is shown in the table's *status* column, which can have any one of the following values: CONNECTING, CONNECTED, DISCONNECTING, or DISCONNECTED.

Connections to API and management nodes which are configured but not currently connected to the cluster are shown with status DISCONNECTED. Rows where the node_id is that of a data nodes which is not currently connected are not shown in this table. (This is similar omission of disconnected nodes in the ndbinfo.nodes table.

Assume you have a 5-node cluster conisting of 2 data nodes, 2 SQL nodes, and 1 management node, as shown in the output of the SHOW command in the ndb_mgm client:

There are 10 rows in the transporters table—5 for the first data node, and 5 for the second—assuming that all data nodes are running, as shown here:

```
mysql> SELECT * FROM transporters;
  node id
            remote node id
                               status
                               CONNECTED
                               CONNECTED
        1
                          10
                               CONNECTED
                          20
                               CONNECTED
        1
                          2.1
                               CONNECTED
                               CONNECTED
                           1 2
        2
                               CONNECTED
                          10
                               CONNECTED
                          2.0
                               CONNECTED
                               CONNECTED
10 rows in set (0.04 sec)
```

If you shut down one of the data nodes in this cluster using the ndb_mgm client STOP command, then repeat the query, this table now shows only 5 rows—1 row for each connection from the remaining data node to another node, including both itself and the data node that is currently offline, as shown here:

	remote_node_id status
1	1 CONNECTEI
1	2 CONNECTEI
1	10 CONNECTEI
1	20 CONNECTEI
1	21 CONNECTEI

5.10. MySQL Cluster Security Issues

This section discusses security considerations to take into account when setting up and running MySQL Cluster.

Topics covered in this section include the following:

- MySQL Cluster and network security issues
- · Configuration issues relating to running MySQL Cluster securely
- MySQL Cluster and the MySQL privilege system
- · MySQL standard security procedures as applicable to MySQL Cluster

5.10.1. MySQL Cluster Security and Networking Issues

In this section, we discuss basic network security issues as they relate to MySQL Cluster. It is extremely important to remember that MySQL Cluster "out of the box" is not secure; you or your network administrator must take the proper steps to ensure that your cluster cannot be compromised over the network.

Cluster communication protocols are inherently insecure, and no encryption or similar security measures are used in communications between nodes in the cluster. Because network speed and latency have a direct impact on the cluster's efficiency, it is also not advisable to employ SSL or other encryption to network connections between nodes, as such schemes will effectively slow communications.

It is also true that no authentication is used for controlling API node access to a MySQL Cluster. As with encryption, the overhead of imposing authentication requirements would have an adverse impact on Cluster performance.

In addition, there is no checking of the source IP address for either of the following when accessing the cluster:

• SQL or API nodes using "free slots" created by empty [mysqld] or [api] sections in the config.ini file

This means that, if there are any empty [mysqld] or [api] sections in the config.ini file, then any API nodes (including SQL nodes) that know the management server's host name (or IP address) and port can connect to the cluster and access its data without restriction. (See Section 5.10.2, "MySQL Cluster and MySQL Privileges", for more information about this and related issues.)

Note

You can exercise some control over SQL and API node access to the cluster by specifying a HostName parameter for all [mysqld] and [api] sections in the config.ini file. However, this also means that, should you wish to connect an API node to the cluster from a previously unused host, you need to add an [api] section containing its host name to the config.ini file.

More information is available elsewhere in this chapter about the HostName parameter. Also see Section 3.1, "Quick Test Setup of MySQL Cluster", for configuration examples using HostName with API nodes.


Any ndb_mgm client

This means that any cluster management client that is given the management server's host name (or IP address) and port (if not the standard port) can connect to the cluster and execute any management client command. This includes commands such as ALL_STOP and SHUTDOWN.

For these reasons, it is necessary to protect the cluster on the network level. The safest network configuration for Cluster is one which isolates connections between Cluster nodes from any other network communications. This can be accomplished by any of the following methods:

1. Keeping Cluster nodes on a network that is physically separate from any public networks. This option is the most dependable; however, it is the most expensive to implement.

We show an example of a MySQL Cluster setup using such a physically segregated network here:



This setup has two networks, one private (solid box) for the Cluster management servers and data nodes, and one public (dotted box) where the SQL nodes reside. (We show the management and data nodes connected using a gigabit switch since this provides the best performance.) Both networks are protected from the outside by a hardware firewall, sometimes also known as a *network-based firewall*.

This network setup is safest because no packets can reach the cluster's management or data nodes from outside the network—and none of the cluster's internal communications can reach the outside—without going through the SQL nodes, as long as the SQL nodes do not permit any packets to be forwarded. This means, of course, that all SQL nodes must be secured against hacking attempts.


Important

With regard to potential security vulnerabilities, an SQL node is no different from any other MySQL server. See Making MySQL Secure Against Attackers, for a description of techniques you can use to secure MySQL servers.

2. Using one or more software firewalls (also known as *host-based firewalls*) to control which packets pass through to the cluster from portions of the network that do not require access to it. In this type of setup, a software firewall must be installed on every host in the cluster which might otherwise be accessible from outside the local network.

The host-based option is the least expensive to implement, but relies purely on software to provide protection and so is the most difficult to keep secure.

This type of network setup for MySQL Cluster is illustrated here:



Using this type of network setup means that there are two zones of MySQL Cluster hosts. Each cluster host must be able to communicate with all of the other machines in the cluster, but only those hosting SQL nodes (dotted box) can be permitted to have any contact with the outside, while those in the zone containing the data nodes and management nodes (solid box) must be isolated from any machines that are not part of the cluster. Applications using the cluster and user of those applications must *not* be permitted to have direct access to the management and data node hosts.

To accomplish this, you must set up software firewalls that limit the traffic to the type or types shown in the following table, according to the type of node that is running on each cluster host computer:

Type of Node to be Accessed	Traffic to Permit	
SQL or API node	 It originates from the IP address of a management or data node (using any TCP or UDP port). It originates from within the network in which the cluster resides and is on the port that your application is using. 	
Data node or Management node	 It originates from the IP address of a management or data node (using any TCP or UDP port). It originates from the IP address of an SQL or API node. 	


Any traffic other than that shown in the table for a given node type should be denied.

The specifics of configuring a firewall vary from firewall application to firewall application, and are beyond the scope of this Manual. iptables is a very common and reliable firewall application, which is often used with APF as a front end to make configuration easier. You can (and should) consult the documentation for the software firewall that you employ, should you

choose to implement a MySQL Cluster network setup of this type, or of a "mixed" type as discussed under the next item.

3. It is also possible to employ a combination of the first two methods, using both hardware and software to secure the cluster—that is, using both network-based and host-based firewalls. This is between the first two schemes in terms of both security level and cost. This type of network setup keeps the cluster behind the hardware firewall, but permits incoming packets to travel beyond the router connecting all cluster hosts to reach the SQL nodes.

One possible network deployment of a MySQL Cluster using hardware and software firewalls in combination is shown here:



In this case, you can set the rules in the hardware firewall to deny any external traffic except to SQL nodes and API nodes, and then permit traffic to them only on the ports required by your application.

Whatever network configuration you use, remember that your objective from the viewpoint of keeping the cluster secure remains the same—to prevent any unessential traffic from reaching the cluster while ensuring the most efficient communication between the nodes in the cluster.

Because MySQL Cluster requires large numbers of ports to be open for communications between nodes, the recommended option is to use a segregated network. This represents the simplest way to prevent unwanted traffic from reaching the cluster.

Note

If you wish to administer a MySQL Cluster remotely (that is, from outside the local network), the recommended way to do this is to use ssh or another secure login shell to access an SQL node host. From this host, you can then run the management client to access the management server safely, from within the Cluster's own local network.

Even though it is possible to do so in theory, it is *not* recommended to use ndb_mgm to manage a Cluster directly from outside the local network on which the Cluster is running. Since neither authentication nor encryption takes place between the management client and the management server, this represents an extremely insecure means of managing the cluster, and is almost certain to be compromised sooner or later.

5.10.2. MySQL Cluster and MySQL Privileges

In this section, we discuss how the MySQL privilege system works in relation to MySQL Cluster and the implications of this for keeping a MySQL Cluster secure.

Standard MySQL privileges apply to MySQL Cluster tables. This includes all MySQL privilege types (SELECT privilege, UPDATE privilege, DELETE privilege, and so on) granted on the database, table, and column level. As with any other MySQL Server, user and privilege information is stored in the mysql system database. The SQL statements used to grant and revoke privileges on NDB tables, databases containing such tables, and columns within such tables are identical in all respects with the GRANT and REVOKE statements used in connection with database objects involving any (other) MySQL storage engine. The same thing is true with respect to the CREATE USER and DROP USER statements.

It is important to keep in mind that, by default, the MySQL grant tables use the MyISAM storage engine. Because of this, those tables are not duplicated or shared among MySQL servers acting as SQL nodes in a MySQL Cluster. By way of example, suppose that two SQL nodes A and B are connected to the same MySQL Cluster, which has an NDB table named mytable in a database named mydb, and that you execute an SQL statement on server A that creates a new user jon@localhost and grants this user the SELECT privilege on that table:

```
mysql> GRANT SELECT ON mydb.mytable
-> TO jon@localhost IDENTIFIED BY 'mypass';
```

This user is *not* created on server **B**. For this to take place, the statement must also be run on server **B**. Similarly, statements run on server **A** and affecting the privileges of existing users on server **A** do not affect users on server **B** unless those statements are actually run on server **B** as well.

In other words, *changes in users and their privileges do not automatically propagate between SQL nodes by default.* Prior to MySQL Cluster NDB 7.2, any synchronization of privileges between SQL nodes must be done either manually or by scripting an application that periodically synchronizes the privilege tables on all SQL nodes in the cluster. In MySQL Cluster NDB 7.2 and later, you can enable automatic distribution of MySQL users and privileges across MySQL Cluster SQL nodes; see Section 5.13, "Distributed MySQL Privileges for MySQL Cluster", for details.

Conversely, because there is no way in MySQL to deny privileges (privileges can either be revoked or not granted in the first place, but not denied as such), there is no special protection for NDB tables on one SQL node from users that have privileges on another SQL node. (This is true even if you are not using the automatic distribution of user priveleges available in MySQl Cluster NDB 7.2 and later.) The most far-reaching example of this is the MySQL root account, which can perform any action on any database object. In combination with empty [mysqld] or [api] sections of the config.ini file, this account can be especially dangerous. To understand why, consider the following scenario:

- The config.ini file contains at least one empty [mysqld] or [api] section. This means that the MySQL Cluster management server performs no checking of the host from which a MySQL Server (or other API node) accesses the MySQL Cluster.
- There is no firewall, or the firewall fails to protect against access to the MySQL Cluster from hosts external to the network.
- The host name or IP address of the MySQL Cluster's management server is known or can be determined from outside the network.

If these conditions are true, then anyone, anywhere can start a MySQL Server with --ndbcluster - -ndb-connectstring=management_host and access the MySQL Cluster. Using the MySQL root account, this person can then perform the following actions:

- Execute a SHOW DATABASES statement to obtain a list of all NDB databases
- Execute a SHOW TABLES FROM some_database statement to obtain a list of all NDB tables in a given database
- Run any legal MySQL statements on any of those tables, such as:
 - SELECT * FROM some_table to read all the data from any table
 - DELETE FROM some_table to delete all the data from a table
 - DESCRIBE some_table or SHOW CREATE TABLE some_table to determine the table schema
 - UPDATE some_table SET column1 = any_value1 to fill a table column with "garbage" data; this could actually cause much greater damage than simply deleting all the data

Even more insidious variations might include statements like these:

```
UPDATE some_table SET an_int_column = an_int_column + 1

or

UPDATE some_table SET a_varchar_column = REVERSE(a_varchar_column)
```

Such malicious statements are limited only by the imagination of the attacker.

The only tables that would be safe from this sort of mayhem would be those tables that were created using storage engines other than NDB, and so not visible to a "rogue" SQL node.

Note

A user who can log in as root can also access the INFORMATION_SCHEMA database and its tables, and so obtain information about databases, tables, stored routines, scheduled events, and any other database objects for which metadata is stored in INFORMATION_SCHEMA.

It is also a very good idea to use different passwords for the root accounts on different cluster SQL nodes (unless you are using distributed privileges as supported in MySQL Cluster NDB 7.2 and later).

In sum, you cannot have a safe MySQL Cluster if it is directly accessible from outside your local network.

Important

Never leave the MySQL root account password empty. This is just as true when running MySQL as a MySQL Cluster SQL node as it is when running it as a standalone (non-Cluster) MySQL Server, and should be done as part of the MySQL installation process before configuring the MySQL Server as an SQL node in a MySQL Cluster.

Prior to MySQL Cluster NDB 7.2, you should never convert the system tables in the mysql database to use the NDB storage engine. There are a number of reasons why you should not do this, but the most important reason is this: Many of the SQL statements that affect mysql tables storing information about user privileges, stored routines, scheduled events, and other database objects cease to function if these tables are changed to use any storage engine other than MyISAM. This is a consequence of various MySQL Server internals. Beginning with MySQL Cluster NDB 7.2, you can use a stored procedure provided for this purpose (see Section 5.13, "Distributed MySQL Privileges for MySQL Cluster"), but you are strongly advised not to attempt convert the system tables manually.

Otherwise, if you need to synchronize mysql system tables between SQL nodes, you can use standard MySQL replication to do so, or employ a script to copy table entries between the MySQL servers.

Summary. The two most important points to remember regarding the MySQL privilege system with regard to MySQL Cluster are:

- Prior to MySQL Cluster NDB 7.2. Users and privileges established on one SQL node do not automatically exist or take effect on other SQL nodes in the cluster. Conversely, removing a user or privilege on one SQL node in the cluster does not remove the user or privilege from any other SQL nodes.
 - In MySQL Cluster NDB 7.2 and later. You can cause MySQL users and privileges to be distributed automatically among SQL nodes using the SQL script, and the stored procedures which it contains, that are supplied for this purpose.
- 2. Once a MySQL user is granted privileges on an NDB table from one SQL node in a MySQL Cluster, that user can "see" any data in that table regardless of the SQL node from which the data originated. (This is true even if you are not using the privilege distribution support available in MySQl Cluster NDB 7.2 or later.)

5.10.3. MySQL Cluster and MySQL Security Procedures

In this section, we discuss MySQL standard security procedures as they apply to running MySQL Cluster.

In general, any standard procedure for running MySQL securely also applies to running a MySQL Server as part of a MySQL Cluster. First and foremost, you should always run a MySQL Server as the mysql system user; this is no different from running MySQL in a standard (non-Cluster) environment. The mysql system account should be uniquely and clearly defined. Fortunately, this is the default behavior for a new MySQL installation. You can verify that the mysqld process is running as the system user mysql by using the system command such as the one shown here:

If the mysqld process is running as any other user than mysql, you should immediately shut it down and restart it as the mysql user. If this user does not exist on the system, the mysql user account should be created, and this user should be part of the mysql user group; in this case, you should also make sure that the MySQL data directory on this system (as set using the --datadir option for mysqld) is owned by the mysql user, and that the SQL node's my.cnf file includes user=mysql in the [mysqld] section. Alternatively, you can start the MySQL server process with --user=mysql on the command line, but it is preferable to use the my.cnf option, since you might forget to use the command-line option and so have mysqld running as another user unintentionally. The mysqld_safe startup script forces MySQL to run as the mysql user.

Important

Never run mysqld as the system root user. Doing so means that potentially any file on the system can be read by MySQL, and thus—should MySQL be compromised—by an attacker.

As mentioned in the previous section (see Section 5.10.2, "MySQL Cluster and MySQL Privileges"), you should always set a root password for the MySQL Server as soon as you have it running. You should also delete the anonymous user account that is installed by default. You can accomplish these tasks using the following statements:

Be very careful when executing the DELETE statement not to omit the WHERE clause, or you risk deleting *all* MySQL users. Be sure to run the FLUSH PRIVILEGES statement as soon as you have modified the mysql.user table, so that the changes take immediate effect. Without FLUSH PRIVILEGES, the changes do not take effect until the next time that the server is restarted.

Note

Many of the MySQL Cluster utilities such as ndb_show_tables, ndb_desc, and ndb_select_all also work without authentication and can reveal table names, schemas, and data. By default these are installed on Unix-style systems with the permissions wxr-xr-x (755), which means they can be executed by any user that can access the mysql/bin directory.

See Chapter 4, MySQL Cluster Programs, for more information about these utilities.

5.11. MySQL Cluster Disk Data Tables

Beginning with MySQL 5.1.6, it is possible to store the nonindexed columns of NDB tables on disk, rather than in RAM as with previous versions of MySQL Cluster.

As part of implementing MySQL Cluster Disk Data work, a number of improvements were made in MySQL Cluster for the efficient handling of very large amounts (terabytes) of data during node recovery and restart. These include a "no-steal" algorithm for synchronising a starting node with very large data sets. For more information, see the paper *Recovery Principles of MySQL Cluster 5.1*, by MySQL Cluster developers Mikael Ronström and Jonas Oreland.

MySQL Cluster Disk Data performance can be influenced by a number of configuration parameters. For information about these parameters and their effects, see MySQL Cluster Disk Data configuration parameters and MySQL Cluster Disk Data storage and GCP_STOP errors

The performance of a MySQL Cluster that uses Disk Data storage can also be greatly improved by separating data node file systems from undo log files and tablespace data files, which can be done using symbolic links. For more information, see Section 5.11.2, "Using Symbolic Links with Disk Data Objects".

5.11.1. MySQL Cluster Disk Data Objects

MySQL Cluster Disk Data storage is implemented using a number of Disk Data objects. These include the following:

- Tablespaces act as containers for other Disk Data objects.
- Undo log files undo information required for rolling back transactions.
- One or more undo log files are assigned to a *log file group*, which is then assigned to a tablespace.
- Data files store Disk Data table data. A data file is assigned directly to a tablespace.

Undo log files and data files are actual files in the file system of each data node; by default they are placed in ndb_node_id_fs

in the <code>DataDir</code> specified in the MySQL Cluster <code>config.ini</code> file, and where <code>node_id</code> is the data node's node ID. It is possible to place these elsewhere by specifying either an absolute or relative path as part of the filename when creating the undo log or data file. Statements that create these files are shown later in this section.

MySQL Cluster tablespaces and log file groups are not implemented as files.

Important

Although not all Disk Data objects are implemented as files, they all share the same namespace. This means that *each Disk Data object* must be uniquely named (and not merely each Disk Data object of a given type). For example, you cannot have a tablespace and a log file group both named dd1.

Assuming that you have already set up a MySQL Cluster with all nodes (including management and SQL nodes) running MySQL 5.1.6 or newer, the basic steps for creating a Cluster table on disk are as follows:

1. Create a log file group, and assign one or more undo log files to it (an undo log file is also sometimes referred to as an *undofile*).

Note

In MySQL 5.1 and later, undo log files are necessary only for Disk Data tables. They are no longer used for NDB-CLUSTER tables that are stored only in memory.

- 2. Create a tablespace; assign the log file group, as well as one or more data files, to the tablespace.
- Create a Disk Data table that uses this tablespace for data storage.

Each of these tasks can be accomplished using SQL statements in the mysql client or other MySQL client application, as shown in the example that follows.

1. We create a log file group named lg_1 using CREATE LOGFILE GROUP. This log file group is to be made up of two undo log files, which we name undo_1.log and undo_2.log, whose initial sizes are 16 MB and 12 MB, respectively. (The default initial size for an undo log file is 128 MB.) Optionally, you can also specify a size for the log file group's undo buffer, or permit it to assume the default value of 8 MB. In this example, we set the UNDO buffer's size at 2 MB. A log file group must be created with an undo log file; so we add undo_1.log to lg_1 in this CREATE LOGFILE GROUP statement:

```
CREATE LOGFILE GROUP 1g_1
ADD UNDOFILE 'undo_1.log'
INITIAL_SIZE 16M
UNDO_BUFFER_SIZE 2M
ENGINE NDBCLUSTER;
```

To add undo_2.log to the log file group, use the following ALTER LOGFILE GROUP statement:

```
ALTER LOGFILE GROUP 1g_1
ADD UNDOFILE 'undo_2.log'
INITIAL_SIZE 12M
ENGINE NDBCLUSTER;
```

Some items of note:

- The .log file extension used here is not required. We use it merely to make the log files easily recognisable.
- Every CREATE LOGFILE GROUP and ALTER LOGFILE GROUP statement must include an ENGINE clause. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the permitted values for this clause are NDB-CLUSTER and NDB.

Important

In MySQL 5.1.8 and later, there can exist only one log file group in the same MySQL Cluster at any given time.

- When you add an undo log file to a log file group using ADD UNDOFILE 'filename', a file with the name filename is created in the ndb_node_id_fs directory within the DataDir of each data node in the cluster, where node_id is the node ID of the data node. Each undo log file is of the size specified in the SQL statement. For example, if a MySQL Cluster has 4 data nodes, then the ALTER LOGFILE GROUP statement just shown creates 4 undo log files, 1 each on in the data directory of each of the 4 data nodes; each of these files is named undo_2.log and each file is 12 MB in size.
- UNDO_BUFFER_SIZE is limited by the amount of system memory available.

- For more information about the CREATE LOGFILE GROUP statement, see CREATE LOGFILE GROUP Syntax. For
 more information about ALTER LOGFILE GROUP, see ALTER LOGFILE GROUP Syntax.
- 2. Now we can create a tablespace, which contains files to be used by MySQL Cluster Disk Data tables for storing their data. A tablespace is also associated with a particular log file group. When creating a new tablespace, you must specify the log file group which it is to use for undo logging; you must also specify a data file. You can add more data files to the tablespace after the tablespace is created; it is also possible to drop data files from a tablespace (an example of dropping data files is provided later in this section).

Assume that we wish to create a tablespace named ts_1 which uses lg_1 as its log file group. This tablespace is to contain two data files named data_1.dat and data_2.dat, whose initial sizes are 32 MB and 48 MB, respectively. (The default value for INITIAL_SIZE is 128 MB.) We can do this using two SQL statements, as shown here:

```
CREATE TABLESPACE ts_1

ADD DATAFILE 'data_1.dat'

USE LOGFILE GROUP lg_1

INITIAL_SIZE 32M

ENGINE NDBCLUSTER;

ALTER TABLESPACE ts_1

ADD DATAFILE 'data_2.dat'

INITIAL_SIZE 48M

ENGINE NDBCLUSTER;
```

The CREATE TABLESPACE statement creates a tablespace ts_1 with the data file data_1.dat, and associates ts_1 with log file group lg_1. The ALTER TABLESPACE adds the second data file (data_2.dat).

Some items of note:

- As is the case with the .log file extension used in this example for undo log files, there is no special significance for the .dat file extension; it is used merely for easy recognition of data files.
- When you add a data file to a tablespace using ADD DATAFILE 'filename', a file with the name filename is created in the ndb_node_id_fs directory within the DataDir of each data node in the cluster, where node_id is the node ID of the data node. Each undo log file is of the size specified in the SQL statement. For example, if a MySQL Cluster has 4 data nodes, then the ALTER TABLESPACE statement just shown creates 4 undo log files, 1 each on in the data directory of each of the 4 data nodes; each of these files is named data_2.dat and each file is 48 MB in size.
- All CREATE TABLESPACE and ALTER TABLESPACE statements must contain an ENGINE clause; only tables using the same storage engine as the tablespace can be created in the tablespace. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the only permitted values for this clause are NDBCLUSTER and NDB.
- For more information about the CREATE TABLESPACE and ALTER TABLESPACE statements, see CREATE TABLESPACE Syntax, and ALTER TABLESPACE Syntax.
- 3. Now it is possible to create a table whose nonindexed columns are stored on disk in the tablespace ts_1:

```
CREATE TABLE dt_1 (
    member_id INT UNSIGNED NOT NULL AUTO_INCREMENT PRIMARY KEY,
    last_name VARCHAR(50) NOT NULL,
    first_name VARCHAR(50) NOT NULL,
    dob DATE NOT NULL,
    joined DATE NOT NULL,
    INDEX(last_name, first_name)
    )
    TABLESPACE ts_1 STORAGE DISK
    ENGINE NDBCLUSTER;
```

The TABLESPACE ... STORAGE DISK option tells the NDBCLUSTER storage engine to use tablespace ts_1 for disk data storage.

Note

Beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2, it is also possible to specify whether an individual column is stored on disk or in memory by using a STORAGE clause as part of the column's definition in a CREATE TABLE or ALTER TABLE statement. STORAGE DISK causes the column to be stored on disk, and STORAGE MEMORY causes in-memory storage to be used. See CREATE TABLE Syntax, for more information.

Once table ts_1 has been created as shown, you can perform INSERT, SELECT, UPDATE, and DELETE statements on it just as you would with any other MySQL table.

For table dt_1 as it has been defined here, only the dob and joined columns are stored on disk. This is because there are indexes on the id, last_name, and first_name columns, and so data belonging to these columns is stored in RAM. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), only nonindexed columns can be held on disk; in-

dexes and indexed column data continue to be stored in memory. This tradeoff between the use of indexes and conservation of RAM is something you must keep in mind as you design Disk Data tables.

Performance note. The performance of a cluster using Disk Data storage is greatly improved if Disk Data files are kept on a separate physical disk from the data node file system. This must be done for each data node in the cluster to derive any noticeable benefit

You may use absolute and relative file system paths with ADD UNDOFILE and ADD DATAFILE. Relative paths are calculated relative to the data node's data directory. You may also use symbolic links; see Section 5.11.2, "Using Symbolic Links with Disk Data Objects", for more information and examples.

A log file group, a tablespace, and any Disk Data tables using these must be created in a particular order. The same is true for dropping any of these objects:

- · A log file group cannot be dropped as long as any tablespaces are using it.
- A tablespace cannot be dropped as long as it contains any data files.
- You cannot drop any data files from a tablespace as long as there remain any tables which are using the tablespace.
- Beginning with MySQL 5.1.12, it is no longer possible to drop files created in association with a different tablespace than the
 one with which the files were created. (Bug #20053)

For example, to drop all the objects created so far in this section, you would use the following statements:

These statements must be performed in the order shown, except that the two ALTER TABLESPACE ... DROP DATAFILE statements may be executed in either order.

You can obtain information about data files used by Disk Data tables by querying the FILES table in the INFORMATION_SCHEMA database. An extra "NULL row" was added to this table in MySQL 5.1.14 for providing additional information about undo log files. For more information and examples of use, see The INFORMATION_SCHEMA FILES Table.

Beginning with MySQL Cluster NDB 6.3.27 and MySQL Cluster NDB 7.0.8, it is also possible to view information about allocated and free disk space for each Disk Data table or table partition using the ndb_desc utility. For more information, see Section 4.9, "ndb_desc — Describe NDB Tables".

5.11.2. Using Symbolic Links with Disk Data Objects

The performance of a MySQL Cluster that uses Disk Data storage can be greatly improved by separating data node file systems from undo log files and tablespace data files and placing these on different disks. Previous to MySQL Cluster NDB 6.2.17, MySQL Cluster NDB 6.3.22, and MySQL Cluster NDB 6.4.3, there was no direct support for this in MySQL Cluster, but it was possible to achieve this separation using symbolic links as described in this section.

Beginning with MySQL Cluster NDB 6.2.17, MySQL Cluster NDB 6.3.22, and MySQL Cluster NDB 6.4.3, the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles make the use of symbolic links for this purpose unnecessary. For information about these parameters, see Disk Data file system parameters.

Each data node in the cluster creates a file system in the directory named ndb_node_id_fs under the data node's DataDir as defined in the config.ini file. In this example, we assume that each data node host has 3 disks, aliased as /data0, /data1, and /data2, and that the cluster's config.ini includes the following:

```
[ndbd default]
DataDir= /data0
```

Our objective is to place all Disk Data log files in /data1, and all Disk Data data files in /data2, on each data node host.

Note

In this example, we assume that the cluster's data node hosts are all using Linux operating systems. For other platforms, you may need to substitute you operating system's commands for those shown here.

To accomplish this, perform the following steps:

• Under the data node file system create symbolic links pointing to the other drives:

```
shell> cd /data0/ndb_2_fs
shell> ls
D1 D10 D11 D2 D8 D9 LCP
shell> ln -s /data0 dnlogs
shell> ln -s /data1 dndata
```

You should now have two symbolic links:

We show this only for the data node with node ID 2; however, you must do this for each data node.

• Now, in the mysql client, create a log file group and tablespace using the symbolic links, as shown here:

```
mysql> CREATE LOGFILE GROUP lg1
   -> ADD UNDOFILE 'dnlogs/undo1.log'
   -> INITIAL_SIZE 150M
   -> UNDO_BUFFER_SIZE = 1M
   -> ENGINE=NDBCLUSTER;
mysql> CREATE TABLESPACE ts1
   -> ADD DATAFILE 'dndata/data1.log'
   -> USE LOGFILE GROUP lg1
   -> INITIAL_SIZE 1G
   -> ENGINE=NDBCLUSTER;
```

Verify that the files were created and placed correctly as shown here:

```
shell> cd /data1
shell> ls -1
total 2099304
-rw-rw-rr- 1 user group 157286400 2007-03-19 14:02 undol.dat
shell> cd /data2
shell> ls -1
total 2099304
-rw-rw-rr- 1 user group 1073741824 2007-03-19 14:02 data1.dat
```

• If you are running multiple data nodes on one host, you must take care to avoid having them try to use the same space for Disk Data files. You can make this easier by creating a symbolic link in each data node file system. Suppose you are using /data0 for both data node file systems, but you wish to have the Disk Data files for both nodes on /data1. In this case, you can do something similar to what is shown here:

```
shell> cd /data0
shell> ln -s /data1/dn2 ndb_2_fs/dd
shell> ln -s /data1/dn3 ndb_3_fs/dd
shell> ls -1 --hide=D* ndb_2_fs
lrwxrwxrwx 1 user group  30 2007-03-19 14:22 dd -> /data1/dn2
shell> ls -1 --hide=D* ndb_3_fs
lrwxrwxrwx 1 user group  30 2007-03-19 14:22 dd -> /data1/dn3
```

Now you can create a logfile group and tablespace using the symbolic link, like this:

```
mysql> CREATE LOGFILE GROUP lg1
-> ADD UNDOFILE 'dd/undo1.log'
-> INITIAL_SIZE 150M
-> UNDO_BUFFER_SIZE = 1M
-> ENGINE=NDBCLUSTER;
mysql> CREATE TABLESPACE ts1
-> ADD DATAFILE 'dd/data1.log'
-> USE LOGFILE GROUP lg1
-> INITIAL_SIZE 1G
-> ENGINE=NDBCLUSTER;
```

Verify that the files were created and placed correctly as shown here:

undo1.log data1.log

5.11.3. MySQL Cluster Disk Data Storage Requirements

The following items apply to Disk Data storage requirements:

• Variable-length columns of Disk Data tables take up a fixed amount of space. For each row, this is equal to the space required to store the largest possible value for that column.

For general information about calculating these values, see Data Type Storage Requirements.

You can obtain an estimate the amount of space available in data files and undo log files by querying the INFORMATION_SCHEMA.FILES table. For more information and examples, see The INFORMATION_SCHEMA FILES Table.

Note

The OPTIMIZE TABLE statement does not have any effect on Disk Data tables.

- In a Disk Data table, the first 256 bytes of a TEXT or BLOB column are stored in memory; only the remainder is stored on disk.
- Each row in a Disk Data table uses 8 bytes in memory to point to the data stored on disk. This means that, in some cases, converting an in-memory column to the disk-based format can actually result in greater memory usage. For example, convering a CHAR (4) column from memory-based to disk-based format increases the amount of DataMemory used per row from 4 to 8 bytes.

Important

Starting the cluster with the --initial option does *not* remove Disk Data files. You must remove these manually prior to performing an initial restart of the cluster.

Performance of Disk Data tables can be improved by minimizing the number of disk seeks by making sure that DiskPageBufferMemory is of sufficient size. You can query the diskpagebuffer table to help determine whether the value for this parameter needs to be increased.

5.12. Adding MySQL Cluster Data Nodes Online

This section describes how to add MySQL Cluster data nodes "online"—that is, without needing to shut down the cluster completely and restart it as part of the process. This capability is available in MySQL Cluster NDB 7.0 (beginning with MySQL Cluster NDB 6.4.0) and later MySQL Cluster release series.

Important

Currently, you must add new data nodes to a MySQL Cluster as part of a new node group. In addition, it is not possible to change the number of replicas (or the number of nodes per node group) online.

5.12.1. Adding MySQL Cluster Data Nodes Online: General Issues

This section provides general information about the behavior of and current limitations in adding MySQL Cluster nodes online.

Redistribution of Data. The ability to add new nodes online includes a means to reorganize NDBCLUSTER table data and indexes so that they are distributed across all data nodes, including the new ones. Table reorganization of both in-memory and Disk Data tables is supported. This redistribution does not currently include unique indexes (only ordered indexes are redistributed) or BLOB table data.

The redistribution for NDBCLUSTER tables already existing before the new data nodes were added is not automatic, but can be accomplished using simple SQL statements in mysql or another MySQL client application. However, all data and indexes added to tables created after a new node group has been added are distributed automatically among all cluster data nodes, including those added as part of the new node group.

Partial starts. It is possible to add a new node group without all of the new data nodes being started. It is also possible to add a new node group to a degraded cluster—that is, a cluster that is only partially started, or where one or more data nodes are not running. In the latter case, the cluster must have enough nodes running to be viable before the new node group can be added.

Effects on ongoing operations. Normal DML operations using MySQL Cluster data are not prevented by the creation or addition of a new node group, or by table reorganization. However, it is not possible to perform DDL concurrently with table reorganization.

tion—that is, no other DDL statements can be issued while an ALTER TABLE ... REORGANIZE PARTITION statement is executing. In addition, during the execution of ALTER TABLE ... REORGANIZE PARTITION (or the execution of any other DDL statement), it is not possible to restart cluster data nodes.

Failure handling. Failures of data nodes during node group creation and table reorganization are handled as hown in the following table:

Failure occurs during:	Failure occurs in:		
	"Old" data nodes	"New" data nodes	System
Node group creation	 If a node other than the master fails: The creation of the node group is always rolled forward. If the master fails: If the internal commit point has been reached: The creation of the node group is rolled forward. If the internal commit point has not yet been reached. The creation of the node group is rolled back 	 If a node other than the master fails: The creation of the node group is always rolled forward. If the master fails: If the internal commit point has been reached: The creation of the node group is rolled forward. If the internal commit point has not yet been reached. The creation of the node group is rolled back 	 If the execution of CRE-ATE NODEGROUP has reached the internal commit point: When restarted, the cluster includes the new node group. Otherwise it without. If the execution of CRE-ATE NODEGROUP has not yet reached the internal commit point: When restarted, the cluster does not include the new node group.
Table reorganization	 If a node other than the master fails: The table reorganization is always rolled forward. If the master fails: If the internal commit point has been reached: The table reorganization is rolled forward. If the internal commit point has not yet been reached. The table reorganization is rolled back. 	 If a node other than the master fails: The table reorganization is always rolled forward. If the master fails: If the internal commit point has been reached: The table reorganization is rolled forward. If the internal commit point has not yet been reached. The table reorganization is rolled back. 	 If the execution of an ALTER ONLINE TABLE table REORGANIZE PARTITION statement has reached the internal commit point: When the cluster is restarted, the data and indexes belonging to table are distributed using the "new" data nodes. If the execution of an ALTER ONLINE TABLE table REORGANIZE PARTITION statement has not yet reached the internal commit point: When the cluster is restarted, the data and indexes belonging to table are distributed using only the "old" data nodes.

Dropping node groups. The ndb_mgm client supports a DROP NODEGROUP command, but it is possible to drop a node group only when no data nodes in the node group contain any data. Since there is currently no way to "empty" a specific data node or node group, this command works only the following two cases:

- 1. After issuing CREATE NODEGROUP in the ndb_mgm client, but before issuing any ALTER ONLINE TABLE ... RE-ORGANIZE PARTITION statements in the mysql client.
- 2. After dropping all NDBCLUSTER tables using DROP TABLE.

TRUNCATE TABLE does not work for this purpose because the data nodes continue to store the table definitions.

5.12.2. Adding MySQL Cluster Data Nodes Online: Basic procedure

In this section, we list the basic steps required to add new data nodes to a MySQL Cluster. For a detailed example, see Section 5.12.3, "Adding MySQL Cluster Data Nodes Online: Detailed Example".

Note

Beginning with MySQL Cluster NDB 7.0.4, this procedure applies whether you are using ndbd or ndbmtd binaries for the data node processes. Previously, this did not work with multi-threaded data nodes. (Bug #43108)

Assuming that you already have a running MySQL Cluster, adding data nodes online requires the following steps:

1. Edit the cluster configuration config.ini file, adding new [ndbd] sections corresponding to the nodes to be added. In the case where the cluster uses multiple management servers, these changes need to be made to all config.ini files used by the management servers.

You must be careful that node IDs for any new data nodes added in the config.ini file do not overlap node IDs used by existing nodes. In the event that you have API nodes using dynamically allocated node IDs and these IDs match node IDs that you want to use for new data nodes, it is possible to force any such API nodes to "migrate", as described later in this procedure.

2. Perform a rolling restart of all MySQL Cluster management servers.

Important

All management servers must be restarted with the --reload or --initial option to force the reading of the new configuration.

3. Perform a rolling restart of all existing MySQL Cluster data nodes. It is not necessary (or usually even desirable) to use --initial when restarting the existing data nodes.

If you are using API nodes with dynamically allocated IDs matching any node IDs that you wish to assign to new data nodes, you must restart all API nodes (including SQL nodes) before restarting any of the data nodes processes in this step. This causes any API nodes with node IDs that were previously not explicitly assigned to relinquish those node IDs and acquire new ones.

- 4. Perform a rolling restart of any SQL or API nodes connected to the MySQL Cluster.
- 5. Perform an initial start of the new data nodes.

Note

The new data nodes may be started in any order, and can also be started concurrently, as long as they are started after the rolling restarts of all existing nodes have been completed and before proceeding to the next step.

- Execute one or more CREATE NODEGROUP commands in the MySQL Cluster management client to create the new node group or node groups to which the new data nodes will belong.
- 7. Redistribute the cluster's data among all data nodes (including the new ones) by issuing an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client for each NDBCLUSTER table.

Note

This needs to be done only for tables already existing at the time the new node group is added. Data in tables created after the new node group is added is distributed automatically; however, data added to any given table tbl that existed before the new nodes were added is not distributed using the new nodes until that table has been reorganized using ALTER ONLINE TABLE tbl REORGANIZE PARTITION.

8. Reclaim the space freed on the "old" nodes by issuing, for each NDBCLUSTER table, an OPTIMIZE TABLE statement in the mysql client.

You can add all the nodes desired, then issue several CREATE NODEGROUP commands in succession to add the new node groups to the cluster. Prior to MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, when adding multiple new node groups to a MySQL Cluster, it was necessary to add only the nodes to be assigned to a given new node group, create that node group using CREATE NODEGROUP, then repeat this process for each new node group to be added to the cluster. (Bug #54497)

5.12.3. Adding MySQL Cluster Data Nodes Online: Detailed Example

In this section we provide a detailed example illustrating how to add new MySQL Cluster data nodes online, starting with a MySQL Cluster having 2 data nodes in a single node group and concluding with a cluster having 4 data nodes in 2 node groups.

Starting configuration. For purposes of illustration, we assume a minimal configuration, and that the cluster uses a configuration file containing only the following information:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NoOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
[ndbd]
Id = 1
HostName = 192.168.0.1
[ndbd]
Id = 2
HostName = 192.168.0.2
[mgm]
HostName = 192.168.0.10
Id = 10
[api]
Id=20
HostName = 192.168.0.20
[api]
Id=21
HostName = 192.168.0.21
```

Note

We have left a gap in the sequence between data node IDs and other nodes. This make it easier later to assign node IDs that are not already in use to data nodes which are newly added.

We also assume that you have already started the cluster using the appropriate command line or my.cnf options, and that running SHOW in the management client produces output similar to what is shown here:

Finally, we assume that the cluster contains a single NDBCLUSTER table created as shown here:

```
USE n;

CREATE TABLE ips (
   id BIGINT NOT NULL AUTO_INCREMENT PRIMARY KEY,
   country_code CHAR(2) NOT NULL,
   type CHAR(4) NOT NULL,
   ip_address varchar(15) NOT NULL,
   addresses BIGINT UNSIGNED DEFAULT NULL,
   date BIGINT UNSIGNED DEFAULT NULL
) ENGINE NDBCLUSTER;
```

The memory usage and related information shown later in this section was generated after inserting approximately 50000 rows into this table.

Note

In this example, we show the single-threaded ndbd being used for the data node processes. However—beginning with MySQL Cluster NDB 7.0.4—you can also apply this example, if you are using the multi-threaded ndbmtd by substituting ndbmtd for ndbd wherever it appears in the steps that follow. (Bug #43108)

Step 1: Update configuration file. Open the cluster global configuration file in a text editor and add [ndbd] sections corresponding to the 2 new data nodes. (We give these data nodes IDs 3 and 4, and assume that they are to be run on host machines at addresses 192.168.0.3 and 192.168.0.4, respectively.) After you have added the new sections, the contents of the config.ini file should look like what is shown here, where the additions to the file are shown in bold type:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NOOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
[ndbd]
Id = 1
```

```
HostName = 192.168.0.1 [ndbd]
Id = 2
HostName = 192.168.0.2 [ndbd]
Id = 3
HostName = 192.168.0.3 [ndbd]
Id = 4
HostName = 192.168.0.4 [mgm]
HostName = 192.168.0.10
Id = 10 [api]
Id=20
HostName = 192.168.0.20 [api]
HostName = 192.168.0.21
```

Once you have made the necessary changes, save the file.

Step 2: Restart the management server. Restarting the cluster management server requires that you issue separate commands to stop the management server and then to start it again, as follows:

1. Stop the management server using the management client STOP command, as shown here:

```
ndb_mgm> 10 STOP
Node 10 has shut down.
Disconnecting to allow Management Server to shutdown
shell>
```

2. Because shutting down the management server causes the management client to terminate, you must start the management server from the system shell. For simplicity, we assume that config.ini is in the same directory as the management server binary, but in practice, you must supply the correct path to the configuration file. You must also supply the -reload or -initial option so that the management server reads the new configuration from the file rather than its configuration cache. If your shell's current directory is also the same as the directory where the management server binary is located, then you can invoke the management server as shown here:

```
shell> ndb_mgmd -f config.ini --reload
2008-12-08 17:29:23 [MgmSrvr] INFO -- NDB Cluster Management Server. 5.1.56-ndb-7.1.16
2008-12-08 17:29:23 [MgmSrvr] INFO -- Reading cluster configuration from 'config.ini'
```

If you check the output of SHOW in the management client after restarting the ndb_mgm process, you should now see something like this:

Step 3: Perform a rolling restart of the existing data nodes. This step can be accomplished entirely within the cluster management client using the RESTART command, as shown here:

```
ndb_mgm> 1 RESTART

Node 1: Node shutdown initiated

Node 1: Node shutdown completed, restarting, no start.

Node 1: start initiated (version 7.1.16)

Node 1: Started (version 7.1.16)

Node 1: Started (version 7.1.16)

Node 1: Started (version 7.1.16)

Node 2: Node shutdown initiated

Node 2: Node shutdown completed, restarting, no start.

Node 2 is being restarted

Node 2: Start initiated (version 7.1.16)

Node 2: Started (version 7.1.16)
```

Important

After issuing each X RESTART command, wait until the management client reports Node X: Started (version ...) before proceeding any further.

Beginning with MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, you can verify that all existing data nodes were restarted using the updated configuration by checking the ndbinfo.nodes table in the mysql client.

Step 4: Perform a rolling restart of all cluster API nodes. Shut down and restart each MySQL server acting as an SQL node in the cluster using mysqladmin shutdown followed by mysqld_safe (or another startup script). This should be similar to what is shown here, where password is the MySQL root password for a given MySQL server instance:

```
shell> mysqladmin -uroot -ppassword shutdown
081208 20:19:56 mysqld_safe mysqld from pid file
/usr/local/mysql/var/tonfisk.pid ended
shell> mysqld_safe --ndbcluster --ndb-connectstring=192.168.0.10 &
081208 20:20:06 mysqld_safe Logging to '/usr/local/mysql/var/tonfisk.err'.
081208 20:20:06 mysqld_safe Starting mysqld daemon with databases
from /usr/local/mysql/var
```

Of course, the exact input and output depend on how and where MySQL is installed on the system, as well as which options you choose to start it (and whether or not some or all of these options are specified in a my.cnf file).

Step 5: Perform an initial start of the new data nodes. From a system shell on each of the hosts for the new data nodes, start the data nodes as shown here, using the --initial option:

```
shell> ndbd -c 192.168.0.10 --initial
```

Note

Unlike the case with restarting the existing data nodes, you can start the new data nodes concurrently; you do not need to wait for one to finish starting before starting the other.

Wait until both of the new data nodes have started before proceeding with the next step. Once the new data nodes have started, you can see in the output of the management client SHOW command that they do not yet belong to any node group (as indicated with bold type here):

Step 6: Create a new node group. You can do this by issuing a CREATE NODEGROUP command in the cluster management client. This command takes as its argument a comma-separated list of the node IDs of the data nodes to be included in the new node group, as shown here:

```
ndb_mgm> CREATE NODEGROUP 3,4
Nodegroup 1 created
```

By issuing SHOW again, you can verify that data nodes 3 and 4 have joined the new node group (again indicated in bold type):

Step 7: Redistribute cluster data. When a node group is created, existing data and indexes are not automatically distributed to the new node group's data nodes, as you can see by issuing the appropriate REPORT command in the management client:

```
ndb_mgm> ALL REPORT MEMORY
```

```
Node 1: Data usage is 5%(177 32K pages of total 3200)
Node 1: Index usage is 0%(108 8K pages of total 12832)
Node 2: Data usage is 5%(177 32K pages of total 3200)
Node 2: Index usage is 0%(108 8K pages of total 12832)
Node 3: Data usage is 0%(0 32K pages of total 3200)
Node 3: Index usage is 0%(0 8K pages of total 12832)
Node 4: Data usage is 0%(0 8K pages of total 3200)
Node 4: Index usage is 0%(0 8K pages of total 3200)
Node 4: Index usage is 0%(0 8K pages of total 12832)
```

By using ndb_desc with the -p option, which causes the output to include partitioning information, you can see that the table still uses only 2 partitions (in the Per partition info section of the output, shown here in bold text):

```
shell> ndb desc -c 192.168.0.10 -d n ips -p
Version: 1
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 6
Number of primary keys:
Length of frm data: 340
Row Checksum: 1
                                      1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 2
TableStatus: Retrieved
-- Attributes -- id Bigint PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR country_code Char(2;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY type Char(4;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
ip_address Varchar(15;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY addresses Bigunsigned NULL AT=FIXED ST=MEMORY
date Bigunsigned NULL AT=FIXED ST=MEMORY
     Indexes
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
-- Per partition info --
Partition
                                       Commit count Frag fixed memory
                   Row count
                                                                                               Frag varsized memory
                   26086
                                       26086
                                                               1572864
                                                                                               557056
                   26329
                                       26329
                                                              1605632
                                                                                               557056
NDBT_ProgramExit: 0 - OK
```

You can cause the data to be redistributed among all of the data nodes by performing, for each NDBCLUSTER table, an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client. After issuing the statement ALTER ONLINE TABLE ips REORGANIZE PARTITION, you can see using ndb_desc that the data for this table is now stored using 4 partitions, as shown here (with the relevant portions of the output in bold type):

```
shell> ndb_desc -c 192.168.0.10 -d n ips -p
Version: 16777217
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 6
Number of primary keys: 1
Length of frm data: 341
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 4
TableStatus: Retrieved
- Attributes --
id Bigint PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
country_code Char(2;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
type Char(4;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
ip_address Varchar(15;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY addresses Bigunsigned NULL AT=FIXED ST=MEMORY
       Bigunsigned NULL AT=FIXED ST=MEMORY
    Indexes
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
-- Per partition info
Partition Row count
                                      Commit count Frag fixed memory
                                                                                           Frag varsized memory
                                                            1572864
                   12981
                                      52296
                                                                                            557056
                   13236
                                      52515
                                                                                            557056
1
                                                            1605632
                   13093
                                      13093
                                                            819200
                                                                                            294912
NDBT_ProgramExit: 0 - OK
```

Note

Normally, ALTER [ONLINE] TABLE table_name REORGANIZE PARTITION is used with a list of partition identifiers and a set of partition definitions to create a new partitioning scheme for a table that has already been expli-

citly partitioned. Its use here to redistribute data onto a new MySQL Cluster node group is an exception in this regard; when used in this way, only the name of the table is used following the TABLE keyword, and no other keywords or identifiers follow REORGANIZE PARTITION.

Prior to MySQL Cluster NDB 6.4.3, ALTER ONLINE TABLE ... REORGANIZE PARTITION with no partition_names INTO (partition_definitions) option did not work correctly with Disk Data tables or with in-memory NDBCLUSTER tables having one or more disk-based columns. (Bug #42549)

For more information, see ALTER TABLE Syntax.

In addition, for each table, the ALTER ONLINE TABLE statement should be followed by an OPTIMIZE TABLE to reclaim wasted space. You can obtain a list of all NDBCLUSTER tables using the following query against the INFORMATION_SCHEMA.TABLES table:

```
SELECT TABLE_SCHEMA, TABLE_NAME
FROM INFORMATION_SCHEMA.TABLES
WHERE ENGINE = 'NDBCLUSTER';
```

Note

The Information_schema. Tables. Engine value for a MySQL Cluster table is always NDBCLUSTER, regardless of whether the CREATE TABLE statement used to create the table (or ALTER TABLE statement used to convert an existing table from a different storage engine) used NDB or NDBCLUSTER in its ENGINE option.

You can see after performing these statements in the output of ALL REPORT MEMORY that the data and indexes are now redistributed between all cluster data nodes, as shown here:

```
ndb_mgm> ALL REPORT MEMORY

Node 1: Data usage is 5%(176 32K pages of total 3200)

Node 1: Index usage is 0%(76 8K pages of total 3200)

Node 2: Data usage is 5%(176 32K pages of total 3200)

Node 2: Index usage is 0%(76 8K pages of total 3200)

Node 3: Data usage is 2%(80 32K pages of total 3200)

Node 3: Index usage is 0%(51 8K pages of total 3200)

Node 4: Data usage is 2%(80 32K pages of total 3200)

Node 4: Index usage is 0%(50 8K pages of total 3200)
```

Note

Since only one DDL operation on NDBCLUSTER tables can be executed at a time, you must wait for each ALTER ONLINE TABLE . . . REORGANIZE PARTITION statement to finish before issuing the next one.

It is not necessary to issue ALTER ONLINE TABLE ... REORGANIZE PARTITION statements for NDBCLUSTER tables created *after* the new data nodes have been added; data added to such tables is distributed among all data nodes automatically. However, in NDBCLUSTER tables that existed *prior to* the addition of the new nodes, neither existing nor new data is distributed using the new nodes until these tables have been reorganized using ALTER ONLINE TABLE ... REORGANIZE PARTITION.

Alternative procedure, without rolling restart. It is possible to avoid the need for a rolling restart by configuring the extra data nodes, but not starting them, when first starting the cluster. We assume, as before, that you wish to start with two data nodes—nodes 1 and 2—in one node group and later to expand the cluster to four data nodes, by adding a second node group consisting of nodes 3 and 4:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NoOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
[ndbd]
Id = 1
HostName = 192.168.0.1
[ndbd]
Id = 2
HostName = 192.168.0.2
[ndbd]
HostName = 192.168.0.3
Nodegroup = 65536 # MySQL Cluster NDB 7.0.24 and later;
# MySQL Cluster NDB 7.1.13 and later
HostName = 192.168.0.4
                          # MySQL Cluster NDB 7.0.24 and later;
# MySQL Cluster NDB 7.1.13 and later
Nodegroup = 65536
HostName = 192.168.0.10
Id = 10
[api]
Id=20
HostName = 192.168.0.20
[api]
```

```
Id=21
HostName = 192.168.0.21
```

Prior to MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, you must perform the initial start of the cluster using the -nowait-nodes option with ndbd (or ndbmtd in MySQL Cluster NDB 7.0.4 and later) for each of the data nodes that you wish to have online immediately, so that the cluster does not wait for the remaining nodes to start:

```
shell> ndbd -c 192.168.0.10 --initial --nowait-nodes=3,4
```

Beginning with MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, the data nodes to be brought online at a later time (nodes 3 and 4) can be configured with NodeGroup = 65536, in which case it is not necessary to start the nodes to be started immediately (nodes 1 and 2) with the --nowait-nodes option, so nodes 1 and 2 can each be started as shown here:

```
shell> ndbd -c 192.168.0.10 --initial
```

The data nodes configured with NodeGroup = 65536 are treated by the management server as though you had started nodes 1 and 2 using --nowait-nodes=3, 4 after waiting for a period of time determined by the setting for the StartNoNodeGroup-Timeout data node configuration parameter (also introduced in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13). By default, this is 15 seconds (15000 milliseconds).

Note

StartNoNodegroupTimeout must be the same for all data nodes in the cluster; for this reason, you should always set it in the [ndbd default] section of the config.ini file, rather than for individual data nodes.

When you are ready to add the second node group, you need only perform the following additional steps:

1. Start data nodes 3 and 4, invoking the data node process once for each new node:

```
shell> ndbd -c 192.168.0.10 --initial
```

2. Issue the appropriate CREATE NODEGROUP command in the management client:

```
ndb_mgm> CREATE NODEGROUP 3,4
```

3. In the mysql client, issue ALTER ONLINE TABLE ... REORGANIZE PARTITION and OPTIMIZE TABLE statements for each existing NDBCLUSTER table. (As noted elsewhere in this section, existing MySQL Cluster tables cannot use the new nodes for data distribution until this has been done.)

5.13. Distributed MySQL Privileges for MySQL Cluster

MySQL Cluster NDB 7.2 introduces support for distributing MySQL users and privileges across all SQL nodes in a MySQL Cluster. This support is not enabled by default; you should follow the procedure outlined in this section in order to do so.

Normally, each MySQL server's user privilege tables in the mysql database must use the MyISAM storage engine, which means that a user account and its associated privileges created on one SQL node are not available on the cluster's other SQL nodes. In MySQL Cluster NDB 7.2 and later, an SQL file ndb_dist_priv.sql is provided with the MySQL Cluster distribution. This file can be found in the share/mysql directory in the MySQL installation directory.

The first step in enabling distributed privileges is to load this script into a MySQL Server that functions as an SQL node (which we refer to after this as the *target* SQL node or MySQL Server). You can do this by executing the following command from the system shell on the target SQL node after changing to its MySQL installation directory (where *options* stands for any additional options needed to connect to this SQL node):

```
shell> mysql options -uroot < share/mysql/ndb_dist_priv.sql
```

Importing ndb_dist_priv.sql creates a number of stored routines (six stored procedures and one stored function) in the mysql database on the target SQL node. After connecting to the SQL node in the mysql client (as MySQL root), you can verify that these were created as shown here:

```
mysql_cluster_backup_privileges mysql PROCEDURE
mysql_cluster_move_grant_tables mysql PROCEDURE
mysql_cluster_move_privileges mysql PROCEDURE
mysql_cluster_restore_local_privileges mysql PROCEDURE
mysql_cluster_restore_privileges mysql PROCEDURE
mysql_cluster_restore_privileges mysql PROCEDURE
mysql_cluster_restore_privileges mysql PROCEDURE
mysql_cluster_restore_privileges_from_local mysql PROCEDURE

**Tows in set (0.01 sec)**
```

The stored procedure named mysql_cluster_move_privileges creates backup copies of the existing privilege tables, then converts them to NDB. Two sets of copies are created in the mysql database:

- A set of local copies that use the MyISAM storage engine, and named by adding the suffix _backup to the original privilege table names.
- A set of distributed copies (using NDBCLUSTER). These tables are named by prefixing ndb_ and appending _backup to the names of the original tables.

Although the original privilege tables are backed up automatically, it is always a good idea to create backups manually of the existing privilege tables on all affected SQL nodes before proceeding. You can do this using mysqldump in a manner similar to what is shown here:

```
shell> mysqldump options -uroot \
   mysql user db tables_priv columns_priv procs_priv > backup_file
```

To perform the conversion, you must be connected to the target SQL node using the mysql client (again, as the MySQL root user). Invoke the stored procedure like this:

```
mysql> CALL mysql_cluster_move privileges();
Query OK, 0 rows affected (22.32 sec)
```

Depending on the number of rows in the privilege tables, this procedure may take some time to execute. If some of the privilege tables are empty, you may see one or more No DATA - ZERO ROWS FETCHED, SELECTED, OR PROCESSED warnings when mysql_cluster_move_privileges returns. In such cases, the warnings may be safely ignored. To verify that the conversion was successful, you can use the stored function mysql_cluster_privileges_are_distributed as shown here:

mysql_cluster_privileges_are_distributed checks for the existence of the distributed privilege tables and returns 1 if all of the privilege tables are distributed; otherwise, it returns 0.

You can verify that the backups have been created using a query such as this one:

```
mysql> SELECT TABLE_NAME, ENGINE FROM INFORMATION_SCHEMA.TABLES
              WHERE TABLE_SCHEMA = 'mysql' AND TABLE_NAME LIKE '%backup'
ORDER BY ENGINE;
     ->
->
  TABLE NAME
                                    ENGINE
                                    MyISAM
  procs_priv_backup
  db_backup
                                    MyISAM
  columns_priv_backup
user_backup
                                    MyISAM
MyISAM
  host_backup
tables_priv_backup
                                    MyISAM
                                    MyISAM
  ndb_user_backup
ndb_tables_priv_backup
                                    ndbcluster
ndbcluster
  ndb_procs_priv_backup
ndb_host_backup
                                    ndbcluster
ndbcluster
  ndb_db_backup
                                    ndbcluster
  ndb columns priv backup
                                    ndbcluster
12 rows in set (0.00 sec)
```

Once the conversion to distributed privileges has been made, any time a MySQL user account is created, dropped, or has its privileges updated on any SQL node, the changes take effect immediately on all other MySQL servers attached to the cluster. Once privileges are distributed, any new MySQL Servers that connect to the cluster automatically participate in the distribution.

Note

For clients connected to SQL nodes at the time that mysql_cluster_move_privileges is executed, you may need to execute FLUSH PRIVILEGES on those SQL nodes, or to disconnect and then reconnect the clients, in order for those clients to be able to see the changes in privileges.

All MySQL user privileges are distributed across all connected MySQL Servers. This includes privileges associated with views and stored routines. While automatic distribution of views and stored routines is not currently supported, you can attempt to distribute stored routines by issuing a statement such as ALTER TABLE mysql.proc ENGINE = NDB, but you must verify manually that any tables referenced by the stored routines exist on all SQL nodes, since MySQL Cluster has no support at the present time for doing this automatically. There is currently no way to distribute views among MySQL Cluster SQL nodes, other than by creating them manually on each SQL node. If you do this, you must make certain that all base tables referenced by the views use the NDB storage engine; otherwise, the views are likely to diverge very quickly.

In the event that an SQL node becomes disconnected from the cluster while mysql_cluster_move_privileges is running, you must drop its privilege tables after reconnecting to the cluster, using a statement such as DROP TABLE IF EXISTS user db tables_priv columns_priv procs_priv. This causes the SQL node to use the shared privilege tables rather than its own local versions of them. This is not needed when connecting a new SQL node to the cluster for the first time.

In the event of an initial restart of the entire cluster (all data nodes shut down, then started again with --initial), the shared privilege tables are lost. In this case, you can restore them using the original target SQL node either from the backups made by mysql_cluster_move_privileges or from a dump file created with mysqldump. If you need to use a new MySQL Server to perform the restoration, you should start it with --skip-grant-tables when connecting to the cluster for the first time; after this, you can restore the privilege tables locally, then distribute them again using mysql_cluster_move_privileges. After restoring and distributing the tables, you should restart this MySQL Server without the --skip-grant-tables option.


Important

Applications that access MySQL Cluster data directly, including NDB API and ClusterJ applications, are not subject to the MySQL privilege system. This means that, once you have distributed the grant tables, they can be freely accessed by such applications, just as they can any other NDB tables. In particular, you should keep in mind that NDB API and ClusterJ applications can read and write user names, host names, password hashes, and any other contents of the distributed grant tables without any restrictions.

Chapter 6. MySQL Cluster Replication

Previous to MySQL 5.1.6, asynchronous replication, more usually referred to simply as "replication", was not available when using MySQL Cluster. MySQL 5.1.6 introduces master-slave replication of this type for MySQL Cluster databases. This section explains how to set up and manage a configuration wherein one group of computers operating as a MySQL Cluster replicates to a second computer or group of computers. We assume some familiarity on the part of the reader with standard MySQL replication as discussed elsewhere in this Manual. (See Replication).

Normal (non-clustered) replication involves a "master" server and a "slave" server, the master being the source of the operations and data to be replicated and the slave being the recipient of these. In MySQL Cluster, replication is conceptually very similar but can be more complex in practice, as it may be extended to cover a number of different configurations including replicating between two complete clusters. Although a MySQL Cluster itself depends on the NDB storage engine for clustering functionality, it is not necessary to use NDB as the storage engine for the slave's copies of the replicated tables (see Replication from NDB to non-NDB tables). However, for maximum availability, it is possible (and preferable) to replicate from one MySQL Cluster to another, and it is this scenario that we discuss, as shown in the following figure:



In this scenario, the replication process is one in which successive states of a master cluster are logged and saved to a slave cluster. This process is accomplished by a special thread known as the NDB binlog injector thread, which runs on each MySQL server and produces a binary log (binlog). This thread ensures that all changes in the cluster producing the binary log—and not just those changes that are effected through the MySQL Server—are inserted into the binary log with the correct serialization order. We refer to the MySQL replication master and replication slave servers as replication servers or replication nodes, and the data flow or line of communication between them as a *replication channel*.

For information about performing point-in-time recovery with MySQL Cluster and MySQL Cluster Replication, see Section 6.9.2, "Point-In-Time Recovery Using MySQL Cluster Replication".

Replication from NDB to non-NDB tables. It is possible to replicate NDB tables from a MySQL Cluster acting as the master to tables using other MySQL storage engines such as InnoDB or MyISAM on a slave mysqld. However, because of differences between the version of mysqld provided with MySQL Cluster and that included with MySQL Server 5.1, the slave server must also use a mysqld binary from the MySQL Cluster distribution. See Section 6.2, "General Requirements for MySQL Cluster Replication".

6.1. MySQL Cluster Replication: Abbreviations and Symbols

Throughout this section, we use the following abbreviations or symbols for referring to the master and slave clusters, and to processes and commands run on the clusters or cluster nodes:

Symbol or Abbreviation	Description (Refers to)
M	The cluster serving as the (primary) replication master
S	The cluster acting as the (primary) replication slave

Symbol or Abbreviation	Description (Refers to)	
shellM>	Shell command to be issued on the master cluster	
mysqlM>	MySQL client command issued on a single MySQL server running as an SQL node on the master cluster	
mysqlM*>	MySQL client command to be issued on all SQL nodes participating in the replication master cluster	
shellS>	Shell command to be issued on the slave cluster	
mysqlS>	MySQL client command issued on a single MySQL server running as an SQL node on the slave cluster	
mysqlS*>	MySQL client command to be issued on all SQL nodes participating in the replication slave cluster	
C	Primary replication channel	
C'	Secondary replication channel	
М'	Secondary replication master	
S'	Secondary replication slave	

6.2. General Requirements for MySQL Cluster Replication

A replication channel requires two MySQL servers acting as replication servers (one each for the master and slave). For example, this means that in the case of a replication setup with two replication channels (to provide an extra channel for redundancy), there will be a total of four replication nodes, two per cluster.

Replication of a MySQL Cluster as described in this section and those following is dependent on row-based replication. This means that the replication master MySQL server must be started with --binlog-format=ROW or --binlog-format=MIXED, as described in Section 6.6, "Starting MySQL Cluster Replication (Single Replication Channel)". For general information about row-based replication, see Replication Formats.

Important

If you attempt to use MySQL Cluster Replication with <code>--binlog-format=STATEMENT</code>, replication fails to work properly because the <code>ndb_binlog_index</code> table on the master and the <code>epoch</code> column of the <code>ndb_apply_status</code> table on the slave are not updated (see Section 6.4, "MySQL Cluster Replication Schema and Tables"). Instead, only updates on the MySQL server acting as the replication master propagate to the slave, and no updates from any other SQL nodes on the master cluster are replicated.

In all MySQL Cluster NDB 6.x and 7.x releases, the default value for the --binlog-format option is MIXED.

Each MySQL server used for replication in either cluster must be uniquely identified among all the MySQL replication servers participating in either cluster (you cannot have replication servers on both the master and slave clusters sharing the same ID). This can be done by starting each SQL node using the <code>--server-id=id</code> option, where <code>id</code> is a unique integer. Although it is not strictly necessary, we will assume for purposes of this discussion that all MySQL Cluster binaries are of the same release version.

It is generally true in MySQL Replication that both MySQL servers (mysqld processes) involved must be compatible with one another with respect to both the version of the replication protocol used and the SQL feature sets which they support (see Replication Compatibility Between MySQL Versions). It is due to such differences between the binaries in the MySQL Cluster and MySQL Server 5.1 distributions that MySQL Cluster Replication has the additional requirement that both mysqld binaries come from a MySQL Cluster distribution. The simplest and easiest way to assure that the mysqld servers are compatible is to use the same MySQL Cluster distribution for all master and slave mysqld binaries.

We assume that the slave server or cluster is dedicated to replication of the master, and that no other data is being stored on it.

Note

It is possible to replicate a MySQL Cluster using statement-based replication. However, in this case, the following restrictions apply:

- · All updates to data rows on the cluster acting as the master must be directed to a single MySQL server.
- It is not possible to replicate a cluster using multiple simultaneous MySQL replication processes.
- Only changes made at the SQL level are replicated.

These are in addition to the other limitations of statement-based replication as opposed to row-based replication; see Comparison of Statement-Based and Row-Based Replication, for more specific information concerning the differences between the two replication formats.

6.3. Known Issues in MySQL Cluster Replication

The following are known problems or issues when using replication with MySQL Cluster in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1):

• Loss of master-slave connection. A loss of connection can occur either between the replication master SQL node and the replication slave SQL node, or between the replication master SQL node and the data nodes in the master cluster. In the latter case, this can occur not only as a result of loss of physical connection (for example, a broken network cable), but due to the overflow of data node event buffers; if the SQL node is too slow to respond, it may be dropped by the cluster (this is controllable to some degree by adjusting the MaxBufferedEpochs and TimeBetweenEpochs configuration parameters). If this occurs, it is entirely possible for new data to be inserted into the master cluster without being recorded in the replication master's binary log. For this reason, to guarantee high availability, it is extremely important to maintain a backup replication channel, to monitor the primary channel, and to fail over to the secondary replication channel when necessary to keep the slave cluster synchronized with the master. MySQL Cluster is not designed to perform such monitoring on its own; for this, an external application is required.

Prior to MySQL 5.1.18, a MySQL Cluster replication slave mysqld had no way of detecting that the connection from the master had been interrupted. For this reason, it was possible for the slave to become inconsistent with the master.

Beginning with MySQL 5.1.18, the replication master issues a "gap" event when connecting or reconnecting to the master cluster. (A gap event is a type of "incident event," which indicates an incident that occurs that affects the contents of the database but that cannot easily be represented as a set of changes. Examples of incidents are server crashes, database resynchronization, (some) software updates, and (some) hardware changes.) When the slave encounters a gap in the replication log, it stops with an error message. This message is available in the output of SHOW SLAVE STATUS, and indicates that the SQL thread has stopped due to an incident registered in the replication stream, and that manual intervention is required. See Section 6.8, "Implementing Failover with MySQL Cluster Replication", for more information about what to do in such circumstances.

Important

Because MySQL Cluster is not designed on its own to monitor replication status or provide failover, if high availability is a requirement for the slave server or cluster, then you must set up multiple replication lines, monitor the master mysqld on the primary replication line, and be prepared fail over to a secondary line if and as necessary. This must be done manually, or possibly by means of a third-party application. For information about implementing this type of setup, see Section 6.7, "Using Two Replication Channels for MySQL Cluster Replication", and Section 6.8, "Implementing Failover with MySQL Cluster Replication".

However, if you are replicating from a standalone MySQL server to a MySQL Cluster, one channel is usually sufficient.


- Multi-byte character sets. Previously, there were several known issues with regard to the use of multi-byte characters sets with MySQL Cluster Replication. These were resolved in MySQL 5.1.21, MySQL Cluster NDB 6.2.14, and MySQL Cluster NDB 6.3.11. (See Bug #27404 and Bug #29562.)
- Circular replication. Prior to MySQL 5.1.18, circular replication was not supported with MySQL Cluster replication, due to the fact that all log events created in a particular MySQL Cluster were wrongly tagged with the server ID of the MySQL server used as master and not with the server ID of the originating server.

Beginning with MySQL 5.1.18, this limitation is lifted, as discussed in the next few paragraphs, in which we consider the example of a replication setup involving three MySQL Clusters numbered 1, 2, and 3, in which Cluster 1 acts as the replication master for Cluster 2, Cluster 2 acts as the master for Cluster 3, and Cluster 3 acts as the master for Cluster 1. Each cluster has two SQL nodes, with SQL nodes A and B belonging to Cluster 1, SQL nodes C and D belonging to Cluster 2, and SQL nodes E and F belonging to Cluster 3.

Circular replication using these clusters is supported as long as:


- The SQL nodes on all masters and slaves are the same
- All SQL nodes acting as replication masters and slaves are started using the --log-slave-updates option

This type of circular replication setup is shown in the following diagram:



In this scenario, SQL node A in Cluster 1 replicates to SQL node C in Cluster 2; SQL node C replicates to SQL node E in Cluster 3; SQL node E replicates to SQL node A. In other words, the replication line (indicated by the red arrows in the diagram) directly connects all SQL nodes used as replication masters and slaves.

It should also be possible to set up circular replication in which not all master SQL nodes are also slaves, as shown here:



In this case, different SQL nodes in each cluster are used as replication masters and slaves. However, you must *not* start any of the SQL nodes using <code>--log-slave-updates</code> (see the description of this option for more information). This type of circular replication scheme for MySQL Cluster, in which the line of replication (again indicated by the red arrows in the diagram) is discontinuous, should be possible, but it should be noted that it has not yet been thoroughly tested and must therefore still be considered experimental.

Note

Beginning with MySQL 5.1.24, the NDB storage engine uses *idempotent execution mode*, which suppresses duplicate-key and other errors that otherwise break circular replication of MySQL Cluster. This is equivalent to setting the global slave_exec_mode system variable to IDEMPOTENT. This is also required for multi-master replication when using MySQL Cluster. (Bug #31609)

It is not necessary to set slave_exec_mode in MySQL Cluster replication; MySQL Cluster does this automatically for all NDB tables and ignores any attempts to set this variable explicitly.

- MySQL Cluster replication and primary keys. In MySQL 5.1.6, only those NDB tables having explicit primary keys could be replicated. This limitation was lifted in MySQL 5.1.7. However, in the event of a node failure, errors in replication of NDB tables without primary keys can still occur, due to the possibility of duplicate rows being inserted in such cases. For this reason, it is highly recommended that all NDB tables being replicated have primary keys.
- MySQL Cluster Replication and Unique Keys. Prior to MySQL Cluster NDB 7.0.25 and MySQL Cluster NDB 7.1.14, operations that updated values of unique key columns of NDB tables could result in duplicate-key errors when replicated. This was due to the ordering of row events in the binary log according to the partitioning of the base table, which meant that they could appear in a different order from that in which they were originally executed. (Bug #11756082)

In MySQL Cluster NDB 7.0.25, MySQL Cluster NDB 7.1.14, and later, this issue is solved for replication between NDB tables by deferring unique key checks until after all table row updates have been performed.

Deferring constraints in this way is currently supported only by NDB. Thus, updates of unique keys when replicating from NDB to a different storage engine such as MyISAM or InnoDB are still not supported.

The problem encountered when replicating without deferred checking of unique key updates can be illustrated using NDB table such as t, is created and populated on the master (and replicated to a slave that does not support deferred unique key updates) as shown here:

```
CREATE TABLE t (
    p INT PRIMARY KEY,
    c INT,
    UNIQUE KEY u (c)
) ENGINE NDB;
INSERT INTO t
    VALUES (1,1), (2,2), (3,3), (4,4), (5,5);
```

The following UPDATE statement on t succeeded on the master, since the rows affected are processed in the order determined by the ORDER BY option, performed over the entire table:

```
UPDATE t SET c = c - 1 ORDER BY p;
```

However, the same statement failed with a duplicate key error or other constraint violation on the slave, because the ordering of the row updates was done for one partition at a time, rather than for the table as a whole.

Note

In MySQL 5.1.6 and later, every NDB table is implicitly partitioned by key when it is created. This also applies to all MySQL Cluster NDB 6.x and MySQL Cluster NDB 7.x releases. See KEY Partitioning, for more information.

- Restarting with --initial. Restarting the cluster with the --initial option causes the sequence of GCI and epoch numbers to start over from 0. (This is generally true of MySQL Cluster and not limited to replication scenarios involving Cluster.) The MySQL servers involved in replication should in this case be restarted. After this, you should use the RESET MASTER and RESET SLAVE statements to clear the invalid ndb_binlog_index and ndb_apply_status tables. respectively.
- auto_increment_offset and auto_increment_increment variables. The use of the auto_increment_offset and auto_increment_increment server system variables is supported beginning with MySQL 5.1.20. Previously, these produced unpredictable results when used with NDB tables or MySQL Cluster replication.
- Replication from NDBCLUSTER to other storage engines. If you attempt to replicate from a MySQL Cluster to a slave that uses a storage engine that does not handle its own binary logging, the replication process aborts with the error Binary logging not possible . . . Statement cannot be written atomically since more than one engine involved and at least one engine is self-logging (Error 1595). It is possible to work around this issue in one of the following ways:
 - Turn off binary logging on the slave. This can be accomplished by setting sql_log_bin = 0.
 - Change the storage engine used for the mysql.ndb_apply_status table. Causing this table to use an engine that does not handle its own binary logging can also eliminate the conflict. This can be done by issuing a statement such as ALTER TABLE mysql.ndb_apply_status ENGINE=MyISAM on the slave. It is safe to do this when using a non-NDB storage engine on the slave, since you do not then need to worry about keeping multiple slave SQL nodes synchronized.
 - **Filter out changes to the mysql.ndb_apply_status table on the slave.** This can be done by starting the slave SQL node with the option --replicate-ignore-table=mysql.ndb_apply_status. If you need for other tables to be ignored by replication, you might wish to use an appropriate --replicate-wild-ignore-table option instead.

Important

You should not disable replication or binary logging of mysql.ndb_apply_status or change the storage engine

used for this table when replicating from one MySQL Cluster to another. See Replication and binary log filtering rules with replication between MySQL Clusters, for details.

• Replication from NDB to a different storage engine. For replication from NDB to a different storage engine, the relationship between the two databases must be a simple master-slave one. This means that circular or master-master replication is not supported between MySQL Cluster and other storage engines. However, the MySQL Cluster database can simultaneously replicate to multiple slave MySQL Cluster databases.

In addition, it is not possible to configure more than one replication channel when replicating between MySQL Cluster and a different storage engine. If MySQL Cluster is the master then it is still possible to have more than one MySQL Server maintain a binary log of all changes; however, for the slave to change masters (fail over), the new master-slave relationship must be explicitly defined on the slave.

• Replication from NDB to a nontransactional storage engine. When replicating from NDB to a nontransactional storage engine such as MyISAM, you may encounter unnecessary duplicate key errors when replicating INSERT ... ON DUPLICATE KEY UPDATE statements. You can suppress these in MySQL Cluster NDB 6.2 and later MySQL Cluster releases by using --ndb-log-update-as-write=0, which forces updates to be logged as writes (rather than as updates).

You should also be aware that, when replicating from NDB to a storage engine that does not implement transactions (such as MyISAM), if the slave fails in applying one or more rows changes from a transaction, it does not roll back the rest of the transaction. Because of this, it cannot be guaranteed that transactional consistency will be maintained on the slave in this type of scenario.

- Replication and binary log filtering rules with replication between MySQL Clusters. If you are using any of the options --replicate-do-*, --replicate-ignore-*, --binlog-do-db, or --binlog-ignore-db to filter databases or tables being replicated, care must be taken not to block replication or binary logging of the mysql.ndb_apply_status, which is required for replication between MySQL Clusters to operate properly. In particular, you must keep in mind the following:
 - Using --replicate-do-db=db_name (and no other --replicate-do-* or --replicate-ignore-* options) means that only tables in database db_name are replicated. In this case, you should also use --replicate-do-db=mysql, --binlog-do-db=mysql, or --replicate-do-table=mysql.ndb_apply_status to ensure that mysql.ndb_apply_status is populated on slaves.

Using --binlog-do-db=db_name (and no other --binlog-do-db options) means that changes *only* to tables in database *db_name* are written to the binary log. In this case, you should also use --replicate-do-db=mysql, --binlog-do-db=mysql, or --replicate-do-table=mysql.ndb_apply_status to ensure that mysql.ndb_apply_status is populated on slaves.

2. Using --replicate-ignore-db=mysql means that no tables in the mysql database are replicated. In this case, you should also use --replicate-do-table=mysql.ndb_apply_status to ensure that mysql.ndb_apply_status is replicated.

Using --binlog-ignore-db=mysql means that no changes to tables in the mysql database are written to the binary log. In this case, you should also use --replicate-do-table=mysql.ndb_apply_status to ensure that mysql.ndb_apply_status is replicated.


You should also remember that each replication rule requires the following:

- Its own --replicate-do-* or --replicate-ignore-* option, and that multiple rules cannot be expressed in a
 single replication filtering option. For information about these rules, see Replication and Binary Logging Options and
 Variables.
- 2. Its own --binlog-do-db or --binlog-ignore-db option, and that multiple rules cannot be expressed in a single binary log filtering option. For information about these rules, see The Binary Log.

Note

If you are replicating a MySQL Cluster to a slave that uses a storage engine other than NDBCLUSTER, the considerations just given previously may not apply. See *Replication from NDBCLUSTER to other storage engines* elsewhere in this section for details.

MySQL Cluster Replication and IPv6. Currently, the NDB API and MGM API do not support IPv6. However, beginning
with MySQL Cluster NDB 6.4.1, MySQL Servers—including those acting as SQL nodes in a MySQL Cluster—can use IPv6 to
contact other MySQL Servers. This means that you can replicate between MySQL Clusters using IPv6 to connect the master
and slave SQL nodes as shown by the dotted arrow in the following diagram:



However, all connections originating within the MySQL Cluster—shown in the diagram by solid arrows—must use IPv4.

All MySQL Cluster data nodes, management servers, and management clients must be accessible from one another using IPv4. In addition, SQL nodes must use IPv4 to communicate with the cluster. There is not currently any support in the NDB and MGM APIs for IPv6, which means that any applications written using these APIs must also make all connections using IPv4.

• Attribute promotion and demotion. Formerly, support in MySQL Cluster for type conversions between columns of similar but different types on the master and the slave was extremely limited. However, starting with MySQL Cluster NDB 6.3.33, 7.0.14, and 7.1.3, MySQL Cluster Replication includes support for attribute promotion and demotion. The implementation of the latter distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave_type_conversions global server system variable.

For more information about attribute promotion and demotion in MySQL Cluster, see Attribute promotion and demotion (MySQL Cluster).

6.4. MySQL Cluster Replication Schema and Tables

Replication in MySQL Cluster makes use of a number of dedicated tables in the mysql database on each MySQL Server instance acting as an SQL node in both the cluster being replicated and the replication slave (whether the slave is a single server or a cluster). These tables are created during the MySQL installation process by the mysql_install_db script, and include a table for storing the binary log's indexing data. Since the ndb_binlog_index table is local to each MySQL server and does not participate in clustering, it uses the MyISAM storage engine. This means that it must be created separately on each mysqld participating in the master cluster. (However, the binlog itself contains updates from all MySQL servers in the cluster to be replicated.) This table is defined as follows:

```
CREATE TABLE `ndb_binlog_index` (
    `Position` BIGINT(20) UNSIGNED NOT NULL,
    `File` VARCHAR(255) NOT NULL,
    `epoch` BIGINT(20) UNSIGNED NOT NULL,
    `inserts` BIGINT(20) UNSIGNED NOT NULL,
    `updates` BIGINT(20) UNSIGNED NOT NULL,
    `deletes` BIGINT(20) UNSIGNED NOT NULL,
    `schemaops` BIGINT(20) UNSIGNED NOT NULL,
    PRIMARY KEY (`epoch`)
) ENGINE=MYISAM DEFAULT CHARSET=latin1;
```

Important

Prior to MySQL 5.1.14, the ndb_binlog_index table was known as binlog_index, and was kept in a separate

cluster database, which in MySQL 5.1.7 and earlier was known as the cluster_replication database. Similarly, the ndb_apply_status and ndb_schema tables were known as apply_status and schema, and were also found in the cluster (earlier cluster_replication) database. However, beginning with MySQL 5.1.14, all MySQL Cluster replication tables reside in the mysql system database.


Information about how this change affects upgrades from MySQL Cluster 5.1.13 and earlier to 5.1.14 and later versions can be found in Changes in MySQL 5.1.14.

Beginning with MySQL Cluster NDB 6.3.2, this table has been changed to facilitate 3-way replication recovery. Two columns orig_server_id and orig_epoch have been added to this table; when mysqld is started with the --ndb-log-orig option, these columns store, respectively, the ID of the server on which the event originated and the epoch in which the event took place on the originating server. In addition, the table's primary key now includes these two columns. The modified table definition is shown here:

The gci column was added in MySQL Cluster NDB 6.2.6 and MySQL Cluster NDB 6.3.2.

The following figure shows the relationship of the MySQL Cluster replication master server, its binlog injector thread, and the mysql.ndb_binlog_index table.

MySQL Replication Between Clusters, Injecting into Binlog



An additional table, named ndb_apply_status, is used to keep a record of the operations that have been replicated from the master to the slave. Unlike the case with ndb_binlog_index, the data in this table is not specific to any one SQL node in the (slave) cluster, and so ndb_apply_status can use the NDBCLUSTER storage engine, as shown here:

```
CREATE TABLE `ndb_apply_status` (
```

```
`server_id` INT(10) UNSIGNED NOT NULL,

`epoch` BIGINT(20) UNSIGNED NOT NULL,

`log_name` VARCHAR(255) CHARACTER SET latin1 COLLATE latin1_bin NOT NULL,

`start_pos` BIGINT(20) UNSIGNED NOT NULL,

`end_pos` BIGINT(20) UNSIGNED NOT NULL,

PRIMARY KEY (`server_id`) USING HASH

) ENGINE=NDBCLUSTER DEFAULT CHARSET=latin1;
```

This table is populated only on slaves; on the master, no <code>DataMemory</code> is allocated to it. Since this table is populated from data originating on the master, it should be allowed to replicate; any replication filtering or binary log filtering rules that inadvertently prevent the slave from updating <code>ndb_apply_status</code> or the master from writing into the binary log may prevent replication between clusters from operating properly. For more information about potential problems arising from such filtering rules, see Replication and binary log filtering rules with replication between <code>MySQL</code> Clusters.

The log_name, start_pos, and end_pos columns were added in MySQL 5.1.18.

Important

If you are using MySQL Cluster replication, see Section 2.7.3, "Upgrade and downgrade compatibility: MySQL 5.1" before upgrading to MySQL 5.1.18 or later from an earlier version.

The ndb_binlog_index and ndb_apply_status tables are created in the mysql database because they should not be explicitly replicated by the user. User intervention is normally not required to create or maintain either of these tables, since both ndb_binlog_index and the ndb_apply_status are maintained by the NDB binary log (binlog) injector thread. This keeps the master mysqld process updated to changes performed by the NDB storage engine. The NDB binlog injector thread receives events directly from the NDB storage engine. The NDB injector is responsible for capturing all the data events within the cluster, and ensures that all events which change, insert, or delete data are recorded in the ndb_binlog_index table. The slave I/O thread transfers the events from the master's binary log to the slave's relay log.

However, it is advisable to check for the existence and integrity of these tables as an initial step in preparing a MySQL Cluster for replication. It is possible to view event data recorded in the binary log by querying the mysql.ndb_binlog_index table directly on the master. This can be also be accomplished using the SHOW BINLOG EVENTS statement on either the replication master or slave MySQL servers. (See SHOW BINLOG EVENTS Syntax.)

You can also obtain useful information from the output of SHOW ENGINE NDB STATUS.

The ndb_schema table is used to track schema changes made to NDB tables. It is defined as shown here:

Unlike the two tables previously mentioned in this section, the ndb_schema table is not visible either to MySQL SHOW statements, or in any INFORMATION_SCHEMA tables; however, it can be seen in the output of ndb_show_tables, as shown here:

```
shell> ndb_show_tables -t 2
id
4
5
                                 state
                                            logging database
                                                                      schema
       type
       UserTable
UserTable
                                                     mysql
ndbworld
                                                                                ndb_apply_status
City
                                 Online
                                            Yes
                                                                     def
                                 Online
                                            Yes
                                                                     def
                                                      ndbworld
       UserTable
                                 Online
                                            Yes
                                                                     def
                                                                                Country
6
3
7
       UserTable
                                 Online
                                                                     def
                                                                                NDB$BLOB_2_3
                                            Yes
                                                      mysql
                                                      ndbworld
                                                                                CountryLanguage
ndb_schema
       UserTable
                                 Online
                                            Yes
                                                                     def
def
       UserTable
                                 Online
                                                      mysql
NDBT_ProgramExit: 0 - OK
```

It is also possible to SELECT from this table in mysql and other MySQL client applications, as shown here:

```
mysql> SELECT * FROM mysql.ndb_schema WHERE name='City' \G
**********************************
    db: nddworld
    name: City
    slock:
    query: alter table City engine=ndb
node_id: 4
    epoch: 0
    id: 0
version: 0
    type: 7
1 row in set (0.00 sec)
```

This can sometimes be useful when debugging applications.

Note

When performing schema changes on NDB tables, applications should wait until the ALTER TABLE statement has returned in the MySQL client connection that issued the statement before attempting to use the updated definition of the table.

The ndb_schema table was added in MySQL 5.1.8.

Beginning with MySQL 5.1.14, if the ndb_apply_status table or the ndb_schema table does not exist on the slave, ndb_restore re-creates the missing table or tables (Bug #14612).

Conflict resolution for MySQL Cluster Replication requires the presence of an additional mysql.ndb_replication table. Currently, this table must be created manually. For information about how to do this, see Section 6.11, "MySQL Cluster Replication Conflict Resolution".

6.5. Preparing the MySQL Cluster for Replication

Preparing the MySQL Cluster for replication consists of the following steps:

- Check all MySQL servers for version compatibility (see Section 6.2, "General Requirements for MySQL Cluster Replication").
- 2. Create a slave account on the master Cluster with the appropriate privileges:

```
mysqlM> GRANT REPLICATION SLAVE
-> ON *.* TO 'slave_user'@'slave_host'
-> IDENTIFIED BY 'slave_password';
```

In the previous statement, <code>slave_user</code> is the slave account user name, <code>slave_host</code> is the host name or IP address of the replication slave, and <code>slave_password</code> is the password to assign to this account.

For example, to create a slave user account with the name "myslave," logging in from the host named "rep-slave," and using the password "53cr37," use the following GRANT statement:

```
mysqlM> GRANT REPLICATION SLAVE
-> ON *.* TO 'myslave'@'rep-slave'
-> IDENTIFIED BY '53cr37';
```

For security reasons, it is preferable to use a unique user account—not employed for any other purpose—for the replication slave account.

Configure the slave to use the master. Using the MySQL Monitor, this can be accomplished with the CHANGE MASTER TO statement:

```
mysqlS> CHANGE MASTER TO
   -> MASTER_HOST='master_host',
   -> MASTER_PORT=master_port,
   -> MASTER_USER='slave_user',
   -> MASTER_PASSWORD='slave_password';
```

In the previous statement, <code>master_host</code> is the host name or IP address of the replication master, <code>master_port</code> is the port for the slave to use for connecting to the master, <code>slave_user</code> is the user name set up for the slave on the master, and <code>slave_password</code> is the password set for that user account in the previous step.

For example, to tell the slave to replicate from the MySQL server whose host name is "rep-master," using the replication slave account created in the previous step, use the following statement:

```
mysqlS> CHANGE MASTER TO
   -> MASTER_HOST='rep-master',
   -> MASTER_PORT=3306,
   -> MASTER_USER='myslave',
   -> MASTER_PASSWORD='53cr37';
```

For a complete list of clauses that can be used with this statement, see CHANGE MASTER TO Syntax.

You can also configure the slave to use the master by setting the corresponding startup options in the slave server's my.cnf file. To configure the slave in the same way as the preceding example CHANGE MASTER TO statement, the following information would need to be included in the slave's my.cnf file:

```
[mysqld]
master-host=rep-master
master-port=3306
master-user=myslave
master-password=53cr37
```

For additional options that can be set in my. cnf for replication slaves, see Replication and Binary Logging Options and Variables.

Note

To provide replication backup capability, you will also need to add an ndb-connectstring option to the slave's my.cnf file prior to starting the replication process. See Section 6.9, "MySQL Cluster Backups With MySQL Cluster Replication", for details.

4. If the master cluster is already in use, you can create a backup of the master and load this onto the slave to cut down on the amount of time required for the slave to synchronize itself with the master. If the slave is also running MySQL Cluster, this can be accomplished using the backup and restore procedure described in Section 6.9, "MySQL Cluster Backups With MySQL Cluster Replication".

```
ndb-connectstring=management_host[:port]
```

In the event that you are *not* using MySQL Cluster on the replication slave, you can create a backup with this command on the replication master:

```
shellM> mysqldump --master-data=1
```

Then import the resulting data dump onto the slave by copying the dump file over to the slave. After this, you can use the mysql client to import the data from the dumpfile into the slave database as shown here, where dump_file is the name of the file that was generated using mysqldump on the master, and db_name is the name of the database to be replicated:

```
shellS> mysql -u root -p db_name < dump_file
```

For a complete list of options to use with mysqldump, see mysqldump.

Note

If you copy the data to the slave in this fashion, you should make sure that the slave is started with the --skip-slave-start option on the command line, or else include skip-slave-start in the slave's my.cnf file to keep it from trying to connect to the master to begin replicating before all the data has been loaded. Once the data loading has completed, follow the additional steps outlined in the next two sections.

5. Ensure that each MySQL server acting as a replication master is configured with a unique server ID, and with binary logging enabled, using the row format. (See Replication Formats.) These options can be set either in the master server's my.cnf file, or on the command line when starting the master mysqld process. See Section 6.6, "Starting MySQL Cluster Replication (Single Replication Channel)", for information regarding the latter option.

6.6. Starting MySQL Cluster Replication (Single Replication Channel)

This section outlines the procedure for starting MySQL Cluster replication using a single replication channel.

1. Start the MySQL replication master server by issuing this command:

```
shellM> mysqld --ndbcluster --server-id=id \
    --log-bin --binlog-format=ROW &
```

In the previous statement, id is this server's unique ID (see Section 6.2, "General Requirements for MySQL Cluster Replication"). This starts the server's mysqld process with binary logging enabled using the proper logging format.

Note

You can also start the master with --binlog-format=MIXED, in which case row-based replication is used automatically when replicating between clusters.

2. Start the MySQL replication slave server as shown here:

```
shellS> mysqld --ndbcluster --server-id=id &
```

In the command just shown, id is the slave server's unique ID. It is not necessary to enable logging on the replication slave.

Note

You should use the <code>--skip-slave-start</code> option with this command or else you should include <code>skip-slave-start</code> in the slave server's <code>my.cnf</code> file, unless you want replication to begin immediately. With the use of this option, the start of replication is delayed until the appropriate <code>START SLAVE</code> statement has been issued, as explained in Step 4 below.

3. It is necessary to synchronize the slave server with the master server's replication binlog. If binary logging has not previously been running on the master, run the following statement on the slave:

```
mysqls> CHANGE MASTER TO
    -> MASTER_LOG_FILE='',
    -> MASTER_LOG_POS=4;
```

This instructs the slave to begin reading the master's binary log from the log's starting point. Otherwise—that is, if you are loading data from the master using a backup—see Section 6.8, "Implementing Failover with MySQL Cluster Replication", for information on how to obtain the correct values to use for MASTER_LOG_FILE and MASTER_LOG_POS in such cases.

4. Finally, you must instruct the slave to begin applying replication by issuing this command from the mysql client on the replication slave:

```
mysqls> start slave;
```

This also initiates the transmission of replication data from the master to the slave.

It is also possible to use two replication channels, in a manner similar to the procedure described in the next section; the differences between this and using a single replication channel are covered in Section 6.7, "Using Two Replication Channels for MySQL Cluster Replication".

Beginning with MySQL Cluster NDB 6.2.3, it is possible to improve cluster replication performance by enabling *batched updates*. This can be accomplished by setting the slave_allow_batching system variable on the slave mysqld processes. Normally, updates are applied as soon as they are received. However, the use of batching causes updates to be applied in 32 KB batches, which can result in higher throughput and less CPU usage, particularly where individual updates are relatively small.

Note

Slave batching works on a per-epoch basis; updates belonging to more than one transaction can be sent as part of the same batch.

All outstanding updates are applied when the end of an epoch is reached, even if the updates total less than 32 KB.

Batching can be turned on and off at runtime. To activate it at runtime, you can use either of these two statements:

```
SET GLOBAL slave_allow_batching = 1;
SET GLOBAL slave_allow_batching = ON;
```

If a particular batch causes problems (such as a statement whose effects do not appear to be replicated correctly), slave batching can be deactivated using either of the following statements:

```
SET GLOBAL slave_allow_batching = 0;
SET GLOBAL slave_allow_batching = OFF;
```

You can check whether slave batching is currently being used by means of an appropriate SHOW VARIABLES statement, like this one:

6.7. Using Two Replication Channels for MySQL Cluster Replication

In a more complete example scenario, we envision two replication channels to provide redundancy and thereby guard against possible failure of a single replication channel. This requires a total of four replication servers, two masters for the master cluster and two slave servers for the slave cluster. For purposes of the discussion that follows, we assume that unique identifiers are assigned as shown here:

Server ID	Description
1	Master - primary replication channel (M)
2	Master - secondary replication channel (M')
3	Slave - primary replication channel (S)
4	Slave - secondary replication channel (S')

Setting up replication with two channels is not radically different from setting up a single replication channel. First, the mysqld processes for the primary and secondary replication masters must be started, followed by those for the primary and secondary slaves. Then the replication processes may be initiated by issuing the START SLAVE statement on each of the slaves. The commands and the order in which they need to be issued are shown here:

1. Start the primary replication master:

```
shellM> mysqld --ndbcluster --server-id=1 \
    --log-bin --binlog-format=row &
```

2. Start the secondary replication master:

```
shellM' > mysqld --ndbcluster --server-id=2 \
    --log-bin --binlog-format=row &
```

3. Start the primary replication slave server:

Start the secondary replication slave:

```
shells'> mysqld --ndbcluster --server-id=4 \
--skip-slave-start &
```

5. Finally, initiate replication on the primary channel by executing the START SLAVE statement on the primary slave as shown here:

```
mysqlS> START SLAVE;
```

Warning

Only the primary channel is to be started at this point. The secondary replication channel is to be started only in the event that the primary replication channel fails, as described in Section 6.8, "Implementing Failover with MySQL Cluster Replication". Running multiple replication channels simultaneously can result in unwanted duplicate records being created on the replication slaves.

As mentioned previously, it is not necessary to enable binary logging on replication slaves.

6.8. Implementing Failover with MySQL Cluster Replication

In the event that the primary Cluster replication process fails, it is possible to switch over to the secondary replication channel. The following procedure describes the steps required to accomplish this.

 Obtain the time of the most recent global checkpoint (GCP). That is, you need to determine the most recent epoch from the ndb_apply_status table on the slave cluster, which can be found using the following query:

2. Using the information obtained from the query shown in Step 1, obtain the corresponding records from the ndb_binlog_index table on the master cluster as shown here:

These are the records saved on the master since the failure of the primary replication channel. We have employed a user variable @latest here to represent the value obtained in Step 1. Of course, it is not possible for one mysqld instance to access user variables set on another server instance directly. These values must be "plugged in" to the second query manually or in application code.

3. Now it is possible to synchronize the secondary channel by running the following query on the secondary slave server:

Again we have employed user variables (in this case @file and @pos) to represent the values obtained in Step 2 and applied in Step 3; in practice these values must be inserted manually or using application code that can access both of the servers involved.

Note

@file is a string value such as '/var/log/mysql/replication-master-bin.00001', and so must be quoted when used in SQL or application code. However, the value represented by @pos must *not* be quoted. Although MySQL normally attempts to convert strings to numbers, this case is an exception.

4. You can now initiate replication on the secondary channel by issuing the appropriate command on the secondary slave mysqld:

```
mysqlS'> START SLAVE;
```

Once the secondary replication channel is active, you can investigate the failure of the primary and effect repairs. The precise actions required to do this will depend upon the reasons for which the primary channel failed.

Warning

The secondary replication channel is to be started only if and when the primary replication channel has failed. Running multiple replication channels simultaneously can result in unwanted duplicate records being created on the replication slaves.

If the failure is limited to a single server, it should (in theory) be possible to replicate from M to S', or from M' to S; however, this has not yet been tested.

6.9. MySQL Cluster Backups With MySQL Cluster Replication

This section discusses making backups and restoring from them using MySQL Cluster replication. We assume that the replication servers have already been configured as covered previously (see Section 6.5, "Preparing the MySQL Cluster for Replication", and the sections immediately following). This having been done, the procedure for making a backup and then restoring from it is as follows:

- 1. There are two different methods by which the backup may be started.
 - Method A. This method requires that the cluster backup process was previously enabled on the master server, prior to starting the replication process. This can be done by including the following line in a [mysql_cluster] section in the my.cnf file, where management_host is the IP address or host name of the NDB management server for the master cluster, and port is the management server's port number:

```
ndb-connectstring=management_host[:port]
```

Note

The port number needs to be specified only if the default port (1186) is not being used. See Section 2.3, "Initial Configuration of MySQL Cluster", for more information about ports and port allocation in MySQL Cluster.

In this case, the backup can be started by executing this statement on the replication master:

```
shellM> ndb_mgm -e "START BACKUP"
```

• **Method B.** If the my.cnf file does not specify where to find the management host, you can start the backup process by passing this information to the NDB management client as part of the START BACKUP command. This can be done as shown here, where management_host and port are the host name and port number of the management server:

```
shellM> ndb_mgm management_host:port -e "START BACKUP"
```

In our scenario as outlined earlier (see Section 6.5, "Preparing the MySQL Cluster for Replication"), this would be executed as follows:

```
shellM> ndb_mgm rep-master:1186 -e "START BACKUP"
```

2. Copy the cluster backup files to the slave that is being brought on line. Each system running an ndbd process for the master cluster will have cluster backup files located on it, and *all* of these files must be copied to the slave to ensure a successful restore. The backup files can be copied into any directory on the computer where the slave management host resides, so long as the MySQL and NDB binaries have read permissions in that directory. In this case, we will assume that these files have been copied into the directory /var/BACKUPS/BACKUP-1.

It is not necessary that the slave cluster have the same number of ndbd processes (data nodes) as the master; however, it is highly recommended this number be the same. It is necessary that the slave be started with the --skip-slave-start option, to prevent premature startup of the replication process.

3. Create any databases on the slave cluster that are present on the master cluster that are to be replicated to the slave.

Important

A CREATE DATABASE (or CREATE SCHEMA) statement corresponding to each database to be replicated must be executed on each SQL node in the slave cluster.

4. Reset the slave cluster using this statement in the MySQL Monitor:

```
mysqls> RESET SLAVE;
```

It is important to make sure that the slave's apply_status table does not contain any records prior to running the restore process. You can accomplish this by running this SQL statement on the slave:

```
mysqlS> DELETE FROM mysql.ndb_apply_status;
```

5. You can now start the cluster restoration process on the replication slave using the ndb_restore command for each backup file in turn. For the first of these, it is necessary to include the -m option to restore the cluster metadata:

```
shellS> ndb_restore -c slave_host:port -n node-id \
   -b backup-id -m -r dir
```

dir is the path to the directory where the backup files have been placed on the replication slave. For the ndb_restore commands corresponding to the remaining backup files, the -m option should not be used.

For restoring from a master cluster with four data nodes (as shown in the figure in Chapter 6, *MySQL Cluster Replication*) where the backup files have been copied to the directory /var/BACKUPS/BACKUP-1, the proper sequence of commands to be executed on the slave might look like this:

Important

The -e (or --restore-epoch) option in the final invocation of ndb_restore in this example is required in order that the epoch is written to the slave mysql.ndb_apply_status. Without this information, the slave will not be able to synchronize properly with the master. (See Section 4.17, "ndb_restore — Restore a MySQL Cluster

Backup".)

6. Now you need to obtain the most recent epoch from the ndb_apply_status table on the slave (as discussed in Section 6.8, "Implementing Failover with MySQL Cluster Replication"):

```
mysqlS> SELECT @latest:=MAX(epoch)
FROM mysql.ndb_apply_status;
```

7. Using @latest as the epoch value obtained in the previous step, you can obtain the correct starting position @pos in the correct binary log file @file from the master's mysql.ndb_binlog_index table using the query shown here:

```
mysqlM> SELECT
   -> @file:=SUBSTRING_INDEX(File, '/', -1),
   -> @pos:=Position
   -> FROM mysql.ndb_binlog_index
   -> WHERE epoch > @latest
   -> ORDER BY epoch ASC LIMIT 1;
```

In the event that there is currently no replication traffic, you can get this information by running SHOW MASTER STATUS on the master and using the value in the Position column for the file whose name has the suffix with the greatest value for all files shown in the File column. However, in this case, you must determine this and supply it in the next step manually or by parsing the output with a script.

8. Using the values obtained in the previous step, you can now issue the appropriate CHANGE MASTER TO statement in the slave's mysql client:

9. Now that the slave "knows" from what point in which binlog file to start reading data from the master, you can cause the slave to begin replicating with this standard MySQL statement:

```
mysqlS> START SLAVE;
```

To perform a backup and restore on a second replication channel, it is necessary only to repeat these steps, substituting the host names and IDs of the secondary master and slave for those of the primary master and slave replication servers where appropriate, and running the preceding statements on them.

For additional information on performing Cluster backups and restoring Cluster from backups, see Section 5.3, "Online Backup of MySQL Cluster".

6.9.1. MySQL Cluster Replication: Automating Synchronization of the Replication Slave to the Master Binary Log

It is possible to automate much of the process described in the previous section (see Section 6.9, "MySQL Cluster Backups With MySQL Cluster Replication"). The following Perl script reset-slave.pl serves as an example of how you can do this.

```
#!/user/bin/perl -w
       file: reset-slave.pl
      Copyright ©2005 MySQL AB
This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or
     the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to:

Free Software Foundation Inc.
      Free Software Foundation,
59 Temple Place, Suite 33
Boston, MA 02111-1307 USA
                                                               Inc.
                                                           330
use DBI;
$m_host=''
$m_port=''
         $m_user='
         $m_pass='
         $s_host=''
        $s_port=''
       $s_pass='';
```

```
$dbhM='';
     $dbhS=''
sub CollectCommandPromptInfo;
sub ConnectToDatabases;
sub DisconnectFromDatabases;
sub GetSlaveEpoch;
sub GetMasterInfo;
sub UpdateSlave;
CollectCommandPromptInfo;
ConnectToDatabases;
GetSlaveEpoch;
GetMasterInfo;
UpdateSlave;
sub CollectCommandPromptInfo
  >master MySQL host< >master MySQL port< \n
>master user< >master pass< >slave MySQL host< \n
>slave MySQL port< >slave user< >slave pass< \n
All 8 arguments must be passed. Use BLANK for NULL passwords\n"
umless @ARGV == 8;
$m_host = $ARGV[0];
$m_port = $ARGV[1];
$m_user = $ARGV[1];
   ### Check that user has supplied correct number of command line args
                 $ARGV[1];
$ARGV[2];
   $m_user =
                 $ARGV[3];
   $m_pass
            =
   $s host
                 $ARGV[4];
                 $ARGV[5];
  $s_port
   $s_user
            = $ARGV[6];
= $ARGV[7];
  $s_pass
  if ($m_pass eq "BLANK") { $m_pass = '';}
if ($s_pass eq "BLANK") { $s_pass = '';}
############# Make connections to both databases #############
sub ConnectToDatabases
   ### Connect to both master and slave cluster databases
   ### Connect to master
   $dbhM
     = DBI->connect(
     ### Connect to slave
   $dbhS
     = DBI->connect(
    "BBI->COMMECT(
   "dbi:mysql:database=mysql;host=$s_host",
        "$s_user", "$s_pass")
or die "Can't connect to Slave Cluster MySQL process!
   Error: $DBI::errstr\n";
############## Disconnect from both databases ###############
sub DisconnectFromDatabases
   ### Disconnect from master
  $dbhM->disconnect
   or warn " Disconnection failed: $DBI::errstr\n";
  ### Disconnect from slave
$dbhS->disconnect
  or warn " Disconnection failed: $DBI::errstr\n";
####################### Find the last good GCI #################
sub GetSlaveEpoch
  $sth = $dbhS->prepare("SELECT MAX(epoch)
       FROM mysql.ndb_apply_status;")
or die "Error while preparing to select epoch from slave: ",
$dbhS->errstr;
  $sth->execute
  or die "Selecting epoch from slave error: ", $sth->errstr; $sth->bind_col (1, \$epoch);
  print "\tSlave Epoch = $epoch\n";
$sth->finish;
          Find the position of the last GCI in the binlog ########
sub GetMasterInfo
  $sth = $dbhM->prepare("SELECT
                                 SUBSTRING_INDEX(File, '/', -1), Position
       SUBSTRING_INDEX(File, '/', -1), Position
FROM mysql.ndb_binlog_index
WHERE epoch > $epoch
ORDER BY epoch ASC LIMIT 1;")
or die "Prepare to select from master error: ", $dbhM->errstr;
  $sth->execute
  or die "Selecting from master error: ", $sth->errstr;
  $sth->bind_col (1, \$binlog);
$sth->bind_col (2, \$binpos);
  print "\tMaster bin log = $binlog\n";
print "\tMaster Bin Log position = $binpos\n";
  Ssth->finish;
```

6.9.2. Point-In-Time Recovery Using MySQL Cluster Replication

Point-in-time recovery—that is, recovery of data changes made since a given point in time—is performed after restoring a full backup that returns the server to its state when the backup was made. Performing point-in-time recovery of MySQL Cluster tables with MySQL Cluster and MySQL Cluster Replication can be accomplished using a native NDB data backup (taken by issuing CREATE BACKUP in the ndb_mgm client) and restoring the ndb_binlog_index table (from a dump made using mysqldump).

To perform point-in-time recovery of MySQL Cluster, it is necessary to follow the steps shown here:

- 1. Back up all NDB databases in the cluster, using the START BACKUP command in the ndb_mgm client (see Section 5.3, "Online Backup of MySQL Cluster").
- 2. At some later point, prior to restoring the cluster, make a backup of the mysql.ndb_binlog_index table. It is probably simplest to use mysqldump for this task. Also back up the binary log files at this time.

This backup should be updated regularly—perhaps even hourly—depending on your needs.

- 3. (Catastrophic failure or error occurs.)
- 4. Locate the last known good backup.
- 5. Clear the data node file systems (using ndbd --initial or, in MySQL Cluster NDB 7.0 and later, ndbmtd --initial).

Note

MySQL Cluster Disk Data tablespace and log files are not removed by --initial. You must delete these manually.

- 6. Use DROP TABLE or TRUNCATE TABLE with the mysql.ndb_binlog_index table.
- 7. Execute ndb_restore, restoring all data. You must include the --restore_epoch option when you run ndb_restore, so that the ndb_apply_status table is populated correctly. (See Section 4.17, "ndb_restore Restore a MySQL Cluster Backup", for more information.)
- Restore the ndb_binlog_index table from the output of mysqldump and restore the binary log files from backup, if necessary.
- 9. Find the epoch applied most recently—that is, the maximum epoch column value in the ndb_apply_status table—as the user variable @LATEST_EPOCH (emphasized):

```
SELECT @LAST_EPOCH:=MAX(epoch)
FROM mysql.ndb_apply_status;
```

10. Find the latest binary log file (@FIRST_FILE) and position (Position column value) within this file that correspond to @LATEST_EPOCH in the ndb_binlog_index table:

```
SELECT Position, @FIRST_FILE:=File
FROM mysql.ndb_binlog_index
WHERE epoch > @LAST_EPOCH ORDER BY epoch ASC LIMIT 1;
```

11. Using mysqlbinlog, replay the binary log events from the given file and position up to the point of the failure. (See mysqlbinlog.)

See also Point-in-Time (Incremental) Recovery Using the Binary Log, for more information about the binary log, replication, and incremental recovery.

6.10. MySQL Cluster Replication: Multi-Master and Circular Replication

Beginning with MySQL 5.1.18, it is possible to use MySQL Cluster in multi-master replication, including circular replication between a number of MySQL Clusters.

Note


Prior to MySQL 5.1.18, multi-master replication including circular replication was not supported with MySQL Cluster replication. This was because log events created in a particular MySQL Cluster were wrongly tagged with the server ID of the master rather than the server ID of the originating server.

Circular replication example. In the next few paragraphs we consider the example of a replication setup involving three MySQL Clusters numbered 1, 2, and 3, in which Cluster 1 acts as the replication master for Cluster 2, Cluster 2 acts as the master for Cluster 3, and Cluster 3 acts as the master for Cluster 1. Each cluster has two SQL nodes, with SQL nodes A and B belonging to Cluster 1, SQL nodes C and D belonging to Cluster 2, and SQL nodes E and F belonging to Cluster 3.

Circular replication using these clusters is supported as long as the following conditions are met:


- · The SQL nodes on all masters and slaves are the same
- All SQL nodes acting as replication masters and slaves are started using the --log-slave-updates option

This type of circular replication setup is shown in the following diagram:



In this scenario, SQL node A in Cluster 1 replicates to SQL node C in Cluster 2; SQL node C replicates to SQL node E in Cluster 3; SQL node E replicates to SQL node A. In other words, the replication line (indicated by the red arrows in the diagram) directly connects all SQL nodes used as replication masters and slaves.

It is also possible to set up circular replication in such a way that not all master SQL nodes are also slaves, as shown here:



In this case, different SQL nodes in each cluster are used as replication masters and slaves. However, you must *not* start any of the SQL nodes using <code>--log-slave-updates</code> (see the description of this option for more information). This type of circular replication scheme for MySQL Cluster, in which the line of replication (again indicated by the red arrows in the diagram) is discontinuous, should be possible, but it should be noted that it has not yet been thoroughly tested and must therefore still be considered experimental.

Important

Beginning with MySQL 5.1.24, you should execute the following statement before starting circular replication:

mysql> SET GLOBAL SLAVE_EXEC_MODE = 'IDEMPOTENT';


This is necessary to suppress duplicate-key and other errors that otherwise break circular replication in MySQL Cluster. IDEMPOTENT mode is also required for multi-master replication when using MySQL Cluster. (Bug #31609)

See slave_exec_mode, for more information.

Using NDB-native backup and restore to initialize a slave MySQL Cluster. When setting up circular replication, it is possible to initialize the slave cluster by using the management client BACKUP command on one MySQL Cluster to create a backup and then applying this backup on another MySQL Cluster using ndb_restore. However, this does not automatically create binary logs on the second MySQL Cluster's SQL node acting as the replication slave. In order to cause the binary logs to be created, you must issue a SHOW TABLES statement on that SQL node; this should be done prior to running START SLAVE.


This is a known issue which we intend to address in a future release.

Multi-master failover example. In this section, we discuss failover in a multi-master MySQL Cluster replication setup with three MySQL Clusters having server IDs 1, 2, and 3. In this scenario, Cluster 1 replicates to Clusters 2 and 3; Cluster 2 also replicates to Cluster 3. This relationship is shown here:



In other words, data replicates from Cluster 1 to Cluster 3 through 2 different routes: directly, and by way of Cluster 2.

Not all MySQL servers taking part in multi-master replication must act as both master and slave, and a given MySQL Cluster might use different SQL nodes for diffferent replication channels. Such a case is shown here:



MySQL servers acting as replication slaves must be run with the --log-slave-updates option. Which mysqld processes require this option is also shown in the preceding diagram.

Note

Using the --log-slave-updates option has no effect on servers not being run as replication slaves.

The need for failover arises when one of the replicating clusters goes down. In this example, we consider the case where Cluster 1 is lost to service, and so Cluster 3 loses 2 sources of updates from Cluster 1. Because replication between MySQL Clusters is asynchronous, there is no guarantee that Cluster 3's updates originating directly from Cluster 1 are more recent than those received through Cluster 2. You can handle this by ensuring that Cluster 3 catches up to Cluster 2 with regard to updates from Cluster 1. In terms of MySQL servers, this means that you need to replicate any outstanding updates from MySQL server C to server F.

On server C, perform the following queries:

Copy over the values for <code>@file</code> and <code>@pos</code> manually from server C to server F (or have your application perform the equivalent). Then, on server F, execute the following <code>CHANGE MASTER TO</code> statement:

Once this has been done, you can issue a START SLAVE statement on MySQL server F, and any missing updates originating from server B will be replicated to server F.

Beginning with MySQL Cluster MySQL Cluster NDB 6.1.29, MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL Cluster NDB 7.1.0, the CHANGE MASTER TO statement also supports an IGNORE_SERVER_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. For more information, see CHANGE MASTER TO Syntax, and SHOW SLAVE STATUS Syntax.

6.11. MySQL Cluster Replication Conflict Resolution

When using a replication setup involving multiple masters (including circular replication), it is possible that different masters may try to update the same row on the slave with different data. Conflict resolution in MySQL Cluster Replication provides a means of resolving such conflicts by permitting a user-defined resolution column to be used to determine whether or not an update to the row on a given master should be applied on the slave. (This column is sometimes referred to as a "timestamp" column, even though this column' type cannot be TIMESTAMP, as explained later in this section.) Different methods can be used to compare resolution column values on the slave when conflicts occur, as explained later in this section; the method used can be set on a per-table basis.

Important

Conflict resolution as described in this section is always applied on a row-by-row basis rather than a transactional basis. In addition, it is the application's responsibility to ensure that the resolution column is correctly populated with relevant values, so that the resolution function can make the appropriate choice when determining whether to apply an update.

Requirements. Preparations for conflict resolution must be made on both the master and the slave. These tasks are described in the following list:

On the master writing the binlogs, you must determine which columns are sent (all columns or only those that have been updated). This is done for the MySQL Server as a whole by applying the mysqld startup option --ndb-log-updated-only (described later in this section) or on a per-table basis by entries in the mysql.ndb_replication table (see The ndb_replication system table).

Note

If you are replicating tables with very large columns (such as TEXT or BLOB columns), - -ndb-log-updated-only can also be useful for reducing the size of the master and slave binary logs and avoiding possible replication failures due to exceeding max_allowed_packet.

See Replication and max_allowed_packet, for more information about this issue.

On the slave, you must determine which type of conflict resolution to apply ("latest timestamp wins", "same timestamp wins", or none). This is done using the mysql.ndb_replication system table, on a per-table basis (see The ndb_replication system table).

We refer to the column used for determining updates as a "timestamp" column, but the data type of this column is never TIMESTAMP; rather, its data type should be INT (INTEGER) or BIGINT. This "timestamp" column should also be UNSIGNED and NOT NULL.

Master column control. We can see update operations in terms of "before" and "after" images—that is, the states of the table before and after the update is applied. Normally, when updating a table with a primary key, the "before" image is not of great interest; however, when we need to determine on a per-update basis whether or not to use the updated values on a replication slave, we need to make sure that both images are written to the master's binary log. This is done with the <code>--ndb-log-update-as-write</code> option for <code>mysqld</code>, as described later in this section.

Important

Whether logging of complete rows or of updated columns only is done is decided when the MySQL server is started, and cannot be changed online; you must either restart mysqld, or start a new mysqld instance with different logging options.

Logging Full or Partial Rows (--ndb-log-updated-only Option)

Version Introduced	5.1.19-ndb-6.3.0		
Command-Line Format	ndb-log-updated-only		
Option-File Format	ndb_log_updated_only		
Variable Name	ndb_log_updated_only		
Variable Scope	Global		
Dynamic Variable	Yes		

Permitted Values	
Type	boolean
Default	ON

For purposes of conflict resolution, there are two basic methods of logging rows, as determined by the setting of the --ndb-log-updated-only option for mysqld:

- · Log complete rows
- Log only column data that has been updated—that is, column data whose value has been set, regardless of whether or not this value was actually changed. This is the default behavior.

It is usually sufficient—and more efficient—to log updated columns only; however, if you need to log full rows, you can do so by setting --ndb-log-updated-only to 0 or OFF.

--ndb-log-update-as-write Option: Logging Changed Data as Updates

Version Introduced	5.1.19-ndb-6.3.0, 5.1.22-ndb-6.2.5		
Command-Line Format	ndb-log-update-as-write		
Option-File Format	ndb-log-update-as-write		
Variable Name	ndb_log_update_as_write		
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		
	Type	boolean	
	Default	ON	

The setting of the MySQL Server's --ndb-log-update-as-write option determines whether logging is performed with or without the "before" image. Because conflict resolution is done in the MySQL Server's update handler, it is necessary to control logging on the master such that updates are updates and not writes; that is, such that updates are treated as changes in existing rows rather than the writing of new rows (even though these replace existing rows). This option is turned on by default; in other words, updates are treated as writes. (That is, updates are by default written as write_row events in the binary log, rather than as update_row events.) To turn off the option, start the master mysqld with --ndb-log-update-as-write=0 or --ndb-log-update-as-write=0FF.

Conflict resolution control. Conflict resolution is usually enabled on the server where conflicts can occur. Like logging method selection, it is enabled by entries in the mysql.ndb_replication table.

The ndb_replication system table. To enable conflict resolution, it is necessary to create an ndb_replication table in the mysql system database on the master, the slave, or both, depending on the conflict resolution type and method to be employed. This table is used to control logging and conflict resolution functions on a per-table basis, and has one row per table involved in replication. ndb_replication is created and filled with control information on the server where the conflict is to be resolved. In a simple master-slave setup where data can also be changed locally on the slave this will typically be the slave. In a more complex master-master (2-way) replication schema this will usually be all of the masters involved. Each row in mysql.ndb_replication corresponds to a table being replicated, and specifies how to log and resolve conflicts (that is, which conflict resolution function, if any, to use) for that table. The definition of the mysql.ndb_replication table is shown here:

```
CREATE TABLE mysql.ndb_replication (
   db VARBINARY(63),
   table_name VARBINARY(63),
   server_id INT UNSIGNED,
   binlog_type INT UNSIGNED,
   conflict_fn VARBINARY(128),
   PRIMARY KEY USING HASH (db, table_name, server_id)
) ENGINE=NDB
PARTITION BY KEY(db,table_name);
```

The columns in this table are described in the following list:

• **db.** The name of the database containing the table to be replicated.

- table_name. The name of the table to be replicated.
- server_id. The unique server ID of the MySQL instance (SQL node) where the table resides.
- binlog_type. The type of binary logging to be employed. This is determined as shown in the following table:

Value	Internal Value	Description
0	NBT_DEFAULT	Use server default
1	NBT_NO_LOGGING	Do not log this table in the binary log
2	NBT_UPDATED_ONLY	Only updated attributes are logged
3	NBT_FULL	Log full row, even if not updated (MySQL server default behavior)
4	NBT_USE_UPDATE	(For generating NBT_UPDATED_ONLY_USE_UPDATE and NBT_FULL_USE_UPDATE values only—not intended for separate use)
5	[Not used]	
6	NBT_UPDATED_ONLY_USE_UPDA TE (equal to NBT_UPDATED_ONLY NBT_USE_UPDATE)	Use updated attributes, even if values are unchanged
7	NBT_FULL_USE_UPDATE (equal to NBT_FULL NBT_USE_UPDATE)	Use full row, even if values are unchanged

- conflict_fn. The conflict resolution function to be applied. This function must be specified as one of the following: .
 - NDB\$OLD(column_name). If the value of column_name is the same on both the master and the slave, then the update is applied; otherwise, the update is not applied on the slave and an exception is written to the log. This is illustrated by the following pseudocode:

```
if (master_old_column_value == slave_current_column_value)
   perform_update();
else
   log_exception();
```

This function can be used for "same value wins" conflict resolution. This type of conflict resolution ensures that updates are not applied on the slave from the wrong master.

Important

The column value from the master's "before" image is used by this function.

This conflict resolution function is available beginning with MySQL Cluster NDB 6.3.4.

• NDB\$MAX(column_name). If the "timestamp" column value for a given row coming from the master is higher than that on the slave, it is applied; otherwise it is not applied on the slave. This is illustrated by the following pseudocode:

```
if (master_new_column_value > slave_current_column_value)
    perform_update();
```

This function can be used for "greatest timestamp wins" conflict resolution. This type of conflict resolution ensures that, in the event of a conflict, the version of the row that was most recently updated is the version that persists.

Important

The column value from the master's "after" image is used by this function.

This conflict resolution function is available beginning with MySQL Cluster NDB 6.3.0.

• NDB\$MAX_DELETE_WIN(column_name). This is a variation on NDB\$MAX(). Due to the fact that no timestamp is available for a delete operation, a delete using NDB\$MAX() is in fact processed as NDB\$OLD. However, for some use cases, this is not optimal. For NDB\$MAX_DELETE_WIN(), if the "timestamp" column value for a given row adding or updating an existing row coming from the master is higher than that on the slave, it is applied. However, delete operations are treated as always having the higher value. This is illustrated in the following pseudocode:

This function can be used for "greatest timestamp, delete wins" conflict resolution. This type of conflict resolution ensures that, in the event of a conflict, the version of the row that was deleted or (otherwise) most recently updated is the version that persists.

This conflict resolution function is available beginning with MySQL Cluster NDB 6.3.31 and MySQL Cluster NDB 7.0.11.

Note

As with NDB\$MAX(), the column value from the master's "after" image is the value used by this function.

NULL. Indicates that conflict resolution is not to be used for the corresponding table.

Status information. Beginning with MySQL Cluster NDB 6.3.3, a server status variable Ndb_conflict_fn_max provides a count of the number of times that a row was not applied on the current SQL node due to "greatest timestamp wins" conflict resolution since the last time that mysqld was started.

Beginning with MySQL Cluster NDB 6.3.4, the number of times that a row was not applied as the result of "same timestamp wins" conflict resolution on a given mysqld since the last time it was restarted is given by the global status variable Ndb_conflict_fn_old. In addition to incrementing Ndb_conflict_fn_old, the primary key of the row that was not used is inserted into an *exceptions table*, as explained later in this section.

Additional requirements for "Same timestamp wins" conflict resolution. To use the NDB\$OLD() conflict resolution function, it is also necessary to create an exceptions table corresponding to each NDB table for which this type of conflict resolution is to be employed. The name of this table is that of the table for which "same timestamp wins" conflict resolution is to be applied, with the string \$EX appended. (For example, if the name of the original table is mytable, the name of the corresponding exception table name should be mytable\$EX.) This table is created as follows:

```
CREATE TABLE original_table$EX (
    server_id INT UNSIGNED,
    master_server_id INT UNSIGNED,
    master_epoch BIGINT UNSIGNED,
    count INT UNSIGNED,
    original_table_pk_columns,
    [additional_columns,]
    PRIMARY KEY(server_id, master_server_id, master_epoch, count)
) ENGINE=NDB;
```

The first four columns are required. Following these columns, the columns making up the original table's primary key should be copied in the order in which they are used to define the primary key of the original table.

Note

The names of the first four columns and the columns matching the original table's primary key columns are not critical; however, we suggest for reasons of clarity and consistency, that you use the names shown here for the server_id, master_server_id, master_epoch, and count columns, and that you use the same names as in the original table for the columns matching those in the original table's primary key.

The data types for the columns duplicating the primary key columns of the original table should be the same as for (or larger than) the original columns.

Additional columns may optionally be defined following these columns, but not before any of them; any such extra columns cannot be NOT NULL. The exception table's primary key must be defined as shown. The exception table must use the NDB storage engine. An example of use for NDB\$OLD() and an exception table is given later in this section.

Important

The mysql.ndb_replication table is read when a data table is set up for replication, so the row corresponding to a table to be replicated must be inserted into mysql.ndb_replication before the table to be replicated is created

Examples. The following examples assume that you have already a working MySQL Cluster replication setup, as described in Section 6.5, "Preparing the MySQL Cluster for Replication", and Section 6.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

- NDB\$MAX() example. Suppose you wish to enable "greatest timestamp wins" conflict resolution on table test.tl, using column mycol as the "timestamp". This can be done using the following steps:
 - 1. Make sure that you have started the master mysqld with --ndb-log-update-as-write=OFF.

2. On the master, perform this INSERT statement:

```
INSERT INTO mysql.ndb_replication
  VALUES ('test', 't1', 0, NULL, 'NDB$MAX(mycol)');
```

Inserting a 0 into the server_id indicates that all SQL nodes accessing this table should use conflict resolution. If you want to use conflict resolution on a specific mysqld only, use the actual server ID.

Inserting NULL into the $binlog_type$ column has the same effect as inserting 0 (NBT_DEFAULT); the server default is used.

Create the test.t1 table:

Now, when updates are done on this table, conflict resolution is applied, and the version of the row having the greatest value for mycol is written to the slave.

Note

Other binlog_type options—such as NBT_UPDATED_ONLY_USE_UPDATE should be used to control logging on the master using the ndb_replication table rather than by using command-line options.

• NDB\$OLD() example. Suppose an NDB table such as the one defined here is being replicated, and you wish to enable "same timestamp wins" conflict resolution for updates to this table:

```
CREATE TABLE test.t2 (
    a INT UNSIGNED NOT NULL,
    b CHAR(25) NOT NULL,
    columns,
    mycol INT UNSIGNED NOT NULL,
    columns,
    PRIMARY KEY pk (a, b)
) ENGINE=NDB;
```

The following steps are required, in the order shown:

 First—and prior to creating test.t2—you must insert a row into the mysql.ndb_replication table, as shown here:

```
INSERT INTO mysql.ndb_replication
   VALUES ('test', 't2', 0, NULL, 'NDB$OLD(mycol)');
```

Possible values for the binlog_type column are shown earlier in this section. The value 'NDB\$OLD(mycol)' should be inserted into the conflict_fn column.

2. Create an appropriate exceptions table for test.t2. The table creation statement shown here includes all required columns; any additional columns must be declared following these columns, and before the definition of the table's primary key.

```
CREATE TABLE test.t2$EX (
    server_id SMALLINT UNSIGNED,
    master_server_id INT UNSIGNED,
    master_epoch BIGINT UNSIGNED,
    count BIGINT UNSIGNED,
    a INT UNSIGNED NOT NULL,
    b CHAR(25) NOT NULL,
    [additional_columns,]
    PRIMARY KEY(server_id, master_server_id, master_epoch, count)
) ENGINE=NDB;
```

Create the table test.t2 as shown previously.

These steps must be followed for every table for which you wish to perform conflict resolution using NDB\$OLD(). For each such table, there must be a corresponding row in mysql.ndb_replication, and there must be an exceptions table in the same database as the table being replicated.

Appendix A. MySQL 5.1 FAQ: MySQL Cluster

In the following section, we answer questions that are frequently asked about MySQL Cluster and the NDBCLUSTER storage engine.

Questions

- A.1: Which versions of the MySQL software support Cluster? Do I have to compile from source?
- A.2: What happened to MySQL Cluster NDB 6.4?
- A.3: What do "NDB" and "NDBCLUSTER" mean?
- A.4: What is the difference between using MySQL Cluster vs using MySQL replication?
- A.5: Do I need to do any special networking to run MySQL Cluster? How do computers in a cluster communicate?
- A.6: How many computers do I need to run a MySQL Cluster, and why?
- A.7: What do the different computers do in a MySQL Cluster?
- A.8: When I run the SHOW command in the MySOL Cluster management client, I see a line of output that looks like this:

```
id=2 @10.100.10.32 (Version: 5.1.59, Nodegroup: 0, Master)
```

What is a "master node", and what does it do? How do I configure a node so that it is the master?

- A.9: With which operating systems can I use Cluster?
- A.10: What are the hardware requirements for running MySQL Cluster?
- A.11: How much RAM do I need to use MySQL Cluster? Is it possible to use disk memory at all?
- A.12: What file systems can I use with MySQL Cluster? What about network file systems or network shares?
- A.13: Can I run MySQL Cluster nodes inside virtual machines (such as those created by VMWare, Parallels, or Xen)?
- A.14: I am trying to populate a MySQL Cluster database. The loading process terminates prematurely and I get an error message like this one: ERROR 1114: THE TABLE 'MY_CLUSTER_TABLE' IS FULL Why is this happening?
- A.15: MySQL Cluster uses TCP/IP. Does this mean that I can run it over the Internet, with one or more nodes in remote locations?
- A.16: Do I have to learn a new programming or query language to use MySQL Cluster?
- A.17: How do I find out what an error or warning message means when using MySQL Cluster?
- A.18: Is MySQL Cluster transaction-safe? What isolation levels are supported?
- A.19: What storage engines are supported by MySQL Cluster?
- A.20: In the event of a catastrophic failure—say, for instance, the whole city loses power and my UPS fails—would I lose all
 my data?
- A.21: Is it possible to use FULLTEXT indexes with MySQL Cluster?
- A.22: Can I run multiple nodes on a single computer?
- A.23: Can I add data nodes to a MySQL Cluster without restarting it?
- A.24: Are there any limitations that I should be aware of when using MySQL Cluster?
- A.25: How do I import an existing MySQL database into a MySQL Cluster?
- A.26: How do cluster nodes communicate with one another?
- A.27: What is an arbitrator?
- A.28: What data types are supported by MySQL Cluster?

- A.29: How do I start and stop MySQL Cluster?
- A.30: What happens to MySQL Cluster data when the cluster is shut down?
- A.31: Is it a good idea to have more than one management node for a MySQL Cluster?
- A.32: Can I mix different kinds of hardware and operating systems in one MySQL Cluster?
- A.33: Can I run two data nodes on a single host? Two SQL nodes?
- A.34: Can I use host names with MySQL Cluster?
- A.35: Does MySQL Cluster support IPv6?
- A.36: How do I handle MySQL users in a MySQL Cluster having multiple MySQL servers?
- A.37: How do I continue to send queries in the event that one of the SQL nodes fails?
- A.38: How do I back up and restore a MySQL Cluster?
- A.39: What is an "angel process"?

Questions and Answers

A.1: Which versions of the MySQL software support Cluster? Do I have to compile from source?

Beginning with MySQL 5.1.24, MySQL Cluster is no longer supported in standard MySQL Server 5.1 releases. Instead, MySQL Cluster is now released as a separate product. Currently, two MySQL Cluster release series are available for production use:

- MySQL Cluster NDB 6.3. This series is now Generally Available (GA) for use in production. The latest MySQL Cluster NDB 6.3 sources and binaries can be obtained from http://dev.mysql.com/downloads/cluster/.
- MySQL Cluster NDB 7.0. This series is now Generally Available (GA) for use in production. The latest MySQL Cluster NDB 7.0 sources can be obtained from http://dev.mysql.com/downloads/cluster/.

You should use MySQL NDB Cluster NDB 6.3 or 7.0 for any new deployments; if you are already using MySQL 5.1 with clustering support, you should upgrade to one of these MySQL Cluster release series as soon as possible. For an overview of improvements made in MySQL Cluster NDB 6.3 and 7.0, see Section 1.4.4, "MySQL Cluster Development in MySQL Cluster NDB 6.3", and Section 1.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", respectively.

You can determine whether your MySQL Server has NDBCLUSTER support using either of the statements SHOW VARIABLES LIKE 'have %' or SHOW ENGINES.

A.2: What happened to MySQL Cluster NDB 6.4?

Because of the number and impact of new features introduced into MySQL Cluster following the General Availability of MySQL Cluster NDB 6.3, it was decided that the following release series represented a "major" new release series rather than a "minor" one, and should be known as MySQL Cluster 7.0.

The earliest development versions of MySQL Cluster NDB 7.0 were originally designated "MySQL Cluster 6.4", and the first four releases in this series were identified as MySQL Cluster NDB 6.4.0 through NDB 6.4.3. MySQL Cluster NDB 7.0 release; it is the successor to MySQL Cluster NDB 6.4.3.

For more information about MySQL Cluster NDB 7.0, see Section 1.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and Changes in MySQL Cluster NDB 7.0.

A.3: What do "NDB" and "NDBCLUSTER" mean?

"NDB" stands for "Network Database". NDB and NDBCLUSTER are both names for the storage engine that enables clustering support in MySQL. While our developers prefer NDB, either name is correct; both names appear in our documentation, and either name can be used in the ENGINE option of a CREATE TABLE statement for creating a MySQL Cluster table.

A.4: What is the difference between using MySQL Cluster vs using MySQL replication?

In traditional MySQL replication, a master MySQL server updates one or more slaves. Transactions are committed sequentially, and a slow transaction can cause the slave to lag behind the master. This means that if the master fails, it is possible that the slave might not have recorded the last few transactions. If a transaction-safe engine such as InnoDB is being used, a transaction will either be complete on the slave or not applied at all, but replication does not guarantee that all data on the master and the slave will be consistent at all times. In MySQL Cluster, all data nodes are kept in synchrony, and a transaction committed by any one data

node is committed for all data nodes. In the event of a data node failure, all remaining data nodes remain in a consistent state.

In short, whereas standard MySQL replication is asynchronous, MySQL Cluster is synchronous.

We have implemented (asynchronous) replication for Cluster in MySQL 5.1 and later. *MySQL Cluster Replication* (also sometimes known as "geo-replication") includes the capability to replicate both between two MySQL Clusters, and from a MySQL Cluster to a non-Cluster MySQL server. However, we do *not* plan to backport this functionality to MySQL 5.1. See MySQL Cluster Replication.

A.5: Do I need to do any special networking to run MySQL Cluster? How do computers in a cluster communicate?

MySQL Cluster is intended to be used in a high-bandwidth environment, with computers connecting using TCP/IP. Its performance depends directly upon the connection speed between the cluster's computers. The minimum connectivity requirements for MySQL Cluster include a typical 100-megabit Ethernet network or the equivalent. We recommend you use gigabit Ethernet whenever available.

The faster SCI protocol is also supported, but requires special hardware. See Section 3.5, "Using High-Speed Interconnects with MySQL Cluster", for more information about SCI.

A.6: How many computers do I need to run a MySQL Cluster, and why?

A minimum of three computers is required to run a viable cluster. However, the minimum *recommended* number of computers in a MySQL Cluster is four: one each to run the management and SQL nodes, and two computers to serve as data nodes. The purpose of the two data nodes is to provide redundancy; the management node must run on a separate machine to guarantee continued arbitration services in the event that one of the data nodes fails.

To provide increased throughput and high availability, you should use multiple SQL nodes (MySQL Servers connected to the cluster). It is also possible (although not strictly necessary) to run multiple management servers.

A.7: What do the different computers do in a MySQL Cluster?

A MySQL Cluster has both a physical and logical organization, with computers being the physical elements. The logical or functional elements of a cluster are referred to as *nodes*, and a computer housing a cluster node is sometimes referred to as a *cluster host*. There are three types of nodes, each corresponding to a specific role within the cluster. These are:

- Management node. This node provides management services for the cluster as a whole, including startup, shutdown, backups, and configuration data for the other nodes. The management node server is implemented as the application ndb_mgmd; the management client used to control MySQL Cluster is ndb_mgm. See Section 4.4, "ndb_mgmd The MySQL Cluster Management Server Daemon", and Section 4.5, "ndb_mgm The MySQL Cluster Management Client", for information about these programs.
- **Data node.** This type of node stores and replicates data. Data node functionality is handled by instances of the NDB data node process ndbd. For more information, see Section 4.2, "ndbd The MySQL Cluster Data Node Daemon".
- SQL node. This is simply an instance of MySQL Server (mysqld) that is built with support for the NDBCLUSTER storage engine and started with the --ndb-cluster option to enable the engine and the --ndb-connectstring option to enable it to connect to a MySQL Cluster management server. For more about these options, see Section 3.4.2, "mysqld Command Options for MySQL Cluster".

Note

An *API node* is any application that makes direct use of Cluster data nodes for data storage and retrieval. An SQL node can thus be considered a type of API node that uses a MySQL Server to provide an SQL interface to the Cluster. You can write such applications (that do not depend on a MySQL Server) using the NDB API, which supplies a direct, object-oriented transaction and scanning interface to MySQL Cluster data; see MySQL Cluster API Overview: The NDB API, for more information.

A.8: When I run the SHOW command in the MySQL Cluster management client, I see a line of output that looks like this:

```
id=2 @10.100.10.32 (Version: 5.1.59, Nodegroup: 0, Master)
```

What is a "master node", and what does it do? How do I configure a node so that it is the master?

The simplest answer is, "It's not something you can control, and it's nothing that you need to worry about in any case, unless you're a software engineer writing or analyzing the MySQL Cluster source code".

If you don't find that answer satisfactory, here's a longer and more technical version:

A number of mechanisms in MySQL Cluster require distributed coordination among the data nodes. These distributed algorithms and protocols include global checkpointing, DDL (schema) changes, and node restart handling. To make this coordination simpler,

the data nodes "elect" one of their number to be a "master". There is no user-facing mechanism for influencing this selection, which is is completely automatic; the fact that it is automatic is a key part of MySQL Cluster's internal architecture.

When a node acts as a master for any of these mechanisms, it is usually the point of coordination for the activity, and the other nodes act as "servants", carrying out their parts of the activity as directed by the master. If the node acting as master fails, then the remaining nodes elect a new master. Tasks in progress that were being coordinated by the old master may either fail or be continued by the new master, depending on the actual mechanism involved.

It is possible for some of these different mechanisms and protocols to have different master nodes, but in general the same master is chosen for all of them. The node indicated as the master in the output of SHOW in the management client is actually the DICT master (see The DBDICT Block, in the *MySQL Cluster API Developer Guide*, for more information), responsible for coordinating DDL and metadata activity.

MySQL Cluster is designed in such a way that the choice of master has no discernable effect outside the cluster itself. For example, the current master does not have significantly higher CPU or resource usage than the other data nodes, and failure of the master should not have a significantly different impact on the cluster than the failure of any other data node.

A.9: With which operating systems can I use Cluster?

MySQL Cluster is supported on most Unix-like operating systems, including Linux, Mac OS X, and Solaris. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported in production on Microsoft Windows operating systems.

For more detailed information concerning the level of support which is offered for MySQL Cluster on various operating system versions, operating system distributions, and hardware platforms, please refer to http://www.mysql.com/support/supportedplatforms/cluster.html.

A.10: What are the hardware requirements for running MySQL Cluster?

MySQL Cluster should run on any platform for which NDB-enabled binaries are available. For data nodes and API nodes, faster CPUs and more memory are likely to improve performance, and 64-bit CPUs are likely to be more effective than 32-bit processors. There must be sufficient memory on machines used for data nodes to hold each node's share of the database (see *How much RAM do I Need?* for more information). For a computer which is used only for running the MySQL Cluster management server, the requirements are minimal; a common desktop PC (or the equivalent) is generally sufficient for this task. Nodes can communicate through the standard TCP/IP network and hardware. They can also use the high-speed SCI protocol; however, special networking hardware and software are required to use SCI (see Section 3.5, "Using High-Speed Interconnects with MySQL Cluster").

A.11: How much RAM do I need to use MySQL Cluster? Is it possible to use disk memory at all?

In MySQL 5.1, Cluster is in-memory only. This means that all table data (including indexes) is stored in RAM. Therefore, if your data takes up 1 GB of space and you want to replicate it once in the cluster, you need 2 GB of memory to do so (1 GB per replica). This is in addition to the memory required by the operating system and any applications running on the cluster computers.

If a data node's memory usage exceeds what is available in RAM, then the system will attempt to use swap space up to the limit set for <code>DataMemory</code>. However, this will at best result in severely degraded performance, and may cause the node to be dropped due to slow response time (missed heartbeats). We do not recommend on relying on disk swapping in a production environment for this reason. In any case, once the <code>DataMemory</code> limit is reached, any operations requiring additional memory (such as inserts) will fail.

We have implemented disk data storage for MySQL Cluster in MySQL 5.1 and later but we have no plans to add this capability in MySQL 5.1. See MySQL Cluster Disk Data Tables, for more information.

You can use the following formula for obtaining a rough estimate of how much RAM is needed for each data node in the cluster:

```
(SizeofDatabase \times NumberOfReplicas \times 1.1 ) / NumberOfDataNodes
```

To calculate the memory requirements more exactly requires determining, for each table in the cluster database, the storage space required per row (see Data Type Storage Requirements, for details), and multiplying this by the number of rows. You must also remember to account for any column indexes as follows:

- Each primary key or hash index created for an NDBCLUSTER table requires 21–25 bytes per record. These indexes use IndexMemory.
- Each ordered index requires 10 bytes storage per record, using DataMemory.
- Creating a primary key or unique index also creates an ordered index, unless this index is created with USING HASH. In other words:
 - A primary key or unique index on a Cluster table normally takes up 31 to 35 bytes per record.
 - However, if the primary key or unique index is created with USING HASH, then it requires only 21 to 25 bytes per record.

Note that creating MySQL Cluster tables with USING HASH for all primary keys and unique indexes will generally cause table updates to run more quickly—in some cases by a much as 20 to 30 percent faster than updates on tables where USING HASH was not used in creating primary and unique keys. This is due to the fact that less memory is required (because no ordered indexes are created), and that less CPU must be utilized (because fewer indexes must be read and possibly updated). However, it also means that queries that could otherwise use range scans must be satisfied by other means, which can result in slower selects.

When calculating Cluster memory requirements, you may find useful the ndb_size.pl utility which is available in recent MySQL 5.1 releases. This Perl script connects to a current (non-Cluster) MySQL database and creates a report on how much space that database would require if it used the NDBCLUSTER storage engine. For more information, see Section 4.21, "ndb_size.pl — NDBCLUSTER Size Requirement Estimator".

It is especially important to keep in mind that *every MySQL Cluster table must have a primary key*. The NDB storage engine creates a primary key automatically if none is defined; this primary key is created without USING HASH.

There is no easy way to determine exactly how much memory is being used for storage of Cluster indexes at any given time; however, warnings are written to the Cluster log when 80% of available <code>DataMemory</code> or <code>IndexMemory</code> is in use, and again when use reaches 85%, 90%, and so on.

A.12: What file systems can I use with MySQL Cluster? What about network file systems or network shares?

Generally, any file system that is native to the host operating system should work well with MySQL Cluster. If you find that a given file system works particularly well (or not so especially well) with MySQL Cluster, we invite you to discuss your findings in the MySQL Cluster Forums.

For Windows, we recommend that you use NTFS file systems for MySQL Cluster, just as we do for standard MySQL. We do not test MySQL Cluster with FAT or VFAT file systems. Because of this, we do not recommend their use with MySQL or MySQL Cluster.

MySQL Cluster is implemented as a shared-nothing solution; the idea behind this is that the failure of a single piece of hardware should not cause the failure of multiple cluster nodes, or possibly even the failure of the cluster as a whole. For this reason, the use of network shares or network file systems is not supported for MySQL Cluster. This also applies to shared storage devices such as SANs.

A.13: Can I run MySQL Cluster nodes inside virtual machines (such as those created by VMWare, Parallels, or Xen)?

This is possible but not recommended for a production environment.

We have found that running MySQL Cluster processes inside a virtual machine can give rise to issues with timing and disk subsystems that have a strong negative impact on the operation of the cluster. The behavior of the cluster is often unpredictable in these cases

If an issue can be reproduced outside the virtual environment, then we may be able to provide assistance. Otherwise, we cannot support it at this time.

A.14: I am trying to populate a MySQL Cluster database. The loading process terminates prematurely and I get an error message like this one: ERROR 1114: The TABLE 'MY_CLUSTER_TABLE' IS FULL Why is this happening?

The cause is very likely to be that your setup does not provide sufficient RAM for all table data and all indexes, *including the* primary key required by the NDB storage engine and automatically created in the event that the table definition does not include the definition of a primary key.

It is also worth noting that all data nodes should have the same amount of RAM, since no data node in a cluster can use more memory than the least amount available to any individual data node. For example, if there are four computers hosting Cluster data nodes, and three of these have 3GB of RAM available to store Cluster data while the remaining data node has only 1GB RAM, then each data node can devote at most 1GB to MySQL Cluster data and indexes.

A.15: MySQL Cluster uses TCP/IP. Does this mean that I can run it over the Internet, with one or more nodes in remote locations?

It is *very* unlikely that a cluster would perform reliably under such conditions, as MySQL Cluster was designed and implemented with the assumption that it would be run under conditions guaranteeing dedicated high-speed connectivity such as that found in a LAN setting using 100 Mbps or gigabit Ethernet—preferably the latter. We neither test nor warrant its performance using anything slower than this

Also, it is extremely important to keep in mind that communications between the nodes in a MySQL Cluster are not secure; they are neither encrypted nor safeguarded by any other protective mechanism. The most secure configuration for a cluster is in a private network behind a firewall, with no direct access to any Cluster data or management nodes from outside. (For SQL nodes, you should take the same precautions as you would with any other instance of the MySQL server.) For more information, see Section 5.10, "MySQL Cluster Security Issues".

A.16: Do I have to learn a new programming or query language to use MySQL Cluster?

No. Although some specialized commands are used to manage and configure the cluster itself, only standard (My)SQL statements are required for the following operations:

- Creating, altering, and dropping tables
- · Inserting, updating, and deleting table data
- Creating, changing, and dropping primary and unique indexes

Some specialized configuration parameters and files are required to set up a MySQL Cluster—see Section 3.2, "MySQL Cluster Configuration Files", for information about these.

A few simple commands are used in the MySQL Cluster management client (ndb_mgm) for tasks such as starting and stopping cluster nodes. See Section 5.2, "Commands in the MySQL Cluster Management Client".

A.17: How do I find out what an error or warning message means when using MySQL Cluster?

There are two ways in which this can be done:

- From within the mysql client, use SHOW ERRORS or SHOW WARNINGS immediately upon being notified of the error or warning condition.
- From a system shell prompt, use perror --ndb error_code.

A.18: Is MySQL Cluster transaction-safe? What isolation levels are supported?

Yes. For tables created with the NDB storage engine, transactions are supported. Currently, MySQL Cluster supports only the READ COMMITTED transaction isolation level.

A.19: What storage engines are supported by MySQL Cluster?

Clustering with MySQL is supported only by the NDB storage engine. That is, in order for a table to be shared between nodes in a MySQL Cluster, the table must be created using ENGINE=NDB (or the equivalent option ENGINE=NDBCLUSTER).

It is possible to create tables using other storage engines (such as MyISAM or InnoDB) on a MySQL server being used with a MySQL Cluster, but these non-NDB tables do *not* participate in clustering; each such table is strictly local to the individual MySQL server instance on which it is created.

A.20: In the event of a catastrophic failure—say, for instance, the whole city loses power and my UPS fails—would I lose all my data?

All committed transactions are logged. Therefore, although it is possible that some data could be lost in the event of a catastrophe, this should be quite limited. Data loss can be further reduced by minimizing the number of operations per transaction. (It is not a good idea to perform large numbers of operations per transaction in any case.)

A.21: Is it possible to use **FULLTEXT** indexes with MySQL Cluster?

FULLTEXT indexing is not supported by any storage engine other than MyISAM. We are working to add this capability to MySQL Cluster tables in a future release.

A.22: Can I run multiple nodes on a single computer?

It is possible but not always advisable. One of the chief reasons to run a cluster is to provide redundancy. To obtain the full benefits of this redundancy, each node should reside on a separate machine. If you place multiple nodes on a single machine and that machine fails, you lose all of those nodes. For this reason, if you do run multiple data nodes on a single machine, it is *extremely* important that they be set up in such a way that the failure of this machine does not cause the loss of all the data nodes in a given node group.

Given that MySQL Cluster can be run on commodity hardware loaded with a low-cost (or even no-cost) operating system, the expense of an extra machine or two is well worth it to safeguard mission-critical data. It also worth noting that the requirements for a cluster host running a management node are minimal. This task can be accomplished with a 300 MHz Pentium or equivalent CPU and sufficient RAM for the operating system, plus a small amount of overhead for the ndb_mgmd and ndb_mgm processes.

It is acceptable to run multiple cluster data nodes on a single host that has multiple CPUs, cores, or both. Beginning with MySQL Cluster NDB 6.4, there is also a special multi-threaded version of the data node binary intended for use on such systems. For more information, see Section 4.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

It is also possible in some cases to run data nodes and SQL nodes concurrently on the same machine; how well such an arrangement performs is dependent on a number of factors such as number of cores and CPUs as well as the amount of disk and memory available to the data node and SQL node processes, and you must take these factors into account when planning such a configuration.

A.23: Can I add data nodes to a MySQL Cluster without restarting it?

Beginning with MySQL Cluster NDB 6.4, it is possible to add new data nodes to a running MySQL Cluster without taking it off-line. For more information, see Section 5.12, "Adding MySQL Cluster Data Nodes Online".

For other types of MySQL Cluster nodes, a rolling restart is all that is required (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").

In MySQL Cluster NDB 6.3 and earlier, it was not possible to add new data nodes without shutting down and restarting the MySQL Cluster.

A.24: Are there any limitations that I should be aware of when using MySQL Cluster?

Limitations on NDB tables in MySQL 5.1 (including MySQL Cluster NDB 6.x) include the following:

- Temporary tables are not supported; a CREATE TEMPORARY TABLE statement using ENGINE=NDB or ENGINE=NDBCLUSTER fails with an error.
- The only types of user-defined partitioning supported for NDBCLUSTER tables are KEY and LINEAR KEY. (Beginning with MySQL 5.1.12, attempting to create an NDB table using any other partitioning type fails with an error.)
- FULLTEXT indexes are not supported.
- Index prefixes are not supported. Only complete columns may be indexed.
- Spatial indexes are not supported (although spatial columns can be used). See Spatial Extensions.
- Prior to MySQL Cluster NDB 6.3.19, the NDBCLUSTER storage engine did not support partial transactions or partial rollbacks
 of transactions. Beginning with MySQL Cluster NDB 6.3.19, this limitation has been removed, and the behavior of NDBCLUSTER is now in line with that of other transactional storage engines (such as InnoDB) that can roll back individual statements.
- Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the maximum number of attributes allowed per table was 128; beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this limit is increased to 512. Attribute names cannot be any longer than 31 characters. For each table, the maximum combined length of the table and database names is 122 characters.
- The maximum size for a table row is 8 kilobytes, not counting BLOB values. There is no set limit for the number of rows per table. Table size limits depend on a number of factors, in particular on the amount of RAM available to each data node.
- The NDBCLUSTER engine does not support foreign key constraints. As with MyISAM tables, if these are specified in a CRE-ATE TABLE or ALTER TABLE statement, they are ignored.

For a complete listing of limitations in MySQL Cluster, see Section 1.6, "Known Limitations of MySQL Cluster". For information about limitations in MySQL Cluster 5.0 that are lifted in MySQL 5.1, MySQL Cluster NDB 6.x, or MySQL Cluster NDB 7.0, see Section 1.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x".

A.25: How do I import an existing MySQL database into a MySQL Cluster?

You can import databases into MySQL Cluster much as you would with any other version of MySQL. Other than the limitations mentioned elsewhere in this FAQ, the only other special requirement is that any tables to be included in the cluster must use the NDB storage engine. This means that the tables must be created with ENGINE=NDB or ENGINE=NDBCLUSTER.

It is also possible to convert existing tables that use other storage engines to NDBCLUSTER using one or more ALTER TABLE statement. However, the definition of the table must be compatible with the NDBCLUSTER storage engine prior to making the conversion. In MySQL 5.1, an additional workaround is also required; see Section 1.6, "Known Limitations of MySQL Cluster", for details.

A.26: How do cluster nodes communicate with one another?

Cluster nodes can communicate through any of three different transport mechanisms: TCP/IP, SHM (shared memory), and SCI (Scalable Coherent Interface). Where available, SHM is used by default between nodes residing on the same cluster host; however, this is considered experimental. SCI is a high-speed (1 gigabit per second and higher), high-availability protocol used in building

scalable multi-processor systems; it requires special hardware and drivers. See Section 3.5, "Using High-Speed Interconnects with MySQL Cluster", for more about using SCI as a transport mechanism for MySQL Cluster.

A.27: What is an arbitrator?

If one or more data nodes in a cluster fail, it is possible that not all cluster data nodes will be able to "see" one another. In fact, it is possible that two sets of data nodes might become isolated from one another in a network partitioning, also known as a "split-brain" scenario. This type of situation is undesirable because each set of data nodes tries to behave as though it is the entire cluster. An arbitrator is required to decide between the competing sets of data nodes.

When all data nodes in at least one node group are alive, network partitioning is not an issue, because no single subset of the cluster can form a functional cluster on its own. The real problem arises when no single node group has all its nodes alive, in which case network partitioning (the "split-brain" scenario) becomes possible. Then an arbitrator is required. All cluster nodes recognize the same node as the arbitrator, which is normally the management server; however, it is possible to configure any of the MySQL Servers in the cluster to act as the arbitrator instead. The arbitrator accepts the first set of cluster nodes to contact it, and tells the remaining set to shut down. Arbitrator selection is controlled by the ArbitrationRank configuration parameter for MySQL Server and management server nodes. In MySQL Cluster NDB 7.0.7 and later, you can also use the ArbitrationRank configuration parameter to control the arbitrator selection process. For more information about these parameters, see Section 3.2.5, "Defining a MySQL Cluster Management Server".

The role of arbitrator does not in and of itself impose any heavy demands upon the host so designated, and thus the arbitrator host does not need to be particularly fast or to have extra memory especially for this purpose.

A.28: What data types are supported by MySQL Cluster?

MySQL Cluster NDB 6.x and later supports all of the usual MySQL data types, including those associated with MySQL's spatial extensions; however, the NDB storage engine does not support spatial indexes. (Spatial indexes are supported only by MyISAM; see Spatial Extensions, for more information.) In addition, there are some differences with regard to indexes when used with NDB tables.

Note

MySQL Cluster Disk Data tables (that is, tables created with TABLESPACE ... STORAGE DISK ENGINE=NDB or TABLESPACE ... STORAGE DISK ENGINE=NDBCLUSTER) have only fixed-width rows. This means that (for example) each Disk Data table record containing a VARCHAR (255) column requires space for 255 characters (as required for the character set and collation being used for the table), regardless of the actual number of characters stored therein.

See Section 1.6, "Known Limitations of MySQL Cluster", for more information about these issues.

A.29: How do I start and stop MySQL Cluster?

It is necessary to start each node in the cluster separately, in the following order:

- 1. Start the management node, using the ndb_mgmd command.
 - You must include the -f or --config-file option to tell the management node where its configuration file can be found.
- 2. Start each data node with the ndbd command.
 - Each data node must be started with the -c or --connect-string option so that the data node knows how to connect to the management server.
- 3. Start each MySQL Server (SQL node) using your preferred startup script, such as mysqld_safe.
 - Each MySQL Server must be started with the --ndbcluster and --ndb-connectstring options. These options cause mysqld to enable NDBCLUSTER storage engine support and how to connect to the management server.

Each of these commands must be run from a system shell on the machine housing the affected node. (You do not have to be physically present at the machine—a remote login shell can be used for this purpose.) You can verify that the cluster is running by starting the NDB management client ndb_mgm on the machine housing the management node and issuing the SHOW or ALL STATUS command.

To shut down a running cluster, issue the command SHUTDOWN in the management client. Alternatively, you may enter the following command in a system shell:

shell> ndb_mgm -e "SHUTDOWN"

(The quotation marks in this example are optional, since there are no spaces in the command string following the -e option; in addition, the SHUTDOWN command, like other management client commands, is not case-sensitive.)

Either of these commands causes the ndb_mgm, ndb_mgm, and any ndbd processes to terminate gracefully. MySQL servers running as SQL nodes can be stopped using mysqladmin shutdown.

For more information, see Section 5.2, "Commands in the MySQL Cluster Management Client", and Section 2.6, "Safe Shutdown and Restart of MySQL Cluster".

A.30: What happens to MySQL Cluster data when the cluster is shut down?

The data that was held in memory by the cluster's data nodes is written to disk, and is reloaded into memory the next time that the cluster is started

A.31: Is it a good idea to have more than one management node for a MySQL Cluster?

It can be helpful as a fail-safe. Only one management node controls the cluster at any given time, but it is possible to configure one management node as primary, and one or more additional management nodes to take over in the event that the primary management node fails.

See Section 3.2, "MySQL Cluster Configuration Files", for information on how to configure MySQL Cluster management nodes.

A.32: Can I mix different kinds of hardware and operating systems in one MySQL Cluster?

Yes, as long as all machines and operating systems have the same "endianness" (all big-endian or all little-endian). We are working to overcome this limitation in a future MySQL Cluster release.

It is also possible to use software from different MySQL Cluster releases on different nodes. However, we support this only as part of a rolling upgrade procedure (see Section 5.4, "Performing a Rolling Restart of a MySQL Cluster").

A.33: Can I run two data nodes on a single host? Two SQL nodes?

Yes, it is possible to do this. In the case of multiple data nodes, it is advisable (but not required) for each node to use a different data directory. If you want to run multiple SQL nodes on one machine, each instance of mysqld must use a different TCP/IP port. However, in MySQL 5.1, running more than one cluster node of a given type per machine is generally not encouraged or supported for production use.

We also advise against running data nodes and SQL nodes together on the same host, since the ndbd and mysqld processes may compete for memory.

A.34: Can I use host names with MySQL Cluster?

Yes, it is possible to use DNS and DHCP for cluster hosts. However, if your application requires "five nines" availability, you should use fixed (numeric) IP addresses, since making communication between Cluster hosts dependent on services such as DNS and DHCP introduces additional potential points of failure.

A.35: Does MySQL Cluster support IPv6?

Beginning with MySQL Cluster NDB 6.4, IPv6 is supported for connections between SQL nodes (MySQL servers). However, connections between all other types of nodes must use IPv4.

In practical terms, this means that you can use IPv6 for replication between MySQL Clusters, but connections between nodes in the same MySQL Cluster must use IPv4. For more information, see Section 6.3, "Known Issues in MySQL Cluster Replication".

A.36: How do I handle MySQL users in a MySQL Cluster having multiple MySQL servers?

MySQL user accounts and privileges are *not* automatically propagated between different MySQL servers accessing the same MySQL Cluster. Therefore, you must make sure that these are copied between the SQL nodes yourself. You can do this manually, or automate the task with scripts.

Warning

Do not attempt to work around this issue by converting the MySQL system tables to use the NDBCLUSTER storage engine. Only the MyISAM storage engine is supported for these tables.

A.37: How do I continue to send queries in the event that one of the SQL nodes fails?

MySQL Cluster does not provide any sort of automatic failover between SQL nodes. Your application must be prepared to handlethe loss of SQL nodes and to fail over between them.

A.38: How do I back up and restore a MySQL Cluster?

You can use the NDB native backup and restore functionality in the MySQL Cluster management client and the ndb_restore program. See Section 5.3, "Online Backup of MySQL Cluster", and Section 4.17, "ndb_restore — Restore a MySQL Cluster Backup".

You can also use the traditional functionality provided for this purpose in mysqldump and the MySQL server. See mysqldump, for more information.

A.39: What is an "angel process"?

This process monitors and, if necessary, attempts to restart the data node process. If you check the list of active processes on your system after starting ndbd, you can see that there are actually 2 processes running by that name, as shown here (we omit the output from ndb_mgmd and ndbd for brevity):

```
shell> ./ndb_mgmd
shell> ps aux | grep ndb
me 23002 0.0 0.0 122948
me 23025 0.0 0.0 5284
                                                  3104 ?
                                                                                              0:00 ./ndb_mgmd
                                                   820 pts/2
                                                                                              0:00 grep ndb
                                        5284
                                                                                 14:14
shell> ./ndbd -c 127.0.0.1 --initial
shell> ps aux | grep ndb

me 23002 0.0 0.0 123080 3356

me 23096 0.0 0.0 35876 2036

me 23097 1.0 2.4 524116 91096
                                                                                              0:00 ./ndb_mgmd
                                                                                              0:00 ./ndbd -c 127.0.0.1 --initial
0:00 ./ndbd -c 127.0.0.1 --initial
                                                  2036 ?
91096 ?
                                                                         Ss
Sl
                                                                                 14:14
14:14
                                                    812 pts/2
me
             23168
                       0.0
                               0.0
                                         5284
                                                                                 14:15
                                                                                              0:00 grep ndb
```

The ndbd process showing 0 memory and CPU usage is the angel process. It actually does use a very small amount of each, of course. It simply checks to see if the main ndbd process (the primary data node process that actually handles the data) is running. If permitted to do so (for example, if the StopOnError configuration parameter is set to false—see Section 3.3.1, "MySQL Cluster Data Node Configuration Parameters"), the angel process tries to restart the primary data node process.

Appendix B. Licenses for Third-Party Components

The following is a list of the libraries we have included with the MySQL Server source and components used to test MySQL. We are thankful to all individuals that have created these. Some of the components require that their licensing terms be included in the documentation of products that include them. Cross references to these licensing terms are given with the applicable items in the list.

Bjorn Benson

For his safe_malloc (memory checker) package which is used in when you build MySQL using one of the BUILD/compile-*-debug scripts or by manually setting the -DSAFEMALLOC flag.

GroupLens Research Project

The MySQL Quality Assurance team would like to acknowledge the use of the MovieLens Data Sets (10 million ratings and 100,000 tags for 10681 movies by 71567 users) to help test MySQL products and to thank the GroupLens Research Project at the University of Minnesota for making the data sets available.

MySQL 5.1

- Section B.4, "dtoa.c License"
- Section B.5, "Editline Library (libedit) License"
- Section B.6, "FindGTest.cmake License"
- Section B.7, "Fred Fish's Dbug Library License"
- Section B.8, "getarg License"
- Section B.10, "GNU General Public License Version 2.0, June 1991"
- Section B.12, "GNU Libtool License"
- Section B.13, "GNU Readline License"
- Section B.14, "Google Controlling Master Thread I/O Rate Patch License"
- Section B.16, "Google SMP Patch License"
- Section B.17, "lib_sql.cc License"
- Section B.23, "md5 (Message-Digest Algorithm 5) License"
- Section B.25, "nt_servc (Windows NT Service class library) License"
- Section B.28, "Percona Multiple I/O Threads Patch License"
- Section B.29, "RegEX-Spencer Library License"
- Section B.30, "RFC 3174 US Secure Hash Algorithm 1 (SHA1) License"
- Section B.31, "Richard A. O'Keefe String Library License"
- Section B.34, "zlib License"

MySQL Cluster

- Section B.2, "ANTLR 3 License"
- Section B.4. "dtoa.c License"
- Section B.5, "Editline Library (libedit) License"
- Section B.6, "FindGTest.cmake License"

- Section B.7, "Fred Fish's Dbug Library License"
- Section B.8, "getarg License"
- Section B.10, "GNU General Public License Version 2.0, June 1991"
- Section B.12, "GNU Libtool License"
- Section B.13, "GNU Readline License"
- Section B.14, "Google Controlling Master Thread I/O Rate Patch License"
- Section B.15, "Google Perftools (TCMalloc utility) License"
- Section B.16, "Google SMP Patch License"
- Section B.17, "lib_sql.cc License"
- Section B.18, "libevent License"
- Section B.19, "Linux-PAM License"
- Section B.23, "md5 (Message-Digest Algorithm 5) License"
- Section B.24, "memcached License"
- Section B.25, "nt_servc (Windows NT Service class library) License"
- Section B.26, "OpenPAM License"
- Section B.28, "Percona Multiple I/O Threads Patch License"
- Section B.29, "RegEX-Spencer Library License"
- Section B.30, "RFC 3174 US Secure Hash Algorithm 1 (SHA1) License"
- Section B.31, "Richard A. O'Keefe String Library License"
- Section B.32, "SHA-1 in C License"
- Section B.34, "zlib License"

MySQL Connector/C

- Section B.7, "Fred Fish's Dbug Library License"
- Section B.29, "RegEX-Spencer Library License"
- Section B.30, "RFC 3174 US Secure Hash Algorithm 1 (SHA1) License"
- Section B.34, "zlib License"

MySQL Connector/CPP

• Section B.3, "Boost Library License"

MySQL Connector/J

- Section B.1, "Ant-Contrib License"
- Section B.33, "Simple Logging Facade for Java (SLF4J) License"

MySQL Connector/Net

- Section B.30, "RFC 3174 US Secure Hash Algorithm 1 (SHA1) License"
- Section B.34, "zlib License"
- Section B.35, "ZLIB.NET License"

MySQL Proxy

- Section B.9, "GLib License (for MySQL Proxy)"
- Section B.11, "GNU Lesser General Public License Version 2.1, February 1999"
- Section B.18, "libevent License"
- Section B.20, "LPeg Library License"
- Section B.21, "Lua (liblua) License"
- Section B.22, "LuaFileSystem Library License"
- Section B.27, "PCRE License"

B.1. Ant-Contrib License

The following software may be included in this product: Ant-Contrib

```
Copyright (c) 2001-2003 Ant-Contrib project. All rights reserved. Licensed under the Apache 1.1 License Agreement, a copy of which is reproduced below.
The Apache Software License, Version 1.1
Copyright (c) 2001-2003 Ant-Contrib project. All rights reserved.
  Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions \frac{1}{2}
   1. Redistributions of source code must retain the above copyright
          notice, this list of conditions and the following disclaimer
   2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the
          distribution.
  3. The end-user documentation included with the redistribution, if any, must include the following acknowlegement:
    "This product includes software developed by the Ant-Contrib project (http://sourceforge.net/projects/ant-contrib)."
    Alternately, this acknowlegement may appear in the software itself, if and wherever such third-party acknowlegements normally appear.
   4. The name Ant-Contrib must not be used to endorse or promote
          products derived from this software without prior written permission. For written permission, please contact ant-contrib-developers@lists.sourceforge.net.
  5. Products derived from this software may not be called "Ant-Contrib" nor may "Ant-Contrib" appear in their names without prior written permission of the Ant-Contrib project.
  THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE ANT-CONTRIB PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT
  THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED
        TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF
   SUCH DAMAGE.
```

B.2. ANTLR 3 License

The following software may be included in this product:

ANTLR 3

ANTLR 3 License [The BSD License] Copyright (c) 2003-2007, Terence Parr All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

 * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.3. Boost Library License

The following software may be included in this product:

Boost C++ Libraries

Use of any of this software is governed by the terms of the license below:

Boost Software License - Version 1.0 - August 17th, 2003

Permission is hereby granted, free of charge, to any person or organization obtaining a copy of the software and accompanying documentation covered by this license (the "Software") to use, reproduce, display, distribute, execute, and transmit the Software

reproduce, display, distribute, execute, and transmit the Software, and to prepare derivative works of the Software, and to permit third-parties to whom the Software is furnished to do so, all subject to the following:

The copyright notices in the Software and this entire statement, including the above license grant, this restriction and the following disclaimer, must be included in all copies of the Software, in whole or in part, and all derivative works of the Software, unless such copies or derivative works are solely in the form of machine-executable object code generated by a source language processor.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR ANYONE DISTRIBUTING THE SOFTWARE BE LIABLE FOR ANY DAMAGES OR OTHER LIABILITY, WHETHER IN CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.4. dtoa.c License

The following software may be included in this product:

dtoa.c

The author of this software is David M. Gay.

Copyright (c) 1991, 2000, 2001 by Lucent Technologies.

Permission to use, copy, modify, and distribute this software for any purpose without fee is hereby granted, provided that this entire notice is included in all copies of any software which is or includes a copy or modification of this software and in all copies of the supporting documentation for such software.

THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT

MAKES ANY REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR

B.5. Editline Library (libedit) License

The following software may be included in this product:

Editline Library (libedit)

Some files are:

Copyright (c) 1992, 1993 The Regents of the University of California. All rights reserved.

This code is derived from software contributed to Berkeley by Christos Zoulas of Cornell University.

Redistribution and use in source and binary forms with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the
- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
 Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
 Neither the name of the University nor the names of its contributors may be used to endowe a promote.
- its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING,
BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO
EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY
DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING
IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
OF THE POSSIBILITY OF SUCH DAMAGE.

Some files are:

Copyright (c) 2001 The NetBSD Foundation, Inc.

This code is derived from software contributed to The NetBSD Foundation

by Anthony Mallet.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE NETBSD FOUNDATION, INC. AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE FOUNDATION OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE DAMAGE

Some files are:

Copyright (c) 1997 The NetBSD Foundation, Inc.

All rights reserved.

This code is derived from software contributed to The NetBSD Foundation

by Jaromir Dolecek.

Redistribution and use in source and binary forms,
with or without modification, are permitted provided
that the following conditions are met:

1. Redistributions of source code must retain the
above copyright notice, this list of conditions
and the following disclaimer.

2. Redistributions in binary form must reproduce
the above copyright notice, this list of conditions
and the following disclaimer in the documentation
and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE NETBSD FOUNDATION, INC.
AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED
WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED
WARRANTIES OF MERCHANTABLITY AND FITNESS FOR A
PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL
THE FOUNDATION OR CONTRIBUTORS BE LIABLE FOR ANY
DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF
USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER
CAUSED AND ON ANY THEORY OF LIABLITY, WHETHER IN
CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE
OR OTHERWISE) ARISINS IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH

Some files are:

Copyright (c) 1998 Todd C. Miller <Todd.Miller@courtesan.com>

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED "AS IS" AND TODD C. MILLER DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL TODD C. MILLER BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

B.6. FindGTest.cmake License

The following software may be included in this product:

```
FindGTest.cmake helper script (part of CMake)

Copyright 2009 Kitware, Inc.
Copyright 2009 Philip Lowman
Copyright 2009 Daniel Blezek

Distributed under the OSI-approved BSD License (the "License");
see accompanying file Copyright.txt for details.

This software is distributed WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.
See the License for more information.

Thanks to Daniel Blezek for the GTEST_ADD_TESTS code

Text of Copyright.txt mentioned above:

CMake - Cross Platform Makefile Generator
Copyright 2000-2009 Kitware, Inc., Insight Software Consortium
All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the
```

documentation and/or other materials provided with the distribution.

* Neither the names of Kitware, Inc., the Insight Software Consortium, nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.7. Fred Fish's Dbug Library License

The following software may be included in this product:

Fred Fish's Dbug Library

NOTICE

Copyright Abandoned, 1987, Fred Fish

This previously copyrighted work has been placed into the public domain by the author and may be freely used for any purpose, private or commercial.

Because of the number of inquiries I was receiving about the use of this product in commercially developed works I have decided to simply make it public domain to further its unrestricted use. I specifically would be most happy to see this material become a part of the standard Unix distributions by AT&T and the Berkeley Computer Science Research Group, and a standard part of the GNU system from the Free Software Foundation.

I would appreciate it, as a courtesy, if this notice is left in all copies and derivative works. Thank you.

The author makes no warranty of any kind with respect to this product and explicitly disclaims any implied warranties of merchantability or fitness for any particular purpose.

The dbug_analyze.c file is subject to the following notice:

Copyright June 1987, Binayak Banerjee All rights reserved.

This program may be freely distributed under the same terms and conditions as Fred Fish's Dbug package.

B.8. getarg License

The following software may be included in this product:

getarg Function (getarg.h, getarg.c files)

Copyright (c) 1997 - 2000 Kungliga Tekniska Högskolan (Royal Institute of Technology, Stockholm, Sweden). All rights reserved.

Redistribution and use in source and binary forms, with

```
or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

3. Neither the name of the Institute nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE INSTITUTE AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE INSTITUTE OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

B.9. GLib License (for MySQL Proxy)

The following software may be included in this product:

This component is licensed under Section B.11, "GNU Lesser General Public License Version 2.1, February 1999".

B.10. GNU General Public License Version 2.0, June 1991

```
The following applies to all products licensed under the GNU General Public License, Version 2.0: You may not use the identified files except in compliance with the GNU General Public License, Version 2.0 (the "License.") You may obtain a copy of the License at http://www.gnu.org/licenses/gpl-2.0.txt. A copy of the license is also reproduced below. Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

GNU GENERAL PUBLIC LICENSE Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not
```

allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software—to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Lesser General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

GNU GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

O. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

- 2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
 - a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
 - b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
 - c) If the modified program normally reads commands interactively

when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

- 3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:
 - a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
 - b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
 - c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

- 4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
- 5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.
- 6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.
- 7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or

otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

- 11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING. REPAIR OR CORRECTION.
- 12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safes to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode: $\[$

Gnomovision version 69, Copyright (C) year name of author Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type 'show w'. This is free software, and you are welcome to redistribute it under certain conditions; type 'show c' for details

The hypothetical commands 'show w' and 'show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than 'show w' and 'show c'; they could even be mouse-clicks or menu items--whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the program 'Gnomovision' (which makes passes at compilers) written by James Hacker.

<signature of Ty Coon>, 1 April 1989
Ty Coon, President of Vice

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License.

B.11. GNU Lesser General Public License Version 2.1, February 1999

The following applies to all products licensed under the GNU Lesser General Public License, Version 2.1: You may not use the identified files except in compliance with the GNU Lesser General Public License, Version 2.1 (the "License"). You may obtain a copy of the License at http://www.gnu.org/licenses/lgpl-2.1.html. A copy of the license is also reproduced below. Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

GNU LESSER GENERAL PUBLIC LICENSE Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that

you have the freedom to distribute copies of free software (and charge for this service if you wish); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

GNU LESSER GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs

(which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee

- 2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
 - a) The modified work must itself be a software library.
 - b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.
 - c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.
 - d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

- 4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.
- If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.
- 5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6 Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

- a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)
- b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.
- c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.
- d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.
- e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for $\,$

reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

- 7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:
 - a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above
 - b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.
- 8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
- 9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.
- 10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.
- 11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version,

but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Libraries

If you develop a new library, and you want it to be of the greatest possible use to the public, we recommend making it free software that everyone can redistribute and change. You can do so by permitting redistribution under these terms (or, alternatively, under the terms of the ordinary General Public License).

To apply these terms, attach the following notices to the library. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

<one line to give the library's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the library, if necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the library `Frob' (a library for tweaking knobs) written by James Random Hacker.

<signature of Ty Coon>, 1 April 1990
Ty Coon, President of Vice

That's all there is to it!

B.12. GNU Libtool License

The following software may be included in this product:

GNU Libtool (The GNU Portable Library Tool)

If you are receiving a copy of the Oracle software in source code, you are also receiving a copy of two files (ltmain.sh and ltdl.h) generated by the GNU Libtool in source code. If you received the Oracle software under a license other than a commercial (non-GPL) license, then the terms of the Oracle license do NOT apply to these files from GNU Libtool; they are licensed under the following licenses, separately from the Oracle programs you receive.

Oracle elects to use GNU General Public License version 2 (GPL) for any software where a choice of GPL or GNU Lesser/Library General Public License (LGPL) license versions are made available with the language indicating that GPL/LGPL or any later version may be used, or where a choice of which version of the GPL/LGPL is applied is unspecified.

From GNU Libtool:

ltmain.sh - Provide generalized library-building support services.
NOTE: Changing this file will not affect anything until you rerun configure.
Copyright (C) 1996, 1997, 1998, 1999, 2000, 2001, 2003, 2004, 2005, 2006, 2007 Free Software Foundation, Inc.
Originally by Gordon Matzigkeit, 1996

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

As a special exception to the GNU General Public License, if you distribute this file as part of a program that contains a configuration script generated by Autoconf, you may include it under the same distribution terms that you use for the rest of that program.

This component is licensed under Section B.10, "GNU General Public License Version 2.0, June 1991"

B.13. GNU Readline License

The following software may be included in this product:

GNU Readline Library

GNU Readline Library With respect to MySQL Server/Cluster software licensed under GNU General Public License, you are receiving a copy of the GNU Readline Library in source code. The terms of any Oracle license that might accompany the Oracle programs do NOT apply to the GNU Readline Library; it is licensed under the following license, separately from the Oracle programs you receive. Oracle elects to use GNU General Public License version 2 (GPL) for any software where a choice of GPL license versions are made available with the language indicating that GPLv2 or any later version may be used, or where a choice of which version of the GPL is applied is unspecified.

This component is licensed under Section B.10, "GNU General Public License Version 2.0, June 1991"

B.14. Google Controlling Master Thread I/O Rate Patch License

The following software may be included in this product:

Google Controlling master thread I/O rate patch

Copyright (c) 2009, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions $\frac{1}{2}$

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- notice, this list of conditions and the following disclaimer.

 * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

 * Neither the name of the Google Inc. nor the names of its contributors are the used to endorse or promote products derived from this software
- may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT ITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.15. Google Perftools (TCMalloc utility) License

The following software may be included in this product:

Google Perftools (TCMalloc utility) Copyright (c) 1998-2006, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided
- with the distribution.

 * Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.16. Google SMP Patch License

The following software may be included in this product:

Google SMP Patch

Google SMP patch

Copyright (c) 2008, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

 * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

 * Neither the name of the Google Inc. nor the names of its contributors may be used to enderge or expects producted derived from this confinence.
- may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.17. lib sql.cc License

The following software may be included in this product:

```
lib_sql.cc
```

```
Copyright (c) 2000
SWsoft company

This material is provided "as is", with absolutely no warranty expressed or implied. Any use is at your own risk.

Permission to use or copy this software for any purpose is hereby granted without fee, provided the above notices are retained on all copies. Permission to modify the code and to distribute modified code is granted, provided the above notices are retained, and a notice that the code was modified is included with the above copyright notice.

This code was modified by the MySQL team.
```

B.18. libevent License

The following software may be included in this product:

```
libevent
Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions

    Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
    Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.
THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS'' AND ANY EXPRESS OR
IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED.
IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE
Parts developed by Adam Langley
log.c
Based on err.c, which was adapted from OpenBSD libc *err*warncode.
Copyright (c) 2005 Nick Mathewson
Copyright (c) 2000 Dug Song
Copyright (c) 1993 The Regents of the University of California.
All rights reserved.
Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions
1. Redistributions of source code must retain the above copyright
notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in
     the documentation and/or other materials provided with the
3. Neither the name of the University nor the names of its
```

contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

min heap.h

Copyright (c) 2006 Maxim Yegorushkin

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions

- 1. Redistributions of source code must retain the above copyright
- notice, this list of conditions and the following disclaimer.

 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

win32.c

Copyright 2000-2002 Niels Provos Copyright 2003 Michael A. Davis All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the
- distribution.

 The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.19. Linux-PAM License

The following software may be included in this product:

Linux-PAM (pam-devel, Pluggable authentication modules for Linux) Copyright Theodore Ts'o, 1996. All rights reserved. (For the avoidance of doubt, Oracle uses and distributes this component under the terms below and elects not to do so under the GPL even though the GPL is referenced as an option below.)

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, and the entire permission notice in its entirety, including the disclaimer of warranties
- including the disclaimer of warranties.

 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

ALTERNATIVELY, this product may be distributed under the terms of the GNU Public License, in which case the provisions of the GPL are required INSTEAD OF the above restrictions. (This clause is necessary due to a potential bad interaction between the GPL and the restrictions contained in a BSD-style copyright.)

THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.20. Lpeg Library License

The following software may be included in this product:

LPeg

Use of any of this software is governed by the terms of the license below:

Copyright © 2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.21. Lua (liblua) License

The following software may be included in this product:

Lua (liblua)

Copyright © 1994-2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.22. LuaFileSystem Library License

The following software may be included in this product:

LuaFileSystem

Copyright © 2003 Kepler Project.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.23. md5 (Message-Digest Algorithm 5) License

The following software may be included in this product:

md5 (Message-Digest Algorithm 5)

This code implements the MD5 message-digest algorithm. The algorithm is due to Ron Rivest. This code was written by Colin Plumb in 1993, no copyright is claimed. This code is in the public domain; do with it what you wish.

Equivalent code is available from RSA Data Security, Inc. This code has been tested against that, and is equivalent, except that you don't need to include two pages of legalese with every copy.

The code has been modified by Mikael Ronstroem to handle calculating a hash value of a key that is always a multiple of 4 bytes long. Word 0 of the calculated 4-word hash value is returned as the hash value.

B.24. memcached License

The following software may be included in this product:

memcached

Copyright (c) 2003, Danga Interactive, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name of the Danga Interactive nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.25. nt_servc (Windows NT Service class library) License

The following software may be included in this product:

nt_servc (Windows NT Service class library)

Windows NT Service class library Copyright Abandoned 1998 Irena Pancirov Irnet Sno This file is public domain and comes with NO WARRANTY of any kind

B.26. OpenPAM License

The following software may be included in this product:

OpenPAM

Copyright (c) 2002-2003 Networks Associates Technology, Inc. Copyright (c) 2004-2007 Dag-Erling Smørgrav All rights reserved.

This software was developed for the FreeBSD Project by ThinkSec AS and Network Associates Laboratories, the Security Research Division of Network Associates, Inc. under DARPA/SPAWAR contract N66001-01-C-8035 ("CBOSS"), as part of the DARPA CHATS research program.

Redistribution and use in source and binary forms with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the
- following disclaimer.

 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

 3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.
- specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING,
BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN
NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA OR DEPORTISE OR BUILDINGS INTERPLICATION) HOWEVER CAUSED. PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRIC LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.27. PCRE License

The following software may be included in this product:

PCRE (Perl Compatible Regular Expressions) Library

```
PCRE LICENCE
PCRE is a library of functions to support regular expressions
whose syntax and semantics are as close as possible to those of the Perl 5 language.
Release 7 of PCRE is distributed under the terms of the "BSD"
licence, as specified below. The documentation for PCRE, supplied in the "doc" directory, is distributed under the same
terms as the software itself.
The basic library functions are written in C and are freestanding. Also included in the distribution is a set of C++ wrapper functions.
THE BASIC LIBRARY FUNCTIONS
                         Philip Hazel
Email local part: ph10
Email domain: cam.
                         cam.ac.uk
University of Cambridge Computing Service, Cambridge, England. Phone: +44 1223 334714
Copyright (c) 1997-2006 University of Cambridge
```

All rights reserved.

THE C++ WRAPPER FUNCTIONS

Contributed by: Google Inc.

Copyright (c) 2006, Google Inc.

All rights reserved.

THE "BSD" LICENCE

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

* Neither the name of the University of Cambridge nor the name of Google Inc. nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS

BE LIABLE FOR ANY DIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DARAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS;

OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.28. Percona Multiple I/O Threads Patch License

The following software may be included in this product:

Percona Multiple I/O threads patch

Copyright (c) 2008, 2009 Percona Inc
All rights reserved.

Redistribution and use of this software in source and binary forms,
with or without modification, are permitted provided that the
following conditions are met:

* Redistributions of source code must retain the above copyright
notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright
notice, this list of conditions and the following disclaimer in the
documentation and/or other materials provided with the distribution.

* Neither the name of Percona Inc. nor the names of its contributors
may be used to endorse or promote products derived from this software
without specific prior written permission of Percona Inc.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING,
BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER
CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN
ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE
POSSIBILITY OF SUCH DAMAGE.

B.29. RegEX-Spencer Library License

The following software may be included in this product: Henry Spencer's Regular-Expression Library (RegEX-Spencer)

Copyright 1992, 1993, 1994 Henry Spencer. All rights reserved.

This software is not subject to any license of the American Telephone and Telegraph Company or of the Regents of the University of California.

Permission is granted to anyone to use this software for any purpose on any computer system, and to alter it and redistribute it, subject

to the following restrictions:

- The author is not responsible for the consequences of use of this software, no matter how awful, even if they arise from flaws in it.
- The origin of this software must not be misrepresented, either by explicit claim or by omission. Since few users ever read sources, credits must appear in the documentation.
- Altered versions must be plainly marked as such, and must not be misrepresented as being the original software. Since few users ever read sources, credits must appear in the documentation.
- 4. This notice may not be removed or altered.

B.30. RFC 3174 - US Secure Hash Algorithm 1 (SHA1) License

The following software may be included in this product:

RFC 3174 - US Secure Hash Algorithm 1 (SHA1)

RFC 3174 - US Secure Hash Algorithm 1 (SHA1)

Copyright (C) The Internet Society (2001). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.

B.31. Richard A. O'Keefe String Library License

The following software may be included in this product:

Richard A. O'Keefe String Library

The Richard O'Keefe String Library is subject to the following notice:

These files are in the public domain. This includes getopt.c, which is the work of Henry Spencer, University of Toronto Zoology, who says of it "None of this software is derived from Bell software. I had no access to the source for Bell's versions at the time I wrote it. This software is hereby explicitly placed in the public domain. It may be used for any purpose on any machine by anyone." I would greatly prefer it if *my* material received no military use.

The t_ctype.h file is subject to the following notice:

Copyright (C) 1998, 1999 by Pruet Boonma, all rights reserved. Copyright (C) 1998 by Theppitak Karoonboonyanan, all rights reserved.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies.

Smaphan Raruenrom and Pruet Boonma makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

B.32. SHA-1 in C License

The following software may be included in this product:

SHA-1 in C

SHA-1 in C By Steve Reid <steve@edmweb.com> 100% Public Domain

B.33. Simple Logging Facade for Java (SLF4J) License

The following software may be included in this product:

Copyright (c) 2004-2008 QOS.ch
All rights reserved.

Permission is hereby granted, free of charge,
to any person obtaining a copy of this software
and associated documentation files (the "Software"),
to deal in the Software without restriction, including
without limitation the rights to use, copy, modify,
merge, publish, distribute, sublicense, and/or sell
copies of the Software, and to permit persons to whom
the Software is furnished to do so, subject to the
following conditions:

The above copyright notice and this permission notice
shall be included in all copies or substantial portions
of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY
OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT
LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS
FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO
EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE
FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN
AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM,
OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE
OR OTHER DEALINGS IN THE SOFTWARE

B.34. zlib License

The following software may be included in this product:

zlib

Oracle gratefully acknowledges the contributions of Jean-loup Gailly and Mark Adler in creating the zlib general purpose compression library which is used in this product.

```
zlib.h -- interface of the 'zlib' general purpose compression library version 1.2.3, July 18th, 2005
Copyright (C) 1995-2005 Jean-loup Gailly and Mark Adler

zlib.h -- interface of the 'zlib' general purpose compression library version 1.2.5, April 19th, 2010
Copyright (C) 1995-2010 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software. Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.

2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.

3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly jloup@gzip.org
Mark Adler madler@alumni.caltech.edu
```

B.35. ZLIB.NET License

The following software may be included in this product:

```
ZLIB.NET

Copyright (c) 2006-2007, ComponentAce http://www.componentace.com
All rights reserved.
```

Redistribution and use in source and binary forms with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and
- above copyright notice, this list of conditions and the following disclaimer.
 Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
 Neither the name of ComponentAce nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission. permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.