# **MySQL Cluster**

# **MySQL Cluster**

#### **Abstract**

This is the MySQL Cluster extract from the MySQL 5.1 Reference Manual.

Document generated on: 2014-08-20 (revision: 39730)

# **Table of Contents**

Preface and Legal Notices	
1 MySQL Cluster NDB 6.1 - 7.1	
2 Preface and Notes	
3 MySQL Cluster Overview	
3.1 MySQL Cluster Core Concepts	
3.2 MySQL Cluster Nodes, Node Groups, Replicas, and Partitions	11
3.3 MySQL Cluster Hardware, Software, and Networking Requirements	
3.4 MySQL Cluster Development History	16
3.4.1 MySQL Cluster Development in MySQL Cluster NDB 7.2.0	
3.4.2 MySQL Cluster Development in MySQL Cluster NDB 7.1	
3.4.3 MySQL Cluster Development in MySQL Cluster NDB 7.0	
3.4.4 MySQL Cluster Development in MySQL Cluster NDB 6.3	
3.4.5 MySQL Cluster Development in MySQL Cluster NDB 6.2	36
3.4.6 MySQL Cluster Development in MySQL Cluster NDB 6.1	39
3.4.7 Development History of MySQL Cluster in MySQL 5.1	39
3.5 MySQL Server Using InnoDB Compared with MySQL Cluster	41
3.5.1 Differences Between the NDB and InnoDB Storage Engines	. 41
3.5.2 NDB and InnoDB Workloads	43
3.5.3 NDB and InnoDB Feature Usage Summary	44
3.6 Known Limitations of MySQL Cluster	
3.6.1 Noncompliance with SQL Syntax in MySQL Cluster	45
3.6.2 Limits and Differences of MySQL Cluster from Standard MySQL Limits	47
3.6.3 Limits Relating to Transaction Handling in MySQL Cluster	. 48
3.6.4 MySQL Cluster Error Handling	50
3.6.5 Limits Associated with Database Objects in MySQL Cluster	. 50
3.6.6 Unsupported or Missing Features in MySQL Cluster	
3.6.7 Limitations Relating to Performance in MySQL Cluster	51
3.6.8 Issues Exclusive to MySQL Cluster	51
3.6.9 Limitations Relating to MySQL Cluster Disk Data Storage	52
3.6.10 Limitations Relating to Multiple MySQL Cluster Nodes	. 53
3.6.11 Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x,	
and MySQL Cluster NDB 7.x	
4 MySQL Cluster Installation and Upgrades	59
4.1 Installing MySQL Cluster on Linux	61
4.1.1 Installing a MySQL Cluster Binary Release on Linux	62
4.1.2 Installing MySQL Cluster from RPM	64
4.1.3 Building MySQL Cluster from Source on Linux	66
4.2 Installing MySQL Cluster on Windows	67
4.2.1 Installing MySQL Cluster on Windows from a Binary Release	68
4.2.2 Compiling and Installing MySQL Cluster from Source on Windows	71
4.2.3 Initial Startup of MySQL Cluster on Windows	. 72
4.2.4 Installing MySQL Cluster Processes as Windows Services	74
4.3 Initial Configuration of MySQL Cluster	77
4.4 Initial Startup of MySQL Cluster	78
4.5 MySQL Cluster Example with Tables and Data	
4.6 Safe Shutdown and Restart of MySQL Cluster	
4.7 Upgrading and Downgrading MySQL Cluster	
4.7.1 Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x	
4.7.2 Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x	
4.7.3 Upgrade and downgrade compatibility: MySQL 5.1	
5 Configuration of MySQL Cluster NDB 6.1-7.1	97

5.1 Quick Test Setup of MySQL Cluster	97
5.2 MySQL Cluster Configuration Files	100
5.2.1 MySQL Cluster Configuration: Basic Example	. 101
5.2.2 Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later	104
5.2.3 MySQL Cluster Connection Strings	108
5.2.4 Defining Computers in a MySQL Cluster	109
5.2.5 Defining a MySQL Cluster Management Server	
5.2.6 Defining MySQL Cluster Data Nodes	115
5.2.7 Defining SQL and Other API Nodes in a MySQL Cluster	169
5.2.8 MySQL Cluster TCP/IP Connections	175
5.2.9 MySQL Cluster TCP/IP Connections Using Direct Connections	
5.2.10 MySQL Cluster Shared-Memory Connections	
5.2.11 SCI Transport Connections in MySQL Cluster	
5.2.12 Configuring MySQL Cluster Parameters for Local Checkpoints	
5.2.13 Configuring MySQL Cluster Send Buffer Parameters	
5.3 Overview of MySQL Cluster Configuration Parameters	
5.3.1 MySQL Cluster Data Node Configuration Parameters	
5.3.2 MySQL Cluster Management Node Configuration Parameters	
5.3.3 MySQL Cluster SQL Node and API Node Configuration Parameters	
5.3.4 Other MySQL Cluster Configuration Parameters	
5.4 MySQL Server Options and Variables for MySQL Cluster	
5.4.1 MySQL Cluster mysqld Option and Variable Reference	
5.4.2 MySQL Server Options for MySQL Cluster	
5.4.3 MySQL Cluster System Variables	
5.4.4 MySQL Cluster Status Variables	
5.5 Using High-Speed Interconnects with MySQL Cluster	
5.5.1 Configuring MySQL Cluster to use SCI Sockets	
5.5.2 MySQL Cluster Interconnects and Performance	
6 MySQL Cluster Programs	
6.1 ndbd — The MySQL Cluster Data Node Daemon	
6.2 ndbinfo_select_all — Select From ndbinfo Tables	
6.3 ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)	
6.4 ndb_mgmd — The MySQL Cluster Management Server Daemon	
6.5 ndb_mgm — The MySQL Cluster Management Client	
6.6 ndb blob tool — Check and Repair BLOB and TEXT columns of MySQL Cluster	200
Tables	300
6.7 ndb_config — Extract MySQL Cluster Configuration Information	
6.8 ndb_cpcd — Automate Testing for NDB Development	
6.9 ndb_delete_all — Delete All Rows from an NDB Table	
6.10 ndb_desc — Describe NDB Tables	
6.11 ndb_drop_index — Drop Index from an NDB Table	
6.12 ndb_drop_table — Drop an NDB Table	
6.13 ndb_error_reporter — NDB Error-Reporting Utility	
6.14 ndb_index_stat — NDB Index Statistics Utility	
6.15 ndb_print_backup_file — Print NDB Backup File Contents	
6.16 ndb_print_schema_file — Print NDB Schema File Contents	
6.17 ndb_print_sys_file — Print NDB System File Contents	
6.18 ndbd_redo_log_reader — Check and Print Content of Cluster Redo Log	
6.19 ndb_restore — Restore a MySQL Cluster Backup	
6.20 ndb_select_all — Print Rows from an NDB Table	
6.21 ndb_select_count — Print Row Counts for NDB Tables	
6.22 ndb_show_tables — Display List of NDB Tables	
6.23 ndb_size.pl — NDBCLUSTER Size Requirement Estimator	
6.24 ndb_waiter — Wait for MySQL Cluster to Reach a Given Status	
0.24 Hab_walter Walk for Myoge Oldstor to Readin a Olven Oldstos	555

	6.25 Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster	
	Programs	
7	Management of MySQL Cluster	
	7.1 Summary of MySQL Cluster Start Phases	
	7.2 Commands in the MySQL Cluster Management Client	365
	7.3 Online Backup of MySQL Cluster	
	7.3.1 MySQL Cluster Backup Concepts	369
	7.3.2 Using The MySQL Cluster Management Client to Create a Backup	369
	7.3.3 Configuration for MySQL Cluster Backups	373
	7.3.4 MySQL Cluster Backup Troubleshooting	373
	7.4 MySQL Server Usage for MySQL Cluster	373
	7.5 Performing a Rolling Restart of a MySQL Cluster	375
	7.6 Event Reports Generated in MySQL Cluster	
	7.6.1 MySQL Cluster Logging Management Commands	
	7.6.2 MySQL Cluster Log Events	
	7.6.3 Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client	
	7.7 MySQL Cluster Log Messages	
	7.7.1 MySQL Cluster: Messages in the Cluster Log	
	7.7.2 MySQL Cluster: NDB Transporter Errors	
	7.8 MySQL Cluster Single User Mode	
	7.9 Quick Reference: MySQL Cluster SQL Statements	
	7.10 The ndbinfo MySQL Cluster Information Database	
	7.10.1 The ndbinfo arbitrator_validity_detail Table	
	7.10.2 The ndbinfo arbitrator_validity_summary Table	
	7.10.3 The ndbinfo blocks Table	
	7.10.4 The ndbinfo cluster_operations Table	
	7.10.5 The ndbinfo cluster_transactions Table	
	7.10.6 The ndbinfo config_params Table	
	7.10.7 The ndbinfo counters Table	
	7.10.8 The ndbinfo diskpagebuffer Table	
	7.10.9 The ndbinfo logbuffers Table	
	7.10.10 The ndbinfo logspaces Table	
	7.10.11 The ndbinfo membership Table	
	7.10.12 The ndbinfo memoryusage Table	
	7.10.13 The ndbinfo nodes Table	
	7.10.14 The https://doi.org/10.1014 The https://doi.org/10	
	7.10.15 The habinfo resources Table	
	7.10.16 The habinfo server operations Table	
	7.10.17 The habinfo server_transactions Table	
	7.10.18 The ndbinfo threadblocks Table	
	7.10.19 The habinfo threadstat Table	
	7.10.20 The habinfo transporters Table	
	7.11 MySQL Cluster Security Issues	
	7.11.1 MySQL Cluster Security and Networking Issues	
	7.11.2 MySQL Cluster and MySQL Privileges	
	7.11.3 MySQL Cluster and MySQL Security Procedures	
	7.113 MySQL Cluster Disk Data Tables	
	7.12.1 MySQL Cluster Disk Data Objects	
	7.12.1 MySQL Sidster Disk Data Objects	
	7.12.2 Osing Symbolic Links with Disk Data Objects	
	7.13 Adding MySQL Cluster Data Nodes Online	
	7.13.1 Adding MySQL Cluster Data Nodes Online: General Issues	
	7.13.2 Adding MySQL Cluster Data Nodes Online: Basic procedure	
	1.13.3 Adding Iviyoql Ciusiei dala ivodes Uniine. Detailed example	44/

### MySQL Cluster

7.14 Distributed MySQL Privileges for MySQL Cluster	
7.15 NDB API Statistics Counters and Variables	458
8 MySQL Cluster Replication	471
8.1 MySQL Cluster Replication: Abbreviations and Symbols	
8.2 General Requirements for MySQL Cluster Replication	
8.3 Known Issues in MySQL Cluster Replication	
8.4 MySQL Cluster Replication Schema and Tables	
8.5 Preparing the MySQL Cluster for Replication	
8.6 Starting MySQL Cluster Replication (Single Replication Channel)	
8.7 Using Two Replication Channels for MySQL Cluster Replication	
8.8 Implementing Failover with MySQL Cluster Replication	
8.9 MySQL Cluster Backups With MySQL Cluster Replication	492
8.9.1 MySQL Cluster Replication: Automating Synchronization of the Replication Slave to	40-
the Master Binary Log	
8.9.2 Point-In-Time Recovery Using MySQL Cluster Replication	
8.10 MySQL Cluster Replication: Multi-Master and Circular Replication	
8.11 MySQL Cluster Replication Conflict Resolution	503
A Licenses for Third-Party Components	513
A.1 ANTLR 3 License	515
A.2 dtoa.c License	516
A.3 Editline Library (libedit) License	516
A.4 FindGTest.cmake License	
A.5 Fred Fish's Dbug Library License	
A.6 getarg License	
A.7 GLib License (for MySQL Proxy)	
A.8 GNU General Public License Version 2.0, June 1991	
A.9 GNU Lesser General Public License Version 2.1, February 1999	
A.10 GNU Libtool License	
A.11 GNU Readline License	
A.12 Google Controlling Master Thread I/O Rate Patch License	
A.13 Google Perftools (TCMalloc utility) License	
A.14 Google SMP Patch License	
A.15 lib_sql.cc License	
A.16 libevent License	
A.17 Libiconv License	
A.18 libintl License	
A.19 Linux-PAM License	
A.20 LPeg Library License	542
A.21 Lua (liblua) License	542
A.22 LuaFileSystem Library License	543
A.23 md5 (Message-Digest Algorithm 5) License	
A.24 memcached License	
A.25 nt_servc (Windows NT Service class library) License	
A.26 OpenPAM License	
A.27 Paramiko License	
A.28 PCRE License	
A.29 Percona Multiple I/O Threads Patch License	
A.30 RegEX-Spencer Library License	
A.31 RFC 3174 - US Secure Hash Algorithm 1 (SHA1) License	
A.32 Richard A. O'Keefe String Library License	
A.33 SHA-1 in C License	
A.34 zlib License	
B MySQL 5.1 FAQ: MySQL Cluster	551

## Preface and Legal Notices

This is the MySQL Cluster extract from the MySQL 5.1 Reference Manual.

### **Legal Notices**

Copyright © 1997, 2014, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. MySQL is a trademark of Oracle Corporation and/or its affiliates, and shall not be used without Oracle's express written authorization. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this material is subject to the terms and conditions of your Oracle Software License and Service Agreement, which has been executed and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle or as specifically provided below. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

This documentation is NOT distributed under a GPL license. Use of this documentation is subject to the following terms:

You may create a printed copy of this documentation solely for your own personal use. Conversion to other formats is allowed as long as the actual content is not altered or edited in any way. You shall not publish or distribute this documentation in any form or on any media, except if you distribute the documentation in a manner similar to how Oracle disseminates it (that is, electronically for download on a Web site with the software) or on a CD-ROM or similar medium, provided however that the documentation is disseminated together with the software on the same medium. Any other use, such as any dissemination of printed copies or use of this documentation, in whole or in part, in another publication, requires the prior written consent from an authorized representative of Oracle. Oracle and/or its affiliates reserve any and all rights to this documentation not expressly granted above.

For more information on the terms of this license, or for details on how the MySQL documentation is built and produced, please visit MySQL Contact & Questions.

For additional licensing information, including licenses for third-party libraries used by MySQL products, see Preface and Legal Notices.

For help with using MySQL, please visit either the MySQL Forums or MySQL Mailing Lists where you can discuss your issues with other MySQL users.

For additional documentation on MySQL products, including translations of the documentation into other languages, and downloadable versions in variety of formats, including HTML and PDF formats, see the MySQL Documentation Library.

# Chapter 1 MySQL Cluster NDB 6.1 - 7.1

This chapter contains information about <u>MySQL Cluster</u>, which is a high-availability, high-redundancy version of MySQL adapted for the distributed computing environment. Current releases of MySQL Cluster use versions 6 and 7 of the NDB storage engine (also known as NDBCLUSTER) to enable running several computers with MySQL servers and other software in a cluster.

Beginning with MySQL 5.1.24, support for the NDBCLUSTER storage engine was removed from the standard MySQL server binaries built by MySQL. Instead, users of MySQL Cluster binaries built by MySQL should upgrade to the most recent binary release of MySQL Cluster NDB 7.0 or MySQL Cluster 7.1 for supported platforms—these include RPMs that should work with most Linux distributions. MySQL Cluster users who build from source should be aware that, also beginning with MySQL 5.1.24, NDBCLUSTER sources in the standard MySQL 5.1 tree are no longer maintained; these users should use the sources provided for MySQL Cluster NDB 7.0 or later. (Locations where the sources can be obtained are listed later in this section.)

#### Note

MySQL Cluster NDB 6.1, 6.2, and 6.3 were formerly known as "MySQL Cluster Carrier Grade Edition". Beginning with MySQL Cluster NDB 6.2.15 and MySQL Cluster NDB 6.3.14, this term is no longer applied to the MySQL Cluster software —which is now known simply as "MySQL Cluster"—but rather to a commercial licensing and support package. You can learn more about available options for commercial licensing of MySQL Cluster from http://mysql.com/products/database/cluster/features.html, on the MySQL web site.

This chapter contains information about MySQL Cluster in MySQL 5.1 mainline releases through MySQL 5.1.23, MySQL Cluster NDB 6.2 releases through 5.1.51-ndb-6.2.19, MySQL Cluster NDB 6.3 releases through 5.1.73-ndb-6.3.55, MySQL Cluster NDB 7.0 releases through 5.1.73-ndb-7.0.42 and MySQL Cluster NDB 7.1 releases through 5.1.73-ndb-7.1.33. Currently, the MySQL Cluster NDB 7.2 release series is Generally Available (GA), as is MySQL Cluster NDB 7.1. MySQL Cluster NDB 7.0 and MySQL Cluster NDB 6.3 are previous GA release series; although they are still supported, we recommend that new deployments use MySQL Cluster NDB 7.2. For information about MySQL Cluster NDB 7.2, see MySQL Cluster NDB 7.2, in the *MySQL 5.5 Manual*.

This chapter also contains historical information about MySQL Cluster NDB 6.1 and MySQL Cluster NDB 6.2, although these release series are no longer in active development, and no longer supported for new deployments. You should upgrade to a MySQL Cluster NDB 7.1 or later release series as soon as possible.

Release notes for the changes in each release of MySQL Cluster are located at MySQL Cluster 7.1 Release Notes.

**Supported Platforms.** MySQL Cluster is currently available and supported on a number of platforms. For exact levels of support available for on specific combinations of operating system versions, operating system distributions, and hardware platforms, please refer to http://www.mysql.com/support/supportedplatforms/cluster.html.

**Availability.** MySQL Cluster binary and source packages are available for supported platforms from http://dev.mysql.com/downloads/cluster/.

#### Note

Binary releases and RPMs were not available for MySQL Cluster NDB 6.2 prior to MySQL Cluster NDB 6.2.15.

**MySQL Cluster release numbers.** Starting with MySQL Cluster NDB 6.1 and MySQL Cluster NDB 6.2, MySQL Cluster follows a somewhat different release pattern from the mainline MySQL 5.1 Cluster series of releases. In this *Manual* and other MySQL documentation, we identify these and later MySQL Cluster releases employing a version number that begins with "NDB". This version number is that of the NDBCLUSTER storage engine used in the release, and not of the MySQL server version on which the MySQL Cluster release is based.

**Version strings used in MySQL Cluster NDB 6.x and 7.x software.** The version string displayed by MySQL Cluster NDB 6.x and 7.x software uses this format:

```
mysql-mysql_server_version-ndb-ndb_engine_version
```

mysql\_server\_version represents the version of the MySQL Server on which the MySQL Cluster release is based. For all MySQL Cluster NDB 6.x and 7.x releases, this is "5.1". ndb\_engine\_version is the version of the NDB storage engine used by this release of the MySQL Cluster software. You can see this format used in the mysql client, as shown here:

This version string is also displayed in the output of the SHOW command in the ndb\_mgm client:

The version string identifies the mainline MySQL version from which the MySQL Cluster release was branched and the version of the NDBCLUSTER storage engine used. For example, the full version string for MySQL Cluster NDB 7.0.5 (the first GA MySQL Cluster NDB 7.0 binary release) was mysql-5.1.32-ndb-7.0.5. From this we can determine the following:

- Since the portion of the version string preceding "-ndb-" is the base MySQL Server version, this means that MySQL Cluster NDB 7.0.5 derives from the MySQL 5.1.32, and contains all feature enhancements and bugfixes from MySQL 5.1 up to and including MySQL 5.1.32.
- Since the portion of the version string following "-ndb-" represents the version number of the NDB (or NDBCLUSTER) storage engine, MySQL Cluster NDB 7.0.5 uses version 7.0.5 of the NDBCLUSTER storage engine.

New MySQL Cluster releases are numbered according to updates in the NDB storage engine, and do not necessarily correspond in a linear fashion with mainline MySQL Server releases. For example, MySQL

Cluster NDB 7.0.5 (as previously noted) is based on MySQL 5.1.32, and MySQL Cluster NDB 7.0.6 is based on MySQL 5.1.34 (version string: mysql-5.1.34-ndb-7.0.6).

Compatibility with standard MySQL 5.1 releases. While many standard MySQL schemas and applications can work using MySQL Cluster, it is also true that unmodified applications and database schemas may be slightly incompatible or have suboptimal performance when run using MySQL Cluster (see Section 3.6, "Known Limitations of MySQL Cluster"). Most of these issues can be overcome, but this also means that you are very unlikely to be able to switch an existing application datastore—that currently uses, for example, MyISAM or InnoDB—to use the NDB storage engine without allowing for the possibility of changes in schemas, queries, and applications. Moreover, from MySQL 5.1.24 onwards, the MySQL Server and MySQL Cluster codebases diverge considerably (and NDB storage engine support dropped from subsequent MySQL Server releases), so that the standard mysqld cannot function as a dropin replacement for the version of mysqld that is supplied with MySQL Cluster.

**MySQL Cluster development source trees.** MySQL Cluster development trees can also be accessed from https://code.launchpad.net/~mysql/:

The MySQL Cluster development sources maintained at https://code.launchpad.net/~mysql/ are licensed under the GPL. For information about obtaining MySQL sources using Bazaar and building them yourself, see Installing MySQL Using a Development Source Tree.

Currently, MySQL Cluster NDB 7.0, MySQL Cluster NDB 7.1, and MySQL Cluster NDB 7.2 releases are all Generally Available (GA), although we recommend that new deployments use MySQL Cluster NDB 7.2. MySQL Cluster NDB 6.1, MySQL Cluster NDB 6.2, and MySQL Cluster NDB 6.3, are no longer in active development. For an overview of major features added in MySQL Cluster NDB 6.x and 7.x releases, see Section 3.4, "MySQL Cluster Development History". For an overview of major features added in MySQL Cluster NDB 7.2, see MySQL Cluster Development History.

This chapter represents a work in progress, and its contents are subject to revision as MySQL Cluster continues to evolve. Additional information regarding MySQL Cluster can be found on the MySQL Web site at http://www.mysql.com/products/cluster/.

**Additional Resources.** More information about MySQL Cluster can be found in the following places:

- For answers to some commonly asked questions about MySQL Cluster, see Appendix B, MySQL 5.1
  FAQ: MySQL Cluster.
- The MySQL Cluster mailing list: http://lists.mysql.com/cluster.
- The MySQL Cluster Forum: http://forums.mysql.com/list.php?25.
- Many MySQL Cluster users and developers blog about their experiences with MySQL Cluster, and make feeds of these available through PlanetMySQL.



## Chapter 2 Preface and Notes

This is an extract from the Reference Manual for the MySQL Database System, version 5.1. It contains information about MySQL Cluster releases, through MySQL Cluster NDB 6.3.55, MySQL Cluster NDB 7.0.42, and MySQL Cluster NDB 7.1.33. Differences between minor versions of MySQL Cluster covered in this extract are noted in the present text with reference to the NDBCLUSTER storage version number (6.3.x, 7.0.x, 7.1.x); differences between versions of the MySQL Server 5.1 software, on which MySQL Cluster is based, are noted with reference to MySQL 5.1 releases (5.1.x). For license information, see the legal notice. This product may contain third-party code. For license information on third-party code, see Appendix A, *Licenses for Third-Party Components*.

This extract also contains historical information about older versions of MySQL Cluster that were also based on version 5.1 of the MySQL database system (MySQL 5.1 Cluster, MySQL Cluster NDB 6.1, MySQL Cluster NDB 6.2), although these older versions are no longer supported, maintained, or recommended for new deployments. This extract is not intended for use with older versions of the MySQL Cluster software due to the many functional and other differences between current versions (MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, and MySQL Cluster NDB 7.1) and previous versions. This extract provides information that is specific to MySQL Cluster and is not intended to replace the *MySQL 5.1 Manual*, which provides additional information about MySQL 5.1 which may also be necessary for use of MySQL Cluster. If you are using MySQL Server 5.1 or an earlier release of the MySQL software, please refer to the appropriate manual. For example, *MySQL 5.0 Reference Manual*, covers the 5.0 series of MySQL software releases.

If you are using MySQL 5.5, please refer to the MySQL 5.5 Reference Manual.



# Chapter 3 MySQL Cluster Overview

### **Table of Contents**


3.1 MySQL Cluster Core Concep	ts	9
3.2 MySQL Cluster Nodes, Node	Groups, Replicas, and Partitions	11
3.3 MySQL Cluster Hardware, Sc	oftware, and Networking Requirements	14
	History	
3.4.1 MySQL Cluster Development	opment in MySQL Cluster NDB 7.2.0	17
3.4.2 MySQL Cluster Development	opment in MySQL Cluster NDB 7.1	18
	opment in MySQL Cluster NDB 7.0	
	opment in MySQL Cluster NDB 6.3	
3.4.5 MySQL Cluster Development	opment in MySQL Cluster NDB 6.2	36
3.4.6 MySQL Cluster Development	opment in MySQL Cluster NDB 6.1	39
3.4.7 Development History	of MySQL Cluster in MySQL 5.1	39
3.5 MySQL Server Using InnoDE	Compared with MySQL Cluster	41
3.5.1 Differences Between t	he NDB and InnoDB Storage Engines	41
3.5.2 NDB and InnoDB Wo	kloads	43
3.5.3 NDB and InnoDB Fea	ture Usage Summary	44
3.6 Known Limitations of MySQL	Cluster	44
	QL Syntax in MySQL Cluster	
3.6.2 Limits and Differences	of MySQL Cluster from Standard MySQL Limits	47
3.6.3 Limits Relating to Trar	nsaction Handling in MySQL Cluster	48
3.6.4 MySQL Cluster Error	Handling	50
3.6.5 Limits Associated with	Database Objects in MySQL Cluster	50
3.6.6 Unsupported or Missir	ng Features in MySQL Cluster	51
3.6.7 Limitations Relating to	Performance in MySQL Cluster	51
3.6.8 Issues Exclusive to M	ySQL Cluster	51
3.6.9 Limitations Relating to	MySQL Cluster Disk Data Storage	52
3.6.10 Limitations Relating t	o Multiple MySQL Cluster Nodes	53
3.6.11 Previous MySQL Clu	ster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and	
MySQL Cluster NDB 7.x		53

<u>MySQL Cluster</u> is a technology that enables clustering of in-memory databases in a shared-nothing system. The shared-nothing architecture enables the system to work with very inexpensive hardware, and with a minimum of specific requirements for hardware or software.

MySQL Cluster is designed not to have any single point of failure. In a shared-nothing system, each component is expected to have its own memory and disk, and the use of shared storage mechanisms such as network shares, network file systems, and SANs is not recommended or supported.

MySQL Cluster integrates the standard MySQL server with an in-memory clustered storage engine called NDB (which stands for "Network DataBase"). In our documentation, the term NDB refers to the part of the setup that is specific to the storage engine, whereas "MySQL Cluster" refers to the combination of one or more MySQL servers with the NDB storage engine.

A MySQL Cluster consists of a set of computers, known as *hosts*, each running one or more processes. These processes, known as *nodes*, may include MySQL servers (for access to NDB data), data nodes (for storage of the data), one or more management servers, and possibly other specialized data access programs. The relationship of these components in a MySQL Cluster is shown here:



All these programs work together to form a MySQL Cluster (see Chapter 6, MySQL Cluster Programs. When data is stored by the NDB storage engine, the tables (and table data) are stored in the data nodes. Such tables are directly accessible from all other MySQL servers (SQL nodes) in the cluster. Thus, in a payroll application storing data in a cluster, if one application updates the salary of an employee, all other MySQL servers that query this data can see this change immediately.

Although a MySQL Cluster SQL node uses the mysqld server daemon, it differs in a number of critical respects from the mysqld binary supplied with the MySQL 5.1 distributions, and the two versions of mysqld are not interchangeable.

In addition, a MySQL server that is not connected to a MySQL Cluster cannot use the NDB storage engine and cannot access any MySQL Cluster data.

The data stored in the data nodes for MySQL Cluster can be mirrored; the cluster can handle failures of individual data nodes with no other impact than that a small number of transactions are aborted due to losing the transaction state. Because transactional applications are expected to handle transaction failure, this should not be a source of problems.

Individual nodes can be stopped and restarted, and can then rejoin the system (cluster). Rolling restarts (in which all nodes are restarted in turn) are used in making configuration changes and software upgrades (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster"). In MySQL Cluster NDB 7.0 and later, rolling restarts are also used as part of the process of adding new data nodes online (see Section 7.13, "Adding MySQL Cluster Data Nodes Online"). For more information about data nodes, how they are organized in a MySQL Cluster, and how they handle and store MySQL Cluster data, see Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions".

Backing up and restoring MySQL Cluster databases can be done using the NDB-native functionality found in the MySQL Cluster management client and the ndb\_restore program included in the MySQL Cluster distribution. For more information, see Section 7.3, "Online Backup of MySQL Cluster", and Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup". You can also use the standard MySQL functionality provided for this purpose in mysqldump and the MySQL server. See mysqldump — A Database Backup Program, for more information.

MySQL Cluster nodes can use a number of different transport mechanisms for inter-node communications, including TCP/IP using standard 100 Mbps or faster Ethernet hardware. It is also possible to use the high-speed *Scalable Coherent Interface* (SCI) protocol with MySQL Cluster, although this is not required to use MySQL Cluster. SCI requires special hardware and software; see Section 5.5, "Using High-Speed Interconnects with MySQL Cluster", for more about SCI and using it with MySQL Cluster.

### 3.1 MySQL Cluster Core Concepts

<u>NDBCLUSTER</u> (also known as NDB) is an in-memory storage engine offering high-availability and datapersistence features.

The NDBCLUSTER storage engine can be configured with a range of failover and load-balancing options, but it is easiest to start with the storage engine at the cluster level. MySQL Cluster's NDB storage engine contains a complete set of data, dependent only on other data within the cluster itself.

The "Cluster" portion of MySQL Cluster is configured independently of the MySQL servers. In a MySQL Cluster, each part of the cluster is considered to be a *node*.

#### Note

In many contexts, the term "node" is used to indicate a computer, but when discussing MySQL Cluster it means a *process*. It is possible to run multiple nodes on a single computer; for a computer on which one or more cluster nodes are being run we use the term *cluster host*.

There are three types of cluster nodes, and in a minimal MySQL Cluster configuration, there will be at least three nodes, one of each of these types:

- <u>Management node</u>: The role of this type of node is to manage the other nodes within the MySQL Cluster, performing such functions as providing configuration data, starting and stopping nodes, running backup, and so forth. Because this node type manages the configuration of the other nodes, a node of this type should be started first, before any other node. An MGM node is started with the command <a href="mailto:ndb\_mgmd">ndb\_mgmd</a>.
- <u>Data node</u>: This type of node stores cluster data. There are as many data nodes as there are replicas, times the number of fragments (see Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions"). For example, with two replicas, each having two fragments, you need four data nodes. One replica is sufficient for data storage, but provides no redundancy; therefore, it is recommended to have 2 (or more) replicas to provide redundancy, and thus high availability. A data node is started with the command ndbd (see Section 6.1, "ndbd The MySQL Cluster Data Node Daemon"). In MySQL Cluster NDB 7.0 and later, ndbmtd can also be used for the data node process; see Section 6.3, "ndbmtd The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

MySQL Cluster tables are normally stored completely in memory rather than on disk (this is why we refer to MySQL Cluster as an *in-memory* database). In MySQL 5.1, MySQL Cluster NDB 6.X, and later, some MySQL Cluster data can be stored on disk; see Section 7.12, "MySQL Cluster Disk Data Tables", for more information.

• <u>SQL node</u>: This is a node that accesses the cluster data. In the case of MySQL Cluster, an SQL node is a traditional MySQL server that uses the NDBCLUSTER storage engine. An SQL node is a mysqld process started with the --ndbcluster and --ndb-connectstring options, which are explained elsewhere in this chapter, possibly with additional MySQL server options as well.

An SQL node is actually just a specialized type of <u>API node</u>, which designates any application which accesses MySQL Cluster data. Another example of an API node is the <u>ndb\_restore</u> utility that is used to restore a cluster backup. It is possible to write such applications using the NDB API. For basic information about the NDB API, see <u>Getting Started with the NDB API</u>.

#### **Important**

It is not realistic to expect to employ a three-node setup in a production environment. Such a configuration provides no redundancy; to benefit from MySQL Cluster's high-availability features, you must use multiple data and SQL nodes. The use of multiple management nodes is also highly recommended.

For a brief introduction to the relationships between nodes, node groups, replicas, and partitions in MySQL Cluster, see Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions".

Configuration of a cluster involves configuring each individual node in the cluster and setting up individual communication links between nodes. MySQL Cluster is currently designed with the intention that data nodes are homogeneous in terms of processor power, memory space, and bandwidth. In addition, to provide a single point of configuration, all configuration data for the cluster as a whole is located in one configuration file.

The management server manages the cluster configuration file and the cluster log. Each node in the cluster retrieves the configuration data from the management server, and so requires a way to determine where the management server resides. When interesting events occur in the data nodes, the nodes transfer information about these events to the management server, which then writes the information to the cluster log.

In addition, there can be any number of cluster client processes or applications. These include standard MySQL clients, NDB-specific API programs, and management clients. These are described in the next few paragraphs.

**Standard MySQL clients.** MySQL Cluster can be used with existing MySQL applications written in PHP, Perl, C, C++, Java, Python, Ruby, and so on. Such client applications send SQL statements to and receive responses from MySQL servers acting as MySQL Cluster SQL nodes in much the same way that they interact with standalone MySQL servers.

MySQL clients using a MySQL Cluster as a data source can be modified to take advantage of the ability to connect with multiple MySQL servers to achieve load balancing and failover. For example, Java clients using Connector/J 5.0.6 and later can use jdbc:mysql:loadbalance:// URLs (improved in Connector/J 5.1.7) to achieve load balancing transparently; for more information about using Connector/J with MySQL Cluster, see Using Connector/J with MySQL Cluster.

NDB client programs. Client programs can be written that access MySQL Cluster data directly from the NDBCLUSTER storage engine, bypassing any MySQL Servers that may connected to the cluster, using the NDB API, a high-level C++ API. Such applications may be useful for specialized purposes where an SQL interface to the data is not needed. For more information, see The NDB API.

Beginning with MySQL Cluster NDB 7.1, NDB-specific Java applications can also be written for MySQL Cluster, using the *MySQL Cluster Connector for Java*. This MySQL Cluster Connector includes *ClusterJ*, a high-level database API similar to object-relational mapping persistence frameworks such as Hibernate and JPA that connect directly to NDBCLUSTER, and so does not require access to a MySQL Server. Support is also provided in MySQL Cluster NDB 7.1 and later for *ClusterJPA*, an OpenJPA implementation for MySQL Cluster that leverages the strengths of ClusterJ and JDBC; ID lookups and other fast operations are performed using ClusterJ (bypassing the MySQL Server), while more complex queries that can benefit from MySQL's query optimizer are sent through the MySQL Server, using JDBC. See Java and MySQL Cluster, and The ClusterJ API and Data Object Model, for more information.

**Management clients.** These clients connect to the management server and provide commands for starting and stopping nodes gracefully, starting and stopping message tracing (debug versions only), showing node versions and status, starting and stopping backups, and so on. An example of this type of program is the ndb\_mgm management client supplied with MySQL Cluster (see Section 6.5, "ndb\_mgm

— The MySQL Cluster Management Client"). Such applications can be written using the <u>MGM API</u>, a Clanguage API that communicates directly with one or more MySQL Cluster management servers. For more information, see The MGM API.

Oracle also makes available MySQL Cluster Manager, which provides an advanced command-line interface simplifying many complex MySQL Cluster management tasks, such restarting a MySQL Cluster with a large number of nodes. The MySQL Cluster Manager client also supports commands for getting and setting the values of most node configuration parameters as well as mysqld server options and variables relating to MySQL Cluster. See MySQL<sup>TM</sup> Cluster Manager 1.3.2 User Manual, for more information.

**Event logs.** MySQL Cluster logs events by category (startup, shutdown, errors, checkpoints, and so on), priority, and severity. A complete listing of all reportable events may be found in Section 7.6, "Event Reports Generated in MySQL Cluster". Event logs are of the two types listed here:

- Cluster log: Keeps a record of all desired reportable events for the cluster as a whole.
- Node log: A separate log which is also kept for each individual node.

#### Note

Under normal circumstances, it is necessary and sufficient to keep and examine only the cluster log. The node logs need be consulted only for application development and debugging purposes.

**Checkpoint.** Generally speaking, when data is saved to disk, it is said that a *checkpoint* has been reached. More specific to MySQL Cluster, a checkpoint is a point in time where all committed transactions are stored on disk. With regard to the NDB storage engine, there are two types of checkpoints which work together to ensure that a consistent view of the cluster's data is maintained. These are shown in the following list:

- Local Checkpoint (LCP): This is a checkpoint that is specific to a single node; however, LCPs take place
  for all nodes in the cluster more or less concurrently. An LCP involves saving all of a node's data to disk,
  and so usually occurs every few minutes. The precise interval varies, and depends upon the amount of
  data stored by the node, the level of cluster activity, and other factors.
- Global Checkpoint (GCP): A GCP occurs every few seconds, when transactions for all nodes are synchronized and the redo-log is flushed to disk.

For more information about the files and directories created by local checkpoints and global checkpoints, see MySQL Cluster Data Node FileSystemDir Files.

### 3.2 MySQL Cluster Nodes, Node Groups, Replicas, and Partitions

This section discusses the manner in which MySQL Cluster divides and duplicates data for storage.

A number of concepts central to an understanding of this topic are discussed in the next few paragraphs.

**(Data) Node.** An ndbd process, which stores a <u>replica</u>—that is, a copy of the <u>partition</u> (see below) assigned to the node group of which the node is a member.

Each data node should be located on a separate computer. While it is also possible to host multiple ndbd processes on a single computer, such a configuration is not supported.

It is common for the terms "node" and "data node" to be used interchangeably when referring to an ndbd process; where mentioned, management nodes (ndb\_mgmd processes) and SQL nodes (mysqld processes) are specified as such in this discussion.

**Node Group.** A node group consists of one or more nodes, and stores partitions, or sets of <u>replicas</u> (see next item).

The number of node groups in a MySQL Cluster is not directly configurable; it is a function of the number of data nodes and of the number of replicas (NoOfReplicas configuration parameter), as shown here:

```
[number_of_node_groups] = number_of_data_nodes / NoOfReplicas
```

Thus, a MySQL Cluster with 4 data nodes has 4 node groups if NoOfReplicas is set to 1 in the config.ini file, 2 node groups if NoOfReplicas is set to 2, and 1 node group if NoOfReplicas is set to 4. Replicas are discussed later in this section; for more information about NoOfReplicas, see Section 5.2.6, "Defining MySQL Cluster Data Nodes".

#### **Note**

All node groups in a MySQL Cluster must have the same number of data nodes.

Prior to MySQL Cluster NDB 7.0, it was not possible to add new data nodes to a MySQL Cluster without shutting down the cluster completely and reloading all of its data. In MySQL Cluster NDB 7.0 (beginning with MySQL Cluster version NDB 6.4.0), you can add new node groups (and thus new data nodes) to a running MySQL Cluster—see Section 7.13, "Adding MySQL Cluster Data Nodes Online", for information about how this can be done.

**Partition.** This is a portion of the data stored by the cluster. There are as many cluster partitions as nodes participating in the cluster. Each node is responsible for keeping at least one copy of any partitions assigned to it (that is, at least one replica) available to the cluster.

A replica belongs entirely to a single node; a node can (and usually does) store several replicas.

**NDB and user-defined partitioning.** MySQL Cluster normally partitions NDBCLUSTER tables automatically. However, in MySQL 5.1 and later MySQL Cluster releases, it is possible to employ user-defined partitioning with NDBCLUSTER tables. This is subject to the following limitations:

- 1. Only KEY and LINEAR KEY partitioning schemes can be used with NDB tables.
- 2. When using ndbd, the maximum number of partitions that may be defined explicitly for any NDB table is 8 \* [number of node groups]. (The number of node groups in a MySQL Cluster is determined as discussed previously in this section.)

When using ndbmtd, this maximum is also affected by the number of local query handler threads, which is determined by the value of the MaxNoOfExecutionThreads configuration parameter. In such cases, the maximum number of partitions that may be defined explicitly for an NDB table is equal to 4 \* MaxNoOfExecutionThreads \* [number of node groups].


See Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

For more information relating to MySQL Cluster and user-defined partitioning, see Section 3.6, "Known Limitations of MySQL Cluster", and Partitioning Limitations Relating to Storage Engines.

**Replica.** This is a copy of a cluster partition. Each node in a node group stores a replica. Also sometimes known as a *partition replica*. The number of replicas is equal to the number of nodes per node group.

The following diagram illustrates a MySQL Cluster with four data nodes, arranged in two node groups of two nodes each; nodes 1 and 2 belong to node group 0, and nodes 3 and 4 belong to node group 1. Note


that only data (ndbd) nodes are shown here; although a working cluster requires an ndb\_mgm process for cluster management and at least one SQL node to access the data stored by the cluster, these have been omitted in the figure for clarity.



The data stored by the cluster is divided into four partitions, numbered 0, 1, 2, and 3. Each partition is stored—in multiple copies—on the same node group. Partitions are stored on alternate node groups as follows:

- Partition 0 is stored on node group 0; a *primary replica* (primary copy) is stored on node 1, and a *backup replica* (backup copy of the partition) is stored on node 2.
- Partition 1 is stored on the other node group (node group 1); this partition's primary replica is on node 3, and its backup replica is on node 4.
- Partition 2 is stored on node group 0. However, the placing of its two replicas is reversed from that of Partition 0; for Partition 2, the primary replica is stored on node 2, and the backup on node 1.
- Partition 3 is stored on node group 1, and the placement of its two replicas are reversed from those of partition 1. That is, its primary replica is located on node 4, with the backup on node 3.

What this means regarding the continued operation of a MySQL Cluster is this: so long as each node group participating in the cluster has at least one node operating, the cluster has a complete copy of all data and remains viable. This is illustrated in the next diagram.



In this example, where the cluster consists of two node groups of two nodes each, any combination of at least one node in node group 0 and at least one node in node group 1 is sufficient to keep the cluster "alive" (indicated by arrows in the diagram). However, if *both* nodes from *either* node group fail, the remaining two nodes are not sufficient (shown by the arrows marked out with an **X**); in either case, the cluster has lost an entire partition and so can no longer provide access to a complete set of all cluster data.

# 3.3 MySQL Cluster Hardware, Software, and Networking Requirements

One of the strengths of MySQL Cluster is that it can be run on commodity hardware and has no unusual requirements in this regard, other than for large amounts of RAM, due to the fact that all live data storage is done in memory. (It is possible to reduce this requirement using Disk Data tables—see Section 7.12, "MySQL Cluster Disk Data Tables", for more information about these.) Naturally, multiple and faster CPUs can enhance performance. Memory requirements for other MySQL Cluster processes are relatively small.

The software requirements for MySQL Cluster are also modest. Host operating systems do not require any unusual modules, services, applications, or configuration to support MySQL Cluster. For supported operating systems, a standard installation should be sufficient. The MySQL software requirements are simple: all that is needed is a production release of MySQL Cluster. It is not strictly necessary to compile MySQL yourself merely to be able to use MySQL Cluster. We assume that you are using the binaries appropriate to your platform, available from the MySQL Cluster software downloads page at http://dev.mysql.com/downloads/cluster/.

For communication between nodes, MySQL Cluster supports TCP/IP networking in any standard topology, and the minimum expected for each host is a standard 100 Mbps Ethernet card, plus a switch, hub, or router to provide network connectivity for the cluster as a whole. We strongly recommend that a MySQL Cluster be run on its own subnet which is not shared with machines not forming part of the cluster for the following reasons:

• **Security.** Communications between MySQL Cluster nodes are not encrypted or shielded in any way. The only means of protecting transmissions within a MySQL Cluster is to run your MySQL Cluster on a protected network. If you intend to use MySQL Cluster for Web applications, the cluster should definitely reside behind your firewall and not in your network's De-Militarized Zone (DMZ) or elsewhere.

See Section 7.11.1, "MySQL Cluster Security and Networking Issues", for more information.

• Efficiency. Setting up a MySQL Cluster on a private or protected network enables the cluster to make exclusive use of bandwidth between cluster hosts. Using a separate switch for your MySQL Cluster not only helps protect against unauthorized access to MySQL Cluster data, it also ensures that MySQL Cluster nodes are shielded from interference caused by transmissions between other computers on the network. For enhanced reliability, you can use dual switches and dual cards to remove the network as a single point of failure; many device drivers support failover for such communication links.

**Network communication and latency.** MySQL Cluster requires communication between data nodes and API nodes (including SQL nodes), as well as between data nodes and other data nodes, to execute queries and updates. Communication latency between these processes can directly affect the observed performance and latency of user queries. In addition, to maintain consistency and service despite the silent failure of nodes, MySQL Cluster uses heartbeating and timeout mechanisms which treat an extended loss of communication from a node as node failure. This can lead to reduced redundancy. Recall that, to maintain data consistency, a MySQL Cluster shuts down when the last node in a node group fails. Thus, to avoid increasing the risk of a forced shutdown, breaks in communication between nodes should be avoided wherever possible.

The failure of a data or API node results in the abort of all uncommitted transactions involving the failed node. Data node recovery requires synchronization of the failed node's data from a surviving data node, and re-establishment of disk-based redo and checkpoint logs, before the data node returns to service. This recovery can take some time, during which the Cluster operates with reduced redundancy.

Heartbeating relies on timely generation of heartbeat signals by all nodes. This may not be possible if the node is overloaded, has insufficient machine CPU due to sharing with other programs, or is experiencing delays due to swapping. If heartbeat generation is sufficiently delayed, other nodes treat the node that is slow to respond as failed.

This treatment of a slow node as a failed one may or may not be desirable in some circumstances, depending on the impact of the node's slowed operation on the rest of the cluster. When setting timeout values such as <code>HeartbeatIntervalDbDb</code> and <code>HeartbeatIntervalDbApi</code> for MySQL Cluster, care must be taken care to achieve quick detection, failover, and return to service, while avoiding potentially expensive false positives.

Where communication latencies between data nodes are expected to be higher than would be expected in a LAN environment (on the order of 100 µs), timeout parameters must be increased to ensure that any allowed periods of latency periods are well within configured timeouts. Increasing timeouts in this way has a corresponding effect on the worst-case time to detect failure and therefore time to service recovery.

LAN environments can typically be configured with stable low latency, and such that they can provide redundancy with fast failover. Individual link failures can be recovered from with minimal and controlled latency visible at the TCP level (where MySQL Cluster normally operates). WAN environments may offer a range of latencies, as well as redundancy with slower failover times. Individual link failures may require route changes to propagate before end-to-end connectivity is restored. At the TCP level this can appear as large latencies on individual channels. The worst-case observed TCP latency in these scenarios is related to the worst-case time for the IP layer to reroute around the failures.

**SCI support.** It is also possible to use the high-speed Scalable Coherent Interface (SCI) with MySQL Cluster, but this is not a requirement. See Section 5.5, "Using High-Speed Interconnects with MySQL Cluster", for more about this protocol and its use with MySQL Cluster.

### 3.4 MySQL Cluster Development History

In this section, we discuss changes in the implementation of MySQL Cluster in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x, as compared to earlier MySQL Cluster releases.

There are a number of significant changes in the implementation of the NDBCLUSTER storage engine in mainline MySQL 5.1 releases up to and including MySQL 5.1.23 as compared to that in MySQL 5.0; MySQL Cluster NDB 6.x and 7.x make further changes and improvements in MySQL Cluster in addition to these. The changes and features most likely to be of interest are shown in the following tables:

#### **MySQL Cluster NDB 7.2**

Distribution of MySQL users and privileges across MySQL Cluster SQL nodes

Distributed pushed-down joins, with greatly improved performance for many joins that can thus be pushed down and executed in parallel on the data nodes.

Improved default values for data node configuration parameters.

#### **MySQL Cluster NDB 7.1**

Production-level support for MySQL Cluster on Microsoft Windows platforms.

ndbinfo meta-information database

MySQL Cluster Connector for Java, including ClusterJ and OpenJPA (ClusterJPA) support

Native support for default column values

#### **MySQL Cluster NDB 7.0**

Multi-threaded data nodes (ndbmtd data node daemon)

Online addition of data nodes; online data redistribution

MySQL on Windows (alpha; source releases only)

Configuration cache

Backup snapshots (START BACKUP ... SNAPSHOTSTART, START BACKUP ... SNAPSHOTEND commands)

IPv6 support for geo-replication

Protected DDL operations

Dynamic buffering for NDB transporters

Increased flexibility in determining arbitration handling, using a new Arbitration data node configuration parameter

NDB API counters and associated status variables, which make it possible to observe the API-level effects of SQL statements on NDB tables from the mysql client.

#### MySQL Cluster NDB 6.3

Conflict detection and resolution for multi-master replication

Compressed backups and local checkpoints

Support for OPTIMIZE TABLE

Parallel data node recovery

Enhanced transaction coordinator selection

Improved SQL statement performance metrics

Transaction batching

#### **MySQL Cluster NDB 6.3**

ndb\_restore attribute promotion

Support for epol1 (Linux only)

Distribution awareness

NDB thread locks; realtime extensions for multiple CPUs

#### MySQL Cluster NDB 6.2

Improved backup status reporting (BackupReportFrequency, REPORT BackupStatus)

Multiple connections per SQL node

Data access with NdbRecord (NDB API)

REPORT MemoryUsage command

Memory allocation improvements

Management client connection control

Micro-GCPs

Online ADD COLUMN; improved online index creation

#### **MySQL Cluster NDB 6.1**

Greater number of cluster nodes

Disabling of arbitration

Additional DUMP commands

Faster Disk Data backups

Batched slave updates

#### MySQL 5.1 (through 5.1.23)

MySQL Cluster Replication

Disk Data storage

Variable-size columns

User-defined partitioning

Autodiscovery of table schema changes

Online adding and dropping of indexes

### 3.4.1 MySQL Cluster Development in MySQL Cluster NDB 7.2.0

The following improvements to MySQL Cluster were made in MySQL Cluster NDB 7.2.0.

• **Distribution of MySQL users and privileges.** Automatic distribution of MySQL users and privileges across all SQL nodes in a given MySQL Cluster is now supported. To enable this support, you must first import an SQL script <a href="mailto:sql">share/mysql/ndb\_dist\_priv.sql</a> that is included with the MySQL Cluster NDB 7.2 distribution. This script creates several stored procedures which you can use to enable privilege distribution and perform related tasks.

When a new MySQL Server joins a MySQL Cluster where privilege distribution is in effect, it also participates in the privilege distribution automatically.

Once privilege distribution is enabled, all changes to the grant tables made on any mysqld attached to the cluster are immediately available on any other attached MySQL Servers. This is true whether the

changes are made using CREATE USER, GRANT, or any of the other statements described elsewhere in this Manual (see Account Management Statements.) This includes privileges relating to stored routines and views; however, automatic distribution of the views or stored routines themselves is not currently supported.

For more information, see Section 7.14, "Distributed MySQL Privileges for MySQL Cluster".

• Distributed pushed-down joins. Many joins can now be pushed down to the NDB kernel for processing on MySQL Cluster data nodes. Previously, a join was handled in MySQL Cluster by means of repeated accesses of NDB by the SQL node; however, when pushed-down joins are enabled, a pushable join is sent in its entirety to the data nodes, where it can be distributed among the data nodes and executed in parallel on multiple copies of the data, with a single, merged result being returned to mysqld. This can reduce greatly the number of round trips between an SQL node and the data nodes required to handle such a join, leading to greatly improved performance of join processing.

It is possible to determine when joins can be pushed down to the data nodes by examining the join with EXPLAIN. A number of new system status variables (Ndb\_pushed\_queries\_defined, Ndb\_pushed\_queries\_dropped, Ndb\_pushed\_queries\_executed, and Ndb\_pushed\_reads) and additions to the counters table (in the ndbinfo information database) can also be helpful in determining when and how well joins are being pushed down.

More information and examples are available in the description of the ndb\_join\_pushdown server system variable. See also the description of the status variables referenced in the previous paragraph, as well as Section 7.10.7, "The ndbinfo counters Table".

- Improved default values for data node configuration parameters. In order to provide more resiliency to environmental issues and better handling of some potential failure scenarios, and to perform more reliably with increases in memory and other resource requirements brought about by recent improvements in join handling by NDB, the default values for a number of MySQL Cluster data node configuration parameters have been changed. The parameters and changes are described in the following list:
  - HeartbeatIntervalDbDb: Default increased from 1500 ms to 5000 ms.
  - ArbitrationTimeout: Default increased from 3000 ms to 7500 ms.
  - TimeBetweenEpochsTimeout: Now effectively disabled by default (default changed from 4000 ms to 0).
  - SharedGlobalMemory: Default increased from 20 MB to 128 MB.
  - MaxParallelScansPerFragment: Default increased from 32 to 256.

In addition, the value computed for MaxNoOfLocalScans when this parameter is not set in config.ini has been increased by a factor of 4.

MySQL Cluster NDB 7.2.1 and later MySQL Cluster NDB 7.2 releases are based on MySQL Server 5.5 and are not covered here. See MySQL Cluster NDB 7.2.

### 3.4.2 MySQL Cluster Development in MySQL Cluster NDB 7.1

The following improvements to MySQL Cluster have been made in MySQL Cluster NDB 7.1.

• MySQL Cluster information database (ndbinfo). The ndbinfo information database makes it possible to obtain real-time characteristics of a MySQL Cluster by issuing queries from the mysql client or other MySQL client applications. ndbinfo provides metadata specific to MySQL Cluster similarly

to how the INFORMATION\_SCHEMA database provides metadata for the standard MySQL Server. This eliminates much of the need to read log files, issue REPORT or DUMP commands in the ndb\_mgm client, or parse the output of ndb\_config in order to get configuration and status information from a running MySQL Cluster.

For more information, see Section 7.10, "The ndbinfo MySQL Cluster Information Database".

• Java connectors for MySQL Cluster. The MySQL Cluster distribution now includes 2 new Java user APIs, ClusterJ and ClusterJPA. ClusterJ is an object-relational interface in a manner similar to that of Java persistence frameworks such as Hibernate. Cluster JPA is a reimplementation of OpenJPA. ClusterJ uses a backend library (NdbJTie) that provides access to the NDB storage engine without using a MySQL Server connection or JDBC. ClusterJPA also uses NdbJTie when it improves performance, but can also process complex queries using JDBC and a MySQL Server connection, where it can take advantage of the MySQL query optimizer.

ClusterJ and Cluster JPA can also be made to work with recent MySQL Cluster NDB 7.0 releases although the necessary library and JAR files are included only in MySQL Cluster NDB 7.1.1 and later.

For more information about using ClusterJ and ClusterJPA, see MySQL Cluster Connector for Java.

• New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 7.1.0, the CHANGE MASTER TO statement supports an IGNORE\_SERVER\_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

Native support for default column values. Starting with MySQL Cluster NDB 7.1.4, default values
for table columns are stored in the NDB kernel rather than by the MySQL server as was done previously.
This means that inserts on tables having column value defaults can be smaller and faster than before,
because less data must be sent from SQL nodes to NDBCLUSTER.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.1.4 and later; however, they do not support native default values until they are upgraded. You can upgrade a table with non-native default values to support native default values using an offline ALTER TABLE statement.

• MySQL Cluster on Windows (*Production*). Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is available for production use on Microsoft Windows operating systems; MySQL Cluster NDB 7.1 binaries for Windows can be obtained from <a href="http://dev.mysql.com/downloads/cluster/">http://dev.mysql.com/downloads/cluster/</a>.

Features and behavior are generally comparable to those found on previously supported platforms such as Linux and Solaris. However, you must install the binaries manually.

Beginning with MySQL Cluster NDB 7.1.5, MySQL Cluster processes can be run as Windows services.

If you wish to build MySQL Cluster from source on Windows, you must configure the build using the WITH\_NDBCLUSTER\_STORAGE\_ENGINE option. For more information, see Installing MySQL from Source on Windows.

- --nowait-nodes option for management servers. It is now possible to configure a cluster with two management servers, but to start the cluster using only one of them by starting the management node daemon with the --nowait-nodes option. The other management server can then be started at a later time to join the running MySQL Cluster.
- Improved lock handling for primary key lookups on BLOB tables. A MySQL Cluster table stores all but the first 256 bytes of any BLOB or TEXT column values in a separate BLOB table; when executing

queries against such tables, a shared lock is obtained. Prior to MySQL Cluster NDB 7.1.1, when the query used a primary key lookup and took place within a transaction, the lock was held for the duration of the transaction, even after no more data was being read from the NDB table. Now in such cases, the lock is released when all BLOB data associated with the table has been read. (Bug #49190)

#### Note

A shared lock is also taken for unique key lookups; it is still the case that this lock is held for the duration of the transaction.

- **Heartbeat thread policy and priority.** Beginning with MySQL Cluster NDB 7.1.2, a new configuration parameter <code>HeartbeatThreadPriority</code> makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb\_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 7.1.2, the --blob-info option causes this program to include partition information for BLOB tables in its output. Also beginning with MySQL Cluster NDB 7.1.2, the --extra-node-info option causes ndb\_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 7.1.2.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster Replication supports attribute promotion and demotion when replicating between columns of different but similar types on the master and the slave. For example, it is possible to promote an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave\_type\_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Change in ndbinfo database. The experimental pools table was removed from ndbinfo in MySQL Cluster NDB 7.1.3. Applications which used this table can and should be rewritten to use other ndbinfo tables.
- Configuration caching control. Beginning with MySQL Cluster NDB 7.1.4, it is possible to disable the management server's configuration cache using the --config-cache option, which forces ndb\_mgmd to read its configuration data from the config.ini configuration file every time it starts. For more information about configuration caching and this option, see Section 5.2, "MySQL Cluster Configuration Files". See also Section 6.4, "ndb\_mgmd The MySQL Cluster Management Server Daemon".
- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 7.1.4, DDL events are no longer reported on Event objects by default. Instead the desired level of event reporting (EventReport value) must be set explicitly using Event::setReport().
- **Number of table attributes.** Beginning with MySQL Cluster NDB 7.1.4, the maximum number of attributes (columns plus indexes) per table has been increased from 128 to 512.
- Innobs support in commercial binaries. Beginning with MySQL Cluster NDB 7.1.4b, all commercial binary releases of MySQL Cluster provide support for the Innobs storage engine.

- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 7.1.5, it is possible to set a specific order for transmission of heartbeats between data nodes, using the <a href="HeartbeatOrder">HeartbeatOrder</a> data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb\_restore column comparison rules. When restoring data, ndb\_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb\_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 7.1.5, ndb\_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
  - COLUMN\_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
  - STORAGE setting (MEMORY or DISK)
  - · The default value
  - The distribution key

In such cases, ndb\_restore reports any such differences to minimize any chance of user error.

- Storage of user data in anyValue. When writing NDB events to the binary log, MySQL Cluster uses OperationOptions::anyValue to store the server ID. Beginning with MySQL Cluster NDB 7.1.6, it is possible to store user data from an NDB API application in part of the anyValue when mysqld has been started with the --server-id-bits option set to a nondefault value. Also beginning with MySQL Cluster NDB 7.1.6, it is possible to view this data in the output of mysqlbinlog, for which its own --server-id-bits option is added.
- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 7.1.8, this option can be used to force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Forcing node shutdown and restart. In MySQL Cluster NDB 7.1.8 and later, it is possible using the ndb\_mgm management client or the MGM API to force a data node shutdown or restart even if this would force the shutdown or restart of the entire cluster. In the management client, this is implemented through the addition of the -f (force) option to the STOP and RESTART commands. For more information, see Section 7.2, "Commands in the MySQL Cluster Management Client". The MGM API also adds two new methods for forcing such a node shutdown or restart; see ndb\_mgm\_stop4(), and ndb\_mgm\_restart4(), for more information about these methods.
- Disk Data usage statistics (diskpagebuffer table). MySQL Cluster 7.1.9 introduces a new table in the ndbinfo information database. The diskpagebuffer table provides real-time data on disk page buffer usage. These statistics can be used to monitor performance of MySQL Cluster Disk Data read and write operations, and can prove useful in the tuning of Disk Data parameters such as DiskPageBufferMemory.
- Innobb Plugin support. Beginning with MySQL Cluster NDB 7.1.9, the MySQL Server supplied with MySQL Cluster supports the Innobb Plugin. For more information about enabling the plugin if you are building MySQL Cluster from source, see Chapter 4, MySQL Cluster Installation and Upgrades.

#### Note

Due to a packaging issue, the InnoDB plugin was not included in RPMs for MySQL Cluster NDB 7.1.9; this issue was corrected in MySQL Cluster NDB 7.1.9a. (Bug #58283)

- TimeBetweenEpochsTimeout and GCP stop control. Beginning with MySQL Cluster NDB 7.1.10, it is possible to disable GCP stops by setting TimeBetweenEpochsTimeout to 0. In addition, a warning is written to the cluster log whenever the time required for a GCP save exceeds 60 seconds or the time required for a GCP commit exceeds 10 seconds. This warning includes a report of the current value of TimeBetweenEpochsTimeout. For more information, see Disk Data and GCP Stop errors.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 7.1.10, you can cause ndb\_restore to ignore tables that are corrupted due to missing blob parts tables by using the --skip-broken-objects [343] option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- BLOB read and write batching. Beginning with MySQL Cluster NDB 7.1.10, it possible to control batching of BLOB read and write operations. For SQL nodes, this can be done using the --ndb-blob-read-batch-bytes and --ndb-blob-write-batch-bytes options for mysqld. In NDB API applications, you can control batching of BLOB reads and writes using the NdbTransaction methods setMaxPendingBlobReadBytes(), getMaxPendingBlobReadBytes(), setMaxPendingBlobWriteBytes().
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 7.1.11 adds a new --rewrite-database [343] option to ndb\_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup", for more information.

• Selective over-commit handling. Beginning with MySQL Cluster NDB 7.1.10, it is possible to exercise more direct control over uncommitted operations from transactions aborted due to timeouts flushing redo logs to disk. This is implemented using three configuration parameters added in this version of MySQL Cluster: the data node configuration parameters RedoOverCommitCounter and RedoOverCommitLimit, and the API node configuration parameter DefaultOperationRedoProblemAction.

When an attempt to flush a given redo log takes longer than RedoOverCommitLimit seconds, and this occurs RedoOverCommitLimit times or more, the transactions contained within the redo log are aborted. Any operations left uncommitted as a result are either aborted or re-tried, according to the value of DefaultOperationRedoProblemAction.

For more information, see Redo log over-commit handling

• INFORMATION\_SCHEMA improvements. Beginning with MySQL Cluster NDB 7.1.11, Beginning with MySQL Cluster NDB 7.0.22, INFORMATION\_SCHEMA provides disk usage information for MySQL Cluster Disk Data tables. Previously, INFORMATION\_SCHEMA.TABLES showed only the space usage for the in-memory data part of the table. Now, it also shows the space allocated for and used by the disk\_part data of that table as well.

In addition, the INFORMATION\_SCHEMA.PARTITIONS table (which did not show any statistics for NDB tables) now shows correct values in this table's TABLE\_ROWS, AVG\_ROW\_LENGTH, DATA\_LENGTH, MAX\_DATA\_LENGTH, and DATA\_FREE columns, for each partition.

• ndb\_restore attribute demotion. Beginning with MySQL Cluster NDB 7.1.11, it is possible to enable attribute demotion when restoring a MySQL Cluster from a native backup running ndb\_restore with a new --lossy-conversions [334] option.

In general, the rules governing demotion are the same as for MySQL replication, although there are some exceptions that you may need to take into account being employing this option. See Replication of Columns Having Different Data Types, for information about type conversions currently supported by attribute promotion and demotion in MySQL Cluster.

- Improved multi-threaded order index building. Previously, it was not possible to enable multi-threaded building of ordered indexes during initial restarts. In MySQL Cluster NDB 7.1.11, this can now be done, using the new TwoPassInitialNodeRestartCopy data node configuration parameter.
- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config\_generation column which is added to the nodes table in MySQL Cluster NDB 7.1.13.
- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config\_generation column which is added to the nodes table in MySQL Cluster NDB 7.1.13.
- Improvements in adding data nodes online. Begining with MySQL Cluster NDB 7.0.24, it is possible to add data nodes online to a running MySQL Cluster without performing a rolling restart of the cluster or starting data node processes with the --nowait-nodes option. This can be done by setting Nodegroup = 65536 in the config.ini file for any data nodes that should be started at a later time, when first starting the cluster. The amount of time the cluster waits before doing this can be controlled using the StartNoNodeGroupTimeout data node configuration parameter.
- **Unique key updates in replication.** It is possible in MySQL Cluster NDB 7.1.14 and later to employ operations that update unique keys when replicating NDB tables. Previously this could lead to duplicate key errors when trying to execute the binary log (due to the fact that row events in the binary log were ordered according to the partitioning of the base table, and could differ in order within the epoch for that in which they were executed).

#### **Important**

Master and slave tables must both be using the  ${\tt NDB}$  storage engine for this to work

• Starting with MySQL Cluster NDB 7.1.17, the NDB kernel implements a number of statistical counters relating to actions performed by or affecting Ndb objects. Such events include starting, closing, and aborting transactions; operations using primary keys or unique keys; table, range, and pruned scans; blocking of threads by incompleted operations; and data and events sent and received by MySQL Cluster nodes. NDB API statistics counters are incremented inside the NDB kernel whenever NDB API calls are made or data is sent to or received by the data nodes. A MySQL Server running as an SQL node in the cluster can access the values of these counters as system status variables, as seen in the output of Show Status, or in the results of queries against the Session\_Status or Global\_Status table in the Information\_Schema database. By comparing the values of these status variables before and after the execution of statements affecting NDB tables, you can observe the corresponding actions taken on the NDB API level. This can be highly useful when monitoring and tuning MySQL Cluster.

For more information, see Section 7.15, "NDB API Statistics Counters and Variables". See also Section 5.4.4, "MySQL Cluster Status Variables", for information about the individual status variables.

• Version 2 binary log row events. New versions of the WRITE\_ROW, UPDATE\_ROW, and DELETE ROW events have been implemented in MySQL Cluster NDB 7.1.16, extending them with

additional information intended to support future enhancements; these are referred to as "Version 2" binary log events.

Version 2 log events are not backward compatible, and cannot be read by older slaves. A new mysqld option --log-bin-use-v1-row-events can be employed to force use of Version 1 events when writing the binary log. This can be used during upgrades to make a newer mysqld generate Version 1 binary log row events that can be read by older slaves.

• Circular replication: "Primary wins first" conflict detection. Two new conflict detection functions NDB\$EPOCH() and NDB\$EPOCH\_TRANS() can be useful in "active-active" circular replication scenarios with two MySQL Clusters. For each case, we designate one cluster as primary and one as secondary, and implement a "primary always wins" rule for determining whether to accept conflicting changes. When using NDB\$EPOCH(), conflicting rows on the secondary are realigned with those on the primary; when using NDB\$EPOCH\_TRANS(), it is transactions containing rows in conflict (and any transactions which depend on them) on the secondary that are realigned.

When using NDB\$EFOCH\_TRANS() as the conflict detection function, the binary log must be written using Version 2 binary logging row events; that is, the mysqld processes on both the primary and the secondary must be started with --log-bin-use-v1-row-events=0. In addition, the secondary's binary log must include transaction IDs for all rows, that is, by setting --ndb-log-transaction-id=1.

You can monitor conflict detection and resolution performed using these functions by reading a number of related server status variables, including Ndb\_conflict\_fn\_epoch, Ndb\_conflict\_fn\_epoch\_trans, and Ndb\_conflict\_trans\_row\_conflict\_count (among others). See Section 5.4.4, "MySQL Cluster Status Variables".

For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

- Fail-fast data node capability. Beginning with MySQL Cluster NDB 7.1.17, it is possible to enable fail-fast behavior for data nodes by enabling the CrashOnCorruptedTuple configuration parameter introduced in this version (disabled by default). Doing so causes data nodes to fail whenever they detect a corrupted tuple.
- Rows per partition limit removed. Previously it was possible to store a maximum of 46137488 rows in a single MySQL Cluster partition—that is, per data node. Beginning with MySQL Cluster NDB 7.0.36 and MySQL Cluster NDB 7.1.25, this limitation has been lifted, and there is no longer any practical upper limit to this number. (Bug #13844405, Bug #14000373)

MySQL Cluster NDB 7.1 is also supported by MySQL Cluster Manager, which provides an advanced command-line interface that can simplify many complex MySQL Cluster management tasks. See MySQL™ Cluster Manager 1.3.2 User Manual, for more information.

### 3.4.3 MySQL Cluster Development in MySQL Cluster NDB 7.0

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 7.0. For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 7.0, see http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-7-0.html.

#### **Important**

Early development versions of MySQL Cluster NDB 7.0 were known as "MySQL Cluster NDB 6.4", and the first four releases in this series were identified as MySQL Cluster NDB 6.4.0 through 6.4.3. Any information relating to these MySQL Cluster NDB 6.4.x releases appearing in this documentation apply to MySQL Cluster NDB 7.0

MySQL Cluster NDB 7.0.4 is the fifth MySQL Cluster NDB 7.0 release; it is the successor to MySQL Cluster NDB 6.4.3.

- MySQL Cluster on Windows (alpha). MySQL Cluster NDB 7.0 is available on an experimental basis for Windows operating systems (for production use on Windows, you should use MySQL Cluster NDB 7.1.3 or later). Features and behavior comparable to those found on platforms that are already supported —such as Linux and Solaris—are planned for MySQL Cluster on Windows. In MySQL Cluster NDB 7.0, you must build from source (Windows binaries are available for MySQL Cluster NDB 7.1 releases). To enable MySQL Cluster support on Windows when building from source, you must configure the build using the WITH\_NDBCLUSTER\_STORAGE\_ENGINE option. For more information, see Installing MySQL from Source on Windows.
- Ability to add nodes and node groups online. Beginning with MySQL Cluster NDB 6.4.0, it is possible to add new node groups (and thus new data nodes) to a running MySQL Cluster without shutting down and reloading the cluster. As part of enabling this feature, a new command CREATE NODEGROUP has been added to the cluster management client and the functionality of the ALTER ONLINE TABLE ... REORGANIZE PARTITION SQL statement has been extended. For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".
- Data node multi-threading support. Beginning with MySQL Cluster NDB 6.4.0, a multi-threaded version of the data node daemon, named ndbmtd, is available for use on data node hosts with multiple CPU cores. This binary is built automatically when compiling with MySQL Cluster support; no additional options other than those needed to provide MySQL Cluster support are needed when configuring the build. In most respects, ndbmtd functions in the same way as ndbd, and can use the same command-line options and configuration parameters. In addition, the new MaxNoOfExecutionThreads configuration parameter can be used to determine the number of data node process threads for ndbmtd. For more information, see Section 6.3, "ndbmtd The MySQL Cluster Data Node Daemon (Multi-Threaded)".

#### Note

Disk Data tables are not yet supported for use with ndbmtd.

- Configuration cache. Formerly, MySQL Cluster configuration was stateless—that is, configuration information was reloaded from the cluster's global configuration file (usually config.ini) each time ndb\_mgmd was started. Beginning with MySQL Cluster NDB 6.4.0, the cluster's configuration is cached internally, and the global configuration file is no longer automatically re-read when the management server is restarted. This behavior can be controlled using the management server options --configdir, --initial, and --reload. In MySQL Cluster NDB 7.0.15 and later, the configuration cache can be disabled using the --config-cache option. For more information about these changes, see Section 5.2, "MySQL Cluster Configuration Files". For more information about the new management server options, see Section 6.4, "ndb\_mgmd The MySQL Cluster Management Server Daemon".
- Detection of NDB API client connection errors. In MySQL Cluster NDB 7.0 (6.4.0 and later releases), the NDB API's Ndb\_cluster\_connection class adds the get\_latest\_error() and get\_latest\_error\_msg() methods for catching and diagnosing problems with NDB API client connections.
- Snapshot options for backups. Beginning with MySQL Cluster NDB 6.4.0, you can determine when performing a cluster backup whether the backup matches the state of the data when the backup was started or when it was completed, using the new options SNAPSHOTSTART and SNAPSHOTEND for the management client's START BACKUP command. See Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup", for more information.

- Dynamic NDB transporter send buffer memory allocation. Previously, the NDB kernel used a fixed-size send buffer for every data node in the cluster, which was allocated when the node started. Because the size of this buffer could not be changed after the cluster was started, it was necessary to make it large enough in advance to accommodate the maximum possible load on any transporter socket. However, this was an inefficient use of memory, since much of it often went unused. Beginning with MySQL Cluster NDB 6.4.0, send buffer memory is allocated dynamically from a memory pool shared between all transporters, which means that the size of the send buffer can be adjusted as necessary. This change is reflected by the addition of the configuration parameters TotalSendBufferMemory, ReservedSendBufferMemory, and OverLoadLimit, as well as a change in how the existing SendBufferMemory configuration parameter is used. For more information, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".
- Robust DDL operations. Beginning with MySQL Cluster NDB 6.4.0, DDL operations (such as CREATE TABLE or ALTER TABLE) are protected from data node failures; in the event of a data node failure, such operations are now rolled back gracefully. Previously, if a data node failed while trying to perform a DDL operation, the MySQL Cluster data dictionary became locked and no further DDL statements could be executed without restarting the cluster.
- **IPv6 support in MySQL Cluster Replication.** Beginning with MySQL Cluster NDB 6.4.1, IPv6 networking is supported between MySQL Cluster SQL nodes, which makes it possible to replicate between instances of MySQL Cluster using IPv6 addresses. However, IPv6 is supported only for direct connections between MySQL servers; all connections *within* an individual MySQL Cluster must use IPv4. For more information, see Section 8.3, "Known Issues in MySQL Cluster Replication".
- Restoring specific databases, tables, or columns from a MySQL Cluster backup. It is now possible to exercise more fine-grained control when restoring a MySQL Cluster from backup using ndb\_restore. Beginning with MySQL Cluster NDB 6.4.3, you can choose to restore only specified tables or databases, or exclude specific tables or databases from being restored, using the new ndb\_restore options --include-tables, --include-databases, --exclude-tables, and --exclude-databases. Beginning with MySQL Cluster NDB 7.0.7, it is also possible to restore to a table having fewer columns than the original using the --exclude-missing-columns option. For more information about all of these options, see Section 6.19, "ndb\_restore Restore a MySQL Cluster Backup".
- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.4.3, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.
- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL Cluster NDB 6.4.3, using the data node configuration parameters InitialLogFileGroup and InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group, tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements are required to create these Disk Data objects. For more information, see Disk Data object creation parameters.
- Improved internal message passing and record handling. MySQL Cluster NDB 7.0 contains 2 changes that optimize the use of network connections by addressing the size and number of messages passed between data nodes, and between data nodes and API nodes, which can increase MySQL Cluster and application performance:
  - Packed reads. Formerly, each read request signal contained a list of columns to be retrieved, each of these column identifiers using 4 bytes within the message. This meant that the message size increased as the number of columns being fetched increased. In addition, in the response from the

data node, each column result was packed to a 4-byte boundary, which resulted in wasted space. In MySQL Cluster NDB 7.0, messaging for read operations is optimized in both directions, using a bitmap in the read request to specify the columns to be fetched. Where many fields are requested, this can result in a significant message size reduction as compared with the old method. In addition, the 4-byte packing in responses is no longer used, which means that smaller fields consume less space.

• Long signal transactions. This enhancement reduces the number of messages and signals that are sent to data nodes for complex requests. Prior to MySQL Cluster NDB 7.0, there was a 100 byte limit on the size of the request signal, which meant that complex requests had to be split up between multiple messages prior to transmission, then reassembled on the receiving end. In addition to actual payload data, each message required its own operating system and protocol overhead such as header information. This often wasted network bandwidth and data node CPU. The maximum size of the message is now 32 KB, which is sufficient to accommodate most queries.

Both of these optimizations are internal to the NDB API, and so is transparent to applications; this is true whether an application uses the NDB API directly or does so indirectly through an SQL node.

- Configuration parameter data dumps. Starting with MySQL Cluster NDB 7.0.6, the ndb\_config utility supports a --configinfo option that causes it to dump a list of all configuration parameters supported by the cluster, along with brief descriptions, information about the parameters' default and permitted values, and the sections of the config.ini file in which the parameters apply. An additional --xml switch causes ndb\_config to use XML rather than plaintext output. Using ndb\_config --configinfo or ndb\_config --configinfo --xml requires no access to a running MySQL Cluster, any other programs, or any files. For more information and examples, see Section 6.7, "ndb\_config Extract MySQL Cluster Configuration Information".
- Per-table reporting of free space on disk. The INFORMATION\_SCHEMA.FILES table shows information about used and free space in MySQL Cluster Disk Data data files, but this information is not applicable to individual tables. In MySQL Cluster NDB 7.0.8 and later, the ndb\_desc utility provides two additional columns in its output that show the amount of space allocated on disk for a given NDB table as well the amount of space that remains available for additional storage of disk-based column data for that table. For more information, see Section 6.10, "ndb\_desc Describe NDB Tables".
- Improved restart times. Optimizations in redo log handling and other file system operations
  introduced in MySQL Cluster NDB 7.0.9 have the potential to reduce considerably the time required for
  restarts. While actual performance benefits observed in production setups will naturally vary depending
  on database size, hardware, and other conditions, our own preliminary testing has shown that these
  improvements can yield startup times that are faster than those typical of previous MySQL Cluster NDB
  7.0 releases by a factor of 50 or more.
- Native support for default column values. Starting with MySQL Cluster NDB 7.0.15, default values
  for table columns are stored in the NDB kernel rather than by the MySQL server as was done previously.
  This means that inserts on tables having column value defaults can be smaller and faster than before,
  because less data must be sent from SQL nodes to NDBCLUSTER.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.0.15 and later; however, they do not support native default values until they are upgraded. You can upgrade a table with non-native default values to support native default values using an offline ALTER TABLE statement.

--nowait-nodes option for management servers. Starting with MySQL Cluster NDB 7.0.10, it is possible to configure a cluster with two management servers, but to start the cluster using only one of them by starting the management node daemon with the --nowait-nodes option. The other management server can then be started at a later time to join the running MySQL Cluster.

• Increased flexibility in online upgrade procedure. Previously, when performing an upgrade of a running MySQL cluster, the order in which the types of cluster nodes had to be upgraded was very strict. However, beginning with MySQL Cluster NDB 7.0.10, MySQL Cluster supports online upgrading of API nodes (including MySQL servers running as SQL nodes) online upgrading management nodes, data nodes, or both.

#### **Important**

Before attempting to use this new upgrade functionality, see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster", for additional information, especially if you are planning an online upgrade to MySQL Cluster NDB 7.0 from MySQL Cluster NDB 6.3.

• New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 7.0.11, the CHANGE MASTER TO statement supports an IGNORE\_SERVER\_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

- New replication conflict resolution strategy. Beginning with MySQL Cluster NDB 7.0.11, the function NDB\$MAX\_DELETE\_WIN() is available to implement "greatest timestamp, delete wins" conflict resolution. See NDB\$MAX\_DELETE\_WIN(column\_name), for more information.
- Improved lock handling for primary key lookups on BLOB tables. A MySQL Cluster table stores all but the first 256 bytes of any BLOB or TEXT column values in a separate BLOB table; when executing queries against such tables, a shared lock is obtained. Prior to MySQL Cluster NDB 7.0.12, when the query used a primary key lookup and took place within a transaction, the lock was held for the duration of the transaction, even after no more data was being read from the NDB table. Now in such cases, the lock is released when all BLOB data associated with the table has been read. (Bug #49190)

#### Note

A shared lock is also taken for unique key lookups; it is still the case that this lock is held for the duration of the transaction.

- Heartbeat thread policy and priority. Beginning with MySQL Cluster NDB 7.0.13, a new configuration parameter HeartbeatThreadPriority makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb\_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 7.0.13, the --blob-info option causes this program to include partition information for BLOB tables in its output. Beginning with MySQL Cluster NDB 7.0.14, the --extra-node-info option causes ndb\_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 7.0.14.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 7.0.14,
MySQL Cluster Replication supports attribute promotion and demotion when replicating between
columns of different but similar types on the master and the slave. For example, it is possible to promote
an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a
VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave\_type\_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 7.0.15, DDL events are no longer reported on Event objects by default. Instead such event reporting must be enabled explicitly using the Event::setReport() method. For more information, see Event::setReport(), and The Event::EventReport Type.
- **Number of table attributes.** Beginning with MySQL Cluster NDB 7.0.15, the maximum number of attributes (columns plus indexes) per table has been increased from 128 to 512.
- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 7.0.16, it is possible to set a specific order for transmission of heartbeats between data nodes, using the <a href="HeartbeatOrder">HeartbeatOrder</a> data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb\_restore column comparison rules. When restoring data, ndb\_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb\_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 7.0.16, ndb\_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
  - COLUMN\_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
  - STORAGE setting (MEMORY or DISK)
  - · The default value
  - The distribution key

In such cases, ndb\_restore reports any such differences to minimize any chance of user error.

- Storage of user data in anyValue. When writing NDB events to the binary log, MySQL Cluster uses OperationOptions::anyValue to store the server ID. Beginning with MySQL Cluster NDB 7.0.17, it is possible to store user data from an NDB API application in part of the anyValue when mysqld has been started with the --server-id-bits option set to a nondefault value. Also beginning with MySQL Cluster NDB 7.0.17, it is possible to view this data in the output of mysqlbinlog, for which its own --server-id-bits option is added.
- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 7.0.19, this option can be used to force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Forcing node shutdown and restart. In MySQL Cluster NDB 7.0.19 and later, it is possible using the ndb\_mgm management client or the MGM API to force a data node shutdown or restart even if this would force the shutdown or restart of the entire cluster. In the management client, this is implemented through the addition of the -f (force) option to the STOP and RESTART commands. For more information, see Section 7.2, "Commands in the MySQL Cluster Management Client". The MGM API also adds two new methods for forcing such a node shutdown or restart; see ndb\_mgm\_stop4(), and ndb\_mgm\_restart4(), for more information about these methods.

- TimeBetweenEpochsTimeout and GCP stop control. Beginning with MySQL Cluster NDB 7.0.21, it is possible to disable GCP stops by setting TimeBetweenEpochsTimeout to 0. In addition, a warning is written to the cluster log whenever the time required for a GCP save exceeds 60 seconds or the time required for a GCP commit exceeds 10 seconds. This warning includes a report of the current value of TimeBetweenEpochsTimeout. For more information, see Disk Data and GCP Stop errors.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 7.0.21, you can cause ndb\_restore to ignore tables that are corrupted due to missing blob parts tables by using the --skip-broken-objects [343] option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- BLOB read and write batching. Beginning with MySQL Cluster NDB 7.0.21, it possible to control batching of BLOB read and write operations. For SQL nodes, this can be done using the --ndb-blob-read-batch-bytes and --ndb-blob-write-batch-bytes options for mysqld. In NDB API applications, you can control batching of BLOB reads and writes using the NdbTransaction methods setMaxPendingBlobReadBytes(), getMaxPendingBlobReadBytes(), setMaxPendingBlobWriteBytes().
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 7.0.22 adds a new --rewrite-database [343] option to ndb\_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup", for more information.

• INFORMATION\_SCHEMA inprovements. Beginning with MySQL Cluster NDB 7.0.22, INFORMATION\_SCHEMA provides disk usage information for MySQL Cluster Disk Data tables. Previously, INFORMATION\_SCHEMA.TABLES showed only the space usage for the in-memory data part of the table. Now, it also shows the space allocated for and used by the disk\_part data of that table as well.

In addition, the INFORMATION\_SCHEMA. PARTITIONS table (which did not show any statistics for NDB tables) now shows correct values in this table's TABLE\_ROWS, AVG\_ROW\_LENGTH, DATA\_LENGTH, MAX\_DATA\_LENGTH, and DATA\_FREE columns, for each partition.

- Configuration version information in ndbinfo.nodes. You can see which version or versions of the MySQL Cluster configuration file are in effect on the data nodes by checking the config\_generation column which is added to the nodes table in MySQL Cluster NDB 7.0.24.
- Improvements in adding data nodes online. Beginning with MySQL Cluster NDB 7.0.24, it is possible to add data nodes online to a running MySQL Cluster without performing a rolling restart of the cluster or starting data node processes with the --nowait-nodes option. This can be done by setting Nodegroup = 65536 in the config.ini file for any data nodes that should be started at a later time, when first starting the cluster. The amount of time the cluster waits before doing this can be controlled using the StartNoNodeGroupTimeout data node configuration parameter.
- Unique key updates in replication. It is possible in MySQL Cluster NDB 7.0.25 and later to employ operations that update unique keys when replicating NDB tables. Previously this could lead to duplicate key errors when trying to execute the binary log (due to the fact that row events in the binary log were ordered according to the partitioning of the base table, and could differ in order within the epoch for that in which they were executed).

#### **Important**

Master and slave tables must both be using the  ${\tt NDB}$  storage engine for this to work.

• Starting with MySQL Cluster NDB 7.0.22, the NDB kernel implements a number of statistical counters relating to actions performed by or affecting Ndb objects. Such events include starting, closing, and aborting transactions; operations using primary keys or unique keys; table, range, and pruned scans; blocking of threads by incompleted operations; and data and events sent and received by MySQL Cluster nodes. NDB API statistics counters are incremented inside the NDB kernel whenever NDB API calls are made or data is sent to or received by the data nodes. A MySQL Server running as an SQL node in the cluster can access the values of these counters as system status variables, as seen in the output of SHOW STATUS, or in the results of queries against the SESSION\_STATUS or GLOBAL\_STATUS table in the INFORMATION\_SCHEMA database. By comparing the values of these status variables before and after the execution of statements affecting NDB tables, you can observe the corresponding actions taken on the NDB API level. This can be highly useful when monitoring and tuning MySQL Cluster.

For more information, see Section 7.15, "NDB API Statistics Counters and Variables". See also Section 5.4.4, "MySQL Cluster Status Variables", for information about the individual status variables.

Version 2 binary log row events. New versions of the WRITE\_ROW, UPDATE\_ROW, and
 DELETE\_ROW events have been implemented in MySQL Cluster NDB 7.0.27, extending them with
 additional information intended to support future enhancements; these are referred to as "Version 2"
 binary log events.

Version 2 log events are not backward compatible, and cannot be read by older slaves. A new mysqld option --log-bin-use-vl-row-events can be employed to force use of Version 1 events when writing the binary log. This can be used during upgrades to make a newer mysqld generate Version 1 binary log row events that can be read by older slaves.

- Fail-fast data node capability. Beginning with MySQL Cluster NDB 7.0.28, it is possible to enable fail-fast behavior for data nodes by enabling the CrashOnCorruptedTuple configuration parameter introduced in this version (disabled by default). Doing so causes data nodes to fail whenever they detect a corrupted tuple.
- Rows per partition limit removed. Previously it was possible to store a maximum of 46137488 rows in a single MySQL Cluster partition—that is, per data node. Beginning with MySQL Cluster NDB 7.0.36, this limitation has been lifted, and there is no longer any practical upper limit to this number.

# 3.4.4 MySQL Cluster Development in MySQL Cluster NDB 6.3

The following list provides an overview of significant feature additions and changes first made in MySQL Cluster NDB 6.3. For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 6.3, see http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-6-3.html.

- Conflict detection and resolution. It is now possible to detect and resolve conflicts that arise in multi-master replication scenarios, such as circular replication, when different masters may try to update the same row on the slave with different data. Both "greatest timestamp wins" and "same timestamp wins" scenarios are supported. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".
- Recovery of "one master, many slaves" replication setups. Recovery of multi-way replication setups ("one master, many slaves") is now supported using the --ndb-log-orig server option and changes in the mysql.ndb\_binlog\_index table. See Section 8.4, "MySQL Cluster Replication Schema and Tables", for more information.
- Enhanced selection options for transaction coordinator. New values and behaviors are introduced for --ndb\_optimized\_node\_selection, enabling greater flexibility when an SQL node chooses a transaction coordinator. For more information, see the description of ndb\_optimized\_node\_selection in Section 5.4.3, "MySQL Cluster System Variables".

- Replication heartbeats. Replication heartbeats facilitate the task of monitoring and detecting failures in master-slave connections in real time. This feature is implemented using a new MASTER\_HEARTBEAT\_PERIOD = value clause for the CHANGE MASTER TO statement and the addition of two status variables Slave\_heartbeat\_period and Slave\_received\_heartbeats. For more information, see CHANGE MASTER TO Syntax.
- NDB thread locks. It is possible to lock NDB execution threads and maintenance threads (such as file system and other operating system threads) to specific CPUs on multiprocessor data node hosts, and to leverage real-time scheduling.
- Improved performance of updates using primary keys or unique keys. The number of unnecessary reads when performing a primary key or unique key update has been greatly reduced. Since it is seldom necessary to read a record prior to an update, this can yield a considerable improvement in performance. In addition, primary key columns are no longer written to when not needed during update operations.
- Batching improvements. Support of batched DELETE and UPDATE operations has been significantly improved. Batching of UPDATE WHERE... and multiple DELETE operations is also now implemented.
- Improved SQL statement performance metrics. The Ndb\_execute\_count system status variable measures the number of round trips made by SQL statements to the NDB kernel, providing an improved metric for determining efficiency with which statements are executed. For more information, see MySQL Cluster Status Variables: Ndb\_execute\_count.
- Compressed LCPs and backups. Compressed local checkpoints and backups can save 50% or more of the disk space used by uncompressed LCPs and backups. These can be enabled using the two new data node configuration parameters CompressedLCP and CompressedBackup, respectively.
- OPTIMIZE TABLE support with NDBCLUSTER tables. OPTIMIZE TABLE is supported for dynamic columns of in-memory NDB tables. In such cases, it is no longer necessary to drop (and possibly to recreate) a table, or to perform a rolling restart, in order to recover memory from deleted rows for general re-use by Cluster. The performance of OPTIMIZE on Cluster tables can be tuned by adjusting the value of the ndb\_optimization\_delay system variable, which controls the number of milliseconds to wait between processing batches of rows by OPTIMIZE TABLE. In addition, OPTIMIZE TABLE on an NDBCLUSTER table can be interrupted by, for example, killing the SQL thread performing the OPTIMIZE operation.
- Batching of transactions. It is possible to cause statements occurring within the same transaction to be run as a batch by setting the session variable transaction\_allow\_batching to 1 or ON. To use this feature, autocommit must be set to 0 or OFF. Batch sizes can be controlled using the --ndb-batch-size option for mysqld. For additional information, see Section 5.4.2, "MySQL Server Options for MySQL Cluster", and Section 5.4.3, "MySQL Cluster System Variables".
- Attribute promotion with ndb\_restore. It is possible using ndb\_restore to restore data reliably from a column of a given type to a column that uses a "larger" type. This is sometimes referred to as <a href="https://doi.org/10.1001/jat.2011/jat.
- Parallel data node recovery. Recovery of multiple data nodes can now be done in parallel, rather than sequentially. In other words, several data nodes can be restored concurrently, which can often result in much faster recovery times than when they are restored one at a time.
- Increased local checkpoint efficiency. Only 2 local checkpoints are stored, rather than 3, lowering disk space requirements and the size and number of redo log files.

- NDBCLUSTER table persistence control. Persistence of NDB tables can be controlled using the session variables ndb\_table\_temporary and ndb\_table\_no\_logging. ndb\_table\_no\_logging causes NDB tables not to be checkpointed to disk; ndb\_table\_temporary does the same, and in addition, no schema files are created. See Section 5.4.1, "MySQL Cluster mysqld Option and Variable Reference".
- Epoll support (*Linux only*). *Epoll* is an improved method for handling file descriptors, which is more efficient than scanning to determine whether a file descriptor has data to be read. (The term *epoll* is specific to Linux and equivalent functionality is known by other names on other platforms such as Solaris and FreeBSD.) Currently, MySQL Cluster supports this functionality on Linux only.
- **Distribution awareness (SQL nodes).** In MySQL Cluster NDB 6.3, SQL nodes can take advantage of distribution awareness. Here we provide a brief example showing how to design a table to make a given class of queries distribution-aware. Suppose an NDBCLUSTER table t1 has the following schema:

```
CREATE TABLE t1 (
    userid INT NOT NULL,
    serviceid INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
    data VARCHAR(255)
) ENGINE=NDBCLUSTER;
```

Suppose further that most of the queries to be used in our application test values of the userid column of this table. The form of such a query looks something like this:

```
SELECT columns FROM t1
WHERE userid relation value;
```

In this query, relation represents some relational operator, such as =, <, >, and so on. Queries using IN and a list of values can also be used:

```
SELECT columns FROM t1
WHERE userid IN value_list;
```

To make use of distribution awareness, we need to make the userid column part of the table's primary key, then explicitly partition the table with this column being used as the partitioning key. (Recall that for a partitioned table having one or more unique keys, all columns of the table's partitioning key must also be part of all of the unique keys—for more information and examples, see Partitioning Keys, Primary Keys, and Unique Keys.) In other words, the table schema should be equivalent to the following CREATE TABLE statement:

```
CREATE TABLE t1 (
    userid INT NOT NULL,
    serviceid INT NOT NULL AUTO_INCREMENT,
    data VARCHAR(255),
    PRIMARY KEY p (userid, serviceid)
) ENGINE=NDBCLUSTER
    PARTITION BY KEY(userid);
```

When the table is partitioned in this way, all rows having the same userid value are found on the same node group, and the MySQL Server can immediately select the optimal node to use as the transaction coordinator.

• Realtime extensions for multiple CPUs. When running MySQL Cluster data nodes on hosts with multiple processors, the realtime extensions make it possible to give priority to the data node process and control on which CPU cores it should operate. This can be done using the data node configuration parameters RealtimeScheduler, SchedulerExecutionTimer, and SchedulerSpinTimer. Doing

so properly can significantly lower response times and make them much more predictable response. For more information about using these parameters, see Defining Data Nodes: Realtime Performance Parameters

- Fully automatic database discovery. It is no longer a requirement for database autodiscovery that an SQL node already be connected to the cluster at the time that a database is created on another SQL node, or for a CREATE DATABASE or CREATE SCHEMA statement to be issued on the new SQL node after it joins the cluster.
- Detection of NDB API client connection errors. Beginning with MySQL Cluster NDB 6.3.20, the NDB API's Ndb\_cluster\_connection class adds the get\_latest\_error() and get\_latest\_error\_msg() methods for catching and diagnosing problems with NDB API client connections.
- Restoring specific databases, tables, or columns from a MySQL Cluster backup. It is now possible to exercise more fine-grained control when restoring a MySQL Cluster from backup using ndb\_restore. Beginning with MySQL Cluster NDB 6.3.22, you can choose to restore only specified tables or databases, or exclude specific tables or databases from being restored, using the new ndb\_restore options --include-tables, --include-databases, --exclude-tables, and --exclude-databases. Beginning with MySQL Cluster NDB 6.3.26, it is also possible to restore to a table having fewer columns than the original using the --exclude-missing-columns option. For more information about all of these options, see Section 6.19, "ndb\_restore Restore a MySQL Cluster Backup".
- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.3.22, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.
- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL
   Cluster NDB 6.3.22, using the data node configuration parameters InitialLogFileGroup and
   InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group,
   tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements
   are required to create these Disk Data objects. For more information, see Disk Data object creation
   parameters.
- Configuration parameter data dumps. Starting with MySQL Cluster NDB 6.3.25, the ndb\_config utility supports a --configinfo option that causes it to dump a list of all configuration parameters supported by the cluster, along with brief descriptions, information about the parameters' default and permitted values, and the sections of the config.ini file in which the parameters apply. An additional --xml switch causes ndb\_config to use XML rather than plaintext output. Using ndb\_config --configinfo or ndb\_config --configinfo --xml requires no access to a running MySQL Cluster, any other programs, or any files. For more information and examples, see Section 6.7, "ndb\_config Extract MySQL Cluster Configuration Information".
- Per-table reporting of free space on disk. The INFORMATION\_SCHEMA.FILES table shows information about used and free space in MySQL Cluster Disk Data data files, but this information is not applicable to individual tables. In MySQL Cluster NDB 6.3.27 and later, the ndb\_desc utility provides two additional columns in its output that show the amount of space allocated on disk for a given NDB table as well the amount of space that remains available for additional storage of disk-based column data for that table. For more information, see Section 6.10, "ndb\_desc Describe NDB Tables".
- Improved restart times. Optimizations in redo log handling and other file system operations introduced in MySQL Cluster NDB 6.3.28 have the potential to reduce considerably the time required for

restarts. While actual performance benefits observed in production setups will naturally vary depending on database size, hardware, and other conditions, our own preliminary testing has shown that these improvements can yield startup times that are faster than those typical of previous MySQL Cluster NDB 6.3 releases by a factor of 50 or more.

Increased flexibility in online upgrade procedure. Previously, when performing an upgrade of a
running MySQL cluster, the order in which the types of cluster nodes had to be upgraded was very strict.
However, beginning with MySQL Cluster NDB 6.3.29, MySQL Cluster supports online upgrading of API
nodes (including MySQL servers running as SQL nodes) before upgrading management nodes, data
nodes, or both.

## **Important**

Before attempting to use this new upgrade functionality, see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster", for additional information, especially if you are planning an online upgrade from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0.

- New replication conflict resolution strategy. Beginning with MySQL Cluster NDB 6.3.31, the function NDB\$MAX\_DELETE\_WIN() is available to implement "greatest timestamp, delete wins" conflict resolution. See NDB\$MAX\_DELETE\_WIN(column\_name), for more information.
- New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 6.3.31, the CHANGE MASTER TO statement supports an IGNORE\_SERVER\_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

- Heartbeat thread policy and priority. Beginning with MySQL Cluster NDB 6.3.32, a new configuration parameter HeartbeatThreadPriority makes it possible to set the policy and the priority for the heartbeat thread on management and API nodes.
- Improved access to partitioning information. The ndb\_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 6.3.32, the --blob-info option causes this program to include partition information for BLOB tables in its output. Beginning with MySQL Cluster NDB 6.3.33, the --extra-node-info option causes ndb\_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). Each of these options also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 6.3.33.

Replication attribute promotion and demotion. Beginning with MySQL Cluster NDB 6.3.33,
MySQL Cluster Replication supports attribute promotion and demotion when replicating between
columns of different but similar types on the master and the slave. For example, it is possible to promote
an INT column on the master to a BIGINT column on the slave, and to demote a TEXT column to a
VARCHAR column.

The implementation of type demotion distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave\_type\_conversions global server system variable.

For more information, see Attribute promotion and demotion (MySQL Cluster).

- Incompatible change in NDB API event reporting. Beginning with MySQL Cluster NDB 6.3.34, DDL events are no longer reported on Event objects by default. Instead such event reporting must be enabled explicitly using the Event::setReport() method. For more information, see Event::setReport(), and The Event::EventReport Type.
- **Heartbeat ordering.** Beginning with MySQL Cluster NDB 6.3.35, it is possible to set a specific order for transmission of heartbeats between data nodes, using the <code>HeartbeatOrder</code> data node configuration parameter introduced in this version. This parameter can be useful in situations where multiple data nodes are running on the same host and a temporary disruption in connectivity between hosts would otherwise cause the loss of a node group (and thus failure of the cluster).
- Relaxed ndb\_restore column comparison rules. When restoring data, ndb\_restore compares the attributes of a column for equality with the definition of the column in the target table. However, not all of these attributes need to be the same for ndb\_restore to be meaningful, safe and useful. Beginning with MySQL Cluster NDB 6.3.35, ndb\_restore automatically ignores differences in certain column attributes which do not necessarily have to match between the version of the column in a backup and the version of that column in the MySQL Cluster to which the column data is being restored. These attributes include the following:
  - COLUMN\_FORMAT setting (FIXED, DYNAMIC, or DEFAULT)
  - STORAGE setting (MEMORY or DISK)
  - · The default value
  - The distribution key

In such cases, ndb\_restore reports any such differences to minimize any chance of user error.

- --add-drop-trigger option for mysqldump. Beginning with MySQL Cluster NDB 6.3.38, this option can be used to force all CREATE TRIGGER statements in mysqldump output to be preceded by a DROP TRIGGER IF EXISTS statement.
- Skipping corrupted tables in NDB native backups. Beginning with MySQL Cluster NDB 6.3.40, you can cause ndb\_restore to ignore tables that are corrupted due to missing blob parts tables by using the --skip-broken-objects [343] option. When this option is used, such tables are skipped, and the restoration of any remaining uncorrupted tables in the backup continues.
- Restoring from a NDB native backup to a differently-named database. MySQL Cluster NDB 6.3.41 adds a new --rewrite-database [343] option to ndb\_restore, which makes it possible to restore to a database having a different name from that of the database in the backup. The option can be used multiple times, and it is possible to restore from more than one source database in the backup to a single target database (although no protection against table or other object name collision is provided).

See Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup", for more information.

# 3.4.5 MySQL Cluster Development in MySQL Cluster NDB 6.2

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 6.2. All of the changes in this list are also available in MySQL Cluster NDB 6.3 . For more detailed information about all feature changes and bugfixes made in MySQL Cluster NDB 6.2, see http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-6-2.html.

• **Enhanced backup status reporting.** Backup status reporting has been improved, aided in part by the introduction of a BackupReportFrequency configuration parameter.

- Multiple cluster connections per SQL node. A single MySQL server acting as a MySQL Cluster SQL node can employ multiple connections to the cluster using the --ndb-cluster-connection-pool startup option for mysqld. This option is described in MySQL Cluster-Related Command Options for mysqld: --ndb-cluster-connection-pool option.
- **New data access interface.** The NdbRecord interface provides a new and simplified data handler for use in NDB API applications.
- New reporting commands. The new management client REPORT BackupStatus and REPORT MemoryUsage commands provide better access to information about the status of MySQL Cluster backups and how much memory is being used by MySQL Cluster for data and index storage. See Section 7.2, "Commands in the MySQL Cluster Management Client", for more information about the REPORT commands. In addition, in-progress status reporting is provided by the ndb\_restore utility; see Section 6.19, "ndb restore Restore a MySQL Cluster Backup".
- Improved memory allocation and configuration. Memory is now allocated by the NDB kernel to tables on a page-by-page basis, which significantly reduces the memory overhead required for maintaining NDBCLUSTER tables. In addition, the MaxAllocate [128] configuration parameter now makes it possible to set the maximum size of the allocation unit used for table memory.
- Choice of fixed-width or variable-width columns. You can control whether fixed-width or variable-width storage is used for a given column of an NDB table by employing of the COLUMN\_FORMAT specifier as part of the column's definition in a CREATE TABLE or ALTER TABLE statement. In addition, the ability to control whether a given column of an NDB table is stored in memory or on disk, using the STORAGE specifier as part of the column's definition in a CREATE TABLE or ALTER TABLE statement. For more information, see CREATE TABLE Syntax, and ALTER TABLE Syntax.
- Controlling management client connections. The --bind-address cluster management server startup option makes it possible to restrict management client connections to ndb\_mgmd to a single host (IP address or host name) and port, which can make MySQL Cluster management operations more secure. For more information about this option, see Section 6.4, "ndb\_mgmd The MySQL Cluster Management Server Daemon".
- **Micro-GCPs.** Due to a change in the protocol for handling of global checkpoints (GCPs handled in this manner sometimes being referred to as "micro-GCPs"), it is now possible to control how often the GCI number is updated, and how often global checkpoints are written to disk, using the <code>TimeBetweenEpochs</code> and <code>TimeBetweenEpochsTimeout</code> configuration parameters. This improves the reliability and performance of MySQL Cluster Replication.
- Core online schema change support. Support for the online ALTER TABLE operations ADD COLUMN, ADD INDEX, and DROP INDEX is available. When the ONLINE keyword is used, the ALTER TABLE is noncopying, which means that indexes do not have to be re-created, which provides these benefits:
  - Single user mode is no longer required for ALTER TABLE operations that can be performed online.
  - Transactions can continue during ALTER TABLE operations that can be performed online.
  - Tables being altered online are not locked against access by other SQL nodes.

However, such tables are locked against other operations on the *same* SQL node for the duration of the ALTER TABLE. We are working to overcome this limitation in a future MySQL Cluster release.

Online CREATE INDEX and DROP INDEX statements are also supported. Online changes can be suppressed using the OFFLINE key word. See ALTER TABLE Online Operations in MySQL Cluster, CREATE INDEX Syntax, and DROP INDEX Syntax, for more detailed information.

- mysql.ndb\_binlog\_index improvements. More information has been added to the mysql.ndb\_binlog\_index table so that it is possible to determine which originating epochs have been applied inside an epoch. This is particularly useful for 3-way replication. See Section 8.4, "MySQL Cluster Replication Schema and Tables", for more information.
- **Epoch lag control.** The MaxBufferedEpochs data node configuration parameter provides a means to control the maximum number of unprocessed epochs by which a subscribing node can lag. Subscribers which exceed this number are disconnected and forced to reconnect.
- Fully automatic database discovery. It is no longer a requirement for database autodiscovery that an SQL node already be connected to the cluster at the time that a database is created on another SQL node, or for a CREATE DATABASE or CREATE SCHEMA statement to be issued on the new SQL node after it joins the cluster.
- Multiple data node processes per host.
   In earlier MySQL Cluster release series, we did not support MySQL Cluster deployments in production where more than one ndbd process was run on a single physical machine. However, beginning with MySQL Cluster NDB 6.2.0, you can use multiple data node processes on a single host.

#### Note

A multi-threaded version of ndbd tailored for use on hosts with multiple CPUs or cores was introduced in MySQL Cluster NDB 7.0. See Section 3.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

- Improved Disk Data file system configuration. As of MySQL Cluster NDB 6.2.17, you can specify default locations for MySQL Cluster Disk Data data files and undo log files using the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles. This eliminates the need to use symbolic links to place Disk Data files separately from other files in data node file systems to improve Disk Data performance. For more information, see Disk Data file system parameters.
- Automatic creation of Disk Data log file groups and tablespaces. Beginning with MySQL Cluster NDB 6.2.17, using the data node configuration parameters InitialLogFileGroup and InitialTablespace, you can cause the creation of a MySQL Cluster Disk Data log file group, tablespace, or both, when the cluster is first started. When using these parameters, no SQL statements are required to create these Disk Data objects.
- Improved access to partitioning information. The ndb\_desc utility now provides additional information about the partitioning of data stored in MySQL Cluster. Beginning with MySQL Cluster NDB 6.2.19, the --extra-node-info option causes ndb\_desc to include information about data distribution (that is, which table fragments are stored on which data nodes). This option also requires the use of the --extra-partition-info option.

Information about partition-to-node mappings can also be obtained using the Table::getFragmentNodes() method, also added in MySQL Cluster NDB 6.2.19.

• New CHANGE MASTER TO option for circular replication. Beginning with MySQL Cluster NDB 6.2.19, the CHANGE MASTER TO statement supports an IGNORE\_SERVER\_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. (Log rotation and log deletion events are preserved.)

See CHANGE MASTER TO Syntax, as well as SHOW SLAVE STATUS Syntax, for more information.

# 3.4.6 MySQL Cluster Development in MySQL Cluster NDB 6.1

The following list provides an overview of significant feature additions and changes made in MySQL Cluster NDB 6.1. All of the changes in this list are also available in MySQL Cluster NDB 6.2 and 6.3 releases. For detailed information about all changes made in MySQL Cluster NDB 6.1, see http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-6-1.html.

- Increased number of cluster nodes. The maximum number of all nodes in a MySQL Cluster has been increased to 255. For more information, see Section 3.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".
- **Disabling arbitration.** It is now possible to disable arbitration by setting ArbitrationRank=0 on all cluster management and SQL nodes. For more information, see *Defining the Management Server:*ArbitrationRank and *Defining SQL and Other API Nodes:* ArbitrationRank.
- Additional DUMP commands. New management client DUMP commands provide help with tracking transactions, scan operations, and locks. See Section 7.2, "Commands in the MySQL Cluster Management Client", and DUMP Commands, for more information.
- Faster Disk Data backups. Improvements in backups of Disk Data tables can yield a 10 to 15% increase in backup speed of Disk Data tables.
- Batched slave updates. Batching of updates on cluster replication slaves, enabled using the -- slave-allow-batching option for mysqld, increases replication efficiency. For more information, see Section 8.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

## 3.4.7 Development History of MySQL Cluster in MySQL 5.1

A number of features for MySQL Cluster were implemented in MySQL 5.1 through MySQL 5.1.23, when support for MySQL Cluster was moved to MySQL Cluster NDB. All of the features in the following list are also available in all MySQL Cluster NDB (6.1 and later) releases.

• Integration of MySQL Cluster into MySQL Replication. MySQL Cluster Replication makes it possible to replicate from one MySQL Cluster to another. Updates on any SQL node (MySQL server) in the cluster acting as the master are replicated to the slave cluster; the state of the slave side remains consistent with the cluster acting as the master. This is sometimes referred to as asynchronous replication between clusters, providing geographic redundancy. It is also possible to replicate from a MySQL Cluster acting as the master to a standalone MySQL server acting as the slave, or from a standalone MySQL master server to a slave cluster; in either of these cases, the standalone MySQL server uses a storage engine other than NDBCLUSTER. Multi-master replication setups such as circular replication are also supported.

See Chapter 8, MySQL Cluster Replication.

• Support for storage of rows on disk. Storage of NDBCLUSTER table data on disk is now supported. Indexed columns, including the primary key hash index, must still be stored in RAM; however, all other columns can be stored on disk.

See Section 7.12, "MySQL Cluster Disk Data Tables".

Variable-size columns. In MySQL 5.0, an NDBCLUSTER table column defined as VARCHAR (255) used 260 bytes of storage independent of what was stored in any particular record. In MySQL 5.1 Cluster tables, only the portion of the column actually taken up by the record is stored. This makes possible a significant reduction in space requirements for such columns as compared to previous release series—by a factor of up to 5 in many cases.

• **User-defined partitioning.** Users can define partitions based on columns that are part of the primary key. It is possible to partition NDB tables based on KEY and LINEAR KEY schemes. This feature is also available for many other MySQL storage engines, which support additional partitioning types that are not available with NDBCLUSTER tables.

For additional general information about user-defined partitioning in MySQL 5.1, see Partitioning. Specifics of partitioning types are discussed in Partitioning Types.

The MySQL Server can also determine whether it is possible to "prune away" some of the partitions from the WHERE clause, which can greatly speed up some queries. See Partition Pruning, for information about designing tables and queries to take advantage of partition pruning.

Autodiscovery of table schema changes. In MySQL 5.0, it was necessary to issue a FLUSH
TABLES statement or a "dummy" SELECT for new NDBCLUSTER tables or changes made to schemas
of existing NDBCLUSTER tables on one SQL node to be visible on the cluster's other SQL nodes. In
MySQL 5.1, this is no longer necessary; new Cluster tables and changes in the definitions of existing
NDBCLUSTER tables made on one SQL node are immediately visible to all SQL nodes connected to the
cluster.

#### Note

When creating a new database, it is still necessary in MySQL 5.1 to issue a CREATE DATABASE or CREATE SCHEMA statement on each SQL node in the cluster.

- **Distribution awareness (NDB API).** <u>Distribution awareness</u> is a mechanism by which the best data node is automatically selected to be queried for information. (Conceptually, it is similar in some ways to partition pruning (see Partition Pruning). To take advantage of distribution awareness, you should do the following:
  - 1. Determine which table column is most likely to be used for finding matching records.
  - 2. Make this column part of the table's primary key.
  - 3. Explicitly partition the table by KEY, using this column as the table' partitioning key.

Following these steps causes records with the same value for the partitioning column to be stored on the same partition (that is, in the same node group). When reading data, transactions are begun on the data node actually having the desired rows instead of this node being determined by the usual round-robin mechanism.

#### Important

To see a measureable impact on performance, the cluster must have at least four data nodes, since, with only two data nodes, both data nodes have exactly the same data.

Using distribution awareness can yield performance increase of as great as 45% when using four data nodes, and possibly more when using a greater number of data nodes.

#### Note

In mainline MySQL 5.1 releases, distribution awareness was supported only when using the NDB API; support was added for SQL and API nodes in MySQL Cluster NDB 6.3 (see Section 3.4.4, "MySQL Cluster Development in MySQL

Cluster NDB 6.3", which includes an example showing how to create a table to take advantage of distribution awareness).

• Online adding and dropping of indexes. For ALTER TABLE statements, ADD INDEX and DROP INDEX operations for dynamic (variable-width) columns on NDB tables are now performed as online operations (no table copying). This is also true for CREATE INDEX and DROP INDEX. As a result, these operations are now performed much more quickly than previously.

For more information, see ALTER TABLE Online Operations in MySQL Cluster, CREATE INDEX Syntax, and DROP INDEX Syntax.

See Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

# 3.5 MySQL Server Using InnoDB Compared with MySQL Cluster

MySQL Server offers a number of choices in storage engines. Since both NDBCLUSTER and InnoDB can serve as transactional MySQL storage engines, users of MySQL Server sometimes become interested in MySQL Cluster. They see NDB as a possible alternative or upgrade to the default InnoDB storage engine in MySQL 5.5. While NDB and InnoDB share common characteristics, there are differences in architecture and implementation, so that some existing MySQL Server applications and usage scenarios can be a good fit for MySQL Cluster, but not all of them.

In this section, we discuss and compare some characteristics of the NDB storage engine used by MySQL Cluster with InnoDB used in MySQL 5.1 and MySQL 5.5. The next few sections provide a technical comparison. In many instances, decisions about when and where to use MySQL Cluster must be made on a case-by-case basis, taking all factors into consideration. While it is beyond the scope of this documentation to provide specifics for every conceivable usage scenario, we also attempt to offer some very general guidance on the relative suitability of some common types of applications for NDB as opposed to InnoDB backends.

While it is possible to use InnoDB tables with MySQL Cluster, such tables are not clustered. MySQL Cluster NDB 7.1 releases use a mysqld based on MySQL 5.1 which includes InnoDB 1.0; MySQL Cluster NDB 7.2.1 and later are based on MySQL Server 5.5, which includes support for InnoDB 1.1. It is also not possible to use programs or libraries from a MySQL Cluster NDB 6.x or MySQL Cluster NDB 7.x distribution with MySQL Server 5.1 or MySQL Server 5.5, or the reverse.

While it is also true that some types of common business applications can be run either on MySQL Cluster or on MySQL Server (most likely using the InnoDB storage engine), there are some important architectural and implementation differences. Section 3.5.1, "Differences Between the NDB and InnoDB Storage Engines", provides a summary of the these differences. Due to the differences, some usage scenarios are clearly more suitable for one engine or the other; see Section 3.5.2, "NDB and InnoDB Workloads". This in turn has an impact on the types of applications that better suited for use with NDB or InnoDB. See Section 3.5.3, "NDB and InnoDB Feature Usage Summary", for a comparison of the relative suitability of each for use in common types of database applications.

For information about the relative characteristics of the NDB and MEMORY storage engines, see When to Use MEMORY or MySQL Cluster.

See Storage Engines, for additional information about MySQL storage engines.

## 3.5.1 Differences Between the NDB and InnoDB Storage Engines

The MySQL Cluster NDB storage engine is implemented using a distributed, shared-nothing architecture, which causes it to behave differently from InnoDB in a number of ways. For those unaccustomed to

working with NDB, unexpected behaviors can arise due to its distributed nature with regard to transactions, foreign keys, joins, and other characteristics. These are shown in the following table:

Feature	InnoDB	MySQL Cluster
MySQL Server Version	InnoDB 1.1: 5.5 InnoDB 1.0: 5.1	MySQL Cluster NDB 6.3, 7.0, 7.1: 5.1
	INNODB 1.0. 5.1	MySQL Cluster NDB 7.2: 5.5
		MySQL Cluster NDB 7.3: 5.6
InnoDB Availability	InnoDB 1.1 plugin	NDB 6.3, 7.0: InnoDB storage engine
		NDB 7.1: InnoDB 1.0 plugin support (MySQL Cluster NDB 7.1.9a and later)
		NDB 7.2: InnoDB 1.1 (MySQL Cluster NDB 7.2.1 and later)
Storage Limits	64TB	3TB
		(Practical upper limit based on 48 data nodes with 64GB RAM each; can be increased with disk-based data and BLOBs)
Foreign Keys	Yes	Prior to MySQL Cluster NDB 7.3: No. (Ignored, as with MyISAM)
		Available in MySQL Cluster NDB 7.3 and later.
Transactions	All standard types	READ COMMITTED
MVCC	Yes	No
Data Compression	Yes	No
		(MySQL Cluster checkpoint and backup files can be compressed)
Large Row Support (> 14K)	Supported for VARBINARY, VARCHAR, BLOB, and TEXT columns	Supported for BLOB and TEXT columns only  (Using these types to store very large amounts of data can lower MySQL Cluster performance)
Replication Support	Asynchronous and semisynchronous replication using MySQL Replication	Automatic synchronous replication within a MySQL Cluster.  Asynchronous replication between MySQL Clusters, using MySQL Replication
Scaleout for Read Operations	Yes (MySQL Replication)	Yes (Automatic partitioning in MySQL Cluster; MySQL Replication)

Feature	InnoDB	MySQL Cluster
Scaleout for Write Operations	Requires application-level partitioning (sharding)	Yes (Automatic partitioning in MySQL Cluster is transparent to applications)
High Availability (HA)	Requires additional software	Yes (Designed for 99.999% uptime)
Node Failure Recovery and Failover	Requires additional software	Automatic (Key element in MySQL Cluster architecture)
Time for Node Failure Recovery	30 seconds or longer	Typically < 1 second
Real-Time Performance	No	Yes
In-Memory Tables	No	Yes (Some data can optionally be stored on disk; both in-memory and disk data storage are durable)
NoSQL Access to Storage Engine	Native memcached interface in development (see the MySQL Dev Zone article MySQL Cluster 7.2 (DMR2): NoSQL, Key/Value, Memcached)	Yes  Multiple APIs, including C++, HTTP/REST, Java and JPA (MySQL Cluster NDB 7.1 and later); Memcached (MySQL Cluster NDB 7.2 and later); Node.js under development (MySQL Cluster NDB 7.3)
Concurrent and Parallel Writes	Not supported	Up to 48 writers, optimized for concurrent writes
Conflict Detection and Resolution (Multiple Replication Masters)	No	Yes
Hash Indexes	No	Yes
Online Addition of Nodes	Read-only replicas using MySQL Replication	Yes (all node types)
Online Upgrades	No	Yes
Online Schema Modifications	No.	Yes.

## 3.5.2 NDB and InnoDB Workloads

MySQL Cluster has a range of unique attributes that make it ideal to serve applications requiring high availability, fast failover, high throughput, and low latency. Due to its distributed architecture and multinode implementation, MySQL Cluster also has specific constraints that may keep some workloads from performing well. A number of major differences in behavior between the NDB and InnoDB storage engines with regard to some common types of database-driven application workloads are shown in the following table::

Workload	InnoDB	MySQL Cluster (NDB)
High-Volume OLTP Applications	Yes	Yes

Workload	InnoDB	MySQL Cluster (NDB)
DSS Applications (data marts, analytics)	Yes	Limited (Join operations across OLTP datasets not exceeding 3TB in size)
Custom Applications	Yes	Yes
Packaged Applications	Yes	Limited (should be mostly primary key access).
		Note
		MySQL Cluster NDB 7.3
		supports foreign keys.
In-Network Telecoms Applications (HLR, HSS, SDP)	No	Yes
Session Management and Caching	Yes	Yes
E-Commerce Applications	Yes	Yes
User Profile Management, AAA Protocol	Yes	Yes

## 3.5.3 NDB and InnoDB Feature Usage Summary

When comparing application feature requirements to the capabilities of InnoDB with NDB, some are clearly more compatible with one storage engine than the other.

The following table lists supported application features according to the storage engine to which each feature is typically better suited.

Preferred applicat	ion requirements for InnoDB	Preferred application requirements for NDB
Foreign keys		Write scaling
	Note	• 99.999% uptime
	MySQL Cluster NDB 7.3 supports foreign keys.	Online addition of nodes and online schema operations
Full table scans		Multiple SQL and NoSQL APIs (see MySQL
Very large database	ases, rows, or transactions	Cluster APIs: Overview and Concepts)
	er than READ COMMITTED	Real-time performance
Transactions our	CI TIGHT READ COMMITTED	Limited use of BLOB columns

# 3.6 Known Limitations of MySQL Cluster

In the sections that follow, we discuss known limitations in current releases of MySQL Cluster as compared with the features available when using the MyISAM and InnoDB storage engines. If you check the "Cluster" category in the MySQL bugs database at http://bugs.mysql.com, you can find known bugs in the following

categories under "MySQL Server:" in the MySQL bugs database at http://bugs.mysql.com, which we intend to correct in upcoming releases of MySQL Cluster:

- MySQL Cluster
- Cluster Direct API (NDBAPI)
- · Cluster Disk Data
- · Cluster Replication
- ClusterJ

This information is intended to be complete with respect to the conditions just set forth. You can report any discrepancies that you encounter to the MySQL bugs database using the instructions given in How to Report Bugs or Problems. If we do not plan to fix the problem in MySQL Cluster NDB 7.1, we will add it to the list.

See Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x" for a list of issues in MySQL Cluster in MySQL 5.0 that have been resolved in the current version.

#### Note

Limitations and other issues specific to MySQL Cluster Replication are described in Section 8.3, "Known Issues in MySQL Cluster Replication".

## 3.6.1 Noncompliance with SQL Syntax in MySQL Cluster

Some SQL statements relating to certain MySQL features produce errors when used with NDB tables, as described in the following list:

- **Temporary tables.** Temporary tables are not supported. Trying either to create a temporary table that uses the NDB storage engine or to alter an existing temporary table to use NDB fails with the error Table storage engine 'ndbcluster' does not support the create option 'TEMPORARY'.
- Indexes and keys in NDB tables. Keys and indexes on MySQL Cluster tables are subject to the following limitations:
  - Column width. Attempting to create an index on an NDB table column whose width is greater than 3072 bytes succeeds, but only the first 3072 bytes are actually used for the index. In such cases, a warning Specified key was too long; max key length is 3072 bytes is issued, and a SHOW CREATE TABLE statement shows the length of the index as 3072.
  - **TEXT and BLOB columns.** You cannot create indexes on NDB table columns that use any of the TEXT or BLOB data types.
  - **FULLTEXT indexes.** The NDB storage engine does not support FULLTEXT indexes, which are possible for MyISAM tables only.

However, you can create indexes on VARCHAR columns of NDB tables.

- USING HASH keys and NULL. Using nullable columns in unique keys and primary keys means that queries using these columns are handled as full table scans. To work around this issue, make the column NOT NULL, or re-create the index without the USING HASH option.
- **Prefixes.** There are no prefix indexes; only entire columns can be indexed. (The size of an NDB column index is always the same as the width of the column in bytes, up to and including 3072 bytes,

as described earlier in this section. Also see Section 3.6.6, "Unsupported or Missing Features in MySQL Cluster", for additional information.)

- **BIT columns.** A BIT column cannot be a primary key, unique key, or index, nor can it be part of a composite primary key, unique key, or index.
- AUTO\_INCREMENT columns. Like other MySQL storage engines, the NDB storage engine can handle a maximum of one AUTO\_INCREMENT column per table. However, in the case of a Cluster table with no explicit primary key, an AUTO\_INCREMENT column is automatically defined and used as a "hidden" primary key. For this reason, you cannot define a table that has an explicit AUTO\_INCREMENT column unless that column is also declared using the PRIMARY KEY option. Attempting to create a table with an AUTO\_INCREMENT column that is not the table's primary key, and using the NDB storage engine, fails with an error.
- MySQL Cluster and geometry data types.
   Geometry data types (WKT and WKB) are supported in NDB tables in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1). However, spatial indexes are not supported.
- Character sets and binary log files. Currently, the ndb\_apply\_status and ndb\_binlog\_index tables are created using the latin1 (ASCII) character set. Because names of binary logs are recorded in this table, binary log files named using non-Latin characters are not referenced correctly in these tables. This is a known issue, which we are working to fix. (Bug #50226)

To work around this problem, use only Latin-1 characters when naming binary log files or setting any the --basedir, --log-bin, or --log-bin-index options.

• Creating NDBCLUSTER tables with user-defined partitioning. Support for user-defined partitioning for MySQL Cluster is restricted to [LINEAR] KEY partitioning. Beginning with MySQL 5.1.12, using any other partitioning type with ENGINE=NDB or ENGINE=NDBCLUSTER in a CREATE TABLE statement results in an error.

**Default partitioning scheme.** As of MySQL 5.1.6, all MySQL Cluster tables are by default partitioned by KEY using the table's primary key as the partitioning key. If no primary key is explicitly set for the table, the "hidden" primary key automatically created by the NDBCLUSTER storage engine is used instead. For additional discussion of these and related issues, see KEY Partitioning.

Beginning with MySQL Cluster NDB 6.2.18, MySQL Cluster NDB 6.3.25, and MySQL Cluster NDB 7.0.6, CREATE TABLE and ALTER TABLE statements that would cause a user-partitioned NDBCLUSTER table not to meet either or both of the following two requirements are not permitted, and fail with an error (Bug #40709):

- 1. The table must have an explicit primary key.
- 2. All columns listed in the table's partitioning expression must be part of the primary key.

**Exception.** If a user-partitioned NDBCLUSTER table is created using an empty column-list (that is, using PARTITION BY [LINEAR] KEY()), then no explicit primary key is required.

**Maximum number of partitions for NDECLUSTER tables.** The maximum number of partitions that can defined for a NDBCLUSTER table when employing user-defined partitioning is 8 per node group. (See Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions", for more information about MySQL Cluster node groups.

**DROP PARTITION not supported.** It is not possible to drop partitions from NDB tables using ALTER TABLE . . . DROP PARTITION. The other partitioning extensions to ALTER TABLE—ADD PARTITION, REORGANIZE PARTITION, and COALESCE PARTITION—are supported for Cluster

tables, but use copying and so are not optimized. See Management of RANGE and LIST Partitions and ALTER TABLE Syntax.

## · Row-based replication.

When using row-based replication with MySQL Cluster, binary logging cannot be disabled. That is, the NDB storage engine ignores the value of sql\_log\_bin. (Bug #16680)

## 3.6.2 Limits and Differences of MySQL Cluster from Standard MySQL Limits

In this section, we list limits found in MySQL Cluster that either differ from limits found in, or that are not found in, standard MySQL.

**Memory usage and recovery.** Memory consumed when data is inserted into an NDB table is not automatically recovered when deleted, as it is with other storage engines. Instead, the following rules hold true:

A DELETE statement on an NDB table makes the memory formerly used by the deleted rows available
for re-use by inserts on the same table only. However, this memory can be made available for general
re-use by performing a rolling restart of the cluster. See Section 7.5, "Performing a Rolling Restart of a
MySQL Cluster".

Beginning with MySQL Cluster NDB 6.3.7, this limitation can be overcome using OPTIMIZE TABLE. See Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

• A DROP TABLE or TRUNCATE TABLE operation on an NDB table frees the memory that was used by this table for re-use by any NDB table, either by the same table or by another NDB table.

#### Note

Recall that TRUNCATE TABLE drops and re-creates the table. See TRUNCATE TABLE Syntax.

## Limits imposed by the cluster's configuration.

A number of hard limits exist which are configurable, but available main memory in the cluster sets limits. See the complete list of configuration parameters in Section 5.2, "MySQL Cluster Configuration Files". Most configuration parameters can be upgraded online. These hard limits include:

Database memory size and index memory size (DataMemory and IndexMemory, respectively).

DataMemory is allocated as 32KB pages. As each DataMemory page is used, it is assigned to a specific table; once allocated, this memory cannot be freed except by dropping the table.

See Section 5.2.6, "Defining MySQL Cluster Data Nodes", for more information.

• The maximum number of operations that can be performed per transaction is set using the configuration parameters MaxNoOfConcurrentOperations and MaxNoOfLocalOperations.

#### Note

Bulk loading, TRUNCATE TABLE, and ALTER TABLE are handled as special cases by running multiple transactions, and so are not subject to this limitation.

• Different limits related to tables and indexes. For example, the maximum number of ordered indexes in the cluster is determined by MaxNoOfOrderedIndexes, and the maximum number of ordered indexes per table is 16.

- **Node and data object maximums.** The following limits apply to numbers of cluster nodes and metadata objects:
  - The maximum number of data nodes is 48.

A data node must have a node ID in the range of 1 to 48, inclusive. (Previous to MySQL Cluster NDB 6.1.1, management and API nodes were restricted to the range 1 to 63 inclusive as a node ID; starting with MySQL Cluster NDB 6.1.1, management and API nodes may use node IDs in the range 1 to 255, inclusive.)

- Prior to MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster was 63.
   Beginning with MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster is 255. In either case, this number includes all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers.
- The maximum number of metadata objects in current versions of MySQL Cluster is 20320. This limit is hard-coded.

See Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

## 3.6.3 Limits Relating to Transaction Handling in MySQL Cluster

A number of limitations exist in MySQL Cluster with regard to the handling of transactions. These include the following:

- Transaction isolation level. The NDBCLUSTER storage engine supports only the READ COMMITTED transaction isolation level. (InnoDB, for example, supports READ COMMITTED, READ UNCOMMITTED, REPEATABLE READ, and SERIALIZABLE.) See Section 7.3.4, "MySQL Cluster Backup Troubleshooting", for information on how this can affect backing up and restoring Cluster databases.)
- Transactions and BLOB or TEXT columns. NDBCLUSTER stores only part of a column value that uses any of MySQL's BLOB or TEXT data types in the table visible to MySQL; the remainder of the BLOB or TEXT is stored in a separate internal table that is not accessible to MySQL. This gives rise to two related issues of which you should be aware whenever executing SELECT statements on tables that contain columns of these types:
  - 1. For any SELECT from a MySQL Cluster table: If the SELECT includes a BLOB or TEXT column, the READ COMMITTED transaction isolation level is converted to a read with read lock. This is done to guarantee consistency.
  - 2. Prior to MySQL Cluster NDB 7.0.12, for any SELECT which used a primary key lookup or unique key lookup to retrieve any columns that used any of the BLOB or TEXT data types and that was executed within a transaction, a shared read lock was held on the table for the duration of the transaction—that is, until the transaction was either committed or aborted.

In MySQL Cluster NDB 7.0.12 and later, for primary key lookups, the lock is released as soon as all BLOB or TEXT data has been read. (Bug #49190) However, for unique key lookups, the shared lock continues to be held for the lifetime of the transaction.

This issue does not occur for queries that use index or table scans, even against NDB tables having BLOB or TEXT columns.

For example, consider the table t defined by the following CREATE TABLE statement:

```
CREATE TABLE t (
```

```
a INT NOT NULL AUTO_INCREMENT PRIMARY KEY,
b INT NOT NULL,
c INT NOT NULL,
d TEXT,
INDEX i(b),
UNIQUE KEY u(c)
) ENGINE = NDB,
```

Either of the following queries on t causes a shared read lock, because the first query uses a primary key lookup and the second uses a unique key lookup:

```
SELECT * FROM t WHERE a = 1;
SELECT * FROM t WHERE c = 1;
```

However, none of the four queries shown here causes a shared read lock:

```
SELECT * FROM t WHERE b 1;

SELECT * FROM t WHERE d = '1';

SELECT * FROM t;

SELECT b,c WHERE a = 1;
```

This is because, of these four queries, the first uses an index scan, the second and third use table scans, and the fourth, while using a primary key lookup, does not retrieve the value of any BLOB or TEXT columns.

You can help minimize issues with shared read locks by avoiding queries that use unique key lookups (or primary key lookups in MySQL Cluster NDB 7.0.11 and earlier) that retrieve BLOB or TEXT columns, or, in cases where such queries are not avoidable, by committing transactions as soon as possible afterward.

• Rollbacks. There are no partial transactions, and no partial rollbacks of transactions. A duplicate key or similar error causes the entire transaction to be rolled back.

This behavior differs from that of other transactional storage engines such as InnoDB that may roll back individual statements.

## · Transactions and memory usage.

As noted elsewhere in this chapter, MySQL Cluster does not handle large transactions well; it is better to perform a number of small transactions with a few operations each than to attempt a single large transaction containing a great many operations. Among other considerations, large transactions require very large amounts of memory. Because of this, the transactional behavior of a number of MySQL statements is effected as described in the following list:

- TRUNCATE TABLE is not transactional when used on NDB tables. If a TRUNCATE TABLE fails to empty
  the table, then it must be re-run until it is successful.
- DELETE FROM (even with no WHERE clause) is transactional. For tables containing a great many rows, you may find that performance is improved by using several DELETE FROM ... LIMIT ... statements to "chunk" the delete operation. If your objective is to empty the table, then you may wish to use TRUNCATE TABLE instead.
- LOAD DATA statements.
   LOAD DATA INFILE is not transactional when used on NDB tables.

## **Important**

When executing a LOAD DATA INFILE statement, the NDB engine performs commits at irregular intervals that enable better utilization of the communication

network. It is not possible to know ahead of time when such commits take place.

LOAD DATA FROM MASTER is not supported in MySQL Cluster.

- ALTER TABLE and transactions. When copying an NDB table as part of an ALTER TABLE, the creation of the copy is nontransactional. (In any case, this operation is rolled back when the copy is deleted.)
- Transactions and the COUNT() function. When using MySQL Cluster Replication, it is not possible to guarantee the transactional consistency of the COUNT() function on the slave. In other words, when performing on the master a series of statements (INSERT, DELETE, or both) that changes the number of rows in a table within a single transaction, executing SELECT COUNT(\*) FROM table queries on the slave may yield intermediate results. This is due to the fact that SELECT COUNT(...) may perform dirty reads, and is not a bug in the NDB storage engine. (See Bug #31321 for more information.)

## 3.6.4 MySQL Cluster Error Handling

Starting, stopping, or restarting a node may give rise to temporary errors causing some transactions to fail. These include the following cases:

- **Temporary errors.** When first starting a node, it is possible that you may see Error 1204 Temporary failure, distribution changed and similar temporary errors.
- Errors due to node failure. The stopping or failure of any data node can result in a number of different node failure errors. (However, there should be no aborted transactions when performing a planned shutdown of the cluster.)

In either of these cases, any errors that are generated must be handled within the application. This should be done by retrying the transaction.

See also Section 3.6.2, "Limits and Differences of MySQL Cluster from Standard MySQL Limits".

# 3.6.5 Limits Associated with Database Objects in MySQL Cluster

Some database objects such as tables and indexes have different limitations when using the NDBCLUSTER storage engine:

• Table names containing special characters. NDB tables whose names contain characters other than letters, numbers, dashes, and underscores and which are created on one SQL node were not always discovered correctly by other SQL nodes. (Bug #31470)

## Note

This issue was fixed in MySQL 5.1.23, MySQL Cluster NDB 6.2.7, and MySQL Cluster NDB 6.3.4.

- **Number of database objects.** The maximum number of *all* NDB database objects in a single MySQL Cluster—including databases, tables, and indexes—is limited to 20320.
- Attributes per table. Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the
  maximum number of attributes (that is, columns and indexes) per table is limited to 128.

Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this limit is increased to 512.

• Attributes per key. The maximum number of attributes per key is 32.

• Row size. Prior to MySQL Cluster NDB 7.0, the maximum permitted size of any one row was 8052 bytes; in MySQL Cluster NDB 7.0 and later, this is 14000 bytes. Each BLOB or TEXT column contributes 256 + 8 = 264 bytes to this total.

## 3.6.6 Unsupported or Missing Features in MySQL Cluster

A number of features supported by other storage engines are not supported for NDB tables. Trying to use any of these features in MySQL Cluster does not cause errors in or of itself; however, errors may occur in applications that expects the features to be supported or enforced:

- Foreign key constraints. Prior to MySQL Cluster NDB 7.3, the foreign key construct is ignored, just as it is by MyISAM tables. Foreign keys are supported in MySQL Cluster NDB 7.3 and later.
- Index prefixes. Prefixes on indexes are not supported for NDBCLUSTER tables. If a prefix is used as part of an index specification in a statement such as CREATE TABLE, ALTER TABLE, or CREATE INDEX, the prefix is ignored.
- OPTIMIZE operations. OPTIMIZE operations are not supported.

Beginning with MySQL Cluster NDB 6.3.7, this limitation has been lifted. See Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x", for more information.

- LOAD TABLE ... FROM MASTER. LOAD TABLE FROM MASTER is not supported.
- Savepoints and rollbacks. Savepoints and rollbacks to savepoints are ignored as in MyISAM.
- **Durability of commits.** There are no durable commits on disk. Commits are replicated, but there is no guarantee that logs are flushed to disk on commit.
- Replication. Statement-based replication is not supported. Use --binlog-format=ROW (or --binlog-format=MIXED) when setting up cluster replication. See Chapter 8, MySQL Cluster Replication, for more information.

## Note

See Section 3.6.3, "Limits Relating to Transaction Handling in MySQL Cluster", for more information relating to limitations on transaction handling in  $\mathtt{NDB}$ .

## 3.6.7 Limitations Relating to Performance in MySQL Cluster

The following performance issues are specific to or especially pronounced in MySQL Cluster:

- Range scans. There are query performance issues due to sequential access to the NDB storage engine; it is also relatively more expensive to do many range scans than it is with either MyISAM or InnoDB.
- Reliability of Records in range. The Records in range statistic is available but is not completely tested or officially supported. This may result in nonoptimal query plans in some cases. If necessary, you can employ USE INDEX or FORCE INDEX to alter the execution plan. See Index Hint Syntax, for more information on how to do this.
- Unique hash indexes. Unique hash indexes created with USING HASH cannot be used for accessing a table if NULL is given as part of the key.

# 3.6.8 Issues Exclusive to MySQL Cluster

The following are limitations specific to the NDBCLUSTER storage engine:

• Machine architecture. All machines used in the cluster must have the same architecture. That is, all machines hosting nodes must be either big-endian or little-endian, and you cannot use a mixture of both. For example, you cannot have a management node running on a PowerPC which directs a data node that is running on an x86 machine. This restriction does not apply to machines simply running mysql or other clients that may be accessing the cluster's SQL nodes.

## · Binary logging.

MySQL Cluster has the following limitations or restrictions with regard to binary logging:

- sql\_log\_bin has no effect on data operations; however, it is supported for schema operations.
- MySQL Cluster cannot produce a binary log for tables having BLOB columns but no primary key.
- Only the following schema operations are logged in a cluster binary log which is not on the mysqld executing the statement:
  - CREATE TABLE
  - ALTER TABLE
  - DROP TABLE
  - CREATE DATABASE / CREATE SCHEMA
  - DROP DATABASE / DROP SCHEMA
  - CREATE TABLESPACE
  - ALTER TABLESPACE
  - DROP TABLESPACE
  - CREATE LOGFILE GROUP
  - ALTER LOGFILE GROUP
  - DROP LOGFILE GROUP

See also Section 3.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

# 3.6.9 Limitations Relating to MySQL Cluster Disk Data Storage

**Disk Data object maximums and minimums.** Disk data objects are subject to the following maximums and minimums:

- Maximum number of tablespaces: 2<sup>32</sup> (4294967296)
- Maximum number of data files per tablespace: 2<sup>16</sup> (65536)
- Maximum data file size: The theoretical limit is 64G; however, in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the practical upper limit is 32G. This is equivalent to 32768 extents of 1M each.

Since a MySQL Cluster Disk Data table can use at most 1 tablespace, this means that the theoretical upper limit to the amount of data (in bytes) that can be stored on disk by a single NDB table is 32G \* 65536 = 2251799813685248, or approximately 2 petabytes.

• The theoretical maximum number of extents per tablespace data file is 2<sup>16</sup> (65536); however, for practical purposes, the recommended maximum number of extents per data file is 2<sup>15</sup> (32768).

The minimum and maximum possible sizes of extents for tablespace data files are 32K and 2G, respectively. See CREATE TABLESPACE Syntax, for more information.

**Disk Data tables and diskless mode.** Use of Disk Data tables is not supported when running the cluster in diskless mode. Beginning with MySQL 5.1.12, it is prohibited altogether. (Bug #20008)

## 3.6.10 Limitations Relating to Multiple MySQL Cluster Nodes

## Multiple SQL nodes.

The following are issues relating to the use of multiple MySQL servers as MySQL Cluster SQL nodes, and are specific to the NDBCLUSTER storage engine:

- No distributed table locks. A LOCK TABLES works only for the SQL node on which the lock is issued; no other SQL node in the cluster "sees" this lock. This is also true for a lock issued by any statement that locks tables as part of its operations. (See next item for an example.)
- ALTER TABLE operations. ALTER TABLE is not fully locking when running multiple MySQL servers (SQL nodes). (As discussed in the previous item, MySQL Cluster does not support distributed table locks.)

## Multiple management nodes.

When using multiple management servers:

- You must give nodes explicit IDs in connect strings because automatic allocation of node IDs does not work across multiple management servers.
- In MySQL Cluster NDB 7.0.7 and earlier, you must take extreme care to have the same configurations for all management servers; no special checks for consistency are performed.

Beginning with MySQL Cluster NDB 7.0.8, a management server when first starting checks for any other management server in the same MySQL Cluster, and upon successful connection to the other management server uses its configuration data. This means that the management server --reload and --initial startup options are ignored unless the management server is the only one running. It also means that, when performing a rolling restart of a MySQL Cluster with multiple management nodes, the management server reads its own configuration file if (and only if) it is the only management server running in this MySQL Cluster. See Section 7.5, "Performing a Rolling Restart of a MySQL Cluster", for more information.

**Multiple network addresses.** Multiple network addresses per data node are not supported. Use of these is liable to cause problems: In the event of a data node failure, an SQL node waits for confirmation that the data node went down but never receives it because another route to that data node remains open. This can effectively make the cluster inoperable.

#### Note

It is possible to use multiple network hardware *interfaces* (such as Ethernet cards) for a single data node, but these must be bound to the same address. This also means that it not possible to use more than one [tcp] section per connection in the config.ini file. See Section 5.2.8, "MySQL Cluster TCP/IP Connections", for more information.

# 3.6.11 Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x

A number of limitations and related issues existing in earlier versions of MySQL Cluster have been resolved:

• Variable-length column support. The NDBCLUSTER storage engine now supports variable-length column types for in-memory tables.

Previously, for example, any Cluster table having one or more VARCHAR fields which contained only relatively small values, much more memory and disk space were required when using the NDBCLUSTER storage engine than would have been the case for the same table and data using the MyISAM engine. In other words, in the case of a VARCHAR column, such a column required the same amount of storage as a CHAR column of the same size. In MySQL 5.1, this is no longer the case for in-memory tables, where storage requirements for variable-length column types such as VARCHAR and BINARY are comparable to those for these column types when used in MyISAM tables (see Data Type Storage Requirements).

## **Important**

For MySQL Cluster Disk Data tables, the fixed-width limitation continues to apply. See Section 7.12, "MySQL Cluster Disk Data Tables".

• **Replication with MySQL Cluster.** It is now possible to use MySQL replication with Cluster databases. For details, see Chapter 8, *MySQL Cluster Replication*.

**Circular Replication.** Circular replication is also supported with MySQL Cluster, beginning with MySQL 5.1.18. See Section 8.10, "MySQL Cluster Replication: Multi-Master and Circular Replication".

- auto\_increment\_increment and auto\_increment\_offset. The
   auto\_increment\_increment and auto\_increment\_offset server system variables are
   supported for Cluster replication beginning with MySQL 5.1.20, MySQL Cluster NDB 6.2.5, and MySQL
   Cluster 6.3.2.
- Database autodiscovery and online schema changes. Autodiscovery of databases is now supported for multiple MySQL servers accessing the same MySQL Cluster. Formerly, autodiscovery in MySQL Cluster 5.1 and MySQL Cluster NDB 6.x releases required that a given mysqld was already running and connected to the cluster at the time that the database was created on a different mysqld—in other words, when a mysqld process connected to the cluster after a database named db\_name was created, it was necessary to issue a CREATE DATABASE db\_name or CREATE SCHEMA db\_name statement on the "new" MySQL server when it first accessed that MySQL Cluster. Beginning with MySQL Cluster NDB 6.2.16 and MySQL Cluster NDB 6.3.18, such a CREATE statement is no longer required. (Bug #39612)

This also means that online schema changes in NDB tables are now possible. That is, the result of operations such as ALTER TABLE and CREATE INDEX performed on one SQL node in the cluster are now visible to the cluster's other SQL nodes without any additional action being taken.

- Backup and restore between architectures. Beginning with MySQL 5.1.10, it is possible to perform a Cluster backup and restore between different architectures. Previously—for example—you could not back up a cluster running on a big-endian platform and then restore from that backup to a cluster running on a little-endian system. (Bug #19255)
- Character set directory. Beginning with MySQL 5.1.10, it is possible to install MySQL with Cluster support to a nondefault location and change the search path for font description files using either the --basedir or --character-sets-dir options. (Previously, ndbd in MySQL 5.1 searched only the default path—typically /usr/local/mysql/share/mysql/charsets—for character sets.)
- Multiple management servers. In MySQL 5.1 (including all MySQL Cluster NDB 6.x and later versions), it is no longer necessary, when running multiple management servers, to restart all the cluster's data nodes to enable the management nodes to see one another.

Also, when using multiple management servers and starting concurrently several API nodes (possibly including one or more SQL nodes) whose connection strings listed the management servers in different order, it was possible for 2 API nodes to be assigned the same node ID. This issue is resolved in MySQL Cluster NDB 6.2.17, 6.3.23, and 6.4.3. (Bug #42973)

Multiple data node processes per host. Beginning with MySQL Cluster NDB 6.2.0, you can use
multiple data node processes on a single host. (In MySQL Cluster NDB 6.1, MySQL 5.1, and earlier
release series, we did not support production MySQL Cluster deployments in which more than one ndbd
process was run on a single physical machine.)

In addition, MySQL Cluster NDB 7.0 introduces support for multi-threaded data nodes (ndbmtd). See Section 3.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)", for more information.

- Identifiers. Formerly (in MySQL 5.0 and earlier), database names, table names and attribute names could not be as long for NDB tables as tables using other storage engines, because attribute names were truncated internally. In MySQL 5.1 and later, names of MySQL Cluster databases, tables, and table columns follow the same rules regarding length as they do for any other storage engine.
- Length of CREATE TABLE statements. CREATE TABLE statements may be no more than 4096 characters in length. This limitation affects MySQL 5.1.6, 5.1.7, and 5.1.8 only. (See Bug #17813)
- IGNORE and REPLACE functionality. In MySQL 5.1.7 and earlier, INSERT IGNORE, UPDATE IGNORE, and REPLACE were supported only for primary keys, but not for unique keys. It was possible to work around this issue by removing the constraint, then dropping the unique index, performing any inserts, and then adding the unique index again.

This limitation was removed for INSERT IGNORE and REPLACE in MySQL 5.1.8. (See Bug #17431.)

• AUTO\_INCREMENT columns. In MySQL 5.1.10 and earlier versions, the maximum number of tables having AUTO\_INCREMENT columns—including those belonging to hidden primary keys—was 2048.

This limitation was lifted in MySQL 5.1.11.

• Maximum number of cluster nodes. Prior to MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster was 63, including all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers.

Starting with MySQL Cluster NDB 6.1.1, the total maximum number of nodes in a MySQL Cluster is 255, including all SQL nodes (MySQL Servers), API nodes (applications accessing the cluster other than MySQL servers), data nodes, and management servers. The total number of data nodes and management nodes beginning with this version is 63, of which up to 48 can be data nodes.

#### Note

The limitation that a data node cannot have a node ID greater than 49 continues to apply.

- Recovery of memory from deleted rows. Beginning with MySQL Cluster NDB 6.3.7, memory can be reclaimed from an NDB table for reuse with any NDB table by employing OPTIMIZE TABLE, subject to the following limitations:
  - Only in-memory tables are supported; the OPTIMIZE TABLE statement still has no effect on MySQL Cluster Disk Data tables.
  - Only variable-length columns (such as those declared as VARCHAR, TEXT, or BLOB) are supported.

However, you can force columns defined using fixed-length data types (such as CHAR) to be dynamic using the ROW\_FORMAT or COLUMN\_FORMAT option with a CREATE TABLE or ALTER TABLE statement.

See CREATE TABLE Syntax, and ALTER TABLE Syntax, for information on these options.

You can regulate the effects of OPTIMIZE on performance by adjusting the value of the global system variable ndb\_optimization\_delay, which sets the number of milliseconds to wait between batches of rows being processed by OPTIMIZE. The default value is 10 milliseconds. It is possible to set a lower value (to a minimum of 0), but not recommended. The maximum is 100000 milliseconds (that is, 100 seconds).

• Implicit Rollbacks. Prior to MySQL Cluster NDB 6.2.17 and MySQL Cluster NDB 6.3.19, MySQL Cluster did not automatically roll back a transaction that was aborted by a duplicate key or similar error, and subsequent statements raised ERROR 1296 (HY000): Got error 4350 'Transaction already aborted' from NDBCLUSTER. In such cases, it was necessary to issue an explicit ROLLBACK statement first, and then to retry the entire transaction.

Beginning with MySQL Cluster NDB 6.2.17 and MySQL Cluster NDB 6.3.19, this limitation has been removed; now, an error which causes a transaction to be aborted generates an implicit rollback of the entire transaction. This is logged with the warning Storage engine NDB does not support rollback for this statement. Transaction rolled back and must be restarted. A statement subsequent to this starts a new transaction. (Bug #32656)

## Note

The NDBCLUSTER storage engine does not support partial transactions or partial rollbacks of transactions in any version of MySQL Cluster.

- Number of tables. Previously, the maximum number of NDBCLUSTER tables in a single MySQL Cluster was 1792, but this is no longer the case in MySQL 5.1 and later MySQL Cluster releases. However, the number of tables is still included in the total maximum number of NDBCLUSTER database objects (20320). (See Section 3.6.5, "Limits Associated with Database Objects in MySQL Cluster".)
- **DDL operations.** Beginning with MySQL Cluster NDB 6.4.0, DDL operations (such as CREATE TABLE or ALTER TABLE) are protected from data node failures. Previously, if a data node failed while trying to perform one of these, the data dictionary became locked and no further DDL statements could be executed without restarting the cluster (Bug #36718).
- Adding and dropping of data nodes. In MySQL Cluster NDB 6.3 and previous versions of MySQL Cluster, the online adding or dropping of data nodes was not possible; such operations required a complete shutdown and restart of the entire cluster. In MySQL Cluster NDB 7.0 (beginning with MySQL Cluster NDB 6.4.0) and later MySQL Cluster release series, it is possible to add new data nodes to a running MySQL Cluster by performing a rolling restart, so that the cluster and the data stored in it remain available to applications.

When planning to increase the number of data nodes in the cluster online in MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1, you should be aware of and take into account the following issues:

- New data nodes can be added online to a MySQL Cluster only as part of a new node group.
- New data nodes can be added online, but cannot yet be dropped online. Reducing the number of data nodes still requires a system restart of the cluster.

- As in previous MySQL Cluster releases, it is not possible to change online either the number of replicas (NoOfReplicas configuration parameter) or the number of data nodes per node group. These changes require a system restart.
- Redistribution of existing cluster data using the new data nodes is not automatic; however, this can be accomplished using simple SQL statements in the mysql client or other MySQL client application once the nodes have been added. During this procedure, it is not possible to perform DDL operations, although DML operations can continue as normal.

The distribution of new cluster data (that is, data stored in the cluster *after* the new nodes have been added) uses the new nodes without manual intervention.

For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".

Native support for default column values. Starting with MySQL Cluster NDB 7.1.0, default values
for table columns are stored by NDBCLUSTER, rather than by the MySQL server as was previously the
case. Because less data must be sent from an SQL node to the data nodes, inserts on tables having
column value defaults can be performed more efficiently than before.

Tables created using previous MySQL Cluster releases can still be used in MySQL Cluster 7.1.0 and later, although they do not support native default values and continue to use defaults supplied by the MySQL server until they are upgraded. This can be done by means of an offline ALTER TABLE statement.

## **Important**

You cannot set or change a table column's default value using an online ALTER TABLE operation

- Innobb plugin support. Previously, Innobb support in MySQL Cluster was limited to the version built in to the MySQl Server. Beginning with MySQL Cluster NDB 7.1.9, MySQL Cluster also provides support for the Innobb Plugin. See Chapter 4, MySQL Cluster Installation and Upgrades, for information about enabling Innobb storage engine and plugin support with MySQL Cluster.
- Distribution of MySQL users and privileges. Previously, MySQL users and privileges created on one SQL node were unique to that SQL node, due to the fact that the MySQL grant tables were restricted to using the MyISAM storage engine. Beginning with MySQL Cluster NDB 7.2.0, it is possible, following installation of the MySQL Cluster software and setup of the desired users and privileges on one SQL node, to convert the grant tables to use NDB and thus to distribute the users and privileges across all SQL nodes connected to the cluster. You can do this by loading and making use of a set of stored procedures defined in an SQL script supplied with the MySQL Cluster distribution. For more information, see Section 7.14, "Distributed MySQL Privileges for MySQL Cluster".
- Number of rows per partition. Previously, a single MySQL Cluster partition could hold a maximum of 46137488 rows. This limitation was removed in MySQL Cluster NDB 7.0.36 and MySQL Cluster NDB 7.1.25. (Bug #13844405, Bug #14000373)

If you are still using a previous MySQL Cluster release, you can work around this limitation by taking advantage of the fact that the number of partitions is the same as the number of data nodes in the cluster (see Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions"). This means that, by increasing the number of data nodes, you can increase the available space for storing data.

In MySQL Cluster NDB 7.0 and later, you can increase the number of data nodes in the cluster while the cluster remains in operation. See Section 7.13, "Adding MySQL Cluster Data Nodes Online", for more information.

It is also possible to increase the number of partitions for NDB tables by using explicit KEY or LINEAR KEY partitioning (see KEY Partitioning).

# Chapter 4 MySQL Cluster Installation and Upgrades

## **Table of Contents**

4.1	Installing MySQL Cluster on Linux	61
	4.1.1 Installing a MySQL Cluster Binary Release on Linux	62
	4.1.2 Installing MySQL Cluster from RPM	64
	4.1.3 Building MySQL Cluster from Source on Linux	66
4.2	Installing MySQL Cluster on Windows	67
	4.2.1 Installing MySQL Cluster on Windows from a Binary Release	68
	4.2.2 Compiling and Installing MySQL Cluster from Source on Windows	71
	4.2.3 Initial Startup of MySQL Cluster on Windows	72
	4.2.4 Installing MySQL Cluster Processes as Windows Services	74
	Initial Configuration of MySQL Cluster	
4.4	Initial Startup of MySQL Cluster	78
	MySQL Cluster Example with Tables and Data	
	Safe Shutdown and Restart of MySQL Cluster	
4.7	Upgrading and Downgrading MySQL Cluster	84
	4.7.1 Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x	85
	4.7.2 Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x	89
	4.7.3 Upgrade and downgrade compatibility: MySQL 5.1	92

This section describes the basics for planning, installing, configuring, and running a MySQL Cluster. Whereas the examples in Chapter 5, Configuration of MySQL Cluster NDB 6.1-7.1 provide more in-depth information on a variety of clustering options and configuration, the result of following the guidelines and procedures outlined here should be a usable MySQL Cluster which meets the *minimum* requirements for availability and safeguarding of data.

For information about upgrading or downgrading a MySQL Cluster between release versions, see Section 4.7, "Upgrading and Downgrading MySQL Cluster".


This section covers hardware and software requirements; networking issues; installation of MySQL Cluster; configuration issues; starting, stopping, and restarting the cluster; loading of a sample database; and performing queries.

**Assumptions.** The following sections make a number of assumptions regarding the cluster's physical and network configuration. These assumptions are discussed in the next few paragraphs.

**Cluster nodes and host computers.** The cluster consists of four nodes, each on a separate host computer, and each with a fixed network address on a typical Ethernet network as shown here:

Node	IP Address
Management node (mgmd)	192.168.0.10
SQL node (mysqld)	192.168.0.20
Data node "A" (ndbd)	192.168.0.30
Data node "B" (ndbd)	192.168.0.40

This may be made clearer by the following diagram:



**Network addressing.** In the interest of simplicity (and reliability), this *How-To* uses only numeric IP addresses. However, if DNS resolution is available on your network, it is possible to use host names in lieu of IP addresses in configuring Cluster. Alternatively, you can use the hosts file (typically /etc/hosts for Linux and other Unix-like operating systems, C:\WINDOWS\system32\drivers\etc\hosts on Windows, or your operating system's equivalent) for providing a means to do host lookup if such is available.

**Potential hosts file issues.** A common problem when trying to use host names for Cluster nodes arises because of the way in which some operating systems (including some Linux distributions) set up the system's own host name in the /etc/hosts during installation. Consider two machines with the host names ndb1 and ndb2, both in the cluster network domain. Red Hat Linux (including some derivatives such as CentOS and Fedora) places the following entries in these machines' /etc/hosts files:

```
# ndb1 /etc/hosts:
127.0.0.1 ndb1.cluster ndb1 localhost.localdomain localhost

# ndb2 /etc/hosts:
127.0.0.1 ndb2.cluster ndb2 localhost.localdomain localhost
```

SUSE Linux (including OpenSUSE) places these entries in the machines' /etc/hosts files:

```
# ndbl /etc/hosts:
127.0.0.1     localhost
127.0.0.2     ndbl.cluster ndbl

# ndb2 /etc/hosts:
127.0.0.1     localhost
127.0.0.2     ndb2.cluster ndb2
```

In both instances, ndb1 routes ndb1.cluster to a loopback IP address, but gets a public IP address from DNS for ndb2.cluster, while ndb2 routes ndb2.cluster to a loopback address and obtains a public address for ndb1.cluster. The result is that each data node connects to the management server, but cannot tell when any other data nodes have connected, and so the data nodes appear to hang while starting.

## Caution

You cannot mix localhost and other host names or IP addresses in config.ini. For these reasons, the solution in such cases (other than to use IP addresses for all config.ini HostName entries) is to remove the fully qualified host names from /etc/hosts and use these in config.ini for all cluster hosts.

**Host computer type.** Each host computer in our installation scenario is an Intel-based desktop PC running a supported operating system installed to disk in a standard configuration, and running no unnecessary services. The core operating system with standard TCP/IP networking capabilities should be sufficient. Also for the sake of simplicity, we also assume that the file systems on all hosts are set up identically. In the event that they are not, you should adapt these instructions accordingly.

**Network hardware.** Standard 100 Mbps or 1 gigabit Ethernet cards are installed on each machine, along with the proper drivers for the cards, and that all four hosts are connected through a standard-issue Ethernet networking appliance such as a switch. (All machines should use network cards with the same throughout. That is, all four machines in the cluster should have 100 Mbps cards *or* all four machines should have 1 Gbps cards.) MySQL Cluster works in a 100 Mbps network; however, gigabit Ethernet provides better performance.

## **Important**

MySQL Cluster is *not* intended for use in a network for which throughput is less than 100 Mbps or which experiences a high degree of latency. For this reason (among others), attempting to run a MySQL Cluster over a wide area network such as the Internet is not likely to be successful, and is not supported in production.

**Sample data.** We use the world database which is available for download from the MySQL Web site (see http://dev.mysql.com/doc/index-other.html). We assume that each machine has sufficient memory for running the operating system, required MySQL Cluster processes, and (on the data nodes) storing the database.

For general information about installing MySQL, see Installing and Upgrading MySQL. For information about installation of MySQL Cluster on Linux and other Unix-like operating systems, see Section 4.1, "Installing MySQL Cluster on Linux". For information about installation of MySQL Cluster on Windows operating systems, see Section 4.2, "Installing MySQL Cluster on Windows".

For general information about MySQL Cluster hardware, software, and networking requirements, see Section 3.3, "MySQL Cluster Hardware, Software, and Networking Requirements".

# 4.1 Installing MySQL Cluster on Linux

This section covers installation of MySQL Cluster on Linux and other Unix-like operating systems. While the next few sections refer to a Linux operating system, the instructions and procedures given there should be easily adaptable to other supported Unix-like platforms.

Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported for production use on Windows operating systems; for installation and setup instructions specific to Windows, see Section 4.2, "Installing MySQL Cluster on Windows".

Each MySQL Cluster host computer must have the correct executable programs installed. A host running an SQL node must have installed on it a MySQL Server binary (mysqld). Management nodes require the management server daemon (ndb\_mgmd); data nodes require the data node daemon (ndbd; in MySQL Cluster NDB 7.0 and later, you can use ndbmtd instead. It is not necessary to install the MySQL Server binary on management node hosts and data node hosts. It is recommended that you also install the management client (ndb\_mgm) on the management server host.

Installation of MySQL Cluster on Linux can be done using precompiled binaries from Oracle (downloaded as a .tar.gz archive), with RPM packages (also available from Oracle), or from source code. All three of these installation methods are described in the section that follow.

Regardless of the method used, it is still necessary following installation of the MySQL Cluster binaries to create configuration files for all cluster nodes, before you can start the cluster. See Section 4.3, "Initial Configuration of MySQL Cluster".

## 4.1.1 Installing a MySQL Cluster Binary Release on Linux

This section covers the steps necessary to install the correct executables for each type of Cluster node from precompiled binaries supplied by Oracle.

For setting up a cluster using precompiled binaries, the first step in the installation process for each cluster host is to download the latest MySQL Cluster NDB 6.3, MySQL Cluster NDB 7.0, or MySQL Cluster NDB 7.1 binary archive (mysql-cluster-gpl-6.3.55-linux-i686-glibc23.tar.gz, mysql-cluster-gpl-7.0.42-linux-i686-glibc23.tar.gz, or mysql-cluster-gpl-7.1.33-linux-i686-glibc23.tar.gz, respectively) from the MySQL Cluster downloads area. We assume that you have placed this file in each machine's /var/tmp directory. (If you do require a custom binary, see Installing MySQL Using a Development Source Tree.)

#### Note

After completing the installation, do not yet start any of the binaries. We show you how to do so following the configuration of the nodes (see Section 4.3, "Initial Configuration of MySQL Cluster").

**SQL nodes.** On each of the machines designated to host SQL nodes, perform the following steps as the system root user:

1. Check your /etc/passwd and /etc/group files (or use whatever tools are provided by your operating system for managing users and groups) to see whether there is already a mysql group and mysql user on the system. Some OS distributions create these as part of the operating system installation process. If they are not already present, create a new mysql user group, and then add a mysql user to this group:

```
shell> groupadd mysql
shell> useradd -g mysql mysql
```

The syntax for useradd and groupadd may differ slightly on different versions of Unix, or they may have different names such as adduser and addgroup.

2. Change location to the directory containing the downloaded file, unpack the archive, and create a symbolic link named mysql to the mysql directory. Note that the actual file and directory names vary according to the MySQL Cluster version number.

```
shell> cd /var/tmp
shell> tar -C /usr/local -xzvf mysql-cluster-gpl-7.1.33-linux-i686-glibc23.tar.gz
shell> ln -s /usr/local/mysql-cluster-gpl-7.1.33-linux-i686-glibc23 /usr/local/mysql
```

3. Change location to the mysql directory and run the supplied script for creating the system databases:

```
shell> cd mysql
shell> scripts/mysql_install_db --user=mysql
```

4. Set the necessary permissions for the MySQL server and data directories:

```
shell> chown -R root .
shell> chown -R mysql data
shell> chgrp -R mysql .
```

5. Copy the MySQL startup script to the appropriate directory, make it executable, and set it to start when the operating system is booted up:

```
shell> cp support-files/mysql.server /etc/rc.d/init.d/
shell> chmod +x /etc/rc.d/init.d/mysql.server
shell> chkconfig --add mysql.server
```

(The startup scripts directory may vary depending on your operating system and version—for example, in some Linux distributions, it is /etc/init.d.)

Here we use Red Hat's chkconfig for creating links to the startup scripts; use whatever means is appropriate for this purpose on your platform, such as update-rc.d on Debian.

Remember that the preceding steps must be repeated on each machine where an SQL node is to reside.

**Data nodes.** Installation of the data nodes does not require the mysqld binary. Only the MySQL Cluster data node executable ndbd (single-threaded) or ndbmtd (multi-threaded) is required. These binaries can also be found in the .tar.gz archive. Again, we assume that you have placed this archive in /var/tmp.

As system root (that is, after using sudo, su root, or your system's equivalent for temporarily assuming the system administrator account's privileges), perform the following steps to install the data node binaries on the data node hosts:

1. Change location to the /var/tmp directory, and extract the ndbd and ndbmtd binaries from the archive into a suitable directory such as /usr/local/bin:

```
shell> cd /var/tmp
shell> tar -zxvf mysql-5.1.73-ndb-7.1.33-linux-i686-glibc23.tar.gz
shell> cd mysql-5.1.73-ndb-7.1.33-linux-i686-glibc23
shell> cp bin/ndbd /usr/local/bin/ndbd
shell> cp bin/ndbmtd /usr/local/bin/ndbmtd
```

(You can safely delete the directory created by unpacking the downloaded archive, and the files it contains, from <code>/var/tmp</code> once <code>ndb\_mgm</code> and <code>ndb\_mgmd</code> have been copied to the executables directory.)

Change location to the directory into which you copied the files, and then make both of them executable:

```
shell> cd /usr/local/bin
shell> chmod +x ndb*
```

The preceding steps should be repeated on each data node host.

Although only one of the data node executables is required to run a MySQL Cluster data node, we have shown you how to install both ndbd and ndbmtd in the preceding instructions. We recommend that you do

this when installing or upgrading MySQL Cluster, even if you plan to use only one of them, since this will save time and trouble in the event that you later decide to change from one to the other.

#### **Note**

The data directory on each machine hosting a data node is /usr/local/mysql/data. This piece of information is essential when configuring the management node. (See Section 4.3, "Initial Configuration of MySQL Cluster".)

Management nodes. Installation of the management node does not require the mysqld binary. Only the MySQL Cluster management server (ndb\_mgmd) is required; you most likely want to install the management client (ndb\_mgm) as well. Both of these binaries also be found in the .tar.gz archive. Again, we assume that you have placed this archive in /var/tmp.

As system root, perform the following steps to install ndb\_mgmd and ndb\_mgm on the management node host:

1. Change location to the /var/tmp directory, and extract the ndb\_mgm and ndb\_mgmd from the archive into a suitable directory such as /usr/local/bin:

```
shell> cd /var/tmp
shell> tar -zxvf mysql-5.1.73-ndb-7.1.33-linux-i686-glibc23.tar.gz
shell> cd mysql-5.1.73-ndb-7.1.33-linux-i686-glibc23
shell> cp bin/ndb_mgm* /usr/local/bin
```

(You can safely delete the directory created by unpacking the downloaded archive, and the files it contains, from /var/tmp once ndb\_mgm and ndb\_mgmd have been copied to the executables directory.)

2. Change location to the directory into which you copied the files, and then make both of them executable:

```
shell> cd /usr/local/bin
shell> chmod +x ndb_mgm*
```

In Section 4.3, "Initial Configuration of MySQL Cluster", we create configuration files for all of the nodes in our example MySQL Cluster.

# 4.1.2 Installing MySQL Cluster from RPM

This section covers the steps necessary to install the correct executables for each type of MySQL Cluster node using RPM packages supplied by Oracle.

RPMs are available for both 32-bit and 64-bit Linux platforms. For a MySQL Cluster, three RPMs are required:

• The Server RPM (for example, MySQL-Cluster-gpl-server-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-server-7.0.42-0.sles10.i586.rpm, or MySQL-Cluster-gpl-server-7.1.33-0.sles10.i586.rpm), which supplies the core files needed to run a MySQL Server with NDBCLUSTER storage engine support (that is, as a MySQL Cluster SQL node).

```
If you do not have your own client application capable of administering a MySQL server, you should also obtain and install the Client RPM (for example, MySQL-Cluster-gpl-client-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-client-7.0.42-0.sles10.i586.rpm, Or MySQL-Cluster-gpl-client-7.1.33-0.sles10.i586.rpm).
```

- The Cluster storage engine RPM (for example, MySQL-Cluster-gpl-storage-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-storage-7.0.42-0.sles10.i586.rpm, or MySQL-Cluster-gpl-storage-7.1.33-0.sles10.i586.rpm), which supplies the MySQL Cluster data node binary (ndbd).
- The Cluster storage engine management RPM (for example, MySQL-Cluster-gpl-management-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-management-7.0.42-0.sles10.i586.rpm, or MySQL-Cluster-gpl-management-7.1.33-0.sles10.i586.rpm) which provides the MySQL Cluster management server binary (ndb\_mgmd).

In addition, you should also obtain the **NDB Cluster - Storage engine basic tools** RPM (for example, MySQL-Cluster-gpl-tools-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-tools-7.0.42-0.sles10.i586.rpm, or MySQL-Cluster-gpl-tools-7.1.33-0.sles10.i586.rpm), which supplies several useful applications for working with a MySQL Cluster. The most important of these is the MySQL Cluster management client (ndb\_mgm). The **NDB Cluster - Storage engine extra tools** RPM (for example, MySQL-Cluster-gpl-extra-6.3.55-0.sles10.i586.rpm, MySQL-Cluster-gpl-extra-7.0.42-0.sles10.i586.rpm, or MySQL-Cluster-gpl-extra-7.1.33-0.sles10.i586.rpm) contains some additional testing and monitoring programs, but is not required to install a MySQL Cluster. (For more information about these additional programs, see Chapter 6, MySQL Cluster Programs.)

The MySQL Cluster version number in the RPM file names (shown here as 6.3.55, 7.0.42, or 7.1.33) can vary according to the version which you are actually using. It is very important that all of the Cluster RPMs to be installed have the same version number. The glibc version number (if present), and architecture designation (shown here as i586) should be appropriate to the machine on which the RPM is to be installed.

**Data nodes.** On a computer that is to host a cluster data node it is necessary to install only the **NDB Cluster - Storage engine** RPM. To do so, copy this RPM to the data node host, and run the following command as the system root user, replacing the name shown for the RPM as necessary to match that of the RPM downloaded from the MySQL web site:

```
shell> rpm -Uhv MySQL-Cluster-gpl-storage-7.1.33-0.sles10.i586.rpm
```

The previous command installs the MySQL Cluster data node binary (ndbd) in the /usr/sbin directory.

**SQL nodes.** On each machine to be used for hosting a cluster SQL node, install the **Server** RPM by executing the following command as the system root user, replacing the name shown for the RPM as necessary to match the name of the RPM downloaded from the MySQL web site:

```
shell> rpm -Uhv MySQL-Cluster-gpl-server-7.1.33-0.sles10.i586.rpm
```

This installs the MySQL server binary (mysqld) in the /usr/sbin directory, as well as all needed MySQL Server support files. It also installs the mysql.server and mysqld\_safe startup scripts in /usr/share/mysql and /usr/bin, respectively. The RPM installer should take care of general configuration issues (such as creating the mysql user and group, if needed) automatically.

#### Note

To administer the SQL node (MySQL server), you should also install the **Client** RPM, as shown here:

```
shell> rpm -Uhv MySQL-Cluster-gpl-client-7.1.33-0.sles10.i586.rpm
```

This installs the mysgl client program.

**Management nodes.** To install the MySQL Cluster management server, it is necessary only to use the **NDB Cluster - Storage engine management** RPM. Copy this RPM to the computer intended to host the management node, and then install it by running the following command as the system root user (replace the name shown for the RPM as necessary to match that of the **Storage engine management** RPM downloaded from the MySQL web site):

```
shell> rpm -Uhv MySQL-Cluster-gpl-management-7.1.33-0.sles10.i586.rpm
```

This installs the management server binary (ndb\_mgmd) to the /usr/sbin directory.

You should also install the NDB management client, which is supplied by the **Storage engine basic tools** RPM. Copy this RPM to the same computer as the management node, and then install it by running the following command as the system root user (again, replace the name shown for the RPM as necessary to match that of the **Storage engine basic tools** RPM downloaded from the MySQL web site):

```
shell> rpm -Uhv MySQL-Cluster-gpl-tools-7.1.33-0.sles10.i586.rpm
```

The **Storage engine basic tools** RPM installs the MySQL Cluster management client (ndb\_mgm) to the / usr/bin directory.

#### Note

You can also install the **Cluster storage engine extra tools** RPM, if you wish, as shown here:

```
shell> rpm -Uhv MySQL-Cluster-gpl-extra-7.1.33-0.sles10.i586.rpm
```

You may find the extra tools useful; however the **Cluster storage engine extra tools** RPM is *not* required to install a working MySQL Cluster.

See Installing MySQL on Linux Using RPM Packages, for general information about installing MySQL using RPMs supplied by Oracle.

After installing from RPM, you still need to configure the cluster as discussed in Section 4.3, "Initial Configuration of MySQL Cluster".

## 4.1.3 Building MySQL Cluster from Source on Linux

This section provides information about compiling MySQL Cluster on Linux and other Unix-like platforms. Building MySQL Cluster from source is similar to building the standard MySQL Server, although it differs in a few key respects discussed here. For general information about building MySQL from source, see Installing MySQL from Source. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported on Windows platforms, and can be built on Windows from source. For information about compiling MySQL Cluster on Windows platforms, see Section 4.2.2, "Compiling and Installing MySQL Cluster from Source on Windows".

Building MySQL Cluster requires using the MySQL Cluster sources. These are available from the MySQL Cluster downloads page at http://dev.mysql.com/downloads/cluster/. The archived source file should have a name similar to mysql-cluster-gpl-6.3.55.tar.gz, mysql-cluster-gpl-7.0.42.tar.gz, or mysql-cluster-gpl-7.1.33.tar.gz. You can also obtain MySQL development sources from launchpad.net. Attempting to build MySQL Cluster from standard MySQL 5.1 sources is not supported.

In addition to any other configure options you wish to use, be sure to include --with-plugins=ndbcluster, --with-plugins=max, or, or --with-plugins=max-no-innodb. Either of these options causes the binaries for the management nodes, data nodes, and other MySQL Cluster programs to be built; it also causes mysqld to be compiled with NDB storage engine support.

After you have run make && make install (or your system's equivalent), the result is similar to what is obtained by unpacking a precompiled binary to the same location. However, the layout can differ. These differences are covered in the next few paragraphs.

Prior to MySQL Cluster NDB 7.1.9, MySQL Cluster was not compatible with the InnoDB Plugin; in earlier MySQL Cluster releases, only the version of InnoDB supplied with the MySQL Server could be used. Beginning with MySQL Cluster NDB 7.1.9, you can build MySQL Cluster with InnoDB storage engine or plugin support using the appropriate —with—plugins option for configure.

**Management nodes.** When building from source and running the default make install, the management server binary (ndb\_mgmd) is placed in /usr/local/mysql/libexec, while the management client binary (ndb\_mgm) can be found in /usr/local/mysql/bin. Only ndb\_mgmd is required to be present on a management node host; however, it is also a good idea to have ndb\_mgm present on the same host machine. Neither of these executables requires a specific location on the host machine's file system.

**Data nodes.** The only executable required on a data node host is ndbd (mysqld, for example, does not have to be present on the host machine). By default when doing a source build, this file is placed in the directory /usr/local/mysql/libexec. For installing on multiple data node hosts, only ndbd need be copied to the other host machine or machines. (This assumes that all data node hosts use the same architecture and operating system; otherwise you may need to compile separately for each different platform.) ndbd need not be in any particular location on the host's file system, as long as the location is known.

When compiling MySQL Cluster NDB 7.0 or later from source, no special options are required for building multi-threaded data node binaries. On Unix platforms, configuring the build with any of the options — with-plugins=ndbcluster, —with-plugins=max, or —with-plugins=max—no-innodb causes ndbmtd to be built automatically; make install places the ndbmtd binary in the libexec directory along with mysqld, ndbd, and ndb\_mgm.

**SQL nodes.** If you compile MySQL with clustering support, and perform the default installation (using make install as the system root user), mysqld is placed in /usr/local/mysql/bin. Follow the steps given in Installing MySQL from Source to make mysqld ready for use. If you want to run multiple SQL nodes, you can use a copy of the same mysqld executable and its associated support files on several machines. The easiest way to do this is to copy the entire /usr/local/mysql directory and all directories and files contained within it to the other SQL node host or hosts, then repeat the steps from Installing MySQL from Source on each machine. If you configure the build with a nondefault --prefix, you need to adjust the directory accordingly.

In Section 4.3, "Initial Configuration of MySQL Cluster", we create configuration files for all of the nodes in our example MySQL Cluster.

## 4.2 Installing MySQL Cluster on Windows

Experimental support for MySQL Cluster on Microsoft Windows operating systems was introduced in MySQL Cluster NDB 7.0. Beginning with MySQL Cluster NDB 7.1.3, production support is provided for MySQL Cluster on Windows, and MySQL Cluster binaries for Windows can be obtained from <a href="http://dev.mysql.com/downloads/cluster/">http://dev.mysql.com/downloads/cluster/</a>. For information about installing MySQL Cluster on Windows from a binary release provided by Oracle, see Section 4.2.1, "Installing MySQL Cluster on Windows from a Binary Release".

It is also possible to compile and install MySQL Cluster from source on Windows using Microsoft Visual Studio. For more information, see Section 4.2.2, "Compiling and Installing MySQL Cluster from Source on Windows".

## 4.2.1 Installing MySQL Cluster on Windows from a Binary Release

This section describes a basic installation of MySQL Cluster on Windows using a binary no-install MySQL Cluster release provided by Oracle, using the same 4-node setup outlined in the beginning of this section (see Chapter 4, MySQL Cluster Installation and Upgrades), as shown in the following table:

Node	IP Address
Management (MGMD) node	192.168.0.10
MySQL server (SQL) node	192.168.0.20
Data (NDBD) node "A"	192.168.0.30
Data (NDBD) node "B"	192.168.0.40

As on other platforms, the MySQL Cluster host computer running an SQL node must have installed on it a MySQL Server binary (mysqld.exe). You should also have the MySQL client (mysql.exe) on this host. For management nodes and data nodes, it is not necessary to install the MySQL Server binary; however, each management node requires the management server daemon (ndb\_mgmd.exe); each data node requires the data node daemon (ndbd.exe or ndbmtd.exe). For this example, we refer to ndbd.exe as the data node executable, but you can install ndbmtd.exe, the multi-threaded version of this program, instead, in exactly the same way. You should also install the management client (ndb\_mgm.exe) on the management server host. This section covers the steps necessary to install the correct Windows binaries for each type of MySQL Cluster node.

ndbmtd.exe was not included in MySQL Cluster NDB 7.1.3 binary releases for Windows, due to a problem with make win bin dist. This issue was corrected in MySQL Cluster NDB 7.1.5.

### Note

As with other Windows programs, MySQL Cluster executables are named with the .exe file extension. However, it is not necessary to include the .exe extension when invoking these programs from the command line. Therefore, we often simply refer to these programs in this documentation as mysqld, mysql, ndb\_mgmd, and so on. You should understand that, whether we refer (for example) to mysqld or mysqld.exe, either name means the same thing (the MySQL Server program).

For setting up a MySQL Cluster using Oracles's no-install binaries, the first step in the installation process is to download the latest MySQL Cluster Windows binary archive from http://dev.mysql.com/downloads/cluster/. This archive has a filename of the form mysql-cluster-gpl-noinstall-ver-winarch.zip, where ver is the NDB storage engine version (such as 7.1.3), and arch is the architecture (32 for 32-bit binaries, and 64 for 64-bit binaries). For example, the MySQL Cluster NDB 7.1.3 no-install archive for 32-bit Windows systems is named mysql-cluster-gpl-noinstall-7.1.3-win32.zip.

You can run 32-bit MySQL Cluster binaries on both 32-bit and 64-bit versions of Windows; however, 64-bit MySQL Cluster binaries can be used only on 64-bit versions of Windows. If you are using a 32-bit version of Windows on a computer that has a 64-bit CPU, then you must use the 32-bit MySQL Cluster binaries.

To minimize the number of files that need to be downloaded from the Internet or copied between machines, we start with the computer where you intend to run the SQL node.

**SQL node.** We assume that you have placed a copy of the no-install archive in the directory C: \Documents and Settings\username\My Documents\Downloads on the computer having the IP

address 192.168.0.20, where *username* is the name of the current user. (You can obtain this name using ECHO %USERNAME% on the command line.) To install and run MySQL Cluster executables as Windows services, this user should be a member of the Administrators group.

Extract all the files from the archive. The Extraction Wizard integrated with Windows Explorer is adequate for this task. (If you use a different archive program, be sure that it extracts all files and directories from the archive, and that it preserves the archive's directory structure.) When you are asked for a destination directory, enter C:\, which causes the Extraction Wizard to extract the archive to the directory C:\mysql-cluster-gpl-noinstall-ver-winarch. Rename this directory to C:\mysql.

It is possible to install the MySQL Cluster binaries to directories other than <code>C:\mysql\bin</code>; however, if you do so, you must modify the paths shown in this procedure accordingly. In particular, if the MySQL Server (SQL node) binary is installed to a location other than <code>C:\mysql</code> or <code>C:\Program Files\MySQL</code> \MySQL Server 5.1, or if the SQL node's data directory is in a location other than <code>C:\mysql\data</code> or <code>C:\Program Files\MySQL\MySQL</code> Server 5.1\data, extra configuration options must be used on the command line or added to the <code>my.ini</code> or <code>my.cnf</code> file when starting the SQL node. For more information about configuring a MySQL Server to run in a nonstandard location, see Installing MySQL on Microsoft Windows Using a noinstall Zip Archive.

For a MySQL Server with MySQL Cluster support to run as part of a MySQL Cluster, it must be started with the options --ndbcluster and --ndb-connectstring. While you can specify these options on the command line, it is usually more convenient to place them in an option file. To do this, create a new text file in Notepad or another text editor. Enter the following configuration information into this file:

You can add other options used by this MySQL Server if desired (see Creating an Option File), but the file must contain the options shown, at a minimum. Save this file as C:\mysql\my.ini. This completes the installation and setup for the SQL node.

**Data nodes.** A MySQL Cluster data node on a Windows host requires only a single executable, one of either ndbd.exe or ndbmtd.exe. For this example, we assume that you are using ndbd.exe, but the same instructions apply when using ndbmtd.exe. On each computer where you wish to run a data node (the computers having the IP addresses 192.168.0.30 and 192.168.0.40), create the directories C: \mysql\bin, and C:\mysql\cluster-data; then, on the computer where you downloaded and extracted the no-install archive, locate ndbd.exe in the C:\mysql\bin directory. Copy this file to the C:\mysql\bin directory on each of the two data node hosts.

To function as part of a MySQL Cluster, each data node must be given the address or hostname of the management server. You can supply this information on the command line using the --ndb-connectstring or -c option when starting each data node process. However, it is usually preferable to put this information in an option file. To do this, create a new text file in Notepad or another text editor and enter the following text:

```
[mysql_cluster]
# Options for data node process:
ndb-connectstring=192.168.0.10 # location of management server
```

Save this file as <code>C:\mysql\my.ini</code> on the data node host. Create another text file containing the same information and save it on as <code>C:mysql\my.ini</code> on the other data node host, or copy the my.ini file from the first data node host to the second one, making sure to place the copy in the second data node's <code>C:\mysql</code> directory. Both data node hosts are now ready to be used in the MySQL Cluster, which leaves only the management node to be installed and configured.

Management node. The only executable program required on a computer used for hosting a MySQL Cluster management node is the management server program ndb\_mgmd.exe. However, in order to administer the MySQL Cluster once it has been started, you should also install the MySQL Cluster management client program ndb\_mgm.exe on the same machine as the management server. Locate these two programs on the machine where you downloaded and extracted the no-install archive; this should be the directory C:\mysql\bin on the SQL node host. Create the directory C:\mysql\bin on the computer having the IP address 192.168.0.10, then copy both programs to this directory.

You should now create two configuration files for use by ndb\_mgmd.exe:

1. A local configuration file to supply configuration data specific to the management node itself. Typically, this file needs only to supply the location of the MySQL Cluster global configuration file (see item 2).

To create this file, start a new text file in Notepad or another text editor, and enter the following information:

```
[mysql_cluster]
# Options for management node process
config-file=C:/mysql/bin/config.ini
```

Save this file as the plaintext file C:\mysql\bin\my.ini.

- 2. A global configuration file from which the management node can obtain configuration information governing the MySQL Cluster as a whole. At a minimum, this file must contain a section for each node in the MySQL Cluster, and the IP addresses or hostnames for the management node and all data nodes (HostName configuration parameter). It is also advisable to include the following additional information:
  - The IP address or hostname of any SQL nodes
  - The data memory and index memory allocated to each data node (DataMemory and IndexMemory configuration parameters)
  - The number of replicas, using the NoOfReplicas configuration parameter (see Section 3.2, "MySQL Cluster Nodes, Node Groups, Replicas, and Partitions")
  - The directory where each data node stores it data and log file, and the directory where the
    management node keeps its log files (in both cases, the DataDir configuration parameter)

Create a new text file using a text editor such as Notepad, and input the following information:

```
[ndbd default]
# Options affecting ndbd processes on all data nodes:
NoOfReplicas=2
                                    # Number of replicas
DataDir=C:/mysql/bin/cluster-data  # Directory for each data node's data files
                                    # Forward slashes used in directory path,
                                     # rather than backslashes. This is correct;
                                     # see Important note in text
                 # Memory allocated to data storage
DataMemory=80M
IndexMemory=18M
                 # Memory allocated to index storage
                  \ensuremath{\text{\#}} For DataMemory and IndexMemory, we have used the
                  # default values. Since the "world" database takes up
                  # only about 500KB, this should be more than enough for
                  # this example Cluster setup.
[ndb_mgmd]
# Management process options:
HostName=192.168.0.10
                                    # Hostname or IP address of management node
DataDir=C:/mysql/bin/cluster-logs  # Directory for management node log files
[ndbd]
```

```
# Options for data node "A":

# (one [ndbd] section per data node)

HostName=192.168.0.30 # Hostname or IP address

[ndbd]

# Options for data node "B":

HostName=192.168.0.40 # Hostname or IP address

[mysqld]

# SQL node options:

HostName=192.168.0.20 # Hostname or IP address
```

Save this file as the plaintext file C:\mysql\bin\config.ini.

### **Important**

A single backslash character (\) cannot be used when specifying directory paths in program options or configuration files used by MySQL Cluster on Windows. Instead, you must either escape each backslash character with a second backslash (\\), or replace the backslash with a forward slash character (/). For example, the following line from the [ndb\_mgmd] section of a MySQL Cluster config.ini file does not work:

```
DataDir=C:\mysql\bin\cluster-logs
Instead, you may use either of the following:
DataDir=C:\mysql\bin\cluster-logs # Escaped backslashes
DataDir=C:/mysql/bin/cluster-logs # Forward slashes
```

For reasons of brevity and legibility, we recommend that you use forward slashes in directory paths used in MySQL Cluster program options and configuration files on Windows.

### 4.2.2 Compiling and Installing MySQL Cluster from Source on Windows

Oracle provides precompiled MySQL Cluster binaries for Windows which should be adequate for most users. However, if you wish, it is also possible to compile MySQL Cluster for Windows from source code. The procedure for doing this is almost identical to the procedure used to compile the standard MySQL Server binaries for Windows, and uses the same tools. However, there are two major differences:

To build MySQL Cluster, you must use the MySQL Cluster sources, which you can obtain from http://dev.mysql.com/downloads/cluster/.

Attempting to build MySQL Cluster from the source code for the standard MySQL Server is likely not to be successful, and is not supported by Oracle.

You must configure the build using the WITH\_NDBCLUSTER\_STORAGE\_ENGINE option in addition to
any other build options you wish to use before creating the Visual Studio project files. Once you have
run configure.js with the desired options, you can create the project files and build from them in
the same manner as you do when compiling the standard MySQL Server. For more information, see
Installing MySQL from Source on Windows.

Prior to MySQL Cluster NDB 7.1.9, MySQL Cluster was not compatible with the InnoDB Plugin; in earlier MySQL Cluster releases, only the version of InnoDB supplied with the MySQL Server could be used. Beginning with MySQL Cluster NDB 7.1.9, you can build MySQL Cluster with InnoDB storage engine or plugin support on Windows using WITH\_INNOBASE\_STORAGE\_ENGINE with configure.js-

Once the build process is complete, you can create a Zip archive containing the compiled binaries by running make\_win\_bin\_dist. The MySQL Cluster binaries can be found in the bin directory of the resulting archive, which is equivalent to the no-install archive, and which can be installed and configured in the same manner. For basic information about how to accomplish these tasks, see Section 4.2.1, "Installing MySQL Cluster on Windows from a Binary Release".

On Windows, beginning with MySQL Cluster NDB 7.0.11, using WITH\_NDBCLUSTER\_STORAGE\_ENGINE with configure.js causes ndbmtd.exe to be built automatically, and to be found in the bin directory of the archive created by make\_win\_bin\_dist. (It was not possible to build ndbmtd.exe on Windows prior to MySQL Cluster NDB 7.0.11.)

### 4.2.3 Initial Startup of MySQL Cluster on Windows

Once the MySQL Cluster executables and needed configuration files are in place, performing an initial start of the cluster is simply a matter of starting the MySQL Cluster executables for all nodes in the cluster. Each cluster node process must be started separately, and on the host computer where it resides. The management node should be started first, followed by the data nodes, and then finally by any SQL nodes.

1. On the management node host, issue the following command from the command line to start the management node process:

```
C:\mysql\bin> ndb_mgmd
2010-06-23 07:53:34 [MgmtSrvr] INFO -- NDB Cluster Management Server. mysql-5.1.73-ndb-7.1.33
2010-06-23 07:53:34 [MgmtSrvr] INFO -- Reading cluster configuration from 'config.ini'
```

The management node process continues to print logging output to the console. This is normal, because the management node is not running as a Windows service. (If you have used MySQL Cluster on a Unix-like platform such as Linux, you may notice that the management node's default behavior in this regard on Windows is effectively the opposite of its behavior on Unix systems, where it runs by default as a Unix daemon process. This behavior is also true of MySQL Cluster data node processes running on Windows.) For this reason, do not close the window in which ndb\_mgmd.exe is running; doing so kills the management node process. (See Section 4.2.4, "Installing MySQL Cluster Processes as Windows Services", where we show how to install and run MySQL Cluster processes as Windows services.)

The required -f option tells the management node where to find the global configuration file (config.ini). The long form of this option is --config-file.

#### **Important**

A MySQL Cluster management node caches the configuration data that it reads from <code>config.ini</code>; once it has created a configuration cache, it ignores the <code>config.ini</code> file on subsequent starts unless forced to do otherwise. This means that, if the management node fails to start due to an error in this file, you must make the management node re-read <code>config.ini</code> after you have corrected any errors in it. You can do this by starting <code>ndb\_mgmd.exe</code> with the <code>--reload</code> or <code>--initial</code> option on the command line. Either of these options works to refresh the configuration cache.

It is not necessary or advisable to use either of these options in the management node's  ${\tt my.ini}$  file.

For additional information about options which can be used with ndb\_mgmd, see Section 6.4, "ndb\_mgmd — The MySQL Cluster Management Server Daemon", as well as Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

2. On each of the data node hosts, run the command shown here to start the data node processes:

```
C:\mysql\bin> ndbd
2010-06-23 07:53:46 [ndbd] INFO -- Configuration fetched from 'localhost:1186', generation: 1
```

In each case, the first line of output from the data node process should resemble what is shown in the preceding example, and is followed by additional lines of logging output. As with the management node process, this is normal, because the data node is not running as a Windows service. For this reason, do not close the console window in which the data node process is running; doing so kills ndbd.exe. (For more information, see Section 4.2.4, "Installing MySQL Cluster Processes as Windows Services".)

3. Do not start the SQL node yet; it cannot connect to the cluster until the data nodes have finished starting, which may take some time. Instead, in a new console window on the management node host, start the MySQL Cluster management client ndb\_mgm.exe, which should be in C:\mysql\bin on the management node host. (Do not try to re-use the console window where ndb\_mgmd.exe is running by typing CTRL+C, as this kills the management node.) The resulting output should look like this:

```
C:\mysql\bin> ndb_mgm
-- NDB Cluster -- Management Client --
ndb_mgm>
```

When the prompt ndb\_mgm> appears, this indicates that the management client is ready to receive MySQL Cluster management commands. You can observe the status of the data nodes as they start by entering ALL STATUS at the management client prompt. This command causes a running report of the data nodes's startup sequence, which should look something like this:

```
ndb_mgm> ALL STATUS

Connected to Management Server at: localhost:1186

Node 2: starting (Last completed phase 3) (mysql-5.1.73-ndb-7.1.33)

Node 3: starting (Last completed phase 3) (mysql-5.1.73-ndb-7.1.33)

Node 2: starting (Last completed phase 4) (mysql-5.1.73-ndb-7.1.33)

Node 3: starting (Last completed phase 4) (mysql-5.1.73-ndb-7.1.33)

Node 2: Started (version 7.1.33)

Node 3: Started (version 7.1.33)

ndb_mgm>
```

### Note

Commands issued in the management client are not case-sensitive; we use uppercase as the canonical form of these commands, but you are not required to observe this convention when inputting them into the ndb\_mgm client. For more information, see Section 7.2, "Commands in the MySQL Cluster Management Client".

The output produced by ALL STATUS is likely to vary from what is shown here, according to the speed at which the data nodes are able to start, the release version number of the MySQL Cluster software you are using, and other factors. What is significant is that, when you see that both data nodes have started, you are ready to start the SQL node.

You can leave ndb\_mgm.exe running; it has no negative impact on the performance of the MySQL Cluster, and we use it in the next step to verify that the SQL node is connected to the cluster after you have started it.

4. On the computer designated as the SQL node host, open a console window and navigate to the directory where you unpacked the MySQL Cluster binaries (if you are following our example, this is C: \mysql\bin).

Start the SQL node by invoking mysqld.exe from the command line, as shown here:

```
C:\mysql\bin> mysqld --console
```

The --console option causes logging information to be written to the console, which can be helpful in the event of problems. (Once you are satisfied that the SQL node is running in a satisfactory manner, you can stop it and restart it out without the --console option, so that logging is performed normally.)

In the console window where the management client (ndb\_mgm.exe) is running on the management node host, enter the SHOW command, which should produce output similar to what is shown here:

You can also verify that the SQL node is connected to the MySQL Cluster in the mysql client (mysql.exe) using the SHOW ENGINE NDB STATUS statement.

You should now be ready to work with database objects and data using MySQL Cluster's NDBCLUSTER storage engine. See Section 4.5, "MySQL Cluster Example with Tables and Data", for more information and examples.

Beginning with MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, you can install ndb\_mgmd.exe, ndbd.exe, and ndbmtd.exe as Windows services. For information on how to do this, see Section 4.2.4, "Installing MySQL Cluster Processes as Windows Services").

## 4.2.4 Installing MySQL Cluster Processes as Windows Services

Once you are satisfied that MySQL Cluster is running as desired, you can—beginning with MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5—install the management nodes and data nodes as Windows services, so that these processes are started and stopped automatically whenever Windows is started or stopped. This also makes it possible to control these processes from the command line with the appropriate NET START or NET STOP command, or using the Windows graphical Services utility.

Installing programs as Windows services usually must be done using an account that has Administrator rights on the system.

To install the management node as a service on Windows, invoke ndb\_mgmd.exe from the command line on the machine hosting the management node, using the --install option, as shown here:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --install
Installing service 'MySQL Cluster Management Server'
   as '"C:\mysql\bin\ndbd.exe" "--service=ndb_mgmd"'
Service successfully installed.
```

### **Important**

When installing a MySQL Cluster program as a Windows service, you should always specify the complete path; otherwise the service installation may fail with the error The system cannot find the file specified.

The --install option must be used first, ahead of any other options that might be specified for ndb\_mgmd.exe. However, it is preferable to specify such options in an options file instead. If your options file is not in one of the default locations as shown in the output of ndb\_mgmd.exe --help, you can specify the location using the --config-file option.

Now you should be able to start and stop the management server like this:

```
C:\> NET START ndb_mgmd

The MySQL Cluster Management Server service is starting.

The MySQL Cluster Management Server service was started successfully.

C:\> NET STOP ndb_mgmd

The MySQL Cluster Management Server service is stopping..

The MySQL Cluster Management Server service was stopped successfully.
```

You can also start or stop the management server as a Windows service using the descriptive name, as shown here:

```
C:\> NET START 'MySQL Cluster Management Server'
The MySQL Cluster Management Server service is starting.
The MySQL Cluster Management Server service was started successfully.
C:\> NET STOP 'MySQL Cluster Management Server'
The MySQL Cluster Management Server service is stopping..
The MySQL Cluster Management Server service was stopped successfully.
```

However, it is usually simpler to specify a short service name or to permit the default service name to be used when installing the service, and then reference that name when starting or stopping the service. To specify a service name other than ndb\_mgmd, append it to the --install option, as shown in this example:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --install=mgmd1
Installing service 'MySQL Cluster Management Server'
as '"C:\mysql\bin\ndb_mgmd.exe" "--service=mgmd1"'
Service successfully installed.
```

Now you should be able to start or stop the service using the name you have specified, like this:

```
C:\> NET START mgmdl
The MySQL Cluster Management Server service is starting.
The MySQL Cluster Management Server service was started successfully.
C:\> NET STOP mgmdl
The MySQL Cluster Management Server service is stopping..
The MySQL Cluster Management Server service was stopped successfully.
```

To remove the management node service, invoke ndb\_mgmd.exe with the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --remove
Removing service 'MySQL Cluster Management Server'
Service successfully removed.
```

If you installed the service using a service name other than the default, you can remove the service by passing this name as the value of the --remove option, like this:

```
C:\> C:\mysql\bin\ndb_mgmd.exe --remove=mgmd1
Removing service 'mgmd1'
Service successfully removed.
```

Installation of a MySQL Cluster data node process as a Windows service can be done in a similar fashion, using the --install option for ndbd.exe (or ndbmtd.exe), as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --install
Installing service 'MySQL Cluster Data Node Daemon' as '"C:\mysql\bin\ndbd.exe" "--service=ndbd"'
Service successfully installed.
```

Now you can start or stop the data node using either the default service name or the descriptive name with net start or net stop, as shown in the following example:

```
C:\> NET START ndbd

The MySQL Cluster Data Node Daemon service is starting.

The MySQL Cluster Data Node Daemon service was started successfully.

C:\> NET STOP ndbd

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service was stopped successfully.

C:\> NET START 'MySQL Cluster Data Node Daemon'

The MySQL Cluster Data Node Daemon service is starting.

The MySQL Cluster Data Node Daemon service was started successfully.

C:\> NET STOP 'MySQL Cluster Data Node Daemon'

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service was stopped successfully.
```

To remove the data node service, invoke ndbd.exe with the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --remove

Removing service 'MySQL Cluster Data Node Daemon'

Service successfully removed.
```

As with ndb\_mgmd.exe (and mysqld.exe), when installing ndbd.exe as a Windows service, you can also specify a name for the service as the value of --install, and then use it when starting or stopping the service, like this:

```
C:\> C:\mysql\bin\ndbd.exe --install=dnode1

Installing service 'dnodel' as '"C:\mysql\bin\ndbd.exe" "--service=dnodel"'

Service successfully installed.

C:\> NET START dnode1

The MySQL Cluster Data Node Daemon service is starting.

The MySQL Cluster Data Node Daemon service was started successfully.

C:\> NET STOP dnode1

The MySQL Cluster Data Node Daemon service is stopping..

The MySQL Cluster Data Node Daemon service was stopped successfully.
```

If you specified a service name when installing the data node service, you can use this name when removing it as well, by passing it as the value of the --remove option, as shown here:

```
C:\> C:\mysql\bin\ndbd.exe --remove=dnodel
Removing service 'dnodel'
Service successfully removed.
```

Installation of the SQL node as a Windows service, starting the service, stopping the service, and removing the service are done in a similar fashion, using <code>mysqld --install</code>, <code>NET START</code>, <code>NET STOP</code>, and <code>mysqld --remove</code>. For additional information, see Starting MySQL Server as a Microsoft Windows Service.

# 4.3 Initial Configuration of MySQL Cluster

For our four-node, four-host MySQL Cluster, it is necessary to write four configuration files, one per node host.

• Each data node or SQL node requires a my.cnf file that provides two pieces of information: a connection string that tells the node where to find the management node, and a line telling the MySQL server on this host (the machine hosting the data node) to enable the NDBCLUSTER storage engine.

For more information on connection strings, see Section 5.2.3, "MySQL Cluster Connection Strings".

• The management node needs a config.ini file telling it how many replicas to maintain, how much memory to allocate for data and indexes on each data node, where to find the data nodes, where to save data to disk on each data node, and where to find any SQL nodes.

**Configuring the data nodes and SQL nodes.** The my.cnf file needed for the data nodes is fairly simple. The configuration file should be located in the /etc directory and can be edited using any text editor. (Create the file if it does not exist.) For example:

```
shell> vi /etc/my.cnf
```

#### Note

We show vi being used here to create the file, but any text editor should work just as well.

For each data node and SQL node in our example setup, my.cnf should look like this:

After entering the preceding information, save this file and exit the text editor. Do this for the machines hosting data node "A", data node "B", and the SQL node.

#### **Important**

Once you have started a mysqld process with the ndbcluster and ndb-connectstring parameters in the [mysqld] and [mysql\_cluster] sections of the my.cnf file as shown previously, you cannot execute any CREATE TABLE or ALTER TABLE statements without having actually started the cluster. Otherwise, these statements will fail with an error. This is by design.

**Configuring the management node.** The first step in configuring the management node is to create the directory in which the configuration file can be found and then to create the file itself. For example (running as root):

```
shell> mkdir /var/lib/mysql-cluster
shell> cd /var/lib/mysql-cluster
shell> vi config.ini
```

For our representative setup, the config.ini file should read as follows:

```
[ndbd default]
# Options affecting ndbd processes on all data nodes:
NoOfReplicas=2 # Number of replicas
                 # How much memory to allocate for data storage
DataMemory=80M
IndexMemory=18M  # How much memory to allocate for index storage
                 # For DataMemory and IndexMemory, we have used the
                 # default values. Since the "world" database takes up
                 # only about 500KB, this should be more than enough for
                 # this example Cluster setup.
[tcp default]
# TCP/IP options:
portnumber=2202  # This the default; however, you can use any
                 # port that is free for all the hosts in the cluster
                 # Note: It is recommended that you do not specify the port
                 # number at all and simply allow the default value to be used
                 # instead
[ndb_mgmd]
# Management process options:
hostname=192.168.0.10
                               # Hostname or IP address of MGM node
datadir=/var/lib/mysql-cluster # Directory for MGM node log files
[ndbd]
# Options for data node "A":
                               # (one [ndbd] section per data node)
hostname=192.168.0.30
                               # Hostname or IP address
datadir=/usr/local/mysql/data  # Directory for this data node's data files
[ndbd]
# Options for data node "B":
hostname=192.168.0.40
                               # Hostname or IP address
datadir=/usr/local/mysql/data  # Directory for this data node's data files
[mysqld]
# SQL node options:
hostname=192.168.0.20
                               # Hostname or IP address
                               # (additional mysgld connections can be
                               # specified for this node for various
                               # purposes such as running ndb_restore)
```

#### Note

The world database can be downloaded from <a href="http://dev.mysql.com/doc/">http://dev.mysql.com/doc/</a>, where it can be found listed under "Examples".

After all the configuration files have been created and these minimal options have been specified, you are ready to proceed with starting the cluster and verifying that all processes are running. We discuss how this is done in Section 4.4, "Initial Startup of MySQL Cluster".

For more detailed information about the available MySQL Cluster configuration parameters and their uses, see Section 5.2, "MySQL Cluster Configuration Files", and Chapter 5, *Configuration of MySQL Cluster NDB 6.1-7.1*. For configuration of MySQL Cluster as relates to making backups, see Section 7.3.3, "Configuration for MySQL Cluster Backups".

#### Note

The default port for Cluster management nodes is 1186; the default port for data nodes is 2202. However, the cluster can automatically allocate ports for data nodes from those that are already free.

### 4.4 Initial Startup of MySQL Cluster

Starting the cluster is not very difficult after it has been configured. Each cluster node process must be started separately, and on the host where it resides. The management node should be started first, followed by the data nodes, and then finally by any SQL nodes:

1. On the management host, issue the following command from the system shell to start the management node process:

```
shell> ndb_mgmd -f /var/lib/mysql-cluster/config.ini
```

ndb\_mgmd must be told where to find its configuration file, using the -f or --config-file option. (See Section 6.4, "ndb\_mgmd — The MySQL Cluster Management Server Daemon", for details.)

For additional options which can be used with ndb\_mgmd, see Section 6.25, "Options Common to MySQL Cluster Programs".

2. On each of the data node hosts, run this command to start the ndbd process:

```
shell> ndbd
```

3. If you used RPM files to install MySQL on the cluster host where the SQL node is to reside, you can (and should) use the supplied startup script to start the MySQL server process on the SQL node.

If all has gone well, and the cluster has been set up correctly, the cluster should now be operational. You can test this by invoking the ndb\_mgm management node client. The output should look like that shown here, although you might see some slight differences in the output depending upon the exact version of MySQL that you are using:

The SQL node is referenced here as [mysqld(API)], which reflects the fact that the mysqld process is acting as a MySQL Cluster API node.

#### Note

The IP address shown for a given MySQL Cluster SQL or other API node in the output of SHOW is the address used by the SQL or API node to connect to the cluster data nodes, and not to any management node.

You should now be ready to work with databases, tables, and data in MySQL Cluster. See Section 4.5, "MySQL Cluster Example with Tables and Data", for a brief discussion.

## 4.5 MySQL Cluster Example with Tables and Data

#### **Note**

The information in this section applies to MySQL Cluster running on both Unix and Windows platforms.

Working with database tables and data in MySQL Cluster is not much different from doing so in standard MySQL. There are two key points to keep in mind:

• For a table to be replicated in the cluster, it must use the NDBCLUSTER storage engine. To specify this, use the ENGINE=NDBCLUSTER or ENGINE=NDB option when creating the table:

```
CREATE TABLE tbl_name (col_name column_definitions) ENGINE=NDBCLUSTER;
```

Alternatively, for an existing table that uses a different storage engine, use ALTER TABLE to change the table to use NDBCLUSTER:

```
ALTER TABLE tbl_name ENGINE=NDBCLUSTER;
```

Every NDBCLUSTER table has a primary key. If no primary key is defined by the user when a table is
created, the NDBCLUSTER storage engine automatically generates a hidden one. Such a key takes up
space just as does any other table index. (It is not uncommon to encounter problems due to insufficient
memory for accommodating these automatically created indexes.)

If you are importing tables from an existing database using the output of mysqldump, you can open the SQL script in a text editor and add the ENGINE option to any table creation statements, or replace any existing ENGINE options. Suppose that you have the world sample database on another MySQL server that does not support MySQL Cluster, and you want to export the City table:

```
shell> mysqldump --add-drop-table world City > city_table.sql
```

The resulting city\_table.sql file will contain this table creation statement (and the INSERT statements necessary to import the table data):

You need to make sure that MySQL uses the NDBCLUSTER storage engine for this table. There are two ways that this can be accomplished. One of these is to modify the table definition *before* importing it into the Cluster database. Using the City table as an example, modify the ENGINE option of the definition as follows:

```
DROP TABLE IF EXISTS `City`;

CREATE TABLE `City` (
  `ID` int(11) NOT NULL auto_increment,
  `Name` char(35) NOT NULL default '',
  `CountryCode` char(3) NOT NULL default '',
  `District` char(20) NOT NULL default '',
  `Population` int(11) NOT NULL default '0',
  PRIMARY KEY (`ID`)
) ENGINE=NDBCLUSTER DEFAULT CHARSET=latin1;

INSERT INTO `City` VALUES (1,'Kabul','AFG','Kabol',1780000);
```

```
INSERT INTO `City` VALUES (2,'Qandahar','AFG','Qandahar',237500);
INSERT INTO `City` VALUES (3,'Herat','AFG','Herat',186800);
(remaining INSERT statements omitted)
```

This must be done for the definition of each table that is to be part of the clustered database. The easiest way to accomplish this is to do a search-and-replace on the file that contains the definitions and replace all instances of TYPE=engine\_name or ENGINE=engine\_name with ENGINE=NDBCLUSTER. If you do not want to modify the file, you can use the unmodified file to create the tables, and then use ALTER TABLE to change their storage engine. The particulars are given later in this section.

Assuming that you have already created a database named world on the SQL node of the cluster, you can then use the mysql command-line client to read city\_table.sql, and create and populate the corresponding table in the usual manner:

```
shell> mysql world < city_table.sql
```

It is very important to keep in mind that the preceding command must be executed on the host where the SQL node is running (in this case, on the machine with the IP address 192.168.0.20).

To create a copy of the entire world database on the SQL node, use mysqldump on the noncluster server to export the database to a file named world.sql; for example, in the /tmp directory. Then modify the table definitions as just described and import the file into the SQL node of the cluster like this:

```
shell> mysql world < /tmp/world.sql
```

If you save the file to a different location, adjust the preceding instructions accordingly.

Running SELECT queries on the SQL node is no different from running them on any other instance of a MySQL server. To run queries from the command line, you first need to log in to the MySQL Monitor in the usual way (specify the root password at the Enter password: prompt):

```
shell> mysql -u root -p
Enter password:
Welcome to the MySQL monitor. Commands end with ; or \g.
Your MySQL connection id is 1 to server version: 5.1.73-ndb-7.1.33
Type 'help;' or '\h' for help. Type '\c' to clear the buffer.
mysql>
```

We simply use the MySQL server's root account and assume that you have followed the standard security precautions for installing a MySQL server, including setting a strong root password. For more information, see Securing the Initial MySQL Accounts.

It is worth taking into account that Cluster nodes do *not* make use of the MySQL privilege system when accessing one another. Setting or changing MySQL user accounts (including the root account) effects only applications that access the SQL node, not interaction between nodes. See Section 7.11.2, "MySQL Cluster and MySQL Privileges", for more information.

If you did not modify the ENGINE clauses in the table definitions prior to importing the SQL script, you should run the following statements at this point:

```
mysql> USE world;
mysql> ALTER TABLE City ENGINE=NDBCLUSTER;
mysql> ALTER TABLE Country ENGINE=NDBCLUSTER;
mysql> ALTER TABLE CountryLanguage ENGINE=NDBCLUSTER;
```

Selecting a database and running a SELECT query against a table in that database is also accomplished in the usual manner, as is exiting the MySQL Monitor:

Applications that use MySQL can employ standard APIs to access NDB tables. It is important to remember that your application must access the SQL node, and not the management or data nodes. This brief example shows how we might execute the SELECT statement just shown by using the PHP 5.X mysqli extension running on a Web server elsewhere on the network:

```
<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.01 Transitional//EN"</pre>
 "http://www.w3.org/TR/html4/loose.dtd">
<html>
<head>
 <meta http-equiv="Content-Type"</pre>
       content="text/html; charset=iso-8859-1">
 <title>SIMPLE mysqli SELECT</title>
</head>
<body>
<?php
 # connect to SOL node:
 $link = new mysqli('192.168.0.20', 'root', 'root_password', 'world');
 # parameters for mysqli constructor are:
    host, user, password, database
 if( mysqli_connect_errno() )
  die("Connect failed: " . mysqli_connect_error());
 $query = "SELECT Name, Population
         FROM City
          ORDER BY Population DESC
         LIMIT 5";
 # if no errors..
 if( $result = $link->query($query) )
?>
City
   Population
 # then display the results...
   while($row = $result->fetch_object())
     printf("\n %s%d\n\n",
           $row->Name, $row->Population);
 </tbody
<?
 # ...and verify the number of rows that were retrieved
```

```
printf("Affected rows: %d\n", $link->affected_rows);
}
else
    # otherwise, tell us what went wrong
    echo mysqli_error();
# free the result set and the mysqli connection object
    $result->close();
    $link->close();
?>
</body>
</html>
```

We assume that the process running on the Web server can reach the IP address of the SQL node.

In a similar fashion, you can use the MySQL C API, Perl-DBI, Python-mysql, or MySQL Connectors to perform the tasks of data definition and manipulation just as you would normally with MySQL.

## 4.6 Safe Shutdown and Restart of MySQL Cluster

To shut down the cluster, enter the following command in a shell on the machine hosting the management node:

```
shell> ndb_mgm -e shutdown
```

The -e option here is used to pass a command to the ndb\_mgm client from the shell. (See Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs", for more information about this option.) The command causes the ndb\_mgm, ndb\_mgmd, and any ndbd or ndbmtd processes to terminate gracefully. Any SQL nodes can be terminated using mysqladmin shutdown and other means. On Windows platforms, assuming that you have installed the SQL node as a Windows service, you can use NET STOP MYSQL.

To restart the cluster on Unix platforms, run these commands:

• On the management host (192.168.0.10 in our example setup):

```
shell> ndb_mgmd -f /var/lib/mysql-cluster/config.ini
```

On each of the data node hosts (192.168.0.30 and 192.168.0.40):

```
shell> ndbd
```

- Use the ndb\_mgm client to verify that both data nodes have started successfully.
- On the SQL host (192.168.0.20):

```
shell> mysqld_safe &
```

On Windows platforms, assuming that you have installed all MySQL Cluster processes as Windows services using the default service names (see Section 4.2.4, "Installing MySQL Cluster Processes as Windows Services"), you can restart the cluster as follows:

• On the management host (192.168.0.10 in our example setup), execute the following command:

```
C:\> NET START ndb_mgmd
```

On each of the data node hosts (192.168.0.30 and 192.168.0.40), execute the following command:

C:\> NET START ndbd

- On the management node host, use the ndb\_mgm client to verify that the management node and both
  data nodes have started successfully (see Section 4.2.3, "Initial Startup of MySQL Cluster on Windows").
- On the SQL node host (192.168.0.20), execute the following command:

```
C:\> NET START mysql
```

In a production setting, it is usually not desirable to shut down the cluster completely. In many cases, even when making configuration changes, or performing upgrades to the cluster hardware or software (or both), which require shutting down individual host machines, it is possible to do so without shutting down the cluster as a whole by performing a *rolling restart* of the cluster. For more information about doing this, see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster".

## 4.7 Upgrading and Downgrading MySQL Cluster

This section provides information about MySQL Cluster software and table file compatibility between MySQL 5.1.23 and earlier, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x releases with regard to performing upgrades and downgrades as well as compatibility matrices and notes. You are expected already to be familiar with installing and configuring a MySQL Cluster prior to attempting an upgrade or downgrade. See Chapter 5, Configuration of MySQL Cluster NDB 6.1-7.1.

For information regarding the rolling restart procedure used to perform an online upgrade, see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster".

### **Important**

Only compatibility between MySQL versions with regard to NDBCLUSTER is taken into account in this section, and there are likely other issues to be considered. As with any other MySQL software upgrade or downgrade, you are strongly encouraged to review the relevant portions of the MySQL Manual for the MySQL versions from which and to which you intend to migrate, before attempting an upgrade or downgrade of the MySQL Cluster software. See Upgrading MySQL.

For information about upgrades and downgrades to, from, and between different releases of MySQL Cluster NDB 7.0 and MySQL Cluster NDB 7.1, see Section 4.7.1, "Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x".

For information about upgrades and downgrades to, from, and between different releases of MySQL Cluster NDB 6.1, MySQL Cluster NDB 6.2, and MySQL Cluster NDB 6.3, see Section 4.7.2, "Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x".

For information about upgrades and downgrades to, from, and between different releases of MySQL Cluster NDB 7.2, see Upgrading and Downgrading MySQL Cluster NDB 7.2.

For information about upgrades and downgrades to, from, and between different editions of MySQL Cluster as found in standard MySQL 5.1.23 and earlier releases, see Section 4.7.3, "Upgrade and downgrade compatibility: MySQL 5.1".


#### **Important**

Only compatibility between MySQL versions with regard to NDBCLUSTER is taken into account in this section, and there are likely other issues to be considered.

As with any other MySQL software upgrade or downgrade, you are strongly encouraged to review the relevant portions of the MySQL Manual for the MySQL versions from which and to which you intend to migrate, before attempting an upgrade or downgrade of the MySQL Cluster software. See Upgrading MySQL.

### 4.7.1 Upgrade and downgrade compatibility: MySQL Cluster NDB 7.x

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL Cluster NDB 7.0 and 7.1. Additional notes about upgrades and downgrades to, from, or within the MySQL Cluster NDB 7.x release series can be found immediately following the table.



### Notes: MySQL Cluster NDB 7.x

**Versions supported.** Online upgrades from any MySQL Cluster NDB 7.0 release up to and including MySQL Cluster NDB 7.0.4 (as well as all early releases numbered NDB 6.4.x) to MySQL Cluster NDB 7.0.5 or later are not possible. Upgrades to MySQL Cluster NDB 7.0.6 or later from MySQL Cluster NDB 6.3.8 or a later MySQL Cluster NDB 6.3 release, or from MySQL Cluster NDB 7.0.5 or later, are supported. (Bug #44294)

**Upgrading ndbd to ndbmtd.** When upgrading online from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0 (or later) release, you should not try to upgrade the data nodes from ndbd to ndbmtd at the same time. Instead, perform the upgrade using the new ndbd executable (from the MySQL Cluster NDB 7.0 or later distribution to which you are upgrading) to replace the one in use on the data nodes. Once the version upgrade is complete, you can perform a second (online) upgrade to replace the data node executables with ndbmtd from the newer distribution. Changing the data node binary type should not be an issue when upgrading from MySQL Cluster NDB 7.0 or later version.

Changes in default values. In MySQL Cluster NDB 7.0.4, the default values for a number of MySQL Cluster configuration parameters relating to memory usage and buffering changed (see http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-5-1-32-ndb-7-0-4.html, for a list of the parameters whose defaults changed). For this reason, you may encounter issues if you try to use a configuration that does not explicitly define each of these buffers (because it was developed for a previous version of MySQL Cluster), SendBufferMemory and ReceiveBufferMemory in particular.

Other known issues include the following:

- Prior to MySQL Cluster NDB 7.0.7, DML statements failed if executed while performing an online upgrade from a MySQL Cluster NDB 6.3 release. (Bug #45917)
- Following an upgrade from any MySQL Cluster NDB 6.3.x release to MySQL Cluster NDB 7.0.6, DDL and backup operations failed. This issue was resolved in MySQL Cluster NDB 7.0.7. (Bug #46494, Bug #46563)
- In some cases, there could be problems with online upgrades from MySQL Cluster NDB 6.3 releases
  to MySQL Cluster NDB 7.0 releases due to a previous change in the signalling format used between
  nodes. This issue was corrected in MySQL Cluster NDB 7.0.9.
- Once an NDB table had an ALTER ONLINE TABLE operation performed on it using a MySQL Cluster NDB 6.3.x release, it could not be upgraded online to MySQL Cluster NDB 7.0. This issue was resolved in MySQL Cluster NDB 7.0.8. (See Bug #47542.)
- Following an upgrade from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0, if there were any tables
  having unique indexes prior to the upgrade, attempts to create unique indexes failed. This could also
  occur when performing offline ALTER TABLE operations on tables having indexes that were not dropped
  as a result of the ALTER TABLE. This issue was due to a change in the way that NDB tracked unique
  indexes internally, and was resolved in MySQL Cluster NDB 7.0.9. (Bug #48416)

For upgrades to MySQL Cluster NDB 7.0 releases prior to version 7.0.9, a workaround is available: Following the upgrade, execute a *second* rolling restart of the cluster before performing any ALTER TABLE operations involving indexes.

Due to an issue discovered after the release of MySQL Cluster NDB 7.0.10 (Bug #50433), it is not
possible to perform an online upgrade from MySQL Cluster NDB 7.0.9b and earlier MySQL Cluster NDB
7.0 releases to MySQL Cluster NDB 7.0.10. Instead, you should upgrade your MySQL Cluster NDB 7.0
installation directly to MySQL Cluster NDB 7.0.11 or later.

This issue did not appear to affect MySQL Cluster NDB 6.3, and it should be possible to upgrade online from MySQL Cluster NDB 6.3 to MySQL Cluster NDB 7.0.10 without any problems other than those noted previously.

- It was not possible to perform an online upgrade from a MySQL Cluster NDB 6.3 or 7.0 release to MySQL Cluster NDB 7.1.0 or 7.1.1. This issue was fixed in MySQL Cluster NDB 7.1.2 (see Bug #51429).
- Following an upgrade to MySQL Cluster NDB 7.0.15 or later (MySQL Cluster NDB 7.0), or to MySQL Cluster NDB 7.1.4 or later (MySQL Cluster NDB 7.1), a table created in a previous version of MySQL Cluster does *not* automatically support NDB-native default values. Such a table continues to use default values supplied by the MySQL server until it is upgraded by performing an offline ALTER TABLE on it.

When upgrading to a MySQL Cluster release that supports native default values from a MySQL Cluster release that does not, you should not attempt to create any new tables until all data nodes are using the new ndbd or ndbmtd binaries. This is because the older binaries do not provide support for native default values.

### **Important**

Tables created with native default value support cannot be used with versions of MySQL Cluster that do not support native default values.

 NDB API changes in MySQL Cluster NDB 7.1.16 and MySQL Cluster NDB 7.0.27 are not backward compatible. Due to these changes the version of the included NDB client library was increased from 4.0.0 to 5.0.0; NDB API applications must be recompiled as part of any upgrade to these or later MySQL Cluster releases.

In addition, NDB API programs should be updated as part of such an upgrade, in order to take into account changes in the default behavior and values for the Ndb\_cluster\_connection::connect() method.

Due to issues discovered shortly after release, MySQL Cluster NDB 7.0.20 was withdrawn and replaced with MySQL Cluster NDB 7.0.20a. Users of MySQL Cluster NDB 7.0.19 and previous MySQL Cluster NDB 7.0 releases should upgrade to MySQL Cluster NDB 7.0.20a, or to a later MySQL Cluster NDB 7.0 release. See http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-5-1-51-ndb-7-0-20a.html, for more information.

Due to issues discovered following release, MySQL Cluster NDB 7.1.15 was withdrawn and replaced with MySQL Cluster NDB 7.1.15a. Users of MySQL Cluster NDB 7.1.14 and previous MySQL Cluster NDB 7.1 releases should upgrade to MySQL Cluster NDB 7.1.15a, or to a later MySQL Cluster NDB 7.1 release. See <a href="http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-5-1-56-ndb-7-1-15a.html">http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-5-1-56-ndb-7-1-15a.html</a>, for more information.

Due to issues discovered shortly after release, MySQL Cluster NDB 7.1.9 was withdrawn and replaced with MySQL Cluster NDB 7.1.9a. Users of MySQL Cluster NDB 7.1.8 and previous MySQL Cluster NDB 7.1 releases should upgrade to MySQL Cluster NDB 7.1.14 (the last release directly upgrade-compatible with MySQL Cluster 7.1.18 and earlier) before upgrading to MySQL Cluster 7.1.15a or later. See http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-5-1-51-ndb-7-1-9a.html, for more information.

• When performing an online upgrade or downgrade between MySQL Cluster NDB 7.1.8 or earlier and a later release up to and including MySQL Cluster NDB 7.1.14, you must upgrade or downgrade the data nodes before upgrading or downgrading any SQL nodes; otherwise mysql\_upgrade fails on the SQL nodes due to differences between ndbinfo tables used in the "old" and "new" versions of the MySQL Cluster software. You should also upgrade or downgrade the data nodes prior to the SQL nodes when


performing an online upgrade or downgrade between MySQL Cluster NDB 7.1 releases where either of the versions involved is MySQL Cluster NDB 7.1.14 or earlier, and where one or more ndbinfo tables has more, fewer, or differing columns between the two versions.

This issue is resolved in MySQL Cluster NDB 7.1.15. (Bug #11885602)

 It was not possible to downgrade online to MySQL Cluster NDB 7.1 from some later versions of MySQL Cluster due to a change in the size used for table hash maps by NDB. (Bug #14645319) This issue was resolved in MySQL Cluster NDB 7.1.26, where the size is made configurable using the DefaultHashMapSize [128] parameter. (Bug #14800539) See the description of this parameter for more information.

### 4.7.2 Upgrade and Downgrade Compatibility: MySQL Cluster NDB 6.x

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL Cluster NDB 6.1, 6.2, and 6.3. Additional notes about upgrades and downgrades to, from, or within the MySQL Cluster NDB 6.x release series can be found immediately following the table.



### **Notes: MySQL Cluster NDB 6.1**

**Availability of older releases.** MySQL Cluster NDB 6.1 is no longer in production; information about this series of releases is of historical interest only. MySQL Cluster NDB 6.2 is still available, but is no longer supported in new deployments. If you are still using a MySQL Cluster NDB 6.1 or MySQL Cluster NDB 6.2 release, you should upgrade to the most recent MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1 release as soon as possible.

- It is not possible to upgrade from MySQL Cluster NDB 6.1.2 (or an older 6.1 release) directly to 6.1.4 or a newer NDB 6.1 release, or to downgrade from 6.1.4 (or a newer 6.1 release) directly to 6.1.2 or an older NDB 6.1 release; in either case, you must upgrade or downgrade to MySQL Cluster NDB 6.1.3 first.
- It is not possible to perform an online downgrade from MySQL Cluster NDB 6.1.8 (or a newer 6.1 release) to MySQL Cluster NDB 6.1.7 (or an older 6.1 release).
- MySQL Cluster NDB 6.1.6 and 6.1.18 were not released.
- It is not possible to perform an online upgrade or downgrade between MySQL Cluster NDB 6.2 and any
  previous release series (including mainline MySQL 5.1 and MySQL Cluster NDB 6.1); it is necessary to
  perform a dump and reload. However, it should be possible to perform online upgrades or downgrades
  between any MySQL Cluster NDB 6.2 release and any MySQL Cluster NDB 6.3 release up to and
  including 6.3.7.

### Notes: MySQL Cluster NDB 6.2 and MySQL Cluster NDB 6.3

Internal column specification changes. The internal specifications for columns in NDB tables changed in MySQL Cluster NDB 6.1.17 and 6.2.1 to enable compatibility with later MySQL Cluster releases implementing online adding and dropping of columns (MySQL 5.1.17 through MySQL 5.1.23; MySQL Cluster NDB 6.2.3 and later; MySQL Cluster NDB 6.3.2 and later). This change is not backward-compatible with earlier MySQL Server or MySQL Cluster releases.

To make tables created in earlier versions compatible with online adding and dropping of columns in later versions, it is necessary to force MySQL Cluster to convert the tables to the new format by following this procedure following an upgrade:

- 1. Upgrade the MySQL Cluster software on all data, management, and SQL nodes
- 2. Back up all NDB tables
- 3. Shut down the cluster (all data, management, and SQL nodes)
- 4. Restart the cluster, starting all data nodes with the --initial option (to clear and rebuild the data node file systems)
- 5. Restore the tables from backup

To minimize possible later difficulties, it is strongly advised that the procedure outlined above be followed as soon as possible after to upgrading between the versions indicated. The procedure is *not* necessary for NDBCLUSTER tables created in any of the following versions:

- MySQL Cluster NDB 6.1.8 or a later MySQL Cluster NDB 6.1 release
- MySQL Cluster 6.2.1 or a later MySQL Cluster NDB 6.2 release
- Any MySQL Cluster NDB 6.3 release (or later MySQL Cluster release series)


Tables created in the versions listed previously (or later versions, as indicated) are already compatible with adding and dropping of columns online (as implemented beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2).

Additional issues encountered when upgrading or downgrading to or from MySQL Cluster NDB 6.2 and MySQL Cluster NDB 6.3 releases are listed here:

- It was not possible to perform an online upgrade between any MySQL Cluster NDB 6.2 release and MySQL Cluster NDB 6.3.8 and later MySQL Cluster 6.3 releases. This issue was fixed in MySQL Cluster NDB 6.3.21. (Bug #41435)
- Online downgrades between MySQL Cluster NDB 6.2.5 and earlier releases are not supported.
- Online downgrades between MySQL Cluster NDB 6.3.8 and earlier releases are not supported.

### 4.7.3 Upgrade and downgrade compatibility: MySQL 5.1

The table shown here provides information on MySQL Cluster upgrade and downgrade compatibility among different releases of MySQL 5.1 prior to MySQL 5.1.24. Additional notes about upgrades and downgrades to, from, or within the MySQL 5.1 release series can be found immediately following the table.



### Notes: MySQL 5.1

- MySQL 5.1.3 was the first public release in this series.
- Direct upgrades or downgrades between MySQL Cluster 5.0 and 5.1 are not supported; you must dump all NDBCLUSTER tables using mysqldump, install the new version of the software, and then reload the tables from the dump.

- You cannot downgrade a MySQL Cluster based on MySQL 5.1.6 or later and using Disk Data tables to MySQL 5.1.5 or earlier unless you convert all such tables to in-memory NDB tables first.
- MySQL 5.1.8, MySQL 5.1.10, and MySQL 5.1.13 were not released.
- Online cluster upgrades and downgrades between MySQL 5.1.11 (or an earlier version) and 5.1.12 (or a later version) are not possible due to major changes in the cluster file system. In such cases, you must perform a backup or dump, upgrade (or downgrade) the software, start each data node with -- initial, and then restore from the backup or dump. You can use native NDB backup and restore, or mysqldump and LOAD DATA INFILE for this purpose.
- Online downgrades from MySQL 5.1.14 or later to versions previous to 5.1.14 are not supported due to incompatible changes in the cluster system tables.

MySQL Cluster Replication: changes in ndb\_apply\_status. Online upgrades from MySQL 5.1.17 and earlier to 5.1.18 and later MySQL 5.1.x releases are not supported for clusters using replication due to incompatible changes in the mysql.ndb\_apply\_status table. (Online upgrades from MySQL 5.1 to MySQL Cluster NDB 6.2 and later are not supported, as discussed elsewhere in this section.) However, it should not be necessary to shut down the cluster entirely, if you follow this modified rolling restart procedure:

- 1. Stop the management server, update the management server software, then start the management server again. For multiple management servers, repeat this step for each management server in turn.
- 2. For each data node in turn: Stop the data node, update the data node daemon (in MySQL Cluster NDB 7.0 and later, this can be either ndbd or ndbmtd) with the new version, then restart the data node. It should not be necessary to use --initial when restarting any of the data nodes after updating the software.
- 3. Stop *all* SQL nodes. Upgrade the existing MySQL server installations to the new version on all SQL nodes, then restart them. It is not necessary to start them one at a time after upgrading the MySQL server software, but *there must be a time when none of them is running before starting any of them again using the 5.1.18 (or later) mysqld.* Otherwise—due to the fact that mysql.ndb\_apply\_status uses the NDB storage engine and is thus shared between all SQL nodes—there may be conflicts between the old and new versions of the table on different SQL nodes.

You can find more information about the changes to ndb\_apply\_status in Section 8.4, "MySQL Cluster Replication Schema and Tables".

#### Note

You should upgrade the MySQL Cluster software on each node using the same method by which it was originally installed. See Chapter 4, *MySQL Cluster Installation and Upgrades*, for more information.

As with any other MySQL Cluster version upgrade, you should also update the MySQL Cluster management client (ndb\_mgm) and other MySQL Cluster client programs such as ndb\_config and ndb\_error\_reporter; however, this does not have to be done in any particular order.

**Internal column specification changes.** The internal specifications for columns in NDBCLUSTER tables changed in MySQL 5.1.18 to enable compatibility with later MySQL Cluster releases that permit online adding and dropping of columns. *This change is not backward-compatible with earlier MySQL versions*.

To make tables created in MySQL 5.1.17 and earlier compatible with online adding and dropping of columns (available beginning with beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2—see ALTER TABLE Syntax, for more information), it is necessary to force MySQL 5.1.18 and later to convert the tables to the new format by following this procedure:

- 1. Back up all NDBCLUSTER tables.
- 2. Upgrade the MySQL Cluster software on all data, management, and SQL nodes.
- 3. Shut down the cluster completely (this includes all data, management, and API or SQL nodes).
- 4. Restart the cluster, starting all data nodes with the --initial option (to clear and rebuild the data node file systems).
- 5. Restore the NDBCLUSTER tables from backup.

It is not necessary to follow this procedure for NDBCLUSTER tables created in MySQL 5.1.18 and later; such tables are already compatible with online adding and dropping of columns (as implemented beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2).

To minimize possible later difficulties, it is strongly advised that the procedure outlined above be followed as soon as possible after to upgrading from MySQL 5.1.17 or earlier to MySQL 5.1.18 or later.

Information about how this change effects users of MySQL Cluster NDB 6.x and 7.x is provided later in this section.

**MySQL Cluster not supported in MySQL Server 5.1.24 and later.** MySQL Cluster is not supported in standard MySQL 5.1 releases beginning with MySQL 5.1.24. If you are using MySQL Cluster in a standard MySQL 5.1 release, you should upgrade to the most recent MySQL Cluster NDB 7.0 or MySQL Cluster NDB 7.1 release.

96

# Chapter 5 Configuration of MySQL Cluster NDB 6.1-7.1

### **Table of Contents**

5.1 Quick Test Setup of MySQL Cluster	. 97
5.2 MySQL Cluster Configuration Files	
5.2.1 MySQL Cluster Configuration: Basic Example	101
5.2.2 Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later	104
5.2.3 MySQL Cluster Connection Strings	108
5.2.4 Defining Computers in a MySQL Cluster	109
5.2.5 Defining a MySQL Cluster Management Server	110
5.2.6 Defining MySQL Cluster Data Nodes	115
5.2.7 Defining SQL and Other API Nodes in a MySQL Cluster	169
5.2.8 MySQL Cluster TCP/IP Connections	175
5.2.9 MySQL Cluster TCP/IP Connections Using Direct Connections	178
5.2.10 MySQL Cluster Shared-Memory Connections	179
5.2.11 SCI Transport Connections in MySQL Cluster	181
5.2.12 Configuring MySQL Cluster Parameters for Local Checkpoints	184
5.2.13 Configuring MySQL Cluster Send Buffer Parameters	185
5.3 Overview of MySQL Cluster Configuration Parameters	
5.3.1 MySQL Cluster Data Node Configuration Parameters	
5.3.2 MySQL Cluster Management Node Configuration Parameters	202
5.3.3 MySQL Cluster SQL Node and API Node Configuration Parameters	204
5.3.4 Other MySQL Cluster Configuration Parameters	207
5.4 MySQL Server Options and Variables for MySQL Cluster	
5.4.1 MySQL Cluster mysqld Option and Variable Reference	
5.4.2 MySQL Server Options for MySQL Cluster	
5.4.3 MySQL Cluster System Variables	
5.4.4 MySQL Cluster Status Variables	
5.5 Using High-Speed Interconnects with MySQL Cluster	275
5.5.1 Configuring MySQL Cluster to use SCI Sockets	
5.5.2 MySQL Cluster Interconnects and Performance	276

A MySQL server that is part of a MySQL Cluster differs in one chief respect from a normal (nonclustered) MySQL server, in that it employs the NDB storage engine. This engine is also referred to sometimes as NDBCLUSTER, although NDB is preferred.

To avoid unnecessary allocation of resources, the server is configured by default with the NDB storage engine disabled. To enable NDB, you must modify the server's my.cnf configuration file, or start the server with the --ndbcluster option.

This MySQL server is a part of the cluster, so it also must know how to access an management node to obtain the cluster configuration data. The default behavior is to look for the management node on localhost. However, should you need to specify that its location is elsewhere, this can be done in my.cnf, or with the mysql client. Before the NDB storage engine can be used, at least one management node must be operational, as well as any desired data nodes.

For more information about --ndbcluster and other mysqld options specific to MySQL Cluster, see Section 5.4.2, "MySQL Server Options for MySQL Cluster".

For information about installing MySQL Cluster, see Chapter 4, MySQL Cluster Installation and Upgrades.

## 5.1 Quick Test Setup of MySQL Cluster

To familiarize you with the basics, we will describe the simplest possible configuration for a functional MySQL Cluster. After this, you should be able to design your desired setup from the information provided in the other relevant sections of this chapter.

First, you need to create a configuration directory such as /var/lib/mysql-cluster, by executing the following command as the system root user:

```
shell> mkdir /var/lib/mysql-cluster
```

In this directory, create a file named config.ini that contains the following information. Substitute appropriate values for HostName and DataDir as necessary for your system.

```
# file "config.ini" - showing minimal setup consisting of 1 data node,
# 1 management server, and 3 SQL nodes.
# The empty default sections are not required, and are shown only for
# the sake of completeness.
# Data nodes must provide a hostname but SQL nodes are not required
# to do so.
# If you do not know the hostname for your machine, use localhost.
# The DataDir parameter also has a default value, but it is recommended to
# set it explicitly.
# Note: [db], [api], and [mgm] are aliases for [ndbd], [mysqld], and [ndb_mgmd],
# respectively. [db] is deprecated and should not be used in new installations.
[ndbd default]
NoOfReplicas= 1
[mysqld default]
[ndb mgmd default]
[tcp default]
[ndb_mgmd]
HostName= myhost.example.com
[ndbd]
HostName= myhost.example.com
DataDir= /var/lib/mysql-cluster
[mysqld]
[mysqld]
[mysqld]
```

You can now start the ndb\_mgmd management server. By default, it attempts to read the config.ini file in its current working directory, so change location into the directory where the file is located and then invoke ndb mgmd:

```
shell> cd /var/lib/mysql-cluster
shell> ndb_mgmd
```

Then start a single data node by running ndbd:

```
shell> ndbd
```

For command-line options which can be used when starting ndbd, see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

By default, ndbd looks for the management server at localhost on port 1186.

#### Note

If you have installed MySQL from a binary tarball, you will need to specify the path of the ndb\_mgmd and ndbd servers explicitly. (Normally, these will be found in / usr/local/mysql/bin.)

Finally, change location to the MySQL data directory (usually /var/lib/mysql or /usr/local/mysql/data), and make sure that the my.cnf file contains the option necessary to enable the NDB storage engine:

```
[mysqld]
ndbcluster
```

You can now start the MySQL server as usual:

```
shell> mysqld_safe --user=mysql &
```

Wait a moment to make sure the MySQL server is running properly. If you see the notice mysql ended, check the server's .err file to find out what went wrong.

If all has gone well so far, you now can start using the cluster. Connect to the server and verify that the NDB storage engine is enabled:

The row numbers shown in the preceding example output may be different from those shown on your system, depending upon how your server is configured.

Try to create an NDB table:

```
shell> mysql
mysql> USE test;
Database changed
mysql> CREATE TABLE ctest (i INT) ENGINE=NDBCLUSTER;
Query OK, 0 rows affected (0.09 sec)
mysql> SHOW CREATE TABLE ctest \G
*******************************
    Table: ctest
Create Table: CREATE TABLE `ctest` (
    `i` int(11) default NULL
) ENGINE=ndbcluster DEFAULT CHARSET=latin1
1 row in set (0.00 sec)
```

To check that your nodes were set up properly, start the management client:

```
shell> ndb_mgm
```

Use the SHOW command from within the management client to obtain a report on the cluster's status:

```
ndb_mgm> SHOW
Cluster Configuration
```

```
[ndbd(NDB)] 1 node(s)
id=2 @127.0.0.1 (Version: 5.1.73-ndb-7.1.33, Nodegroup: 0, *)
[ndb_mgmd(MGM)] 1 node(s)
id=1 @127.0.0.1 (Version: 5.1.73-ndb-7.1.33)
[mysqld(API)] 3 node(s)
id=3 @127.0.0.1 (Version: 5.1.73-ndb-7.1.33)
id=4 (not connected, accepting connect from any host)
id=5 (not connected, accepting connect from any host)
```

At this point, you have successfully set up a working MySQL Cluster. You can now store data in the cluster by using any table created with ENGINE=NDBCLUSTER or its alias ENGINE=NDB.

## 5.2 MySQL Cluster Configuration Files

Configuring MySQL Cluster requires working with two files:

- my.cnf: Specifies options for all MySQL Cluster executables. This file, with which you should be familiar with from previous work with MySQL, must be accessible by each executable running in the cluster.
- config.ini: This file, sometimes known as the *global configuration file*, is read only by the MySQL Cluster management server, which then distributes the information contained therein to all processes participating in the cluster. config.ini contains a description of each node involved in the cluster. This includes configuration parameters for data nodes and configuration parameters for connections between all nodes in the cluster. For a quick reference to the sections that can appear in this file, and what sorts of configuration parameters may be placed in each section, see Sections of the config.ini File.

**Caching of configuration data.** Beginning with MySQL Cluster NDB 6.4.0, MySQL Cluster uses *stateful configuration*. The global configuration file is no longer read every time the management server is restarted. Instead, the management server caches the configuration the first time it is started, and thereafter, the global configuration file is read only when one of the following items is true:

- The management server is started using the --initial option. In this case, the global configuration file is re-read, any existing cache files are deleted, and the management server creates a new configuration cache.
- The management server is started using the --reload option. In this case, the management server compares its cache with the global configuration file. If they differ, the management server creates a new configuration cache; any existing configuration cache is preserved, but not used. If the management server's cache and the global configuration file contain the same configuration data, then the existing cache is used, and no new cache is created.
- The management server is started using a --config-cache option. Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option can be used to force the management server to bypass configuration caching altogether. In this case, the management server ignores any configuration files that may be present, always reading its configuration data from the config.ini file instead.
- No configuration cache is found. In this case, the management server reads the global configuration file and creates a cache containing the same configuration data as found in the file.

**Configuration cache files.** Beginning with MySQL Cluster 6.4.0, the management server by default creates configuration cache files in a directory named mysql-cluster in the MySQL installation directory. (If you build MySQL Cluster from source on a Unix system, the default location is /usr/local/mysql-cluster.) This can be overridden at runtime by starting the management server with the --configdir option. Configuration cache files are binary files named according to the pattern  $ndb\_node\_id\_config.bin.seq\_id$ , where  $node\_id$  is the management server's node ID in the cluster, and  $seq\_id$  is a cache identifier. Cache files are numbered sequentially using  $seq\_id$ , in the

order in which they are created. The management server uses the latest cache file as determined by the  $seq\_id$ .

# **Note**

It is possible to roll back to a previous configuration by deleting later configuration cache files, or by renaming an earlier cache file so that it has a higher  $seq\_id$ . However, since configuration cache files are written in a binary format, you should not attempt to edit their contents by hand.

For more information about the --configdir, --config-cache, --initial, and --reload options for the MySQL Cluster management server, see Section 6.4, "ndb\_mgmd — The MySQL Cluster Management Server Daemon".

We are continuously making improvements in Cluster configuration and attempting to simplify this process. Although we strive to maintain backward compatibility, there may be times when introduce an incompatible change. In such cases we will try to let Cluster users know in advance if a change is not backward compatible. If you find such a change and we have not documented it, please report it in the MySQL bugs database using the instructions given in How to Report Bugs or Problems.

# 5.2.1 MySQL Cluster Configuration: Basic Example

To support MySQL Cluster, you will need to update my.cnf as shown in the following example. You may also specify these parameters on the command line when invoking the executables.

#### Note

The options shown here should not be confused with those that are used in config.ini global configuration files. Global configuration options are discussed later in this section.

```
# my.cnf
# example additions to my.cnf for MySQL Cluster
# (valid in MySQL 5.1)
# enable ndbcluster storage engine, and provide connection string for
# management server host (default port is 1186)
[mysqld]
ndbcluster
ndb-connectstring=ndb_mgmd.mysql.com
# provide connection string for management server host (default port: 1186)
[ndbd]
connect-string=ndb_mgmd.mysql.com
# provide connection string for management server host (default port: 1186)
[ndb_mgm]
connect-string=ndb_mgmd.mysql.com
# provide location of cluster configuration file
[ndb_mgmd]
config-file=/etc/config.ini
```

(For more information on connection strings, see Section 5.2.3, "MySQL Cluster Connection Strings".)

```
# my.cnf
# example additions to my.cnf for MySQL Cluster
# (will work on all versions)
# enable ndbcluster storage engine, and provide connection string for management
# server host to the default port 1186
[mysqld]
ndbcluster
ndb-connectstring=ndb_mgmd.mysql.com:1186
```

# **Important**

Once you have started a mysqld process with the NDBCLUSTER and ndb-connectstring parameters in the [mysqld] in the my.cnf file as shown previously, you cannot execute any CREATE TABLE or ALTER TABLE statements without having actually started the cluster. Otherwise, these statements will fail with an error. This is by design.

You may also use a separate [mysql\_cluster] section in the cluster my.cnf file for settings to be read and used by all executables:

```
# cluster-specific settings
[mysql_cluster]
ndb-connectstring=ndb_mgmd.mysql.com:1186
```

For additional NDB variables that can be set in the my. cnf file, see Section 5.4.3, "MySQL Cluster System Variables".

The MySQL Cluster global configuration file is by convention named <code>config.ini</code> (but this is not required). It is read by <code>ndb\_mgmd</code> at startup and can be placed in any location that can be read by it. The location and name of the configuration are specified using <code>--config-file=path\_name</code> with <code>ndb\_mgmd</code> on the command line. Beginning with MySQL Cluster NDB 6.4.0, this option has no default value, and is ignored if <code>ndb\_mgmd</code> uses the configuration cache.

The global configuration file for MySQL Cluster uses INI format, which consists of sections preceded by section headings (surrounded by square brackets), followed by the appropriate parameter names and values. One deviation from the standard INI format is that the parameter name and value can be separated by a colon (":") as well as the equal sign ("="); however, the equal sign is preferred. Another deviation is that sections are not uniquely identified by section name. Instead, unique sections (such as two different nodes of the same type) are identified by a unique ID specified as a parameter within the section.

Default values are defined for most parameters, and can also be specified in config.ini. (Prior to MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, there was no default value for NoOfReplicas, which always had to be specified explicitly in the [ndbd default] section. Beginning with versions just stated, the default value is 2, which is the recommended setting in most common usage scenarios.) To create a default value section, simply add the word default to the section name. For example, an [ndbd] section contains parameters that apply to a particular data node, whereas an [ndbd default] section contains parameters that apply to all data nodes. Suppose that all data nodes should use the same data memory size. To configure them all, create an [ndbd default] section that contains a DataMemory line to specify the data memory size.

The global configuration file must define the computers and nodes involved in the cluster and on which computers these nodes are located. An example of a simple configuration file for a cluster consisting of one management server, two data nodes and two SQL nodes is shown here:

```
# file "config.ini" - 2 data nodes and 2 SQL nodes
# This file is placed in the startup directory of ndb_mgmd (the
# management server)
# The first SQL node can be started from any host. The second
# can be started only on the host mysqld_5.mysql.com
[ndbd default]
NoOfReplicas= 2
DataDir= /var/lib/mysql-cluster
[ndb_mgmd]
Hostname= ndb_mgmd.mysql.com
DataDir= /var/lib/mysql-cluster
[ndbd]
HostName= ndbd_2.mysql.com
```

```
[ndbd]
HostName= ndbd_3.mysql.com
[mysqld]
[mysqld]
HostName= mysqld_5.mysql.com
```

#### Note

The preceding example is intended as a minimal starting configuration for purposes of familiarization with MySQL Cluster, and is almost certain not to be sufficient for production settings. See Section 5.2.2, "Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later", which provides more complete example starting configurations for use with MySQL Cluster NDB 6.2 and newer versions of MySQL Cluster.

Each node has its own section in the config.ini file. For example, this cluster has two data nodes, so the preceding configuration file contains two [ndbd] sections defining these nodes.

#### Note

Do not place comments on the same line as a section heading in the config.ini file; this causes the management server not to start because it cannot parse the configuration file in such cases.

# Sections of the config.ini File

There are six different sections that you can use in the config.ini configuration file, as described in the following list:

- [computer]: Defines cluster hosts. This is not required to configure a viable MySQL Cluster, but be may used as a convenience when setting up a large cluster. See Section 5.2.4, "Defining Computers in a MySQL Cluster", for more information.
- [ndbd]: Defines a cluster data node (ndbd process). See Section 5.2.6, "Defining MySQL Cluster Data Nodes", for details.
- [mysqld]: Defines the cluster's MySQL server nodes (also called SQL or API nodes). For a discussion of SQL node configuration, see Section 5.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".
- [mgm] or [ndb\_mgmd]: Defines a cluster management server (MGM) node. For information concerning the configuration of management nodes, see Section 5.2.5, "Defining a MySQL Cluster Management Server".
- [tcp]: Defines a TCP/IP connection between cluster nodes, with TCP/IP being the default connection protocol. Normally, [tcp] or [tcp default] sections are not required to set up a MySQL Cluster, as the cluster handles this automatically; however, it may be necessary in some situations to override the defaults provided by the cluster. See Section 5.2.8, "MySQL Cluster TCP/IP Connections", for information about available TCP/IP configuration parameters and how to use them. (You may also find Section 5.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections" to be of interest in some cases.)
- [shm]: Defines shared-memory connections between nodes. In MySQL 5.1, it is enabled by default, but should still be considered experimental. For a discussion of SHM interconnects, see Section 5.2.10, "MySQL Cluster Shared-Memory Connections".
- [sci]:Defines <u>Scalable Coherent Interface</u> connections between cluster data nodes. Such connections require software which, while freely available, is not part of the MySQL Cluster distribution, as well as specialized hardware. See <u>Section 5.2.11</u>, "SCI Transport Connections in MySQL Cluster" for detailed information about SCI interconnects.

You can define default values for each section. All Cluster parameter names are case-insensitive, which differs from parameters specified in my.cnf or my.ini files.

# 5.2.2 Recommended Starting Configurations for MySQL Cluster NDB 6.2 and Later

Achieving the best performance from a MySQL Cluster depends on a number of factors including the following:

- · MySQL Cluster software version
- · Numbers of data nodes and SQL nodes
- Hardware
- Operating system
- · Amount of data to be stored
- · Size and type of load under which the cluster is to operate

Therefore, obtaining an optimum configuration is likely to be an iterative process, the outcome of which can vary widely with the specifics of each MySQL Cluster deployment. Changes in configuration are also likely to be indicated when changes are made in the platform on which the cluster is run, or in applications that use the MySQL Cluster's data. For these reasons, it is not possible to offer a single configuration that is ideal for all usage scenarios. However, in this section, we provide recommended base configurations for MySQL Cluster NDB 6.2 and 6.3 that can serve as reasonable starting points.

**Starting configuration for MySQL Cluster NDB 6.2.** The following is a recommended starting point for configuring a cluster running MySQL Cluster NDB 6.2.

```
# TCP PARAMETERS
[tcp default]
SendBufferMemory=2M
ReceiveBufferMemory=2M
# Increasing the sizes of these 2 buffers beyond the default values
# helps prevent bottlenecks due to slow disk I/O.
# MANAGEMENT NODE PARAMETERS
[ndb_mgmd default]
DataDir=path/to/management/server/data/directory
# It is possible to use a different data directory for each management
# server, but for ease of administration it is preferable to be
# consistent.
[ndb mqmd]
HostName=management-server-1-hostname
# NodeId=management-server-1-nodeid
[ndb_mgmd]
HostName=management-server-2-hostname
# Using 2 management servers helps guarantee that there is always an
# arbitrator in the event of network partitioning, and so is
# recommended for high availability. Each management server must be
# identified by a HostName. You may for the sake of convenience specify
# a node ID for any management server, although one will be allocated
# for it automatically; if you do so, it must be in the range 1-255
# inclusive and must be unique among all IDs specified for cluster
# DATA NODE PARAMETERS
[ndbd default]
NoOfReplicas=2
# Using 2 replicas is recommended to guarantee availability of data;
# using only 1 replica does not provide any redundancy, which means
# that the failure of a single data node causes the entire cluster to
```

```
# shut down. We do not recommend using more than 2 replicas, since 2 is
# sufficient to provide high availability, and we do not currently test
# with greater values for this parameter.
LockPagesInMainMemory=1
# On Linux and Solaris systems, setting this parameter locks data node
# processes into memory. Doing so prevents them from swapping to disk,
# which can severely degrade cluster performance.
DataMemory=3072M
IndexMemory=384M
# The values provided for DataMemory and IndexMemory assume 4 GB RAM
# per data node. However, for best results, you should first calculate
# the memory that would be used based on the data you actually plan to
# store (you may find the ndb_size.pl utility helpful in estimating
# this), then allow an extra 20% over the calculated values. Naturally,
# you should ensure that each data node host has at least as much
# physical memory as the sum of these two values.
# ODirect=1
# Enabling this parameter causes NDBCLUSTER to try using O_DIRECT
# writes for local checkpoints and redo logs; this can reduce load on
# CPUs. We recommend doing so when using MySQL Cluster NDB 6.2.3 or
# newer on systems running Linux kernel 2.6 or later.
NoOfFragmentLogFiles=300
DataDir=path/to/data/node/data/directory
MaxNoOfConcurrentOperations=100000
TimeBetweenGlobalCheckpoints=1000
TimeBetweenEpochs=200
DiskCheckpointSpeed=10M
DiskCheckpointSpeedInRestart=100M
RedoBuffer=32M
# MaxNoOfLocalScans=64
MaxNoOfTables=1024
MaxNoOfOrderedIndexes=256
[ndbd]
HostName=data-node-A-hostname
# NodeId=data-node-A-nodeid
[ndbd]
HostName=data-node-B-hostname
# NodeId=data-node-B-nodeid
# You must have an [ndbd] section for every data node in the cluster;
# each of these sections must include a HostName. Each section may
# optionally include an Id for convenience, but in most cases, it is
# sufficient to allow the cluster to allocate node IDs dynamically. If
# you do specify the node ID for a data node, it must be in the range 1
# to 48 inclusive and must be unique among all IDs specified for
# cluster nodes.
# SQL NODE / API NODE PARAMETERS
[mysqld]
# HostName=SQL-node-1-hostname
# NodeId=sql-node-A-nodeid
[mysqld]
[mysqld]
# Each API or SQL node that connects to the cluster requires a [mysqld]
# or [api] section of its own. Each such section defines a connection
# "slot"; you should have at least as many of these sections in the
# config.ini file as the total number of API nodes and SQL nodes that
# you wish to have connected to the cluster at any given time. There is
# no performance or other penalty for having extra slots available in
# case you find later that you want or need more API or SQL nodes to
# connect to the cluster at the same time.
# If no HostName is specified for a given [mysqld] or [api] section,
# then any API or SQL node may use that slot to connect to the
# cluster. You may wish to use an explicit HostName for one connection slot
# to guarantee that an API or SQL node from that host can always
# connect to the cluster. If you wish to prevent API or SQL nodes from
# connecting from other than a desired host or hosts, then use a
# HostName for every [mysqld] or [api] section in the config.ini file.
# You can if you wish define a node ID (Id parameter) for any API or
```

```
# SQL node, but this is not necessary; if you do so, it must be in the
# range 1 to 255 inclusive and must be unique among all IDs specified
# for cluster nodes.
```

**Starting configuration for MySQL Cluster NDB 6.3.** The following is a recommended starting point for configuring a cluster running MySQL Cluster NDB 6.3. It is similar to the recommendation for MySQL Cluster NDB 6.2, with the addition of parameters for better control of NDBCLUSTER process threads.

```
# TCP PARAMETERS
[tcp default]
SendBufferMemory=2M
ReceiveBufferMemory=2M
# Increasing the sizes of these 2 buffers beyond the default values
# helps prevent bottlenecks due to slow disk I/O.
# MANAGEMENT NODE PARAMETERS
[ndb_mgmd default]
DataDir=path/to/management/server/data/directory
# It is possible to use a different data directory for each management
# server, but for ease of administration it is preferable to be
# consistent.
[ndb_mgmd]
HostName=management-server-A-hostname
# NodeId=management-server-A-nodeid
[ndb_mgmd]
HostName=management-server-B-hostname
# NodeId=management-server-B-nodeid
# Using 2 management servers helps guarantee that there is always an
# arbitrator in the event of network partitioning, and so is
# recommended for high availability. Each management server must be
# identified by a HostName. You may for the sake of convenience specify
# a NodeId for any management server, although one will be allocated
# for it automatically; if you do so, it must be in the range 1-255
# inclusive and must be unique among all IDs specified for cluster
# nodes.
# DATA NODE PARAMETERS
[ndbd default]
NoOfReplicas=2
# Using 2 replicas is recommended to guarantee availability of data;
# using only 1 replica does not provide any redundancy, which means
# that the failure of a single data node causes the entire cluster to
# shut down. We do not recommend using more than 2 replicas, since 2 is
# sufficient to provide high availability, and we do not currently test
# with greater values for this parameter.
LockPagesInMainMemory=1
# On Linux and Solaris systems, setting this parameter locks data node
# processes into memory. Doing so prevents them from swapping to disk,
# which can severely degrade cluster performance.
DataMemory=3072M
IndexMemory=384M
\# The values provided for DataMemory and IndexMemory assume 4 GB RAM
# per data node. However, for best results, you should first calculate
# the memory that would be used based on the data you actually plan to
# store (you may find the ndb_size.pl utility helpful in estimating
# this), then allow an extra 20% over the calculated values. Naturally,
# you should ensure that each data node host has at least as much
# physical memory as the sum of these two values.
# ODirect=1
# Enabling this parameter causes NDBCLUSTER to try using O_DIRECT
# writes for local checkpoints and redo logs; this can reduce load on
# CPUs. We recommend doing so when using MySQL Cluster NDB 6.2.3 or
# newer on systems running Linux kernel 2.6 or later.
NoOfFragmentLogFiles=300
DataDir=path/to/data/node/data/directory
MaxNoOfConcurrentOperations=100000
SchedulerSpinTimer=400
SchedulerExecutionTimer=100
```

```
RealTimeScheduler=1
# Setting these parameters allows you to take advantage of real-time scheduling
# of NDB threads (introduced in MySQL Cluster NDB 6.3.4) to achieve increased
# throughput when using ndbd. They are not needed when using ndbmtd; in
# particular, you should not set RealTimeScheduler for ndbmtd data nodes.
TimeBetweenGlobalCheckpoints=1000
TimeBetweenEpochs=200
DiskCheckpointSpeed=10M
DiskCheckpointSpeedInRestart=100M
RedoBuffer=32M
# CompressedLCP=1
# CompressedBackup=1
# Enabling CompressedLCP and CompressedBackup causes, respectively, local
checkpoint files and backup files to be compressed, which can result in a space
savings of up to 50% over noncompressed LCPs and backups.
# MaxNoOfLocalScans=64
MaxNoOfTables=1024
MaxNoOfOrderedIndexes=256
[ndbd]
HostName=data-node-A-hostname
# NodeId=data-node-A-nodeid
LockExecuteThreadToCPU=1
LockMaintThreadsToCPU=0
# On systems with multiple CPUs, these parameters can be used to lock NDBCLUSTER
# threads to specific CPUs
[ndbd]
HostName=data-node-B-hostname
# NodeId=data-node-B-nodeid
LockExecuteThreadToCPU=1
LockMaintThreadsToCPU=0
# You must have an [ndbd] section for every data node in the cluster;
# each of these sections must include a HostName. Each section may
# optionally include a NodeId for convenience, but in most cases, it is
# sufficient to allow the cluster to allocate node IDs dynamically. If
# you do specify the node ID for a data node, it must be in the range 1
# to 48 inclusive and must be unique among all IDs specified for
# cluster nodes.
# SQL NODE / API NODE PARAMETERS
[mysqld]
# HostName=sql-node-A-hostname
# NodeId=sql-node-A-nodeid
[mysqld]
[mysqld]
# Each API or SQL node that connects to the cluster requires a [mysqld]
# or [api] section of its own. Each such section defines a connection
# "slot"; you should have at least as many of these sections in the
# config.ini file as the total number of API nodes and SQL nodes that
# you wish to have connected to the cluster at any given time. There is
# no performance or other penalty for having extra slots available in
# case you find later that you want or need more API or SQL nodes to
# connect to the cluster at the same time.
# If no HostName is specified for a given [mysqld] or [api] section,
# then any API or SQL node may use that slot to connect to the
# cluster. You may wish to use an explicit HostName for one connection slot
# to quarantee that an API or SQL node from that host can always
# connect to the cluster. If you wish to prevent API or SQL nodes from
# connecting from other than a desired host or hosts, then use a
# HostName for every [mysqld] or [api] section in the config.ini file.
# You can if you wish define a node ID (NodeId parameter) for any API or
# SQL node, but this is not necessary; if you do so, it must be in the
# range 1 to 255 inclusive and must be unique among all IDs specified
# for cluster nodes.
```

**Recommended my.cnf options for SQL nodes.** MySQL Servers acting as MySQL Cluster SQL nodes must always be started with the --ndbcluster and --ndb-connectstring options, either

on the command line or in my.cnf. In addition, set the following options for all mysqld processes in the cluster, unless your setup requires otherwise:

- --ndb-use-exact-count=0
- --ndb-index-stat-enable=0
- --ndb-force-send=1
- --engine-condition-pushdown=1

# 5.2.3 MySQL Cluster Connection Strings

With the exception of the MySQL Cluster management server (ndb\_mgmd), each node that is part of a MySQL Cluster requires a *connection string* that points to the management server's location. This connection string is used in establishing a connection to the management server as well as in performing other tasks depending on the node's role in the cluster. The syntax for a connection string is as follows:

```
[nodeid=node_id, ]host-definition[, host-definition[, ...]]
host-definition:
   host_name[:port_number]
```

node\_id is an integer greater than or equal to 1 which identifies a node in config.ini. host\_name is a string representing a valid Internet host name or IP address. port\_number is an integer referring to a TCP/IP port number.

```
example 1 (long): "nodeid=2,myhost1:1100,myhost2:1100,192.168.0.3:1200"
example 2 (short): "myhost1"
```

localhost:1186 is used as the default connection string value if none is provided. If <code>port\_num</code> is omitted from the connection string, the default port is 1186. This port should always be available on the network because it has been assigned by IANA for this purpose (see <a href="http://www.iana.org/assignments/port-numbers">http://www.iana.org/assignments/port-numbers</a> for details).

By listing multiple host definitions, it is possible to designate several redundant management servers. A MySQL Cluster data or API node attempts to contact successive management servers on each host in the order specified, until a successful connection has been established.

Beginning with MySQL Cluster NDB 6.3.19, it is also possible in a connection string to specify one or more bind addresses to be used by nodes having multiple network interfaces for connecting to management servers. A bind address consists of a hostname or network address and an optional port number. This enhanced syntax for connection strings is shown here:

```
[nodeid=node_id, ]
    [bind-address=host-definition, ]
    host-definition[; bind-address=host-definition]
    host-definition[; bind-address=host-definition]
    [, ...]]
host-definition:
    host_name[:port_number]
```

If a single bind address is used in the connection string *prior* to specifying any management hosts, then this address is used as the default for connecting to any of them (unless overridden for a given management server; see later in this section for an example). For example, the following connection string causes the node to use 192.168.178.242 regardless of the management server to which it connects:

```
bind-address=192.168.178.242, poseidon:1186, perch:1186
```

If a bind address is specified *following* a management host definition, then it is used only for connecting to that management node. Consider the following connection string:

```
poseidon:1186;bind-address=localhost, perch:1186;bind-address=192.168.178.242
```

In this case, the node uses localhost to connect to the management server running on the host named poseidon and 192.168.178.242 to connect to the management server running on the host named perch.

You can specify a default bind address and then override this default for one or more specific management hosts. In the following example, localhost is used for connecting to the management server running on host poseidon; since 192.168.178.242 is specified first (before any management server definitions), it is the default bind address and so is used for connecting to the management servers on hosts perch and orca:

```
bind-address=192.168.178.242,poseidon:1186;bind-address=localhost,perch:1186,orca:2200
```

There are a number of different ways to specify the connection string:

- Each executable has its own command-line option which enables specifying the management server at startup. (See the documentation for the respective executable.)
- It is also possible to set the connection string for all nodes in the cluster at once by placing it in a [mysql\_cluster] section in the management server's my.cnf file.
- For backward compatibility, two other options are available, using the same syntax:
  - 1. Set the NDB CONNECTSTRING environment variable to contain the connection string.
  - 2. Write the connection string for each executable into a text file named Ndb.cfg and place this file in the executable's startup directory.

However, these are now deprecated and should not be used for new installations.

The recommended method for specifying the connection string is to set it on the command line or in the my.cnf file for each executable.

Previous to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the maximum length of a connection string was 1024 characters.

# 5.2.4 Defining Computers in a MySQL Cluster

The [computer] section has no real significance other than serving as a way to avoid the need of defining host names for each node in the system. All parameters mentioned here are required.

• Id

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	string	[none]		S

This is a unique identifier, used to refer to the host computer elsewhere in the configuration file.

# **Important**

The computer ID is *not* the same as the node ID used for a management, API, or data node. Unlike the case with node IDs, you cannot use NodeId in place of Id in the [computer] section of the config.ini file.

#### • HostName

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

This is the computer's hostname or IP address.

# 5.2.5 Defining a MySQL Cluster Management Server

The [ndb\_mgmd] section is used to configure the behavior of the management server. If multiple management servers are employed, you can specify parameters common to all of them in an [ndb\_mgmd default] section. [mgm] and [mgm default] are older aliases for these, supported for backward compatibility.

All parameters in the following list are optional and assume their default values if omitted.

#### **Note**

If neither the ExecuteOnComputer nor the HostName parameter is present, the default value localhost will be assumed for both.

## • Id

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 63	S
NDB 6.1.1	unsigned	[none]	1 - 255	S

Each node in the cluster has a unique identity. For a management node, this is represented by an integer value in the range 1 to 63 inclusive (previous to MySQL Cluster NDB 6.1.1), or in the range 1 to 255 inclusive (MySQL Cluster NDB 6.1.1 and later). This ID is used by all internal cluster messages for addressing the node, and so must be unique for each MySQL Cluster node, regardless of the type of node.

# Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for management nodes (and API nodes) to values greater than 48.

The use of the Id parameter for identifying management nodes is deprecated in favor of NodeId beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it now generates a warning.

# NodeId

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 63	S

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	unsigned	[none]	1 - 255	S

Each node in the cluster has a unique identity. For a management node, this is represented by an integer value in the range 1 to 63 inclusive (previous to MySQL Cluster NDB 6.1.1), or in the range 1 to 255 inclusive (MySQL Cluster NDB 6.1.1 and later). This ID is used by all internal cluster messages for addressing the node, and so must be unique for each MySQL Cluster node, regardless of the type of node.

#### Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for management nodes (and API nodes) to values greater than 48.

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

# • ExecuteOnComputer

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name	[none]		S

This refers to the Id set for one of the computers defined in a [computer] section of the config.ini file.

## • PortNumber

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	1186	0 - 64K	S

This is the port number on which the management server listens for configuration requests and management commands.

## • HostName

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

Specifying this parameter defines the hostname of the computer on which the management node is to reside. To specify a hostname other than localhost, either this parameter or ExecuteOnComputer is required.

# • LogDestination

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	{CONSOLE  SYSLOG FILE}	[see text]		S

This parameter specifies where to send cluster logging information. There are three options in this regard—CONSOLE, SYSLOG, and FILE—with FILE being the default:

• CONSOLE outputs the log to stdout:

CONSOLE

• SYSLOG sends the log to a syslog facility, possible values being one of auth, authpriv, cron, daemon, ftp, kern, lpr, mail, news, syslog, user, uucp, local0, local1, local2, local3, local4, local5, local6, or local7.

#### Note

Not every facility is necessarily supported by every operating system.

SYSLOG: facility=syslog

- FILE pipes the cluster log output to a regular file on the same machine. The following values can be specified:
  - filename: The name of the log file.

Prior to MySQL Cluster NDB 7.0.43 and MySQL Cluster NDB 7.1.23, the log file's default name, used if FILE was specified without also setting filename, was logger.log. Beginning with MySQL Cluster NDB 7.0.43 and MySQL Cluster NDB 7.1.23, the default log file name used in such cases is ndb\_nodeid\_cluster.log.

- maxsize: The maximum size (in bytes) to which the file can grow before logging rolls over to a new file. When this occurs, the old log file is renamed by appending .N to the file name, where N is the next number not yet used with this name.
- maxfiles: The maximum number of log files.

```
FILE:filename=cluster.log,maxsize=1000000,maxfiles=6
```

The default value for the FILE parameter is

FILE: filename=ndb\_node\_id\_cluster.log, maxsize=1000000, maxfiles=6, where node\_id is the ID of the node.

It is possible to specify multiple log destinations separated by semicolons as shown here:

CONSOLE; SYSLOG: facility=local0; FILE: filename=/var/log/mgmd

• ArbitrationRank

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	0-2	1	0 - 2	S

This parameter is used to define which nodes can act as arbitrators. Only management nodes and SQL nodes can be arbitrators. ArbitrationRank can take one of the following values:

- 0: The node will never be used as an arbitrator.
- 1: The node has high priority; that is, it will be preferred as an arbitrator over low-priority nodes.

• 2: Indicates a low-priority node which be used as an arbitrator only if a node with a higher priority is not available for that purpose.

Normally, the management server should be configured as an arbitrator by setting its ArbitrationRank to 1 (the default for management nodes) and those for all SQL nodes to 0 (the default for SQL nodes).

Beginning with MySQL 5.1.16 and MySQL Cluster NDB 6.1.3, it is possible to disable arbitration completely by setting ArbitrationRank to 0 on all management and SQL nodes. In MySQL Cluster NDB 7.0.7 and later releases, you can also control arbitration by overriding this parameter; to do this, set the Arbitration parameter in the [ndbd default] section of the config.ini global configuration file.

# • ArbitrationDelay

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	_	0 - 4294967039	S
			(0xFFFFFEFF)	

An integer value which causes the management server's responses to arbitration requests to be delayed by that number of milliseconds. By default, this value is 0; it is normally not necessary to change it.

#### • DataDir

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	path			S

This specifies the directory where output files from the management server will be placed. These files include cluster log files, process output files, and the daemon's process ID (PID) file. (For log files, this location can be overridden by setting the FILE parameter for LogDestination as discussed previously in this section.)

The default value for this parameter is the directory in which ndb\_mgmd is located.

# • PortNumberStats

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	0 - 64K	S

This parameter specifies the port number used to obtain statistical information from a MySQL Cluster management server. It has no default value.

#### Wan

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	boolean	false	true, false	S

Use WAN TCP setting as default. Introduced in MySQL Cluster NDB 6.1.1.

# HeartbeatThreadPriority

Beginning with MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2, it is possible to use this parameter to set the scheduling policy and priority of heartbeat threads for management and API nodes.

The syntax for setting this parameter is shown here:

```
HeartbeatThreadPriority = policy[, priority]
policy:
{FIFO | RR}
```

When setting this parameter, you must specify a policy. This is one of FIFO (first in, first out) or RR (round robin). The policy value is followed optionally by the priority (an integer).

## • ExtraSendBufferMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.39	bytes	0	0 - 32G	S

This parameter specifies the amount of transporter send buffer memory to allocate in addition to any that has been set using TotalSendBufferMemory, SendBufferMemory, or both.

This parameter was added in MySQL Cluster NDB 7.0.39 and MySQL Cluster NDB 7.1.28. (Bug #14555359)

# • TotalSendBufferMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	bytes	256K	0 - 4294967039	S
			(0xFFFFEFF)	

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039. For more detailed information about the behavior and use of TotalSendBufferMemory and configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

## • HeartbeatIntervalMgmdMgmd

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.40	milliseconds	1500	100 - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.29	milliseconds	1500	100 - 4294967039 (0xFFFFFEFF)	S

Specify the interval between heartbeat messages used to determine whether another management node is on contact with this one. The management node waits after 3 of these intervals to declare the connection dead; thus, the default setting of 1500 milliseconds causes the management node to wait for approximately 1600 ms before timing out.

This parameter was added in MySQL Cluster NDB 7.0.40 and MySQL Cluster NDB 7.1.29. (Bug #16426805)

## Note

After making changes in a management node's configuration, it is necessary to perform a rolling restart of the cluster for the new configuration to take effect.

To add new management servers to a running MySQL Cluster, it is also necessary to perform a rolling restart of all cluster nodes after modifying any existing config.ini files. For more information about issues arising when using multiple management nodes, see Section 3.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

# 5.2.6 Defining MySQL Cluster Data Nodes

The [ndbd] and [ndbd default] sections are used to configure the behavior of the cluster's data nodes.

[ndbd] and [ndbd\_default] are always used as the section names whether you are using ndbd or (in MySQL Cluster NDB 6.4.0 and later) ndbmtd binaries for the data node processes.

There are many parameters which control buffer sizes, pool sizes, timeouts, and so forth. The only mandatory parameters are:

- Either ExecuteOnComputer or HostName, which must be defined in the local [ndbd] section.
- The parameter NoOfReplicas, which must be defined in the [ndbd default] section, as it is common to all Cluster data nodes.

# Note

It is no longer strictly necessary to set NoOfReplicas starting with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, where it acquires a default value (2). However, it remains good practice to set it explicitly.

Most data node parameters are set in the <code>[ndbd default]</code> section. Only those parameters explicitly stated as being able to set local values are permitted to be changed in the <code>[ndbd]</code> section. Where present, <code>HostName</code>, <code>NodeId</code> and <code>ExecuteOnComputer</code> must be defined in the local <code>[ndbd]</code> section, and not in any other section of <code>config.ini</code>. In other words, settings for these parameters are specific to one data node.

For those parameters affecting memory usage or buffer sizes, it is possible to use K, M, or G as a suffix to indicate units of 1024, 1024×1024, or 1024×1024×1024. (For example, 100K means 100 × 1024 = 102400.) Parameter names and values are currently case-sensitive.

Information about configuration parameters specific to MySQL Cluster Disk Data tables can be found later in this section (see Disk Data Configuration Parameters).

Beginning with MySQL Cluster NDB 6.4.0, all of these parameters also apply to ndbmtd (the multi-threaded version of ndbd). Two additional data node configuration parameters —MaxNoOfExecutionThreads and ThreadConfig—apply to ndbmtd only; these have no effect when used with ndbd. For more information, see Multi-Threading Configuration Parameters (ndbmtd). See also Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

**Identifying data nodes.** The NodeId or Id value (that is, the data node identifier) can be allocated on the command line when the node is started or in the configuration file.

## • Id

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 48	S

A unique node ID is used as the node's address for all cluster internal messages. For data nodes, this is an integer in the range 1 to 48 inclusive. Each node in the cluster must have a unique identifier.

NodeId is the preferred parameter name to use when identifying data nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

## • NodeId

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 48	S

A unique node ID is used as the node's address for all cluster internal messages. For data nodes, this is an integer in the range 1 to 48 inclusive. Each node in the cluster must have a unique identifier.

NodeId is the preferred parameter name to use when identifying data nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

# • ExecuteOnComputer

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name	[none]		S

This refers to the Id set for one of the computers defined in a [computer] section.

# • HostName

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	localhost		S

Specifying this parameter defines the hostname of the computer on which the data node is to reside. To specify a hostname other than localhost, either this parameter or ExecuteOnComputer is required.

#### ServerPort

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 64K	S

Each node in the cluster uses a port to connect to other nodes. By default, this port is allocated dynamically in such a way as to ensure that no two nodes on the same host computer receive the same port number, so it should normally not be necessary to specify a value for this parameter.

However, if you need to be able to open specific ports in a firewall to permit communication between data nodes and API nodes (including SQL nodes), you can set this parameter to the number of the desired port in an [ndbd] section or (if you need to do this for multiple data nodes) the [ndbd]

default] section of the config.ini file, and then open the port having that number for incoming connections from SQL nodes, API nodes, or both.

#### Note

Connections from data nodes to management nodes is done using the ndb\_mgmd management port (the management server's PortNumber; see Section 5.2.5, "Defining a MySQL Cluster Management Server") so outgoing connections to that port from any data nodes should always be permitted.

## • TcpBind\_INADDR\_ANY

Setting this parameter to TRUE or 1 binds IP\_ADDR\_ANY so that connections can be made from anywhere (for autogenerated connections). The default is FALSE (0).

This parameter was added in MySQL Cluster NDB 6.2.0.

#### NodeGroup

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0		[none]	0 - 65536	S

This parameter can be used to assign a data node to a specific node group. It is read only when the cluster is started for the first time, and cannot be used to reassign a data node to a different node group online. It is generally not desirable to use this parameter in the <code>[ndbd default]</code> section of the <code>config.ini</code> file, and care must be taken not to assign nodes to node groups in such a way that an invalid numbers of nodes are assigned to any node groups.

The NodeGroup parameter is chiefly intended for use in adding a new node group to a running MySQL Cluster without having to perform a rolling restart. For this purpose, you should set it to 65536 (the maximum value). You are not required to set a NodeGroup value for all cluster data nodes, only for those nodes which are to be started and added to the cluster as a new node group at a later time. For more information, see Section 7.13.3, "Adding MySQL Cluster Data Nodes Online: Detailed Example".

This parameter was added in MySQL Cluster NDB 6.4.0.

## NoOfReplicas

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	[none]	1 - 4	S
NDB 6.3.25	integer	2	1 - 4	S
NDB 7.0.6	integer	2	1 - 4	S

This global parameter can be set only in the [ndbd default] section, and defines the number of replicas for each table stored in the cluster. This parameter also specifies the size of node groups. A node group is a set of nodes all storing the same information.

Node groups are formed implicitly. The first node group is formed by the set of data nodes with the lowest node IDs, the next node group by the set of the next lowest node identities, and so on. By way of example, assume that we have 4 data nodes and that NoOfReplicas is set to 2. The four data nodes have node IDs 2, 3, 4 and 5. Then the first node group is formed from nodes 2 and 3, and the second node group by nodes 4 and 5. It is important to configure the cluster in such a manner that nodes in the same node groups are not placed on the same computer because a single hardware failure would cause the entire cluster to fail.

If no node IDs are provided, the order of the data nodes will be the determining factor for the node group. Whether or not explicit assignments are made, they can be viewed in the output of the management client's SHOW command.

Prior to MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, there was no default value for NoOfReplicas; beginning with these versions, the default value is 2, which is the recommended setting in most common usage scenarios. (Bug #44746)

The maximum possible value is 4; currently, only the values 1 and 2 are actually supported.

# **Important**

Setting NoOfReplicas to 1 means that there is only a single copy of all Cluster data; in this case, the loss of a single data node causes the cluster to fail because there are no additional copies of the data stored by that node.

The value for this parameter must divide evenly into the number of data nodes in the cluster. For example, if there are two data nodes, then NoOfReplicas must be equal to either 1 or 2, since 2/3 and 2/4 both yield fractional values; if there are four data nodes, then NoOfReplicas must be equal to 1, 2, or 4.

#### • DataDir

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	path			S

This parameter specifies the directory where trace files, log files, pid files and error logs are placed.

The default is the data node process working directory.

# FileSystemPath

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	path	DataDir		S

This parameter specifies the directory where all files created for metadata, REDO logs, UNDO logs (for Disk Data tables), and data files are placed. The default is the directory specified by DataDir.

#### Note

This directory must exist before the ndbd process is initiated.

The recommended directory hierarchy for MySQL Cluster includes /var/lib/mysql-cluster, under which a directory for the node's file system is created. The name of this subdirectory contains the node ID. For example, if the node ID is 2, this subdirectory is named ndb\_2\_fs.

# • BackupDataDir

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	path	[see text]		S

This parameter specifies the directory in which backups are placed.

# **Important**

The string '/BACKUP' is always appended to this value. For example, if you set the value of BackupDataDir to /var/lib/cluster-data, then all backups are stored under /var/lib/cluster-data/BACKUP. This also means that the effective default backup location is the directory named BACKUP under the location specified by the FileSystemPath parameter.

# Data Memory, Index Memory, and String Memory

DataMemory and IndexMemory are [ndbd] parameters specifying the size of memory segments used to store the actual records and their indexes. In setting values for these, it is important to understand how DataMemory and IndexMemory are used, as they usually need to be updated to reflect actual usage by the cluster:

# DataMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	80M	1M - 1024G	S

This parameter defines the amount of space (in bytes) available for storing database records. The entire amount specified by this value is allocated in memory, so it is extremely important that the machine has sufficient physical memory to accommodate it.

The memory allocated by <code>DataMemory</code> is used to store both the actual records and indexes. There is a 16-byte overhead on each record; an additional amount for each record is incurred because it is stored in a 32KB page with 128 byte page overhead (see below). There is also a small amount wasted per page due to the fact that each record is stored in only one page.

For variable-size table attributes in MySQL 5.1, the data is stored on separate data pages, allocated from <code>DataMemory</code>. Variable-length records use a fixed-size part with an extra overhead of 4 bytes to reference the variable-size part. The variable-size part has 2 bytes overhead plus 2 bytes per attribute.

Prior to MySQL Cluster NDB 7.0, the maximum record size was 8052 bytes; in MySQL Cluster NDB 7.0 and later, it is 14000 bytes.

The memory space defined by <code>DataMemory</code> is also used to store ordered indexes, which use about 10 bytes per record. Each table row is represented in the ordered index. A common error among users is to assume that all indexes are stored in the memory allocated by <code>IndexMemory</code>, but this is not the case: Only primary key and unique hash indexes use this memory; ordered indexes use the memory allocated by <code>DataMemory</code>. However, creating a primary key or unique hash index also creates an ordered index on the same keys, unless you specify <code>USING HASH</code> in the index creation statement. This can be verified by running <code>ndb\_desc -d db\_name table\_name</code> in the management client.

Currently, MySQL Cluster can use a maximum of 512 MB for hash indexes per partition, which means in some cases it is possible to get Table is full errors in MySQL client applications even when ndb\_mgm -e "ALL REPORT MEMORYUSAGE" shows significant free DataMemory. This can also pose a problem with data node restarts on nodes that are heavily loaded with data. You can force NDB to create extra partitions for MySQL Cluster tables and thus have more memory available for hash indexes by using the MAX\_ROWS option for CREATE TABLE. In general, setting MAX\_ROWS to twice the number of rows that you expect to store in the table should be sufficient. In MySQL Cluster 7.1.18 and later, you can also use the MinFreePct [122] configuration parameter to help avoid problems with node restarts. (Bug #13436216)

The memory space allocated by <code>DataMemory</code> consists of 32KB pages, which are allocated to table fragments. Each table is normally partitioned into the same number of fragments as there are data nodes in the cluster. Thus, for each node, there are the same number of fragments as are set in <code>NoOfReplicas</code>.

In addition, due to the way in which new pages are allocated when the capacity of the current page is exhausted, there is an additional overhead of approximately 18.75%. When more DataMemory is required, more than one new page is allocated, according to the following formula:

```
number of new pages = FLOOR(number of current pages × 0.1875) + 1
```

For example, if 15 pages are currently allocated to a given table and an insert to this table requires additional storage space, the number of new pages allocated to the table is  $FLOOR(15 \times 0.1875) + 1 = FLOOR(2.8125) + 1 = 2 + 1 = 3$ . Now 15 + 3 = 18 memory pages are allocated to the table. When the last of these 18 pages becomes full,  $FLOOR(18 \times 0.1875) + 1 = FLOOR(3.3750) + 1 = 3 + 1 = 4$  new pages are allocated, so the total number of pages allocated to the table is now 22.

#### Note

The "18.75% + 1" overhead is no longer required beginning with MySQL Cluster NDB 6.2.3 and MySQL Cluster NDB 6.3.0.

Once a page has been allocated, it is currently not possible to return it to the pool of free pages, except by deleting the table. (This also means that <code>DataMemory</code> pages, once allocated to a given table, cannot be used by other tables.) Performing a node recovery also compresses the partition because all records are inserted into empty partitions from other live nodes.

The <code>DataMemory</code> memory space also contains UNDO information: For each update, a copy of the unaltered record is allocated in the <code>DataMemory</code>. There is also a reference to each copy in the ordered table indexes. Unique hash indexes are updated only when the unique index columns are updated, in which case a new entry in the index table is inserted and the old entry is deleted upon commit. For this reason, it is also necessary to allocate enough memory to handle the largest transactions performed by applications using the cluster. In any case, performing a few large transactions holds no advantage over using many smaller ones, for the following reasons:

- · Large transactions are not any faster than smaller ones
- Large transactions increase the number of operations that are lost and must be repeated in event of transaction failure
- · Large transactions use more memory

The default value for <code>DataMemory</code> is 80MB; the minimum is 1MB. There is no maximum size, but in reality the maximum size has to be adapted so that the process does not start swapping when the limit is reached. This limit is determined by the amount of physical RAM available on the machine and by the amount of memory that the operating system may commit to any one process. 32-bit operating systems are generally limited to 2–4GB per process; 64-bit operating systems can use more. For large databases, it may be preferable to use a 64-bit operating system for this reason.

# • IndexMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	18M	1M - 1T	S

This parameter controls the amount of storage used for hash indexes in MySQL Cluster. Hash indexes are always used for primary key indexes, unique indexes, and unique constraints. When defining a primary key or a unique index, two indexes are created, one of which is a hash index used for all tuple accesses as well as lock handling. This index is also used to enforce unique constraints.

You can estimate the size of a hash index using this formula:

fragments is the number of fragments, replicas is the number of replicas (normally 2), and rows is the number of rows. If a table has one million rows, 8 fragments, and 2 replicas, the expected index memory usage is calculated as shown here:

```
((8 * 32K) + (1000000 * 18)) * 2 = ((8 * 32768) + (1000000 * 18)) * 2
= (262144 + 18000000) * 2
= 18262144 * 2 = 36524288 bytes = ~35MB
```

The default value for IndexMemory is 18MB. The minimum is 1MB.

• StringMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	% or bytes	0	0 - 4294967039 (0xFFFFEFF)	S
MySQL 5.1.32	% or bytes	25	0 - 4294967039 (0xFFFFEFF)	S
MySQL 5.1.6	% or bytes	5	0 - 4294967039 (0xFFFFEFF)	S
NDB 7.2.1	% or bytes	25	0 - 4294967039 (0xFFFFEFF)	S

This parameter determines how much memory is allocated for strings such as table names, and is specified in an <code>[ndbd]</code> or <code>[ndbd]</code> default] section of the <code>config.ini</code> file. A value between 0 and 100 inclusive is interpreted as a percent of the maximum default value, which is calculated based on a number of factors including the number of tables, maximum table name size, maximum size of <code>.FRM</code> files, <code>MaxNoOfTriggers</code>, maximum column name size, and maximum default column value.

A value greater than 100 is interpreted as a number of bytes.

The default value is 25—that is, 25 percent of the default maximum. (Previously, prior to MySQL Cluster NDB 6.2.18, MySQL Cluster NDB 6.3.24, and MySQL Cluster NDB 7.0.5, the default value was 5; prior to MySQL 5.1.6, the default was 0.)

Under most circumstances, the default value should be sufficient, but when you have a great many Cluster tables (1000 or more), it is possible to get Error 773 Out of string memory, please modify StringMemory config parameter: Permanent error: Schema error, in which case you should increase this value. 25 (25 percent) is not excessive, and should prevent this error from recurring in all but the most extreme conditions.

The following example illustrates how memory is used for a table. Consider this table definition:

```
CREATE TABLE example (
a INT NOT NULL,
b INT NOT NULL,
c INT NOT NULL,
PRIMARY KEY(a),
UNIQUE(b)
) ENGINE=NDBCLUSTER;
```

For each record, there are 12 bytes of data plus 12 bytes overhead. Having no nullable columns saves 4 bytes of overhead. In addition, we have two ordered indexes on columns a and b consuming roughly 10 bytes each per record. There is a primary key hash index on the base table using roughly 29 bytes per record. The unique constraint is implemented by a separate table with b as primary key and a as a column. This other table consumes an additional 29 bytes of index memory per record in the example table as well 8 bytes of record data plus 12 bytes of overhead.

Thus, for one million records, we need 58MB for index memory to handle the hash indexes for the primary key and the unique constraint. We also need 64MB for the records of the base table and the unique index table, plus the two ordered index tables.

You can see that hash indexes takes up a fair amount of memory space; however, they provide very fast access to the data in return. They are also used in MySQL Cluster to handle uniqueness constraints.

Currently, the only partitioning algorithm is hashing and ordered indexes are local to each node. Thus, ordered indexes cannot be used to handle uniqueness constraints in the general case.

An important point for both IndexMemory and DataMemory is that the total database size is the sum of all data memory and all index memory for each node group. Each node group is used to store replicated information, so if there are four nodes with two replicas, there will be two node groups. Thus, the total data memory available is 2 x DataMemory for each data node.

It is highly recommended that <code>DataMemory</code> and <code>IndexMemory</code> be set to the same values for all nodes. Data distribution is even over all nodes in the cluster, so the maximum amount of space available for any node can be no greater than that of the smallest node in the cluster.

DataMemory and IndexMemory can be changed, but decreasing either of these can be risky; doing so can easily lead to a node or even an entire MySQL Cluster that is unable to restart due to there being insufficient memory space. Increasing these values should be acceptable, but it is recommended that such upgrades are performed in the same manner as a software upgrade, beginning with an update of the configuration file, and then restarting the management server followed by restarting each data node in turn.

Beginning with MySQL Cluster NDB 7.0.29 and MySQL Cluster NDB 7.1.18, a proportion (5% by default) of data node resources including <code>DataMemory</code> and <code>IndexMemory</code> is kept in reserve to insure that the data node does not exhaust its memory when performing a restart. This can be adjusted using the <code>MinFreePct</code> [122] data node configuration parameter (default 5) introduced in the same versions of MySQL Cluster.

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.29	unsigned	5	0 - 100	S
NDB 7.1.18	unsigned	5	0 - 100	S
NDB 7.2.3	unsigned	5	0 - 100	S

Updates do not increase the amount of index memory used. Inserts take effect immediately; however, rows are not actually deleted until the transaction is committed.

**Transaction parameters.** The next few [ndbd] parameters that we discuss are important because they affect the number of parallel transactions and the sizes of transactions that can be handled by the system. MaxNoOfConcurrentTransactions sets the number of parallel transactions possible in a node. MaxNoOfConcurrentOperations sets the number of records that can be in update phase or locked simultaneously.

Both of these parameters (especially MaxNoOfConcurrentOperations) are likely targets for users setting specific values and not using the default value. The default value is set for systems using small transactions, to ensure that these do not use excessive memory.

MaxDMLOperationsPerTransaction, added in MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.15, sets the maximum number of DML operations that can be performed in a given transaction.

• MaxNoOfConcurrentTransactions

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	4096	32 - 4294967039	S
			(0xFFFFEFF)	

Each cluster data node requires a transaction record for each active transaction in the cluster. The task of coordinating transactions is distributed among all of the data nodes. The total number of transaction records in the cluster is the number of transactions in any given node times the number of nodes in the cluster.

Transaction records are allocated to individual MySQL servers. Each connection to an SQL node requires at least one transaction record, plus an additional transaction object per table accessed by that connection. This means that a reasonable minimum for this parameter is

```
MaxNoOfConcurrentTransactions =
  (maximum number of tables accessed in any single transaction + 1)
  * number of cluster SQL nodes
```

Suppose that there are 10 SQL nodes using the cluster. A single join involving 10 tables requires 11 transaction records; if there are 10 such joins in a transaction, then 10 \* 11 = 110 transaction records are required for this transaction, per SQL node, or 110 \* 10 = 1100 transaction records total. Each data node can be expected to handle TotalNoOfConcurrentTransactions / number of data nodes. For a MySQL Cluster having 4 data nodes, this would mean setting MaxNoOfConcurrentTransactions on each data node to 1100 / 4 = 275. In addition, you should provide for failure recovery by ensuring that a single node group can accommodate all concurrent transactions; in other words, that each data node's MaxNoOfConcurrentTransactions is sufficient to cover a number of transaction equal to TotalNoOfConcurrentTransactions / number of node groups. If this cluster has a single node group, then MaxNoOfConcurrentTransactions should be set to 1100 (the same as the total number of concurrent transactions for the entire cluster).

In addition, each transaction involves at least one operation; for this reason, the value set for MaxNoOfConcurrentTransactions should always be no more than the value of MaxNoOfConcurrentOperations.

This parameter must be set to the same value for all cluster data nodes. This is due to the fact that, when a data node fails, the oldest surviving node re-creates the transaction state of all transactions that were ongoing in the failed node.

It is possible to change this value using a rolling restart, but the amount of traffic on the cluster must be such that no more transactions occur than the lower of the old and new levels while this is taking place.

The default value is 4096.

• MaxNoOfConcurrentOperations

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	32K	32 - 4294967039 (0xFFFFFEFF)	S

It is a good idea to adjust the value of this parameter according to the size and number of transactions. When performing transactions which involve only a few operations and records, the default value for this parameter is usually sufficient. Performing large transactions involving many records usually requires that you increase its value.

Records are kept for each transaction updating cluster data, both in the transaction coordinator and in the nodes where the actual updates are performed. These records contain state information needed to find UNDO records for rollback, lock queues, and other purposes.

This parameter should be set to the number of records to be updated simultaneously in transactions, divided by the number of cluster data nodes. For example, in a cluster which has four data nodes and which is expected to handle one million concurrent updates using transactions, you should set this value to 1000000 / 4 = 250000. To help provide resiliency against failures, it is suggested that you set this parameter to a value that is high enough to permit an individual data node to handle the load for its node group. In other words, you should set the value equal to total number of concurrent operations / number of node groups. (In the case where there is a single node group, this is the same as the total number of concurrent operations for the entire cluster.)

Because each transaction always involves at least one operation, the value of MaxNoOfConcurrentOperations should always be greater than or equal to the value of MaxNoOfConcurrentTransactions.

Read queries which set locks also cause operation records to be created. Some extra space is allocated within individual nodes to accommodate cases where the distribution is not perfect over the nodes.

When queries make use of the unique hash index, there are actually two operation records used per record in the transaction. The first record represents the read in the index table and the second handles the operation on the base table.

The default value is 32768.

This parameter actually handles two values that can be configured separately. The first of these specifies how many operation records are to be placed with the transaction coordinator. The second part specifies how many operation records are to be local to the database.

A very large transaction performed on an eight-node cluster requires as many operation records in the transaction coordinator as there are reads, updates, and deletes involved in the transaction. However, the operation records of the are spread over all eight nodes. Thus, if it is necessary to configure the system for one very large transaction, it is a good idea to configure the two parts separately.

MaxNoOfConcurrentOperations will always be used to calculate the number of operation records in the transaction coordinator portion of the node.

It is also important to have an idea of the memory requirements for operation records. These consume about 1KB per record.

MaxNoOfLocalOperations

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	UNDEFINED	32 - 4294967039 (0xFFFFFEFF)	S

By default, this parameter is calculated as 1.1 x MaxNoOfConcurrentOperations. This fits systems with many simultaneous transactions, none of them being very large. If there is a need to handle one very large transaction at a time and there are many nodes, it is a good idea to override the default value by explicitly specifying this parameter.

## MaxDMLOperationsPerTransaction

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.26	operations (DML)	4294967295	32 - 4294967295	S
NDB 7.1.15	operations (DML)	4294967295	32 - 4294967295	S

Added in MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.15, this parameter limits the size of a transaction. The transaction is aborted if it requires more than this many DML operations. The minimum number of operations per transaction is 32; however, you can set <a href="MaxDMLOperationsPerTransaction">MaxDMLOperationsPerTransaction</a> to 0 to disable any limitation on the number of DML operations per transaction. The maximum (and default) is 4294967295.

**Transaction temporary storage.** The next set of [ndbd] parameters is used to determine temporary storage when executing a statement that is part of a Cluster transaction. All records are released when the statement is completed and the cluster is waiting for the commit or rollback.

The default values for these parameters are adequate for most situations. However, users with a need to support transactions involving large numbers of rows or operations may need to increase these values to enable better parallelism in the system, whereas users whose applications require relatively small transactions can decrease the values to save memory.

# • MaxNoOfConcurrentIndexOperations

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	_	0 - 4294967039 (0xFFFFFEFF)	S

For queries using a unique hash index, another temporary set of operation records is used during a query's execution phase. This parameter sets the size of that pool of records. Thus, this record is allocated only while executing a part of a query. As soon as this part has been executed, the record is released. The state needed to handle aborts and commits is handled by the normal operation records, where the pool size is set by the parameter MaxNoOfConcurrentOperations.

The default value of this parameter is 8192. Only in rare cases of extremely high parallelism using unique hash indexes should it be necessary to increase this value. Using a smaller value is possible and can save memory if the DBA is certain that a high degree of parallelism is not required for the cluster.

# • MaxNoOfFiredTriggers

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer		0 - 4294967039	S
			(0xFFFFFEFF)	

The default value of MaxNoOfFiredTriggers is 4000, which is sufficient for most situations. In some cases it can even be decreased if the DBA feels certain the need for parallelism in the cluster is not high.

A record is created when an operation is performed that affects a unique hash index. Inserting or deleting a record in a table with unique hash indexes or updating a column that is part of a unique hash index fires an insert or a delete in the index table. The resulting record is used to represent this index table operation while waiting for the original operation that fired it to complete. This operation is short-lived but can still require a large number of records in its pool for situations with many parallel write operations on a base table containing a set of unique hash indexes.

# • TransactionBufferMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	1M	1K - 4294967039 (0xFFFFFEFF)	S

The memory affected by this parameter is used for tracking operations fired when updating index tables and reading unique indexes. This memory is used to store the key and column information for these operations. It is only very rarely that the value for this parameter needs to be altered from the default.

The default value for TransactionBufferMemory is 1MB.

Normal read and write operations use a similar buffer, whose usage is even more short-lived. The compile-time parameter ZATTRBUF\_FILESIZE (found in ndb/src/kernel/blocks/Dbtc/Dbtc.hpp) set to 4000 x 128 bytes (500KB). A similar buffer for key information, ZDATABUF\_FILESIZE (also in Dbtc.hpp) contains 4000 x 16 = 62.5KB of buffer space. Dbtc is the module that handles transaction coordination.

Scans and buffering. There are additional [ndbd] parameters in the Dblqh module (in ndb/src/kernel/blocks/Dblqh/Dblqh.hpp) that affect reads and updates. These include ZATTRINBUF\_FILESIZE, set by default to 10000 x 128 bytes (1250KB) and ZDATABUF\_FILE\_SIZE, set by default to 10000\*16 bytes (roughly 156KB) of buffer space. To date, there have been neither any reports from users nor any results from our own extensive tests suggesting that either of these compile-time limits should be increased.

## • MaxNoOfConcurrentScans

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	256	2 - 500	S

This parameter is used to control the number of parallel scans that can be performed in the cluster. Each transaction coordinator can handle the number of parallel scans defined for this parameter. Each scan query is performed by scanning all partitions in parallel. Each partition scan uses a scan record in the node where the partition is located, the number of records being the value of this parameter times the number of nodes. The cluster should be able to sustain MaxNoOfConcurrentScans scans concurrently from all nodes in the cluster.

Scans are actually performed in two cases. The first of these cases occurs when no hash or ordered indexes exists to handle the query, in which case the query is executed by performing a full table scan. The second case is encountered when there is no hash index to support the query but there is an ordered index. Using the ordered index means executing a parallel range scan. The order is kept on the local partitions only, so it is necessary to perform the index scan on all partitions.

The default value of MaxNoOfConcurrentScans is 256. The maximum value is 500.

## • MaxNoOfLocalScans

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	[see text]	32 - 4294967039 (0xFFFFFEFF)	S
NDB 7.2.0	integer	[see text]	32 - 4294967039 (0xFFFFFEFF)	S

Specifies the number of local scan records if many scans are not fully parallelized. In MySQL Cluster NDB 7.2.0 and later, when the number of local scan records is not provided, it is calculated as shown here:

```
4 * MaxNoOfConcurrentScans * [# data nodes] + 2
```

In MySQL Cluster NDB 7.1 and earlier, the default is calculated as the product of MaxNoOfConcurrentScans and the number of data nodes, plus 2. The minimum value is 32.

# • BatchSizePerLocalScan

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	64	1 - 992	S
NDB 7.2.1	integer	256	1 - 992	S

This parameter is used to calculate the number of lock records used to handle concurrent scan operations.

BatchSizePerLocalScan has a strong connection to the BatchSize defined in the SQL nodes.

# • LongMessageBuffer

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	1M	512K - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	4M	512K - 4294967039 (0xFFFFFEFF)	S
NDB 7.2.0	bytes	4M	512K - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.31	bytes	64M	512K - 4294967039 (0xFFFFFEFF)	S

This is an internal buffer used for passing messages within individual nodes and between nodes. In MySQL Cluster NDB 6.4.3 and earlier, the default is 1MB; beginning with MySQL Cluster NDB 7.0.4, this increased to 4MB; the default increased to 64MB in MySQL Cluster NDB 7.1.31.

This parameter seldom needs to be changed from the default. However, when replicating a MySQL Cluster using ndbmtd for the data nodes, you may need to increase this value to 8MB (or possibly more) to prevent data node instability, because ndbmtd uses much more of this resource than ndbd does. Beginning with MySQL Cluster NDB 7.0.13 and MySQL Cluster NDB 7.1.2, this should no longer be necessary when using ndbmtd with MySQL Cluster Replication (Bug #46914).

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.23	bytes	32	1 - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.12	bytes	32	1 - 4294967039 (0xFFFFFEFF)	S
NDB 7.2.0	bytes	256	1 - 4294967039 (0xFFFFFEFF)	S

Beginning with MySQL Cluster NDB 7.0.23 and MySQL Cluster NDB 7.1.12, it is possible to configure the maximum number of parallel scans (TUP scans and TUX scans) allowed before they begin queuing for serial handling. (Previously, the maximum number of parallel scans per fragment was fixed at 32.) You can increase this to take advantage of any unused CPU when performing large number of scans in parallel and improve their performance.

Beginning with MySQL Cluster NDB 7.2.0, the default value for this parameter is increased from 32 to 256.

# **Memory Allocation**

# MaxAllocate [128]

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.19	unsigned	32M	1M - 1G	S
NDB 6.2.3	unsigned	32M	1M - 1G	S
MySQL 5.1.20	unsigned	32M	1M - 1G	S

This is the maximum size of the memory unit to use when allocating memory for tables. In cases where NDB gives Out of memory errors, but it is evident by examining the cluster logs or the output of DUMP 1000 (see DUMP 1000) that all available memory has not yet been used, you can increase the value of this parameter (or MaxNoOfTables, or both) to cause NDB to make sufficient memory available.

This parameter was introduced in MySQL 5.1.20, MySQL Cluster NDB 6.1.12 and MySQL Cluster NDB 6.2.3.

# Hash Map Size

# DefaultHashMapSize [128]

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.38	LDM threads	240	0 - 3840	S
NDB 7.1.27	LDM threads	240	0 - 3840	S

Beginning with MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.26, the size of the table hash maps used by NDB is configurable using this parameter; previously this value was hard-coded. DefaultHashMapSize can take any of three possible values (0, 240, 3840). These values and their effects are described in the following table:

Value	Description / Effect
	Use the lowest value set, if any, for this parameter among all data nodes and API nodes in the cluster; if it is not set on any data or API node, use the default value.

Value	Description / Effect
240	Original hash map size used by default in all MySQL Cluster NDB 7.1 and MySQL Cluster NDB 7.0 (and earlier) releases; effectively the only value prior to versions 7.0.38 and 7.1.26 (when this parameter was introduced).
3840	Larger hash map size available beginning with MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.26

The primary intended use for this parameter is to facilitate upgrades and esecially downgrades between MySQL Cluster NDB 7.1 and later MySQL Cluster versions in which the larger hash map size (3840) is the default; by setting this parameter to 240 prior to performing an upgrade, you can cause the cluster to continue using the smaller size for table hash maps, in which case the tables remain compatible with earlier versions. DefaultHashMapSize can be set for individual data nodes, API nodes, or both, but setting it once only, in the [ndbd default] section of the config.ini file, is the recommended practice. You can also set this parameter to 0, in which case the default value is used.

After increasing this parameter, to have existing tables to take advantage of the new size, you can run ALTER TABLE ... REORGANIZE PARTITION on them, after which they can use the larger hash map size. This is in addition to performing a rolling restart, which makes the larger hash maps available to new tables, but does not enable existing tables to use them.

Decreasing this parameter online after any tables have been created or modified with DefaultHashMapSize equal to 3840 is not currently supported.

**Logging and checkpointing.** The following [ndbd] parameters control log and checkpoint behavior.

• NoOfFragmentLogFiles

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	8	3 - 4294967039 (0xFFFFFEFF)	S
MySQL 5.1.0	integer	16	3 - 4294967039 (0xFFFFFEFF)	S

This parameter sets the number of REDO log files for the node, and thus the amount of space allocated to REDO logging. Because the REDO log files are organized in a ring, it is extremely important that the first and last log files in the set (sometimes referred to as the "head" and "tail" log files, respectively) do not meet. When these approach one another too closely, the node begins aborting all transactions encompassing updates due to a lack of room for new log records.

A REDO log record is not removed until the required number of local checkpoints has been completed since that log record was inserted (prior to MySQL Cluster NDB 6.3.8, this was 3 local checkpoints; in later versions of MySQL Cluster, only 2 local checkpoints are necessary). Checkpointing frequency is determined by its own set of configuration parameters discussed elsewhere in this chapter.

How these parameters interact and proposals for how to configure them are discussed in Section 5.2.12, "Configuring MySQL Cluster Parameters for Local Checkpoints".

The default parameter value is 16, which by default means 16 sets of 4 16MB files for a total of 1024MB. Beginning with MySQL Cluster NDB 6.1.1, the size of the individual log files is configurable using the FragmentLogFileSize parameter. In scenarios requiring a great many updates, the value for NoOfFragmentLogFiles may need to be set as high as 300 or even higher to provide sufficient space for REDO logs.

If the checkpointing is slow and there are so many writes to the database that the log files are full and the log tail cannot be cut without jeopardizing recovery, all updating transactions are aborted with internal error code 410 (Out of log file space temporarily). This condition prevails until a checkpoint has completed and the log tail can be moved forward.

# **Important**

This parameter cannot be changed "on the fly"; you must restart the node using <code>--initial</code>. If you wish to change this value for all data nodes in a running cluster, you can do so using a rolling node restart (using <code>--initial</code> when starting each data node).

# • FragmentLogFileSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.11	bytes	16M	4M - 1G	S

Setting this parameter enables you to control directly the size of redo log files. This can be useful in situations when MySQL Cluster is operating under a high load and it is unable to close fragment log files quickly enough before attempting to open new ones (only 2 fragment log files can be open at one time); increasing the size of the fragment log files gives the cluster more time before having to open each new fragment log file. The default value for this parameter is 16M. FragmentLogFileSize was added in MySQL Cluster NDB 6.1.11.

For more information about fragment log files, see the description for NoOfFragmentLogFiles.

## • InitFragmentLogFiles

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.19	[see values]	SPARSE	SPARSE, FULL	S

By default, fragment log files are created sparsely when performing an initial start of a data node—that is, depending on the operating system and file system in use, not all bytes are necessarily written to disk. Beginning with MySQL Cluster NDB 6.3.19, it is possible to override this behavior and force all bytes to be written regardless of the platform and file system type being used by mean of this parameter.

InitFragmentLogFiles takes one of two values:

- SPARSE. Fragment log files are created sparsely. This is the default value.
- FULL. Force all bytes of the fragment log file to be written to disk.

Depending on your operating system and file system, setting InitFragmentLogFiles=FULL may help eliminate I/O errors on writes to the REDO log.

# • MaxNoOfOpenFiles

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	40	20 - 4294967039 (0xFFFFFEFF)	S
MySQL 5.1.16	unsigned	0	20 - 4294967039 (0xFFFFFEFF)	S

This parameter sets a ceiling on how many internal threads to allocate for open files. *Any situation requiring a change in this parameter should be reported as a bug.* 

The default value is 0. (Prior to MySQL 5.1.16, the default was 40.) However, the minimum value to which this parameter can be set is 20.

## • InitialNoOfOpenFiles

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.9	files		20 - 4294967039	S
			(0xFFFFFEFF)	

This parameter sets the initial number of internal threads to allocate for open files.

The default value is 27.

# MaxNoOfSavedMessages

pe/Units	Default	Range/Values	Restart Type
eger	-		S
_		ger 25	

This parameter sets the maximum number of trace files that are kept before overwriting old ones. Trace files are generated when, for whatever reason, the node crashes.

The default is 25 trace files.

## MaxLCPStartDelay

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.23	seconds	0	0 - 600	S
NDB 6.4.3	seconds	0	0 - 600	S

In parallel data node recovery (supported in MySQL Cluster NDB 6.3.8 and later), only table data is actually copied and synchronized in parallel; synchronization of metadata such as dictionary and checkpoint information is done in a serial fashion. In addition, recovery of dictionary and checkpoint information cannot be executed in parallel with performing of local checkpoints. This means that, when starting or restarting many data nodes concurrently, data nodes may be forced to wait while a local checkpoint is performed, which can result in longer node recovery times.

Beginning with MySQL Cluster NDB 6.3.23 and MySQL Cluster NDB 6.4.3, it is possible to force a delay in the local checkpoint to permit more (and possibly all) data nodes to complete metadata synchronization; once each data node's metadata synchronization is complete, all of the data nodes can recover table data in parallel, even while the local checkpoint is being executed.

To force such a delay, you can set MaxLCPStartDelay, which determines the number of seconds the cluster can wait to begin a local checkpoint while data nodes continue to synchronize metadata. This parameter should be set in the [ndbd default] section of the config.ini file, so that it is the same for all data nodes. The maximum value is 600; the default is 0.

# LcpScanProgressTimeout

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.40	second	60	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.29	second	60	0 - 4294967039 (0xFFFFFEFF)	S

A local checkpoint fragment scan watchdog checks periodically for no progress in each fragment scan performed as part of a local checkpoint, and shuts down the node if there is no progress after a given amount of time has elapsed. Prior to MySQL Cluster NDB 7.0.39 and MySQL Cluster NDB 7.1.29, this interval is always 60 seconds (Bug #16630410). In MySQL Cluster NDB 7.0.39, MySQL Cluster NDB 7.1.29, and later this interval can be set using the LcpScanProgressTimeout data node configuration parameter, which sets the maximum time for which the local checkpoint can be stalled before the LCP fragment scan watchdog shuts down the node.

The default value is 60 seconds (providing compatibility with previous releases). Setting this parameter to 0 disables the LCP fragment scan watchdog altogether.

**Metadata objects.** The next set of [ndbd] parameters defines pool sizes for metadata objects, used to define the maximum number of attributes, tables, indexes, and trigger objects used by indexes, events, and replication between clusters. Note that these act merely as "suggestions" to the cluster, and any that are not specified revert to the default values shown.

# • MaxNoOfAttributes

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	1000	32 - 4294967039 (0xFFFFFEFF)	S

This parameter sets a suggested maximum number of attributes that can be defined in the cluster; like MaxNoOfTables, it is not intended to function as a hard upper limit.

Prior to MySQL Cluster NDB 6.3.45, MySQL Cluster NDB 7.0.26, and MySQL Cluster NDB 7.1.15, this parameter was sometimes treated as a hard limit for certain operations. This caused problems with MySQL Cluster Replication, when it was possible to create more tables than could be replicated, and sometimes led to confusion when it was possible (or not possible, depending on the circumstances) to create more than MaxNoOfAttributes attributes. (Bug #61684)

The default value is 1000, with the minimum possible value being 32. The maximum is 4294967039. Each attribute consumes around 200 bytes of storage per node due to the fact that all metadata is fully replicated on the servers.

When setting MaxNoOfAttributes, it is important to prepare in advance for any ALTER TABLE statements that you might want to perform in the future. This is due to the fact, during the execution of ALTER TABLE on a Cluster table, 3 times the number of attributes as in the original table are used, and a good practice is to permit double this amount. For example, if the MySQL Cluster table having the greatest number of attributes (greatest\_number\_of\_attributes) has 100 attributes, a good starting point for the value of MaxNoOfAttributes would be 6 \* greatest\_number\_of\_attributes = 600.

You should also estimate the average number of attributes per table and multiply this by MaxNoOfTables. If this value is larger than the value obtained in the previous paragraph, you should use the larger value instead.

Assuming that you can create all desired tables without any problems, you should also verify that this number is sufficient by trying an actual ALTER TABLE after configuring the parameter. If this is not successful, increase MaxNoOfAttributes by another multiple of MaxNoOfTables and test it again.

## • MaxNoOfTables

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	128	8 - 20320	S

A table object is allocated for each table and for each unique hash index in the cluster. This parameter sets a suggested maximum number of table objects for the cluster as a whole; like MaxNoOfAttributes, it is not intended to function as a hard upper limit.

Prior to MySQL Cluster NDB 6.3.45, MySQL Cluster NDB 7.0.26, and MySQL Cluster NDB 7.1.15, this parameter was sometimes treated as a hard limit for certain operations. This caused problems with MySQL Cluster Replication, when it was possible to create more tables than could be replicated, and sometimes led to confusion when it was possible (or not possible, depending on the circumstances) to create more than MaxNoOfTables tables.

For each attribute that has a BLOB data type an extra table is used to store most of the BLOB data. These tables also must be taken into account when defining the total number of tables.

The default value of this parameter is 128. The minimum is 8 and the maximum is 20320. Each table object consumes approximately 20KB per node.

## Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not exceed 2<sup>32</sup> - 2 (4294967294).

# • MaxNoOfOrderedIndexes

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	_	0 - 4294967039 (0xFFFFFEFF)	S

For each ordered index in the cluster, an object is allocated describing what is being indexed and its storage segments. By default, each index so defined also defines an ordered index. Each unique index and primary key has both an ordered index and a hash index. MaxNoOfOrderedIndexes sets the total number of ordered indexes that can be in use in the system at any one time.

The default value of this parameter is 128. Each index object consumes approximately 10KB of data per node.

#### Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not exceed 2<sup>32</sup> - 2 (4294967294).

# MaxNoOfUniqueHashIndexes

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	_	0 - 4294967039	S
			(0xFFFFFEFF)	

For each unique index that is not a primary key, a special table is allocated that maps the unique key to the primary key of the indexed table. By default, an ordered index is also defined for each unique index. To prevent this, you must specify the USING HASH option when defining the unique index.

The default value is 64. Each index consumes approximately 15KB per node.

## Note

The sum of MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes must not exceed 2<sup>32</sup> - 2 (4294967294).

## • MaxNoOfTriggers

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	768	0 - 4294967039 (0xFFFFFEFF)	S

Internal update, insert, and delete triggers are allocated for each unique hash index. (This means that three triggers are created for each unique hash index.) However, an *ordered* index requires only a single trigger object. Backups also use three trigger objects for each normal table in the cluster.

Replication between clusters also makes use of internal triggers.

This parameter sets the maximum number of trigger objects in the cluster.

The default value is 768.

# • MaxNoOfIndexes

This parameter is deprecated. You should use MaxNoOfOrderedIndexes and MaxNoOfUniqueHashIndexes instead.

This parameter is used only by unique hash indexes. There needs to be one record in this pool for each unique hash index defined in the cluster.

The default value of this parameter is 128.

# • MaxNoOfSubscriptions

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.10	unsigned	0	0 - 4294967039 (0xFFFFFEFF)	S
NDB 6.3.7	unsigned	0	0 - 4294967039 (0xFFFFEFF)	S

Each NDB table in a MySQL Cluster requires a subscription in the NDB kernel. For some NDB API applications, it may be necessary or desirable to change this parameter, which became available in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7. However, for normal usage with MySQL servers acting as SQL nodes, there is not any need to do so.

The default value for MaxNoOfSubscriptions is 0, which is treated as equal to MaxNoOfTables. Each subscription consumes 108 bytes.

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.10	unsigned	0	0 - 4294967039 (0xFFFFFEFF)	S
NDB 6.3.7	unsigned	0	0 - 4294967039 (0xFFFFFEFF)	S

This parameter, added in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7, is of interest only when using MySQL Cluster Replication. The default value is 0, which is treated as 2 \* MaxNoOfTables; that is, there is one subscription per NDB table for each of two MySQL servers (one acting as the replication master and the other as the slave). Each subscriber uses 16 bytes of memory.

When using circular replication, multi-master replication, and other replication setups involving more than 2 MySQL servers, you should increase this parameter to the number of mysqld processes included in replication (this is often, but not always, the same as the number of clusters). For example, if you have a circular replication setup using three MySQL Clusters, with one mysqld attached to each cluster, and each of these mysqld processes acts as a master and as a slave, you should set MaxNoOfSubscribers equal to 3 \* MaxNoOfTables.

For more information, see Chapter 8, MySQL Cluster Replication.

• MaxNoOfConcurrentSubOperations

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.10	unsigned	256	0 - 4294967039 (0xFFFFFEFF)	S
NDB 6.3.7	unsigned	256	0 - 4294967039 (0xFFFFFEFF)	S

This parameter sets a ceiling on the number of operations that can be performed by all API nodes in the cluster at one time. The default value (256) is sufficient for normal operations, and might need to be adjusted only in scenarios where there are a great many API nodes each performing a high volume of operations concurrently.

This parameter was added in MySQL Cluster NDB 6.2.10 and MySQL Cluster NDB 6.3.7.

**Boolean parameters.** The behavior of data nodes is also affected by a set of [ndbd] parameters taking on boolean values. These parameters can each be specified as TRUE by setting them equal to 1 or Y, and as FALSE by setting them equal to 0 or N.

LateAlloc

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	numeric	1	0 - 1	S

Allocate memory for this data node after a connection to the management server has been established. Enabled by default.

Added in MySQL Cluster NDB 6.4.0.

LockPagesInMainMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	0	0 - 2	S
MySQL 5.1.0	true false (1 0)	0	0 - 1	S
MySQL 5.1.15	numeric	0	0 - 2	S

For a number of operating systems, including Solaris and Linux, it is possible to lock a process into memory and so avoid any swapping to disk. This can be used to help guarantee the cluster's real-time characteristics.

Beginning with MySQL 5.1.15 and MySQL Cluster NDB 6.1.1, this parameter takes one of the integer values 0, 1, or 2, which act as follows:

- 0: Disables locking. This is the default value.
- 1: Performs the lock after allocating memory for the process.
- 2: Performs the lock before memory for the process is allocated.

Previously, this parameter was a Boolean. 0 or false was the default setting, and disabled locking. 1 or true enabled locking of the process after its memory was allocated.

# **Important**

Beginning with MySQL 5.1.15 and MySQL Cluster NDB 6.1.1, it is no longer possible to use true or false for the value of this parameter; when upgrading from a previous version, you must change the value to 0, 1, or 2.

Prior to MySQL Cluster NDB 6.3.31 and MySQL Cluster NDB 7.0.11, setting this parameter did not cause the stated memory to be allocated when the node was started, but rather only when the memory was used by the data node process for other reasons. (Bug #37430)

# Note

If the operating system is not configured to permit unprivileged users to lock pages, then the data node process making use of this parameter may have to be run as system root. (LockPagesInMainMemory uses the mlockall function. From Linux kernel 2.6.9, unprivileged users can lock memory as limited by max locked memory. For more information, see ulimit -l and http://linux.die.net/man/2/mlock).

## **Important**

Beginning with glibc 2.10, glibc uses per-thread arenas to reduce lock contention on a shared pool, which consumes real memory. In general, a data node process does not need per-thread arenas, since it does not perform any memory allocation after startup. (This difference in allocators does not appear to affect performance significantly.)

The glibc behavior is intended to be configurable via the MALLOC\_ARENA\_MAX environment variable, but a bug in this mechanism prior to glibc 2.16 meant that this variable could not be set to less than 8, so that the wasted memory could not be reclaimed. (Bug #15907219; see also http://sourceware.org/bugzilla/show\_bug.cgi?id=13137 for more information concerning this issue.)

One possible workaround for this problem is to use the LD\_PRELOAD environment variable to preload a jemalloc memory allocation library to take the place of that supplied with glibc.

### • StopOnError

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	true	true, false	S

This parameter specifies whether a data node process should exit or perform an automatic restart when an error condition is encountered.

This parameter's default value is true; this means that, by default, an error causes the data node process to halt.

# • CrashOnCorruptedTuple

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.28, 5.1.56-ndb-7.1.17	boolean	false	true, false	S
NDB 7.2.1	boolean	true	true, false	S

This parameter was introduced in MySQL Cluster NDB 7.0.28 and MySQL Cluster NDB 7.1.17. When enabled, it forces a data node to shut down whenever it encounters a corrupted tuple. By default, it is disabled.

# Diskless

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	true false (1 0)	false	true, false	S

It is possible to specify MySQL Cluster tables as <u>diskless</u>, meaning that tables are not checkpointed to disk and that no logging occurs. Such tables exist only in main memory. A consequence of using diskless tables is that neither the tables nor the records in those tables survive a crash. However, when operating in diskless mode, it is possible to run ndbd on a diskless computer.

# **Important**

This feature causes the *entire* cluster to operate in diskless mode.

When this feature is enabled, Cluster online backup is disabled. In addition, a partial start of the cluster is not possible.

Diskless is disabled by default.

### ODirect

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.11	boolean	false	true, false	S
NDB 6.2.3	boolean	false	true, false	S
NDB 6.3.0	boolean	fa <b>1337</b>	true, false	S

Enabling this parameter causes NDB to attempt using O\_DIRECT writes for LCP, backups, and redo logs, often lowering kswapd and CPU usage. When using MySQL Cluster on Linux, enable ODirect if you are using a 2.6 or later kernel.

This parameter was added in MySQL 5.1.20, MySQL Cluster NDB 6.1.11, MySQL Cluster NDB 6.2.3, and MySQL Cluster NDB 6.3.0.

ODirect is disabled by default.

#### • RestartOnErrorInsert

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	error code	2	0 - 4	S

This feature is accessible only when building the debug version where it is possible to insert errors in the execution of individual blocks of code as part of testing.

This feature is disabled by default.

### • CompressedBackup

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.7	boolean	false	true, false	S

Setting this parameter to 1 causes backup files to be compressed. The compression used is equivalent to gzip --fast, and can save 50% or more of the space required on the data node to store uncompressed backup files. Compressed backups can be enabled for individual data nodes, or for all data nodes (by setting this parameter in the [ndbd default] section of the config.ini file).

# **Important**

You cannot restore a compressed backup to a cluster running a MySQL version that does not support this feature.

The default value is 0 (disabled).

This parameter was introduced in MySQL Cluster NDB 6.3.7.

# CompressedLCP

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.7	boolean	false	true, false	S

Setting this parameter to 1 causes local checkpoint files to be compressed. The compression used is equivalent to gzip --fast, and can save 50% or more of the space required on the data node to store uncompressed checkpoint files. Compressed LCPs can be enabled for individual data nodes, or for all data nodes (by setting this parameter in the [ndbd default] section of the config.ini file).

# **Important**

You cannot restore a compressed local checkpoint to a cluster running a MySQL version that does not support this feature.

This parameter was introduced in MySQL Cluster NDB 6.3.7.

# Controlling Timeouts, Intervals, and Disk Paging

There are a number of <code>[ndbd]</code> parameters specifying timeouts and intervals between various actions in Cluster data nodes. Most of the timeout values are specified in milliseconds. Any exceptions to this are mentioned where applicable.

### • TimeBetweenWatchDogCheck

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	6000	70 - 4294967039 (0xFFFFFEFF)	S

To prevent the main thread from getting stuck in an endless loop at some point, a "watchdog" thread checks the main thread. This parameter specifies the number of milliseconds between checks. If the process remains in the same state after three checks, the watchdog thread terminates it.

This parameter can easily be changed for purposes of experimentation or to adapt to local conditions. It can be specified on a per-node basis although there seems to be little reason for doing so.

The default timeout is 6000 milliseconds (6 seconds).

# • TimeBetweenWatchDogCheckInitial

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.20	milliseconds	6000	70 - 4294967039 (0xFFFFFEFF)	S

This is similar to the TimeBetweenWatchDogCheck parameter, except that TimeBetweenWatchDogCheckInitial controls the amount of time that passes between execution checks inside a database node in the early start phases during which memory is allocated.

The default timeout is 6000 milliseconds (6 seconds).

This parameter was added in MySQL 5.1.20.

#### StartPartialTimeout

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	30000	0 - 4294967039 (0xFFFFFEFF)	S

This parameter specifies how long the Cluster waits for all data nodes to come up before the cluster initialization routine is invoked. This timeout is used to avoid a partial Cluster startup whenever possible.

This parameter is overridden when performing an initial start or initial restart of the cluster.

The default value is 30000 milliseconds (30 seconds). 0 disables the timeout, in which case the cluster may start only if all nodes are available.

### • StartPartitionedTimeout

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	60000	0 - 4294967039 (0xFFFFFEFF)	S

If the cluster is ready to start after waiting for StartPartialTimeout milliseconds but is still possibly in a partitioned state, the cluster waits until this timeout has also passed. If StartPartitionedTimeout is set to 0, the cluster waits indefinitely.

This parameter is overridden when performing an initial start or initial restart of the cluster.

The default timeout is 60000 milliseconds (60 seconds).

#### StartFailureTimeout

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	0	0 - 4294967039 (0xFFFFFEFF)	S

If a data node has not completed its startup sequence within the time specified by this parameter, the node startup fails. Setting this parameter to 0 (the default value) means that no data node timeout is applied.

For nonzero values, this parameter is measured in milliseconds. For data nodes containing extremely large amounts of data, this parameter should be increased. For example, in the case of a data node containing several gigabytes of data, a period as long as 10–15 minutes (that is, 600000 to 1000000 milliseconds) might be required to perform a node restart.

# • StartNoNodeGroupTimeout

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.24	milliseconds		0 - 4294967039 (0xFFFFFEFF)	S
			(**** * * * * * * * * * * * * * * * * *	

When a data node is configured with Nodegroup = 65536, is regarded as not being assigned to any node group. When that is done, the cluster waits StartNoNodegroupTimeout milliseconds, then treats such nodes as though they had been added to the list passed to the --nowait-nodes option, and starts. The default value is 15000 (that is, the management server waits 15 seconds). Setting this parameter equal to 0 means that the cluster waits indefinitely.

StartNoNodegroupTimeout must be the same for all data nodes in the cluster; for this reason, you should always set it in the [ndbd default] section of the config.ini file, rather than for individual data nodes.

This parameter was added in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13. See Section 7.13, "Adding MySQL Cluster Data Nodes Online", for more information.

# HeartbeatIntervalDbDb

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	1500	10 - 4294967039 (0xFFFFFEFF)	S

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.2.0	milliseconds	5000	10 - 4294967039 (0xFFFFFEFF)	S

One of the primary methods of discovering failed nodes is by the use of heartbeats. This parameter states how often heartbeat signals are sent and how often to expect to receive them. After missing three heartbeat intervals in a row, the node is declared dead. Thus, the maximum time for discovering a failure through the heartbeat mechanism is four times the heartbeat interval.

In MySQL Cluster NDB 7.2.0 and later, the default heartbeat interval is 5000 milliseconds (5 seconds). Previously, the default was 1500 milliseconds (1.5 seconds). This parameter must not be changed drastically and should not vary widely between nodes. If one node uses 5000 milliseconds and the node watching it uses 1000 milliseconds, obviously the node will be declared dead very quickly. This parameter can be changed during an online software upgrade, but only in small increments.

See also Network communication and latency.

### • HeartbeatIntervalDbApi

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	1500	100 - 4294967039 (0xFFFFFEFF)	S

Each data node sends heartbeat signals to each MySQL server (SQL node) to ensure that it remains in contact. If a MySQL server fails to send a heartbeat in time it is declared "dead," in which case all ongoing transactions are completed and all resources released. The SQL node cannot reconnect until all activities initiated by the previous MySQL instance have been completed. The three-heartbeat criteria for this determination are the same as described for HeartbeatIntervalDbDb.

The default interval is 1500 milliseconds (1.5 seconds). This interval can vary between individual data nodes because each data node watches the MySQL servers connected to it, independently of all other data nodes.

For more information, see Network communication and latency.

### • HeartbeatOrder

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.35	numeric	0	0 - 65535	S
NDB 7.0.16	numeric	0	0 - 65535	S
NDB 7.1.5	numeric	0	0 - 65535	S

Data nodes send heartbeats to one another in a circular fashion whereby each data node monitors the previous one. If a heartbeat is not detected by a given data node, this node declares the previous data node in the circle "dead" (that is, no longer accessible by the cluster). The determination that a data node is dead is done globally; in other words; once a data node is declared dead, it is regarded as such by all nodes in the cluster.

It is possible for heartbeats between data nodes residing on different hosts to be too slow compared to heartbeats between other pairs of nodes (for example, due to a very low heartbeat interval or temporary connection problem), such that a data node is declared dead, even though the node can still function as part of the cluster.

In this type of situation, it may be that the order in which heartbeats are transmitted between data nodes makes a difference as to whether or not a particular data node is declared dead. If this declaration occurs unnecessarily, this can in turn lead to the unnecessary loss of a node group and as thus to a failure of the cluster.

Consider a setup where there are 4 data nodes A, B, C, and D running on 2 host computers host1 and host2, and that these data nodes make up 2 node groups, as shown in the following table:

Node Group	Nodes Running on host1	Nodes Running on host2
Node Group 0:	Node A	Node B
Node Group 1:	Node C	Node D

Suppose the heartbeats are transmitted in the order A->B->C->D->A. In this case, the loss of the heartbeat between the hosts causes node B to declare node A dead and node C to declare node B dead. This results in loss of Node Group 0, and so the cluster fails. On the other hand, if the order of transmission is A->B->D->C->A (and all other conditions remain as previously stated), the loss of the heartbeat causes nodes A and D to be declared dead; in this case, each node group has one surviving node, and the cluster survives.

Priot to MySQL Cluster NDB 6.3.35, MySQL Cluster NDB 7.0.16, and MySQL Cluster NDB 7.1.5, the order of heartbeat transmission between data nodes was always automatically determined by NDB. However, beginning with these versions, the HeartbeatOrder configuration parameter makes the order of heartbeat transmission user-configurable.

The default value for <code>HeartbeatOrder</code> is zero; allowing the default value to be used on all data nodes causes the order of heartbeat transmission to be determined by <code>NDB</code>. If this parameter is used, it must be set to a nonzero value (maximum 65535) for every data node in the cluster, and this value must be unique for each data node; this causes the heartbeat transmission to proceed from data node to data node in the order of their <code>HeartbeatOrder</code> values from lowest to highest (and then directly from the data node having the highest <code>HeartbeatOrder</code> to the data node having the lowest value, to complete the circle). The values need not be consecutive; for example, to force the heartbeat transmission order A->B->D->C->A in the scenario outlined previously, you could set the <code>HeartbeatOrder</code> values as shown here:

Node	HeartbeatOrder
A	10
В	20
С	30
D	25

To use this parameter to change the heartbeat transmission order in a running MySQL Cluster, you must first set HeartbeatOrder for each data node in the cluster in the global configuration (config.ini) file (or files). To cause the change to take effect, you must perform either of the following:

- A complete shutdown and restart of the entire cluster.
- 2 rolling restarts of the cluster in succession. All nodes must be restarted in the same order in both rolling restarts.

You can use DUMP 908 to observe the effect of this parameter in the data node logs.

ConnectCheckIntervalDelay

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.13	string	1500	0 - 4294967039 (0xFFFFEFF)	S
NDB 7.2.1	string	0	0 - 4294967039 (0xFFFFFEFF)	S

Enables connection checking between data nodes. A data node that fails to respond within an interval of ConnectCheckIntervalDelay seconds is considered suspect, and is considered dead after two such intervals.

# • TimeBetweenLocalCheckpoints

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	number of 4-byte words, as a base-2 logarithm	20	0 - 31	S

This parameter is an exception in that it does not specify a time to wait before starting a new local checkpoint; rather, it is used to ensure that local checkpoints are not performed in a cluster where relatively few updates are taking place. In most clusters with high update rates, it is likely that a new local checkpoint is started immediately after the previous one has been completed.

The size of all write operations executed since the start of the previous local checkpoints is added. This parameter is also exceptional in that it is specified as the base-2 logarithm of the number of 4-byte words, so that the default value 20 means 4MB ( $4 \times 2^{20}$ ) of write operations, 21 would mean 8MB, and so on up to a maximum value of 31, which equates to 8GB of write operations.

All the write operations in the cluster are added together. Setting TimeBetweenLocalCheckpoints to 6 or less means that local checkpoints will be executed continuously without pause, independent of the cluster's workload.

# • TimeBetweenGlobalCheckpoints

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	2000	10 - 32000	S
NDB 6.2.0	milliseconds	2000	20 - 32000	S

When a transaction is committed, it is committed in main memory in all nodes on which the data is mirrored. However, transaction log records are not flushed to disk as part of the commit. The reasoning behind this behavior is that having the transaction safely committed on at least two autonomous host machines should meet reasonable standards for durability.

It is also important to ensure that even the worst of cases—a complete crash of the cluster—is handled properly. To guarantee that this happens, all transactions taking place within a given interval are put into a global checkpoint, which can be thought of as a set of committed transactions that has been flushed to disk. In other words, as part of the commit process, a transaction is placed in a global checkpoint group. Later, this group's log records are flushed to disk, and then the entire group of transactions is safely committed to disk on all computers in the cluster.

This parameter defines the interval between global checkpoints. The default is 2000 milliseconds.

# • TimeBetweenEpochs

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.5	milliseconds	100	0 - 32000	S

This parameter defines the interval between synchronization epochs for MySQL Cluster Replication. The default value is 100 milliseconds.

TimeBetweenEpochs is part of the implementation of "micro-GCPs", which can be used to improve the performance of MySQL Cluster Replication. This parameter was introduced in MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2.

# • TimeBetweenEpochsTimeout

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.22	milliseconds	4000	0 - 32000	S
MySQL 5.1.51	milliseconds	0	0 - 256000	S

This parameter defines a timeout for synchronization epochs for MySQL Cluster Replication. If a node fails to participate in a global checkpoint within the time determined by this parameter, the node is shut down. In MySQL Cluster NDB 7.2.0 and later, the default value is 0; in other words, the timeout is disabled. This represents a change from previous versions of MySQL Cluster, in which the default value was 4000 milliseconds (4 seconds).

TimeBetweenEpochsTimeout is part of the implementation of "micro-GCPs", which can be used to improve the performance of MySQL Cluster Replication. This parameter was introduced in MySQL Cluster NDB 6.2.7 and MySQL Cluster NDB 6.3.4.

The following changes regarding this parameter were made in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10:

- The maximum possible value for this parameter was increased from 32000 milliseconds to 256000 milliseconds.
- Setting this parameter to zero now has the effect of disabling GCP stops caused by save timeouts, commit timeouts, or both.
- The current value of this parameter and a warning are now written to the cluster log whenever a GCP save takes longer than 1 minute or a GCP save takes longer than 10 seconds.

### • MaxBufferedEpochs

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.14	epochs	100	0 - 100000	S

The number of unprocessed epochs by which a subscribing node can lag behind. Exceeding this number causes a lagging subscriber to be disconnected.

The default value of 100 is sufficient for most normal operations. If a subscribing node does lag enough to cause disconnections, it is usually due to network or scheduling issues with regard to processes or threads. (In rare circumstances, the problem may be due to a bug in the NDB client.) It may be desirable to set the value lower than the default when epochs are longer.

Disconnection prevents client issues from affecting the data node service, running out of memory to buffer data, and eventually shutting down. Instead, only the client is affected as a result of the disconnect (by, for example gap events in the binary log), forcing the client to reconnect or restart the process.

### • MaxBufferedEpochBytes

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.52	bytes	26214400	26214400 (0x01900000) - 4294967039 (0xFFFFEFF)	S
NDB 7.0.38	bytes	26214400	26214400 (0x01900000) - 4294967039 (0xFFFFEFF)	S
NDB 7.1.27	bytes	26214400	26214400 (0x01900000) - 4294967039 (0xFFFFFEFF)	S

The total number of bytes allocated for buffering epochs by this node.

This parameter was introduced in MySQL Cluster NDB 6.3.52, MySQL Cluster NDB 7.0.38, and MySQL Cluster NDB 7.1.27. (Bug #16203623)

### • TimeBetweenInactiveTransactionAbortCheck

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	1000	1000 - 4294967039 (0xFFFFFEFF)	S

Timeout handling is performed by checking a timer on each transaction once for every interval specified by this parameter. Thus, if this parameter is set to 1000 milliseconds, every transaction will be checked for timing out once per second.

The default value is 1000 milliseconds (1 second).

### • TransactionInactiveTimeout

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	[see text]	0 - 4294967039 (0xFFFFFEFF)	S

This parameter states the maximum time that is permitted to lapse between operations in the same transaction before the transaction is aborted.

The default for this parameter is 4G (also the maximum). For a real-time database that needs to ensure that no transaction keeps locks for too long, this parameter should be set to a relatively small value. The unit is milliseconds.

# TransactionDeadlockDetectionTimeout

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	1200	50 - 4294967039 (0xFFFFFEFF)	S

When a node executes a query involving a transaction, the node waits for the other nodes in the cluster to respond before continuing. A failure to respond can occur for any of the following reasons:

- · The node is "dead"
- The operation has entered a lock queue
- The node requested to perform the action could be heavily overloaded.

This timeout parameter states how long the transaction coordinator waits for query execution by another node before aborting the transaction, and is important for both node failure handling and deadlock detection. In MySQL 5.1.10 and earlier versions, setting it too high could cause undesirable behavior in situations involving deadlocks and node failure. Beginning with MySQL 5.1.11, active transactions occurring during node failures are actively aborted by the MySQL Cluster Transaction Coordinator, and so high settings are no longer an issue with this parameter.

The default timeout value is 1200 milliseconds (1.2 seconds).

Prior to MySQL Cluster NDB versions 6.2.18, 6.3.24, and 7.0.5, the effective minimum for this parameter was 100 milliseconds. (Bug #44099) Beginning with these versions, the actual minimum is 50 milliseconds.

### • DiskSyncSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.12	bytes	4M	32K - 4294967039 (0xFFFFFEFF)	S

This is the maximum number of bytes to store before flushing data to a local checkpoint file. This is done to prevent write buffering, which can impede performance significantly. This parameter is *not* intended to take the place of TimeBetweenLocalCheckpoints.

### Note

When ODirect is enabled, it is not necessary to set DiskSyncSize; in fact, in such cases its value is simply ignored.

The default value is 4M (4 megabytes).

This parameter was added in MySQL 5.1.12.

# • DiskCheckpointSpeed

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.12	bytes	10M	1M - 4294967039 (0xFFFFFEFF)	S

The amount of data,in bytes per second, that is sent to disk during a local checkpoint. This allocation is shared by DML operations and backups (but not backup logging), which means that backups started

during times of intensive DML may be impaired by flooding of the redo log buffer and may fail altogether if the contention is sufficiently severe.

The default value is 10M (10 megabytes per second).

This parameter was added in MySQL 5.1.12.

• DiskCheckpointSpeedInRestart

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes		1M - 4294967039 (0xFFFFFEFF)	S

The amount of data, in bytes per second, that is sent to disk during a local checkpoint as part of a restart operation.

The default value is 100M (100 megabytes per second).

This parameter was added in MySQL 5.1.12.

NoOfDiskPagesToDiskAfterRestartTUP

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	8K pages/100	40	1 - 4294967039	S
	milliseconds		(0xFFFFFEFF)	

When executing a local checkpoint, the algorithm flushes all data pages to disk. Merely doing so as quickly as possible without any moderation is likely to impose excessive loads on processors, networks, and disks. To control the write speed, this parameter specifies how many pages per 100 milliseconds are to be written. In this context, a "page" is defined as 8KB. This parameter is specified in units of 80KB per second, so setting NoOfDiskPagesToDiskAfterRestartTUP to a value of 20 entails writing 1.6MB in data pages to disk each second during a local checkpoint. This value includes the writing of UNDO log records for data pages. That is, this parameter handles the limitation of writes from data memory. (See the entry for IndexMemory for information about index pages.)

In short, this parameter specifies how quickly to execute local checkpoints. It operates in conjunction with NoOfFragmentLogFiles, DataMemory, and IndexMemory.

For more information about the interaction between these parameters and possible strategies for choosing appropriate values for them, see Section 5.2.12, "Configuring MySQL Cluster Parameters for Local Checkpoints".

The default value is 40 (3.2MB of data pages per second).

### Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use DiskCheckpointSpeed and DiskSyncSize instead.

NoOfDiskPagesToDiskAfterRestartACC

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	8K pages/100	29 <sub>47</sub>	1 - 4294967039	S
	milliseconds		(0xFFFFFEFF)	

This parameter uses the same units as NoOfDiskPagesToDiskAfterRestartTUP and acts in a similar fashion, but limits the speed of writing index pages from index memory.

The default value of this parameter is 20 (1.6MB of index memory pages per second).

### Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use <code>DiskCheckpointSpeed</code> and <code>DiskSyncSize</code>.

• NoOfDiskPagesToDiskDuringRestartTUP (DEPRECATED)

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	8K pages/100 milliseconds	40	1 - 4294967039 (0xFFFFFEFF)	S

This parameter is used in a fashion similar to NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC, only it does so with regard to local checkpoints executed in the node when a node is restarting. A local checkpoint is always performed as part of all node restarts. During a node restart it is possible to write to disk at a higher speed than at other times, because fewer activities are being performed in the node.

This parameter covers pages written from data memory.

The default value is 40 (3.2MB per second).

# Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use <code>DiskCheckpointSpeedInRestart</code> and <code>DiskSyncSize</code>.

• NoOfDiskPagesToDiskDuringRestartACC (DEPRECATED)

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	8K pages/100 milliseconds	20	1 - 4294967039 (0xFFFFFEFF)	S

Controls the number of index memory pages that can be written to disk during the local checkpoint phase of a node restart.

As with NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC, values for this parameter are expressed in terms of 8KB pages written per 100 milliseconds (80KB/second).

The default value is 20 (1.6MB per second).

### Note

This parameter is deprecated as of MySQL 5.1.6. For MySQL 5.1.12 and later versions, use <code>DiskCheckpointSpeedInRestart</code> and <code>DiskSyncSize</code>.

• ArbitrationTimeout

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	3000	10 - 4294967039 (0xFFFFFEFF)	S
NDB 7.2.0	milliseconds	7500	10 - 4294967039 (0xFFFFFEFF)	S

This parameter specifies how long data nodes wait for a response from the arbitrator to an arbitration message. If this is exceeded, the network is assumed to have split.

In MySQL Cluster NDB 7.2.0 and later, the default value is 7500 milliseconds (7.5 seconds). Previously, this was 3000 milliseconds (3 seconds).

#### • Arbitration

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.7	enumeration		Default, Disabled, WaitExternal	S

The Arbitration parameter, added in MySQL Cluster NDB 7.0.7, enables a choice of arbitration schemes, corresponding to one of 3 possible values for this parameter:

- **Default.** This enables arbitration to proceed normally, as determined by the ArbitrationRank settings for the management and API nodes. This is the default value.
- **Disabled.** Previously, it was possible to disable arbitration only by setting ArbitrationRank to 0 on all management and API nodes. Now, you can now use Arbitration = Disabled in the [ndbd default] section of the config.ini file to accomplish this task. In this case, any ArbitrationRank settings are ignored.
- WaitExternal. The Arbitration parameter also makes it possible to configure arbitration in such a way that the cluster waits until after the time determined by ArbitrationTimeout has passed for an external cluster manager application to perform arbitration instead of handling arbitration internally. This can be done by setting Arbitration = WaitExternal in the [ndbd default] section of the config.ini file. For best results with the WaitExternal setting, it is recommended that ArbitrationTimeout be 2 times as long as the interval required by the external cluster manager to perform arbitration.

# **Important**

This parameter should be used only in the <code>[ndbd default]</code> section of the cluster configuration file. The behavior of the cluster is unspecified when <code>Arbitration</code> is set to different values for individual data nodes.

**Buffering and logging.** Several [ndbd] configuration parameters enable the advanced user to have more control over the resources used by node processes and to adjust various buffer sizes at need.

These buffers are used as front ends to the file system when writing log records to disk. If the node is running in diskless mode, these parameters can be set to their minimum values without penalty due to the fact that disk writes are "faked" by the NDB storage engine's file system abstraction layer.

UndoIndexBuffer

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	2M	1M - 4294967039 (0xFFFFFEFF)	S

The UNDO index buffer, whose size is set by this parameter, is used during local checkpoints. The NDB storage engine uses a recovery scheme based on checkpoint consistency in conjunction with an operational REDO log. To produce a consistent checkpoint without blocking the entire system for writes, UNDO logging is done while performing the local checkpoint. UNDO logging is activated on a single table fragment at a time. This optimization is possible because tables are stored entirely in main memory.

The UNDO index buffer is used for the updates on the primary key hash index. Inserts and deletes rearrange the hash index; the NDB storage engine writes UNDO log records that map all physical changes to an index page so that they can be undone at system restart. It also logs all active insert operations for each fragment at the start of a local checkpoint.

Reads and updates set lock bits and update a header in the hash index entry. These changes are handled by the page-writing algorithm to ensure that these operations need no UNDO logging.

This buffer is 2MB by default. The minimum value is 1MB, which is sufficient for most applications. For applications doing extremely large or numerous inserts and deletes together with large transactions and large primary keys, it may be necessary to increase the size of this buffer. If this buffer is too small, the NDB storage engine issues internal error code 677 (Index UNDO buffers overloaded).

# **Important**

It is not safe to decrease the value of this parameter during a rolling restart.

### • UndoDataBuffer

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	16M	1M - 4294967039 (0xFFFFFEFF)	S

This parameter sets the size of the UNDO data buffer, which performs a function similar to that of the UNDO index buffer, except the UNDO data buffer is used with regard to data memory rather than index memory. This buffer is used during the local checkpoint phase of a fragment for inserts, deletes, and updates.

Because UNDO log entries tend to grow larger as more operations are logged, this buffer is also larger than its index memory counterpart, with a default value of 16MB.

This amount of memory may be unnecessarily large for some applications. In such cases, it is possible to decrease this size to a minimum of 1MB.

It is rarely necessary to increase the size of this buffer. If there is such a need, it is a good idea to check whether the disks can actually handle the load caused by database update activity. A lack of sufficient disk space cannot be overcome by increasing the size of this buffer.

If this buffer is too small and gets congested, the NDB storage engine issues internal error code 891 (Data UNDO buffers overloaded).

# **Important**

It is not safe to decrease the value of this parameter during a rolling restart.

### • RedoBuffer

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	8M	1M - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	32M	1M - 4294967039 (0xFFFFFEFF)	S

All update activities also need to be logged. The REDO log makes it possible to replay these updates whenever the system is restarted. The NDB recovery algorithm uses a "fuzzy" checkpoint of the data together with the UNDO log, and then applies the REDO log to play back all changes up to the restoration point.

RedoBuffer sets the size of the buffer in which the REDO log is written. In MySQL Cluster NDB 6.4.3 and earlier, the default value is 8MB; beginning with MySQL Cluster NDB 7.0.4, the default is 32MB. The minimum value is 1MB.

If this buffer is too small, the NDB storage engine issues error code 1221 (REDO log buffers overloaded). For this reason, you should exercise care if you attempt to decrease the value of RedoBuffer as part of an online change in the cluster's configuration.

# • EventLogBufferSize

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.4	bytes	8192	0 - 64K	S

Controls the size of the circular buffer used for NDB log events within data nodes.

Added in MySQL Cluster NDB 7.0.4.

**Controlling log messages.** In managing the cluster, it is very important to be able to control the number of log messages sent for various event types to stdout. For each event category, there are 16 possible event levels (numbered 0 through 15). Setting event reporting for a given event category to level 15 means all event reports in that category are sent to stdout; setting it to 0 means that there will be no event reports made in that category.

By default, only the startup message is sent to stdout, with the remaining event reporting level defaults being set to 0. The reason for this is that these messages are also sent to the management server's cluster log.

An analogous set of levels can be set for the management client to determine which event levels to record in the cluster log.

# • LogLevelStartup

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	1	0 - 15	S

The reporting level for events generated during startup of the process.

# The default level is 1.

# • LogLevelShutdown

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for events generated as part of graceful shutdown of a node.

The default level is 0.

# • LogLevelStatistic

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for statistical events such as number of primary key reads, number of updates, number of inserts, information relating to buffer usage, and so on.

The default level is 0.

# • LogLevelCheckpoint

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	log level	0	0 - 15	S

The reporting level for events generated by local and global checkpoints.

The default level is 0.

# • LogLevelNodeRestart

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for events generated during node restart.

The default level is 0.

# • LogLevelConnection

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for events generated by connections between cluster nodes.

The default level is 0.

# • LogLevelError

152				
<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for events generated by errors and warnings by the cluster as a whole. These errors do not cause any node failure but are still considered worth reporting.

The default level is 0.

• LogLevelCongestion

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	levelr	0	0 - 15	S

The reporting level for events generated by congestion. These errors do not cause node failure but are still considered worth reporting.

The default level is 0.

• LogLevelInfo

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	integer	0	0 - 15	S

The reporting level for events generated for information about the general state of the cluster.

The default level is 0.

• MemReportFrequency

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.0	unsigned	0	0 - 4294967039 (0xFFFFFEFF)	S
MySQL 5.1.16	unsigned	0	0 - 4294967039 (0xFFFFFEFF)	S

This parameter controls how often data node memory usage reports are recorded in the cluster log; it is an integer value representing the number of seconds between reports.

Each data node's data memory and index memory usage is logged as both a percentage and a number of 32 KB pages of the <code>DataMemory</code> and <code>IndexMemory</code>, respectively, set in the <code>config.ini</code> file. For example, if <code>DataMemory</code> is equal to 100 MB, and a given data node is using 50 MB for data memory storage, the corresponding line in the cluster log might look like this:

```
2006-12-24 01:18:16 [MgmSrvr] INFO -- Node 2: Data usage is 50%(1280 32K pages of total 2560)
```

MemReportFrequency is not a required parameter. If used, it can be set for all cluster data nodes in the [ndbd default] section of config.ini, and can also be set or overridden for individual data nodes in the corresponding [ndbd] sections of the configuration file. The minimum value—which is also the default value—is 0, in which case memory reports are logged only when memory usage reaches certain percentages (80%, 90%, and 100%), as mentioned in the discussion of statistics events in Section 7.6.2, "MySQL Cluster Log Events".

This parameter was added in MySQL Cluster 5.1.16 and MySQL Cluster NDB 6.1.0.

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	seconds	0	0 - 4294967039 (0xFFFFFEFF)	S

When a data node is started with the <code>--initial</code>, it initializes the redo log file during Start Phase 4 (see Section 7.1, "Summary of MySQL Cluster Start Phases"). When very large values are set for <code>NoOfFragmentLogFiles</code>, <code>FragmentLogFileSize</code>, or both, this initialization can take a long time. Previous to MySQL Cluster NDB 6.4.0, only the beginning and end of the redo log file initialization process were logged. Beginning with this version, it is possible to force reports on the progress of this process to be logged periodically, by means of the <code>StartupStatusReportFrequency</code> configuration parameter. In this case, progress is reported in the cluster log, in terms of both the number of files and the amount of space that have been initialized, as shown here:

```
2009-06-20 16:39:23 [MgmSrvr] INFO -- Node 1: Local redo log file initialization status: #Total files: 80, Completed: 60 #Total MBytes: 20480, Completed: 15557 2009-06-20 16:39:23 [MgmSrvr] INFO -- Node 2: Local redo log file initialization status: #Total files: 80, Completed: 60 #Total MBytes: 20480, Completed: 15570
```

These reports are logged each StartupStatusReportFrequency seconds during Start Phase 4. If StartupStatusReportFrequency is 0 (the default), then reports are written to the cluster log only when at the beginning and at the completion of the redo log file initialization process.

**Debugging Parameters.** Beginning with MySQL Cluster NDB 6.3.36, MySQL Cluster NDB 7.0.17, and MySQL Cluster NDB 7.1.6, it is possible to cause logging of traces for events generated by creating and dropping tables using <code>DictTrace</code>. This parameter is useful only in debugging NDB kernel code. <code>DictTrace</code> takes an integer value; currently, 0 (default - no logging) and 1 (logging enabled) are the only supported values.

**Backup parameters.** The [ndbd] parameters discussed in this section define memory buffers set aside for execution of online backups.

• BackupDataBufferSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	2M	0 - 4294967039 (0xFFFFEFF)	S
NDB 6.3.23	bytes	16M	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	16M	0 - 4294967039 (0xFFFFFEFF)	S

In creating a backup, there are two buffers used for sending data to the disk. The backup data buffer is used to fill in data recorded by scanning a node's tables. Once this buffer has been filled to the level specified as <code>BackupWriteSize</code>, the pages are sent to disk. While flushing data to disk, the backup process can continue filling this buffer until it runs out of space. When this happens, the backup process pauses the scan and waits until some disk writes have completed freeing up memory so that scanning may continue.

In MySQL Cluster NDB 6.4.3 and earlier, the default value is 2MB; in MySQL Cluster NDB 7.0.4 and later, it is 16MB.

# • BackupLogBufferSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	2M	0 - 4294967039 (0xFFFFFEFF)	S
NDB 6.3.23	bytes	16M	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	16M	0 - 4294967039 (0xFFFFFEFF)	S

The backup log buffer fulfills a role similar to that played by the backup data buffer, except that it is used for generating a log of all table writes made during execution of the backup. The same principles apply for writing these pages as with the backup data buffer, except that when there is no more space in the backup log buffer, the backup fails. For that reason, the size of the backup log buffer must be large enough to handle the load caused by write activities while the backup is being made. See Section 7.3.3, "Configuration for MySQL Cluster Backups".

The default value for this parameter should be sufficient for most applications. In fact, it is more likely for a backup failure to be caused by insufficient disk write speed than it is for the backup log buffer to become full. If the disk subsystem is not configured for the write load caused by applications, the cluster is unlikely to be able to perform the desired operations.

It is preferable to configure cluster nodes in such a manner that the processor becomes the bottleneck rather than the disks or the network connections.

In MySQL Cluster NDB 6.4.3 and earlier, the default value is 2MB; in MySQL Cluster NDB 7.0.4 and later, it is 16MB.

# BackupMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	4M	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	32M	0 - 4294967039 (0xFFFFFEFF)	S

This parameter is simply the sum of BackupDataBufferSize and BackupLogBufferSize.

In MySQL Cluster NDB 7.0.4 and later, the default value is 16MB + 16MB = 32MB. (Previously, it was 2MB + 2MB = 4MB.)

# **Important**

If BackupDataBufferSize and BackupLogBufferSize taken together exceed the default value for BackupMemory, then this parameter must be set explicitly in the config.ini file to their sum.

# • BackupReportFrequency

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.2.3	seconds	0	0 - 4294967039	S
		155	(0xFFFFFEFF)	

This parameter controls how often backup status reports are issued in the management client during a backup, as well as how often such reports are written to the cluster log (provided cluster event logging is configured to permit it—see Logging and checkpointing). BackupReportFrequency represents the time in seconds between backup status reports.

The default value is 0.

This parameter was added in MySQL Cluster NDB 6.2.3.

# • BackupWriteSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	32K	2K - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	256K	2K - 4294967039 (0xFFFFFEFF)	S

This parameter specifies the default size of messages written to disk by the backup log and backup data buffers.

In MySQL Cluster 6.4.3 and earlier, the default value for this parameter was 32KB; beginning with MySQL Cluster NDB 7.0.4, it is 256KB.

### • BackupMaxWriteSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	256K	2K - 4294967039 (0xFFFFFEFF)	S
MySQL 5.1.32	bytes	1M	2K - 4294967039 (0xFFFFFEFF)	S
NDB 7.2.1	bytes	1M	2K - 4294967039 (0xFFFFFEFF)	S

This parameter specifies the maximum size of messages written to disk by the backup log and backup data buffers.

In MySQL Cluster 6.4.3 and earlier, the default value for this parameter was 256KB; beginning with MySQL Cluster NDB 7.0.4, it is 1MB.

# **Important**

When specifying these parameters, the following relationships must hold true. Otherwise, the data node will be unable to start.

- BackupDataBufferSize >= BackupWriteSize + 188KB
- BackupLogBufferSize >= BackupWriteSize + 16KB
- BackupMaxWriteSize >= BackupWriteSize

# **MySQL Cluster Realtime Performance Parameters**

The [ndbd] parameters discussed in this section are used in scheduling and locking of threads to specific CPUs on multiprocessor data node hosts. They were introduced in MySQL Cluster NDB 6.3.4.

### Note

To make use of these parameters, the data node process must be run as system root.

#### LockExecuteThreadToCPU

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.4	CPU ID	64K	0 - 64K	S

**Previous to MySQL Cluster NDB 7.0.** This parameter specifies the ID of the CPU assigned to handle the NDBCLUSTER execution thread. The value of this parameter is an integer in the range 0 to 65535 (inclusive). The default is 65535.

MySQL Cluster NDB 7.0 and later (beginning with MySQL Cluster NDB 6.4.0). When used with ndbd, this parameter (now a string) specifies the ID of the CPU assigned to handle the NDBCLUSTER execution thread.

When used with ndbmtd, the value of this parameter is a comma-separated list of CPU IDs assigned to handle execution threads. Each CPU ID in the list should be an integer in the range 0 to 65535 (inclusive). The number of IDs specified should match the number of execution threads determined by MaxNoOfExecutionThreads. However, there is no guarantee that threads are assigned to CPUs in any given order when using this parameter; beginning with in MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, you can obtain more finely-grained control of this type using ThreadConfig.

LockExecuteThreadToCPU has no default value.

Prior to MySQL Cluster NDB 7.0.18 and MySQL Cluster NDB 7.1.7, the effective maximum value recognized by this parameter as a valid CPU ID was 255; using a greater value caused thread locking to be disabled. (Bug #56185)

### • LockMaintThreadsToCPU

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.4	CPU ID	64K	0 - 64K	S
NDB 6.4.0	CPU ID	[none]	0 - 64K	S

This parameter specifies the ID of the CPU assigned to handle NDBCLUSTER maintenance threads.

The value of this parameter is an integer in the range 0 to 65535 (inclusive). This parameter was added in MySQL Cluster NDB 6.3.4. Prior to MySQL Cluster NDB 6.4.0, the default is 65535; in MySQL Cluster NDB 7.0 and later MySQL Cluster release series, there is no default value.

### • RealtimeScheduler

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.4	boolean	false	true, false	S

Setting this parameter to 1 enables real-time scheduling of data node threads.

Prior to MySQL Cluster NDB 7.0.40 and MySQL Cluster NDB 7.1.29, this parameter did not work correctly with data nodes running ndbmtd. (Bug #16961971)

### • SchedulerExecutionTimer

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.4	µsec	50	0 - 11000	S

This parameter specifies the time in microseconds for threads to be executed in the scheduler before being sent. Setting it to 0 minimizes the response time; to achieve higher throughput, you can increase the value at the expense of longer response times.

The default is 50 µsec, which our testing shows to increase throughput slightly in high-load cases without materially delaying requests.

This parameter was added in MySQL Cluster NDB 6.3.4.

### • SchedulerSpinTimer

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.4	µsec	0	0 - 500	S

This parameter specifies the time in microseconds for threads to be executed in the scheduler before sleeping.

The default value is 0.

### • BuildIndexThreads

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.30	numeric	0	0 - 128	S
NDB 7.0.11	numeric	0	0 - 128	S

This parameter determines the number of threads to create when rebuilding ordered indexes during a system or node start, as well as when running ndb\_restore --rebuild-indexes [342]. It is supported only when there is more than one fragment for the table per data node (for example, when the MAX\_ROWS option has been used with CREATE TABLE).

Setting this parameter to 0 (the default) disables multi-threaded building of ordered indexes.

This parameter was added in MySQL Cluster NDB 6.3.30 and MySQL Cluster NDB 7.0.11. Prior to MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, it was supported only when using ndbd; in these and later MySQL Cluster releases, BuildIndexThreads is also supported for data nodes running ndbmtd (see Bug #54521).

You can enable multi-threaded builds during data node initial restarts by setting the TwoPassInitialNodeRestartCopy data node configuration parameter to TRUE.

# TwoPassInitialNodeRestartCopy

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.11	boolean	false	true, false	S

In MySQL Cluster NDB 7.1.11 and later, multi-threaded building of ordered indexes can be enabled for initial restarts of data nodes by setting this configuration parameter to TRUE, which enables two-pass copying of data during initial node restarts.

You must also set BuildIndexThreads to a nonzero value.

#### Numa

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.20	boolean	1		S
NDB 7.1.9	boolean	1		S

NDB is extremely sensitive to Non-Uniform Memory Access settings and multi-CPU systems due to timeouts that it can cause. Due to this fact, and because most MySQL Cluster users do not employ numactl, support for NUMA is ignored by default by ndbd when running on a Linux system. If your Linux system provides NUMA support and you wish for data node memory to be subject to NUMA control, you can set this parameter equal to 0.

The Numa configuration parameter is supported only on Linux systems where libnuma.so is installed.

Multi-Threading Configuration Parameters (ndbmtd). ndbmtd runs by default as a single-threaded process and must be configured to use multiple threads, using either of two methods, both of which require setting configuration parameters in the config.ini file. The first method is simply to set an appropriate value for the MaxNoOfExecutionThreads configuration parameter. In MySQL Cluster NDB 7.1.17 and later, a second method is also supported, whereby it is possible to set up more complex rules for ndbmtd multi-threading using ThreadConfig. The next few paragraphs provide information about these parameters and their use with multi-threaded data nodes.

### • MaxNoOfExecutionThreads

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	integer	[none]	2 - 8	S
NDB 7.0.4	integer	2	2 - 8	S

This parameter controls the number of execution threads used by ndbmtd, up to a maximum of 8 threads, 4 of which can be LDM (LQH) threads. Although this parameter is set in the [ndbd] or [ndbd default] sections of the config.ini file, it is exclusive to ndbmtd and does not apply to ndbd.

Setting MaxNoOfExecutionThreads sets the number of threads by type as determined in the following table:

MaxNoOfExecutionThreads Value	LDM Threads	TC Threads	Send Threads	Receive Threads
03	1	1	0	1
4 6	2	1	0	1
78	4	1	0	1

There is always one SUMA (replication) thread.

The thread types are described later in this section (see ThreadConfig).

Setting this parameter outside the permitted range of values causes the management server to abort on startup with the error Error line *number*: Illegal value *value* for parameter MaxNoOfExecutionThreads.

For MaxNoOfExecutionThreads, a value of 0 or 1 is rounded up internally by NDB to 2, so that 2 is considered this parameter's default and minimum value.

MaxNoOfExecutionThreads is generally intended to be set equal to the number of CPU threads available, and to allocate a number of threads of each type suitable to typical workloads. It does not assign particular threads to specified CPUs. For cases where it is desirable to vary from the settings provided, or to bind threads to CPUs, you should use ThreadConfig instead, which allows you to allocate each thread directly to a desired type, CPU, or both.

The multi-threaded data node process always spawns at least 4 threads, listed here:

- · 1 local query handler (LDM) thread
- 1 transaction coordinator (TC) thread
- · 1 receive thread
- 1 subscription manager (SUMA or replication) thread

In MySQL Cluster NDB 7.1 and earlier, it is not possible to cause ndbmtd to use more than 1 TC thread. (This is possible in MySQL Cluster NDB 7.2.)

# • ThreadConfig

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.17	string	"		S
NDB 7.2.3	string	II .		S

This parameter is used with ndbmtd to assign threads of different types to different CPUs. Its value is a string whose format has the following syntax:

```
ThreadConfig := entry[,entry[,...]]
entry := type={param[,param[,...]]}
type := ldm | main | recv | rep | io
param := count=number | cpubind=cpu_list
```

The curly braces  $(\{...\})$  surrounding the list of parameters is required, even if there is only one parameter in the list.

A param (parameter) specifies the number of threads of the given type (count), the CPUs to which the threads of the given type are to be bound (cpubind), or both.

The *type* attribute represents an NDB thread type. The thread types supported in MySQL Cluster NDB 7.1 and the range of permitted count values for each are provided in the following list:

• 1dm: Local query handler (DBLQH kernel block) that handles data. The more LDM threads that are used, the more highly partitioned the data becomes. Each LDM thread maintains its own sets of data and index partitions, as well as its own redo log. In MySQL Cluster NDB 7.1, the maximum is 4 such threads.

Range: 1 - 4.

tc: Transaction coordinator thread (DBTC kernel block) containing the state of an ongoing transaction.
 In MySQL Cluster NDB 7.1, there can be only 1 TC thread. (In MySQL Cluster NDB 7.2, this number is configurable.)

Range: 1 only.

 main: Data dictionary and transaction coordinator (DBDIH and DBTC kernel blocks), providing schema management. This is always handled by a single dedicated thread.

Range: 1 only.

 recv: Receive thread (CMVMI kernel block). Each receive thread handles one or more sockets for communicating with other nodes in a MySQL Cluster, with one socket per node. Previously, this was limited to a single thread, but MySQL Cluster 7.2 implements multiple receive threads (up to 8).

Range: 1 only.

• rep: Replication thread (SUMA kernel block). Asynchronous replication operations are always handled by a single.dedicated thread.

Range: 1 only.

• io: File system and other miscellaneous operations. These are not demanding tasks, and are always handled as a group by a single, dedicated I/O thread.

Range: 1 only.

# Simple examples:

```
# Example 1.
ThreadConfig=ldm={count=2,cpubind=1,2},main={cpubind=12},rep={cpubind=11}
# Example 2.
Threadconfig=main={cpubind=0},ldm={count=4,cpubind=1,2,5,6},io={cpubind=3}
```

It is usually desirable when configuring thread usage for a data node host to reserve one or more CPUs for operating system and other tasks. Thus, for a host machine with 8 CPUs, you might want to use 8 CPU threads bound to 7 CPUs (leaving one for operating system and other functions), with 4 LDM threads, 1 TC thread, 1 receive thread, and 1 thread each for schema management, asynchronous replication, and I/O operations. (This is almost the same distribution of threads used when MaxNoOfExecutionThreads is set equal to 8.) The following ThreadConfig setting performs these assignments, additionally binding all of these threads to specific CPUs:

```
ThreadConfig=ldm{count=4,cpubind=1,2,3,4},main={cpubind=5}, \
io={cpubind=5},rep={cpubind=6},tc{cpubind=7},recv={cpubind=8}
```

It should be possible in most cases to bind the main (schema management) thread and the I/O thread to the same CPU, as we have done in the example just shown.

In order to take advantage of the enhanced stability that the use of ThreadConfig offers, it is necessary to insure that CPUs are isolated, and that they not subject to interrupts, or to being scheduled for other tasks by the operating system. On many Linux systems, you can do this by setting IRQBALANCE\_BANNED\_CPUS in /etc/sysconfig/irqbalance to 0xfffff0, and by using the isolcpus boot option in grub.conf. For specific information, see your operating system or platform documentation.

In MySQL Cluster NDB 7.1 and earlier, it is not possible to cause ndbmtd to use more than 1 TC thread; this capability is introduced in MySQL Cluster NDB 7.2.

**Disk Data Configuration Parameters.** Configuration parameters affecting Disk Data behavior include the following:

# • DiskPageBufferMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.6	bytes	64M	4M - 1T	S

This determines the amount of space used for caching pages on disk, and is set in the [ndbd] or [ndbd] default] section of the config.ini file. It is measured in bytes. Each page takes up 32 KB. This means that Cluster Disk Data storage always uses N \* 32 KB memory where N \* 32 KB mem

The default value for this parameter is 64M (2000 pages of 32 KB each).

This parameter was added in MySQL 5.1.6.

Beginning with MySQL Cluster NDB 7.1.9, you can query the ndbinfo.diskpagebuffer table to help determine whether the value for this parameter should be increased to minimize unnecessary disk seeks. See Section 7.10.8, "The ndbinfo diskpagebuffer Table", for more information.

### SharedGlobalMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.2.0	bytes	128M	0 - 64T	S
MySQL 5.1.6	bytes	20M	0 - 64T	S

This parameter determines the amount of memory that is used for log buffers, disk operations (such as page requests and wait queues), and metadata for tablespaces, log file groups, UNDO files, and data files. The shared global memory pool also provides memory used for satisfying the memory requirements of the INITIAL\_SIZE and UNDO\_BUFFER\_SIZE options used with CREATE LOGFILE GROUP and ALTER LOGFILE GROUP statements, including any default value implied for these options by the setting of the InitialLogFileGroup data node configuration parameter. SharedGlobalMemory can be set in the [ndbd] or [ndbd default] section of the config.ini configuration file, and is measured in bytes.

As of MySQL Cluster NDB 7.2.0, the default value is 128M. (Previously, this was 20M.)

This parameter was added in MySQL 5.1.6.

# • DiskIOThreadPool

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.3	threads	8	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.7	threads	2	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.0	threads	2	0 - 4294967039 (0xFFFFFEFF)	S

This parameter determines the number of unbound threads used for Disk Data file access. Before <code>DiskIOThreadPool</code> was introduced, exactly one thread was spawned for each Disk Data file, which could lead to performance issues, particularly when using very large data files. With <code>DiskIOThreadPool</code>, you can—for example—access a single large data file using several threads working in parallel.

This parameter applies to Disk Data I/O threads only.

The optimum value for this parameter depends on your hardware and configuration, and includes these factors:

- Physical distribution of Disk Data files. You can obtain better performance by placing data files, undo log files, and the data node file system on separate physical disks. If you do this with some or all of these sets of files, then you can set DiskIOThreadPool higher to enable separate threads to handle the files on each disk.
- **Disk performance and types.** The number of threads that can be accommodated for Disk Data file handling is also dependent on the speed and throughput of the disks. Faster disks and higher throughput allow for more disk I/O threads. Our test results indicate that solid-state disk drives can handle many more disk I/O threads than conventional disks, and thus higher values for <code>DiskIOThreadPool</code>.

This parameter was added in MySQL Cluster NDB 6.4.0. Previous to MySQL Cluster NDB 6.4.3, it was named IOThreadPool. Previous to MySQL Cluster NDB 7.0.7, the default value was 8. Beginning with MySQL Cluster NDB 7.0.7 and MySQL Cluster NDB 7.1.0, the default is 2.

- **Disk Data file system parameters.** The parameters in the following list were added in MySQL Cluster NDB 6.2.17, 6.3.22, and 6.4.3 to make it possible to place MySQL Cluster Disk Data files in specific directories without the need for using symbolic links.
  - FileSystemPathDD

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.22	filename	[see text]		S
NDB 6.2.17	filename	[see text]		S
NDB 6.4.3	filename	[see text]		S

If this parameter is specified, then MySQL Cluster Disk Data data files and undo log files are placed in the indicated directory. This can be overridden for data files, undo log files, or both, by specifying values for FileSystemPathDataFiles, FileSystemPathUndoFiles, or both, as explained for these parameters. It can also be overridden for data files by specifying a path in the ADD DATAFILE clause of a CREATE TABLESPACE or ALTER TABLESPACE statement, and for undo log files by specifying a path in the ADD UNDOFILE clause of a CREATE LOGFILE GROUP or ALTER LOGFILE GROUP statement. If FileSystemPathDD is not specified, then FileSystemPath is used.

If a FileSystemPathDD directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

FileSystemPathDataFiles

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.22	filename	[see text]		S
NDB 6.2.17	filename	[see text]		S
NDB 6.4.3	filename	[see text]		S

If this parameter is specified, then MySQL Cluster Disk Data data files are placed in the indicated directory. This overrides any value set for FileSystemPathDD. This parameter can be overridden

for a given data file by specifying a path in the ADD DATAFILE clause of a CREATE TABLESPACE or ALTER TABLESPACE statement used to create that data file. If FileSystemPathDataFiles is not specified, then FileSystemPathDD is used (or FileSystemPath, if FileSystemPathDD has also not been set).

If a FileSystemPathDataFiles directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

• FileSystemPathUndoFiles

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.22	filename	[see text]		S
NDB 6.2.17	filename	[see text]		S
NDB 6.4.3	filename	[see text]		S

If this parameter is specified, then MySQL Cluster Disk Data undo log files are placed in the indicated directory. This overrides any value set for FileSystemPathDD. This parameter can be overridden for a given data file by specifying a path in the ADD UNDO clause of a CREATE LOGFILE GROUP or CREATE LOGFILE GROUP statement used to create that data file. If FileSystemPathUndoFiles is not specified, then FileSystemPathDD is used (or FileSystemPath, if FileSystemPathDD has also not been set).

If a FileSystemPathUndoFiles directory is specified for a given data node (including the case where the parameter is specified in the [ndbd default] section of the config.ini file), then starting that data node with --initial causes all files in the directory to be deleted.

For more information, see Section 7.12.1, "MySQL Cluster Disk Data Objects".

- **Disk Data object creation parameters.** The next two parameters enable you—when starting the cluster for the first time—to cause a Disk Data log file group, tablespace, or both, to be created without the use of SQL statements.
  - InitialLogFileGroup

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.22	string	[see text]		S
NDB 6.2.17	string	[see text]		S
NDB 6.4.3	string	[see text]		S

This parameter can be used to specify a log file group that is created when performing an initial start of the cluster. InitialLogFileGroup is specified as shown here:

```
InitialLogFileGroup = [name=name;] [undo_buffer_size=size;] file-specification-list
file-specification-list:
    file-specification[; file-specification[; ...]]
file-specification:
    filename:size
```

The name of the log file group is optional and defaults to DEFAULT-LG. The undo\_buffer\_size is also optional; if omitted, it defaults to 64M. Each file-specification corresponds to an undo log file, and at least one must be specified in the file-specification-list. Undo log files are placed according to any values that have been set for FileSystemPath, FileSystemPathDD, and

FileSystemPathUndoFiles, just as if they had been created as the result of a CREATE LOGFILE GROUP or ALTER LOGFILE GROUP statement.

### Consider the following:

```
InitialLogFileGroup = name=LG1; undo_buffer_size=128M; undo1.log:250M; undo2.log:150M
```

This is equivalent to the following SQL statements:

```
CREATE LOGFILE GROUP LG1

ADD UNDOFILE 'undo1.log'
INITIAL_SIZE 250M
UNDO_BUFFER_SIZE 128M
ENGINE NDBCLUSTER;

ALTER LOGFILE GROUP LG1
ADD UNDOFILE 'undo2.log'
INITIAL_SIZE 150M
ENGINE NDBCLUSTER;
```

This logfile group is created when the data nodes are started with --initial.

Resources for the initial log file group are taken from the global memory pool whose size is determined by the value of the SharedGlobalMemory data node configuration parameter; if this parameter is set too low and the values set in InitialLogFileGroup for the logfile group's initial size or undo buffer size are too high, the cluster may fail to create the default log file group when starting, or fail to start altogether.

This parameter, if used, should always be set in the <code>[ndbd default]</code> section of the <code>config.ini</code> file. The behavior of a MySQL Cluster when different values are set on different data nodes is not defined.

### InitialTablespace

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.22	string	[see text]		S
NDB 6.2.17	string	[see text]		S
NDB 6.4.3	string	[see text]		S

This parameter can be used to specify a MySQL Cluster Disk Data tablespace that is created when performing an initial start of the cluster. InitialTablespace is specified as shown here:

```
InitialTablespace = [name=name;] [extent_size=size;] file-specification-list
```

The name of the tablespace is optional and defaults to DEFAULT-TS. The extent\_size is also optional; it defaults to 1M. The <code>file-specification-list</code> uses the same syntax as shown with the <code>InitialLogfileGroup</code> parameter, the only difference being that each <code>file-specification</code> used with <code>InitialTablespace</code> corresponds to a data file. At least one must be specified in the <code>file-specification-list</code>. Data files are placed according to any values that have been set for <code>FileSystemPath</code>, <code>FileSystemPathDD</code>, and <code>FileSystemPathDataFiles</code>, just as if they had been created as the result of a <code>CREATE TABLESPACE</code> or <code>ALTER TABLESPACE</code> statement.

For example, consider the following line specifying InitialTablespace in the [ndbd default] section of the config.ini file (as with InitialLogfileGroup, this parameter should always be

set in the [ndbd default] section, as the behavior of a MySQL Cluster when different values are set on different data nodes is not defined):

```
InitialTablespace = name=TS1; extent_size=8M; data1.dat:2G; data2.dat:4G
```

This is equivalent to the following SQL statements:

```
CREATE TABLESPACE TS1

ADD DATAFILE 'data1.dat'

EXTENT_SIZE 8M

INITIAL_SIZE 2G

ENGINE NDBCLUSTER;

ALTER TABLESPACE TS1

ADD UNDOFILE 'data2.dat'

INITIAL_SIZE 4G

ENGINE NDBCLUSTER;
```

This tablespace is created when the data nodes are started with --initial, and can be used whenever creating MySQL Cluster Disk Data tables thereafter.

**Disk Data and GCP Stop errors.** Errors encountered when using Disk Data tables such as Node nodeid killed this node because GCP stop was detected (error 2303) are often referred to as "GCP stop errors". Such errors occur when the redo log is not flushed to disk quickly enough; this is usually due to slow disks and insufficient disk throughput.

You can help prevent these errors from occurring by using faster disks, and by placing Disk Data files on a separate disk from the data node file system. Reducing the value of TimeBetweenGlobalCheckpoints tends to decrease the amount of data to be written for each global checkpoint, and so may provide some protection against redo log buffer overflows when trying to write a global checkpoint; however, reducing this value also permits less time in which to write the GCP, so this must be done with caution.

In addition, adjusting the cluster configuration as discussed here can also help:

• MySQL Cluster NDB 6.2 and 6.3. When working with large amounts of data on disk under high load, the default value for <code>DiskPageBufferMemory</code> may not be large enough. In such cases, you should increase its value to include most of the memory available to the data nodes after accounting for index memory, data memory, internal buffers, and memory needed by the data node host operating system.

You can use this formula as a guide:

```
DiskPageBufferMemory
= 0.8
x (
     [total memory]
     - ([operating system memory] + [buffer memory] + DataMemory + IndexMemory)
)
```

Once you have established that sufficient memory is reserved for <code>DataMemory</code>, <code>IndexMemory</code>, NDB internal buffers, and operating system overhead, it is possible (and sometimes desirable) to allocate more than the above amount of the remainder to <code>DiskPageBufferMemory</code>.

• MySQL Cluster NDB 7.X. In addition to the considerations given for <code>DiskPageBufferMemory</code> as explained previously, it is also very important that the <code>DiskIOThreadPool</code> configuration parameter be set correctly; having <code>DiskIOThreadPool</code> set too high is very likely to cause GCP stop errors (Bug #37227).

GCP stops can be caused by save or commit timeouts; the TimeBetweenEpochsTimeout data node configuration parameter determines the timeout for commits. However, beginning with MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10, it is possible to disable both types of timeouts by setting this parameter to 0.

Parameters for configuring send buffer memory allocation (MySQL Cluster NDB 7.0 and later). Beginning with MySQL Cluster NDB 6.4.0, send buffer memory is allocated dynamically from a memory pool shared between all transporters, which means that the size of the send buffer can be adjusted as necessary. (Previously, the NDB kernel used a fixed-size send buffer for every node in the cluster, which was allocated when the node started and could not be changed while the node was running.) The following data node configuration parameters were added in MySQL Cluster NDB 6.4.0 to permit the setting of limits on this memory allocation; this change is reflected by the addition of the configuration parameters TotalSendBufferMemory and OverLoadLimit, as well as a change in how the existing SendBufferMemory configuration parameter is used. For more information, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

# • ExtraSendBufferMemory

This parameter specifies the amount of transporter send buffer memory to allocate in addition to any set using TotalSendBufferMemory, SendBufferMemory, or both.

This parameter was added in MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20. (Bug #13633845, Bug #11760629, Bug #53053)

### TotalSendBufferMemory

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

Prior to MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, this parameter did not work correctly with ndbmtd. (Bug #13633845)

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039.

### ReservedSendBufferMemory

This parameter is present in NDBCLUSTER source code beginning with MySQL Cluster NDB 6.4.0. However, it is not currently enabled.

As of MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, this parameter is deprecated, and is subject to removal in a future release of MySQL Cluster (Bug #11760629, Bug #53053).

For more detailed information about the behavior and use of TotalSendBufferMemory and about configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

### Note

Previous to MySQL Cluster NDB 7.0, to add new data nodes to a MySQL Cluster, it was necessary to shut down the cluster completely, update the config.ini file, and then restart the cluster (that is, you had to perform a system restart). All data node processes had to be started with the --initial option.

Beginning with MySQL Cluster NDB 7.0, it is possible to add new data node groups to a running cluster online. See Section 7.13, "Adding MySQL Cluster Data Nodes Online", for more information.

Redo log over-commit handling. Beginning with MySQL Cluster NDB 7.1.10, it is possible to control the data node's handling of operations when too much time is taken flushing redo logs to disk. This occurs when a given redo log flush takes longer than RedoOverCommitLimit seconds, more than RedoOverCommitCounter times, causing any pending transactions to be aborted. When this happens, the API node that sent the transaction can handle the operations that should have been committed either by queuing the operations and re-trying them, or by aborting them, as determined by DefaultOperationRedoProblemAction. The data node configuration parameters for setting the timeout and number of times it may be exceeded before the API node takes this action are described in the following list:

#### • RedoOverCommitCounter

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.10	numeric	3	0 - 4294967039	S
			(0xFFFFFEFF)	

When RedoOverCommitLimit is exceeded when trying to write a given redo log to disk this many times or more, any transactions that were not committed as a result are aborted, and an API node where any of these transactions originated handles the operations making up those transactions according to its value for DefaultOperationRedoProblemAction (by either queuing the operations to be re-tried, or aborting them).

RedoOverCommitCounter defaults to 3. Set it to 0 to disable the limit. This parameter was added in MySQL Cluster NDB 7.1.10.

# • RedoOverCommitLimit

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.10	seconds	_	0 - 4294967039 (0xFFFFFEFF)	S

This parameter sets an upper limit in seconds for trying to write a given redo log to disk before timing out. The number of times the data node tries to flush this redo log, but takes longer than RedoOverCommitLimit, is kept and compared with RedoOverCommitCounter, and when flushing takes too long more times than the value of that parameter, any transactions that were not committed as a result of the flush timeout are aborted. When this occurs, the API node where any of these transactions originated handles the operations making up those transactions according to its DefaultOperationRedoProblemAction setting (it either queues the operations to be re-tried, or aborts them).

By default, RedoOverCommitLimit is 20 seconds. Set to 0 to disable checking for redo log flush timeouts. This parameter was added in MySQL Cluster NDB 7.1.10.

**Controlling restart attempts.** Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to exercise more finely-grained control over restart attempts by data nodes when they fail to start using two data node configuration parameters added in these releases. MaxStartFailRetries limits the total number of retries made before giving up on starting the data node; StartFailRetryDelay sets the number of seconds between retry attempts, as described in the following list:

### • StartFailRetryDelay

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.37	unsigned	0	0 - 4294967039 (0xFFFFEFF)	S
NDB 7.0.18	unsigned	0	0 - 4294967039 (0xFFFFEFF)	S
NDB 7.1.7	unsigned	0	0 - 4294967039 (0xFFFFEFF)	S
NDB 6.2.19	unsigned	0	0 - 4294967039 (0xFFFFEFF)	S

Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to set the number of seconds between restart attempts by the data node in the event on failure on startup. The default is 0 (no delay).

# Note

This parameter is ignored unless StopOnError is equal to 0.

### MaxStartFailRetries

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.37	unsigned	3	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.18	unsigned	3	0 - 4294967039 (0xFFFFFEFF)	S
NDB 7.1.7	unsigned	3	0 - 4294967039 (0xFFFFFEFF)	S
NDB 6.2.19	unsigned	3	0 - 4294967039 (0xFFFFFEFF)	S

Beginning in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.37, MySQL Cluster NDB 7.0.18, and MySQL Cluster NDB 7.1.7, it is possible to limit the number restart attempts made by the data node in the event that it fails on startup. The default is 3 attempts.

#### Note

This parameter is ignored unless StopOnError is equal to 0.

# 5.2.7 Defining SQL and Other API Nodes in a MySQL Cluster

The [mysqld] and [api] sections in the config.ini file define the behavior of the MySQL servers (SQL nodes) and other applications (API nodes) used to access cluster data. None of the parameters shown is required. If no computer or host name is provided, any host can use this SQL or API node.

Generally speaking, a [mysqld] section is used to indicate a MySQL server providing an SQL interface to the cluster, and an [api] section is used for applications other than mysqld processes accessing cluster data, but the two designations are actually synonymous; you can, for instance, list parameters for a MySQL server acting as an SQL node in an [api] section.

### Note

For a discussion of MySQL server options for MySQL Cluster, see Section 5.4.2, "MySQL Server Options for MySQL Cluster"; for information about MySQL server system variables relating to MySQL Cluster, see Section 5.4.3, "MySQL Cluster System Variables".

### • Id

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 63	S
NDB 6.1.1	unsigned	[none]	1 - 255	S

The Id is an integer value used to identify the node in all cluster internal messages. Prior to MySQL Cluster NDB 6.1.1, the permitted range of values for this parameter was 1 to 63 inclusive. Beginning with MySQL Cluster NDB 6.1.1, the permitted range is 1 to 255 inclusive. This value must be unique for each node in the cluster, regardless of the type of node.

### Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for API nodes (and management nodes) to values greater than 48.

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

### • ConnectionMap

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.0	string	[none]		S

Specifies which data nodes to connect. Introduced in MySQL Cluster NDB 6.1.0.

### • NodeId

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	1 - 63	S
NDB 6.1.1	unsigned	[none]	1 - 255	S

The NodeId is an integer value used to identify the node in all cluster internal messages. Prior to MySQL Cluster NDB 6.1.1, the permitted range of values for this parameter was 1 to 63 inclusive. Beginning with MySQL Cluster NDB 6.1.1, the permitted range is 1 to 255 inclusive. This value must be unique for each node in the cluster, regardless of the type of node.

### Note

Data node IDs must be less than 49, regardless of the MySQL Cluster version used. If you plan to deploy a large number of data nodes, it is a good idea to limit the node IDs for API nodes (and management nodes) to values greater than 48.

NodeId is the preferred parameter name to use when identifying management nodes beginning with MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.39, MySQL Cluster NDB 7.0.20, and MySQL Cluster NDB 7.1.9. Although Id continues to be supported for backward compatibility, it is now deprecated and generates a warning when used.

#### • ExecuteOnComputer

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name	[none]		S

This refers to the Id set for one of the computers (hosts) defined in a [computer] section of the configuration file.

### • HostName

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

Specifying this parameter defines the hostname of the computer on which the SQL node (API node) is to reside. To specify a hostname, either this parameter or ExecuteOnComputer is required.

If no HostName or ExecuteOnComputer is specified in a given [mysql] or [api] section of the config.ini file, then an SQL or API node may connect using the corresponding "slot" from any host which can establish a network connection to the management server host machine. This differs from the default behavior for data nodes, where localhost is assumed for HostName unless otherwise specified.

### • ArbitrationRank

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	0-2	0	0 - 2	S

This parameter defines which nodes can act as arbitrators. Both management nodes and SQL nodes can be arbitrators. A value of 0 means that the given node is never used as an arbitrator, a value of 1 gives the node high priority as an arbitrator, and a value of 2 gives it low priority. A normal configuration uses the management server as arbitrator, setting its ArbitrationRank to 1 (the default for management nodes) and those for all SQL nodes to 0 (the default for SQL nodes).

Beginning with MySQL 5.1.16 and MySQL Cluster NDB 6.1.3, it is possible to disable arbitration completely by setting ArbitrationRank to 0 on all management and SQL nodes. In MySQL Cluster NDB 7.0.7 and later releases, you can also control arbitration by overriding this parameter; to do this, set the Arbitration parameter in the [ndbd default] section of the config.ini global configuration file.

# ArbitrationDelay

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	milliseconds	_	0 - 4294967039 (0xFFFFFEFF)	S

Setting this parameter to any other value than 0 (the default) means that responses by the arbitrator to arbitration requests will be delayed by the stated number of milliseconds. It is usually not necessary to change this value.

# • BatchByteSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	32K	1024 - 1M	S
NDB 7.2.1	bytes	16K	1024 - 1M	S

For queries that are translated into full table scans or range scans on indexes, it is important for best performance to fetch records in properly sized batches. It is possible to set the proper size both in terms of number of records (BatchSize) and in terms of bytes (BatchByteSize). The actual batch size is limited by both parameters.

The speed at which queries are performed can vary by more than 40% depending upon how this parameter is set.

This parameter is measured in bytes. The default value is 32K.

#### • BatchSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	records	64	1 - 992	S
NDB 7.2.1	records	256	1 - 992	S

This parameter is measured in number of records and is by default set to 64. The maximum size is 992.

# • ExtraSendBufferMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.39	bytes	0	0 - 4294967039 (0xFFFFFEFF)	S

This parameter specifies the amount of transporter send buffer memory to allocate in addition to any that has been set using TotalSendBufferMemory, SendBufferMemory, or both.

This parameter was added in MySQL Cluster NDB 7.0.39 and MySQL Cluster NDB 7.1.28. (Bug #14555359)

# • HeartbeatThreadPriority

Beginning with MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2, it is possible to use this parameter to set the scheduling policy and priority of heartbeat threads for management and API nodes.

The syntax for setting this parameter is shown here:

```
HeartbeatThreadPriority = policy[, priority]
policy:
{FIFO | RR}
```

When setting this parameter, you must specify a policy. This is one of FIFO (first in, first in) or RR (round robin). This followed optionally by the priority (an integer).

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	256K	32K - 16M	S

The batch size is the size of each batch sent from each data node. Most scans are performed in parallel to protect the MySQL Server from receiving too much data from many nodes in parallel; this parameter sets a limit to the total batch size over all nodes.

The default value of this parameter is set to 256KB. Its maximum size is 16MB.

#### • TotalSendBufferMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	bytes	256K	0 - 4294967039 (0xFFFFFEFF)	S

This parameter is available beginning with MySQL Cluster NDB 6.4.0. It is used to determine the total amount of memory to allocate on this node for shared send buffer memory among all configured transporters.

If this parameter is set, its minimum permitted value is 256KB; the maxmimum is 4294967039. For more detailed information about the behavior and use of TotalSendBufferMemory and configuring send buffer memory parameters in MySQL Cluster NDB 6.4.0 and later, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

#### • AutoReconnect

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.3.26	boolean	false	true, false	S
NDB 7.0.7	boolean	false	true, false	S

This parameter is available beginning with MySQL Cluster NDB 6.3.26 and MySQL Cluster NDB 7.0.7. By default, its value is false, which forces disconnected API nodes (including MySQL Servers acting as SQL nodes) the use a new connection to the cluster rather than attempting to re-use an existing one, which can cause problems when using dynamically-allocated node IDs. (Bug #45921)

#### Note

This parameter can be overridden using the NDB API. For more information, see Ndb\_cluster\_connection::set\_auto\_reconnect(), and Ndb\_cluster\_connection::get\_auto\_reconnect().

## • DefaultOperationRedoProblemAction

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 7.1.10	enumeration	ABORT	ABORT, QUEUE	S
NDB 7.2.1	enumeration	ABORT	ABORT, QUEUE	S

This parameter was introduced in MySQL Cluster NDB 7.1.10 (along with RedoOverCommitLimit and RedoOverCommitCounter) for controlling the data node's handling of operations when too much time is taken flushing redo logs to disk. This occurs when a given redo log flush takes longer than RedoOverCommitLimit seconds, more than RedoOverCommitCounter times, causing any pending transactions to be aborted.

When this happens, the node can respond in either of two ways, according to the value of DefaultOperationRedoProblemAction, listed here:

- ABORT: Any pending operations from aborted transactions are also aborted.
- QUEUE: Pending operations from transactions that were aborted are queued up to be re-tried.

Prior to MySQL Cluster NDB 7.1.26, setting this parameter did not have any effect. (Bug #15855588)

DefaultHashMapSize

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 7.0.38	LDM threads	240	0 - 3840	S
NDB 7.1.27	LDM threads	240	0 - 3840	S

Beginning with MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.26, the size of the table hash maps used by NDB is configurable using this parameter; previously this value was hard-coded. DefaultHashMapSize can take any of three possible values (0, 240, 3840). These values and their effects are described in the following table.

Value	Description / Effect
0	Use the lowest value set, if any, for this parameter among all data nodes and API nodes in the cluster; if it is not set on any data or API node, use the default value.
240	Original hash map size used by default in all MySQL Cluster NDB 7.1 and MySQL Cluster NDB 7.0 (and earlier) releases; effectively the only value prior to versions 7.0.38 and 7.1.26 (when this parameter was introduced).
3840	Larger hash map size available beginning with MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.26

The primary intended use for this parameter is to facilitate upgrades and especially downgrades between MySQL Cluster NDB 7.1 and later MySQL Cluster versions in which the larger hash map size (3840) is the default; by setting this parameter to 240 prior to performing an upgrade, you can cause the cluster to continue using the smaller size for table hash maps, in which case the tables remain compatible with earlier versions. DefaultHashMapSize can be set for individual data nodes, API nodes, or both, but setting it once only, in the [ndbd default] section of the config.ini file, is the recommended practice. You can also set this parameter to 0, in which case the default value is used.

After increasing this parameter, to have existing tables to take advantage of the new size, you can run ALTER TABLE ... REORGANIZE PARTITION on them, after which they can use the larger hash map size. This is in addition to performing a rolling restart, which makes the larger hash maps available to new tables, but does not enable existing tables to use them.

Decreasing this parameter online after any tables have been created or modified with DefaultHashMapSize equal to 3840 is not currently supported.

• Wan

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	boolean	false	true, false	S

Use WAN TCP setting as default. Introduced in MySQL Cluster NDB 6.1.1.

You can obtain some information from a MySQL server running as a Cluster SQL node using SHOW STATUS in the mysql client, as shown here:

For information about these Cluster system status variables, see Server Status Variables.

#### Note

To add new SQL or API nodes to the configuration of a running MySQL Cluster, it is necessary to perform a rolling restart of all cluster nodes after adding new [mysqld] or [api] sections to the config.ini file (or files, if you are using more than one management server). This must be done before the new SQL or API nodes can connect to the cluster.

It is *not* necessary to perform any restart of the cluster if new SQL or API nodes can employ previously unused API slots in the cluster configuration to connect to the cluster.

## 5.2.8 MySQL Cluster TCP/IP Connections

TCP/IP is the default transport mechanism for all connections between nodes in a MySQL Cluster. Normally it is not necessary to define TCP/IP connections; MySQL Cluster automatically sets up such connections for all data nodes, management nodes, and SQL or API nodes.

#### Note

For an exception to this rule, see Section 5.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections".

To override the default connection parameters, it is necessary to define a connection using one or more <code>[tcp]</code> sections in the <code>config.ini</code> file. Each <code>[tcp]</code> section explicitly defines a TCP/IP connection between two MySQL Cluster nodes, and must contain at a minimum the parameters <code>NodeId1</code> and <code>NodeId2[176]</code>, as well as any connection parameters to override.

It is also possible to change the default values for these parameters by setting them in the [tcp default] section.

## **Important**

Any [tcp] sections in the config.ini file should be listed *last*, following all other sections in the file. However, this is not required for a [tcp default] section. This requirement is a known issue with the way in which the config.ini file is read by the MySQL Cluster management server.

Connection parameters which can be set in [tcp] and [tcp default] sections of the config.ini file are listed here:

• NodeId1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

#### NodeId2

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

To identify a connection between two nodes it is necessary to provide their node IDs in the [tcp] section of the configuration file. These are the same unique NodeId (or Id) values for each of these nodes as described in Section 5.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

## • HostName1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

#### HostName2

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given TCP connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

## • OverloadLimit

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	bytes	0	0 - 4294967039	S
			(0xFFFFFEFF)	

Beginning in MySQL Cluster NDB 6.4.0, this parameter can be used to determine the amount of unsent data that must be present in the send buffer before the connection is considered overloaded. See Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters", for more information.

Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, the effective value of this parameter was limited by the size of SendBufferMemory; beginning with these releases, the actual value for OverloadLimit (up to the stated maximum of 4G) is used instead.

## • SendBufferMemory

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	256K	64K - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	unsigned	2M76	256K - 4294967039 (0xFFFFFEFF)	S

TCP transporters use a buffer to store all messages before performing the send call to the operating system. When this buffer reaches 64KB its contents are sent; these are also sent when a round of messages have been executed. To handle temporary overload situations it is also possible to define a bigger send buffer.

Prior to MySQL Cluster NDB 7.0, this parameter determines a fixed amount of memory allocated at startup for each configured TCP connection. Beginning with MySQL Cluster NDB 6.4.0, if this parameter is set explicitly, then the memory is not dedicated to each transporter; instead, the value used denotes the hard limit for how much memory (out of the total available memory—that is, TotalSendBufferMemory) that may be used by a single transporter. For more information about configuring dynamic transporter send buffer memory allocation in MySQL Cluster NDB 7.0 and later, see Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters".

In MySQL Cluster NDB 6.4.3 and earlier, the default size of the send buffer was 256 KB; in MySQL Cluster NDB 7.0.4 and later, it is 2MB, which is the size recommended in most situations. The minimum size is 64 KB; the theoretical maximum is 4 GB.

### • SendSignalId

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	[see text]	true, false	S

To be able to retrace a distributed message datagram, it is necessary to identify each message. When this parameter is set to Y, message IDs are transported over the network. This feature is disabled by default in production builds, and enabled in -debug builds.

#### Checksum

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	false	true, false	S

This parameter is a boolean parameter (enabled by setting it to  $\underline{v}$  or  $\underline{1}$ , disabled by setting it to  $\underline{v}$  or  $\underline{0}$ ). It is disabled by default. When it is enabled, checksums for all messages are calculated before they placed in the send buffer. This feature ensures that messages are not corrupted while waiting in the send buffer, or by the transport mechanism.

## • PortNumber (OBSOLETE)

This formerly specified the port number to be used for listening for connections from other nodes. This parameter should no longer be used; use the ServerPort data node configuration parameter for this purpose instead.

#### ReceiveBufferMemory

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	64K	16K - 4294967039 (0xFFFFFEFF)	S
NDB 7.0.4	bytes	2M	16K - 4294967039 (0xFFFFEFF)	S

Specifies the size of the buffer used when receiving data from the TCP/IP socket.

In MySQL Cluster NDB 6.4.3 and earlier, the default value of this parameter was 64 KB; beginning with MySQL Cluster NDB 7.0.4, 2MB is the default. The minimum possible value is 16KB; the theoretical maximum is 4GB.

## • TCP RCV BUF SIZE

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	unsigned	70080	1 - 2G	S

Determines the size of the receive buffer set during TCP transporter initialization. The default is recommended for most common usage cases.

TCP\_RCV\_BUF\_SIZE was added in MySQL Cluster NDB 6.1.1.

## • TCP\_SND\_BUF\_SIZE

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	unsigned	71540	1 - 2G	S

Determines the size of the send buffer set during TCP transporter initialization. The default is recommended for most common usage cases.

TCP\_SND\_BUF\_SIZE was added in MySQL Cluster NDB 6.1.1.

#### • TCP MAXSEG SIZE

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.1.1	unsigned	0	0 - 2G	S

Determines the size of the memory set during TCP transporter initialization. The default is recommended for most common usage cases.

TCP MAXSEG SIZE was added in MySQL Cluster NDB 6.1.1.

### • TcpBind INADDR ANY

Setting this parameter to TRUE or 1 binds IP\_ADDR\_ANY so that connections can be made from anywhere (for autogenerated connections). The default is FALSE (0).

This parameter was added in MySQL Cluster NDB 6.2.0.

# 5.2.9 MySQL Cluster TCP/IP Connections Using Direct Connections

Setting up a cluster using direct connections between data nodes requires specifying explicitly the crossover IP addresses of the data nodes so connected in the [tcp] section of the cluster config.ini file.

In the following example, we envision a cluster with at least four hosts, one each for a management server, an SQL node, and two data nodes. The cluster as a whole resides on the 172.23.72.\* subnet of a LAN. In addition to the usual network connections, the two data nodes are connected directly using a standard crossover cable, and communicate with one another directly using IP addresses in the 1.1.0.\* address range as shown:

# Management Server

```
[ndb_mgmd]
Id=1
HostName=172.23.72.20
# SQL Node
[mysqld]
Td=2
HostName=172.23.72.21
# Data Nodes
[ndbd]
Id=3
HostName=172.23.72.22
[ndbd]
Id=4
HostName=172.23.72.23
# TCP/IP Connections
[tcp]
NodeId1=3
NodeId2=4
HostName1=1.1.0.1
HostName2=1.1.0.2
```

The HostName1 and HostName2 [176] parameters are used only when specifying direct connections.

The use of direct TCP connections between data nodes can improve the cluster's overall efficiency by enabling the data nodes to bypass an Ethernet device such as a switch, hub, or router, thus cutting down on the cluster's latency. It is important to note that to take the best advantage of direct connections in this fashion with more than two data nodes, you must have a direct connection between each data node and every other data node in the same node group.

## 5.2.10 MySQL Cluster Shared-Memory Connections

MySQL Cluster attempts to use the shared memory transporter and configure it automatically where possible. [shm] sections in the config.ini file explicitly define shared-memory connections between nodes in the cluster. When explicitly defining shared memory as the connection method, it is necessary to define at least NodeId1, NodeId2 [179], and ShmKey. All other parameters have default values that should work well in most cases.

#### **Important**

SHM functionality is considered experimental only. It is not officially supported in any current MySQL Cluster release, and testing results indicate that SHM performance is not appreciably greater than when using TCP/IP for the transporter.

For these reasons, you must determine for yourself or by using our free resources (forums, mailing lists) whether SHM can be made to work correctly in your specific case.

### • NodeId1

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

#### NodeId2

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

To identify a connection between two nodes it is necessary to provide node identifiers for each of them, as NodeId1 and NodeId2.

## • HostName1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

#### HostName2

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given SHM connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

#### OverloadLimit

Effective Version	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	bytes	0	0 - 4294967039	S
			(0xFFFFFEFF)	

Beginning in MySQL Cluster NDB 6.4.0, this parameter can be used to determine the amount of unsent data that must be present in the send buffer before the connection is considered overloaded. See Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters", for more information.

Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, the effective value of this parameter was limited by the size of SendBufferMemory; beginning with these releases, the actual value for OverloadLimit (up to the stated maximum) is used instead.

## ShmKey

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	0 - 4294967039 (0xFFFFFEFF)	S

When setting up shared memory segments, a node ID, expressed as an integer, is used to identify uniquely the shared memory segment to use for the communication. There is no default value.

## • ShmSize

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	bytes	1M	64K - 4294967039 (0xFFFFFEFF)	S

Each SHM connection has a shared memory segment where messages between nodes are placed by the sender and read by the reader. The size of this segment is defined by ShmSize. The default value is 1MB.

### SendSignalId

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	false	true, false	S

To retrace the path of a distributed message, it is necessary to provide each message with a unique identifier. Setting this parameter to Y causes these message IDs to be transported over the network as well. This feature is disabled by default in production builds, and enabled in -debug builds.

#### • Checksum

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	true	true, false	S

This parameter is a boolean (Y/N) parameter which is disabled by default. When it is enabled, checksums for all messages are calculated before being placed in the send buffer.

This feature prevents messages from being corrupted while waiting in the send buffer. It also serves as a check against data being corrupted during transport.

### • SigNum

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	L 3	0 - 4294967039 (0xFFFFFEFF)	S

When using the shared memory transporter, a process sends an operating system signal to the other process when there is new data available in the shared memory. Should that signal conflict with an existing signal, this parameter can be used to change it. This is a possibility when using SHM due to the fact that different operating systems use different signal numbers.

The default value of SigNum is 0; therefore, it must be set to avoid errors in the cluster log when using the shared memory transporter. Typically, this parameter is set to 10 in the [shm default] section of the config.ini file.

# **5.2.11 SCI Transport Connections in MySQL Cluster**

[sci] sections in the config.ini file explicitly define SCI (Scalable Coherent Interface) connections between cluster nodes. Using SCI transporters in MySQL Cluster is supported only when the MySQL binaries are built using --with-ndb-sci=/your/path/to/SCI. The path should point to a directory that contains at a minimum lib and include directories containing SISCI libraries and header files. (See Section 5.5, "Using High-Speed Interconnects with MySQL Cluster" for more information about SCI.)

In addition, SCI requires specialized hardware.

It is strongly recommended to use SCI Transporters only for communication between ndbd processes. Note also that using SCI Transporters means that the ndbd processes never sleep. For this reason, SCI Transporters should be used only on machines having at least two CPUs dedicated for use by ndbd processes. There should be at least one CPU per ndbd process, with at least one CPU left in reserve to handle operating system activities.

#### • NodeId1

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	numeric	[none]		S

To identify a connection between two nodes it is necessary to provide node identifiers for each of them, as NodeId1 and NodeId2.

## • Host1SciId0

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	0 - 4294967039 (0xFFFFEFF)	S

This identifies the SCI node ID on the first Cluster node (identified by NodeId1).

## • Host1SciId1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	0	0 - 4294967039	S
			(0xFFFFFEFF)	

It is possible to set up SCI Transporters for failover between two SCI cards which then should use separate networks between the nodes. This identifies the node ID and the second SCI card to be used on the first node.

## • Host2SciId0

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	[none]	0 - 4294967039 (0xFFFFFEFF)	S

This identifies the SCI node ID on the second Cluster node (identified by NodeId2 [181]).

## • Host2SciId1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	0	0 - 4294967039	S
			(0xFFFFFEFF)	

When using two SCI cards to provide failover, this parameter identifies the second SCI card to be used on the second node.

## HostName1

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

#### HostName2

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	name or IP address	[none]		S

The HostName1 and HostName2 parameters can be used to specify specific network interfaces to be used for a given SCI connection between two nodes. The values used for these parameters can be hostnames or IP addresses.

#### • SharedBufferSize

Effective Version	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned		64K - 4294967039 (0xFFFFFEFF)	S

Each SCI transporter has a shared memory segment used for communication between the two nodes. Setting the size of this segment to the default value of 1MB should be sufficient for most applications. Using a smaller value can lead to problems when performing many parallel inserts; if the shared buffer is too small, this can also result in a crash of the ndbd process.

## • SendLimit

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	unsigned	8K	128 - 32K	S

A small buffer in front of the SCI media stores messages before transmitting them over the SCI network. By default, this is set to 8KB. Our benchmarks show that performance is best at 64KB but 16KB reaches within a few percent of this, and there was little if any advantage to increasing it beyond 8KB.

#### • SendSignalId

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	true	true, false	S

To trace a distributed message it is necessary to identify each message uniquely. When this parameter is set to Y, message IDs are transported over the network. This feature is disabled by default in production builds, and enabled in -debug builds.

### • Checksum

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
MySQL 5.1.0	boolean	false	true, false	S

This parameter is a boolean value, and is disabled by default. When Checksum is enabled, checksums are calculated for all messages before they are placed in the send buffer. This feature prevents messages from being corrupted while waiting in the send buffer. It also serves as a check against data being corrupted during transport.

### OverloadLimit

<b>Effective Version</b>	Type/Units	Default	Range/Values	Restart Type
NDB 6.4.0	bytes	=	0 - 4294967039	S
			(0xFFFFFEFF)	

When more than this many unsent bytes are in the send buffer, the connection is considered overloaded. See Section 5.2.13, "Configuring MySQL Cluster Send Buffer Parameters", for more information.

# 5.2.12 Configuring MySQL Cluster Parameters for Local Checkpoints

The parameters discussed in Logging and Checkpointing and in Data Memory, Index Memory, and String Memory that are used to configure local checkpoints for a MySQL Cluster do not exist in isolation, but rather are very much interdepedent on each other. In this section, we illustrate how these parameters—including DataMemory, IndexMemory, NoOfDiskPagesToDiskAfterRestartTUP, NoOfDiskPagesToDiskAfterRestartACC, and NoOfFragmentLogFiles—relate to one another in a working Cluster.

## **Important**

The parameters NoOfDiskPagesToDiskAfterRestartTUP and NoOfDiskPagesToDiskAfterRestartACC were deprecated in MySQL 5.1.6. From MySQL 5.1.6 through 5.1.11, disk writes during LCPs took place at the maximum speed possible. Beginning with MySQL 5.1.12, the speed and throughput for LCPs are controlled using the parameters DiskSyncSize, DiskCheckpointSpeed, and DiskCheckpointSpeedInRestart. See Section 5.2.6, "Defining MySQL Cluster Data Nodes".

In this example, we assume that our application performs the following numbers of types of operations per hour:

- 50000 selects
- 15000 inserts
- 15000 updates
- 15000 deletes

We also make the following assumptions about the data used in the application:

- · We are working with a single table having 40 columns.
- Each column can hold up to 32 bytes of data.
- A typical UPDATE run by the application affects the values of 5 columns.
- No NULL values are inserted by the application.

A good starting point is to determine the amount of time that should elapse between local checkpoints (LCPs). It is worth noting that, in the event of a system restart, it takes 40-60 percent of this interval to execute the REDO log—for example, if the time between LCPs is 5 minutes (300 seconds), then it should take 2 to 3 minutes (120 to 180 seconds) for the REDO log to be read.

The maximum amount of data per node can be assumed to be the size of the <code>DataMemory</code> parameter. In this example, we assume that this is 2 GB. The <code>NoOfDiskPagesToDiskAfterRestartTUP</code> parameter represents the amount of data to be checkpointed per unit time—however, this parameter is actually expressed as the number of 8K memory pages to be checkpointed per 100 milliseconds. 2 GB per 300 seconds is approximately 6.8 MB per second, or 700 KB per 100 milliseconds, which works out to roughly 85 pages per 100 milliseconds.

Similarly, we can calculate NoOfDiskPagesToDiskAfterRestartACC in terms of the time for local checkpoints and the amount of memory required for indexes—that is, the IndexMemory. Assuming that we permit 512 MB for indexes, this works out to approximately 20 8-KB pages per 100 milliseconds for this parameter.

Next, we need to determine the number of REDO log files required—that is, fragment log files—the corresponding parameter being NoOfFragmentLogFiles. We need to make sure that there are sufficient REDO log files for keeping records for at least 3 local checkpoints (in MySQL Cluster NDB 6.3.8 and later, we need only allow for 2 local checkpoints). In a production setting, there are always uncertainties—for instance, we cannot be sure that disks always operate at top speed or with maximum throughput. For this reason, it is best to err on the side of caution, so we double our requirement and calculate a number of fragment log files which should be enough to keep records covering 6 local checkpoints (in MySQL Cluster NDB 6.3.8 and later, a number of fragment log files accommodating 4 local checkpoints should be sufficient).

It is also important to remember that the disk also handles writes to the REDO log, so if you find that the amount of data being written to disk as determined by the values of NoOfDiskPagesToDiskAfterRestartACC and NoOfDiskPagesToDiskAfterRestartTUP is approaching the amount of disk bandwidth available, you may wish to increase the time between local checkpoints.

Given 5 minutes (300 seconds) per local checkpoint, this means that we need to support writing log records at maximum speed for 6 \* 300 = 1800 seconds (*MySQL Cluster NDB 6.3.8 and later.* 4 \* 300 = 1200 seconds). The size of a REDO log record is 72 bytes plus 4 bytes per updated column value plus the maximum size of the updated column, and there is one REDO log record for each table record updated in a transaction, on each node where the data reside. Using the numbers of operations set out previously in this section, we derive the following:

- 50000 select operations per hour yields 0 log records (and thus 0 bytes), since SELECT statements are not recorded in the REDO log.
- 15000 DELETE statements per hour is approximately 5 delete operations per second. (Since we wish to be conservative in our estimate, we round up here and in the following calculations.) No columns are updated by deletes, so these statements consume only 5 operations \* 72 bytes per operation = 360 bytes per second.
- 15000 UPDATE statements per hour is roughly the same as 5 updates per second. Each update uses 72 bytes, plus 4 bytes per column \* 5 columns updated, plus 32 bytes per column \* 5 columns—this works out to 72 + 20 + 160 = 252 bytes per operation, and multiplying this by 5 operation per second yields 1260 bytes per second.
- 15000 INSERT statements per hour is equivalent to 5 insert operations per second. Each insert requires REDO log space of 72 bytes, plus 4 bytes per record \* 40 columns, plus 32 bytes per column \* 40 columns, which is 72 + 160 + 1280 = 1512 bytes per operation. This times 5 operations per second yields 7560 bytes per second.

So the total number of REDO log bytes being written per second is approximately 0 + 360 + 1260 + 7560 = 9180 bytes. Multiplied by 1800 seconds, this yields 16524000 bytes required for REDO logging, or approximately 15.75 MB. The unit used for NoOfFragmentLogFiles represents a set of 4 16-MB log files—that is, 64 MB. Thus, the minimum value (3) for this parameter is sufficient for the scenario envisioned in this example, since 3 times 64 = 192 MB, or about 12 times what is required; the default value of 8 (or 512 MB) is more than ample in this case.

# 5.2.13 Configuring MySQL Cluster Send Buffer Parameters

Formerly, the NDB kernel used a send buffer whose size was fixed at 2MB for every node in the cluster, which was allocated when the node started. Because the size of this buffer could not be changed after the cluster was started, it was necessary to make it large enough in advance to accommodate the maximum possible load on any transporter socket. However, this was an inefficient use of memory, since much of it often went unused, and could result in large amounts of resources being wasted when scaling up to many API nodes.

Beginning with MySQL Cluster NDB 7.0, this problem is solved by employing a unified send buffer whose memory is allocated dynamically from a pool shared by all transporters. This means that the size of the send buffer can be adjusted as necessary. Configuration of the unified send buffer can accomplished by setting the following parameters:

• TotalSendBufferMemory. This parameter can be set for all types of MySQL Cluster nodes—that is, it can be set in the [ndbd], [mgm], and [api] (or [mysql]) sections of the config.ini file. It represents the total amount of memory (in bytes) to be allocated by each node for which it is set for use among all configured transporters. If set, its minimum is 256KB; the maximum is 4294967039.

To be backward-compatible with existing configurations, this parameter takes as its default value the sum of the maximum send buffer sizes of all configured transporters, plus an additional 32KB (one page) per transporter. The maximum depends on the type of transporter, as shown in the following table:

Transporter	Maximum Send Buffer Size (bytes)	
TCP	SendBufferMemory (default = 2M)	
SCI	SendLimit (default = 8K) plus 16K	
SHM	20K	

This enables existing configurations to function in close to the same way as they did with MySQL Cluster NDB 6.3 and earlier, with the same amount of memory and send buffer space available to each transporter. However, memory that is unused by one transporter is not available to other transporters.

- OverloadLimit. This parameter is used in the config.ini file [tcp] section, and denotes the amount of unsent data (in bytes) that must be present in the send buffer before the connection is considered overloaded. When such an overload condition occurs, transactions that affect the overloaded connection fail with NDB API Error 1218 (Send Buffers overloaded in NDB kernel) until the overload status passes. The default value is 0, in which case the effective overload limit is calculated as SendBufferMemory \* 0.8 for a given connection. The maximum value for this parameter is 4G.
- SendBufferMemory. In MySQL Cluster NDB 6.3 and earlier, this TCP configuration parameter represented the amount of memory allocated at startup for each configured TCP connection. Beginning with MySQL Cluster NDB 7.0, this value denotes a hard limit for the amount of memory that may be used by a single transporter out of the entire pool specified by TotalSendBufferMemory. However, the sum of SendBufferMemory for all configured transporters may be greater than the TotalSendBufferMemory that is set for a given node. This is a way to save memory when many nodes are in use, as long as the maximum amount of memory is never required by all transporters at the same time.

# 5.3 Overview of MySQL Cluster Configuration Parameters

The next four sections provide summary tables of MySQL Cluster configuration parameters used in the <code>config.ini</code> file to govern the cluster's functioning. Each table lists the parameters for one of the Cluster node process types (ndbd, ndb\_mgmd, and mysqld), and includes the parameter's type as well as its default, minimum, and maximum values as applicable.

These tables also indicate what type of restart is required (node restart or system restart)—and whether the restart must be done with --initial—to change the value of a given configuration parameter.

When performing a node restart or an initial node restart, all of the cluster's data nodes must be restarted in turn (also referred to as a *rolling restart*). It is possible to update cluster configuration parameters marked as node online—that is, without shutting down the cluster—in this fashion. An initial node restart requires restarting each ndbd process with the --initial option.

A system restart requires a complete shutdown and restart of the entire cluster. An initial system restart requires taking a backup of the cluster, wiping the cluster file system after shutdown, and then restoring from the backup following the restart.

In any cluster restart, all of the cluster's management servers must be restarted for them to read the updated configuration parameter values.

## **Important**

Values for numeric cluster parameters can generally be increased without any problems, although it is advisable to do so progressively, making such adjustments in relatively small increments. Many of these can be increased online, using a rolling restart.

However, decreasing the values of such parameters—whether this is done using a node restart, node initial restart, or even a complete system restart of the cluster—is not to be undertaken lightly; it is recommended that you do so only after careful planning and testing. This is especially true with regard to those parameters that relate to memory usage and disk space, such as MaxNoOfTables, MaxNoOfOrderedIndexes, and MaxNoOfUniqueHashIndexes. In addition, it is the generally the case that configuration parameters relating to memory and disk usage can be raised using a simple node restart, but they require an initial node restart to be lowered.

Because some of these parameters can be used for configuring more than one type of cluster node, they may appear in more than one of the tables.

#### Note

4294967039 often appears as a maximum value in these tables. This value is defined in the NDBCLUSTER sources as MAX\_INT\_RNIL and is equal to 0xFFFFFEFF, or  $2^{32}-2^8-1$ .

# 5.3.1 MySQL Cluster Data Node Configuration Parameters

The summary table in this section provides information about parameters used in the <code>[ndbd]</code> or <code>[ndbd]</code> default] sections of a <code>config.ini</code> file for configuring MySQL Cluster data nodes. For detailed descriptions and other additional information about each of these parameters, see Section 5.2.6, "Defining MySQL Cluster Data Nodes".

Beginning with MySQL Cluster NDB 6.4.0, these parameters also apply to ndbmtd, which is a multi-threaded version of ndbd. For more information, see Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

**Restart types.** Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

**Table 5.1 Data Node Configuration Parameters** 

	Type or Units		
	Default Value		In
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	enumeration		
	Default		
Arbitration	Default, Disabled, WaitExternal	N	NDB 7.0.7
	milliseconds		
	7500		
ArbitrationTimeout	10 / 4294967039 (0xFFFFEFF)	N	NDB 7.2.0
	bytes	N	
BackupDataBufferSize	16M		NDB 7.0.4
	0 / 4294967039 (0xFFFFEFF)		
BackupDataDir	path FileSystemPath	IN	all 5.1- based
	bytes		
	16M		
BackupLogBufferSize	0 / 4294967039 (0xFFFFEFF)	_ N	NDB 7.0.4
	bytes		
	1M		
BackupMaxWriteSize	2K / 4294967039 (0xFFFFEFF)	N	5.1.32
	bytes		
BackupMemory	32M	N	NDB 7.0.4
раскириешот у	0 / 4294967039 (0xFFFFEFF)	IN	100 7.0.4
	seconds		
BackupReportFrequency	0	N	NDB 6.2.3
240114PMCPOTOLIC GAUCHO)	0 / 4294967039 (0xFFFFEFF)		
BackupWriteSize	bytes	N	NDB 7.0.4

	Type or Units		
	Default Value		_
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	256K		
	2K / 4294967039 (0xFFFFEFF)		
	integer		
BatchSizePerLocalScan	256	N	NDB 7.2.1
	1 / 992		
	numeric		
BuildIndexThreads	0	S	NDB 7.0.11
	0 / 128		
	boolean	N	
CompressedBackup	false		NDB 6.3.7
	true, false		
	boolean	N	
CompressedLCP	false		NDB 6.3.7
	true, false		
	string		NDB 7.1.13
ConnectCheckIntervalDelay	1500	N	
	0 / 4294967039 (0xFFFFEFF)		
	boolean		NDB
CrashOnCorruptedTuple	false	S	7.0.28, 5.1.56-
	true, false		ndb-7.1.17
	path		
DataDir		IN	all 5.1- based
			basea
	bytes		
DataMemory	80M	N	all 5.1- based
	1M / 1024G		Sassa
	LDM threads		
DefaultHashMapSize [128]	240	N	NDB 7.1.27
	0 / 3840		
Di shimos so	bytes	NI	E 4 40
DictTrace	undefined	N	5.1.12

	Type or Units			
	Default Value		In	
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)	
	0 / 100			
	bytes			
	10M			
DiskCheckpointSpeed	1M / 4294967039 (0xFFFFEFF)	N	5.1.12	
	bytes			
	100M		all 5.1-	
DiskCheckpointSpeedInRestart	1M / 4294967039 (0xFFFFEFF)	N	based	
	threads	N		
DiskIOThreadPool	2		NDB 7.1.0	
DIBRIOTHI Caar oo i	0 / 4294967039 (0xFFFFEFF)			
	true false (1 0)	IS	all 5.1- based	
Diskless	false			
	true, false			
	bytes		5.1.6	
DiskPageBufferMemory	64M	N		
	4M / 1T			
	bytes			
	4M			
DiskSyncSize	32K / 4294967039 (0xFFFFEFF)	N	5.1.12	
	name			
ExecuteOnComputer	[none]	S	all 5.1- based	
			baooa	
	bytes			
ExtraSendBufferMemory	0	N	NDB 6.4.0	
	0 / 32G			
	path			
FileSystemPath	DataDir 	IN	all 5.1- based	
FileSystemPathDataFiles	filename	IN	NDB 6.4.3	

Parameter Name	Type or Units  Default Value  Minimum/  Maximum  or Permitted  Values	Restart Type	In Version (and later)
	[see text]		
	filename		
  FileSystemPathDD	FileSystemPath	IN	NDB 6.4.3
-			
	filename		
FileSystemPathUndoFiles	[see text]	IN	NDB 6.4.3
	bytes		
FragmentLogFileSize	16M	IN	NDB 6.1.11
	4M / 1G		
	milliseconds	N	all 5.1- based
	1500		
HeartbeatIntervalDbApi	100 / 4294967039 (0xFFFFEFF)		
	milliseconds		NDB 7.2.0
	5000		
HeartbeatIntervalDbDb	10 / 4294967039 (0xFFFFEFF)	N	
	numeric		
HeartbeatOrder	0	S	NDB 7.1.5
	0 / 65535		
HoghNome	name or IP address		all 5.1-
HostName	localhost	S	based
	unsigned		all 5.1-
Id	[none]	IS	based
	1 / 48		
	bytes	N	all 5.1-
IndexMemory	18M		based
	1M / 1T		ND5
InitFragmentLogFiles	[see values]	IN	NDB 6.3.19

Default Value   Minimum		Type or Units		
Parameter Name				
SPARSE, FULL   String     See text   String     See text   String     See text   String   See text   String   See text   String   See text   String   See text   String   See text   String   See text   String   String   See text   See tex	Parameter Name	Maximum or Permitted		Version (and later)
String   [see text]   S   NDB 6.4		SPARSE		
InitialLogFileGroup		SPARSE, FULL		
InitialNoOfOpenFiles		string		
files   27	InitialLogFileGroup	[see text]	S	NDB 6.4.3
27				
InitialNoOfOpenFiles		files		
2094967039   (0xFFFFEFF)		27		
S   NDB 6.4	InitialNoOfOpenFiles	4294967039	N	5.1.9
ToThreadPool		string	S	
threads   8	InitialTablespace	[see text]		NDB 6.4.3
Note				
N		threads		NDB 6.4.0
0 / 4294967039 (0xFFFFEFF)	TOThroadpool	8		
LateAlloc         1	TOTHERAPOOT			
D / 1   Second   GO		numeric		NDB 6.4.0
Second   60	LateAlloc	1	N	
LcpScanProgressTimeout   60		0 / 1		
LockExecuteThreadToCPU		second		
0 / 4294967039   (0xFFFFEFF)	I angan Drograga Timoout	60	N	NDR 7 1 20
LockExecuteThreadToCPU         64K         N         NDB 6.3           CPU ID         [none]         N         NDB 6.4           LockMaintThreadsToCPU         [none]         N         NDB 6.4           LockPagesInMainMemory         0         N         5.1.15           LockPagesInMainMemory         0 / 2         N         all 5.1-	nopscanriogressiimeouc		, N	7.1.29 מטאו
0 / 64K   CPU ID		CPU ID		
CPU ID	LockExecuteThreadToCPU	64K	N	NDB 6.3.4
LockMaintThreadsToCPU  [none]  0/64K  numeric  0  0/2  log level  N  NDB 6.4		0 / 64K		
DockPagesInMainMemory   Dock		CPU ID		
LockPagesInMainMemory  0 N 5.1.15 0/2  log level N all 5.1-	LockMaintThreadsToCPU	[none]	N	NDB 6.4.0
LockPagesInMainMemory  0 N 5.1.15 0/2 log level N all 5.1-		0 / 64K		
0 / 2 log level N all 5.1-		numeric		
log level N all 5.1-	LockPagesInMainMemory	0	N	5.1.15
LogLevel Checkpoint N		0/2		
Logievel('heckpoint		log level	<b>.</b>	all 5.1-
0   based	LogLevelCheckpoint	0	N	based

Parameter Name	Type or Units		
	Default Value		l.
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0 / 15		
	levelr		
LogLevelCongestion	0	N	all 5.1- based
	0 / 15		Daooa
	integer		
LogLevelConnection	0	N	all 5.1- based
	0 / 15		basea
	integer		
LogLevelError	0	N	all 5.1- based
	0 / 15		basea
	integer		all 5.1- based
LogLevelInfo	0	N	
	0 / 15		
	integer	N	all 5.1- based
LogLevelNodeRestart	0		
	0 / 15		basea
	integer	N	all 5.1- based
LogLevelShutdown	0		
	0 / 15		basea
	integer		
LogLevelStartup	1	N	all 5.1- based
	0 / 15		basea
	integer		
LogLevelStatistic	0	N	all 5.1- based
	0 / 15		basea
	bytes		
	64M		
LongMessageBuffer	512K / 4294967039 (0xFFFFEFF)	N	NDB 7.1.31
MaxAllocate [128]	unsigned		
	32M	N	5.1.20
	1M / 1G		
MaxBufferedEpochs	epochs	N	NDB 6.2.14

	Type or Units		
Parameter Name	Default Value		
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	100		
	0 / 100000		
	bytes		
	26214400		
MaxBufferedEpochBytes	26214400 (0x01900000) / 4294967039 (0xFFFFEFF)	N	NDB 7.1.27
	operations (DML)		
MaxDMLOperationsPerTransaction	4294967295	N	NDB 7.1.15
	32 / 4294967295		
	seconds	N	
MaxLCPStartDelay	0		NDB 6.4.3
	0 / 600		
	integer		all 5.1-
	1000		
MaxNoOfAttributes	32 / 4294967039 (0xFFFFEFF)	N	based
	integer		
MaxNoOfConcurrentIndexOperations	8K	N	all 5.1-
namooreoneurrenemackoperacrons	0 / 4294967039 (0xFFFFEFF)	.,	based
	integer		
	32K		all 5.1-
MaxNoOfConcurrentOperations	32 / 4294967039 (0xFFFFEFF)	N	based
	integer		-U.F.4
MaxNoOfConcurrentScans	256	N	all 5.1- based
	2 / 500		34554
	unsigned		
MaxNoOfConcurrentSubOperations	256	N	NDB 6.3.7
MaxNoOfConcurrentSubOperations	0 / 4294967039 (0xFFFFEFF)		

Parameter Name	Type or Units  Default Value  Minimum/  Maximum  or Permitted  Values	Restart Type	In Version (and later)
MaxNoOfConcurrentTransactions	integer 4096 32 / 4294967039 (0xFFFFEFF)	N	all 5.1- based
MaxNoOfFiredTriggers	integer 4000 0 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxNoOfLocalOperations	integer UNDEFINED 32 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxNoOfLocalScans	integer [see text] 32 / 4294967039 (0xFFFFFEFF)	N	NDB 7.2.0
MaxNoOfOpenFiles	unsigned 0 20 / 4294967039 (0xFFFFFEFF)	N	5.1.16
MaxNoOfOrderedIndexes	integer 128 0 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxNoOfSavedMessages	integer 25 0 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxNoOfSubscribers	unsigned 0 0 / 4294967039 (0xFFFFEFF)	N	NDB 6.3.7
MaxNoOfSubscriptions	unsigned	N	NDB 6.3.7

Parameter Name	Type or Units  Default Value  Minimum/  Maximum  or Permitted  Values	Restart Type	In Version (and later)
	0 0 / 4294967039 (0xFFFFEFF)		
MaxNoOfTables	integer 128 8 / 20320	N	all 5.1- based
MaxNoOfTriggers	integer 768 0 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxNoOfUniqueHashIndexes	integer 64 0 / 4294967039 (0xFFFFFEFF)	N	all 5.1- based
MaxParallelScansPerFragment	bytes 256 1 / 4294967039 (0xFFFFFEFF)	N	NDB 7.2.0
MaxStartFailRetries	unsigned 3 0 / 4294967039 (0xFFFFEFF)	N	NDB 6.2.19
MemReportFrequency	unsigned 0 0 / 4294967039 (0xFFFFEFF)	N	5.1.16
MinFreePct [122]	unsigned 5 0 / 100	N	NDB 7.1.18
NodeGroup	[none] 0 / 65536	IS	NDB 6.4.0
NodeId	unsigned [none] 1 / 48	IS	all 5.1- based

Parameter Name	Type or Units Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	8K pages/100 milliseconds		all 5.1-
NoOfDiskPagesToDiskAfterRestartACC	20	N	
	1 / 4294967039 (0xFFFFEFF)		based
	8K pages/100 milliseconds		
NoOfDiskPagesToDiskAfterRestartTUP	40	N	all 5.1- based
	1 / 4294967039 (0xFFFFEFF)		Jacoa
	8K pages/100 milliseconds		all 5.1- based
NoOfDiskPagesToDiskDuringRestartACC	20	N	
	1 / 4294967039 (0xFFFFEFF)		
	8K pages/100 milliseconds	N	all 5.1- based
NoOfDiskPagesToDiskDuringRestartTUP	40		
	1 / 4294967039 (0xFFFFEFF)		
	integer		
NoOfFragmentLogFiles	16	IN	5.1.0
	3 / 4294967039 (0xFFFFEFF)		
	integer		
NoOfReplicas	2	IS	NDB 7.0.6
	1 / 4		
	boolean		
Numa	1	N	NDB 7.1.9
	boolean		
ODirect	false	N	NDB 6.3.0
	true, false		
	boolean		
RealtimeScheduler	false	N	NDB 6.3.4
	true, false		

	Type or Units		
	Default Value		
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	bytes		
	32M		
RedoBuffer	1M / 4294967039 (0xFFFFEFF)	N	NDB 7.0.4
	numeric		
RedoOverCommitCounter	3	N	NDB 7.1.10
Redoovercommitecourrer	0 / 4294967039 (0xFFFFFEFF)	N	7.1.10
	seconds		
RedoOverCommitLimit	20	N	NDB 7.1.10
RedooverCommittlimit	0 / 4294967039 (0xFFFFEFF)	IN	
	bytes	N	NDB 6.4.0
ReservedSendBufferMemory	256K		
Reservedsendsurrememory	0 / 4294967039 (0xFFFFFEFF)		
	error code		all 5.1- based
RestartOnErrorInsert	2	N	
	0 / 4		basca
	μsec		
SchedulerExecutionTimer	50	N	NDB 6.3.4
	0 / 11000		
	µsec		
SchedulerSpinTimer	0	N	NDB 6.3.4
	0 / 500		
	unsigned		
ServerPort	[none]	Ν	all 5.1- based
	1 / 64K		Daooa
SharedGlobalMemory	bytes		
	20M	N	5.1.6
	0 / 64T		
Ghant Tail Daton Dalla	unsigned	N.I.	NDD C 2 42
StartFailRetryDelay	0	N	NDB 6.2.19

Parameter Name	Type or Units  Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0 / 4294967039 (0xFFFFEFF)		
	milliseconds		
StartFailureTimeout	0	N	all 5.1-
Scarcraffaccimeode	0 / 4294967039 (0xFFFFEFF)		based
	milliseconds		
StartNoNodeGroupTimeout	15000	N	NDB 7.0.24
Bearenonoacoroaprimeoac	0 / 4294967039 (0xFFFFEFF)		11007.0.24
	milliseconds		
StartPartialTimeout	30000	N	all 5.1- based
Startpartiallimeout	0 / 4294967039 (0xFFFFFEF)	N	
	milliseconds	N	all 5.1- based
StartPartitionedTimeout	60000		
Startfartitionedrimeout	0 / 4294967039 (0xFFFFFEF)		
	seconds		NDB 6.4.0
StartupStatusReportFrequency	0	N	
bear eapseacusicepor or requestey	0 / 4294967039 (0xFFFFEFF)	IN	1400 0.4.0
	boolean		
StopOnError	true	N	all 5.1- based
	true, false		Daseu
	% or bytes		
StringMemory	5	S	5.1.6
SCITIIGMEMOLY	0 / 4294967039 (0xFFFFEFF)	3	3.1.0
	boolean		
TcpBind_INADDR_ANY	false	N	NDB 6.2.0
	true, false		
	milliseconds		
TimeBetweenEpochs	100	N	NDB 6.2.5
	0 / 32000		
TimeBetweenEpochsTimeout	milliseconds	N	5.1.51

Parameter Name	Type or Units  Default Value  Minimum/  Maximum  or Permitted  Values	Restart Type	In Version (and later)
	0 / 256000		
	milliseconds		
TimeBetweenGlobalCheckpoints	2000	N	NDB 6.2.0
	20 / 32000		
	milliseconds		
	1000		all 5.1-
TimeBetweenInactiveTransactionAbortCheck	1000 / 4294967039 (0xFFFFEFF)	N	based
TimeBetweenLocalCheckpoints	number of 4- byte words, as a base-2 logarithm 20 0 / 31	N	all 5.1- based
	milliseconds		
	6000		all 5.1- based
TimeBetweenWatchDogCheck	70 / 4294967039 (0xFFFFEFF)	N	
	milliseconds		
	6000		
TimeBetweenWatchDogCheckInitial	70 / 4294967039 (0xFFFFEFF)	N	5.1.20
	bytes		
TotalSendBufferMemory	256K	N	NDB 6.4.0
Total Schaballel Helmol /	0 / 4294967039 (0xFFFFEFF)		11,55 0. 110
	bytes		
	1M	N I	all 5.1-
TransactionBufferMemory	1K / 4294967039 (0xFFFFEFF)	N	based
TransactionDeadlockDetectionTimeout	milliseconds 1200	N	all 5.1- based

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
	50 / 4294967039 (0xFFFFEFF)		
	milliseconds		
TransactionInactiveTimeout	[see text]	N	all 5.1- based
Transactioninactivelimeout	0 / 4294967039 (0xFFFFEFF)	11	
	boolean	N	NDB 7.1.11
TwoPassInitialNodeRestartCopy	false		
	true, false		
	unsigned		all 5.1- based
	16M	N	
UndoDataBuffer	1M / 4294967039 (0xFFFFEFF)		
	unsigned	N	
UndoIndexBuffer	2M		all 5.1- based
	1M / 4294967039 (0xFFFFEFF)		

**Table 5.2 Multi-Threaded Data Node Configuration Parameters** 

	Type or Units		
	Default Value	Restart Type	In Version (and later)
Parameter Name	Minimum/ Maximum or Permitted Values		
	integer	N	NDB 7.0.4
MaxNoOfExecutionThreads	2		
	2/8		
	string		
ThreadConfig	"	N	NDB 7.1.17

## Note

Prior to MySQL Cluster NDB 7.0, to add new data nodes to a MySQL Cluster, it is necessary to shut down the cluster completely, update the <code>config.ini</code> file,

and then restart the cluster, starting all data node processes using the --initial option—that is, you must perform a system restart.

Beginning in MySQL Cluster NDB 7.0, it is possible to add new data node groups to a running cluster online. For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".

## 5.3.2 MySQL Cluster Management Node Configuration Parameters

The summary table in this section provides information about parameters used in the <code>[ndb\_mgmd]</code> or <code>[mgm]</code> sections of a <code>config.ini</code> file for configuring MySQL Cluster management nodes. For detailed descriptions and other additional information about each of these parameters, see Section 5.2.5, "Defining a MySQL Cluster Management Server".

**Restart types.** Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").
- s—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

**Table 5.3 Management Node Configuration Parameters** 

	Type or Units	Restart Type	In Version (and later)
	Default Value		
Parameter Name	Minimum/ Maximum or Permitted Values		
	milliseconds		
ArbitrationDelay	0	N	all 5.1-
AIDICIACIONDEIAY	0 / 4294967039 (0xFFFFFEFF)		based
	0-2	N	all 5.1- based
ArbitrationRank	1		
	0/2		
	path	N	
DataDir			all 5.1- based
			Jacoa
	name	S	
ExecuteOnComputer	[none]		all 5.1- based
ExtraSendBufferMemory	bytes	N	NDB 7.0.39

Parameter Name	Type or Units  Default Value  Minimum/  Maximum  or Permitted  Values	Restart Type	In Version (and later)
	0 0 / 32G		
	milliseconds		
	1500		
HeartbeatIntervalMgmdMgmd	100 / 4294967039 (0xFFFFFEFF)	N	NDB 7.1.29
	string		
HeartbeatThreadPriority	[none]	S	NDB 7.1.2
	name or IP address		all 5.1- based
HostName	[none]	S	
	unsigned	IS	NDB 6.1.1
Id	[none]		
	1 / 255		
	{CONSOLE  SYSLOG FILE}	N.	all 5.1-
LogDestination	[see text]	N	based
	unsigned		
MaxNoOfSavedEvents	100	N	all 5.1-
	0 / 4294967039 (0xFFFFFEFF)		based
	unsigned		
NodeId	[none]	IS	NDB 6.1.1
	1 / 255		
	unsigned		-11.5.4
PortNumber	1186	N	all 5.1- based
	0 / 64K		
	unsigned		- N T 4
PortNumberStats	[none]	N	all 5.1- based
	0 / 64K		
TotalSendBufferMemory	bytes	N	NDB 6.4.0

	Type or Units	Restart Type	In Version (and later)
	Default Value Minimum/ Maximum or Permitted Values		
Parameter Name			
	256K		
	0 / 4294967039 (0xFFFFEFF)		
	boolean		
wan	false	N	NDB 6.1.1
	true, false		

#### **Note**

After making changes in a management node's configuration, it is necessary to perform a rolling restart of the cluster for the new configuration to take effect. See Section 5.2.5, "Defining a MySQL Cluster Management Server", for more information.

To add new management servers to a running MySQL Cluster, it is also necessary perform a rolling restart of all cluster nodes after modifying any existing config.ini files. For more information about issues arising when using multiple management nodes, see Section 3.6.10, "Limitations Relating to Multiple MySQL Cluster Nodes".

# 5.3.3 MySQL Cluster SQL Node and API Node Configuration Parameters

The summary table in this section provides information about parameters used in the [mysqld] and [api] sections of a config.ini file for configuring MySQL Cluster SQL nodes and API nodes. For detailed descriptions and other additional information about each of these parameters, see Section 5.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

#### Note

For a discussion of MySQL server options for MySQL Cluster, see Section 5.4.2, "MySQL Server Options for MySQL Cluster"; for information about MySQL server system variables relating to MySQL Cluster, see Section 5.4.3, "MySQL Cluster System Variables".

**Restart types.** Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary table as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").
- s—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

Table 5.4 SQL Node / API Node Configuration Parameters

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
	milliseconds	N	all 5.1- based
ArbitrationDelay	0		
	0 / 4294967039 (0xFFFFEFF)		
	0-2		
ArbitrationRank	0	N	all 5.1- based
	0/2		basea
	boolean		
AutoReconnect	false	N	NDB 7.0.7
	true, false		
	bytes		NDB 7.2.1
BatchByteSize	16K	N	
	1024 / 1M		
	records	N	NDB 7.2.1
BatchSize	256		
	1 / 992		
	string	N	NDB 6.1.0
ConnectionMap	[none]		
	LDM threads	N	NDB 7.1.27
DefaultHashMapSize	240		
	0 / 3840		
	enumeration	S	NDB 7.1.10
DefaultOperationRedoProblemAction	ABORT		
20144130per4010imedof10bfeiimet10if	ABORT, QUEUE		
	bytes	S	NDB 7.0.4
EventLogBufferSize	8192		
	0 / 64K		
	name	S	all 5.1- based
ExecuteOnComputer	[none]		
ExtraSendBufferMemory	bytes	N	NDB 7.0.39

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
	0		
	0 / 4294967039 (0xFFFFEFF)		
	string		
HeartbeatThreadPriority	[none]	S	NDB 7.1.2
HostName	name or IP address	S	all 5.1- based
	[none]		
	unsigned	IS	NDB 6.1.1
Id	[none]		
	1 / 255		
	bytes	N	all 5.1- based
MaxScanBatchSize	256K		
	32K / 16M		
	unsigned	IS	NDB 6.1.1
NodeId	[none]		
	1 / 255		
	bytes	N	NDB 6.4.0
TotalSendBufferMemory	256K		
	0 / 4294967039 (0xFFFFEFF)		
wan	boolean	N	NDB 6.1.1
	false		
	true, false		

## Note

To add new SQL or API nodes to the configuration of a running MySQL Cluster, it is necessary to perform a rolling restart of all cluster nodes after adding new [mysqld] or [api] sections to the config.ini file (or files, if you are using more than one management server). This must be done before the new SQL or API nodes can connect to the cluster.

It is *not* necessary to perform any restart of the cluster if new SQL or API nodes can employ previously unused API slots in the cluster configuration to connect to the cluster.

# **5.3.4 Other MySQL Cluster Configuration Parameters**

The summary tables in this section provide information about parameters used in the [computer], [tcp], [shm], and [sci] sections of a config.ini file for configuring MySQL Cluster management nodes. For detailed descriptions and other additional information about individual parameters, see Section 5.2.8, "MySQL Cluster TCP/IP Connections", Section 5.2.10, "MySQL Cluster Shared-Memory Connections", or Section 5.2.11, "SCI Transport Connections in MySQL Cluster", as appropriate.

**Restart types.** Changes in MySQL Cluster configuration parameters do not take effect until the cluster is restarted. The type of restart required to change a given parameter is indicated in the summary tables as follows:

- N—Node restart: The parameter can be updated using a rolling restart (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").
- S—System restart: The cluster must be shut down completely, then restarted, to effect a change in this parameter.
- I—Initial restart: Data nodes must be restarted using the --initial option.

**Table 5.5 Computer Configuration Parameters** 

	Type or Units		In Version (and later)
	Default Value	Restart Type	
Parameter Name	Minimum/ Maximum or Permitted Values		
HostName	name or IP address	S	all 5.1- based
	[none]		
	string	IS	all 5.1- based
Id	[none]		
			23304

**Table 5.6 TCP Configuration Parameters** 

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
Checksum	boolean	N	all 5.1- based
	false		
	true, false		
Group	unsigned	N	all 5.1- based

Parameter Name	Type or Units  Default Value  Minimum/ Maximum or Permitted Values  55	Restart Type	In Version (and later)
	0 / 200		
	numeric		all 5.1- based
NodeId1	[none]	N	
	numeric		all 5.1-
NodeId2 [176]	[none]	N	based
	numeric		all 5.1- based
NodeIdServer	[none]	N	
	bytes		NDB 6.4.0
OverloadLimit	0	N	
	0 / 4294967039 (0xFFFFFEFF)		
	unsigned	N	all 5.1- based
PortNumber	[none]		
	0 / 64K		
	string		all 5.1- based
Proxy	[none]	N	
	bytes	N	NDB 7.0.4
	2M		
ReceiveBufferMemory	16K / 4294967039 (0xFFFFEFF)		
	unsigned	N	NDB 7.0.4
SendBufferMemory	2M		
	256K / 4294967039 (0xFFFFEFF)		
	boolean	N	all 5.1- based
SendSignalId	[see text]		
	true, false		มลงธน
TCP_MAXSEG_SIZE	unsigned	N	NDB 6.1.1

	Type or Units		
	Default Value		In
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0		
	0 / 2G		
	unsigned		
TCP_RCV_BUF_SIZE	70080	N	NDB 6.1.1
	1 / 2G		
	unsigned		
TCP_SND_BUF_SIZE	71540	N	NDB 6.1.1
	1 / 2G		
	boolean		
TcpBind_INADDR_ANY	false	N	NDB 6.2.0
	true, false		

**Table 5.7 Shared Memory Configuration Parameters** 

	Type or Units		
	Default Value		In
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	boolean		
Checksum	true	N	all 5.1- based
	true, false		Daooa
	unsigned	N	all 5.1- based
Group	35		
	0 / 200		
	numeric		
NodeId1	[none]	N	all 5.1- based
			Daoca
	numeric		all 5.1- based
NodeId2 [179]	[none]	N	
	numeric		
NodeldServer	[none]	I NI I	all 5.1- based
			24004
OverloadLimit	bytes	N	NDB 6.4.0

	Type or Units		
	Default Value		In
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0		
	0 / 4294967039 (0xFFFFEFF)		
	unsigned		
PortNumber	[none]	N	all 5.1- based
	0 / 64K		
	boolean	N	all 5.1- based
SendSignalId	false		
	true, false		
	unsigned		all 5.1- based all 5.1-
ShmKey	[none]	N	
	0 / 4294967039 (0xFFFFEFF)		
	bytes		
	1M		
ShmSize	64K / 4294967039 (0xFFFFEFF)	N	based
	unsigned		
Signum	[none]	N	all 5.1- based
	0 / 4294967039 (0xFFFFEFF)		

# **Table 5.8 SCI Configuration Parameters**

	Type or Units		
	Default Value	IVDA	In
Parameter Name	Minimum/ Maximum or Permitted Values		Version (and later)
	boolean		
Checksum	false	N	all 5.1- based
	true, false		Daooa
	unsigned		
Group	15	N	all 5.1- based
	0 / 200		Dasou

	Type or Units		
	Default Value		
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	unsigned		
Host1SciId0	[none]	N	all 5.1-
	0 / 4294967039 (0xFFFFEFF)		based
	unsigned		
   Host1SciId1	0	N	all 5.1-
Nobelieliai	0 / 4294967039 (0xFFFFEFF)	IX	based
	unsigned		
Host2SciId0	[none]	N	all 5.1-
	0 / 4294967039 (0xFFFFEFF)	IN	based
	unsigned	N	all 5.1- based
Host2SciId1	0		
	0 / 4294967039 (0xFFFFEFF)		
	numeric		all 5.1- based
NodeId1	[none]	N	
	numeric		all 5.1-
NodeId2 [181]	[none]	N	
			based
	numeric		all 5.1- based
NodeIdServer	[none]	N	
			basca
	bytes		
OverloadLimit	0	N	NDB 6.4.0
over roadring.	0 / 4294967039 (0xFFFFEFF)		1122 01110
	unsigned		u. = .
PortNumber	[none]	N	all 5.1- based
	0 / 64K		Daood
	unsigned		- " - "
SendLimit	8K	N	all 5.1- based
	128 / 32K		34004

	Type or Units		
	Default Value		ln ln
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	boolean		
SendSignalId	true	N	all 5.1- based
	true, false		Daood
	unsigned		
	10M		all 5.1-
SharedBufferSize	64K / 4294967039 (0xFFFFFEFF)	N	based

# 5.4 MySQL Server Options and Variables for MySQL Cluster

This section provides information about MySQL server options, server and status variables that are specific to MySQL Cluster. For general information on using these, and for other options and variables not specific to MySQL Cluster, see The MySQL Server.

For MySQL Cluster configuration parameters used in the cluster configuration file (usually named config.ini), see Chapter 5, Configuration of MySQL Cluster NDB 6.1-7.1.

# 5.4.1 MySQL Cluster mysqld Option and Variable Reference

The following table provides a list of the command-line options, server and status variables applicable within <code>mysqld</code> when it is running as an SQL node in a MySQL Cluster. For a table showing *all* command-line options, server and status variables available for use with <code>mysqld</code>, see Server Option and Variable Reference.

Table 5.9 MySQL Server Options and Variables for MySQL Cluster: MySQL 5.1, MySQL Cluster NDB 6.3-7.1

Option or Variable Na	ame
System Variable	Status Variable
Scope	Dynamic
Handler_discove	er
No	Yes
Both	No
per of times that tables have been d	iscovered
db_api_wait_exec_complete_	_count_session
No	Yes
Session	No
	Scope  Handler_discove  No  Both  Der of times that tables have been didb_api_wait_exec_complete_  No

	Option or Variable N	ame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		·
	Ndb_api_wait_exec_complete	e_count_slave
No	No	Yes
No	Global	No
DESCRIPTION: Number complete by this slave.		hile waiting for execution of an operation to
	Ndb_api_wait_exec_compl	
No	No	Yes
No	Global	No
DESCRIPTION: Number complete by this MySQL		hile waiting for execution of an operation to
No	No	Yes
No	Session	No
		hile waiting for a scan-based signal in this
client session.	Ndb_api_wait_scan_result_	_count_slave
No	Global	No
DESCRIPTION: Number slave.	of times thread has been blocked when Ndb_api_wait_scan_resu	hile waiting for a scan-based signal by this
No	No	Yes
No	Global	No
DESCRIPTION: Number MySQL Server (SQL nod		hile waiting for a scan-based signal by this
No	No	Yes
No	Session	No
DESCRIPTION: Number client session.	of times thread has been blocked was	aiting for a metadata-based signal in this _count_slave
No	No	Yes
No	Global	No
	of times thread has been blocked wa	aiting for a metadata-based signal by this
	Ndb_api_wait_meta_requ	est_count

	Option or Variable N	lame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: Number of MySQL Server (SQL node)		raiting for a metadata-based signal by this
No	No.	Yes
No	Session	No
DESCRIPTION: Total time this client session.	(in nanoseconds) spent waiting fo	or some type of signal from the data nodes in
No	No	Yes
No	Global	No
DESCRIPTION: Total time by this slave.		or some type of signal from the data nodes
No	Ndb_api_wait_nanos	Yes
No No	Global	No
DESCRIPTION: Total time by this MySQL Server (SQ		or some type of signal from the data nodes  nt_session
No	No	Yes
No	Session	No
DESCRIPTION: Amount of	data (in bytes) sent to the data no	odes in this client session.
	Ndb_api_bytes_sent_co	unt_slave
No	No	Yes
No	Global	No
DESCRIPTION: Amount of	data (in bytes) sent to the data no	odes by this slave.
	Ndb_api_bytes_sent	_count
No	No	Yes
No	Global	No
DESCRIPTION: Amount of	data (in bytes) sent to the data no	odes by this MySQL Server (SQL node).
	Ndb_api_bytes_received_c	ount_session
No	No	Yes
No	Session	No
DESCRIPTION: Amount of	f data (in bytes) received from the  Ndb_api_bytes_received_	
No	No	Yes
INU	INO	169

Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: Amount (	of data (in bytes) received from the o	
	Ndb_api_bytes_receive	•
No	No	Yes
No	Global	No
DESCRIPTION: Amount on node).	of data (in bytes) received from the o	data nodes by this MySQL Server (SQL
No	No	Yes
No	Session	No
DESCRIPTION: Number	of transactions started in this client s	
	Ndb_api_trans_start_co	
No	No	Yes
No	Global	No
DESCRIPTION: Number	of transactions started by this slave.	
	Ndb_api_trans_start	_count
No	No	Yes
No	Global	No
DESCRIPTION: Number	of transactions started by this MySQ	L Server (SQL node).
	Ndb_api_trans_commit_cou	unt_session
No	No	Yes
No	Session	No
DESCRIPTION: Number	of transactions committed in this clie	ent session.
	Ndb_api_trans_commit_co	ount_slave
No	No	Yes
No	Global	No
DESCRIPTION: Number	of transactions committed by this sla	ave.
	Ndb_api_trans_commit	c_count
No	No	Yes
No	Global	No
DESCRIPTION: Number	of transactions committed by this My	/SQL Server (SQL node).
	Ndb_api_trans_abort_cou	nt_session
No	No	Yes

	Option or Variable N	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_trans_abort_co	ount_slave
No	No	Yes
No	Global	No
DESCRIPTION: Num	ber of transactions aborted by this slave	9.
	Ndb_api_trans_abort	_count
No	No	Yes
No	Global	No
DESCRIPTION: Num	ber of transactions aborted by this MyS	QL Server (SQL node).
	Ndb_api_trans_close_co	unt_session
No	No	Yes
No	Session	No
	ber of transactions aborted (may be gre ) in this client session. Ndb_api_trans_close_co	eater than the sum of TransCommitCount
No	No	Yes
No	Global	No
and TransAbortCount	, •	
No	Ndb_api_trans_close	
	No	Yes
No	No Global	Yes No
No DESCRIPTION: Numl	No Global	Yes No
No DESCRIPTION: Numl	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).	Yes  No eater than the sum of TransCommitCount
No DESCRIPTION: Numl and TransAbortCount	No Global ber of transactions aborted (may be gre	Yes  No eater than the sum of TransCommitCount
No DESCRIPTION: Numl and TransAbortCount No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_ No	Yes No eater than the sum of TransCommitCount _session Yes
No DESCRIPTION: Numl and TransAbortCount No No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_ No Session	Yes No eater than the sum of TransCommitCount session Yes No
No DESCRIPTION: Numl and TransAbortCount No No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_ No Session ber of operations based on or using prince.	Yes No eater than the sum of TransCommitCount Session Yes No mary keys in this client session.
No DESCRIPTION: Numl and TransAbortCount No No DESCRIPTION: Numl	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_ No Session ber of operations based on or using print Ndb_api_pk_op_count	Yes  No eater than the sum of TransCommitCount  Session  Yes  No mary keys in this client session.
No DESCRIPTION: Numl and TransAbortCount No No DESCRIPTION: Numl	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_  No Session ber of operations based on or using print Ndb_api_pk_op_count_  No	Yes  No eater than the sum of TransCommitCount  Session  Yes  No mary keys in this client session.  Substitute    Yes  Yes
No DESCRIPTION: Numl and TransAbortCount No No DESCRIPTION: Numl No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_ No Session ber of operations based on or using print Ndb_api_pk_op_count No Global	Yes  No eater than the sum of TransCommitCount  Session  Yes  No mary keys in this client session.  Substitute of TransCommitCount  Yes  No Mo Mo Mo No
No DESCRIPTION: Numl and TransAbortCount No No DESCRIPTION: Numl No No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_  No Session ber of operations based on or using print Ndb_api_pk_op_count_  No	Yes  No eater than the sum of TransCommitCount  Session  Yes  No mary keys in this client session.  Selave  Yes  No mary keys by this slave.
and TransAbortCount  No  No  DESCRIPTION: Numl  No  No	No Global ber of transactions aborted (may be gree) by this MySQL Server (SQL node).  Ndb_api_pk_op_count_  No Session ber of operations based on or using print  No Global ber of operations based on or using print  No Clobal	Yes  No eater than the sum of TransCommitCount  Session  Yes  No mary keys in this client session.  Selave  Yes  No mary keys by this slave.

	Option or Variable Na	ame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_uk_op_count_	session
No	No	Yes
No	Session	No
DESCRIPTION: Number	of operations based on or using unio	que keys in this client session.
	Ndb_api_uk_op_count	_slave
No	No	Yes
No	Global	No
DESCRIPTION: Number	of operations based on or using unic	que keys by this slave.
	Ndb_api_uk_op_co	unt
No	No	Yes
No	Global	No
DESCRIPTION: Number	of operations based on or using unic	que keys by this MySQL Server (SQL
node).	or of orange and or or normal or normal	
	Ndb_api_table_scan_cour	nt_session
No	No	Yes
No	Session	No
DESCRIPTION: Number client session.	of table scans that have been started Ndb_api_table_scan_cou	d, including scans of internal tables, in this unt_slave
No	No	Yes
No	Global	No
DESCRIPTION: Number slave.	of table scans that have been started	d, including scans of internal tables, by the
	Ndb_api_table_scan_	
No	No	Yes
No	Global	No
DESCRIPTION: Number MySQL Server (SQL nod		d, including scans of internal tables, by th
	Ndb_api_range_scan_cour	nt_session
	Ndb_api_range_scan_cour	nt_session Yes
No		
No No	No Session	Yes No
No No	No Session of range scans that have been started	Yes No ed in this client session.
No No DESCRIPTION: Number	No Session of range scans that have been starte Ndb_api_range_scan_cou	Yes No ed in this client session. unt_slave
No No	No Session of range scans that have been started	Yes No ed in this client session.

	Option or Variable	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_range_sca	n_count
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of range scans that have been sta	rted by this MySQL Server (SQL node).
	Ndb_api_pruned_scan_co	ount_session
No	No	Yes
No	Session	No
DESCRIPTION: Numb	per of scans that have been pruned to	a single partition in this client session.
	Ndb_api_pruned_scan_o	count_slave
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of scans that have been pruned to	a single partition by this slave.
	Ndb_api_pruned_sca	an_count
	N.L.	Yes
No	No	163
No	Global	No
No	Global	No a single partition by this MySQL Server
No DESCRIPTION: Numb	Global ber of scans that have been pruned to	No a single partition by this MySQL Server
No DESCRIPTION: Numb (SQL node).	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co	No a single partition by this MySQL Server unt_session
No DESCRIPTION: Numb (SQL node). No	Global  per of scans that have been pruned to  Ndb_api_scan_batch_co	No a single partition by this MySQL Server unt_session Yes No
No DESCRIPTION: Numb (SQL node). No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session	No a single partition by this MySQL Server  unt_session Yes No s client session.
No DESCRIPTION: Numb (SQL node). No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this	No a single partition by this MySQL Server  unt_session Yes No s client session.
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c	No o a single partition by this MySQL Server  unt_session Yes No o client session. ount_slave
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No	No o a single partition by this MySQL Server  unt_session Yes No o client session. ount_slave Yes No
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No Global	No a single partition by this MySQL Server  unt_session Yes No c client session. ount_slave Yes No s slave.
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this	No a single partition by this MySQL Server  unt_session Yes No c client session. ount_slave Yes No s slave.
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No No DESCRIPTION: Numb	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this  Ndb_api_scan_batch	No a single partition by this MySQL Server  unt_session Yes No a client session. ount_slave Yes No s slave. h_count
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  No  No	No a single partition by this MySQL Server  unt_session Yes No client session. ount_slave Yes No s slave. h_count Yes No
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  Global	No o a single partition by this MySQL Server  unt_session Yes No o client session. ount_slave Yes No s slave. h_count Yes No s MySQL Server (SQL node).
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No Global  oer of batches of rows received by this  Ndb_api_scan_batc  No Global  oer of batches of rows received by this	No o a single partition by this MySQL Server  unt_session Yes No o client session. ount_slave Yes No s slave. h_count Yes No s MySQL Server (SQL node).
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  Global  oer of batches of rows received by this  Ndb_api_read_row_cour	No a single partition by this MySQL Server  unt_session Yes No client session. ount_slave Yes No s slave. h_count Yes No s MySQL Server (SQL node). nt_session
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No Global  oer of batches of rows received by this  Ndb_api_scan_batc  No Global  oer of batches of rows received by this  Ndb_api_scan_batc  No Global  oer of batches of rows received by this  Ndb_api_read_row_cour	No of a single partition by this MySQL Server  nunt_session Yes No of client session.  ount_slave Yes No s slave. h_count Yes No s MySQL Server (SQL node). nt_session Yes No
No DESCRIPTION: Numb (SQL node).  No No DESCRIPTION: Numb No DESCRIPTION: Numb No DESCRIPTION: Numb No	Global  oer of scans that have been pruned to  Ndb_api_scan_batch_co  No  Session  oer of batches of rows received in this  Ndb_api_scan_batch_c  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  Global  oer of batches of rows received by this  Ndb_api_scan_batc  No  Global  oer of batches of rows received by this  Ndb_api_read_row_cour  No  Session	No of a single partition by this MySQL Server  unt_session  Yes No of client session.  ount_slave  Yes No s slave.  h_count  Yes No s MySQL Server (SQL node).  nt_session  Yes No in this client session.

	Option or Variable	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: Total nur	mber of rows that have been read	by this slave.
	Ndb_api_read_row	_count
No	No	Yes
No	Global	No
DESCRIPTION: Total nur	mber of rows that have been read	by this MySQL Server (SQL node).
N	db_api_trans_local_read_r	ow_count_session
No	No	Yes
No	Session	No
DESCRIPTION: Total nur	mber of rows that have been read	in this client session.
	Ndb_api_trans_local_read_	row_count_slave
No	No	Yes
No	Global	No
DESCRIPTION: Total nur	mber of rows that have been read	by this slave.
	Ndb_api_trans_local_re	ad_row_count
No	No	Yes
No	Global	No
DESCRIPTION: Total nur	mber of rows that have been read	by this MySQL Server (SQL node).
	Ndb_api_event_data_cou	
No	No	Yes
No	Global	No
	of row change events received by	
	Ndb_api_event_dat	• •
No	No	Yes
No	Global	No
	of row change events received by	
DESCRIPTION, NUMBER	Ndb_api_event_nondata_c	` ,
No	No	Yes
No	Global	No
thread.	oi events received, other than row	change events, by the NDB binlog injector
	Ndb_api_event_nonda	ata count
No	No	Yes
No	Global	No
	0.000.	110

	Option or Variable N	lame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_event_bytes_cou	nt_injector
No	No	Yes
No	Global	No
DESCRIPTION: Number of	of bytes of events received by the N	IDB binlog injector thread.
	Ndb_api_event_bytes	s_count
No	No	Yes
No	Global	No
DESCRIPTION: Number of	of bytes of events received by this N	MySQL Server (SQL node).
	Ndb_number_of_data	_nodes
No	No	Yes
No	Global	No
	ver is part of a MySQL Cluster, the	value of this variable is the number of data
nodes in the cluster		
	Ndb_conflict_fn_	
No	No	Yes
No	Global	No
		ved in cluster replication, the value of this based on "greater timestamp wins" has
	Ndb_conflict_fn_	old
No	No	Yes
No	Global	No
		ved in cluster replication, the value of this wins" conflict resolution has been applied
No	No	Yes
No	Global	No
DESCRIPTION: Number of function		flict by the NDB\$EPOCH() conflict detection
NI -	Ndb_conflict_fn_epoc	
No	No Olahar	Yes
No	Global	No
detection function	of rows that have been found in con  Ndb_conflict_trans_row_co	iflict by the NDB\$EPOCH_TRANS() conflict
No	No	Yes
No	Global	No
110	Olobai	140

	Option or Variable N	lame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
DESCRIPTION: Number	of rows found to be in conflict by a t	ransactional conflict function
	Ndb_conflict_trans_row_r	reject_count
No	No	Yes
No	Global	No
		ound in conflict by a transactional conflict any rows included in or dependent on
No	No	Yes
No	Global	No
		found in conflict by a transactional conflict
NI-	Ndb_conflict_trans_detec	
No	No	Yes
No	Global	No
(slightly) greater than or e	equal to Ndb_conflict_trans_conflict_	
(slightly) greater than or e	equal to Ndb_conflict_trans_conflict_Ndb_conflict_trans_conflic	_commit_count.
(slightly) greater than or e	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No	_commit_count.
(slightly) greater than or e	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict No Global	_commit_count. t_commit_count Yes No d after requiring transactional conflict
(slightly) greater than or each No No DESCRIPTION: The num	equal to Ndb_conflict_trans_conflict_  Ndb_conflict_trans_conflict_  No  Global  There of epoch transactions committee	_commit_count. t_commit_count Yes No d after requiring transactional conflict
(slightly) greater than or each of the No No DESCRIPTION: The number handling.	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  hber of epoch transactions committe  ndb_optimization_e	_commit_count. t_commit_count Yes No d after requiring transactional conflict
(slightly) greater than or each of the state	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  hber of epoch transactions committe  ndb_optimization_c  Yes Global	_commit_count. t_commit_count  Yes  No d after requiring transactional conflict  delay  No Yes  yeen processing sets of rows by OPTIMIZE
(slightly) greater than or each of the state	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  hber of epoch transactions committe  ndb_optimization_c  Yes Global  number of milliseconds to wait betw	_commit_count. t_commit_count  Yes  No d after requiring transactional conflict  delay  No Yes  yeen processing sets of rows by OPTIMIZE
No No DESCRIPTION: The num handling. No DESCRIPTION: Sets the TABLE on NDB tables.	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  hber of epoch transactions committe  ndb_optimization_o  Yes Global  number of milliseconds to wait betwood to the conflict trans_conflict_  ndb_table_tempor	commit_count.  t_commit_count  Yes  No  d after requiring transactional conflict  delay  No  Yes  veen processing sets of rows by OPTIMIZE
No No DESCRIPTION: The num handling. No DESCRIPTION: Sets the TABLE on NDB tables. No No	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  The optimization_conflict_trans_conflict_ No Global  The optimization_conflict_trans_conflict_ No Global  The optimization_conflict_trans_conflict_ No Global  The optimization_conflict_trans_conflic	rary  No Yes  No Yes  No Yes  No Yes  Veen processing sets of rows by OPTIMIZE  Yes  No Yes
No No DESCRIPTION: The num handling. No DESCRIPTION: Sets the TABLE on NDB tables. No No DESCRIPTION: NOB tables.	equal to Ndb_conflict_trans_conflict_ Ndb_conflict_trans_conflict_ No Global  her of epoch transactions committee  ndb_optimization_o  Yes Global  number of milliseconds to wait betwood to the conflict_trans_conflict_  ndb_optimization_o  Yes Global  number of milliseconds to wait betwood to the conflict trans_conflict_	rary  No Yes  No Yes  No Yes  No Yes  Veen processing sets of rows by OPTIMIZE  Yes  No Yes

	Option or Variable I	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
table schema files are	created). The setting in effect when the setting	abled are not checkpointed to disk (although the table is created with or altered to use
· · · · · · · · · · · · · · · · · · ·	ndb_autoincrement_pr	
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: NDB	auto-increment prefetch size	
	ndb-batch-siz	ze
Yes	Yes	No
Yes	Global	No
DESCRIPTION: The s	ize (in bytes) to use for NDB transaction	on batches
	ndb-blob-read-batc	h-bytes
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Speci	fies the size in bytes that large BLOB	reads should be batched into. 0 = no limit.
	ndb-blob-write-bato	ch-bytes
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Speci	fies the size in bytes that large BLOB	writes should be batched into. 0 = no limit.
	ndb_cache_check_	time
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: The n query cache		s of cluster SQL nodes made by the MySQL
	ndb-cluster-connect	
Yes	Yes	Yes
Yes	Global	No
DESCRIPTION: The n	umber of connections to the cluster us ndb_join_pushd	• •
No	Yes	No
No	Global	No
DESCRIPTION: Enabl	es pushing down of joins to data node  Ndb_execute_co	
No	No No	Yes
No	Global	No
INC.	TAILUU (CII	

	Option or Variable Na	ame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes	·	
	Ndb_scan_count	:
No	No	Yes
No	Global	No
DESCRIPTION: The tot	tal number of scans executed by NDB	since the cluster was last started
	Ndb_pruned_scan_co	ount
No	No	Yes
No	Global	No
DESCRIPTION: The nu pruning could be used	ndb-connectstri	e the cluster was last started where partition
Yes	No	No
Yes		No
DESCRIPTION: Point to	o the management server that distribut	tes the cluster configuration
	ndb_extra_loggin	ng
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Contro the MySQL error log	Is logging of MySQL Cluster schema, on ndb_force_send	connection, and data distribution events in
Yes	Yes	No
		140
VAC	Roth	Voc
Yes  DESCRIPTION: Forces	Both	Yes
	sending of buffers to NDB immediatel	y, without waiting for other threads
DESCRIPTION: Forces	sending of buffers to NDB immediatel	y, without waiting for other threads
DESCRIPTION: Forces	sending of buffers to NDB immediatel  ndb_use_exact_com  Yes	y, without waiting for other threads unt No
DESCRIPTION: Forces No No	Yes Both cact row count when planning queries	y, without waiting for other threads unt  No Yes
DESCRIPTION: Forces No No	sending of buffers to NDB immediatel  ndb_use_exact_com  Yes  Both	y, without waiting for other threads unt  No Yes
No No DESCRIPTION: Forces No No DESCRIPTION: Use ex	Yes Both cact row count when planning queries ndb-log-apply-sta	y, without waiting for other threads unt  No Yes
No No DESCRIPTION: Use ex Yes Yes DESCRIPTION: Cause	Yes Both tact row count when planning queries ndb-log-apply-sta Yes Global a MySQL server acting as a slave to logitate master in its own binary log, using endbcluster option.	y, without waiting for other threads unt  No Yes  No No No
No No DESCRIPTION: Use ex Yes Yes DESCRIPTION: Cause received from its immed	Yes Both Tact row count when planning queries  ndb-log-apply-sta  Yes Global  a MySQL server acting as a slave to logiate master in its own binary log, using	No Yes  No

	Option or Variable N	lame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		j
DESCRIPTION: Write updawithlog-bin.	ates to NDB tables in the binary log ndb_log_binlog_in	g. Effective only if binary logging is enabled
Yes	Yes	No
No	Global	Yes
	oping between epochs and binary I ctive only if binary logging is enable ndb-log-orig	og positions into the ndb_binlog_index ed on the server.
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Log origina	ating server id and epoch in mysql	.ndb_binlog_index table.
	ndb-log-transaction	on-id
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Write NDE	3 transaction IDs in the binary log.	Requireslog-bin-v1-events=OFF.
	ndb_log_transactio	on_id
No	Yes	No
No	Global	No
DESCRIPTION: Whether N	NDB transaction IDs are written into	o the binary log. (Read-only.)
	ndb_log_updated_only	y [504]
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Log compl	lete rows (ON) or updates only (OF	-F)
	ndb-log-update-as-wri	te [505]
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Toggles lo	ogging of updates on the master be ndb-log-empty-epo	etween updates (OFF) and writes (ON)
Yes	Yes	No
Yes	Global	Yes
	bled, causes epochs in which ther _binlog_index tables, even when ndb_log_empty_epo	
Yes	Yes	No
Yes	Global	Yes

Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
	enabled, epochs in which there were randb_binlog_index tables, even when long_binlog_index tables, even when long_binlog_index tables, even when long_index table	og_slave_updates is enabled.
Yes	No	No
No		No
	ION_SCHEMA table having that name	
No	Ndb_pushed_read	Yes
No	Global	No
	er of reads executed on the data node	
DESCRIPTION, INUITIDE	Ndb_pushed_queries_c	
No	No	Yes
No	Global	No
	er of joins that API nodes have attemp	
	Ndb_pushed_queries_c	dropped
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of joins that API nodes have tried to Ndb_pushed_queries_e	•
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of joins successfully pushed down a	and executed on the data nodes
Yes	No	Yes
Yes	Global	No
DESCRIPTION: MySQI	L Cluster node ID for this MySQL serv	er
	ndb-mgmd-host	
Yes	No	No
165		No
Yes		<del></del>
Yes	e host (and port, if desired) for connect	ting to the management server
Yes	e host (and port, if desired) for connect	g g
Yes		g g

	Option or Variable	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
	ndb-wait-set	up
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Time	(in seconds) for the MySQL server to	wait for NDB engine setup to complete.
	ndbcluster	
Yes	No	No
Yes		No
DESCRIPTION: Enab	le NDB Cluster (if this version of MyS	QL supports it)
	ndbinfo_datab	ase
No	Yes	No
No	Global	No
DESCRIPTION: The r	name used for the NDB information da	atabase; read only.
	ndbinfo_max_by	ytes
Yes	Yes	No
No	Both	Yes
DESCRIPTION: Used	for debugging only.	
	ndbinfo_max_r	ows
Yes	Yes	No
No	Both	Yes
DESCRIPTION: Used	for debugging only.	<u> </u>
	ndbinfo_offli	ine
No	Yes	No
No	Global	Yes
DESCRIPTION: Put th	ne ndbinfo database into offline mode,	, in which no rows are returned from tables or
views.		
	ndbinfo_show_hi	idden
Yes	Yes	No
No	Both	Yes
DESCRIPTION: Whet	her to show ndbinfo internal base tabl	les in the mysql client. The default is OFF.
	ndbinfo_table_p	refix
Yes	Yes	No
No	Both	Yes
	C	al base tables. Defaults to leade(!
DESCRIPTION: The p	prefix to use for naming ndbinfo interna	al base tables. Delauits to hobs.
DESCRIPTION: The p	prefix to use for naming indbinfo international national	

	Option or Variable Na	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: The vers	ion of the ndbinfo engine; read only.	,
	server-id-bits	3
Yes	Yes	No
Yes	Global	No
	PI applications to store application da	e server_id actually used for identifying the ata in the most significant bits. server_id
No	Yes	No
No	Session	Yes
		action. Disable AUTOCOMMIT to use.
	have_ndbcluste:	
No	Yes	No
No	Global	No
	mysqld supports NDB Cluster tables	
DECORNI FICIA. WHENCE	ndb-deferred-constr	. ,
Yes	Yes	No
Yes	Both	Yes
•	that constraint checks on unique incime. Not normally needed or used; for ndb_deferred_constr	• • • • • • • • • • • • • • • • • • • •
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Specifies		eferred (where these are supported). Not
Yes	Yes	No
Yes	Global	Yes
		JSTER (KEYHASH or LINHASH, default i
Yes	Yes	No
	Global	Yes
	Juliusai	I 53
Yes DESCRIPTION: Default d	listribution for new tables in NDPCLL	ISTER (KEVHASH or I INIUASH dofoult)
	listribution for new tables in NDBCLU	JSTER (KEYHASH or LINHASH, default i

Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes	ССОРС	Dynamic
	Vac	NIC
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Maximun to 0 (no limit).	n memory that can be allocated for t ndb_index_stat_cache_	ouffering events by the NDB API. Defaults _entries
Yes	No	No
Yes		No
DESCRIPTION: Sets the keys	granularity of the statistics by detern ndb_index_stat_en	mining the number of starting and ending able
Yes	No	No
Yes		No
DESCRIPTION: Use NDE	3 index statistics in query optimization ndb_index_stat_op	
Yes	No	No
Yes		No
no spaces	ndb_index_stat_updat	
Yes	No	No
Yes		No
DESCRIPTION: How ofte	n to query data nodes instead of the	e statistics cache
	ndb_optimized_node_se	election
Yes	No	No
Yes		No
DESCRIPTION: Determin coordinator	nes how an SQL node chooses a clu	ster data node to use as transaction
	ndb_report_thresh_binlog	_epoch_slip
Yes	No	No
Yes		No
DESCRIPTION: This is a	threshold on the number of epochs ndb_report_thresh_binlog	to be behind before reporting binlog statu
Yes	No	No
Yes		No
	threshold on the percentage of free	memory remaining before reporting binlo

	No Yes COUNT(*) query planning to
ndb_use_transactions  Yes  Both a count of records during SELECT  ndb_version  Yes	No Yes
Yes  Both a count of records during SELECT  ndb_version  Yes	Yes
Yes  Both a count of records during SELECT  ndb_version  Yes	Yes
Both a count of records during SELECT  ndb_version  Yes	Yes
a count of records during SELECT  ndb_version  Yes	
ndb_version	COUNT(*) query planning to
⁄es	
	No
Global	No
DB engine version as an integer.	
ndb_version_string	
l'es	No
Global	No
ation including NDB engine versior	ı in ndb-x.y.z format.
Ndb_cluster_node_id	
No	Yes
Both	No
ng as a MySQL Cluster node, then  Ndb_config_from_host	the value of this variable its node
No	Yes
Both	No
P address of the Cluster managem  Ndb_config_from_port	ent server. Formerly
No	Yes
Both	No
cting to the Cluster management se	
COM_BITOW_IIOD BLACUS	Yes
	100
No Both	No
	g as a MySQL Cluster node, then a Ndb_config_from_host No Soth P address of the Cluster managem Ndb_config_from_port No Soth ting to the Cluster management secon_show_ndb_status

# 5.4.2 MySQL Server Options for MySQL Cluster

This section provides descriptions of mysqld server options relating to MySQL Cluster. For information about mysqld options not specific to MySQL Cluster, and for general information about the use of options with mysqld, see Server Command Options.

For information about command-line options used with other MySQL Cluster processes (ndbd, ndb\_mgmd, and ndb\_mgm), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs". For information about command-line options used with NDB utility programs (such as ndb\_desc, ndb\_size.pl, and ndb\_show\_tables), see Chapter 6, MySQL Cluster Programs.

• --ndb-batch-size=#

Introduced	5.1.23-ndb-6.3.8		
Command-Line Format	ndb-k	oatch-size	
Option-File Format	ndb-bat	cch-size	
System Variable Name	ndb_bat	cch_size	
Variable Scope	Global	Global	
Dynamic Variable	No		
	Permitted Values		
	Type numeric		
	Default 32768		
	Min 0 Value		
	Max Value 31536000		

This sets the size in bytes that is used for NDB transaction batches.

• --ndb-cluster-connection-pool=#

Introduced	5.1.19-no	5.1.19-ndb-6.2.2		
Command-Line Format	ndb-d	ndb-cluster-connection-pool		
Option-File Format	ndb-cli	uster-connection-pool		
Status Variable Name	Ndb_cli	uster_connection_pool		
Variable Scope	Global			
Dynamic Variable	No			
System Variable Name	ndb_clu	ndb_cluster_connection_pool		
Variable Scope	Global			
Dynamic Variable	No			
	Permitte	Permitted Values		
	Туре	Type numeric		
	Default	Default 1		
	Min Value			
	Max Value			

By setting this option to a value greater than 1 (the default), a mysqld process can use multiple connections to the cluster, effectively mimicking several SQL nodes. Each connection requires its own

[api] or [mysqld] section in the cluster configuration (config.ini) file, and counts against the maximum number of API connections supported by the cluster.

Suppose that you have 2 cluster host computers, each running an SQL node whose mysqld process was started with --ndb-cluster-connection-pool=4; this means that the cluster must have 8 API slots available for these connections (instead of 2). All of these connections are set up when the SQL node connects to the cluster, and are allocated to threads in a round-robin fashion.

This option is useful only when running mysqld on host machines having multiple CPUs, multiple cores, or both. For best results, the value should be smaller than the total number of cores available on the host machine. Setting it to a value greater than this is likely to degrade performance severely.

### **Important**

Because each SQL node using connection pooling occupies multiple API node slots—each slot having its own node ID in the cluster—you must *not* use a node ID as part of the cluster connection string when starting any mysqld process that employs connection pooling.

Setting a node ID in the connection string when using the --ndb-cluster-connection-pool option causes node ID allocation errors when the SQL node attempts to connect to the cluster.

This option was introduced in MySQL Cluster NDB 6.2.2. Beginning with MySQL Cluster NDB 6.2.16 and MySQL Cluster NDB 6.3.13, the value used for this option is available as a system variable (Bug #35573).

Prior to MySQL Cluster NDB 7.0.23 and MySQL Cluster NDB 7.1.12, there was also a status variable corresponding to this option; however, the status variable was removed as redundant as of these versions. (Bug #60119)

• --ndb-blob-read-batch-bytes=bytes

Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10	
Command-Line Format	ndb-k	olob-read-batch-bytes
Option-File Format	ndb-blo	bb-read-batch-bytes
System Variable Name	ndb_blo	b_read_batch_bytes
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type numeric	
	Default 65536	
	Min 0 Value	
	Max Value 4294967295	

This option can be used to set the size (in bytes) for batching of BLOB data reads in MySQL Cluster applications. When this batch size is exceeded by the amount of BLOB data to be read within the current transaction, any pending BLOB read operations are immediately executed.

The maximum value for this option is 4294967295; the default is 65536. Setting it to 0 has the effect of disabling BLOB read batching.

#### Note

In NDB API applications, you can control BLOB write batching with the setMaxPendingBlobReadBytes() and getMaxPendingBlobReadBytes() methods.

This option was introduced in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

• --ndb-blob-write-batch-bytes=bytes

Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10	
Command-Line Format	ndb-l	olob-write-batch-bytes
Option-File Format	ndb-blo	ob-write-batch-bytes
System Variable Name	ndb_blo	ob_write_batch_bytes
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type numeric	
	Default 65536	
	Min 0 Value	
	Max 4294967295 Value	

This option can be used to set the size (in bytes) for batching of BLOB data writes in MySQL Cluster applications. When this batch size is exceeded by the amount of BLOB data to be written within the current transaction, any pending BLOB write operations are immediately executed.

The maximum value for this option is 4294967295; the default is 65536. Setting it to 0 has the effect of disabling BLOB write batching.

#### Note

In NDB API applications, you can control <code>BLOB</code> write batching with the <code>setMaxPendingBlobWriteBytes()</code> and <code>getMaxPendingBlobWriteBytes()</code> methods.

This option was introduced in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

• --ndb-connectstring=connect\_string

Command-Line Format	ndb-d	ndb-connectstring	
Option-File Format	ndb-cor	ndb-connectstring	
	Permitted Values		
	Туре	string	

When using the NDBCLUSTER storage engine, this option specifies the management server that distributes cluster configuration data. See Section 5.2.3, "MySQL Cluster Connection Strings", for syntax.

• --ndb-deferred-constraints=[0|1]

Introduced	5.1.56-ndb-7.0.28, 5.1.56-ndb-7.1.14		
Command-Line Format	ndb-d	deferred-constraints	
Option-File Format	ndb-def	erred-constraints	
System Variable Name	ndb_def	erred_constraints	
Variable Scope	Global, S	Global, Session	
Dynamic Variable	Yes		
	Permitted Values		
	Type integer		
	Default 0		
	Min 0 Value		
	Max 1 Value		

Controls whether or not constraint checks on unique indexes are deferred until commit time, where such checks are supported. 0 is the default.

This option is not normally needed for operation of MySQL Cluster or MySQL Cluster Replication, and is intended primarily for use in testing.

This option was added in MySQL Cluster NDB 7.0.28 and MySQL Cluster NDB 7.1.14.

--ndb-distribution=[KEYHASH|LINHASH]

Introduced	5.1.32-ndb-7.0.4	
Command-Line Format	ndb-d	distribution={KEYHASH LINHASH}
Option-File Format	ndb-dis	stribution
System Variable Name	ndb_dis	stribution
Variable Scope	Global	
Dynamic Variable	Yes	
	Permitted Values	
	Type enumeration Default KEYHASH	
	Valid	LINHASH
Value		KEYHASH

Controls the default distribution method for NDB tables. Can be set to either of KEYHASH (key hashing) or LINHASH (linear hashing). KEYHASH is the default.

--ndb-mgmd-host=host[:port]

Command-Line Format	ndb-r	ndb-mgmd-host=host[:port]	
Option-File Format	ndb-mgmd-host		
	Permitte	Permitted Values	
	Туре	Type string	
	Default	Default localhost:1186	

Can be used to set the host and port number of a single management server for the program to connect to. If the program requires node IDs or references to multiple management servers (or both) in its connection information, use the --ndb-connectstring option instead.

### • --ndbcluster

Command-Line Format	ndbc	ndbcluster	
Option-File Format	ndbclus	ndbcluster	
Disabled by	skip-no	skip-ndbcluster	
	Permitte	Permitted Values	
	Туре	Type boolean	
	Default	FALSE	

The NDBCLUSTER storage engine is necessary for using MySQL Cluster. If a mysqld binary includes support for the NDBCLUSTER storage engine, the engine is disabled by default. Use the --ndbcluster option to enable it. Use --skip-ndbcluster to explicitly disable the engine.

### • --ndb-log-apply-status

Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10	
Command-Line Format	ndb-]	log-apply-status
Option-File Format	ndb-log	g-apply-status
System Variable Name	ndb_log	g_apply_status
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Туре	boolean
	Default	OFF

Causes a slave mysqld to log any updates received from its immediate master to the mysql.ndb\_apply\_status table in its own binary log using its own server ID rather than the server ID of the master. In a circular or chain replication setting, this allows such updates to propagate to the mysql.ndb\_apply\_status tables of any MySQL servers configured as slaves of the current mysqld.

In a chain replication setup, using this option allows downstream (slave) clusters to be aware of their positions relative to all of their upstream contributors (masters).

In a circular replication setup, this option causes changes to ndb\_apply\_status tables to complete the entire circuit, eventually propagating back to the originating MySQL Cluster. This also allows a cluster acting as a master to see when its changes (epochs) have been applied to the other clusters in the circle.

This option was added in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10. It has no effect unless the MySQL server is started with the --ndbcluster option.

## • --ndb-log-orig

Introduced	5.1.22-ndb-6.3.2	
Command-Line Format	ndb-l	log-orig
Option-File Format	ndb-log	g-orig
System Variable Name	ndb_log_orig	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type boolean	
	Default	OFF

Log the originating server ID and epoch in the ndb\_binlog\_index table.

Note that this makes it possible for a given epoch to have multiple rows in ndb\_binlog\_index, one for each originating epoch.

For more information, see Section 8.4, "MySQL Cluster Replication Schema and Tables".

### --ndb-log-transaction-id

Introduced	5.1.56-ndb-7.1.16	
Command-Line Format	ndb-1	log-transaction-id[={0 1}]
Option-File Format	ndb-log	g-transaction-id
System Variable Name	ndb_log	g_transaction_id
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type boolean	
	Default OFF	

Causes a slave <code>mysqld</code> to write the NDB transaction ID in each row of the binary log. Such logging requires the use of the Version 2 event format for the binary log; thus, <code>--log-bin-use-v1-row-events</code> must be set to <code>FALSE</code> in order to use this option.

This option is available beginning with MySQL Cluster NDB 7.1.16 (and is not supported in mainline MySQL Server 5.1). It is required to enable MySQL Cluster Replication conflict detection and resolution using the NDB\$EPOCH\_TRANS() function introduced in the same MySQL Cluster release.

The default value is FALSE.

For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

• --ndb-nodeid=#

Introduced	5.1.15		
Command-Line Format	ndb-	nodeid=#	
Option-File Format	ndb-no	ndb-nodeid	
Status Variable Name	Ndb_cl	Ndb_cluster_node_id	
Variable Scope	Global		
Dynamic Variable	No		
	Permitte	Permitted Values (>= 5.1.5)	
	Туре	Type numeric	
	Min Value	1	
	Max Value	255	

Set this MySQL server's node ID in a MySQL Cluster.

Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option can be used *instead* of specifying the node ID as part of the connection string or in the <code>config.ini</code> file, or permitting the cluster to determine an arbitrary node ID. If you use this option, then <code>--ndb-nodeid</code> must be specified <code>before--ndb-connectstring</code>. If <code>--ndb-nodeid</code> is used <code>and</code> a node ID is specified in the connection string, then the MySQL server cannot connect to the cluster.

Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the --ndb-nodeid option overrides any node ID set with --ndb-connectstring, regardless of the order in which the two options are used.

In addition (regardless of the MySQL Cluster version), if --ndb-nodeid is used, then either a matching node ID must be found in a [mysqld] or [api] section of config.ini, or there must be an "open" [mysqld] or [api] section in the file (that is, a section without a NodeId or Id parameter specified). This is also true if the node ID is specified as part of the connection string.

Regardless of how the node ID is determined, its is shown as the value of the global status variable Ndb\_cluster\_node\_id in the output of SHOW STATUS, and as cluster\_node\_id in the connection row of the output of SHOW ENGINE NDBCLUSTER STATUS.

For more information about node IDs for MySQL Cluster SQL nodes, see Section 5.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster".

--ndb-log-empty-epochs=[0|1]

Introduced	5.1.31-ndb-6.3.21, 5.1.31-ndb-6.4.1		
Command-Line Format	ndb-log-empty-epochs		
Option-File Format	ndb-lo	ndb-log-empty-epochs	
System Variable Name	ndb_log_empty_epochs		
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		

# Default OFF

Causes epochs during which there were no changes to be written to the ndb\_apply\_status and ndb\_binlog\_index tables, even when --log-slave-updates is enabled.

By default this option is disabled. Disabling --ndb-log-empty-epochs causes epoch transactions with no changes not to be written to the binary log, although a row is still written even for an empty epoch in ndb\_binlog\_index (Bug #49559, Bug #11757505).

Because --ndb-log-empty-epochs=1 causes the size of ndb\_binlog\_index table to increase independently of the size of the binary log, users should be prepared to manage the growth of this table, even if they expect the cluster to be idle a large part of the time.

This option was introduced in MySQL Cluster NDB 6.3.21 and MySQL Cluster NDB 6.4.1. Prior to MySQL Cluster NDB 6.3.33, MySQL Cluster NDB 7.0.14, and MySQL Cluster NDB 7.1.3, setting -- ndb-log-empty-epochs=0 also caused no row to be written in ndb\_binlog\_index for an empty epoch.

### • --server-id-bits=#

Introduced	5.1.47-ndb-7.0.17, 5.1.47-ndb-7.1.6	
Command-Line Format	server-id-bits=#	
Option-File Format	server-id-bits	
System Variable Name	server_id_bits	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type numeric	
	Default	32
	Min Value	7
	Max Value	32

This option indicates the number of least significant bits within the 32-bit server\_id which actually identify the server. Indicating that the server is actually identified by fewer than 32 bits makes it possible for some of the remaining bits to be used for other purposes, such as storing user data generated by applications using the NDB API's Event API within the AnyValue of an OperationOptions structure (MySQL Cluster uses the AnyValue to store the server ID).

When extracting the effective server ID from server\_id for purposes such as detection of replication loops, the server ignores the remaining bits. The --server-id-bits option is used to mask out any irrelevant bits of server\_id in the IO and SQL threads when deciding whether an event should be ignored based on the server ID.

This data can be read from the binary log by mysqlbinlog, provided that it is run with its own --server-id-bits option set to 32 (the default).

The value of server\_id must be less than 2 ^ server\_id\_bits; otherwise, mysqld refuses to start.

This system variable was added in MySQL Cluster NDB 7.0.17 and MySQL Cluster NDB 7.1.6; it is supported only in these and later releases of MySQL Cluster. It is not supported by the standard MySQL Server.

## • --skip-ndbcluster

Command-Line Format	skip-ndbcluster		
Option-File Format	skip-ndbcluster		

Disable the NDBCLUSTER storage engine. This is the default for binaries that were built with NDBCLUSTER storage engine support; the server allocates memory and other resources for this storage engine only if the --ndbcluster option is given explicitly. See Section 5.1, "Quick Test Setup of MySQL Cluster", for an example.

### • ndb-transid-mysql-connection-map=state

Introduced	5.1.56-ndb-7.1.17	
Command-Line Format	ndb-	from 5.1.16-ndb-7.1.17
	transid	<b>!</b> -
	mysql-	
	connect	ion-
	map[=st	ate]
	Permitted Values	
	Type enumera	enumeration
Ī	Default	ON
	Valid	ON
Values	OFF	
		FORCE

Enables or disables the plugin that handles the ndb\_transid\_mysql\_connection\_map table in the INFORMATION\_SCHEMA database. Takes one of the values ON, OFF, or FORCE. ON (the default) enables the plugin. OFF disables the plugin, which makes ndb\_transid\_mysql\_connection\_map inaccessible. FORCE keeps the MySQL Server from starting if the plugin fails to load and start.

You can see whether the ndb\_transid\_mysql\_connection\_map table plugin is running by checking the output of SHOW PLUGINS.

This option was added in MySQL Cluster NDB 7.1.17.

### • --ndb-wait-connected=seconds

Introduced	5.1.16-ndb-6.2.0		
Command-Line Format	ndb-wait-connected=#		
Option-File Format	ndb-wait-connected		
System Variable Name	ndb_wait_connected		
Variable Scope	Global		
Dynamic Variable	No		
	Permitted Values (<= 5.1.56-ndb-7.0.26, 5.1.56-ndb-7.1.15)		

Туре	numeric
Defa	ult 0
Min Value	0
Max Value	31536000
Perm	itted Values (>= 5.1.56-ndb-7.1.16, 5.1.56-ndb-7.0.27)
Туре	numeric
Defa	<b>ult</b> 30
Min Value	0
Max Value	31536000

This option sets the period of time that the MySQL server waits for connections to MySQL Cluster management and data nodes to be established before accepting MySQL client connections. The time is specified in seconds.

Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, there existed a hard-coded 30-second timeout (which was removed in these versions), and the default value for this option was 0. Starting with these releases, the default value is 30, and user-supplied values are handled correctly. (Bug #12543299)

## • --ndb-wait-setup=seconds

Introduced	5.1.39-ndb-6.2.19, 5.1.39-ndb-6.3.28, 5.1.39-ndb-7.0.9	
Command-Line Format	ndb-wait-setup=#	
Option-File Format	ndb-wai	it-setup
System Variable Name	ndb_wai	it_setup
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values (<= 5.1.56-ndb-7.0.26, 5.1.56-ndb-7.1.15)	
	Туре	numeric
	Default	15
	Min Value	0
	Max Value	31536000
	Permitted Values (>= 5.1.56-ndb-7.0.27, 5.1.56-ndb-7.1.16)	
	Туре	numeric
	Default	30
	Min Value	0
	Max Value	31536000

This variable shows the period of time that the MySQL server waits for the NDB storage engine to complete setup before timing out and treating NDB as unavailable. The time is specified in seconds.

Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, the default value for this option was 15. In these and later releases, the default value is 30. (Bug #12543299)

• --ndb\_optimization\_delay=milliseconds

Introduced	5.1.23-ndb-6.3.7		
System Variable Name	ndb_opt	ndb_optimization_delay	
Variable Scope	Global	Global	
Dynamic Variable	Yes		
	Permitted Values		
	Type numeric		
	Default 10	10	
	Min Value	0	
	Max Value	100000	

Set the number of milliseconds to wait between sets of rows by OPTIMIZE TABLE statements on NDB tables. The default is 10.

# 5.4.3 MySQL Cluster System Variables

This section provides detailed information about MySQL server system variables that are specific to MySQL Cluster and the NDB storage engine. For system variables not specific to MySQL Cluster, see Server System Variables. For general information on using system variables, see Using System Variables.

• have\_ndbcluster

System Variable Name	have_ndbcluster	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Туре	boolean

YES if mysqld supports NDBCLUSTER tables. DISABLED if --skip-ndbcluster is used.

This variable is deprecated and is removed in MySQL 5.6. Use SHOW ENGINES instead.

• multi\_range\_count

Command-Line Format	multi_range_count=#		
Option-File Format	multi_range_count		
System Variable Name	multi_range_count		
Variable Scope	Global, Session		
Dynamic Variable	Yes		

Permitte	Permitted Values	
Туре	numeric	
Default	256	
Min Value	1	
Max Value	4294967295	

The maximum number of ranges to send to a table handler at once during range selects. The default value is 256. Sending multiple ranges to a handler at once can improve the performance of certain selects dramatically. This is especially true for the NDBCLUSTER table handler, which needs to send the range requests to all nodes. Sending a batch of those requests at once reduces communication costs significantly.

This variable is deprecated in MySQL 5.1, and is no longer supported in MySQL 5.5, in which arbitrarily long lists of ranges can be processed.

• ndb\_autoincrement\_prefetch\_sz

Command-Line Format	ndb_autoincrement_prefetch_sz		
Option-File Format	ndb_autoincrement_prefetch_sz		
Option Sets Variable	Yes, ndb_autoincrement_prefetch_sz		
Variable Name	ndb_aut	toincrement_prefetch_sz	
Variable Scope	Global, S	Session	
Dynamic Variable	Yes		
	Permitted Values (>= 5.1.1, <= 5.1.22)		
	Туре	numeric	
	Default	32	
	Range 1 256		
	Permitted Values (>= 5.1.23, <= 5.1.24)		
	Туре	numeric	
	Default	1	
	Range	1 256	
	Permitted Values (>= NDB 6.2.0, <= NDB 6.2.9)		
	Type numeric		
	Default 32		
	Range 1 256		
	Permitted Values (>= NDB 6.2.10)		
	Туре	numeric	
	Default	32	
	<b>Range</b> 1 256		
	Permitted Values (>= NDB 6.3.0, <= 6.3.6)		
	Type numeric		

	Default	32
F	Range	1 256
F	Permitted Values (>= NDB 6.3.7, <= 6.3.30)	
1	Гуре	numeric
[	Default	1
F	Range	1 256
F	Permitted Values (>= NDB 6.3.31)	
1	Гуре	numeric
	Default	1
F	Range	1 65536
F	Permitte	d Values (>= NDB 6.4.0, <= 7.0.10)
1	Гуре	numeric
	Default	32
F	Range	1 256
F	Permitted Values (>= NDB 7.0.11)	
1	Гуре	numeric
	Default	1
F	Range	1 65536
F	Permitted Values (>= NDB 7.1.1)	
1	Гуре	numeric
	Default	1
F	Range	1 65536

Determines the probability of gaps in an autoincremented column. Set it to 1 to minimize this. Setting it to a high value for optimization makes inserts faster, but decreases the likelihood that consecutive autoincrement numbers will be used in a batch of inserts. The minimum value is 1. Prior to MySQL 5.1.23, MySQL Cluster NDB 6.2.9, and MySQL Cluster NDB 6.3.7, the default value was 32; in these and all later versions, the default is 1. Prior to MySQL Cluster NDB 6.3.31 and MySQL Cluster NDB 7.0.11, the maximum value was 256; in these and all later versions of MySQL Cluster (including all MySQL Cluster NDB 7.1 releases), the maximum is 65536 (Bug #50621).

Beginning with MySQL Cluster NDB 6.2.10, MySQL Cluster NDB 6.3.7, and MySQL 5.1.23, this variable affects the number of AUTO\_INCREMENT IDs that are fetched between statements only. Within a statement, at least 32 IDs are now obtained at a time. Also beginning with these releases, the default value is 1. (Bug #31956)

## **Important**

This variable does not affect inserts performed using INSERT ... SELECT.

• ndb\_cache\_check\_time

Command-Line Format	ndb_cache_check_time		
Option-File Format	ndb_cache_check_time		
System Variable Name	ndb_cache_check_time		

Variable Scope	Global	Global	
Dynamic Variable	Yes	Yes	
	Permitte	Permitted Values	
	Type	numeric	
	Default	0	

The number of milliseconds that elapse between checks of MySQL Cluster SQL nodes by the MySQL query cache. Setting this to 0 (the default and minimum value) means that the query cache checks for validation on every query.

The recommended maximum value for this variable is 1000, which means that the check is performed once per second. A larger value means that the check is performed and possibly invalidated due to updates on different SQL nodes less often. It is generally not desirable to set this to a value greater than 2000.

#### • ndb deferred constraints

Introduced	5.1.56-ndb-7.0.28, 5.1.56-ndb-7.1.14	
Command-Line Format	ndb-deferred-constraints	
Option-File Format	ndb_deferred_constraints	
System Variable Name	ndb_deferred_constraints	
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type integer	
	Default 0	
	Min Value	0
	Max Value	1

Controls whether or not constraint checks are deferred, where these are supported. 0 is the default.

This variable was added in MySQL Cluster NDB 7.0.28 and MySQL Cluster NDB 7.1.14.

This variable is not normally needed for operation of MySQL Cluster or MySQL Cluster Replication, and is intended primarily for use in testing.

### • ndb\_distribution

Introduced	5.1.32-ndb-7.0.4		
Command-Line Format	ndb-distribution={KEYHASH LINHASH}		
Option-File Format	ndb_distribution		
System Variable Name	ndb_distribution={KEYHASH LINHASH}		
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		

Туре	enumeration
Default	KEYHASH
Valid	LINHASH
Values	KEYHASH

Controls the default distribution method for NDB tables. Can be set to either of KEYHASH (key hashing) or LINHASH (linear hashing). KEYHASH is the default.

• ndb\_eventbuffer\_max\_alloc

Introduced	5.1.72-ndb-7.1.29	
Command-Line Format	ndb_eventbuffer_max_alloc	
Option-File Format	ndb_eventbuffer_max_alloc	
System Variable Name	ndb_eventbuffer_max_alloc	
Variable Scope	Global	
Dynamic Variable	Yes	
	Permitted Values	
	Type numeric	
	Default 0	
	Min Value	0
	Max Value	4294967295

Sets the maximum amount memory (in bytes) that can be allocated for buffering events by the NDB API. 0 means that no limit is imposed, and is the default.

This variable was added in MySQL Cluster NDB 7.1.29.

• ndb\_extra\_logging

Introduced	5.1.6	
Command-Line Format	ndb_extra_logging=#	
Option-File Format	ndb_extra_logging	
System Variable Name	ndb_extra_logging	
Variable Scope	Global	
Dynamic Variable	Yes	
	Permitted Values (<= 5.1.18)	
	Туре	numeric
	Default	0

This variable enables recording in the MySQL error log of information specific to the NDB storage engine.

When this variable is set to 0, the only information specific to NDB that is written to the MySQL error log relates to transaction handling. If it set to a value greater than 0 but less than 10, NDB table schema and connection events are also logged, as well as whether or not conflict resolution is in use, and other NDB

errors and information. If the value is set to 10 or more, information about NDB internals, such as the progress of data distribution among cluster nodes, is also written to the MySQL error log.

This variable was added in MySQL 5.1.6. Prior to MySQL Cluster NDB 6.3, the default value was 0; in MySQL Cluster NDB 6.3.0 and later, the default is 1.

#### • ndb\_force\_send

Command-Line Format	ndb-force-send		
Option-File Format	ndb_force_send		
System Variable Name	ndb_force_send		
Variable Scope	Global, Session		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default	TRUE	

Forces sending of buffers to NDB immediately, without waiting for other threads. Defaults to ON.

## • ndb\_index\_stat\_cache\_entries

Deprecated	5.1.19	
Removed	5.1.73-ndb-7.1.31	
Command-Line Format	ndb_index_stat_cache_entries	
Option-File Format	ndb_index_stat_cache_entries	
	Permitted Values	
	Type numeric	
	Default 32 Min 0 Value	
	Max 4294967295 Value	

Sets the granularity of the statistics by determining the number of starting and ending keys to store in the statistics memory cache. Zero means no caching takes place; in this case, the data nodes are always queried directly. Default value: 32.

#### Note

If  $ndb\_index\_stat\_enable$  is OFF, then setting this variable has no effect.

This variable is deprecated as of MySQL 5.1.19, and is removed from MySQL Cluster NDB 7.1.31 and later.

## • ndb\_index\_stat\_enable

	Permitted Values	
Option-File Format	ndb_index_stat_enable	
Command-Line Format	ndb_index_stat_enable	

Туре	boolean	
Default	OFF	
Permitte	Permitted Values	
Туре	boolean	
Default	ON	

Use NDB index statistics in query optimization. Defaults to OFF prior to MySQL Cluster NDB 7.2; ON is the default in MySQL Cluster NDB 7.2 and later.

• ndb\_index\_stat\_option

Introduced	5.1.1.56	5.1.1.56-ndb-7.1.15	
Command-Line Format	ndb-:	ndb-index-stat-option	
Option-File Format	ndb_inc	dex_stat_option	
	Permitte	Permitted Values	
	Туре	string	
	Default	loop_enable=1000ms,loop_idle=1000ms,loop_busy=100 update_batch=1,read_batch=4,idle_batch=32,check_b check_delay=10m,delete_batch=8, clean_delay=1m,error_batch=4, error_delay=1m,evict_batch=8,evict_delay=1m,cache cache_lowpct=90,zero_total=0	oatch=8,
	Permitte	ed Values	
	Туре	string	
	Default	<pre>loop_checkon=1000ms,loop_idle=1000ms,loop_busy=10 update_batch=1,read_batch=4,idle_batch=32,check_b check_delay=1m,delete_batch=8,clean_delay=0,error error_delay=1m,evict_batch=8,evict_delay=1m,cache cache_lowpct=90</pre>	atch=32, _batch=4,

This variable is used for providing tuning options for NDB index statistics generation. The list consist of comma-separated name-value pairs of option names and values. Note that this list must not contain any space characters.

Options not used when setting ndb\_index\_stat\_option are not changed from their default values. For example, you can set ndb\_index\_stat\_option = 'loop\_idle=1000ms, cache\_limit=32M'.

Time values can be optionally suffixed with s (seconds) or ms (milliseconds). Integer values can be suffixed with k, m, or m.

The names of the options that can be set using this variable are shown in the table that follows. The table also provides brief descriptions of the options, their default values, and (where applicable) their minimum and maximum values.

Name	Description	Default/Units	Minimum/Maximum
loop_enable		1000 ms	0/4G
loop_idle	Time to sleep when idle	1000 ms	0/4G

Name	Description	Default/Units	Minimum/Maximum
loop_busy	Time to sleep when more work is waiting	100 ms	0/4G
update_batch		1	0/4G
read_batch		4	1/4G
idle_batch		32	1/4G
check_batch		8	1/4G
check_delay	How often to check for new statistics	10 ms	1/4G
delete_batch		8	0/4G
clean_delay		1 ms	0/4G
error_batch		4	1/4G
error_delay		1 ms	1/4G
evict_batch		8	1/4G
evict_delay	Clean LRU cache, from read time	1 ms	0/4G
cache_limit	Maximum amount of memory in bytes used for cached index statistics by this mysqld; clean up the cache when this is exceeded.	32 M	0/4G
cache_lowpct		90	0/100
zero_total	Setting this to 1 causes all accumulating counters in ndb_index_stat_stat to be reset to 0. Note that the option value is also reset to 0 when this is done.	0 us	0/1

ndb\_index\_stat\_option was added in MySQL Cluster NDB 7.1.15.

• ndb\_index\_stat\_update\_freq

Deprecated	5.1.19	5.1.19	
Removed	5.1.73-no	5.1.73-ndb-7.1.31	
Command-Line Format	ndb_:	ndb_index_stat_update_freq	
Option-File Format	ndb_index_stat_update_freq		
	Permitte	Permitted Values	
	Туре	Type numeric	
	Default	20	

Min Value	0
Max Value	4294967295

How often to query data nodes instead of the statistics cache. For example, a value of 20 (the default) means to direct every 20<sup>th</sup> query to the data nodes.

#### Note

If ndb\_index\_stat\_cache\_entries is 0, then setting this variable has no effect; in this case, every query is sent directly to the data nodes.

This variable is deprecated as of MySQL 5.1.19, and is removed from MySQL Cluster NDB 7.1.31 and later.

• ndb\_join\_pushdown

Introduced	5.1.51-ndb-7.2.0	
System Variable Name	ndb_join_pushdown	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type boolean	
	Default TRUE	

Added in MySQL Cluster NDB 7.2.0, this variable controls whether joins on NDB tables are pushed down to the NDB kernel (data nodes). Previously, a join was handled using multiple accesses of NDB by the SQL node; however, when ndb\_join\_pushdown is enabled, a pushable join is sent in its entirety to the data nodes, where it can be distributed among the data nodes and executed in parallel on multiple copies of the data, with a single, merged result being returned to mysqld. This can reduce greatly the number of round trips between an SQL node and the data nodes required to handle such a join.

By default, ndb\_join\_pushdown is enabled.

In order for a join to be pushable, it must meet the following conditions:

1. Only columns can be compared, and all columns to be joined must use exactly the same data type.

This means that expressions such as t1.a = t2.a + constant cannot be pushed down, and that (for example) a join on an INT column and a BIGINT column also cannot be pushed down.

- 2. Queries referencing BLOB or TEXT columns are not supported.
- 3. Explicit locking is not supported; however, the NDB storage engine's characteristic implicit row-based locking is enforced.

This means that a join using FOR UPDATE cannot be pushed down.

4. In order for a join to be pushed down, child tables in the join must be accessed using one of the ref, eq\_ref, or const access methods, or some combination of these methods.

Outer joined child tables can only be pushed using eq\_ref.

If the root of the pushed join is an eq\_ref or const, only child tables joined by eq\_ref can be appended. (A table joined by ref is likely to become the root of another pushed join.)

If the query optimizer decides on Using join cache for a candidate child table, that table cannot be pushed as a child. However, it may be the root of another set of pushed tables.

5. Joins referencing tables explicitly partitioned by [LINEAR] HASH, LIST, or RANGE currently cannot be pushed down.

You can see whether a given join can be pushed down by checking it with EXPLAIN; when the join can be pushed down, you can see references to the pushed join in the Extra column of the output, as shown in this example:

```
mysql> EXPLAIN
   -> SELECT e.first_name, e.last_name, t.title, d.dept_name
        FROM employees e
   ->
          JOIN dept_emp de ON e.emp_no=de.emp_no
   ->
          JOIN departments d ON d.dept_no=de.dept_no
          JOIN titles t ON e.emp_no=t.emp_no\G
id: 1
 select_type: SIMPLE
     table: d
       type: ALL
possible_keys: PRIMARY
       key: NULL
    key_len: NULL
       ref: NULL
      rows: 9
      Extra: Parent of 4 pushed join@1
************************ 2. row *****************
        id: 1
 select_type: SIMPLE
     table: de
       type: ref
possible_keys: PRIMARY,emp_no,dept_no
       key: dept_no
    key_len: 4
       ref: employees.d.dept_no
      rows: 5305
     Extra: Child of 'd' in pushed join@1
id: 1
 select_type: SIMPLE
      table: e
      type: eq_ref
possible_keys: PRIMARY
       key: PRIMARY
    key_len: 4
       ref: employees.de.emp_no
     Extra: Child of 'de' in pushed join@1
id: 1
 select_type: SIMPLE
      table: t
       type: ref
possible_keys: PRIMARY,emp_no
       key: emp_no
    key_len: 4
       ref: employees.de.emp_no
       rows: 19
      Extra: Child of 'e' in pushed join@1
```

4 rows in set (0.00 sec)

#### Note

If inner joined child tables are joined by ref, and the result is ordered or grouped by a sorted index, this index cannot provide sorted rows, which forces writing to a sorted tempfile.

Two additional sources of information about pushed join performance are available:

- 1. The status variables Ndb\_pushed\_queries\_defined, Ndb\_pushed\_queries\_dropped, Ndb\_pushed\_queries\_executed, and Ndb\_pushed\_reads (all introduced in MySQL Cluster NDB 7.2.0).
- 2. The counters in the ndbinfo.counters table that belong to the DBSPJ kernel block. (These counters and the DBSPJ block were also introduced in MySQL Cluster NDB 7.2.0). See Section 7.10.7, "The ndbinfo counters Table", for information about these counters. See also The DBSPJ Block, in the MySQL Cluster API Developer Guide.
- ndb\_log\_apply\_status

Introduced	5.1.51-ndb-7.0.21, 5.1.51-ndb-7.1.10	
Command-Line Format	ndb-log-apply-status	
Option-File Format	ndb-log-apply-status	
System Variable Name	ndb_log_apply_status	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type boolean	
	Default OFF	

A read-only variable which shows whether the server was started with the --ndb-log-apply-status option.

This variable was added in MySQL Cluster NDB 7.0.21 and MySQL Cluster NDB 7.1.10.

## • ndb\_log\_bin

Introduced	5.1.6		
Command-Line Format	ndb-log-bin={1 0}		
System Variable Name	ndb_log	ndb_log_bin	
Variable Scope	Global, Session		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default ON		

Causes updates to NDB tables to be written to the binary log. Setting this variable has no effect if binary logging is not already enabled for the server using log\_bin.ndb\_log\_bin defaults to 1 (ON); normally, there is never any need to change this value in a production environment.

This variable was added in MySQL 5.1.6.

## • ndb\_log\_binlog\_index

Introduced	5.1.6		
Command-Line Format	ndb-l	log-binlog-index={1 0}	
System Variable Name	ndb_log	g_binlog_index	
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default	ON	

Causes a mapping of epochs to positions in the binary log to be inserted into the ndb\_binlog\_index table. Setting this variable has no effect if binary logging is not already enabled for the server using log\_bin. (In addition, ndb\_log\_bin must not be disabled.) ndb\_log\_binlog\_index defaults to 1 (ON); normally, there is never any need to change this value in a production environment.

This variable was added in MySQL 5.1.6.

#### • ndb\_log\_orig

Introduced	5.1.22-ndb-6.3.2		
Command-Line Format	ndb-I	log-orig	
Option-File Format	ndb-log	g-orig	
System Variable Name	ndb_log	ndb_log_orig	
Variable Scope	Global		
Dynamic Variable	No		
	Permitted Values		
	Туре	boolean	
	Default	OFF	

Shows whether the originating server ID and epoch are logged in the ndb\_binlog\_index table. Set using the --ndb-log-orig server option.

This variable was added in MySQL Cluster NDB 6.3.2.

## • ndb\_optimized\_node\_selection

Command-Line Format	ndb-	from 5.1.22-ndb-6.3.4	
	optimiz	optimized-	
	node-	node-	
	selecti	on=#	
Option-File Format	ndb_optimized_node_selection		
	Permitte	Permitted Values	
	Туре	Type boolean	
	Default	ON	

Permitte	Permitted Values	
Туре	numeric	
Default	3	
Min Value	0	
Max Value	3	

**Prior to MySQL Cluster NDB 6.3.4.** Causes an SQL node to use the "closest" data node as transaction coordinator. Enabled by default. Set to 0 or OFF to disable, in which case the SQL node uses each data node in the cluster in succession. When this option is disabled each SQL thread attempts to use a given data node 8 times before proceeding to the next one.

**Beginning with MySQL Cluster NDB 6.3.4.** There are two forms of optimized node selection, described here:

- The SQL node uses <u>promixity</u> to determine the transaction coordinator; that is, the "closest" data
  node to the SQL node is chosen as the transaction coordinator. For this purpose, a data node having
  a shared memory connection with the SQL node is considered to be "closest" to the SQL node; the
  next closest (in order of decreasing proximity) are: TCP connection to localhost; SCI connection;
  TCP connection from a host other than localhost.
- 2. The SQL thread uses <u>distribution awareness</u> to select the data node. That is, the data node housing the cluster partition accessed by the first statement of a given transaction is used as the transaction coordinator for the entire transaction. (This is effective only if the first statement of the transaction accesses no more than one cluster partition.)

This option takes one of the integer values 0, 1, 2, or 3. 3 is the default. These values affect node selection as follows:

- 0: Node selection is not optimized. Each data node is employed as the transaction coordinator 8 times before the SQL thread proceeds to the next data node. (This is the same "round-robin" behavior as caused by setting this option to 0 or OFF in previous versions of MySQL Cluster.)
- 1: Proximity to the SQL node is used to determine the transaction coordinator. (This is the same behavior as caused by setting this option to 1 or ON in previous MySQL versions.)
- 2: Distribution awareness is used to select the transaction coordinator. However, if the first statement of the transaction accesses more than one cluster partition, the SQL node reverts to the round-robin behavior seen when this option is set to 0.
- 3: If distribution awareness can be employed to determine the transaction coordinator, then it is used; otherwise proximity is used to select the transaction coordinator. (This is the default behavior in MySQL Cluster NDB 6.3.4 and later.)

#### **Important**

Beginning with MySQL Cluster NDB 6.3.4, it is no longer possible to set -- ndb\_optimized\_node\_selection to ON or OFF; attempting to do so causes mysqld to abort with an error.

• ndb\_report\_thresh\_binlog\_epoch\_slip

Command-Line Format	ndb_report_thresh_binlog_epoch_slip
---------------------	-------------------------------------

Option-File Format	ndb_report_thresh_binlog_epoch_slip	
	Permitte	ed Values
	Туре	numeric
	Default	3
	Min Value	0
	Max Value	256

This is a threshold on the number of epochs to be behind before reporting binary log status. For example, a value of 3 (the default) means that if the difference between which epoch has been received from the storage nodes and which epoch has been applied to the binary log is 3 or more, a status message will be sent to the cluster log.

• ndb\_report\_thresh\_binlog\_mem\_usage

Command-Line Format	ndb_report_thresh_binlog_mem_usage		
Option-File Format	ndb_rep	ndb_report_thresh_binlog_mem_usage	
	Permitte	Permitted Values	
	Type numeric		
	Default 10		
	Min 0 Value		
	Max Value	10	

This is a threshold on the percentage of free memory remaining before reporting binary log status. For example, a value of 10 (the default) means that if the amount of available memory for receiving binary log data from the data nodes falls below 10%, a status message will be sent to the cluster log.

• slave\_allow\_batching

Introduced	5.1.19-ndb-6.2.3			
Command-Line Format	slave	slave-allow-batching		
Option-File Format	slave_a	allow_batching		
System Variable Name	slave_a	slave_allow_batching		
Variable Scope	Global			
Dynamic Variable	Yes			
	Permitted Values			
	Type boolean			
	Default	off		

Whether or not batched updates are enabled on MySQL Cluster replication slaves.

This variable is available beginning with MySQL Cluster NDB 6.2.3. Currently, it is available for mysqld only as supplied with MySQL Cluster or built from the MySQL Cluster sources. For more information, see Section 8.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

## • ndb\_table\_no\_logging

Introduced	5.1.23-ndb-6.3.8		
System Variable Name	ndb_table_no_logging		
Variable Scope	Session		
Dynamic Variable	Yes		
	Permitted Values		
	Type boolean		
	Default	FALSE	

When this variable is set to ON or 1, it causes NDB tables not to be checkpointed to disk. More specifically, this setting applies to tables which are created or altered using ENGINE NDB when ndb\_table\_no\_logging is enabled, and continues to apply for the lifetime of the table, even if ndb\_table\_no\_logging is later changed. Suppose that A, B, C, and D are tables that we create (and perhaps also alter), and that we also change the setting for ndb\_table\_no\_logging as shown here:

```
SET @@ndb_table_no_logging = 1;

CREATE TABLE A ... ENGINE NDB;

CREATE TABLE B ... ENGINE MYISAM;

CREATE TABLE C ... ENGINE MYISAM;

ALTER TABLE B ENGINE NDB;

SET @@ndb_table_no_logging = 0;

CREATE TABLE D ... ENGINE NDB;

ALTER TABLE C ENGINE NDB;

SET @@ndb_table_no_logging = 1;
```

After the previous sequence of events, tables A and B are not checkpointed; A was created with ENGINE NDB and B was altered to use NDB, both while ndb\_table\_no\_logging was enabled. However, tables C and D are logged; C was altered to use NDB and D was created using ENGINE NDB, both while ndb\_table\_no\_logging was disabled. Setting ndb\_table\_no\_logging back to 1 or ON does not cause table C or D to be checkpointed.

## Note

ndb\_table\_no\_logging has no effect on the creation of NDB table schema files; to suppress these, use ndb\_table\_temporary instead.

• ndb table temporary

Introduced	5.1.23-ndb-6.3.8		
System Variable Name	ndb_table_temporary		
Variable Scope	Session		
Dynamic Variable	Yes		
	Permitted Values		
	Туре	boolean	
	Default	FALSE	

When set to ON or 1, this variable causes NDB tables not to be written to disk: This means that no table schema files are created, and that the tables are not logged.

## Note

Setting this variable currently has no effect in MySQL Cluster NDB 7.0 and later. This is a known issue; see Bug #34036.

• ndb\_use\_copying\_alter\_table

Introduced	5.1.12		
System Variable Name	ndb_use_copying_alter_table		
Variable Scope	Global, Session		
Dynamic Variable	No		

Forces NDB to use copying of tables in the event of problems with online ALTER TABLE operations. The default value is OFF.

This variable was added in MySQL 5.1.12.

• ndb\_version

Introduced	5.1.16-ndb-7.1.19		
System Variable Name	ndb_vei	ndb_version	
Variable Scope	Global	Global	
Dynamic Variable	No		
	Permitted Values		
	Туре	string	
	Default		

NDB engine version, as a composite integer.

This variable was added in MySQL Cluster NDB 7.1.19.

• ndb\_version\_string

Introduced	5.1.16-ndb-7.1.19	
System Variable Name	ndb_version_string	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Type string	
	Default	

NDB engine version in ndb-x.y.z format.

This variable was added in MySQL Cluster NDB 7.1.19.

• ndb\_use\_exact\_count

System Variable Name	ndb_use_exa <b>255</b> count
•	

Variable Scope	Global, S	Global, Session	
Dynamic Variable	Yes	Yes	
	Permitte	Permitted Values	
	Туре	Type boolean	
	Default ON		
	Permitte	Permitted Values	
	Туре	boolean	
	Default	Default OFF	

Forces NDB to use a count of records during SELECT COUNT(\*) query planning to speed up this type of query. Prior to MySQL Cluster NDB 7.1.7, the default value for this variable was ON. Starting with the MySQL Cluster NDB 7.1.8, the value of ndb\_use\_exact\_count defaults to OFF, which allows for faster queries overall.

• ndb\_use\_transactions

Command-Line Format	ndb_use_transactions	
Option-File Format	ndb_use	e_transactions
System Variable Name	ndb_use	e_transactions
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type boolean	
	Default ON	

You can disable NDB transaction support by setting this variable's values to OFF (not recommended). The default is ON.

## Note

The setting for this variable was not honored in MySQL Cluster NDB 6.4.3 and MySQL Cluster NDB 7.0.4. (Bug #43236)

• transaction\_allow\_batching

Introduced	5.1.23-ndb-6.3.7	
System Variable Name	transaction_allow_batching	
Variable Scope	Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type boolean	
	Default FALSE	

When set to 1 or ON, this variable enables batching of statements within the same transaction. To use this variable, autocommit must first be disabled by setting it to 0 or OFF; otherwise, setting transaction\_allow\_batching has no effect.

It is safe to use this variable with transactions that performs writes only, as having it enabled can lead to reads from the "before" image. You should ensure that any pending transactions are committed (using an explicit COMMIT if desired) before issuing a SELECT.

## **Important**

transaction\_allow\_batching should not be used whenever there is the possibility that the effects of a given statement depend on the outcome of a previous statement within the same transaction.

This variable was added in MySQL Cluster NDB 6.3.7, and is currently supported in MySQL Cluster only.

The system variables in the following list all relate to the ndbinfo information database. They were added in MySQL Cluster NDB 7.1.1.

#### • ndbinfo\_database

Introduced	5.1.41-ndb-7.1.1		
System Variable Name	ndbinfo	ndbinfo_database	
Variable Scope	Global	Global	
Dynamic Variable	No		
	Permitted Values		
	Type string		
	Default ndbinfo		

Shows the name used for the NDB information database; the default is ndbinfo. This is a read-only variable whose value is determined at compile time; you can set it by starting the server using --ndbinfo-database=name, which sets the value shown for this variable but does not actually change the name used for the NDB information database.

## • ndbinfo\_max\_bytes

Introduced	5.1.41-ndb-7.1.1	
Command-Line Format	ndbinfo-max-bytes=#	
System Variable Name	ndbinfo	o_max_bytes
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type numeric	
	Default 0	

Used in testing and debugging only.

## • ndbinfo\_max\_rows

Introduced	5.1.41-ndb-7.1.1		
Command-Line Format	ndbinfo-max-rows=#		
System Variable Name	ndbinfo_max_rows		

Variable Scope	Global, Session		
Dynamic Variable	Yes		
	Permitte	Permitted Values	
	Туре	Type numeric	
	Default	Default 10	

Used in testing and debugging only.

• ndbinfo\_offline

Introduced	5.1.41-ndb-7.1.1	
System Variable Name	ndbinfo	o_offline
Variable Scope	Global	
Dynamic Variable	Yes	
	Permitted Values	
	Type boolean	
	Default OFF	

Place the ndbinfo database into offline mode, in which tables and views can be opened even when they do not actually exist, or when they exist but have different definitions in NDB. No rows are returned from such tables (or views).

• ndbinfo\_show\_hidden

Introduced	5.1.41-ndb-7.1.1	
Command-Line Format	ndbir	nfo-show-hidden={0 1}
System Variable Name	ndbinfo	o_show_hidden
Variable Scope	Global, Session	
Dynamic Variable	Yes	
	Permitted Values	
	Type boolean	
	Default OFF	

Whether or not the ndbinfo database's underlying internal tables are shown in the mysql client. The default is OFF.

• ndbinfo\_table\_prefix

Introduced	5.1.41-ndb-7.1.1		
Command-Line Format	ndbinfo-table-prefix=name		
System Variable Name	ndbinfo_table_prefix		
Variable Scope	Global, Session		
Dynamic Variable	Yes		
	Permitted Values		
	Type string 258		

Default ndb\$		
---------------	--	--

The prefix used in naming the ndbinfo database's base tables (normally hidden, unless exposed by setting ndbinfo\_show\_hidden). This is a read-only variable whose default value is "ndb\$". You can start the server with the --ndbinfo-table-prefix option, but this merely sets the variable and does not change the actual prefix used to name the hidden base tables; the prefix itself is determined at compile time.

## • ndbinfo\_version

Introduced	5.1.41-ndb-7.1.1	
System Variable Name	ndbinfo_version	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Туре	string
	Default	

Shows the version of the ndbinfo engine in use; read-only.

## • ndb\_log\_transaction\_id

Introduced	5.1.56-ndb-7.1.16	
System Variable Name	ndb_log_transaction_id	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Туре	boolean
	Default	OFF

This read-only, Boolean system variable shows whether a slave mysqld writes NDB transaction IDs in the binary log (required to use "active-active" MySQL Cluster Replication with ndspload N

ndb\_log\_transaction\_id is available in MySQL Cluster NDB 7.1.16 and later. It is not supported in mainline MySQL Server 5.1.

For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

## • ndb\_log\_empty\_epochs

Introduced	5.1.31-ndb-6.3.21, 5.1.31-ndb-6.4.1		
Command-Line Format	ndb-log-empty-epochs		
Option-File Format	ndb_log_empty_epochs		
System Variable Name	ndb_log_empty_epochs		
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		

Туре	boolean
Defa	off off

When this variable is set to 0, epoch transactions with no changes are not written to the binary log, although a row is still written even for an empty epoch in ndb\_binlog\_index (Bug #49559, Bug #11757505).

#### • server\_id\_bits

Introduced	5.1.47-ndb-7.0.17, 5.1.47-ndb-7.1.6	
Command-Line Format	server-id-bits=#	
Option-File Format	server-	-id-bits
System Variable Name	server_id_bits	
Variable Scope	Global	
Dynamic Variable	No	
	Permitted Values	
	Туре	numeric
	Default	32
	Min Value	7
	Max Value	32

The effective value of server\_id if the server was started with the --server-id-bits option set to a nondefault value.

If the value of server\_id greater than or equal to 2 to the power of server\_id\_bits, mysqld refuses to start.

This system variable was added in MySQL Cluster NDB 7.0.17 and MySQL Cluster NDB 7.1.6; it is supported only in these and later releases of MySQL Cluster. server\_id\_bits is not supported by the standard MySQL Server.

# 5.4.4 MySQL Cluster Status Variables

This section provides detailed information about MySQL server status variables that relate to MySQL Cluster and the NDB storage engine. For status variables not specific to MySQL Cluster, and for general information on using status variables, see Server Status Variables.

• Handler discover

The MySQL server can ask the NDBCLUSTER storage engine if it knows about a table with a given name. This is called discovery. Handler\_discover indicates the number of times that tables have been discovered using this mechanism.

• Ndb\_api\_wait\_exec\_complete\_count\_session

The number of times a thread has been blocked in this client session while waiting for execution of an operation to complete. This includes all <code>execute()</code> calls as well as implicit implicit executes for blob and auto-increment operations not visible to clients.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysgld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_wait\_exec\_complete\_count\_slave

The number of times a thread has been blocked by this slave while waiting for execution of an operation to complete. This includes all <code>execute()</code> calls as well as implicit implicit executes for blob and auto-increment operations not visible to clients.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_wait\_exec\_complete\_count

The number of times a thread has been blocked by this MySQL Server (SQL node) while waiting for execution of an operation to complete. This includes all <code>execute()</code> calls as well as implicit implicit executes for blob and auto-increment operations not visible to clients.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_wait\_scan\_result\_count\_session

The number of times a thread has been blocked in this client session while waiting for a scan-based signal, such as when waiting for more results from a scan, or when waiting for a scan to close.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_wait\_scan\_result\_count\_slave

The number of times a thread has been blocked by this slave while waiting for a scan-based signal, such as when waiting for more results from a scan, or when waiting for a scan to close.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_wait\_scan\_result\_count

The number of times a thread has been blocked by this MySQL Server (SQL node) while waiting for a scan-based signal, such as when waiting for more results from a scan, or when waiting for a scan to close.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_wait\_meta\_request\_count\_session

The number of times a thread has been blocked in this client session waiting for a metadata-based signal, such as is expected for DDL requests, new epochs, and seizure of transaction records.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_wait\_meta\_request\_count\_slave

The number of times a thread has been blocked by this slave waiting for a metadata-based signal, such as is expected for DDL requests, new epochs, and seizure of transaction records.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_wait\_meta\_request\_count

The number of times a thread has been blocked by this MySQL Server (SQL node) waiting for a metadata-based signal, such as is expected for DDL requests, new epochs, and seizure of transaction records.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_wait\_nanos\_count\_session

Total time (in nanoseconds) spent in this client session waiting for any type of signal from the data nodes.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api wait nanos count slave

Total time (in nanoseconds) spent by this slave waiting for any type of signal from the data nodes.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb api wait nanos count

Total time (in nanoseconds) spent by this MySQL Server (SQL node) waiting for any type of signal from the data nodes.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_sent\_count\_session

Amount of data (in bytes) sent to the data nodes in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_sent\_count\_slave

Amount of data (in bytes) sent to the data nodes by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_sent\_count

Amount of data (in bytes) sent to the data nodes by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_received\_count\_session

Amount of data (in bytes) received from the data nodes in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_received\_count\_slave

Amount of data (in bytes) received from the data nodes by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_bytes\_received\_count

Amount of data (in bytes) received from the data nodes by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_start\_count\_session

The number of transactions started in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_start\_count\_slave

The number of transactions started by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_start\_count

The number of transactions started by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_commit\_count\_session

The number of transactions committed in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_commit\_count\_slave

The number of transactions committed by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_commit\_count

The number of transactions committed by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_abort\_count\_session

The number of transactions aborted in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_abort\_count\_slave

The number of transactions aborted by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_trans\_abort\_count

The number of transactions aborted by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_trans\_close\_count\_session

The number of transactions closed in this client session. This value may be greater than the sum of Ndb\_api\_trans\_commit\_count\_session and Ndb\_api\_trans\_abort\_count\_session, since some transactions may have been rolled back.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_trans\_close\_count\_slave

The number of transactions closed by this slave. This value may be greater than the sum of Ndb\_api\_trans\_commit\_count\_slave and Ndb\_api\_trans\_abort\_count\_slave, since some transactions may have been rolled back.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_trans\_close\_count

The number of transactions closed by this MySQL Server (SQL node). This value may be greater than the sum of Ndb\_api\_trans\_commit\_count and Ndb\_api\_trans\_abort\_count, since some transactions may have been rolled back.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_pk\_op\_count\_session

The number of operations in this client session based on or using primary keys. This includes operations on blob tables, implicit unlock operations, and auto-increment operations, as well as user-visible primary key operations.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_pk\_op\_count\_slave

The number of operations by this slave based on or using primary keys. This includes operations on blob tables, implicit unlock operations, and auto-increment operations, as well as user-visible primary key operations.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api pk op count

The number of operations by this MySQL Server (SQL node) based on or using primary keys. This includes operations on blob tables, implicit unlock operations, and auto-increment operations, as well as user-visible primary key operations.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_uk\_op\_count\_session

The number of operations in this client session based on or using unique keys.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_uk\_op\_count\_slave

The number of operations by this slave based on or using unique keys.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_uk\_op\_count

The number of operations by this MySQL Server (SQL node) based on or using unique keys.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_table\_scan\_count\_session

The number of table scans that have been started in this client session, including scans of internal tables,.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api table scan count slave

The number of table scans that have been started by this slave, including scans of internal tables,.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_table\_scan\_count

The number of table scans that have been started by this MySQL Server (SQL node), including scans of internal tables,.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api range scan count session

The number of range scans that have been started in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_range\_scan\_count\_slave

The number of range scans that have been started by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_range\_scan\_count

The number of range scans that have been started by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_pruned\_scan\_count\_session

The number of scans in this client session that have been pruned to a single partition.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_pruned\_scan\_count\_slave

The number of scans by this slave that have been pruned to a single partition.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb api pruned scan count

The number of scans by this MySQL Server (SQL node) that have been pruned to a single partition.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_scan\_batch\_count\_session

The number of batches of rows received in this client session. 1 batch is defined as 1 set of scan results from a single fragment.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb\_api\_scan\_batch\_count\_slave

The number of batches of rows received by this slave. 1 batch is defined as 1 set of scan results from a single fragment.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

• Ndb api scan batch count

The number of batches of rows received by this MySQL Server (SQL node). 1 batch is defined as 1 set of scan results from a single fragment.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_read\_row\_count\_session

The total number of rows that have been read in this client session. This includes all rows read by any primary key, unique key, or scan operation made in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api read row count slave

The total number of rows that have been read by this slave. This includes all rows read by any primary key, unique key, or scan operation made by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_read\_row\_count

The total number of rows that have been read by this MySQL Server (SQL node). This includes all rows read by any primary key, unique key, or scan operation made by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_trans\_local\_read\_row\_count\_session

The total number of rows that have been read in this client session. This includes all rows read by any primary key, unique key, or scan operation made in this client session.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it relates to the current session only, and is not affected by any other clients of this mysqld.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_trans\_local\_read\_row\_count\_slave

The total number of rows that have been read by this slave. This includes all rows read by any primary key, unique key, or scan operation made by this slave.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope. If this MySQL server does not act as a replication slave, or does not use NDB tables, this value is always 0.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_trans\_local\_read\_row\_count

The total number of rows that have been read by this MySQL Server (SQL node). This includes all rows read by any primary key, unique key, or scan operation made by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_event\_data\_count\_injector

The number of row change events received by the NDB binlog injector thread.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api event data count

The number of row change events received by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_event\_nondata\_count\_injector

The number of events received, other than row change events, by the NDB binlog injector thread.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_api\_event\_nondata\_count

The number of events received, other than row change events, by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

## • Ndb\_api\_event\_bytes\_count\_injector

The number of bytes of events received by the NDB binlog injector thread.

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb api event bytes count

The number of bytes of events received by this MySQL Server (SQL node).

Although this variable can be read using either SHOW GLOBAL STATUS or SHOW SESSION STATUS, it is effectively global in scope.

This variable was added in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. For more information, see Section 7.15, "NDB API Statistics Counters and Variables".

#### • Ndb\_cluster\_node\_id

If the server is acting as a MySQL Cluster node, then the value of this variable its node ID in the cluster.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

## • Ndb\_config\_from\_host

If the server is part of a MySQL Cluster, the value of this variable is the host name or IP address of the Cluster management server from which it gets its configuration data.

If the server is not part of a MySQL Cluster, then the value of this variable is an empty string.

Prior to MySQL 5.1.12, this variable was named Ndb\_connected\_host.

#### • Ndb\_config\_from\_port

If the server is part of a MySQL Cluster, the value of this variable is the number of the port through which it is connected to the Cluster management server from which it gets its configuration data.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

Prior to MySQL 5.1.12, this variable was named Ndb\_connected\_port.

#### • Ndb\_conflict\_fn\_max

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of times that a row was not applied on the current SQL node due to "greatest timestamp wins" conflict resolution since the last time that this mysqld was started.

This variable was added in MySQL Cluster NDB 6.3.3. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

#### • Ndb conflict fn old

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of times that a row was not applied as the result of "same timestamp wins" conflict resolution on a given mysqld since the last time it was restarted.

This variable was added in MySQL Cluster NDB 6.3.4. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

## • Ndb\_conflict\_fn\_epoch

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of rows found to be in conflict using NDB\$EPOCH() conflict resolution on a given mysqld since the last time it was restarted.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

## • Ndb\_conflict\_fn\_epoch\_trans

Used in MySQL Cluster Replication conflict resolution, this variable shows the number of rows found to be in conflict using NDB\$EPOCH\_TRANS() conflict resolution on a given mysqld since the last time it was restarted.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

#### • Ndb conflict trans row conflict count

Used in MySQL Cluster Replication conflict resolution, this status variable shows the number of rows found to be directly in-conflict by a transactional conflict function on a given mysqld since the last time it was restarted.

Currently, the only transactional conflict detection function supported by MySQL Cluster is NDB\$EPOCH\_TRANS(), so this status variable is effectively the same as Ndb\_conflict\_fn\_epoch\_trans.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

#### • Ndb\_conflict\_trans\_row\_reject\_count

Used in MySQL Cluster Replication conflict resolution, this status variable shows the total number of rows realigned due to being determined as conflicting by a transactional conflict detection function. This includes not only Ndb\_conflict\_trans\_row\_conflict\_count, but any rows in or dependent on conflicting transactions.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

#### • Ndb conflict trans reject count

Used in MySQL Cluster Replication conflict resolution, this status variable shows the number of transactions found to be in conflict by a transactional conflict detection function.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

## • Ndb\_conflict\_trans\_detect\_iter\_count

Used in MySQL Cluster Replication conflict resolution, this shows the number of internal iterations required to commit an epoch transaction. Should be (slightly) greater than or equal to Ndb\_conflict\_trans\_conflict\_commit\_count.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

• Ndb\_conflict\_trans\_conflict\_commit\_count

Used in MySQL Cluster Replication conflict resolution, this shows the number of epoch transactions committed after they required transactional conflict handling.

This variable was added in MySQL Cluster NDB 7.1.16. For more information, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

• Ndb execute count

Provides the number of round trips to the NDB kernel made by operations. Added in MySQL Cluster NDB 6.3.6.

• Ndb number of data nodes

If the server is part of a MySQL Cluster, the value of this variable is the number of data nodes in the cluster.

If the server is not part of a MySQL Cluster, then the value of this variable is 0.

Prior to MySQL 5.1.12, this variable was named Ndb\_number\_of\_storage\_nodes.

• Ndb\_pushed\_queries\_defined

The total number of joins pushed down to the NDB kernel for distributed handling on the data nodes. Note that joins tested using EXPLAIN that can be pushed down contribute to this number. Added in MySQL Cluster NDB 7.2.0.

• Ndb pushed queries dropped

The number of joins that were pushed down to the NDB kernel but that could not be handled there. Added in MySQL Cluster NDB 7.2.0.

• Ndb\_pushed\_queries\_executed

The number of joins successfully pushed down to NDB and executed there. Added in MySQL Cluster NDB 7.2.0.

• Ndb\_pushed\_reads

The number of rows returned to mysqld from the NDB kernel by joins that were pushed down. Note that executing EXPLAIN on joins that can be pushed down to NDB does not add to this number. Added in MySQL Cluster NDB 7.2.0.

• Slave heartbeat period

Shows the replication heartbeat interval (in seconds) on a replication slave.

This variable was added in MySQL Cluster NDB 6.3.4.

• Slave\_received\_heartbeats

This counter increments with each replication heartbeat received by a replication slave since the last time that the slave was restarted or reset, or a CHANGE MASTER TO statement was issued.

This variable was added in MySQL Cluster NDB 6.3.4.

• Ndb\_pruned\_scan\_count

This variable holds a count of the number of scans executed by NDBCLUSTER since the MySQL Cluster was last started where NDBCLUSTER was able to use partition pruning.

Using this variable together with Ndb\_scan\_count can be helpful in schema design to maximize the ability of the server to prune scans to a single table partition, thereby involving only a single data node.

This variable was added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.5.

• Ndb scan count

This variable holds a count of the total number of scans executed by NDBCLUSTER since the MySQL Cluster was last started.

This variable was added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.5.

# 5.5 Using High-Speed Interconnects with MySQL Cluster

Even before design of NDBCLUSTER began in 1996, it was evident that one of the major problems to be encountered in building parallel databases would be communication between the nodes in the network. For this reason, NDBCLUSTER was designed from the very beginning to permit the use of a number of different data transport mechanisms. In this Manual, we use the term *transporter* for these.

The MySQL Cluster codebase provides for four different transporters:

- TCP/IP using 100 Mbps or gigabit Ethernet, as discussed in Section 5.2.8, "MySQL Cluster TCP/IP Connections".
- Direct (machine-to-machine) TCP/IP; although this transporter uses the same TCP/IP protocol as mentioned in the previous item, it requires setting up the hardware differently and is configured differently as well. For this reason, it is considered a separate transport mechanism for MySQL Cluster. See Section 5.2.9, "MySQL Cluster TCP/IP Connections Using Direct Connections", for details.
- Shared memory (SHM). For more information about SHM, see Section 5.2.10, "MySQL Cluster Shared-Memory Connections".

#### Note

SHM is considered experimental only, and is not officially supported.

 Scalable Coherent Interface (SCI), as described in the next section of this chapter, Section 5.2.11, "SCI Transport Connections in MySQL Cluster".

Most users today employ TCP/IP over Ethernet because it is ubiquitous. TCP/IP is also by far the best-tested transporter for use with MySQL Cluster.

We are working to make sure that communication with the ndbd process is made in "chunks" that are as large as possible because this benefits all types of data transmission.

For users who desire it, it is also possible to use cluster interconnects to enhance performance even further. There are two ways to achieve this: Either a custom transporter can be designed to handle this case, or you can use socket implementations that bypass the TCP/IP stack to one extent or another. We have experimented with both of these techniques using the SCI (Scalable Coherent Interface) technology developed by Dolphin Interconnect Solutions.

# 5.5.1 Configuring MySQL Cluster to use SCI Sockets

It is possible employing Scalable Coherent Interface (SCI) technology to achieve a significant increase in connection speeds and throughput between MySQL Cluster data and SQL nodes. To use SCI, it is necessary to obtain and install Dolphin SCI network cards and to use the drivers and other software supplied by Dolphin. You can get information on obtaining these, from Dolphin Interconnect Solutions. SCI SuperSocket or SCI Transporter support is available for 32-bit and 64-bit Linux, Solaris, Windows, and other platforms. See the Dolphin documentation referenced later in this section for more detailed information regarding platforms supported for SCI.

#### Note

Prior to MySQL 5.1.20, there were issues with building MySQL Cluster with SCI support (see Bug #25470), but these have been resolved due to work contributed by Dolphin. SCI Sockets are now correctly supported for MySQL Cluster hosts running recent versions of Linux using the <code>-max</code> builds, and versions of MySQL Cluster with SCI Transporter support can be built using either of <code>compile-amd64-max-sci</code> or <code>compile-pentium64-max-sci</code>. Both of these build scripts can be found in the <code>BUILD</code> directory of the MySQL Cluster source trees; it should not be difficult to adapt them for other platforms. Generally, all that is necessary is to compile MySQL Cluster with SCI Transporter support is to configure the MySQL Cluster build using <code>--with-ndb-sci=/opt/DIS</code>.

Once you have acquired the required Dolphin hardware and software, you can obtain detailed information on how to adapt a MySQL Cluster configured for normal TCP/IP communication to use SCI from the from the Dolphin SCI online documentation.

## 5.5.2 MySQL Cluster Interconnects and Performance

The ndbd process has a number of simple constructs which are used to access the data in a MySQL Cluster. We have created a very simple benchmark to check the performance of each of these and the effects which various interconnects have on their performance.

There are four access methods:

- **Primary key access.** This is access of a record through its primary key. In the simplest case, only one record is accessed at a time, which means that the full cost of setting up a number of TCP/IP messages and a number of costs for context switching are borne by this single request. In the case where multiple primary key accesses are sent in one batch, those accesses share the cost of setting up the necessary TCP/IP messages and context switches. If the TCP/IP messages are for different destinations, additional TCP/IP messages need to be set up.
- Unique key accesse. Unique key accesses are similar to primary key accesses, except that a unique
  key access is executed as a read on an index table followed by a primary key access on the table.
  However, only one request is sent from the MySQL Server, and the read of the index table is handled by
  ndbd. Such requests also benefit from batching.
- **Full table scan.** When no indexes exist for a lookup on a table, a full table scan is performed. This is sent as a single request to the ndbd process, which then divides the table scan into a set of parallel scans on all cluster ndbd processes. In future versions of MySQL Cluster, an SQL node will be able to filter some of these scans.
- Range scan using ordered index. When an ordered index is used, it performs a scan in the same manner as the full table scan, except that it scans only those records which are in the range used by the query transmitted by the MySQL server (SQL node). All partitions are scanned in parallel when all bound index attributes include all attributes in the partitioning key.

With benchmarks developed internally by MySQL for testing simple and batched primary and unique key accesses, we have found that using SCI sockets improves performance by approximately 100% over TCP/IP, except in rare instances when communication performance is not an issue. This can occur when scan filters make up most of processing time or when very large batches of primary key accesses are achieved. In that case, the CPU processing in the ndbd processes becomes a fairly large part of the overhead.

Using the SCI transporter instead of SCI Sockets is only of interest in communicating between ndbd processes. Using the SCI transporter is also only of interest if a CPU can be dedicated to the ndbd process because the SCI transporter ensures that this process will never go to sleep. It is also important to ensure that the ndbd process priority is set in such a way that the process does not lose priority due to running for an extended period of time, as can be done by locking processes to CPUs in Linux 2.6. If such a configuration is possible, the ndbd process will benefit by 10–70% as compared with using SCI sockets. (The larger figures will be seen when performing updates and probably on parallel scan operations as well.)

There are several other optimized socket implementations for computer clusters, including Myrinet, Gigabit Ethernet, Infiniband and the VIA interface. However, we have tested MySQL Cluster so far only with SCI sockets. See Section 5.5.1, "Configuring MySQL Cluster to use SCI Sockets", for information on how to set up SCI sockets using ordinary TCP/IP for MySQL Cluster.

278	

# Chapter 6 MySQL Cluster Programs

# **Table of Contents**

6.1 ndbd — The MySQL Cluster Data Node Daemon	279
6.2 ndbinfo_select_all — Select From ndbinfo Tables	287
6.3 ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)	289
6.4 ndb_mgmd — The MySQL Cluster Management Server Daemon	290
6.5 ndb_mgm — The MySQL Cluster Management Client	299
6.6 ndb_blob_tool — Check and Repair BLOB and TEXT columns of MySQL Cluster Tables	300
6.7 ndb_config — Extract MySQL Cluster Configuration Information	303
6.8 ndb_cpcd — Automate Testing for NDB Development	
6.9 ndb_delete_all — Delete All Rows from an NDB Table	312
6.10 ndb_desc — Describe NDB Tables	
6.11 ndb_drop_index — Drop Index from an NDB Table	317
6.12 ndb_drop_table — Drop an NDB Table	318
6.13 ndb_error_reporter — NDB Error-Reporting Utility	318
6.14 ndb_index_stat — NDB Index Statistics Utility	320
6.15 ndb_print_backup_file — Print NDB Backup File Contents	326
6.16 ndb_print_schema_file — Print NDB Schema File Contents	327
6.17 ndb_print_sys_file — Print NDB System File Contents	327
6.18 ndbd_redo_log_reader — Check and Print Content of Cluster Redo Log	327
6.19 ndb_restore — Restore a MySQL Cluster Backup	
6.20 ndb_select_all — Print Rows from an NDB Table	344
6.21 ndb_select_count — Print Row Counts for NDB Tables	348
6.22 ndb_show_tables — Display List of NDB Tables	348
6.23 ndb_size.pl — NDBCLUSTER Size Requirement Estimator	350
6.24 ndb_waiter — Wait for MySQL Cluster to Reach a Given Status	353
6.25 Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster	
Programs	355

Using and managing a MySQL Cluster requires several specialized programs, which we describe in this chapter. We discuss the purposes of these programs in a MySQL Cluster, how to use the programs, and what startup options are available for each of them.

These programs include the MySQL Cluster data, management, and SQL node processes (ndbd, ndbmtd, ndb\_mgmd, and mysgld) and the management client (ndb\_mgm).

For information about using mysqld as a MySQL Cluster process, see Section 7.4, "MySQL Server Usage for MySQL Cluster".

Other NDB utility, diagnostic, and example programs are included with the MySQL Cluster distribution. These include ndb\_restore, ndb\_show\_tables, and ndb\_config. These programs are also covered in this section.

The final portion of this section contains tables of options that are common to all the various MySQL Cluster programs.

# 6.1 ndbd — The MySQL Cluster Data Node Daemon

ndbd is the process that is used to handle all the data in tables using the NDB Cluster storage engine. This is the process that empowers a data node to accomplish distributed transaction handling, node recovery, checkpointing to disk, online backup, and related tasks.

In a MySQL Cluster, a set of ndbd processes cooperate in handling data. These processes can execute on the same computer (host) or on different computers. The correspondences between data nodes and Cluster hosts is completely configurable.

The following table includes command options specific to the MySQL Cluster data node program ndbd. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndbd), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.1 This table describes command-line options for the ndbd program

Format	Description	Added or Removed
initial	Perform initial start of ndbd, including cleaning the file system. Consult the documentation before using this option	All MySQL 5.1 based releases
nostart,	Don't start ndbd immediately; ndbd waits for command to start from ndb_mgmd	All MySQL 5.1 based releases
daemon,	Start ndbd as daemon (default); override withnodaemon	All MySQL 5.1 based releases
-d		
nodaemon	Do not start ndbd as daemon; provided for testing purposes	All MySQL 5.1 based releases
foreground	Run ndbd in foreground, provided for debugging purposes (implies nodaemon)	All MySQL 5.1 based releases
nowait-nodes=list	Do not wait for these data nodes to start (takes comma-separated list of node IDs). Also requires ndb-nodeid to be used.	ADDED: 5.1.9
initial-start	Perform partial initial start (requiresnowait-nodes)	ADDED: 5.1.11
bind-address=name	Local bind address	ADDED: 5.1.12
install[=name]	Used to install the data node process as a Windows service. Does not apply on non-Windows platforms.	ADDED: NDB 7.0.16, NDB 7.1.5
remove[=name]	Used to remove a data node process that was previously installed as a Windows service. Does not apply on non-Windows platforms.	ADDED: NDB 7.0.16, NDB 7.1.5
connect-retries=#	Number of times to try contacting the management server; set to -1 to keep trying indefinitely	ADDED: NDB 7.0.36, NDB 7.1.25

Format	Description	Added or Removed
connect-delay=#	Time to wait between attempts to contact a management server, in seconds	ADDED: NDB 7.0.36, NDB 7.1.25

#### Note

All of these options also apply to the multi-threaded version of this program (ndbmtd, available in MySQL Cluster NDB 7.0 and later) and you may substitute "ndbmtd" for "ndbd" wherever the latter occurs in this section.

#### • --bind-address

Introduced	5.1.12	
Command-Line Format	bind-address=name	
	Permitted Values	
	Туре	string
	Default	

Causes ndbd to bind to a specific network interface (host name or IP address). This option has no default value.

This option was added in MySQL 5.1.12.

#### • --daemon, -d

Command-Line Format	daemo	daemon	
	-d		
	Permitted Values Type boolean		
	Default	TRUE	

Instructs ndbd or ndbmtd to execute as a daemon process. This is the default behavior. --nodaemon can be used to prevent the process from running as a daemon.

This option has no effect when running ndbd or ndbmtd on Windows platforms.

#### • --nodaemon

Command-Line Format	nodaemon	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Prevents ndbd or ndbmtd from executing as a daemon process. This option overrides the --daemon option. This is useful for redirecting output to the screen when debugging the binary.

As of MySQL Cluster NDB 7.0.8, the default behavior for ndbd and ndbmtd on Windows is to run in the foreground, making this option unnecessary on Windows platforms, where it has no effect. (Bug #45588)

#### • --foreground

Command-Line Format	foreground	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Causes ndbd or ndbmtd to execute as a foreground process, primarily for debugging purposes. This option implies the --nodaemon option.

This option has no effect when running ndbd or ndbmtd on Windows platforms.

#### • --initial

Command-Line Format	initial	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Instructs ndbd to perform an initial start. An initial start erases any files created for recovery purposes by earlier instances of ndbd. It also re-creates recovery log files. Note that on some operating systems this process can take a substantial amount of time.

An --initial start is to be used *only* when starting the ndbd process under very special circumstances; this is because this option causes all files to be removed from the MySQL Cluster file system and all redo log files to be re-created. These circumstances are listed here:

- When performing a software upgrade which has changed the contents of any files.
- When restarting the node with a new version of ndbd.
- As a measure of last resort when for some reason the node restart or system restart repeatedly fails.
   In this case, be aware that this node can no longer be used to restore data due to the destruction of the data files.

Use of this option prevents the StartPartialTimeout and StartPartitionedTimeout configuration parameters from having any effect.

#### **Important**

This option does *not* affect either of the following types of files:

- Backup files that have already been created by the affected node
- MySQL Cluster Disk Data files (see Section 7.12, "MySQL Cluster Disk Data Tables").

This option also has no effect on recovery of data by a data node that is just starting (or restarting) from data nodes that are already running. This recovery of data occurs automatically, and requires no user intervention in a MySQL Cluster that is running normally.

It is permissible to use this option when starting the cluster for the very first time (that is, before any data node files have been created); however, it is *not* necessary to do so.

#### • --initial-start

Introduced	5.1.11		
Command-Line Format	initial-start		
	Permitted Values		
	Туре	Type boolean	
	Default	FALSE	

This option is used when performing a partial initial start of the cluster. Each node should be started with this option, as well as --nowait-nodes.

Suppose that you have a 4-node cluster whose data nodes have the IDs 2, 3, 4, and 5, and you wish to perform a partial initial start using only nodes 2, 4, and 5—that is, omitting node 3:

```
shell> ndbd --ndb-nodeid=2 --nowait-nodes=3 --initial-start
shell> ndbd --ndb-nodeid=4 --nowait-nodes=3 --initial-start
shell> ndbd --ndb-nodeid=5 --nowait-nodes=3 --initial-start
```

Prior to MySQL 5.1.19, it was not possible to perform DDL operations involving Disk Data tables on a partially started cluster. (See Bug #24631.)

When using this option, you must also specify the node ID for the data node being started with the --ndb-nodeid option.

This option was added in MySQL 5.1.11.

#### **Important**

Do not confuse this option with the --nowait-nodes option added for ndb\_mgmd in MySQL Cluster NDB 7.0.10, which can be used to enable a cluster configured with multiple management servers to be started without all management servers being online.

--nowait-nodes=node\_id\_1[, node\_id\_2[, ...]]

Introduced	5.1.9	5.1.9	
Command-Line Format	nowait-nodes=list		
	Permitted Values		
	Туре	string	
	Default		

This option takes a list of data nodes which for which the cluster will not wait for before starting.

This can be used to start the cluster in a partitioned state. For example, to start the cluster with only half of the data nodes (nodes 2, 3, 4, and 5) running in a 4-node cluster, you can start each ndbd process with --nowait-nodes=3, 5. In this case, the cluster starts as soon as nodes 2 and 4 connect, and does not wait StartPartitionedTimeout milliseconds for nodes 3 and 5 to connect as it would otherwise.

If you wanted to start up the same cluster as in the previous example without one ndbd (say, for example, that the host machine for node 3 has suffered a hardware failure) then start nodes 2, 4, and 5

with --nowait-nodes=3. Then the cluster will start as soon as nodes 2, 4, and 5 connect and will not wait for node 3 to start.

This option was added in MySQL 5.1.9.

• --nostart, -n

Command-Line Format	nostart	
	-n	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Instructs ndbd not to start automatically. When this option is used, ndbd connects to the management server, obtains configuration data from it, and initializes communication objects. However, it does not actually start the execution engine until specifically requested to do so by the management server. This can be accomplished by issuing the proper START command in the management client (see Section 7.2, "Commands in the MySQL Cluster Management Client").

• --install[=name]

Introduced	5.1.47-ndb-7.1.5	
Command-Line Format	install[=name]	
	Permitted Values	
	Туре	string
	Default	ndbd

Causes ndbd to be installed as a Windows service. Optionally, you can specify a name for the service; if not set, the service name defaults to ndbd. Although it is preferable to specify other ndbd program options in a my.ini or my.cnf configuration file, it is possible to use together with --install. However, in such cases, the --install option must be specified first, before any other options are given, for the Windows service installation to succeed.

It is generally not advisable to use this option together with the <code>--initial</code> option, since this causes the data node file system to be wiped and rebuilt every time the service is stopped and started. Extreme care should also be taken if you intend to use any of the other <code>ndbd</code> options that affect the starting of data nodes—including <code>--initial-start</code>, <code>--nostart</code>, and <code>--nowait-nodes</code>—together with <code>--install</code>, and you should make absolutely certain you fully understand and allow for any possible consequences of doing so.

The --install option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

• --remove[=name]

Introduced	5.1.47-ndb-7.1.5	
Command-Line Format	remove[=name]	
	Permitted Values	
	Type stri <sub>284</sub>	

Default	ndbd
---------	------

Causes an ndbd process that was previously installed as a Windows service to be removed. Optionally, you can specify a name for the service to be uninstalled; if not set, the service name defaults to ndbd.

The --remove option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

--connect-retries=#

Introduced	5.1.66-ndb-7.1.25	
Command-Line Format	connect-retries=#	
	Permitted Values	
	Type numeric	
	Default	12
	Min Value	-1
	Max Value	65535

Determines the number of times that the data node attempts to contact a management server when starting. Setting this option to -1 causes the data node to keep trying to make contact indefinitely. The default is 12 attempts. The time to wait between attempts is controlled by the --connect-delay option.

This option was added in MySQL Cluster NDB 7.0.36 and MySQL Cluster 7.1.25.

--connect-delay=#

Introduced	5.1.66-ndb-7.1.25	
Command-Line Format	connect-delay=#  Permitted Values  Type numeric	
	Default	5
	Min Value	0
	Max Value	3600

Determines the time to wait between attempts to contact a management server when starting (the time between attempts is controlled by the --connect-retries option). The default is 5 attempts.

This option was added in MySQL Cluster NDB 7.0.36 and MySQL Cluster 7.1.25.

ndbd generates a set of log files which are placed in the directory specified by DataDir in the config.ini configuration file.

These log files are listed below.  $node\_id$  is the node's unique identifier. Note that  $node\_id$  represents the node's unique identifier. For example,  $ndb\_2\_error.log$  is the error log generated by the data node whose node ID is 2.

• ndb\_node\_id\_error.log is a file containing records of all crashes which the referenced ndbd process has encountered. Each record in this file contains a brief error string and a reference to a trace file for this crash. A typical entry in this file might appear as shown here:

```
Date/Time: Saturday 30 July 2004 - 00:20:01
Type of error: error
Message: Internal program error (failed ndbrequire)
Fault ID: 2341
Problem data: DbtupFixAlloc.cpp
Object of reference: DBTUP (Line: 173)
ProgramName: NDB Kernel
ProcessID: 14909
TraceFile: ndb_2_trace.log.2
***EOM***
```

Listings of possible ndbd exit codes and messages generated when a data node process shuts down prematurely can be found in ndbd Error Messages.

#### **Important**

The last entry in the error log file is not necessarily the newest one (nor is it likely to be). Entries in the error log are not listed in chronological order; rather, they correspond to the order of the trace files as determined in the ndb\_node\_id\_trace.log.next file (see below). Error log entries are thus overwritten in a cyclical and not sequential fashion.

• ndb\_node\_id\_trace.log.trace\_id is a trace file describing exactly what happened just before the error occurred. This information is useful for analysis by the MySQL Cluster development team.

It is possible to configure the number of these trace files that will be created before old files are overwritten. *trace id* is a number which is incremented for each successive trace file.

- ndb\_node\_id\_trace.log.next is the file that keeps track of the next trace file number to be assigned.
- ndb\_node\_id\_out.log is a file containing any data output by the ndbd process. This file is created only if ndbd is started as a daemon, which is the default behavior.
- ndb\_node\_id.pid is a file containing the process ID of the ndbd process when started as a daemon. It also functions as a lock file to avoid the starting of nodes with the same identifier.
- ndb\_node\_id\_signal.log is a file used only in debug versions of ndbd, where it is possible to trace all incoming, outgoing, and internal messages with their data in the ndbd process.

It is recommended not to use a directory mounted through NFS because in some environments this can cause problems whereby the lock on the .pid file remains in effect even after the process has terminated.

To start ndbd, it may also be necessary to specify the host name of the management server and the port on which it is listening. Optionally, one may also specify the node ID that the process is to use.

```
shell> ndbd --connect-string="nodeid=2;host=ndb_mgmd.mysql.com:1186"
```

See Section 5.2.3, "MySQL Cluster Connection Strings", for additional information about this issue. Section 6.1, "ndbd — The MySQL Cluster Data Node Daemon", describes other options for ndbd.

When ndbd starts, it actually initiates two processes. The first of these is called the "angel process"; its only job is to discover when the execution process has been completed, and then to restart the ndbd process if it is configured to do so. Thus, if you attempt to kill ndbd using the Unix kill command, it is necessary to kill both processes, beginning with the angel process. The preferred method of terminating an ndbd process is to use the management client and stop the process from there.

The execution process uses one thread for reading, writing, and scanning data, as well as all other activities. This thread is implemented asynchronously so that it can easily handle thousands of concurrent actions. In addition, a watch-dog thread supervises the execution thread to make sure that it does not hang in an endless loop. A pool of threads handles file I/O, with each thread able to handle one open file. Threads can also be used for transporter connections by the transporters in the ndbd process. In a multi-processor system performing a large number of operations (including updates), the ndbd process can consume up to 2 CPUs if permitted to do so.

For a machine with many CPUs it is possible to use several ndbd processes which belong to different node groups; however, such a configuration is still considered experimental and is not supported for MySQL 5.1 in a production setting. See Section 3.6, "Known Limitations of MySQL Cluster".

## 6.2 ndbinfo select all — Select From ndbinfo Tables

ndbinfo\_select\_all is a client program that selects all rows and columns from one or more tables in the ndbinfo database. It is included with the MySQL Cluster distribution beginning with MySQL Cluster NDB 7.1.17.

Not all ndbinfo tables can be accessed by this program. ndbinfo\_select\_all can access the counters, diskpagebuffer, logbuffers, logspaces, nodes, resources, threadblocks, threadstat, and transporters tables.

To select from one or more ndbinfo tables using ndbinfo\_select\_all, it is necessary to supply the names of the tables when invoking the program as shown here:

```
shell> ndbinfo_select_all table_name1 [table_name2] [...]
```

#### For example:

```
shell> ndbinfo_select_all logbuffers logspaces
== logbuffers ==
node_id log_type
                   log_id log_part
                                       total
                                             used
                                                    high
      0 0 0
                  0
                                       262144
                          33554432
                                             Ω
                         33554432
6
                                      262144 0
                  0 33554432
0 33554432
      0
           0
                                      262144 0
      0
                                      262144 0
== logspaces ==
node_id log_type
                   log_id log_part
                                       total
                                              used
                                                    high
      0
            0
                   0
                          268435456
                                       0
                                              0
                  1
                         268435456
5
      0
             0
                                       0
                                              0
5
      0
             0
                  2
                        268435456
                                      0
                                              0
5
                  3
                        268435456
      0
            0
                                       0
                                              0
                   0
6
             0
                                       0
                                              0
      0
                         268435456
6
             0
      0
                   1
                          268435456
                                       0
                                              0
                   2
                        268435456
6
      0
             0
                                       0
                                              0
                        268435456
6
      0
             0
                  3
                                       0
                                              0
      0
             0
                  0
                        268435456
                                       0
7
      Ω
             Ω
                  1
                        268435456
                                       Ω
                                              Ω
7
      0
             0
                   2
                          268435456
                                       0
                                              0
7
      0
             0
                   3
                          268435456
                                       0
                                              0
                   0
8
      0
             0
                          268435456
                                       0
                                              0
      0
             0
                   1
                          268435456
                                       0
                                              0
                   2
                          268435456
```

8 0 0 3 268435456 0 0 shell>

The following table includes options that are specific to ndbinfo\_select\_all. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndbinfo\_select\_all), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.2 This table describes command-line options for the ndbinfo\_select\_all program

Format	Description	Added or Removed
delay=#	Set the delay in seconds between loops. Default is 5.	All MySQL 5.1 based releases
loops=#, -1	Set the number of times to perform the select. Default is 1.	All MySQL 5.1 based releases
database=db_name,	Name of the database where the table located.	All MySQL 5.1 based releases
parallelism=#,	Set the degree of parallelism.	All MySQL 5.1 based releases
-p		

#### • --delay=seconds

Command-Line Format	delay=# Permitted Values	
	Туре	numeric
	Default	5
	Min Value	0
	Max Value	MAX_INT

This option sets the number of seconds to wait between executing loops. Has no effect if --loops is set to 0 or 1.

#### • --loops=number, -1 *number*

Command-Line Format	loops=#		
	-1	-1	
	Permitte	Permitted Values	
	Туре	numeric	
	Default	1	
	Min Value	0	
	Max Value	MAX_INT	

This option sets the number of times to execute the select. Use --delay to set the time between loops.

# 6.3 ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)

ndbmtd is a multi-threaded version of ndbd, the process that is used to handle all the data in tables using the NDBCLUSTER storage engine. ndbmtd is intended for use on host computers having multiple CPU cores. Except where otherwise noted, ndbmtd functions in the same way as ndbd; therefore, in this section, we concentrate on the ways in which ndbmtd differs from ndbd, and you should consult Section 6.1, "ndbd — The MySQL Cluster Data Node Daemon", for additional information about running MySQL Cluster data nodes that apply to both the single-threaded and multi-threaded versions of the data node process.

Command-line options and configuration parameters used with ndbd also apply to ndbmtd. For more information about these options and parameters, see Section 6.1, "ndbd — The MySQL Cluster Data Node Daemon", and Section 5.2.6, "Defining MySQL Cluster Data Nodes", respectively.

ndbmtd is also file system-compatible with ndbd. In other words, a data node running ndbd can be stopped, the binary replaced with ndbmtd, and then restarted without any loss of data. (However, when doing this, you must make sure that MaxNoOfExecutionThreads is set to an appriate value before restarting the node if you wish for ndbmtd to run in multi-threaded fashion.) Similarly, an ndbmtd binary can be replaced with ndbd simply by stopping the node and then starting ndbd in place of the multi-threaded binary. It is not necessary when switching between the two to start the data node binary using --initial.

Prior to MySQL Cluster NDB 7.0.6, there were known issues when using ndbmtd with MySQL Cluster Disk Data tables. If you wish to use multi-threaded data nodes with disk-based NDB tables, you should ensure that you are running MySQL Cluster NDB 7.0.6 or later (see Bug #41915 and Bug #44915)

Using ndbmtd differs from using ndbd in two key respects:

- 1. Because ndbmtd runs by default in single-threaded mode (that is, it behaves like ndbd), you must configure it to use multiple threads. This can be done by setting an appropriate value in the config.ini file for the MaxNoOfExecutionThreads configuration parameter. For more information about this parameter and its use, see Multi-Threading Configuration Parameters (ndbmtd).
- 2. Trace files are generated by critical errors in ndbmtd processes in a somewhat different fashion from how these are generated by ndbd failures. These differences are discussed in more detail in the next few paragraphs.

Like ndbd, ndbmtd generates a set of log files which are placed in the directory specified by DataDir in the config.ini configuration file. Except for trace files, these are generated in the same way and have the same names as those generated by ndbd.

In the event of a critical error, ndbmtd generates trace files describing what happened just prior to the error' occurrence. These files, which can be found in the data node's DataDir, are useful for analysis of problems by the MySQL Cluster Development and Support teams. One trace file is generated for each ndbmtd thread. The names of these files have the following pattern:

```
ndb_node_id_trace.log.trace_id_tthread_id,
```

In this pattern, <code>node\_id</code> stands for the data node's unique node ID in the cluster, <code>trace\_id</code> is a trace sequence number, and <code>thread\_id</code> is the thread ID. For example, in the event of the failure of an <code>ndbmtd</code> process running as a MySQL Cluster data node having the node ID 3 and with <code>MaxNoOfExecutionThreads</code> equal to 4, four trace files are generated in the data node's data directory. If the is the first time this node has failed, then these files are named <code>ndb\_3\_trace.log.1\_t1</code>,

ndb\_3\_trace.log.1\_t2, ndb\_3\_trace.log.1\_t3, and ndb\_3\_trace.log.1\_t4. Internally, these trace files follow the same format as ndbd trace files.

The ndbd exit codes and messages that are generated when a data node process shuts down prematurely are also used by ndbmtd. See ndbd Error Messages, for a listing of these.

#### Note

It is possible to use ndbd and ndbmtd concurrently on different data nodes in the same MySQL Cluster. However, such configurations have not been tested extensively; thus, we cannot recommend doing so in a production setting at this time.

# 6.4 ndb\_mgmd — The MySQL Cluster Management Server Daemon

The management server is the process that reads the cluster configuration file and distributes this information to all nodes in the cluster that request it. It also maintains a log of cluster activities. Management clients can connect to the management server and check the cluster's status.

The following table includes options that are specific to the MySQL Cluster management server program ndb\_mgmd. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_mgmd), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.3 This table describes command-line options for the ndb\_mgmd program

Format	Description	Added or Removed
config-file=file, -f	Specify the cluster configuration file; in NDB-6.4.0 and later, needsreload orinitial to override configuration cache if present	All MySQL 5.1 based releases
configdir=directory,config-dir=directory	Specify the cluster management server's configuration cache directory	ADDED: NDB 6.4.0
bind-address=ip_address	Local bind address	ADDED: NDB 6.2.5, NDB 6.3.2
print-full-config,	Print full configuration and exit	All MySQL 5.1 based releases
-P		
daemon,	Run ndb_mgmd in daemon mode (default)	All MySQL 5.1 based releases
-d nodaemon	Do not run ndb_mgmd as a daemon	ADDED: NDB 7.0.8
interactive	Run ndb_mgmd in interactive mode (not officially supported in production; for testing purposes only)	All MySQL 5.1 based releases
log-name=name	A name to use when writing messages applying to this node in the cluster log.	ADDED: NDB 7.0.8
no-nodeid-checks	Do not provide any node id checks	All MySQL 5.1 based releases

Format	Description	Added or Removed
mycnf	Read cluster configuration data from the my.cnf file	All MySQL 5.1 based releases
reload	Causes the management server to compare the configuration file with its configuration cache	ADDED: NDB 6.4.0
initial	Causes the management server reload its configuration data from the configuration file, bypassing the configuration cache	ADDED: NDB 6.4.0
nowait-nodes=list	Do not wait for these management nodes when starting this management server. Also requiresndb-nodeid to be used.	ADDED: NDB 7.0.10, NDB 7.1.0
config-cache[=TRUE  FALSE]	Enable the management server configuration cache; TRUE by default.	ADDED: NDB 7.0.15, NDB 7.1.4
install[=name]	Used to install the management server process as a Windows service. Does not apply on non-Windows platforms.	ADDED: NDB 7.0.16, NDB 7.1.5
remove[=name]	Used to remove a management server process that was previously installed as a Windows service, optionally specifying the name of the service to be removed. Does not apply on non-Windows platforms.	ADDED: NDB 7.0.16, NDB 7.1.5

#### • --bind-address=host[:port]

Introduced	5.1.22-no	5.1.22-ndb-6.3.2	
Command-Line Format	bind-	bind-address=ip_address	
	Permitte	Permitted Values	
	Туре	Type string	
	Default	[none]	

When specified, this option limits management server connections by management clients to clients at the specified host name or IP address (and possibly port, if this is also specified). In such cases, a management client attempting to connect to the management server from any other address fails with the error Unable to setup port: host:port!

If the *port* is not specified, the management client attempts to use port 1186.

This option was added in MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2.

### • --no-nodeid-checks

no-nodeid-checks	
Permitted Values	

Туре	boolean
Defaul	FALSE

Do not perform any checks of node IDs.

• --configdir=path

Introduced	5.1.30-nd	5.1.30-ndb-6.4.0	
Command-Line Format	confi	configdir=directory	
		from 5.1.37-ndb-7.0.8	
	config-		
	dir=dir	rectory	
	Permitte	Permitted Values	
	Туре	file name	
	Default	\$INSTALLDIR/mysql-cluster	

In MySQL Cluster NDB 7.0 and later, specifies the cluster management server's configuration cache directory. Starting with MySQL Cluster NDB 7.0.8, --config-dir is accepted as an alias for this option.

• --config-cache

Introduced	5.1.44-ndb-7.1.4	
Command-Line Format	config-cache[=TRUE FALSE]	
	Permitted Values	
	Type boolean	
	Default	TRUE

This option, whose default value is 1 (or TRUE, or ON), can be used to disable the management server's configuration cache, so that it reads its configuration from config.ini every time it starts (see Section 5.2, "MySQL Cluster Configuration Files"). You can do this by starting the ndb\_mgmd process with any one of the following options:

- --config-cache=0
- --config-cache=FALSE
- --config-cache=OFF
- --skip-config-cache

Using one of the options just listed is effective only if the management server has no stored configuration at the time it is started. If the management server finds any configuration cache files, then the --config-cache option or the --skip-config-cache option is ignored. Therefore, to disable configuration caching, the option should be used the *first* time that the management server is started. Otherwise—that is, if you wish to disable configuration caching for a management server that has already created a configuration cache—you must stop the management server, delete any existing configuration cache files manually, then restart the management server with --skip-config-cache (or with --config-cache set equal to 0, OFF, or FALSE).

Configuration cache files are normally created in a directory named mysql-cluster under the installation directory (unless this location has been overridden using the --configdir option). Each time the management server updates its configuration data, it writes a new cache file. The files are named sequentially in order of creation using the following format:

```
ndb_node-id_config.bin.seq-number
```

node-id is the management server's node ID; seq-number is a sequence number, beginning with 1. For example, if the management server's node ID is 5, then the first three configuration cache files would, when they are created, be named ndb\_5\_config.bin.1, ndb\_5\_config.bin.2, and ndb\_5\_config.bin.3.

If your intent is to purge or reload the configuration cache without actually disabling caching, you should start ndb\_mgmd with one of the options --reload or --initial instead of --skip-config-cache.

To re-enable the configuration cache, simply restart the management server, but without the --config-cache or --skip-config-cache option that was used previously to disable the configuration cache.

This option was added in MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4.

Beginning with MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, ndb\_mgmd no longer checks for the configuration directory (--configdir) or attempts to create one when --skip-config-cache is used. (Bug #13428853)

--config-file=filename, -f filename

Command-Line Format	config-file=file		
	-f	-f	
	Permitte	Permitted Values	
	Туре	Type file name	
	Default	./config.ini	
	Permitted Values		
	Туре	file name	
	Default	[none]	

Instructs the management server as to which file it should use for its configuration file. By default, the management server looks for a file named config.ini in the same directory as the ndb\_mgmd executable; otherwise the file name and location must be specified explicitly.

Beginning with MySQL Cluster NDB 6.4.0, this option has no default value, and is ignored unless the management server is forced to read the configuration file, either because ndb\_mgmd was started with the --reload or --initial option, or because the management server could not find any configuration cache. Beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this option is also read if ndb\_mgmd was started with --config-cache=OFF. See Section 5.2, "MySQL Cluster Configuration Files", for more information.

Formerly, using this option together with --initial caused removal of the configuration cache even if the file was not found. This issue was resolved in MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.27. (Bug #1299289)

--mycnf

Command-Line Format	mycnf	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Read configuration data from the my.cnf file.

#### • --daemon, -d

Command-Line Format	daemon		
	-d	-d	
	Permitted Values		
	Type boolean		
	Default	TRUE	

Instructs ndb\_mgmd to start as a daemon process. This is the default behavior.

This option has no effect when running ndb\_mgmd on Windows platforms.

#### • --interactive

Command-Line Format	interactive	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Starts ndb\_mgmd in interactive mode; that is, an ndb\_mgm client session is started as soon as the management server is running. This option does not start any other MySQL Cluster nodes.

#### • --initial

Introduced	5.1.30-ndb-6.4.0		
Command-Line Format	initial		
	Permitted Values		
	Туре	Type boolean	
	Default	FALSE	

Beginning with MySQL Cluster NDB 6.4.0, configuration data is cached internally rather than being read from the cluster global configuration file each time the management server is started (see Section 5.2, "MySQL Cluster Configuration Files"). Using this option overrides this behavior, by forcing the management server to delete any existing cache files, and then to re-read the configuration data from the cluster configuration file and to build a new cache.

This differs in two ways from the --reload option. First, --reload forces the server to check the configuration file against the cache and reload its data only if the contents of the file are different from the cache. Second, --reload does not delete any existing cache files.

If ndb\_mgmd is invoked with --initial but cannot find a global configuration file, the management server cannot start.

In MySQL Cluster NDB 7.0.8 and later, when starting, the management server checks for another management server in the same MySQL Cluster and tries to use its configuration data. In other words, ndb\_mgmd ignores --initial unless it is the only management server running. This behavior has implications when performing a rolling restart of a MySQL Cluster with multiple management nodes. See Section 7.5, "Performing a Rolling Restart of a MySQL Cluster", for more information.

Formerly, using this option together with the --config-file option caused removal of the configuration cache even if the file was not found. Starting with MySQL Cluster NDB 7.0.38 and MySQL Cluster NDB 7.1.27, the cache is cleared in such cases only if the configuration file is actually found. (Bug #1299289)

This option was introduced in MySQL Cluster NDB 6.4.0.

#### • --log-name=*name*

Introduced	5.1.37-ndb-7.0.8		
Command-Line Format	log-name=name		
	Permitte	Permitted Values	
	Туре	Type string	
	Default	MgmtSrvr	

Provides a name to be used for this node in the cluster log.

This option was added in MySQL Cluster NDB 7.0.8.

#### • --nodaemon

Introduced	5.1.37-ndb-7.0.8	
Command-Line Format	nodaemon	
	Permitted Values	
	Type boolean	
	Default	FALSE

Instructs ndb\_mgmd not to start as a daemon process.

As of MySQL Cluster NDB 7.0.8, the default behavior for ndb\_mgmd on Windows is to run in the foreground, making this option unnecessary on Windows platforms. (Bug #45588)

#### --print-full-config, -P

Command-Line Format	print-full-config	
	-P	
	Permitted Values  Type boolean	
	Default	FALSE

Shows extended information regarding the configuration of the cluster. With this option on the command line the ndb\_mgmd process prints information about the cluster setup including an extensive list of the cluster configuration sections as well as parameters and their values. Normally used together with the --config-file (-f) option.

#### • --reload

Introduced	5.1.30-ndb-6.4.0		
Command-Line Format	reload		
	Permitte	Permitted Values	
	Туре	Type boolean	
	Default	FALSE	

Beginning with MySQL Cluster NDB 6.4.0, configuration data is stored internally rather than being read from the cluster global configuration file each time the management server is started (see Section 5.2, "MySQL Cluster Configuration Files"). Using this option forces the management server to check its internal data store against the cluster configuration file and to reload the configuration if it finds that the configuration file does not match the cache. Existing configuration cache files are preserved, but not used.

This differs in two ways from the --initial option. First, --initial causes all cache files to be deleted. Second, --initial forces the management server to re-read the global configuration file and construct a new cache.

If the management server cannot find a global configuration file, then the --reload option is ignored.

In MySQL Cluster NDB 7.0.8 and later, when starting, the management server checks for another management server in the same MySQL Cluster and tries to use its configuration data. In other words, ndb\_mgmd ignores --reload unless it is the only management server running. This behavior has implications when performing a rolling restart of a MySQL Cluster with multiple management nodes. See Section 7.5, "Performing a Rolling Restart of a MySQL Cluster", for more information.

This option was introduced in MySQL Cluster NDB 6.4.0.

#### • --nowait-nodes

Introduced	5.1.39-no	5.1.39-ndb-7.1.0	
Command-Line Format	nowai	nowait-nodes=list	
	Permitte	Permitted Values	
	Туре	Type numeric	
	Default		
	Min Value	1	
	Max Value	255	

When starting a MySQL Cluster is configured with two management nodes and running MySQL Cluster NDB 7.0 and later, each management server normally checks to see whether the other ndb\_mgmd is also operational and whether the other management server's configuration is identical to its own. However, it is sometimes desirable to start the cluster with only one management node (and perhaps to allow the other ndb\_mgmd to be started later). This option causes the management node to bypass any checks for any other management nodes whose node IDs are passed to this option, permitting the cluster to start as though configured to use only the management node that was started.

For purposes of illustration, consider the following portion of a config.ini file (where we have omitted most of the configuration parameters that are approximately transfer to this example):

```
[ndbd]
NodeId = 1
HostName = 192.168.0.101
[ndbd]
NodeId = 2
HostName = 192.168.0.102
[ndbd]
NodeId = 3
HostName = 192.168.0.103
[ndbd]
NodeId = 4
HostName = 192.168.0.104
[ndb mqmd]
NodeId = 10
HostName = 192.168.0.150
[ndb_mgmd]
NodeId = 11
HostName = 192.168.0.151
[api]
NodeId = 20
HostName = 192.168.0.200
[api]
NodeId = 21
HostName = 192.168.0.201
```

Assume that you wish to start this cluster using only the management server having node ID 10 and running on the host having the IP address 192.168.0.150. (Suppose, for example, that the host computer on which you intend to the other management server is temporarily unavailable due to a hardware failure, and you are waiting for it to be repaired.) To start the cluster in this way, use a command line on the machine at 192.168.0.150 to enter the following command:

```
shell> ndb_mgmd --ndb-nodeid=10 --nowait-nodes=11
```

As shown in the preceding example, when using --nowait-nodes, you must also use the --ndb-nodeid option to specify the node ID of this ndb\_mgmd process.

You can then start each of the cluster's data nodes in the usual way. If you wish to start and use the second management server in addition to the first management server at a later time without restarting the data nodes, you must start each data node with a connection string that references both management servers, like this:

```
shell> ndbd -c 192.168.0.150,192.168.0.151
```

The same is true with regard to the connection string used with any mysqld processes that you wish to start as MySQL Cluster SQL nodes connected to this cluster. See Section 5.2.3, "MySQL Cluster Connection Strings", for more information.

When used with ndb\_mgmd, this option affects the behavior of the management node with regard to other management nodes only. Do not confuse it with the --nowait-nodes option used with ndbd (or ndbmtd in MySQL Cluster NDB 7.0 and later) to permit a cluster to start with fewer than its full complement of data nodes; when used with data nodes, this option affects their behavior only with regard to other data nodes.

Multiple management node IDs may be passed to this option as a comma-separated list. Each node ID must be no less than 1 and no greater than 255. In practice, it is quite rare to use more than two management servers for the same MySQL Cluster (or to have any need for doing so); in most cases you

need to pass to this option only the single node ID for the one management server that you do not wish to use when starting the cluster.

#### Note

When you later start the "missing" management server, its configuration must match that of the management server that is already in use by the cluster. Otherwise, it fails the configuration check performed by the existing management server, and does not start.

This option was introduced in MySQL Cluster NDB 7.0.10 and MySQL Cluster NDB 7.1.0.

It is not strictly necessary to specify a connection string when starting the management server. However, if you are using more than one management server, a connection string should be provided and each node in the cluster should specify its node ID explicitly.

See Section 5.2.3, "MySQL Cluster Connection Strings", for information about using connection strings. Section 6.4, "ndb\_mgmd — The MySQL Cluster Management Server Daemon", describes other options for ndb\_mgmd.

The following files are created or used by ndb\_mgmd in its starting directory, and are placed in the DataDir as specified in the config.ini configuration file. In the list that follows, node\_id is the unique node identifier.

- config.ini is the configuration file for the cluster as a whole. This file is created by the user and read by the management server. Chapter 5, Configuration of MySQL Cluster NDB 6.1-7.1, discusses how to set up this file.
- ndb\_node\_id\_cluster.log is the cluster events log file. Examples of such events include checkpoint startup and completion, node startup events, node failures, and levels of memory usage. A complete listing of cluster events with descriptions may be found in Chapter 7, Management of MySQL Cluster.

When the size of the cluster log reaches one million bytes, the file is renamed to ndb\_node\_id\_cluster.log.seq\_id, where seq\_id is the sequence number of the cluster log file. (For example: If files with the sequence numbers 1, 2, and 3 already exist, the next log file is named using the number 4.)

- ndb\_node\_id\_out.log is the file used for stdout and stderr when running the management server
  as a daemon.
- ndb node id.pid is the process ID file used when running the management server as a daemon.
- --install[=name]

Introduced	5.1.47-ndb-7.1.5	
Command-Line Format	install[=name]	
	Permitted Values	
	Туре	string
	Default	ndb_mgmd

Causes ndb\_mgmd to be installed as a Windows service. Optionally, you can specify a name for the service; if not set, the service name defaults to ndb\_mgmd. Although it is preferable to specify other ndb\_mgmd program options in a my.ini or my.cnf configuration file, it is possible to use them together with --install. However, in such cases, the --install option must be specified first, before any other options are given, for the Windows service installation to succeed.

It is generally not advisable to use this option together with the <code>--initial</code> option, since this causes the configuration cache to be wiped and rebuilt every time the service is stopped and started. Care should also be taken if you intend to use any other <code>ndb\_mgmd</code> options that affect the starting of the management server, and you should make absolutely certain you fully understand and allow for any possible consequences of doing so.

The --install option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

• --remove[=name]

Introduced	5.1.47-ndb-7.1.5		
Command-Line Format	remove[=name]		
	Permitte	Permitted Values	
	Туре	Type string	
	Default	ndb_mgmd	

Causes an ndb\_mgmd process that was previously installed as a Windows service to be removed. Optionally, you can specify a name for the service to be uninstalled; if not set, the service name defaults to ndb\_mgmd.

The --remove option has no effect on non-Windows platforms.

This option became available in MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5.

## 6.5 ndb\_mgm — The MySQL Cluster Management Client

The ndb\_mgm management client process is actually not needed to run the cluster. Its value lies in providing a set of commands for checking the cluster's status, starting backups, and performing other administrative functions. The management client accesses the management server using a C API. Advanced users can also employ this API for programming dedicated management processes to perform tasks similar to those performed by ndb\_mgm.

To start the management client, it is necessary to supply the host name and port number of the management server:

```
shell> ndb_mgm [host_name [port_num]]
```

For example:

```
shell> ndb_mgm ndb_mgmd.mysql.com 1186
```

The default host name and port number are localhost and 1186, respectively.

The following table includes options that are specific to the MySQL Cluster management client program ndb\_mgm. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_mgm), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.4 This table describes command-line options for the ndb\_mgm program

Format	Description	Added or Removed
try-reconnect=#,	Specify number of tries for connecting to ndb_mgmd (0 = infinite)	All MySQL 5.1 based releases
execute=name, -e	Execute command and exit	All MySQL 5.1 based releases

• --execute=command, -e command

Command-Line Format	execute=name	
	-е	

This option can be used to send a command to the MySQL Cluster management client from the system shell. For example, either of the following is equivalent to executing SHOW in the management client:

```
shell> ndb_mgm -e "SHOW"
shell> ndb_mgm --execute="SHOW"
```

This is analogous to how the --execute or -e option works with the mysql command-line client. See Using Options on the Command Line.

#### Note

If the management client command to be passed using this option contains any space characters, then the command *must* be enclosed in quotation marks. Either single or double quotation marks may be used. If the management client command contains no space characters, the quotation marks are optional.

• --try-reconnect=number

Command-Line Format	try-reconnect=#		
	-t	-t	
	Permitte	Permitted Values	
	Туре	boolean	
	Default	TRUE	

If the connection to the management server is broken, the node tries to reconnect to it every 5 seconds until it succeeds. By using this option, it is possible to limit the number of attempts to *number* before giving up and reporting an error instead.

Additional information about using ndb\_mgm can be found in Section 7.2, "Commands in the MySQL Cluster Management Client".

# 6.6 ndb\_blob\_tool — Check and Repair BLOB and TEXT columns of MySQL Cluster Tables

This tool, which is available in MySQL Cluster NDB 7.0.4 and later, can be used to check for and remove orphaned BLOB column parts from NDB tables, as well as to generate a file listing any orphaned parts. It is

sometimes useful in diagnosing and repairing corrupted or damaged NDB tables containing BLOB or TEXT columns.

The basic syntax for ndb\_blob\_tool is shown here:

```
ndb_blob_tool [options] table [column, ...]
```

Unless you use the <code>--help</code> option, you must specify an action to be performed by including one or more of the options <code>--check-orphans</code>, <code>--delete-orphans</code>, or <code>--dump-file</code>. These options cause <code>ndb\_blob\_tool</code> to check for orphaned BLOB parts, remove any orphaned BLOB parts, and generate a dump file listing orphaned BLOB parts, respectively, and are described in more detail later in this section.

You must also specify the name of a table when invoking ndb\_blob\_tool. In addition, you can optionally follow the table name with the (comma-separated) names of one or more BLOB or TEXT columns from that table. If no columns are listed, the tool works on all of the table's BLOB and TEXT columns. If you need to specify a database, use the --database (-d) option.

The --verbose option provides additional information in the output about the tool's progress.

The following table includes options that are specific to ndb\_blob\_tool. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_blob\_tool), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.5 This table describes command-line options for the ndb\_blob\_tool program

Format	Description	Added or Removed
check-orphans	Check for orphan blob parts	ADDED: NDB 7.0.4
database=db_name,	Database to find the table in.	ADDED: NDB 7.0.4
-d		
delete-orphans	Delete orphan blob parts	ADDED: NDB 7.0.4
dump-file=file	Write orphan keys to specified file	ADDED: NDB 7.0.4
verbose,	Verbose output	ADDED: NDB 7.0.4
-v		

• --check-orphans

Introduced	5.1.32-ndb-7.0.4		
Command-Line Format	check-orphans		
	Permitted Values		
	Туре	Type boolean	
	Default	FALSE	

Check for orphaned BLOB parts in MySQL Cluster tables.

• --database=db\_name, -d

Introduced	5.1.32-ndb-7.0.4	
------------	------------------	--

Command-Line Format	database=db_name		
	-d	-d	
	Permitte	Permitted Values	
	Туре	string	
	Default	[none]	

Specify the database to find the table in.

• --delete-orphans

Introduced	5.1.32-ndb-7.0.4	
Command-Line Format	delete-orphans	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Remove orphaned BLOB parts from MySQL Cluster tables.

• --dump-file=file

Introduced	5.1.32-ndb-7.0.4		
Command-Line Format	dump-file=file		
	Permitte	Permitted Values	
	Туре	Type file name	
	Default	[none]	

Writes a list of orphaned BLOB column parts to *file*. The information written to the file includes the table key and BLOB part number for each orphaned BLOB part.

• --verbose

Introduced	5.1.32-ndb-7.0.4	
Command-Line Format	verbose	
	-v	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Provide extra information in the tool's output regarding its progress.

## **Example**

First we create an NDB table in the test database, using the CREATE TABLE statement shown here:

```
USE test;
CREATE TABLE btest (
    c0 BIGINT UNSIGNED NOT NULL AUTO_INCREMENT PRIMARY KEY,
    c1 TEXT,
```

```
c2 BLOB
) ENGINE=NDB;
```

Then we insert a few rows into this table, using a series of statements similar to this one:

```
INSERT INTO btest VALUES (NULL, 'x', REPEAT('x', 1000));
```

When run with --check-orphans against this table, ndb blob tool generates the following output:

```
shell> ndb_blob_tool --check-orphans --verbose -d test btest
connected
processing 2 blobs
processing blob #0 c1 NDB$BLOB_19_1
NDB$BLOB_19_1: nextResult: res=1
total parts: 0
orphan parts: 0
processing blob #1 c2 NDB$BLOB_19_2
NDB$BLOB_19_2: nextResult: res=0
NDB$BLOB_19_2: nextResult: res=0
NDB$BLOB 19 2: nextResult: res=0
NDB$BLOB_19_2: nextResult: res=1
total parts: 10
orphan parts: 0
disconnected
NDBT_ProgramExit: 0 - OK
```

The tool reports that there are no NDB BLOB column parts associated with column c1, even though c1 is a TEXT column. This is due to the fact that, in an NDB table, only the first 256 bytes of a BLOB or TEXT column value are stored inline, and only the excess, if any, is stored separately; thus, if there are no values using more than 256 bytes in a given column of one of these types, no BLOB column parts are created by NDB for this column. See Data Type Storage Requirements, for more information.

# 6.7 ndb\_config — Extract MySQL Cluster Configuration Information

This tool extracts current configuration information for data nodes, SQL nodes, and API nodes from one of a number of sources: a MySQL Cluster management node, or its <code>config.ini</code> or <code>my.cnf</code> file. By default, the management node is the source for the configuration data; to override the default, execute ndb\_config with the <code>--config-file</code> or <code>--mycnf</code> option. Beginning with MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, it is also possible to use a data node as the source by specifying its node ID using <code>--config\_from\_node=node\_id</code>.

Beginning with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, ndb\_config can also provide an offline dump of all configuration parameters which can be used, along with their default, maximum, and minimum values and other information. The dump can be produced in either text or XML format; for more information, see the discussion of the --configinfo and --xml [309] options later in this section).

Beginning with MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, you can filter the results by section (DB, SYSTEM, or CONNECTIONS) using one of the options --nodes, --system, or --connections.

The following table includes options that are specific to ndb\_config. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_config), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.6 This table describes command-line options for the ndb\_config program

Format	Description	Added or Removed
nodes	Print node information (DB section) only.	All MySQL 5.1 based releases
connections	Print CONNECTIONS section information only. Cannot be used withnodes orsystem option.	All MySQL 5.1 based releases
query=string,	One or more query options (attributes)	All MySQL 5.1 based releases
-d		
host=name	Specify host	All MySQL 5.1 based releases
type=name	Specify node type	All MySQL 5.1 based releases
nodeid [307],	Get configuration of node with this ID	All MySQL 5.1 based releases
id [307]		
fields=string,	Field separator	All MySQL 5.1 based releases
-f		
rows=string,	Row separator	All MySQL 5.1 based releases
-r		
config-file=path	Set the path to config.ini file	All MySQL 5.1 based releases
mycnf	Read configuration data from my.cnf file	All MySQL 5.1 based releases
-c	Short form forndb-connectstring	ADDED: 5.1.12
configinfo	Dumps information about all NDB configuration parameters in text format with default, maximum, and minimum values. Use withxml to obtain XML output.	ADDED: NDB 6.3.25, NDB 7.0.6
configinfoxml [309]	Usexml withconfiginfo to obtain a dump of all NDB configuration parameters in XML format with default, maximum, and minimum values.	ADDED: NDB 6.3.25, NDB 7.0.6
system	Print SYSTEM section information only. Cannot be used withnodes orconnections option.	ADDED: NDB 7.0.27, NDB 7.1.16
config_from_node=#	Obtain configuration data from the node having this ID (must be a data node).	ADDED: NDB 7.0.27, NDB 7.1.16

• --usage, --help, **or** -?

Command-Line Format	help

usage
-?

Causes ndb\_config to print a list of available options, and then exit.

• --config\_from\_node=#

Introduced	5.1.56-ndb-7.1.16		
Command-Line Format	conf	config_from_node=#	
	Permitte	Permitted Values	
	Type numeric		
	Default	none	
	Min Value	1	
	Max Value	48	

Obtain the cluster's configuration data from the data node that has this ID.

If the node having this ID is not a data node, ndb\_config fails with an error. (To obtain configuration data from the management node instead, simply omit this option.)

--config\_from\_node was added in MySQL Cluster NDB 7.0.27 and MySQL NDB 7.1.16.

• --version, -V

Command-Line Format	version		
	-V		

Causes ndb\_config to print a version information string, and then exit.

• --ndb-connectstring=connect\_string

Command-Line Format	ndb-c	ndb-connectstring=connectstring	
	conne	connect-string=connectstring	
	-c		
	Permitte	Permitted Values Type string	
	Туре		
	Default	localhost:1186	

Specifies the connection string to use in connecting to the management server. The format for the connection string is the same as described in Section 5.2.3, "MySQL Cluster Connection Strings", and defaults to localhost:1186.

The use of -c as a short version for this option is supported for ndb\_config beginning with MySQL 5.1.12.

• --config-file=path-to-file

<b>Command-Line Format</b>	config-file=path

Permitted Values	
Туре	file name
Default	

Gives the path to the management server's configuration file (config.ini). This may be a relative or absolute path. If the management node resides on a different host from the one on which ndb\_config is invoked, then an absolute path must be used.

• --mycnf

Command-Line Format	mycnf	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Read configuration data from the my.cnf file.

• --query=query-options, -q query-options

Command-Line Format	query=string		
	-q		
	Permitted Values  Type string		
	Default		

This is a comma-delimited list of *query options*—that is, a list of one or more node attributes to be returned. These include id (node ID), type (node type—that is, ndbd, mysqld, or ndb\_mgmd), and any configuration parameters whose values are to be obtained.

For example, --query=id, type, indexmemory, datamemory returns the node ID, node type, DataMemory, and IndexMemory for each node.

#### Note

If a given parameter is not applicable to a certain type of node, than an empty string is returned for the corresponding value. See the examples later in this section for more information.

• --host=hostname

Command-Line Format	host=name		
	Permitted Values		
	Туре	string	
	Default		

Specifies the host name of the node for which configuration information is to be obtained.

#### Note

While the hostname localhost usually resolves to the IP address 127.0.0.1, this may not necessarily be true for all operating platforms and configurations.

This means that it is possible, when localhost is used in config.ini, for ndb\_config --host=localhost to fail if ndb\_config is run on a different host where localhost resolves to a different address (for example, on some versions of SUSE Linux, this is 127.0.0.2). In general, for best results, you should use numeric IP addresses for all MySQL Cluster configuration values relating to hosts, or verify that all MySQL Cluster hosts handle localhost in the same fashion.

- --id=node\_id
  - --nodeid=node id

Command-Line Format	ndb-nodeid=#	
	Permitted Values Type numeric	
	Default	0

Either of these options can be used to specify the node ID of the node for which configuration information is to be obtained. --nodeid is the preferred form.

#### --nodes

Command-Line Format	nodes	nodes	
	Permitted Values		
	Туре	boolean	
	Default	FALSE	

Tells ndb\_config to print information from parameters defined in DB sections only. Prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, this option had no affect. This option cannot be used together with --connections or --system.

#### • --connections

Command-Line Format	connections	
	Permitted Values  Type boolean	
	Default	FALSE

Tells  $ndb\_config$  to print CONNECTIONS information only. This option existed prior to MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16, but had no affect before then. This option cannot be used together with --nodes or --system.

### • --system

Introduced	5.1.56-ndb-7.1.16	
Command-Line Format	system	
	Permitted Values	
	Туре	boolean
	Default	FALS207

Tells ndb\_config to print SYSTEM information only.

This option was introduced in MySQL Cluster NDB 7.0.27 and MySQL Cluster NDB 7.1.16. It cannot be used together with the --nodes or --system options.

• --type=node\_type

Command-Line Format	type=name	
	Permitte	ed Values
	Туре	enumeration
,	Default	[none]
	Valid	ndbd
	Values	mysqld
		ndb_mgmd

Filters results so that only configuration values applying to nodes of the specified *node\_type* (ndbd, mysqld, or ndb\_mgmd) are returned.

• --fields=delimiter, -f delimiter

Command-Line Format	fields=string	
	-f	
	Permitted Values	
	Туре	string
	Default	

Specifies a *delimiter* string used to separate the fields in the result. The default is "," (the comma character).

#### Note

If the delimiter contains spaces or escapes (such as  $\n$  for the linefeed character), then it must be quoted.

• --rows=separator, -r separator

Command-Line Format	rows=string		
	-r		
	Permitted Values		
	Туре	string	
	Default		

Specifies a *separator* string used to separate the rows in the result. The default is a space character.

#### Note

If the separator contains spaces or escapes (such as n for the linefeed character), then it must be quoted.

#### • --configinfo

The --configinfo option, added in MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6, causes ndb\_config to dump a list of each MySQL Cluster configuration parameter supported by the MySQL Cluster distribution of which ndb\_config is a part, including the following information:

- A brief description of each parameter's purpose, effects, and usage
- The section of the config.ini file where the parameter may be used
- The parameter's data type or unit of measurement
- · Where applicable, the parameter's default, minimum, and maximum values
- · A brief description of the parameter's purpose, effects, and usage
- MySQL Cluster release version and build information

By default, this output is in text format. Part of this output is shown here:

```
shell> ndb_config --configinfo
***** SYSTEM *****
Name (String)
Name of system (NDB Cluster)
MANDATORY
PrimaryMGMNode (Non-negative Integer)
Node id of Primary ndb_mgmd(MGM) node
Default: 0 (Min: 0, Max: 4294967039)
ConfigGenerationNumber (Non-negative Integer)
Configuration generation number
Default: 0 (Min: 0, Max: 4294967039)
***** DB *****
MaxNoOfSubscriptions (Non-negative Integer)
Max no of subscriptions (default 0 == MaxNoOfTables)
Default: 0 (Min: 0, Max: 4294967039)
MaxNoOfSubscribers (Non-negative Integer)
Max no of subscribers (default 0 == 2 * MaxNoOfTables)
Default: 0 (Min: 0, Max: 4294967039)
```

#### --configinfo --xml

Introduced	5.1.34-ndb-7.0.6	
Command-Line Format	configinfoxml	
	Permitted Values	
	Туре	boolean
	Default	false

You can obtain the output of ndb\_config --configinfo as XML by adding the --xml option (like the --configinfo option, available beginning with MySQL Cluster NDB 6.3.25 and MySQL Cluster NDB 7.0.6). A portion of the resulting output is shown in this example:

```
<param name="Name" comment="Name of system (NDB Cluster)" type="string"</pre>
             mandatory="true"/>
    <param name="PrimaryMGMNode" comment="Node id of Primary ndb_mgmd(MGM) node"</pre>
             type="unsigned" default="0" min="0" max="4294967039"/>
    <param name="ConfigGenerationNumber" comment="Configuration generation number"</pre>
             type="unsigned" default="0" min="0" max="4294967039"/>
  </section>
  <section name="NDBD">
    <param name="MaxNoOfSubscriptions"</pre>
              comment="Max no of subscriptions (default 0 == MaxNoOfTables)"
              type="unsigned" default="0" min="0" max="4294967039"/>
    <param name="MaxNoOfSubscribers"</pre>
             comment="Max no of subscribers (default 0 == 2 * MaxNoOfTables)"
              type="unsigned" default="0" min="0" max="4294967039"/>
  </section>
</configuariables>
```

#### Note

Normally, the XML output produced by ndb\_config --configinfo --xml is formatted using one line per element; we have added extra whitespace in the previous example, as well as the next one, for reasons of legibility. This should not make any difference to applications using this output, since most XML processors either ignore nonessential whitespace as a matter of course, or can be instructed to do so.

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, the XML output also indicates when changing a given parameter requires that data nodes be restarted using the <code>--initial</code> option. This is shown by the presence of an <code>initial="true"</code> attribute in the corresponding <code><param></code> element. In addition (also beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10), the restart type (<code>system</code> or node) is also shown; if a given parameter requires a system restart, this is indicated by the presence of a <code>restart="system"</code> attribute in the corresponding <code><param></code> element. For example, changing the value set for the <code>Diskless</code> parameter requires a system initial restart, as shown here (with the <code>restart</code> and <code>initial</code> attributes highlighted for visibility):

```
<param name="Diskless" comment="Run wo/ disk" type="bool" default="false"
    restart="system" initial="true"/>
```

#### **Important**

The --xml option can be used only with the --configinfo option. Using --xml without --configinfo fails with an error.

Unlike the options used with this program to obtain current configuration data, --configinfo and --xml use information obtained from the MySQL Cluster sources when ndb\_config was compiled. For this reason, no connection to a running MySQL Cluster or access to a config.ini or my.cnf file is required for these two options.

Combining other ndb\_config options (such as --query or --type) with --configinfo or --xml is not supported. Currently, if you attempt to do so, the usual result is that all other options besides --configinfo or --xml are simply ignored. However, this behavior is not guaranteed and is subject to change at any time. In addition, since ndb\_config, when used with the --configinfo option, does not access the MySQL Cluster or read any files, trying to specify additional options such as --ndb-connectstring or --config-file with --configinfo serves no purpose.

## **Examples**

1. To obtain the node ID and type of each node in the cluster:

```
shell> ./ndb_config --query=id,type --fields=':' --rows='\n'
1:ndbd
2:ndbd
3:ndbd
4:ndbd
5:ndb_mgmd
6:mysqld
7:mysqld
8:mysqld
9:mysqld
```

In this example, we used the --fields options to separate the ID and type of each node with a colon character (:), and the --rows options to place the values for each node on a new line in the output.

2. To produce a connection string that can be used by data, SQL, and API nodes to connect to the management server:

```
shell> ./ndb_config --config-file=usr/local/mysql/cluster-data/config.ini \
--query=hostname,portnumber --fields=: --rows=, --type=ndb_mgmd
192.168.0.179:1186
```

3. This invocation of ndb\_config checks only data nodes (using the --type option), and shows the values for each node's ID and host name, as well as the values set for its DataMemory, IndexMemory, and DataDir parameters:

```
shell> ./ndb_config --type=ndbd --query=id,host,datamemory,indexmemory,datadir -f ': '-r '\n'
1 : 192.168.0.193 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
2 : 192.168.0.112 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
3 : 192.168.0.176 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
4 : 192.168.0.119 : 83886080 : 18874368 : /usr/local/mysql/cluster-data
```

In this example, we used the short options -f and -r for setting the field delimiter and row separator, respectively.

4. To exclude results from any host except one in particular, use the --host option:

```
shell> ./ndb_config --host=192.168.0.176 -f : -r '\n' -q id,type
3:ndbd
5:ndb_mgmd
```

In this example, we also used the short form -q to determine the attributes to be queried.

Similarly, you can limit results to a node with a specific ID using the --id or --nodeid [307] option.

## 6.8 ndb\_cpcd — Automate Testing for NDB Development

This utility is found in the libexec directory. It is part of an internal automated test framework used in testing and debugging MySQL Cluster. Because it can control processes on remote systems, it is not advisable to use ndb\_cpcd in a production cluster.

The source files for ndb\_cpcd may be found in the directory storage/ndb/src/cw/cpcd, in the MySQL Cluster source tree.

**Deprecated feature.** As of MySQL Cluster NDB 7.0, this program is deprecated and no longer actively maintained. It is subject to removal in a future MySQL Cluster version.

## 6.9 ndb\_delete\_all — Delete All Rows from an NDB Table

ndb\_delete\_all deletes all rows from the given NDB table. In some cases, this can be much faster than DELETE or even TRUNCATE TABLE.

### **Usage**

```
ndb_delete_all -c connect_string tbl_name -d db_name
```

This deletes all rows from the table named *tb1\_name* in the database named *db\_name*. It is exactly equivalent to executing TRUNCATE *db\_name* in MySQL.

The following table includes options that are specific to ndb\_delete\_all. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_delete\_all), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.7 This table describes command-line options for the ndb\_delete\_all program

Format	Description	Added or Removed
database=dbname,	Name of the database in which the table is found	All MySQL 5.1 based releases
-d		
transactional,	Perform the delete in a single transaction (may run out of	All MySQL 5.1 based releases
-t	operations)	
tupscan	Run tup scan	All MySQL 5.1 based releases
diskscan	Run disk scan	All MySQL 5.1 based releases

• --transactional, -t

Use of this option causes the delete operation to be performed as a single transaction.

#### Warning

With very large tables, using this option may cause the number of operations available to the cluster to be exceeded.

## 6.10 ndb\_desc — Describe NDB Tables

ndb\_desc provides a detailed description of one or more NDB tables.

## **Usage**

```
ndb_desc -c connect_string tbl_name -d db_name [-p]
```

(MySQL Cluster NDB 7.0.36 and later; MySQL Cluster NDB 7.1.25 and later:)

```
ndb_desc -c connect_string index_name -d db_name -t tbl_name
```

## **Sample Output**

MySQL table creation and population statements:

```
USE test;
CREATE TABLE fish (
   id INT(11) NOT NULL AUTO_INCREMENT,
   name VARCHAR(20) NOT NULL,
   length_mm INT(11) NOT NULL,
   weight_gm INT(11) NOT NULL,
   PRIMARY KEY pk (id),
   UNIQUE KEY uk (name)
) ENGINE=NDB;
INSERT INTO fish VALUES
  ('','guppy', 35, 2), ('','tuna', 2500, 150000),
   ('','shark', 3000, 110000), ('','manta ray', 1500, 50000),
   ('','grouper', 900, 125000), ('','puffer', 250, 2500);
```

#### Output from ndb\_desc:

```
shell> ./ndb_desc -c localhost fish -d test -p
-- fish --
Version: 2
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 4
Number of primary keys: 1
Length of frm data: 311
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 2
TableStatus: Retrieved
-- Attributes --
id Int PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
name Varchar(20; latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
length_mm Int NOT NULL AT=FIXED ST=MEMORY
weight_gm Int NOT NULL AT=FIXED ST=MEMORY
-- Indexes --
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
uk$unique(name) - UniqueHashIndex
uk(name) - OrderedIndex
-- Per partition info --
Partition Row count Commit count Frag fixed memory ...
  2 2 32768
4 4 32768
0
1
... Frag varsized memory Extent_space Free extent_space
... 32768
                         0
... 32768
                         0
                                       0
NDBT_ProgramExit: 0 - OK
```

Information about multiple tables can be obtained in a single invocation of ndb\_desc by using their names, separated by spaces. All of the tables must be in the same database.

Beginning with MySQL Cluster NDB 7.0.36 and MySQL Cluster NDB 7.1.25, it is possible to obtain additional information about a specific index using the --table (short form: -t) option introduced in these versions and supplying the name of the index as the first argument to ndb\_desc, as shown here:

```
shell> ./ndb_desc uk -d test -t fish
-- 11k --
Version: 3
Base table: fish
Number of attributes: 1
Logging: 0
Index type: OrderedIndex
Index status: Retrieved
-- Attributes -
name Varchar(20; latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
-- IndexTable 10/uk --
Version: 3
Fragment type: FragUndefined
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: yes
Number of attributes: 2
Number of primary keys: 1
Length of frm data: 0
Row Checksum: 1
Row GCI: 1
SingleUserMode: 2
ForceVarPart: 0
FragmentCount: 4
ExtraRowGciBits: 0
ExtraRowAuthorBits: 0
TableStatus: Retrieved
-- Attributes --
name Varchar(20; latin1 swedish ci) NOT NULL AT=SHORT VAR ST=MEMORY
NDB$TNODE Unsigned [64] PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY
-- Indexes --
PRIMARY KEY(NDB$TNODE) - UniqueHashIndex
NDBT_ProgramExit: 0 - OK
```

When an index is specified in this way, the --extra-partition-info and --extra-node-info options have no effect.

The Version column in the output contains the table's schema object version. For information about interpreting this value, see NDB Schema Object Versions.

The Extent\_space and Free extent\_space columns were added in MySQL Cluster NDB 6.3.27 and MySQL Cluster NDB 7.0.8. They are applicable only to NDB tables having columns on disk; for tables having only in-memory columns, these columns always contain the value 0.

To illustrate their use, we modify the previous example. First, we must create the necessary Disk Data objects, as shown here:

```
CREATE LOGFILE GROUP 1g_1

ADD UNDOFILE 'undo_1.log'

INITIAL_SIZE 16M

UNDO_BUFFER_SIZE 2M

ENGINE NDB;

ALTER LOGFILE GROUP 1g_1

ADD UNDOFILE 'undo_2.log'

INITIAL_SIZE 12M

ENGINE NDB;

CREATE TABLESPACE ts_1
```

```
ADD DATAFILE 'data_1.dat'
USE LOGFILE GROUP lg_1
INITIAL_SIZE 32M
ENGINE NDB;
ALTER TABLESPACE ts_1
ADD DATAFILE 'data_2.dat'
INITIAL_SIZE 48M
ENGINE NDB;
```

(For more information on the statements just shown and the objects created by them, see Section 7.12.1, "MySQL Cluster Disk Data Objects", as well as CREATE LOGFILE GROUP Syntax, and CREATE TABLESPACE Syntax.)

Now we can create and populate a version of the fish table that stores 2 of its columns on disk (deleting the previous version of the table first, if it already exists):

```
CREATE TABLE fish (
    id INT(11) NOT NULL AUTO_INCREMENT,
    name VARCHAR(20) NOT NULL,
    length_mm INT(11) NOT NULL,
    weight_gm INT(11) NOT NULL,
    PRIMARY KEY pk (id),
    UNIQUE KEY uk (name)
) TABLESPACE ts_1 STORAGE DISK
ENGINE=NDB;
INSERT INTO fish VALUES
    ('','guppy', 35, 2), ('','tuna', 2500, 150000),
    ('','shark', 3000, 110000), (''','manta ray', 1500, 50000),
    (''','grouper', 900, 125000), (''','puffer', 250, 2500);
```

When run against this version of the table, ndb\_desc displays the following output:

```
shell> ./ndb_desc -c localhost fish -d test -p
-- fish --
Version: 3
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 4
Number of primary keys: 1
Length of frm data: 321
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 2
TableStatus: Retrieved
-- Attributes -
id Int PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
name Varchar(20;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
length_mm Int NOT NULL AT=FIXED ST=DISK
weight_gm Int NOT NULL AT=FIXED ST=DISK
-- Indexes -
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
uk$unique(name) - UniqueHashIndex
uk(name) - OrderedIndex
-- Per partition info --
Partition Row count Commit count Frag fixed memory ...
0 2 2 32768
1 4 4 32768
... Frag varsized memory Extent_space Free extent_space
```

```
... 32768 0 0 ... 32768 0 0 NDBT_ProgramExit: 0 - OK
```

This means that 1048576 bytes are allocated from the tablespace for this table on each partition, of which 1044440 bytes remain free for additional storage. In other words, 1048576 - 1044440 = 4136 bytes per partition is currently being used to store the data from this table's disk-based columns. The number of bytes shown as Free extent\_space is available for storing on-disk column data from the fish table only; for this reason, it is not visible when selecting from the INFORMATION\_SCHEMA.FILES table.

The following table includes options that are specific to ndb\_desc. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_desc), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.8 This table describes command-line options for the ndb\_desc program

Format	Description	Added or Removed
blob-info,	Include partition information for BLOB tables in output. Requires	ADDED: NDB 6.3.32, NDB 7.0.13, NDB 7.1.2
-b	that the -p option also be used	
database=dbname,	Name of database containing table	All MySQL 5.1 based releases
-d		
extra-node-info,	Include partition-to-data-node mappings in output. Requires that	ADDED: NDB 6.2.19, NDB 6.3.33, NDB 7.0.14, NDB 7.1.2
-n	the -p option also be used	ololog, NBB Flori I, NBB FFIIE
extra-partition-info,	Display information about partitions	All MySQL 5.1 based releases
-p		
retries=#,	Number of times to retry the connection (once per second)	All MySQL 5.1 based releases
-r	, , ,	
table=tbl_name,	Specify the table in which to find an index. When this option is	ADDED: NDB 7.0.36, NDB 7.1.25
-t	used, -p and -n have no effect and are ignored.	
unqualified,	Use unqualified table names	All MySQL 5.1 based releases
-u		

#### • --blob-info, -b

Include information about subordinate BLOB and TEXT columns.

Use of this option also requires the use of the --extra-partition-info (-p) option.

This option was added in MySQL Cluster NDB 6.3.32, MySQL Cluster NDB 7.0.13, and MySQL Cluster NDB 7.1.2.

• --database=db\_name, -d

Specify the database in which the table should be found.

• --extra-node-info,-n

Include information about the mappings between table partitions and the data nodes upon which they reside. This information can be useful for verifying distribution awareness mechanisms and supporting more efficient application access to the data stored in MySQL Cluster.

Use of this option also requires the use of the --extra-partition-info (-p) option.

This option was added in MySQL Cluster NDB 6.2.19, MySQL Cluster NDB 6.3.33, MySQL Cluster NDB 7.0.14, and MySQL Cluster NDB 7.1.2.

• --extra-partition-info,-p

Print additional information about the table's partitions.

• --retries=#, -r

Try to connect this many times before giving up. One connect attempt is made per second.

• --table=tbl\_name, -t

Specify the table in which to look for an index.

This option was added in MySQL Cluster NDB 7.0.36 and MySQL Cluster NDB 7.1.25.

• --unqualified, -u

Use unqualified table names.

## 6.11 ndb\_drop\_index — Drop Index from an NDB Table

ndb\_drop\_index drops the specified index from an NDB table. It is recommended that you use this utility only as an example for writing NDB API applications—see the Warning later in this section for details.

## Usage

```
ndb_drop_index -c connect_string table_name index -d db_name
```

The statement shown above drops the index named index from the table in the database.

The following table includes options that are specific to ndb\_drop\_index. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_drop\_index), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.9 This table describes command-line options for the ndb drop index program

Format	Description	Added or Removed
database=dbname,	Name of the database in which the table is found	All MySQL 5.1 based releases

#### Warning

Operations performed on Cluster table indexes using the NDB API are not visible to MySQL and make the table unusable by a MySQL server. If you use this program to drop an index, then try to access the table from an SQL node, an error results, as shown here:

```
shell> ./ndb_drop_index -c localhost dogs ix -d ctest1
Dropping index dogs/idx...OK
NDBT_ProgramExit: 0 - OK
shell> ./mysql -u jon -p ctest1
Enter password: *****
Reading table information for completion of table and column names
You can turn off this feature to get a quicker startup with -A
Welcome to the MySQL monitor. Commands end with ; or \gray{g}.
Your MySQL connection id is 7 to server version: 5.1.73-ndb-7.1.33
Type 'help;' or '\h' for help. Type '\c' to clear the buffer.
mysql> SHOW TABLES;
| Tables_in_ctest1 |
 bt1
 bt 2
 dogs
 employees
| fish
6 rows in set (0.00 sec)
mysql > SELECT * FROM dogs;
ERROR 1296 (HY000): Got error 4243 'Index not found' from NDBCLUSTER
```

In such a case, your *only* option for making the table available to MySQL again is to drop the table and re-create it. You can use either the SQL statementDROP TABLE or the ndb\_drop\_table utility (see Section 6.12, "ndb\_drop\_table — Drop an NDB Table") to drop the table.

## 6.12 ndb\_drop\_table — Drop an NDB Table

ndb\_drop\_table drops the specified NDB table. (If you try to use this on a table created with a storage engine other than NDB, the attempt fails with the error 723: No such table exists.) This operation is extremely fast; in some cases, it can be an order of magnitude faster than using a MySQL DROP TABLE statement on an NDB table.

## **Usage**

```
ndb_drop_table -c connect_string tbl_name -d db_name
```

The following table includes options that are specific to ndb\_drop\_table. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_drop\_table), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.10 This table describes command-line options for the ndb\_drop\_table program

Format	Description	Added or Removed
	Name of the database in which the table is found	All MySQL 5.1 based releases
-d		

# 6.13 ndb\_error\_reporter — NDB Error-Reporting Utility

ndb\_error\_reporter creates an archive from data node and management node log files that can be used to help diagnose bugs or other problems with a cluster. It is highly recommended that you make use of this utility when filing reports of bugs in MySQL Cluster.

The following table includes command options specific to the MySQL Cluster program ndb\_error\_reporter. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_error\_reporter), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

ndb\_error\_reporter did not support the --help option prior to MySQL Cluster NDB 6.3.52, MySQL Cluster NDB 7.0.40, and MySQL Cluster NDB 7.1.29 (Bug #11756666, Bug #48606). The --connection-timeout --dry-scp, and --skip-nodegroup options were also added in these releases (Bug #16602002).

Table 6.11 This table describes command-line options for the ndb\_error\_reporter program

Format	Description	Added or Removed
connection- timeout=timeout	Number of seconds to wait when connecting to nodes before timing out.	ADDED: NDB 6.3.52, NDB 7.0.40, NDB 7.1.29
dry-scp	Disable scp with remote hosts; used only for testing.	ADDED: NDB 6.3.52, NDB 7.0.40, NDB 7.1.29
fs	Include file system data in error report; can use a large amount of disk space	All MySQL 5.1 based releases
skip- nodegroup=nodegroup_id	Skip all nodes in the node group having this ID.	ADDED: NDB 6.3.52, NDB 7.0.40, NDB 7.1.29

## **Usage**

```
ndb_error_reporter path/to/config-file [username] [options]
```

This utility is intended for use on a management node host, and requires the path to the management host configuration file (usually named <code>config.ini</code>). Optionally, you can supply the name of a user that is able to access the cluster's data nodes using SSH, to copy the data node log files. <code>ndb\_error\_reporter</code> then includes all of these files in archive that is created in the same directory in which it is run. The archive is named <code>ndb\_error\_report\_yyyymmddhhmmss.tar.bz2</code>, where <code>yyyymmddhhmmss</code> is a datetime string.

ndb error reporter also accepts the options listed here:

• --connection-timeout=timeout

Introduced	5.1.72-ndb-7.1.29	
Command-Line Format	connection-timeout=timeout	
	Permitted Values	
	Type integer	
	Default 0	

Wait this many seconds when trying to connect to nodes before timing out.

• --dry-scp

Introduced	5.1.72-ndb-7.1.29	
Command-Line Format	dry-scp	
	Permitted Values	

Туре	boolean
Defau	TRUE

Run ndb\_error\_reporter without using scp from remote hosts. Used for testing only.

• --fs

Command-Line Format	fs	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Copy the data node file systems to the management host and include them in the archive.

Because data node file systems can be extremely large, even after being compressed, we ask that you please do *not* send archives created using this option to Oracle unless you are specifically requested to do so.

• --skip-nodegroup=nodegroup\_id

Introduced	5.1.72-ndb-7.1.29	
Command-Line Format	connection-timeout=timeout	
	Permitted Values	
	Type integer	
	Default 0	

Skip all nodes belong to the node group having the supplied node group ID.

# 6.14 ndb\_index\_stat — NDB Index Statistics Utility

ndb\_index\_stat ...

## **Usage**

To obtain basic index statistics about a given NDB table, invoke ndb\_index\_stat as shown here, with the name of the table as the first argument and the name of the database containing this table specified immediately following it, using the --database (-d) option:

```
ndb_index_stat table -d database
```

In this example, we use ndb\_index\_stat to obtain such information about an NDB table named mytable in the test database:

```
shell> ndb_index_stat -d test mytable
table:City index:PRIMARY fragCount:2
sampleVersion:3 loadTime:1399585986 sampleCount:1994 keyBytes:7976
query cache: valid:1 sampleCount:1994 totalBytes:27916
times in ms: save: 7.133 sort: 1.974 sort per sample: 0.000
NDBT_ProgramExit: 0 - OK
```

sampleVersion is the version number of the cache from which the statistics data is taken. Running ndb index stat with the --update option causes sampleVersion to be incremented.

loadTime shows when the cache was last updated. This is expressed as seconds since the Unix Epoch.

sampleCount is the number of index entries found per partition. You can estimate the total number of entries by multiplying this by the number of fragments (shown as fragCount).

sampleCount cab be compared with the cardinality of SHOW INDEX or INFORMATION\_SCHEMA.STATISTICS, although the latter two provide a view of the table as a whole, while ndb index stat provides a per-fragment average.

keyBytes is the number of bytes used by the index. In this example, the primary key is an integer, which requires four bytes for each index, so keyBytes can be calculated in this case as shown here:

```
keyBytes = sampleCount * (4 bytes per index) = 1994 * 4 = 7976
```

This information can also be obtained using the corresponding column definitions from INFORMATION SCHEMA. COLUMNS (this requires a MySQL Server and a MySQL client application).

totalBytes is the total memory consumed by all indexes on the table, in bytes.

Timings shown in the preceding examples are specific to each invocation of ndb\_index\_stat.

The --verbose option provides some additional output, as shown here:

```
shell> ndb_index_stat -d test mytable --verbose
random seed 1337010518
connected
loop 1 of 1
table:mytable index:PRIMARY fragCount:4
sampleVersion:2 loadTime:1336751773 sampleCount:0 keyBytes:0
read stats
query cache created
query cache: valid:1 sampleCount:0 totalBytes:0
times in ms: save: 20.766 sort: 0.001
disconnected
NDBT_ProgramExit: 0 - OK
shell>
```

## **Options**

The following table includes options that are specific to the MySQL Cluster ndb\_index\_stat utility. Additional descriptions are listed following the table. For options common to most MySQL Cluster programs (including ndb\_index\_stat), see Section 6.25, "Options Common to MySQL Cluster Programs".

Table 6.12 This table describes command-line options for the ndb index stat program

Format	Description	Added or Removed
database=name,	Name of the database containing the table.	All MySQL 5.1 based releases
-d		
delete	Delete index statistics for the given table, stopping any auto-update previously configured.	All MySQL 5.1 based releases
update	Update index statistics for the given table, restarting any auto-update previously configured.	All MySQL 5.1 based releases
dump	Print the query cache.	All MySQL 5.1 based releases

Format	Description	Added or Removed
query=#	Perform a number of random range queries on first key attr (must be int unsigned).	All MySQL 5.1 based releases
sys-drop	Drop any statistics tables and events in NDB kernel (all statistics are lost)	All MySQL 5.1 based releases
sys-create	Create all statistics tables and events in NDB kernel, if none of them already exist	All MySQL 5.1 based releases
sys-create-if-not-exist	Create any statistics tables and events in NDB kernel that do not already exist.	All MySQL 5.1 based releases
sys-create-if-not-valid	Create any statistics tables or events that do not already exist in the NDB kernel. after dropping any that are invalid.	All MySQL 5.1 based releases
sys-check	Verify that NDB system index statistics and event tables exist.	All MySQL 5.1 based releases
sys-skip-tables	Do not apply sys-* options to tables.	All MySQL 5.1 based releases
sys-skip-events	Do not apply sys-* options to events.	All MySQL 5.1 based releases
verbose,	Turn on verbose output	All MySQL 5.1 based releases
-A		
loops=#	Set the number of times to perform a given command. Default is 0.	All MySQL 5.1 based releases

ndb\_index\_stat statistics options. The following options are used to generate index statistics. They work with a given table and database. They cannot be mixed with ndb\_index\_stat system options.

--database=name, -d name

Command-Line Format	datal	base=name
	Permitted Values Type string	
	Default	[none]
	Min Value	
	Max Value	

The name of the database that contains the table being queried.

• --delete

Command-Line Format	delete Permitted Values	
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Delete the index statistics for the given table, stopping any auto-update that was previously configured.

• --update

Command-Line Format	updat	ce
	Permitte	d Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Update the index statistics for the given table, and restart any auto-update that previously configured.

• --dump

Command-Line Format	dump	
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Dump the contents of the query cache.

• --query=#

Command-Line Format	query	r=#
	Permitte	d Values
	Туре	numeric
	Default	0
	Min	0
	Value	

Max	MAX_INT
Value	

Perform random range queries on first key attribute (must be int unsigned).

ndb\_index\_stat system options. The following options are used to generate and update the statistics tables in the NDB kernel. They cannot be mixed with ndb\_index\_stat statistics options.

• --sys-drop

Command-Line Format	sys-c	drop
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Drop all statistics tables and events in the NDB kernel. This causes all statistics to be lost.

• --sys-create

Command-Line Format	sys-c	create
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Create all statistics tables and events in the NDB kernel. This works only if none of them exist previously.

• sys-create-if-not-exist

Command-Line Format	sys-c	create-if-not-exist
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Create any NDB system statistics tables or events (or both) that do not already exist when the program is invoked.

• --sys-create-if-not-valid

Command-Line Format	sys-c	create-if-not-valid
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Create any NDB system statistics tables or events that do not already exist, after dropping any that are invalid.

• --sys-check

Command-Line Format	sys-c	check
	Permitte	d Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Verify that all required system statistics tables and events exist in the NDB kernel.

• --sys-skip-tables

Command-Line Format	sys-s	skip-tables
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Do not apply any --sys-\* options to any statistics tables.

--sys-skip-events

Command-Line Format	sys-s	skip-events
	Permitte	d Values
	Туре	boolean
	Default	true
	Min Value	

Value

Do not apply any --sys-\* options to any events.

• --verbose

Command-Line Format	verbose	
	-A	
	Permitte	ed Values
	Туре	boolean
	Default	true
	Min Value	
	Max Value	

Turn on verbose output.

• --loops=#

Command-Line Format	loops=#	
	Permitted Values	
	Туре	numeric
	Default	0
	Min Value	0
	Max Value	MAX_INT

Repeat commands this number of times (for use in testing).

# 6.15 ndb\_print\_backup\_file — Print NDB Backup File Contents

ndb\_print\_backup\_file obtains diagnostic information from a cluster backup file.

## Usage

```
ndb_print_backup_file file_name
```

file\_name is the name of a cluster backup file. This can be any of the files (.Data, .ctl, or .log file) found in a cluster backup directory. These files are found in the data node's backup directory under the subdirectory BACKUP-#, where # is the sequence number for the backup. For more information about cluster backup files and their contents, see Section 7.3.1, "MySQL Cluster Backup Concepts".

Like ndb\_print\_schema\_file and ndb\_print\_sys\_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb\_print\_backup\_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

## **Additional Options**

None.

## 6.16 ndb print schema file — Print NDB Schema File Contents

ndb\_print\_schema\_file obtains diagnostic information from a cluster schema file.

## **Usage**

```
ndb_print_schema_file file_name
```

file\_name is the name of a cluster schema file. For more information about cluster schema files, see MySQL Cluster Data Node FileSystemDir Files.

Like ndb\_print\_backup\_file and ndb\_print\_sys\_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb\_schema\_backup\_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

## **Additional Options**

None.

## 6.17 ndb\_print\_sys\_file — Print NDB System File Contents

ndb\_print\_sys\_file obtains diagnostic information from a MySQL Cluster system file.

## **Usage**

```
ndb_print_sys_file file_name
```

file\_name is the name of a cluster system file (sysfile). Cluster system files are located in a data node's data directory (DataDir); the path under this directory to system files matches the pattern ndb\_#\_fs/D#/DBDIH/P#.sysfile. In each case, the # represents a number (not necessarily the same number). For more information, see MySQL Cluster Data Node FileSystemDir Files.

Like ndb\_print\_backup\_file and ndb\_print\_schema\_file (and unlike most of the other NDB utilities that are intended to be run on a management server host or to connect to a management server) ndb\_print\_backup\_file must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

## **Additional Options**

None.

# 6.18 ndbd\_redo\_log\_reader — Check and Print Content of Cluster Redo Log

Reads a redo log file, checking it for errors, printing its contents in a human-readable format, or both. ndbd\_redo\_log\_reader is intended for use primarily by MySQL Cluster developers and Support personnel in debugging and diagnosing problems. This utility was made available as part of default builds beginning with MySQL Cluster NDB 6.1.3. It remains under development, and its syntax and behavior are subject to change in future releases. For this reason, it should be considered experimental at this time.

The C++ source files for ndbd\_redo\_log\_reader can be found in the directory /storage/ndb/src/kernel/blocks/dblqh/redoLogReader.

The following table includes options that are specific to the MySQL Cluster program ndbd\_redo\_log\_reader. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndbd\_redo\_log\_reader), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.13 This table describes command-line options for the ndbd\_redo\_log\_reader program

Format	Description	Added or Removed
-noprint [328]	Do not print records	All MySQL 5.1 based releases
-nocheck [328]	Do not check records for errors	All MySQL 5.1 based releases
help [328]	Print usage information	ADDED: NDB 6.3.53, NDB 7.0.41, NDB 7.1.30

## **Usage**

```
ndbd_redo_log_reader file_name [options]
```

file\_name is the name of a cluster redo log file. redo log files are located in the numbered directories under the data node's data directory (DataDir); the path under this directory to the redo log files matches the pattern ndb\_#\_fs/D#/LCP/#/T#F#.Data. In each case, the # represents a number (not necessarily the same number). For more information, see MySQL Cluster Data Node FileSystemDir Files.

The name of the file to be read may be followed by one or more of the options listed here:

•	Command-Line Format	-noprin	-noprint	
		Permitte	d Values	
		Туре	boolean	
		Default	FALSE	

-noprint: Do not print the contents of the log file.

•	Command-Line Format	-noched	-nocheck	
		Permitte	d Values	
		Туре	boolean	
		Default	FALSE	

-nocheck: Do not check the log file for errors.

•	Introduced	5.1.73-ndb-7.1.30
	Command-Line Format	help

--help: Print usage information.

Added in MySQL Cluster NDB 6.3.53, MySQL Cluster NDB 7.0.41, and MySQL Cluster NDB 7.1.30. (Bug #11749591, Bug #36805)

Like ndb\_print\_backup\_file and ndb\_print\_schema\_file (and unlike most of the NDB utilities that are intended to be run on a management server host or to connect to a management server) ndbd\_redo\_log\_reader must be run on a cluster data node, since it accesses the data node file system directly. Because it does not make use of the management server, this utility can be used when the management server is not running, and even when the cluster has been completely shut down.

## 6.19 ndb\_restore — Restore a MySQL Cluster Backup

The cluster restoration program is implemented as a separate command-line utility ndb\_restore, which can normally be found in the MySQL bin directory. This program reads the files created as a result of the backup and inserts the stored information into the database.

ndb\_restore must be executed once for each of the backup files that were created by the START BACKUP command used to create the backup (see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"). This is equal to the number of data nodes in the cluster at the time that the backup was created.

#### Note

Before using ndb\_restore, it is recommended that the cluster be running in single user mode, unless you are restoring multiple data nodes in parallel. See Section 7.8, "MySQL Cluster Single User Mode", for more information.

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb\_restore. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_restore), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.14 This table describes command-line options for the ndb\_restore program

Format	Description	Added or Removed
connect [332],	Alias forconnectstring.	All MySQL 5.1 based releases
-c [332]		
nodeid=# [332],	Back up files from node with this ID	All MySQL 5.1 based releases
-n [332]		
backupid=# [334],	Restore from the backup with the given ID	All MySQL 5.1 based releases
-b [334]		
restore_data [334],	Restore table data and logs into NDB Cluster using the NDB API	All MySQL 5.1 based releases
-r [334]	S S	
restore_meta [335],	Restore metadata to NDB Cluster using the NDB API	All MySQL 5.1 based releases
-m [335]		
no-upgrade [336],	Do not upgrade array type for varsize attributes which do not	ADDED: 5.1.19
-u [336]	already resize VAR data, and do not change column attributes	
promote-	Allow attributes to be promoted	ADDED: NDB 6.3.8
attributes [333],	when restoring data from backup	
-A [333]		

Format	Description	Added or Removed
preserve-trailing-spaces [334], -P [334]	Allow preservation of trailing spaces (including padding) when promoting fixed-width string types to variable-width types	ADDED: NDB 6.3.8
no-restore-disk- objects [338],	Do not restore objects relating to Disk Data	ADDED: 5.1.6
-d [338]		
restore_epoch [334], -e [334]	Restore epoch info into the status table. Convenient on a MySQL Cluster replication slave for	All MySQL 5.1 based releases
	starting replication. The row in mysql.ndb_apply_status with id 0 will be updated/inserted.	
skip-table-check [332], -s [332]	Skip table structure check during restoring of data	ADDED: 5.1.17
parallelism=# [338],	Number of parallel transactions to use while restoring data	All MySQL 5.1 based releases
-p [338]	<b>3</b>	
print [338]	Print metadata, data and log to stdout (equivalent toprint_metaprint_dataprint_log)	All MySQL 5.1 based releases
print_meta [337]	Print metadata to stdout	All MySQL 5.1 based releases
print_data [336]	Print data to stdout	All MySQL 5.1 based releases
print_log [337]	Print to stdout	All MySQL 5.1 based releases
backup_path=path [335]	Path to backup files directory	ADDED: 5.1.17, NDB 6.1.5
dont_ignore_systab_0 [338]	Do not ignore system table during restore. Experimental only; not for production use	All MySQL 5.1 based releases
-f [338]		
ndb-nodegroup- map=map [338],	Nodegroup map for NDBCLUSTER storage engine. Syntax: list of (source_nodegroup,	All MySQL 5.1 based releases
-z [338]	destination_nodegroup)	
fields-enclosed-by=char	Fields are enclosed with the indicated character	ADDED: 5.1.18
fields-terminated- by=char	Fields are terminated by the indicated character	ADDED: 5.1.18
fields-optionally- enclosed-by	Fields are optionally enclosed with the indicated character	ADDED: 5.1.18
lines-terminated- by=char	Lines are terminated by the indicated character	ADDED: 5.1.18
hex	Print binary types in hexadecimal format	ADDED: 5.1.18
tab=path,	Creates a tab-separated .txt file for each table in the given path	ADDED: 5.1.18

Format	Description	Added or Removed
-T		
append	Append data to a tab-delimited file	ADDED: 5.1.18
progress- frequency=# [338]	Print status of restoration each given number of seconds	All MySQL 5.1 based releases
no-binlog [338]	If a mysqld is connected and using binary logging, do not log the restored data	ADDED: NDB 6.2.16, NDB 6.3.16
verbose=# [338]	Level of verbosity in output	All MySQL 5.1 based releases
include-databases=db- list [339]	List of one or more databases to restore (excludes those not named)	ADDED: NDB 6.3.22, NDB 6.4.3
exclude-databases=db- list [340]	List of one or more databases to exclude (includes those not named)	ADDED: NDB 6.3.22, NDB 6.4.3
include-tables=table- list [339]	List of one or more tables to restore (excludes those in same database that are not named); each table reference must include the database name	ADDED: NDB 6.3.22, NDB 6.4.3
exclude-tables=table- list [340]	List of one or more tables to exclude (includes those in the same database that are not named); each table reference must include the database name	ADDED: NDB 6.3.22, NDB 6.4.3
exclude-missing-columns [341]	Causes columns from the backup version of a table that are missing from the version of the table in the database to be ignored.	ADDED: NDB 6.3.26, NDB 7.0.7
exclude-missing- tables [342]	Causes tables from the backup that are missing from the database to be ignored.	ADDED: NDB 7.1.33
disable-indexes [342]	Causes indexes from a backup to be ignored; may decrease time needed to restore data.	ADDED: NDB 6.3.31, NDB 7.0.11, NDB 7.1.2
rebuild-indexes [342]	Causes multi-threaded rebuilding of ordered indexes found in the backup. Number of threads used is determined by setting BuildIndexThreads parameter.	ADDED: NDB 6.3.31, NDB 7.0.11, NDB 7.1.2
skip-broken- objects [343]	Causes missing blob tables in the backup file to be ignored.	ADDED: NDB 6.3.40, NDB 7.0.21, NDB 7.1.10
skip-unknown- objects [343]	Causes schema objects not recognized by ndb_restore to be ignored when restoring a backup made from a newer MySQL Cluster version to an older version.	ADDED: NDB 6.3.34, NDB 7.0.15, NDB 7.1.4

Format	Description	Added or Removed
rewrite-database=olddb,newdb [343]	Restores to a database with a different name than the original	ADDED: NDB 6.3.41, NDB 7.0.22, NDB 7.1.11
lossy-conversions [334], -L [334]	Allow lossy conversions of column values (type demotions or changes in sign) when restoring data from backup	ADDED: NDB 7.1.11
restore-privilege- tables [335]	Restore MySQL privilege tables that were previously moved to NDB.	ADDED: NDB 7.2.0
exclude-intermediate- sql-tables[=TRUE  FALSE] [344]	If TRUE (the default), do not restore any intermediate tables (having names prefixed with '#sql-') that were left over from copying ALTER TABLE operations.	ADDED: NDB 7.1.31

Typical options for this utility are shown here:

```
ndb_restore [-c connection_string] -n node_id -b backup_id \
[-m] -r --backup_path=/path/to/backup/files
```

Normally, when restoring from a MySQL Cluster backup, ndb\_restore requires at a minimum the --nodeid [332] (short form: -n), --backupid [334] (short form: -b), and --backup\_path [335] options.

The -c option is used to specify a connection string which tells ndb\_restore where to locate the cluster management server. (See Section 5.2.3, "MySQL Cluster Connection Strings", for information on connection strings.) If this option is not used, then ndb\_restore attempts to connect to a management server on localhost:1186. This utility acts as a cluster API node, and so requires a free connection "slot" to connect to the cluster management server. This means that there must be at least one [api] or [mysqld] section that can be used by it in the cluster config.ini file. It is a good idea to keep at least one empty [api] or [mysqld] section in config.ini that is not being used for a MySQL server or other application for this reason (see Section 5.2.7, "Defining SQL and Other API Nodes in a MySQL Cluster").

You can verify that ndb\_restore is connected to the cluster by using the SHOW command in the ndb\_mgm management client. You can also accomplish this from a system shell, as shown here:

```
shell> ndb_mgm -e "SHOW"
```

-n is used to specify the node ID of the data node on which the backups were taken.

The first time you run the ndb\_restore restoration program, you also need to restore the metadata. In other words, you must re-create the database tables—this can be done by running it with the -- restore\_meta (-m) option. Restoring the metdata need be done only on a single data node; this is sufficient to restore it to the entire cluster. Note that the cluster should have an empty database when starting to restore a backup. (In other words, you should start ndbd with --initial prior to performing the restore.)

It is possible to restore data without restoring table metadata. Prior to MySQL 5.1.17, ndb\_restore did not perform any checks of table schemas; if a table was altered between the time the backup was taken

and when ndb\_restore was run, ndb\_restore would still attempt to restore the data to the altered table.

Beginning with MySQL 5.1.17, the default behavior is for ndb\_restore to fail with an error if table data do not match the table schema; this can be overridden using the --skip-table-check or -s option. Prior to MySQL 5.1.21, if this option is used, then ndb\_restore attempts to fit data into the existing table schema, but the result of restoring a backup to a table schema that does not match the original is unspecified.

Beginning with MySQL Cluster NDB 6.3.35, MySQL Cluster NDB 7.0.16, and MySQL Cluster NDB 7.1.5, some of the restrictions on mismatches in column definitions when restoring data using ndb\_restore are relaxed; when one of these types of mismatches is encountered, ndb\_restore does not stop with an error as it did previously, but rather accepts the data and inserts it into the target table while issuing a warning to the user that this is being done. This behavior occurs whether or not either of the options --skip-table-check or --promote-attributes [333] is in use. These differences in column definitions are of the following types:

- Different COLUMN\_FORMAT settings (FIXED, DYNAMIC, DEFAULT)
- Different STORAGE settings (MEMORY, DISK)
- · Different default values
- · Different distribution key settings

Beginning with MySQL Cluster NDB 6.3.8, ndb\_restore supports limited <u>attribute promotion</u> in much the same way that it is supported by MySQL replication; that is, data backed up from a column of a given type can generally be restored to a column using a "larger, similar" type. For example, data from a CHAR(20) column can be restored to a column declared as VARCHAR(20), VARCHAR(30), or CHAR(30); data from a MEDIUMINT column can be restored to a column of type INT or BIGINT. See Replication of Columns Having Different Data Types, for a table of type conversions currently supported by attribute promotion.

Attribute promotion by ndb restore must be enabled explicitly, as follows:

- 1. Prepare the table to which the backup is to be restored. ndb\_restore cannot be used to re-create the table with a different definition from the original; this means that you must either create the table manually, or alter the columns which you wish to promote using ALTER TABLE after restoring the table metadata but before restoring the data.
- 2. Invoke ndb\_restore with the --promote-attributes [333] option (short form -A) when restoring the table data. Attribute promotion does not occur if this option is not used; instead, the restore operation fails with an error.

Prior to MySQL Cluster NDB 7.0.40 and MySQL Cluster NDB 7.1.29, conversions between character data types and TEXT or BLOB were not handled correctly (Bug #17325051).

Prior to MySQL Cluster NDB 7.1.32, demotion of TEXT to TINYTEXT was not handled correctly (Bug #18875137).

When converting between character data types and TEXT or BLOB, only conversions between character types (CHAR and VARCHAR) and binary types (BINARY and VARBINARY) can be performed at the same time. For example, you cannot promote an INT column to BIGINT while promoting a VARCHAR column to TEXT in the same invocation of ndb\_restore.

Converting between TEXT columns using different character sets is not supported. Beginning with MySQL Cluster NDB 7.1.32, it is expressly disallowed (Bug #18875137).

When performing conversions of character or binary types to TEXT or BLOB with ndb\_restore, you may notice that it creates and uses one or more staging tables named table\_name\$STnode\_id. These tables are not needed afterwards, and are normally deleted by ndb\_restore following a successful restoration.

#### --lossy-conversions, -L

Introduced	5.1.51-nd	5.1.51-ndb-7.1.11	
Command-Line Format	lossy-conversions		
	-L		
	Permitte	Permitted Values	
	Туре	Type boolean	
	Default	FALSE	

This option is intended to complement the --promote-attributes [333] option. Using --lossy-conversions allows lossy conversions of column values (type demotions or changes in sign) when restoring data from backup. With some exceptions, the rules governing demotion are the same as for MySQL replication; see Replication of Columns Having Different Data Types, for information about specific type conversions currently supported by attribute demotion.

ndb\_restore reports any truncation of data that it performs during lossy conversions once per attribute and column.

This option was added in MySQL Cluster NDB 7.1.11.

The --preserve-trailing-spaces option is also available beginning with MySQL Cluster NDB 6.3.8. This option (short form -R) causes trailing spaces to be preserved when promoting a fixed-width character data type to its variable-width equivalent—that is, when promoting a CHAR column value to VARCHAR or a BINARY column value to VARBINARY. Otherwise, any trailing spaces are dropped from such column values when they are inserted into the new columns.

#### Note

Although you can promote CHAR columns to VARCHAR and BINARY columns to VARBINARY, you cannot promote VARCHAR columns to CHAR or VARBINARY columns to BINARY.

The -b option is used to specify the ID or sequence number of the backup, and is the same number shown by the management client in the Backup backup\_id completed message displayed upon completion of a backup. (See Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup".)

#### **Important**

When restoring cluster backups, you must be sure to restore all data nodes from backups having the same backup ID. Using files from different backups will at best result in restoring the cluster to an inconsistent state, and may fail altogether.

--restore\_epoch (short form: -e) adds (or restores) epoch information to the cluster replication status table. This is useful for starting replication on a MySQL Cluster replication slave. When this option is used, the row in the mysql.ndb\_apply\_status having 0 in the id column is updated if it already exists; such a row is inserted if it does not already exist. (See Section 8.9, "MySQL Cluster Backups With MySQL Cluster Replication".)

--restore\_data

This option causes ndb\_restore to output NDB table data and logs.

```
--restore meta
```

This option causes ndb\_restore to print NDB table metadata. Generally, you need only use this option when restoring the first data node of a cluster; additional data nodes can obtain the metadata from the first one.

```
--restore-privilege-tables
```

ndb\_restore does not by default restore distributed MySQL privilege tables (MySQL Cluster NDB 7.2.0 and later). This option causes ndb\_restore to restore the privilege tables.

This works only if the privilege tables were converted to NDB before the backup was taken. For more information, see Section 7.14, "Distributed MySQL Privileges for MySQL Cluster".

```
--backup_path
```

The path to the backup directory is required; this is supplied to ndb\_restore using the --backup\_path option, and must include the subdirectory corresponding to the ID backup of the backup to be restored. For example, if the data node's DataDir is /var/lib/mysql-cluster, then the backup directory is /var/lib/mysql-cluster/BACKUP, and the backup files for the backup with the ID 3 can be found in /var/lib/mysql-cluster/BACKUP/BACKUP-3. The path may be absolute or relative to the directory in which the ndb\_restore executable is located, and may be optionally prefixed with backup\_path=.

#### Note

Previous to MySQL 5.1.17 and MySQL Cluster NDB 6.1.5, the path to the backup directory was specified as shown here, with backup\_path= being optional:

```
[backup_path=]/path/to/backup/files
```

Beginning with MySQL 5.1.17 and MySQL Cluster NDB 6.1.5, this syntax changed to --backup\_path=/path/to/backup/files, to conform more closely with options used by other MySQL programs; --backupid [334] is required, and there is no short form for this option.

It is possible to restore a backup to a database with a different configuration than it was created from. For example, suppose that a backup with backup ID 12, created in a cluster with two database nodes having the node IDs 2 and 3, is to be restored to a cluster with four nodes. Then <a href="mailto:ndb\_restore">ndb\_restore</a> must be run twice—once for each database node in the cluster where the backup was taken. However, <a href="mailto:ndb\_restore">ndb\_restore</a> cannot always restore backups made from a cluster running one version of MySQL to a cluster running a different MySQL version. See Section 4.7, "Upgrading and Downgrading MySQL Cluster", for more information.

#### **Important**

It is not possible to restore a backup made from a newer version of MySQL Cluster using an older version of ndb\_restore. You can restore a backup made from a newer version of MySQL to an older cluster, but you must use a copy of ndb\_restore from the newer MySQL Cluster version to do so.

For example, to restore a cluster backup taken from a cluster running MySQL Cluster NDB 7.1.8 to a cluster running MySQL Cluster NDB 7.0.16, you must use the ndb\_restore that comes with the MySQL Cluster NDB 7.1.8 distribution.

For more rapid restoration, the data may be restored in parallel, provided that there is a sufficient number of cluster connections available. That is, when restoring to multiple nodes in parallel, you must have an <code>[api]</code> or <code>[mysqld]</code> section in the cluster <code>config.ini</code> file available for each concurrent <code>ndb\_restore</code> process. However, the data files must always be applied before the logs.

#### --no-upgrade

Formerly, when using ndb\_restore to restore a backup made from a MySQL 5.0 cluster to a 5.1 cluster, VARCHAR columns were not resized and were recreated using the 5.0 fixed format. Beginning with MySQL 5.1.19, ndb\_restore recreates such VARCHAR columns using MySQL Cluster 5.1's variable-width format. Also beginning with MySQL 5.1.19, this behavior can be overridden using the --no-upgrade [336] option (short form: -u) when running ndb\_restore.

#### --print\_data

The --print\_data option causes ndb\_restore to direct its output to stdout.

TEXT and BLOB column values are always truncated to the first 256 bytes in the output; this cannot currently be overridden when using --print\_data.

Beginning with MySQL 5.1.18, several additional options are available for use with the --print\_data option in generating data dumps, either to stdout, or to a file. These are similar to some of the options used with mysqldump, and are shown in the following list:

#### • --tab, -T

Introduced	5.1.18	
Command-Line Format	tab=path	
	-T	

This option causes --print\_data [336] to create dump files, one per table, each named <code>tbl\_name.txt</code>. It requires as its argument the path to the directory where the files should be saved; use . for the current directory.

#### • --fields-enclosed-by=string

Introduced	5.1.18		
Command-Line Format	fields-enclosed-by=char		
	Permitte	Permitted Values	
	Туре	Type string	
	Default	Default	

Each column values are enclosed by the string passed to this option (regardless of data type; see next item).

#### • --fields-optionally-enclosed-by=string

Introduced	5.1.18		
Command-Line Format	fields-optionally-enclosed-by		
	Permitte	Permitted Values	
	Туре	Type string	
	Default	Default	

The string passed to this option is used to enclose column values containing character data (such as CHAR, VARCHAR, BINARY, TEXT, or ENUM).

• --fields-terminated-by=string

Introduced	5.1.18	
Command-Line Format	fields-terminated-by=char	
	Permitted Values	
	Type string	
	Default	\t (tab)

The string passed to this option is used to separate column values. The default value is a tab character  $(\t$ ).

• --hex

Introduced	5.1.18
Command-Line Format	hex

If this option is used, all binary values are output in hexadecimal format.

• --fields-terminated-by=string

Introduced	5.1.18	
Command-Line Format	fields-terminated-by=char	
	Permitted Values	
	Type string	
	Default \t (tab)	

This option specifies the string used to end each line of output. The default is a linefeed character  $(\n)$ .

--append

Introduced	5.1.18
<b>Command-Line Format</b>	append

When used with the --tab and  $--print\_data$  [336] options, this causes the data to be appended to any existing files having the same names.

#### Note

If a table has no explicit primary key, then the output generated when using the --print\_data [336] option includes the table's hidden primary key.

--print\_meta

This option causes ndb\_restore to print all metadata to stdout.

--print\_log

The --print\_log option causes ndb\_restore to output its log to stdout.

#### --print

Causes ndb\_restore to print all data, metadata, and logs to stdout. Equivalent to using the --print\_data [336], --print\_meta [337], and --print\_log [337] options together.

#### Note

Use of --print or any of the --print\_\* options is in effect performing a dry run. Including one or more of these options causes any output to be redirected to stdout; in such cases, ndb\_restore makes no attempt to restore data or metadata to a MySQL Cluster.

```
--dont_ignore_systab_0
```

Normally, when restoring table data and metadata, ndb\_restore ignores the copy of the NDB system table that is present in the backup. --dont\_ignore\_systab\_0 causes the system table to be restored. This option is intended for experimental and development use only, and is not recommended in a production environment.

```
--ndb-nodegroup-map,-z
```

This option can be used to restore a backup taken from one node group to a different node group. Its argument is a list of the form <code>source\_node\_group</code>, <code>target\_node\_group</code>.

```
--no-binlog
```

This option prevents any connected SQL nodes from writing data restored by ndb\_restore to their binary logs. Available beginning with MySQL Cluster NDB 6.2.16 and MySQL Cluster NDB 6.3.16.

```
--no-restore-disk-objects, -d
```

This option stops ndb\_restore from restoring any MySQL Cluster Disk Data objects, such as tablespaces and log file groups; see Section 7.12, "MySQL Cluster Disk Data Tables", for more information about these. Added in MySQL 5.1.6.

```
--parallelism=#, -p
```

Determines the maximum number of parallel transactions that ndb\_restore tries to use. By default, this is 128; the minimum is 1, and the maximum is 1024.

```
--progress-frequency=N
```

Print a status report each N seconds while the backup is in progress. 0 (the default) causes no status reports to be printed. The maximum is 65535.

```
--verbose=#
```

Sets the level for the verbosity of the output. The minimum is 0; the maximum is 255. The default value is 1.

Beginning with MySQL 5.1.18, it is possible to restore only selected databases, or selected tables from a single database, using the syntax shown here:

```
ndb_restore other_options db_name,[db_name[,...] | tbl_name[,tbl_name][,...]]
```

In other words, you can specify either of the following to be restored:

- · All tables from one or more databases
- · One or more tables from a single database

--include-databases=db\_name[,db\_name][,...]

Introduced	5.1.32-ndb-6.4.3		
Command-Line Format	include-databases=db-list		
	Permitted Values		
	Туре	Type string	
	Default		

--include-tables=db\_name.tbl\_name[,db\_name.tbl\_name][,...]

Introduced	5.1.32-nc	lb-6.4.3	
Command-Line Format	inclu	include-tables=table-list	
	Permitte	Permitted Values	
	Туре	Type string	
	Default		

Beginning with MySQL Cluster NDB 6.3.22 and MySQL Cluster NDB 6.4.3, you can (and should) use instead the <code>--include-databases</code> [339] option or the <code>--include-tables</code> option for restoring only specific databases or tables, respectively. <code>--include-databases</code> takes a comma-delimited list of databases to be restored. <code>--include-tables</code> takes a comma-delimited list of tables (in <code>database.table</code> format) to be restored.

When --include-databases or --include-tables is used, only those databases or tables named by the option are restored; all other databases and tables are excluded by ndb\_restore, and are not restored.

The following table shows several invocations of ndb\_restore using --include-\* options (other options possibly required have been omitted for clarity), and the effects these have on restoring from a MySQL Cluster backup:

Option Used	Result
include-databases=db1	Only tables in database db1 are restored; all tables in all other databases are ignored
include-databases=db1,db2 (orinclude-databases=db1include-databases=db2)	Only tables in databases db1 and db2 are restored; all tables in all other databases are ignored
include-tables=db1.t1	Only table t1 in database db1 is restored; no other tables in db1 or in any other database are restored
include-tables=db1.t2,db2.t1 (or include-tables=db1.t2include- tables=db2.t1)	Only the table t2 in database db1 and the table t1 in database db2 are restored; no other tables in db1, db2, or any other database are restored

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use these two options together. For example, the following causes all tables in databases db1 and db2, together with the tables t1 and t2 in database db3, to be restored (and no other databases or tables):

```
shell> ndb_restore [...] --include-databases=db1,db2 --include-tables=db3.t1,db3.t2
```

(Again we have omitted other, possibly required, options in the example just shown.)

#### Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, multiple -- include-\* options were not handled correctly, and the result of the options shown in the previous example was that only the tables db3.t1 and db3.t2 were actually restored. (Bug #48907)

--exclude-databases=db\_name[,db\_name][,...]

Introduced	5.1.32-nd	5.1.32-ndb-6.4.3	
Command-Line Format	excl	exclude-databases=db-list	
	Permitte	Permitted Values	
	Туре	Type string	
	Default		

--exclude-tables=db\_name.tbl\_name[,db\_name.tbl\_name][,...]

Introduced	5.1.32-nd	5.1.32-ndb-6.4.3	
Command-Line Format	excl	exclude-tables=table-list	
	Permitte	Permitted Values	
	Туре	Type string	
	Default		

Beginning with MySQL Cluster NDB 6.3.22 and MySQL Cluster NDB 6.4.3, it is possible to prevent one or more databases or tables from being restored using the ndb\_restore options --exclude-databases and --exclude-tables. --exclude-databases takes a comma-delimited list of one or more databases which should not be restored. --exclude-tables takes a comma-delimited list of one or more tables (using database.table format) which should not be restored.

When --exclude-databases or --exclude-tables is used, only those databases or tables named by the option are excluded; all other databases and tables are restored by ndb\_restore.

This table shows several invocations of ndb\_restore usng --exclude-\* options (other options possibly required have been omitted for clarity), and the effects these options have on restoring from a MySQL Cluster backup:

Option Used	Result
exclude-databases=db1	All tables in all databases except db1 are restored; no tables in db1 are restored
exclude-databases=db1,db2 (or exclude-databases=db1exclude- databases=db2)	All tables in all databases except db1 and db2 are restored; no tables in db1 or db2 are restored
exclude-tables=db1.t1	All tables except t1 in database db1 are restored; all other tables in db1 are restored; all tables in all other databases are restored

Option Used	Result
exclude-tables=db1.t2,db2.t1 (orexclude-tables=db1.t2exclude-	All tables in database db1 except for t2 and all tables in database db2 except for table t1 are
tables=db2.t1)	restored; no other tables in db1 or db2 are restored; all tables in all other databases are restored

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use these two options together. For example, the following causes all tables in all databases *except for* databases db1 and db2, along with the tables t1 and t2 in database db3, *not* to be restored:

```
shell> ndb_restore [...] --exclude-databases=db1,db2 --exclude-tables=db3.t1,db3.t2
```

(Again, we have omitted other possibly necessary options in the interest of clarity and brevity from the example just shown.)

#### Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, multiple --exclude-\* options were not handled correctly, with the result that the options shown in the previous example caused ndb\_restore to exclude only the tables db3.t1 and db3.t2. (Bug #48907)

Beginning with MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, you can use --include-\* and --exclude-\* options together, subject to the following rules:

- The actions of all --include-\* and --exclude-\* options are cumulative.
- All --include-\* and --exclude-\* options are evaluated in the order passed to ndb\_restore, from right to left.
- In the event of conflicting options, the first (rightmost) option takes precedence. In other words, the first option (going from right to left) that matches against a given database or table "wins".

For example, the following set of options causes ndb\_restore to restore all tables from database db1 except db1.t1, while restoring no other tables from any other databases:

```
--include-databases=db1 --exclude-tables=db1.t1
```

However, reversing the order of the options just given simply causes all tables from database db1 to be restored (including db1.t1, but no tables from any other database), because the --include-databases [339] option, being farthest to the right, is the first match against database db1 and thus takes precedence over any other option that matches db1 or any tables in db1:

```
--exclude-tables=db1.t1 --include-databases=db1
```

#### Note

Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10, it was not possible to use --include-databases or --include-tables together with --exclude-databases or --exclude-tables, as these combinations were evaluated inconsistently. (Bug #48907)

--exclude-missing-columns

Introduced	5.1.35-ndb-7.0.7
Command-Line Format	exclude-missing-columns

Beginning with MySQL Cluster NDB 6.3.26 and MySQL Cluster NDB 7.0.7, it is also possible to restore only selected table columns using the <code>--exclude-missing-columns</code> option. When this option is used, <code>ndb\_restore</code> ignores any columns missing from tables being restored as compared to the versions of those tables found in the backup. This option applies to all tables being restored. If you wish to apply this option only to selected tables or databases, you can use it in combination with one or more of the options described in the previous paragraph to do so, then restore data to the remaining tables using a complementary set of these options.

#### --exclude-missing-tables

Introduced	5.1.73-ndb-7.1.33
Command-Line Format	exclude-missing-tables

Beginning with MySQL Cluster NDB 7.1.33, it is also possible to restore only selected tables columns using this option, which causes ndb\_restore to ignore any tables from the backup that are not found in the target database.

#### --disable-indexes

Introduced	5.1.41-ndb-7.1.2
Command-Line Format	disable-indexes

Beginning with MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL Cluster NDB 7.1.2, you can use this option with ndb\_restore to disable restoration of indexes during restoration of the data from a native NDB backup. Afterwards, you can restore indexes for all tables at once with multi-threaded building of indexes using --rebuild-indexes [342], which should be faster than rebuilding indexes concurrently for very large tables.

#### --rebuild-indexes

Introduced	5.1.41-ndb-7.1.2
Command-Line Format	rebuild-indexes

Beginning with MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL Cluster NDB 7.1.2, you can use this option with ndb\_restore to cause multi-threaded rebuilding of the ordered indexes while restoring a native NDB backup. The number of threads used for building ordered indexes by ndb\_restore with this option is controlled by the BuildIndexThreads data node configuration parameter.

It is necessary to use this option only for the first run of ndb\_restore; this causes all ordered indexes to be rebuilt without using --rebuild-indexes again when restoring subsequent nodes. You should use this option prior to inserting new rows into the database; otherwise, it is possible for a row to be inserted that later causes a unique constraint violation when trying to rebuild the indexes.

Rebuilding of unique indexes uses disk write bandwidth for redo logging and local checkpointing. An insufficient amount of this bandwith can lead to redo buffer overload or log overload errors. In such cases you can run ndb\_restore --rebuild-indexes again; the process resumes at the point where the error occurred. You can also do this when you have encountered temporarary errors. You can repeat

execution of ndb\_restore --rebuild-indexes indefinitely; you may be able to stop such errors by reducing the value of DiskCheckpointSpeed to provide additional disk bandwidth to redo logging.

#### --skip-broken-objects

Introduced	5.1.51-ndb-7.1.10
Command-Line Format	skip-broken-objects

This option causes ndb\_restore to ignore corrupt tables while reading a native NDB backup, and to continue restoring any remaining tables (that are not also corrupted). Currently, the --skip-broken-objects option works only in the case of missing blob parts tables.

This option was added in MySQL Cluster NDB 6.3.40, MySQL Cluster NDB 7.0.21, and MySQL Cluster NDB 7.1.10.

#### --skip-unknown-objects

Introduced	5.1.44-ndb-7.1.4
Command-Line Format	skip-unknown-objects

This option causes ndb\_restore to ignore any schema objects it does not recognize while reading a native NDB backup. This can be used for restoring a backup made from a cluster running MySQL Cluster NDB 7.0 to a cluster running MySQL Cluster NDB 6.3.

This option was added in MySQL Cluster NDB 6.3.34, MySQL Cluster NDB 7.0.15, and MySQL Cluster NDB 7.1.4.

#### --rewrite-database=old\_dbname,new\_dbname

Introduced	5.1.51-ndb-7.1.11	
Command-Line Format	rewrite-database=olddb,newdb	
	Permitted Values	
	Туре	string
	Default	none

This option makes it possible to restore to a database having a different name from that used in the backup. For example, if a backup is made of a database named products, you can restore the data it contains to a database named inventory, use this option as shown here (omitting any other options that might be required):

```
shell> ndb_restore --rewrite-database=product,inventory
```

The option can be employed multiple times in a single invocation of ndb\_restore. Thus it is possible to restore simultaneously from a database named db1 to a database named db2 and from a database named db3 to one named db4 using --rewrite-database=db1,db2 --rewrite-database=db1,db2 --rewrite-database=db1. Other ndb\_restore options may be used between multiple occurrences of --rewrite-database.

In the event of conflicts between multiple --rewrite-database options, the last --rewrite-database option used, reading from left to right, is the one that takes effect. For example, if --rewrite-database=db1,db2 --rewrite-database=db1,db3 is used, only --rewrite-

database=db1,db3 is honored, and --rewrite-database=db1,db2 is ignored. It is also possible to restore from multiple databases to a single database, so that --rewrite-database=db1,db3 --rewrite-database=db2,db3 restores all tables and data from databases db1 and db2 into database db3.

#### **Important**

When restoring from multiple backup databases into a single target database using <code>--rewrite-database</code>, no check is made for collisions between table or other object names, and the order in which rows are restored is not guaranteed. This means that it is possible in such cases for rows to be overwritten and updates to be lost.

This option was added in MySQL Cluster NDB 6.3.41, MySQL Cluster NDB 7.0.22, and MySQL Cluster NDB 7.1.11.

--exclude-intermediate-sql-tables[=TRUE|FALSE]

Introduced	5.1.73-nd	db-7.1.31	
Command-Line Format	exclude-intermediate-sql-tables[=TRUE FALSE]		
	Permitted Values		
	Type boolean		
	Default	TRUE	

When performing copying ALTER TABLE operations, mysqld creates intermediate tables (whose names are prefixed with #sql-). When TRUE, the --exclude-intermediate-sql-tables option keeps ndb\_restore from restoring such tables that may have been left over from such operations. This option is TRUE by default.

The --exclude-intermediate-sql-tables option was introduced in MySQL Cluster NDB 7.1.31. (Bug #17882305)

#### Error reporting.

ndb\_restore reports both temporary and permanent errors. In the case of temporary errors, it may able to recover from them. Beginning with MySQL 5.1.12, it reports Restore successful, but encountered temporary error, please look at configuration in such cases.

#### **Important**

After using ndb\_restore to initialize a MySQL Cluster for use in circular replication, binary logs on the SQL node acting as the replication slave are not automatically created, and you must cause them to be created manually. To cause the binary logs to be created, issue a SHOW TABLES statement on that SQL node before running START SLAVE. This is a known issue in MySQL Cluster.

# 6.20 ndb\_select\_all — Print Rows from an NDB Table

ndb select all prints all rows from an NDB table to stdout.

## Usage

ndb\_select\_all -c connect\_string tbl\_name -d db\_name [> file\_name]

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb\_select\_all. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_select\_all), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.15 This table describes command-line options for the ndb\_select\_all program

Format	Description	Added or Removed
database=dbname,	Name of the database in which the table is found	All MySQL 5.1 based releases
-d parallelism=#,	Degree of parallelism	All MySQL 5.1 based releases
-р		
lock=#,	Lock type	All MySQL 5.1 based releases
-1		
order=index,	Sort resultset according to index whose name is supplied	All MySQL 5.1 based releases
-0		
descending,	Sort resultset in descending order (requires order flag)	All MySQL 5.1 based releases
header,	Print header (set to 0 FALSE to disable headers in output)	All MySQL 5.1 based releases
-h		
useHexFormat,	Output numbers in hexadecimal format	All MySQL 5.1 based releases
-x		
delimiter=char,	Set a column delimiter	All MySQL 5.1 based releases
-D		
disk	Print disk references (useful only for Disk Data tables having nonindexed columns)	All MySQL 5.1 based releases
rowid	Print rowid	All MySQL 5.1 based releases
gci	Include GCI in output	All MySQL 5.1 based releases
gci64	Include GCI and row epoch in output	All MySQL 5.1 based releases
tup,	Scan in tup order	All MySQL 5.1 based releases
l-t		
nodata	Do not print table column data	All MySQL 5.1 based releases

• --database=dbname, -d dbname

Name of the database in which the table is found. The default value is TEST\_DB.

• parallelism=#,-p#

Specifies the degree of parallelism.

• --lock=lock\_type, -l lock\_type

Employs a lock when reading the table. Possible values for *lock\_type* are:

- 0: Read lock
- 1: Read lock with hold
- · 2: Exclusive read lock

There is no default value for this option.

• --order=index\_name, -o index\_name

Orders the output according to the index named *index\_name*. Note that this is the name of an index, not of a column, and that the index must have been explicitly named when created.

• --descending, -z

Sorts the output in descending order. This option can be used only in conjunction with the  $-\circ$  ( $--\circ$ rder) option.

• --header=FALSE

Excludes column headers from the output.

--useHexFormat -x

Causes all numeric values to be displayed in hexadecimal format. This does not affect the output of numerals contained in strings or datetime values.

• --delimiter=character, -D character

Causes the *character* to be used as a column delimiter. Only table data columns are separated by this delimiter.

The default delimiter is the tab character.

• --disk

Adds a disk reference column to the output. The column is nonempty only for Disk Data tables having nonindexed columns.

--rowid

Adds a ROWID column providing information about the fragments in which rows are stored.

• --gci

Adds a GCI column to the output showing the global checkpoint at which each row was last updated. See Chapter 3, *MySQL Cluster Overview*, and Section 7.6.2, "MySQL Cluster Log Events", for more information about checkpoints.

• --gci64

Adds a ROW\$GCI64 column to the output showing the global checkpoint at which each row was last updated, as well as the number of the epoch in which this update occurred.

--tupscan, -t

Scan the table in the order of the tuples.

--nodata

Causes any table data to be omitted.

## **Sample Output**

Output from a MySQL SELECT statement:

Output from the equivalent invocation of ndb\_select\_all:

```
shell> ./ndb_select_all -c localhost fish -d ctest1
id    name
3     [shark]
6     [puffer]
2     [tuna]
4     [manta ray]
5     [grouper]
1     [guppy]
6 rows returned
NDBT_ProgramExit: 0 - OK
```

Note that all string values are enclosed by square brackets ("[...]") in the output of ndb\_select\_all. For a further example, consider the table created and populated as shown here:

```
CREATE TABLE dogs (
   id INT(11) NOT NULL AUTO_INCREMENT,
   name VARCHAR(25) NOT NULL,
   breed VARCHAR(50) NOT NULL,
   pRIMARY KEY pk (id),
   KEY ix (name)
)

TABLESPACE ts STORAGE DISK
ENGINE=NDBCLUSTER;
INSERT INTO dogs VALUES
   ('', 'Lassie', 'collie'),
   ('', 'Scooby-Doo', 'Great Dane'),
   ('', 'Rin-Tin-Tin', 'Alsatian'),
   ('', 'Rosscoe', 'Mutt');
```

This demonstrates the use of several additional ndb\_select\_all options:

```
shell> ./ndb_select_all -d ctest1 dogs -o ix -z --gci --disk

GCI id name breed DISK_REF

834461 2 [Scooby-Doo] [Great Dane] [ m_file_no: 0 m_page: 98 m_page_idx: 0 ]

834878 4 [Rosscoe] [Mutt] [ m_file_no: 0 m_page: 98 m_page_idx: 16 ]
```

```
834463 3 [Rin-Tin-Tin] [Alsatian] [ m_file_no: 0 m_page: 34 m_page_idx: 0 ]
835657 1 [Lassie] [Collie] [ m_file_no: 0 m_page: 66 m_page_idx: 0 ]
4 rows returned
NDBT_ProgramExit: 0 - OK
```

#### Note

In earlier MySQL Cluster NDB 7.0 and 7.1 releases, ndb\_select\_all did not print any output for NULL values as it did in MySQL Cluster NDB 6.3 and earlier release series. This issue was fixed in MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11. (Bug #60045)

## 6.21 ndb select count — Print Row Counts for NDB Tables

ndb\_select\_count prints the number of rows in one or more NDB tables. With a single table, the result is equivalent to that obtained by using the MySQL statement SELECT COUNT(\*) FROM tbl\_name.

## **Usage**

```
ndb_select_count [-c connect_string] -ddb_name tbl_name[, tbl_name2[, ...]]
```

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb\_select\_count. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_select\_count), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.16 This table describes command-line options for the ndb select count program

Format	Description	Added or Removed
database=dbname,	Name of the database in which the table is found	All MySQL 5.1 based releases
parallelism=#,	Degree of parallelism	All MySQL 5.1 based releases
-p lock=#,	Lock type	All MySQL 5.1 based releases
-1		

You can obtain row counts from multiple tables in the same database by listing the table names separated by spaces when invoking this command, as shown under **Sample Output**.

## Sample Output

```
shell> ./ndb_select_count -c localhost -d ctest1 fish dogs
6 records in table fish
4 records in table dogs
NDBT_ProgramExit: 0 - OK
```

# 6.22 ndb\_show\_tables — Display List of NDB Tables

ndb\_show\_tables displays a list of all NDB database objects in the cluster. By default, this includes not only both user-created tables and NDB system tables, but NDB-specific indexes, internal triggers, and MySQL Cluster Disk Data objects as well.

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb\_show\_tables. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_show\_tables), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.17 This table describes command-line options for the ndb\_show\_tables program

Format	Description	Added or Removed
database=string,	Specifies the database in which the table is found	All MySQL 5.1 based releases
-d		
loops=#,	Number of times to repeat output	All MySQL 5.1 based releases
-1		
type=#,	Limit output to objects of this type	All MySQL 5.1 based releases
l-t		
unqualified,	Do not qualify table names	All MySQL 5.1 based releases
l-u		
parsable,	Return output suitable for MySQL	All MySQL 5.1 based releases
	LOAD DATA INFILE statement	
-p		
show-temp-status	Show table temporary flag	All MySQL 5.1 based releases

## **Usage**

ndb\_show\_tables [-c connect\_string]

• --database, -d

Specifies the name of the database in which the tables are found.

• --loops, -l

Specifies the number of times the utility should execute. This is 1 when this option is not specified, but if you do use the option, you must supply an integer argument for it.

--parsable, -p

Using this option causes the output to be in a format suitable for use with LOAD DATA INFILE.

• --show-temp-status

If specified, this causes temporary tables to be displayed.

• --type, -t

Can be used to restrict the output to one type of object, specified by an integer type code as shown here:

- 1: System table
- 2: User-created table
- 3: Unique hash index

Any other value causes all NDB database objects to be listed (the default).

--unqualified, -u

If specified, this causes unqualified object names to be displayed.

#### Note

Only user-created MySQL Cluster tables may be accessed from MySQL; system tables such as SYSTAB\_0 are not visible to mysqld. However, you can examine the contents of system tables using NDB API applications such as ndb\_select\_all (see Section 6.20, "ndb\_select\_all — Print Rows from an NDB Table").

# 6.23 ndb\_size.pl — NDBCLUSTER Size Requirement Estimator

This is a Perl script that can be used to estimate the amount of space that would be required by a MySQL database if it were converted to use the NDBCLUSTER storage engine. Unlike the other utilities discussed in this section, it does not require access to a MySQL Cluster (in fact, there is no reason for it to do so). However, it does need to access the MySQL server on which the database to be tested resides.

## Requirements

- A running MySQL server. The server instance does not have to provide support for MySQL Cluster.
- A working installation of Perl.
- The DBI module, which can be obtained from CPAN if it is not already part of your Perl installation. (Many Linux and other operating system distributions provide their own packages for this library.)
- Previous to MySQL 5.1.18, ndb\_size.pl also required the HTML::Template module and an associated template file share/mysql/ndb\_size.tmpl. Beginning with MySQL 5.1.18, ndb\_size.tmpl is no longer needed (or included).
- A MySQL user account having the necessary privileges. If you do not wish to use an existing account, then creating one using GRANT\_USAGE\_ON\_db\_name.\*—where db\_name is the name of the database to be examined—is sufficient for this purpose.

ndb\_size.pl can also be found in the MySQL sources in storage/ndb/tools.

The following table includes options that are specific to the MySQL Cluster program ndb\_size.pl. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_size.pl), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.18 This table describes command-line options for the ndb\_size.pl program

Format	Description	Added or Removed
database=dbname [351]	The database or databases to examine; accepts a commadelimited list; the default is ALL (use all databases found on the server)	All MySQL 5.1 based releases
hostname[:port] [351]	Specify host and optional port as host[:port]	All MySQL 5.1 based releases
socket=file [351]	Specify a socket to connect to	ADDED: NDB 6.2.5

Format	Description	Added or Removed	
user=string [351]	Specify a MySQL user name	All MySQL 5.1 based releases	
password=string [351]	Specify a MySQL user password	All MySQL 5.1 based releases	
format=string [352]	Set output format (text or HTML)	All MySQL 5.1 based releases	
excludetables=tbl_list [35]	Skip any tables in a comma- separated list of tables	All MySQL 5.1 based releases	
excludedbs=db_list [351]	Skip any databases in a commaseparated list of databases	All MySQL 5.1 based releases	
savequeries=file [352]	Saves all queries to the database into the file specified	All MySQL 5.1 based releases	
loadqueries=file [352]	Loads all queries from the file specified; does not connect to a database	All MySQL 5.1 based releases	
real_table_name=table [35]	Designates a table to handle unique index size calculations	ADDED: NDB 6.2.5	

## **Usage**

```
perl ndb_size.pl [--database={db_name|ALL}] [--hostname=host[:port]] [--socket=socket] \
        [--user=user] [--password=password] \
        [--help|-h] [--format={html|text}] \
        [--loadqueries=file_name] [--savequeries=file_name]
```

By default, this utility attempts to analyze all databases on the server. You can specify a single database using the <code>--database</code> option; the default behavior can be made explicit by using <code>ALL</code> for the name of the database. You can also exclude one or more databases by using the <code>--excludedbs</code> option with a comma-separated list of the names of the databases to be skipped. Similarly, you can cause specific tables to be skipped by listing their names, separated by commas, following the optional <code>--excludetables</code> option. A host name (and possibly a port as well) can be specified using <code>--hostname</code>; the default is <code>localhost</code>. Beginning with MySQL Cluster NDB 6.3.49, MySQL Cluster NDB 7.0.32, and MySQL Cluster NDB 7.1.21, you can specify a port in addition to the host using <code>host:port</code> format for the value of <code>--hostname</code>. The default port number is 3306. If necessary, you can also specify a socket; the default is <code>/var/lib/mysql.sock</code>. A MySQL user name and password can be specified the corresponding options shown. It also possible to control the format of the output using the <code>--format</code> option; this can take either of the values <code>html</code> or <code>text</code>, with <code>text</code> being the default. An example of the text output is shown here:

```
shell> ndb_size.pl --database=test --socket=/tmp/mysql.sock
ndb_size.pl report for database: 'test' (1 tables)
Connected to: DBI:mysql:host=localhost;mysql_socket=/tmp/mysql.sock
Including information for versions: 4.1, 5.0, 5.1
test.t1
DataMemory for Columns (* means varsized DataMemory):

        Column Name
        Type
        Varsized
        Key
        4.1
        5.0

        HIDDEN_NDB_PKEY
        bigint
        PRI
        8
        8

        c2
        varchar(50)
        Y
        52
        52

                                                                                   5.1
                                                              PRT 8 8
                                                                                     8
                                                                       52 52
                      c1
                                 int(11)
                                                                       4 4
                                                                                     4
Fixed Size Columns DM/Row
                                                                       64 64
                                                                                     12
   Varsize Columns DM/Row
                                                                        0
                                                                              0
                                                                                      4
DataMemory for Indexes:
   Index Name
                                      Type
                                                      4.1
                                                                     5.0
                                                                                   5.1
```

PRIMARY	BTREE	16 	16	16 	
Total Index DM/Row		16	16	16	
IndexMemory for Indexes:		10	10	10	
Index Name	4.1	5.0	5.1		
PRIMARY	33	16	16		
FICIPACI					
Indexes IM/Row	33	16	16		
Summary (for THIS table):	33	10	10		
Dammary (101 11112 Capte)	4.1	5.0	5.1		
Fixed Overhead DM/Row	12	12	16		
NULL Bytes/Row	4	4	4		
DataMemory/Row	96	96	48		
(Include	es overhead,	bitmap and	indexes)		
Varsize Overhead DM/Row	0	0	8		
Varsize NULL Bytes/Row	0	0	4		
Avg Varside DM/Row	0	0	16		
No. Rows	0	0	0		
Rows/32kb DM Page	340	340	680		
Fixedsize DataMemory (KB)	0	0	0		
Rows/32kb Varsize DM Page	0	0	2040		
Varsize DataMemory (KB)	0	0	0		
Rows/8kb IM Page	248	512	512		
IndexMemory (KB)	0	0	0		
Parameter Minimum Requiremen	nts				
* indicates greater than det	ault				
Parameter	Default	4.1	5.0	5.1	
DataMemory (KB)	81920	0	0	0	
NoOfOrderedIndexes	128	1	1	1	
NoOfTables	128	1	1	1	
IndexMemory (KB)	18432	0	0	0	
NoOfUniqueHashIndexes	64	0	0	0	
NoOfAttributes	1000	3	3	3	
NoOfTriggers	768	5	5	5	

For debugging purposes, the Perl arrays containing the queries run by this script can be read from the file specified using can be saved to a file using --savequeries; a file containing such arrays to be read in during script execution can be specified using --loadqueries. Neither of these options has a default value.

To produce output in HTML format, use the --format option and redirect the output to a file, as shown here:

```
shell> ndb_size.pl --database=test --socket=/tmp/mysql.sock --format=html > ndb_size.html
```

(Without the redirection, the output is sent to stdout.)

The output from this script includes the following information:

- Minimum values for the DataMemory, IndexMemory, MaxNoOfTables, MaxNoOfAttributes, MaxNoOfOrderedIndexes, MaxNoOfUniqueHashIndexes, and MaxNoOfTriggers configuration parameters required to accommodate the tables analyzed.
- Memory requirements for all of the tables, attributes, ordered indexes, and unique hash indexes defined in the database.
- The IndexMemory and DataMemory required per table and table row.

#### Note

Prior to MySQL 5.1.23, MySQL Cluster NDB 6.2.5, and MySQL Cluster NDB 6.3.7, ndb\_size.pl was invoked as shown here:

perl ndb\_size.pl db\_name hostname username password > file\_name.html

For more information about this change, see Bug #28683 and Bug #28253.

# 6.24 ndb\_waiter — Wait for MySQL Cluster to Reach a Given Status

ndb\_waiter repeatedly (each 100 milliseconds) prints out the status of all cluster data nodes until either the cluster reaches a given status or the --timeout limit is exceeded, then exits. By default, it waits for the cluster to achieve STARTED status, in which all nodes have started and connected to the cluster. This can be overridden using the --no-contact and --not-started options.

The node states reported by this utility are as follows:

- NO\_CONTACT: The node cannot be contacted.
- UNKNOWN: The node can be contacted, but its status is not yet known. Usually, this means that the node has received a START or RESTART command from the management server, but has not yet acted on it.
- NOT\_STARTED: The node has stopped, but remains in contact with the cluster. This is seen when restarting the node using the management client's RESTART command.
- STARTING: The node's ndbd process has started, but the node has not yet joined the cluster.
- STARTED: The node is operational, and has joined the cluster.
- SHUTTING\_DOWN: The node is shutting down.
- SINGLE USER MODE: This is shown for all cluster data nodes when the cluster is in single user mode.

The following table includes options that are specific to the MySQL Cluster native backup restoration program ndb\_waiter. Additional descriptions follow the table. For options common to most MySQL Cluster programs (including ndb\_waiter), see Section 6.25, "Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs".

Table 6.19 This table describes command-line options for the ndb\_waiter program

Format	Description	Added or Removed
no-contact,	Wait for cluster to reach NO CONTACT state	All MySQL 5.1 based releases
-n		
not-started	Wait for cluster to reach NOT STARTED state	All MySQL 5.1 based releases
single-user	Wait for cluster to enter single user mode	All MySQL 5.1 based releases
timeout=#,	Wait this many seconds, then exit whether or not cluster has	All MySQL 5.1 based releases
-t	reached desired state; default is 2 minutes (120 seconds)	
nowait-nodes=list	List of nodes not to be waited for.	ADDED: NDB 6.2.1
wait-nodes=list,	List of nodes to be waited for.	ADDED: NDB 6.3.34, NDB 7.0.15, NDB 7.1.4
_ w		

## **Usage**

ndb\_waiter [-c connect\_string]

## **Additional Options**

• --no-contact, -n

Instead of waiting for the STARTED state, ndb\_waiter continues running until the cluster reaches NO\_CONTACT status before exiting.

• --not-started

Instead of waiting for the STARTED state, ndb\_waiter continues running until the cluster reaches NOT\_STARTED status before exiting.

• --timeout=seconds, -t seconds

Time to wait. The program exits if the desired state is not achieved within this number of seconds. The default is 120 seconds (1200 reporting cycles).

• --single-user

The program waits for the cluster to enter single user mode.

• --nowait-nodes=list

When this option is used, ndb\_waiter does not wait for the nodes whose IDs are listed. The list is comma-delimited; ranges can be indicated by dashes, as shown here:

```
shell> ndb_waiter --nowait-nodes=1,3,7-9
```

#### **Important**

Do *not* use this option together with the --wait-nodes option.

This option was added in MySQL Cluster NDB 6.2.1.

• --wait-nodes=list, -w list

When this option is used, ndb\_waiter waits only for the nodes whose IDs are listed. The list is commadelimited; ranges can be indicated by dashes, as shown here:

```
shell> ndb_waiter --wait-nodes=2,4-6,10
```

#### **Important**

Do *not* use this option together with the --nowait-nodes option.

This option was added in MySQL Cluster NDB 6.3.34, 7.0.15, and 7.1.4.

**Sample Output.** Shown here is the output from ndb\_waiter when run against a 4-node cluster in which two nodes have been shut down and then started again manually. Duplicate reports (indicated by "...") are omitted.

```
shell> ./ndb_waiter -c localhost
```

```
Connecting to mgmsrv at (localhost)
State node 1 STARTED
State node 2 NO_CONTACT
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 UNKNOWN
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 NO_CONTACT
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 UNKNOWN
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTING
State node 3 STARTED
State node 4 STARTING
Waiting for cluster enter state STARTED
. . .
State node 1 STARTED
State node 2 STARTED
State node 3 STARTED
State node 4 STARTING
Waiting for cluster enter state STARTED
State node 1 STARTED
State node 2 STARTED
State node 3 STARTED
State node 4 STARTED
Waiting for cluster enter state STARTED
NDBT_ProgramExit: 0 - OK
```

#### Note

If no connection string is specified, then ndb\_waiter tries to connect to a management on localhost, and reports Connecting to mgmsrv at (null).

# 6.25 Options Common to MySQL Cluster Programs — Options Common to MySQL Cluster Programs

All MySQL Cluster programs accept the options described in this section, with the following exceptions:

- mysqld
- ndb\_print\_backup\_file
- ndb\_print\_schema\_file
- ndb\_print\_sys\_file

Users of earlier MySQL Cluster versions should note that some of these options have been changed to make them consistent with one another as well as with mysqld. You can use the --help option with any

MySQL Cluster program—with the exception of ndb\_print\_backup\_file, ndb\_print\_schema\_file, and ndb\_print\_sys\_file—to view a list of the options which the program supports.

The options in the following table are common to all MySQL Cluster executables (except those noted previously in this section).

Table 6.20 This table describes command-line options common to all MySQL Cluster programs

Format	Description	Added or Removed
help,	Display help message and exit	All MySQL 5.1 based releases
usage,		
-?		
ndb-	Set connection string for	All MySQL 5.1 based releases
connectstring=connectstring	Syntax: [nodeid= <id>;]</id>	
connect-	[host=] <hostname>[:<port>].</port></hostname>	
string=connectstring,	Overrides entries specified in	
-c	NDB_CONNECTSTRING or my.cnf.	
ndb-mgmd-	Set the host (and port, if desired)	All MySQL 5.1 based releases
host=host[:port]	for connecting to the management server	
ndb-nodeid=#	Set node id for this node	All MySQL 5.1 based releases
ndb-shm	Allow for optimization using shared memory connections where available (was EXPERIMENTAL, later REMOVED)	REMOVED: NDB 7.0.16, NDB 7.1.5
ndb-optimized-node- selection	Select nodes for transactions in a more optimal way	All MySQL 5.1 based releases
character-sets-dir=path	Directory where character sets are	All MySQL 5.1 based releases
debug=options	Enable output from debug calls. Can be used only for versions compiled with debugging enabled	All MySQL 5.1 based releases
core-file	Write core on errors (defaults to TRUE in debug builds)	All MySQL 5.1 based releases
version,	Output version information and exit	All MySQL 5.1 based releases
-V		

For options specific to individual MySQL Cluster programs, see Chapter 6, MySQL Cluster Programs.

See Section 5.4.2, "MySQL Server Options for MySQL Cluster", for mysqld options relating to MySQL Cluster.

• --help, --usage, -?

Command-Line Format	help
---------------------	------

usage
-?

Prints a short list with descriptions of the available command options.

• --character-sets-dir=name

Command-Line Format	character-sets-dir=path	
	Permitted Values	
	Туре	file name
	Default	

Tells the program where to find character set information.

 --ndb-connectstring=connect\_string, --connect-string=connect\_string, -c connect\_string

Command-Line Format	ndb-connectstring=connectstring	
	connect-string=connectstring	
	-c	
	Permitted Values	
	Type string	
	Default	localhost:1186

This option takes a MySQL Cluster connection string that specifies the management server for the application to connect to, as shown here:

```
shell> ndbd --ndb-connectstring="nodeid=2;host=ndb_mgmd.mysql.com:1186"
```

For more information, see Section 5.2.3, "MySQL Cluster Connection Strings".

--core-file

Command-Line Format	core-file	
	Permitted Values	
	Туре	boolean
	Default	FALSE

Write a core file if the program dies. The name and location of the core file are system-dependent. (For MySQL Cluster programs nodes running on Linux, the default location is the program's working directory—for a data node, this is the node's <code>DataDir</code>.) For some systems, there may be restrictions or limitations; for example, it might be necessary to execute <code>ulimit -c unlimited</code> before starting the server. Consult your system documentation for detailed information.

If MySQL Cluster was built using the --debug option for configure, then --core-file is enabled by default. For regular builds, --core-file is disabled by default.

--debug[=options]

Command-Line Format	debug=options
---------------------	---------------

Permitted Values	
Туре	string
Default	d:t:0,/tmp/ndb_restore.trace

This option can be used only for versions compiled with debugging enabled. It is used to enable output from debug calls in the same manner as for the mysqld process.

• --ndb-mgmd-host=host[:port]

Command-Line Format	ndb-n	ndb-mgmd-host=host[:port]	
Option-File Format	ndb-mgm	ndb-mgmd-host	
	Permitte	Permitted Values	
	Туре	Type string	
	Default	Default localhost:1186	

Can be used to set the host and port number of a single management server for the program to connect to. If the program requires node IDs or references to multiple management servers (or both) in its connection information, use the --ndb-connectstring option instead.

• --ndb-nodeid=#

Command-Line Format	ndb-nodeid=#	
	Permitted Values	
	Type numeric	
	Default	0

Sets this node's MySQL Cluster node ID. The range of permitted values depends on the node's type (data, management, or API) and the MySQL Cluster software version. See Section 3.6.2, "Limits and Differences of MySQL Cluster from Standard MySQL Limits", for more information.

• --ndb-optimized-node-selection

Command-Line Format	ndb-optimized-node-selection	
	Permitted Values	
	Туре	boolean
	Default	TRUE

Optimize selection of nodes for transactions. Enabled by default.

• --version, -V

Command-Line Format	version
	-V

Prints the MySQL Cluster version number of the executable. The version number is relevant because not all versions can be used together, and the MySQL Cluster startup process verifies that the versions of the binaries being used can co-exist in the same cluster. This is also important when performing an online (rolling) software upgrade or downgrade of MySQL Cluster.

See Section 7.5, "Performing a Rolling Restart of a MySQL Cluster"), for more information.

#### • --ndb-shm

Removed	5.1.47-ndb-7.1.5		
Command-Line Format	ndb-shm		
	Permitted Values  Type boolean  Default FALSE		

In older versions of MySQL Cluster, this experimental option allowed the application to use shared memory for optimization when available. --ndb-shm was removed from all MySQL Cluster programs beginning with MySQL Cluster NDB 7.0.16 and MySQL Cluster 7.1.5.

360	

## Chapter 7 Management of MySQL Cluster

## **Table of Contents**

7.1 Summary of MySQL Cluster Start Phases	
7.2 Commands in the MySQL Cluster Management Client	365
7.3 Online Backup of MySQL Cluster	369
7.3.1 MySQL Cluster Backup Concepts	369
7.3.2 Using The MySQL Cluster Management Client to Create a Backup	
7.3.3 Configuration for MySQL Cluster Backups	
7.3.4 MySQL Cluster Backup Troubleshooting	
7.4 MySQL Server Usage for MySQL Cluster	
7.5 Performing a Rolling Restart of a MySQL Cluster	
7.6 Event Reports Generated in MySQL Cluster	
7.6.1 MySQL Cluster Logging Management Commands	
7.6.2 MySQL Cluster Log Events	
7.6.3 Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client	
7.7 MySQL Cluster Log Messages	
7.7.1 MySQL Cluster: Messages in the Cluster Log	
7.7.2 MySQL Cluster: NDB Transporter Errors	
7.8 MySQL Cluster Single User Mode	
7.9 Quick Reference: MySQL Cluster SQL Statements	
7.10 The ndbinfo MySQL Cluster Information Database	
7.10.1 The ndbinfo arbitrator_validity_detail Table	
7.10.2 The ndbinfo arbitrator_validity_summary Table	
7.10.3 The habinfo blocks Table	
7.10.4 The ndbinfo cluster_operations Table	
7.10.5 The ndbinfo cluster_transactions Table	
7.10.6 The habinto config_params Table	
7.10.7 The habinfo counters Table	
7.10.8 The habinfo diskpagebuffer Table	
7.10.0 The habinto diskpagebuffer Table	
7.10.10 The habinfo logspaces Table	
7.10.10 The habinto logspaces lable	
7.10.17 The habinto membership table	
7.10.12 The habinto memoryusage table	
7.10.14 The ndbinfo pools Table	
7.10.16 The ndbinfo server_operations Table	
7.10.17 The ndbinfo server_transactions Table	
7.10.18 The ndbinfo threadblocks Table	
7.10.19 The ndbinfo threadstat Table	
7.10.20 The ndbinfo transporters Table	
7.11 MySQL Cluster Security Issues	
7.11.1 MySQL Cluster Security and Networking Issues	
7.11.2 MySQL Cluster and MySQL Privileges	
7.11.3 MySQL Cluster and MySQL Security Procedures	
7.12 MySQL Cluster Disk Data Tables	
7.12.1 MySQL Cluster Disk Data Objects	
7.12.2 Using Symbolic Links with Disk Data Objects	
7.12.3 MySQL Cluster Disk Data Storage Requirements	
7.13 Adding MySQL Cluster Data Nodes Online	444

	7.13.1 Adding MySQL Cluster Data Nodes Online: General Issues	444
•	7.13.2 Adding MySQL Cluster Data Nodes Online: Basic procedure	446
	7.13.3 Adding MySQL Cluster Data Nodes Online: Detailed Example	447
7.14 [	Distributed MySQL Privileges for MySQL Cluster	455
7.15	NDB API Statistics Counters and Variables	458

Managing a MySQL Cluster involves a number of tasks, the first of which is to configure and start MySQL Cluster. This is covered in Chapter 5, *Configuration of MySQL Cluster NDB 6.1-7.1*, and Chapter 6, *MySQL Cluster Programs*.

The next few sections cover the management of a running MySQL Cluster.

For information about security issues relating to management and deployment of a MySQL Cluster, see Section 7.11, "MySQL Cluster Security Issues".

There are essentially two methods of actively managing a running MySQL Cluster. The first of these is through the use of commands entered into the management client whereby cluster status can be checked, log levels changed, backups started and stopped, and nodes stopped and started. The second method involves studying the contents of the cluster log ndb\_node\_id\_cluster.log; this is usually found in the management server's DataDir directory, but this location can be overridden using the LogDestination option. (Recall that node\_id represents the unique identifier of the node whose activity is being logged.) The cluster log contains event reports generated by ndbd. It is also possible to send cluster log entries to a Unix system log.

Some aspects of the cluster's operation can be also be monitored from an SQL node using the SHOW ENGINE NDB STATUS statement.

In MySQL Cluster NDB 7.1.1 and later, detailed information about cluster operations is available in real time through an SQL interface using the ndbinfo database. For more information, see Section 7.10, "The ndbinfo MySQL Cluster Information Database".

Beginning with MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11, NDB statistics counters provide improved monitoring using the mysql client. These counters, implemented in the NDB kernel, relate to operations performed by or affecting Ndb objects, such as starting, closing, and aborting transactions; primary key and unique key operations; table, range, and pruned scans; blocked threads waiting for various operations to complete; and data and events sent and received by MySQL Cluster. The counters are incremented by the NDB kernel whenever NDB API calls are made or data is sent to or received by the data nodes.

mysqld exposes the NDB API statistics counters as system status variables, which can be identified from the prefix common to all of their names (Ndb\_api\_). The values of these variables can be read in the mysql client from the output of a SHOW STATUS statement, or by querying either the SESSION\_STATUS table or the GLOBAL\_STATUS table (in the INFORMATION\_SCHEMA database). By comparing the values of the status variables before and after the execution of an SQL statement that acts on NDB tables, you can observe the actions taken on the NDB API level that correspond to this statement, which can be beneficial for monitoring and performance tuning of MySQL Cluster.

MySQL Enterprise Monitor can also be used to monitor MySQL Servers that are part of a MySQL Cluster deployment. MySQL Enterprise Monitor 2.3, added a MySQL Cluster advisor, including a set of graphs providing information on MySQL Cluster resources, and defining rules for alerts on key information from data nodes such as <code>DataMemory</code> usage. This information is made available to MySQL Enterprise Monitor 2.3 or later by any MySQL Server which is connected to the MySQL Cluster, using <code>ndbinfo</code>. The advisor could be run against a single MySQL Server in the Cluster, or against a pair in order to provide a higher level of availability for the monitoring service. For more information, see the <code>MySQL Enterprise Monitor 2.3 Manual</code>.

MySQL Cluster Manager provides an advanced command-line interface that simplifies many otherwise complex MySQL Cluster management tasks, such as starting, stopping, or restarting a MySQL Cluster with a large number of nodes. The MySQL Cluster Manager client also supports commands for getting and setting the values of most node configuration parameters as well as mysqld server options and variables relating to MySQL Cluster. MySQL Cluster Manager 1.1 provides support for adding data nodes online. See the MySQL Cluster Manager 1.1 User Manual, for more information.

## 7.1 Summary of MySQL Cluster Start Phases

This section provides a simplified outline of the steps involved when MySQL Cluster data nodes are started. More complete information can be found in MySQL Cluster Start Phases, in the NDB Internals Guide.

These phases are the same as those reported in the output from the <code>node\_id</code> STATUS command in the management client (see Section 7.2, "Commands in the MySQL Cluster Management Client"). In MySQL Cluster NDB 7.1.1 and later, these start phases are also reported in the <code>start\_phase</code> column of the <code>ndbinfo.nodes</code> table.

**Start types.** There are several different startup types and modes, as shown in the following list:

• **Initial start.** The cluster starts with a clean file system on all data nodes. This occurs either when the cluster started for the very first time, or when all data nodes are restarted using the --initial option.

#### Note

Disk Data files are not removed when restarting a node using --initial.

- **System restart.** The cluster starts and reads data stored in the data nodes. This occurs when the cluster has been shut down after having been in use, when it is desired for the cluster to resume operations from the point where it left off.
- Node restart. This is the online restart of a cluster node while the cluster itself is running.
- **Initial node restart.** This is the same as a node restart, except that the node is reinitialized and started with a clean file system.

**Setup and initialization (phase -1).** Prior to startup, each data node (ndbd process) must be initialized. Initialization consists of the following steps:

- 1. Obtain a node ID
- 2. Fetch configuration data
- 3. Allocate ports to be used for inter-node communications
- 4. Allocate memory according to settings obtained from the configuration file

When a data node or SQL node first connects to the management node, it reserves a cluster node ID. To make sure that no other node allocates the same node ID, this ID is retained until the node has managed to connect to the cluster and at least one ndbd reports that this node is connected. This retention of the node ID is guarded by the connection between the node in question and ndb\_mgmd.

Normally, in the event of a problem with the node, the node disconnects from the management server, the socket used for the connection is closed, and the reserved node ID is freed. However, if a node is disconnected abruptly—for example, due to a hardware failure in one of the cluster hosts, or because of network issues—the normal closing of the socket by the operating system may not take place. In this case, the node ID continues to be reserved and not released until a TCP timeout occurs 10 or so minutes later.

To take care of this problem, you can use PURGE STALE SESSIONS. Running this statement forces all reserved node IDs to be checked; any that are not being used by nodes actually connected to the cluster are then freed.

Beginning with MySQL 5.1.11, timeout handling of node ID assignments is implemented. This performs the ID usage checks automatically after approximately 20 seconds, so that PURGE STALE SESSIONS should no longer be necessary in a normal Cluster start.

After each data node has been initialized, the cluster startup process can proceed. The stages which the cluster goes through during this process are listed here:

- Phase 0. The NDBFS and NDBCNTR blocks start (see NDB Kernel Blocks). Data node file systems are cleared on those data nodes that were started with --initial option.
- **Phase 1.** In this stage, all remaining NDB kernel blocks are started. MySQL Cluster connections are set up, inter-block communications are established, and heartbeats are started. In the case of a node restart, API node connections are also checked.

#### Note

When one or more nodes hang in Phase 1 while the remaining node or nodes hang in Phase 2, this often indicates network problems. One possible cause of such issues is one or more cluster hosts having multiple network interfaces. Another common source of problems causing this condition is the blocking of TCP/IP ports needed for communications between cluster nodes. In the latter case, this is often due to a misconfigured firewall.

- **Phase 2.** The NDBCNTR kernel block checks the states of all existing nodes. The master node is chosen, and the cluster schema file is initialized.
- **Phase 3.** The DBLQH and DBTC kernel blocks set up communications between them. The startup type is determined; if this is a restart, the DBDIH block obtains permission to perform the restart.
- **Phase 4.** For an initial start or initial node restart, the redo log files are created. The number of these files is equal to NoOfFragmentLogFiles.

For a system restart:

- · Read schema or schemas.
- · Read data from the local checkpoint.
- · Apply all redo information until the latest restorable global checkpoint has been reached.

For a node restart, find the tail of the redo log.

- **Phase 5.** Most of the database-related portion of a data node start is performed during this phase. For an initial start or system restart, a local checkpoint is executed, followed by a global checkpoint. Periodic checks of memory usage begin during this phase, and any required node takeovers are performed.
- Phase 6. In this phase, node groups are defined and set up.
- **Phase 7.** The arbitrator node is selected and begins to function. The next backup ID is set, as is the backup disk write speed. Nodes reaching this start phase are marked as Started. It is now possible for API nodes (including SQL nodes) to connect to the cluster.
- Phase 8. If this is a system restart, all indexes are rebuilt (by DBDIH).

- Phase 9. The node internal startup variables are reset.
- Phase 100 (OBSOLETE). Formerly, it was at this point during a node restart or initial node restart that API nodes could connect to the node and begin to receive events. Currently, this phase is empty.
- **Phase 101.** At this point in a node restart or initial node restart, event delivery is handed over to the node joining the cluster. The newly-joined node takes over responsibility for delivering its primary data to subscribers. This phase is also referred to as *SUMA handover phase*.

After this process is completed for an initial start or system restart, transaction handling is enabled. For a node restart or initial node restart, completion of the startup process means that the node may now act as a transaction coordinator.

## 7.2 Commands in the MySQL Cluster Management Client

In addition to the central configuration file, a cluster may also be controlled through a command-line interface available through the management client <a href="mailto:ndb\_mgm">ndb\_mgm</a>. This is the primary administrative interface to a running cluster.

Commands for the event logs are given in Section 7.6, "Event Reports Generated in MySQL Cluster"; commands for creating backups and restoring from them are provided in Section 7.3, "Online Backup of MySQL Cluster".

**Using ndb\_mgm with MySQL Cluster Manager.** MySQL Cluster Manager handles starting and stopping processes and tracks their states internally, so it is not necessary to use ndb\_mgm for these tasks for a MySQL Cluster that is under MySQL Cluster Manager control. it is recommended *not* to use the ndb\_mgm command-line client that comes with the MySQL Cluster distribution to perform operations that involve starting or stopping nodes. These include but are not limited to the START, STOP, RESTART, and SHUTDOWN commands. For more information, see MySQL Cluster Manager Process Commands.

The management client has the following basic commands. In the listing that follows, *node\_id* denotes either a database node ID or the keyword ALL, which indicates that the command should be applied to all of the cluster's data nodes.

• HELP

Displays information on all available commands.

SHOW

Displays information on the cluster's status. Possible node status values include UNKNOWN, NO\_CONTACT, NOT\_STARTED, STARTING, STARTED, SHUTTING\_DOWN, and RESTARTING.

Beginning with MySQL Cluster NDB 6.2.8 and MySQL Cluster NDB 6.3.6, the output from this command indicates when the cluster is in single user mode (status SINGLE USER MODE).

Prior to MySQL Cluster NDB 7.0.26 and MySQL Cluster NDB 7.1.5, in a cluster having multiple management nodes, this command displayed information only for data nodes that were actually connected to the current management server; in addition, management servers could not find each other until all nodes had been started. Beginning with these versions, such issues are fixed (see Bug #12352191), and management nodes can be additionally be reported with status RESUME or CONNECTED.

node\_id START

Brings online the data node identified by node\_id (or all data nodes).

ALL START works on all data nodes only, and does not affect management nodes.

#### Important

To use this command to bring a data node online, the data node must have been started using ndbd --nostart or ndbd -n.

• node id STOP [-a] [-f]

Stops the data or management node identified by *node\_id*. Note that ALL STOP works to stop all data nodes only, and does not affect management nodes.

A node affected by this command disconnects from the cluster, and its associated ndbd or ndb\_mgmd process terminates.

The -a option causes the node to be stopped immediately, without waiting for the completion of any pending transactions.

Normally, STOP fails if the result would cause an incomplete cluster. The -f option, added in MySQL Cluster NDB 7.0.19 and MySQL Cluster NDB 7.1.8, forces the node to shut down without checking for this. If this option is used and the result is an incomplete cluster, the cluster immediately shuts down.

#### Warning

Use of the -a option also disables the safety check otherwise performed when STOP is invoked to insure that stopping the node does not cause an incomplete cluster. In other words, you should exercise extreme care when using the -a option with the STOP command, due to the fact that this option makes it possible for the cluster to undergo a forced shutdown because it no longer has a complete copy of all data stored in NDB.

• node\_id RESTART [-n] [-i] [-a] [-f]

Restarts the data node identified by *node\_id* (or all data nodes).

Using the -i option with RESTART causes the data node to perform an initial restart; that is, the node's file system is deleted and recreated. The effect is the same as that obtained from stopping the data node process and then starting it again using ndbd --initial from the system shell. Note that backup files and Disk Data files are not removed when this option is used.

Using the -n option causes the data node process to be restarted, but the data node is not actually brought online until the appropriate START command is issued. The effect of this option is the same as that obtained from stopping the data node and then starting it again using ndbd --nostart or ndbd - n from the system shell.

Using the -a causes all current transactions relying on this node to be aborted. No GCP check is done when the node rejoins the cluster.

Normally, RESTART fails if taking the node offline would result in an incomplete cluster. The -f option, added in MySQL Cluster NDB 7.0.19 and MySQL Cluster NDB 7.1.8, forces the node to restart without checking for this. If this option is used and the result is an incomplete cluster, the entire cluster is restarted.

node\_id STATUS

Displays status information for the data node identified by node\_id (or for all data nodes).

Beginning with MySQL Cluster NDB 6.2.8 and MySQL Cluster NDB 6.3.6, the output from this command indicates when the cluster is in single user mode.

node\_id REPORT report-type

Displays a report of type report-type for the data node identified by  $node\_id$ , or for all data nodes using ALL.

Currently, there are two accepted values for report-type:

- BackupStatus provides a status report on a cluster backup in progress
- MemoryUsage displays how much data memory and index memory is being used by each data node as shown in this example:

```
ndb_mgm> ALL REPORT MEMORY

Node 1: Data usage is 5%(177 32K pages of total 3200)

Node 1: Index usage is 0%(108 8K pages of total 12832)

Node 2: Data usage is 5%(177 32K pages of total 3200)

Node 2: Index usage is 0%(108 8K pages of total 12832)
```

In MySQL Cluster NDB 7.1.1 and later, this information is also available from the ndbinfo.memoryusage table.

report-type is case-insensitive and "fuzzy"; for MemoryUsage, you can use MEMORY (as shown in the prior example), memory, or even simply MEM (or mem). You can abbreviate BackupStatus in a similar fashion.

Prior to MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26, ALL REPORT BackupStatus did not work correctly with multi-threaded data nodes. (Bug #15908907)

The REPORT command was introduced in MySQL Cluster NDB 6.2.3 and MySQL Cluster NDB 6.3.0.

ENTER SINGLE USER MODE node\_id

Enters single user mode, whereby only the MySQL server identified by the node ID node\_id is permitted to access the database.

Currently, it is not possible for data nodes to join a MySQL Cluster while it is running in single user mode. (Bug #20395)

EXIT SINGLE USER MODE

Exits single user mode, enabling all SQL nodes (that is, all running mysqld processes) to access the database.

#### Note

It is possible to use EXIT SINGLE USER MODE even when not in single user mode, although the command has no effect in this case.

• QUIT, EXIT

Terminates the management client.

This command does not affect any nodes connected to the cluster.

#### SHUTDOWN

Shuts down all cluster data nodes and management nodes. To exit the management client after this has been done, use EXIT or QUIT.

This command does not shut down any SQL nodes or API nodes that are connected to the cluster.

• CREATE NODEGROUP nodeid[, nodeid, ...]

Creates a new MySQL Cluster node group and causes data nodes to join it.

This command is used after adding new data nodes online to a MySQL Cluster, and causes them to join a new node group and thus to begin participating fully in the cluster. The command takes as its sole parameter a comma-separated list of node IDs—these are the IDs of the nodes just added and started that are to join the new node group. The number of nodes must be the same as the number of nodes in each node group that is already part of the cluster (each MySQL Cluster node group must have the same number of nodes). In other words, if the MySQL Cluster has 2 node groups of 2 data nodes each, then the new node group must also have 2 data nodes.

The node group ID of the new node group created by this command is determined automatically, and always the next highest unused node group ID in the cluster; it is not possible to set it manually.

This command was introduced in MySQL Cluster NDB 6.4.0. For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".

• DROP NODEGROUP nodegroup\_id

Drops the MySQL Cluster node group with the given *nodegroup* id.

This command can be used to drop a node group from a MySQL Cluster. DROP NODEGROUP takes as its sole argument the node group ID of the node group to be dropped.

DROP NODEGROUP acts only to remove the data nodes in the effected node group from that node group. It does not stop data nodes, assign them to a different node group, or remove them from the cluster's configuration. A data node that does not belong to a node group is indicated in the output of the management client SHOW command with no nodegroup in place of the node group ID, like this (indicated using bold text):

```
id=3 @10.100.2.67 (5.1.73-ndb-7.1.33, no nodegroup)
```

Prior to MySQL Cluster NDB 7.0.4, the SHOW output was not updated correctly following DROP NODEGROUP. (Bug #43413)

DROP NODEGROUP works only when all data nodes in the node group to be dropped are completely empty of any table data and table definitions. Since there is currently no way using ndb\_mgm or the mysql client to remove all data from a specific data node or node group, this means that the command succeeds only in the two following cases:

- 1. After issuing CREATE NODEGROUP in the ndb\_mgm client, but before issuing any ALTER ONLINE TABLE ... REORGANIZE PARTITION statements in the mysql client.
- 2. After dropping all NDBCLUSTER tables using DROP TABLE.

TRUNCATE TABLE does not work for this purpose because this removes only the table data; the data nodes continue to store an NDBCLUSTER table's definition until a DROP TABLE statement is issued that causes the table metadata to be dropped.

DROP NODEGROUP was introduced in MySQL Cluster NDB 6.4.0. For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".

## 7.3 Online Backup of MySQL Cluster

The next few sections describe how to prepare for and then to create a MySQL Cluster backup using the functionality for this purpose found in the ndb\_mgm management client. To distinguish this type of backup from a backup made using mysqldump, we sometimes refer to it as a "native" MySQL Cluster backup. (For information about the creation of backups with mysqldump, see mysqldump — A Database Backup Program.) Restoration of MySQL Cluster backups is done using the ndb\_restore utility provided with the MySQL Cluster distribution; for information about ndb\_restore and its use in restoring MySQL Cluster backups, see Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup".

## 7.3.1 MySQL Cluster Backup Concepts

A backup is a snapshot of the database at a given time. The backup consists of three main parts:

- **Metadata.** The names and definitions of all database tables
- Table records. The data actually stored in the database tables at the time that the backup was made
- Transaction log. A sequential record telling how and when data was stored in the database

Each of these parts is saved on all nodes participating in the backup. During backup, each node saves these three parts into three files on disk:

• BACKUP-backup\_id.node\_id.ctl

A control file containing control information and metadata. Each node saves the same table definitions (for all tables in the cluster) to its own version of this file.

• BACKUP-backup\_id-0.node\_id.data

A data file containing the table records, which are saved on a per-fragment basis. That is, different nodes save different fragments during the backup. The file saved by each node starts with a header that states the tables to which the records belong. Following the list of records there is a footer containing a checksum for all records.

• BACKUP-backup\_id.node\_id.log

A log file containing records of committed transactions. Only transactions on tables stored in the backup are stored in the log. Nodes involved in the backup save different records because different nodes host different database fragments.

In the listing above, <code>backup\_id</code> stands for the backup identifier and <code>node\_id</code> is the unique identifier for the node creating the file.

## 7.3.2 Using The MySQL Cluster Management Client to Create a Backup

Before starting a backup, make sure that the cluster is properly configured for performing one. (See Section 7.3.3, "Configuration for MySQL Cluster Backups".)

The START BACKUP command is used to create a backup:

```
START BACKUP [backup_id] [wait_option] [snapshot_option]
wait_option:
WAIT {STARTED | COMPLETED} | NOWAIT
```

```
snapshot_option:
SNAPSHOTSTART | SNAPSHOTEND
```

Successive backups are automatically identified sequentially, so the <code>backup\_id</code>, an integer greater than or equal to 1, is optional; if it is omitted, the next available value is used. If an existing <code>backup\_id</code> value is used, the backup fails with the error <code>Backup failed</code>: file already exists. If used, the <code>backup\_id</code> must follow <code>START BACKUP</code> immediately, before any other options are used.

Prior to MySQL Cluster NDB 6.2.17, 6.3.23, and 6.4.3, backup IDs greater than 2147483648 (2<sup>31</sup>) were not supported correctly. (Bug #43042) Beginning with these versions, the maximum possible backup ID is 4294967296 (2<sup>32</sup>).

#### Note

Prior to MySQL Cluster NDB 7.0.5, when starting a backup using ndb\_mgm -e "START BACKUP", the backup\_id was required. (Bug #31754)

The wait\_option can be used to determine when control is returned to the management client after a START BACKUP command is issued, as shown in the following list:

If NOWAIT is specified, the management client displays a prompt immediately, as seen here:

```
ndb_mgm> START BACKUP NOWAIT
ndb_mgm>
```

In this case, the management client can be used even while it prints progress information from the backup process.

• With WAIT STARTED the management client waits until the backup has started before returning control to the user, as shown here:

```
ndb_mgm> START BACKUP WAIT STARTED
Waiting for started, this may take several minutes
Node 2: Backup 3 started from node 1
ndb_mgm>
```

 WAIT COMPLETED causes the management client to wait until the backup process is complete before returning control to the user.

WAIT COMPLETED is the default.

Beginning with MySQL Cluster NDB 6.4.0, a <code>snapshot\_option</code> can be used to determine whether the backup matches the state of the cluster when <code>START BACKUP</code> was issued, or when it was completed. <code>SNAPSHOTSTART</code> causes the backup to match the state of the cluster when the backup began; <code>SNAPSHOTEND</code> causes the backup to reflect the state of the cluster when the backup was finished. <code>SNAPSHOTEND</code> is the default, and matches the behavior found in previous MySQL Cluster releases.

#### Note

If you use the SNAPSHOTSTART option with START BACKUP, and the CompressedBackup parameter is enabled, only the data and control files are compressed—the log file is not compressed.

If both a <code>wait\_option</code> and a <code>snapshot\_option</code> are used, they may be specified in either order. For example, all of the following commands are valid, assuming that there is no existing backup having 4 as its ID:

```
START BACKUP WAIT STARTED SNAPSHOTSTART
START BACKUP SNAPSHOTSTART WAIT STARTED
START BACKUP 4 WAIT COMPLETED SNAPSHOTSTART
START BACKUP SNAPSHOTEND WAIT COMPLETED
START BACKUP 4 NOWAIT SNAPSHOTSTART
```

The procedure for creating a backup consists of the following steps:

- 1. Start the management client (ndb\_mgm), if it not running already.
- 2. Execute the START BACKUP command. This produces several lines of output indicating the progress of the backup, as shown here:

```
ndb_mgm> START BACKUP
Waiting for completed, this may take several minutes
Node 2: Backup 1 started from node 1
Node 2: Backup 1 started from node 1 completed
StartGCP: 177 StopGCP: 180
#Records: 7362 #LogRecords: 0
Data: 453648 bytes Log: 0 bytes
ndb_mgm>
```

3. When the backup has started the management client displays this message:

```
Backup backup_id started from node node_id
```

backup\_id is the unique identifier for this particular backup. This identifier is saved in the cluster log, if it has not been configured otherwise. node\_id is the identifier of the management server that is coordinating the backup with the data nodes. At this point in the backup process the cluster has received and processed the backup request. It does not mean that the backup has finished. An example of this statement is shown here:

```
Node 2: Backup 1 started from node 1
```

4. The management client indicates with a message like this one that the backup has started:

```
Backup backup_id started from node node_id completed
```

As is the case for the notification that the backup has started, <code>backup\_id</code> is the unique identifier for this particular backup, and <code>node\_id</code> is the node ID of the management server that is coordinating the backup with the data nodes. This output is accompanied by additional information including relevant global checkpoints, the number of records backed up, and the size of the data, as shown here:

```
Node 2: Backup 1 started from node 1 completed
StartGCP: 177 StopGCP: 180
#Records: 7362 #LogRecords: 0
Data: 453648 bytes Log: 0 bytes
```

It is also possible to perform a backup from the system shell by invoking ndb\_mgm with the -e or -- execute option, as shown in this example:

```
shell> ndb_mgm -e "START BACKUP 6 WAIT COMPLETED SNAPSHOTSTART"
```

When using START BACKUP in this way, you must specify the backup ID.

Cluster backups are created by default in the BACKUP subdirectory of the DataDir on each data node. This can be overridden for one or more data nodes individually, or for all cluster data nodes in the

config.ini file using the BackupDataDir configuration parameter. The backup files created for a backup with a given <code>backup\_id</code> are stored in a subdirectory named <code>BACKUP-backup\_id</code> in the backup directory.

To abort a backup that is already in progress:

- 1. Start the management client.
- 2. Execute this command:

```
ndb_mgm> ABORT BACKUP backup_id
```

The number <code>backup\_id</code> is the identifier of the backup that was included in the response of the management client when the backup was started (in the message <code>Backup\_id</code> started from node <code>management\_node\_id</code>).

3. The management client will acknowledge the abort request with Abort of backup <code>backup\_id</code> ordered.

#### Note

At this point, the management client has not yet received a response from the cluster data nodes to this request, and the backup has not yet actually been aborted

4. After the backup has been aborted, the management client will report this fact in a manner similar to what is shown here:

```
Node 1: Backup 3 started from 5 has been aborted.

Error: 1321 - Backup aborted by user request: Permanent error: User defined error

Node 3: Backup 3 started from 5 has been aborted.

Error: 1323 - 1323: Permanent error: Internal error

Node 2: Backup 3 started from 5 has been aborted.

Error: 1323 - 1323: Permanent error: Internal error

Node 4: Backup 3 started from 5 has been aborted.

Error: 1323 - 1323: Permanent error: Internal error
```

In this example, we have shown sample output for a cluster with 4 data nodes, where the sequence number of the backup to be aborted is 3, and the management node to which the cluster management client is connected has the node ID 5. The first node to complete its part in aborting the backup reports that the reason for the abort was due to a request by the user. (The remaining nodes report that the backup was aborted due to an unspecified internal error.)

#### Note

There is no guarantee that the cluster nodes respond to an ABORT BACKUP command in any particular order.

The Backup <code>backup\_id</code> started from node <code>management\_node\_id</code> has been aborted messages mean that the backup has been terminated and that all files relating to this backup have been removed from the cluster file system.

It is also possible to abort a backup in progress from a system shell using this command:

```
shell> ndb_mgm -e "ABORT BACKUP backup_id"
```

#### Note

If there is no backup having the ID <code>backup\_id</code> running when an <code>ABORT BACKUP</code> is issued, the management client makes no response, nor is it indicated in the cluster log that an invalid abort command was sent.

## 7.3.3 Configuration for MySQL Cluster Backups

Five configuration parameters are essential for backup:

BackupDataBufferSize

The amount of memory used to buffer data before it is written to disk.

BackupLogBufferSize

The amount of memory used to buffer log records before these are written to disk.

BackupMemory

The total memory allocated in a data node for backups. This should be the sum of the memory allocated for the backup data buffer and the backup log buffer.

BackupWriteSize

The default size of blocks written to disk. This applies for both the backup data buffer and the backup log buffer.

• BackupMaxWriteSize

The maximum size of blocks written to disk. This applies for both the backup data buffer and the backup log buffer.

More detailed information about these parameters can be found in Backup Parameters.

## 7.3.4 MySQL Cluster Backup Troubleshooting

If an error code is returned when issuing a backup request, the most likely cause is insufficient memory or disk space. You should check that there is enough memory allocated for the backup.

#### **Important**

If you have set BackupDataBufferSize and BackupLogBufferSize and their sum is greater than 4MB, then you must also set BackupMemory as well.

You should also make sure that there is sufficient space on the hard drive partition of the backup target.

NDB does not support repeatable reads, which can cause problems with the restoration process. Although the backup process is "hot", restoring a MySQL Cluster from backup is not a 100% "hot" process. This is due to the fact that, for the duration of the restore process, running transactions get nonrepeatable reads from the restored data. This means that the state of the data is inconsistent while the restore is in progress.

## 7.4 MySQL Server Usage for MySQL Cluster

mysqld is the traditional MySQL server process. To be used with MySQL Cluster, mysqld needs to be built with support for the NDBCLUSTER storage engine, as it is in the precompiled binaries available from

http://dev.mysql.com/downloads/. If you build MySQL from source, you must invoke configure with one of the options to enable NDBCLUSTER storage engine support:

- --with-plugins=ndbcluster
- --with-plugins=max
- --with-plugins=max-no-innodb

(--with-ndbcluster also works to enable NDBCLUSTER support, but is deprecated and so produces a configure warning as of MySQL 5.1.9.)

For information about other MySQL server options and variables relevant to MySQL Cluster in addition to those discussed in this section, see Section 5.4, "MySQL Server Options and Variables for MySQL Cluster".

If the mysqld binary has been built with Cluster support, the NDBCLUSTER storage engine is still disabled by default. You can use either of two possible options to enable this engine:

- Use --ndbcluster as a startup option on the command line when starting mysqld.
- Insert a line containing ndbcluster in the [mysqld] section of your my.cnf file.

An easy way to verify that your server is running with the NDBCLUSTER storage engine enabled is to issue the SHOW ENGINES statement in the MySQL Monitor (mysql). You should see the value YES as the Support value in the row for NDBCLUSTER. If you see NO in this row or if there is no such row displayed in the output, you are not running an NDB-enabled version of MySQL. If you see DISABLED in this row, you need to enable it in either one of the two ways just described.

To read cluster configuration data, the MySQL server requires at a minimum three pieces of information:

- The MySQL server's own cluster node ID
- The host name or IP address for the management server (MGM node)
- The number of the TCP/IP port on which it can connect to the management server

Node IDs can be allocated dynamically, so it is not strictly necessary to specify them explicitly.

The <code>mysqld</code> parameter <code>ndb-connectstring</code> is used to specify the connection string either on the command line when starting <code>mysqld</code> or in <code>my.cnf</code>. The connection string contains the host name or IP address where the management server can be found, as well as the TCP/IP port it uses.

In the following example,  $ndb_mgmd.mysql.com$  is the host where the management server resides, and the management server listens for cluster messages on port 1186:

```
shell> mysqld --ndbcluster --ndb-connectstring=ndb_mgmd.mysql.com:1186
```

See Section 5.2.3, "MySQL Cluster Connection Strings", for more information on connection strings.

Given this information, the MySQL server will be a full participant in the cluster. (We often refer to a mysqld process running in this manner as an SQL node.) It will be fully aware of all cluster data nodes as well as their status, and will establish connections to all data nodes. In this case, it is able to use any data node as a transaction coordinator and to read and update node data.

You can see in the <code>mysql</code> client whether a MySQL server is connected to the cluster using <code>SHOW PROCESSLIST</code>. If the MySQL server is connected to the cluster, and you have the <code>PROCESS</code> privilege, then the first row of the output is as shown here:

```
mysql> SHOW PROCESSLIST \G

********************************
    Id: 1
    User: system user
    Host:
        db:

Command: Daemon
    Time: 1
    State: Waiting for event from ndbcluster
    Info: NULL
```

#### **Important**

To participate in a MySQL Cluster, the mysqld process must be started with both the options --ndbcluster and --ndb-connectstring (or their equivalents in my.cnf). If mysqld is started with only the --ndbcluster option, or if it is unable to contact the cluster, it is not possible to work with NDB tables, nor is it possible to create any new tables regardless of storage engine. The latter restriction is a safety measure intended to prevent the creation of tables having the same names as NDB tables while the SQL node is not connected to the cluster. If you wish to create tables using a different storage engine while the mysqld process is not participating in a MySQL Cluster, you must restart the server without the --ndbcluster option.

## 7.5 Performing a Rolling Restart of a MySQL Cluster

This section discusses how to perform a *rolling restart* of a MySQL Cluster installation, so called because it involves stopping and starting (or restarting) each node in turn, so that the cluster itself remains operational. This is often done as part of a *rolling upgrade* or *rolling downgrade*, where high availability of the cluster is mandatory and no downtime of the cluster as a whole is permissible. Where we refer to upgrades, the information provided here also generally applies to downgrades as well.

There are a number of reasons why a rolling restart might be desirable. These are described in the next few paragraphs.

#### Configuration change.

To make a change in the cluster's configuration, such as adding an SQL node to the cluster, or setting a configuration parameter to a new value.

**MySQL Cluster software upgrade or downgrade.** To upgrade the cluster to a newer version of the MySQL Cluster software (or to downgrade it to an older version). This is usually referred to as a "rolling upgrade" (or "rolling downgrade", when reverting to an older version of MySQL Cluster).

**Change on node host.** To make changes in the hardware or operating system on which one or more MySQL Cluster node processes are running.

#### System reset (cluster reset).

To reset the cluster because it has reached an undesirable state. In such cases it is often desirable to reload the data and metadata of one or more data nodes. This can be done in any of three ways:

- Start each data node process (ndbd, or possibly ndbmtd in MySQL Cluster NDB 7.0 and later) with the
   --initial option, which forces the data node to clear its file system and to reload all MySQL Cluster
   data and metadata from the other data nodes.
- Create a backup using the ndb\_mgm client BACKUP command prior to performing the restart. Following
  the upgrade, restore the node or nodes using ndb\_restore.

See Section 7.3, "Online Backup of MySQL Cluster", and Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup", for more information.

• Use mysqldump to create a backup prior to the upgrade; afterward, restore the dump using LOAD DATA INFILE.

#### Resource Recovery.

To free memory previously allocated to a table by successive INSERT and DELETE operations, for re-use by other MySQL Cluster tables.

The process for performing a rolling restart may be generalized as follows:

- 1. Stop all cluster management nodes (ndb\_mgmd processes), reconfigure them, then restart them.
  - (If there are multiple management servers and you are using MySQL Cluster NDB 7.0.8 or later, see Rolling restarts with multiple management servers (MySQL Cluster NDB 7.0.8 and later).)
- 2. Stop, reconfigure, then restart each cluster data node (ndbd process) in turn.
- 3. Stop, reconfigure, then restart each cluster SQL node (mysqld process) in turn.

The specifics for implementing a given rolling upgrade depend upon the changes being made. A more detailed view of the process is presented here:

RESTART TYPE:								
Cluster Configuration Change		Cluster Software Upgrade or Downgrade	Change on Node Host	Cluster Reset				
	A. Management node (ndb_mgmd) processes							
1. Stop all ndb_mgmd processes  2. Make changes in global configuration file(s)  3. Start all ndb_mgmd processes		1. Stop all ndb_mgmd processes 2. Replace each ndb_mgmd binary with new version 3. Start ndb_mgmd processes	1. Stop all ndb_mgmd processes 2. Make desired changes in hardware, operating system, or both 3. Start all ndb_mgmd processes	(OR)  1. Stop all ndb_mgmd processes  2. Start all ndb_mgmd processes (option all processes)				
		each data no	de (nābā) prod	ess				
( 01	R )	3 54	1. Stop nábá	(OF	1)			
Stop ndbd     Start ndbd	Restart ndbd	Stop ndbd     Replace     ndbd binary     with new     version     Start ndbd	2. Make desired changes in hardware, operating system, or both	1. Stop ndbd 2. Start ndbd	Restart nďbd			
	C For	anch SOL mad	3. Start ndbd					
(0)		each SQL nod		cess (OF	2.1			
1. Stop mysqld 2. Start mysqld	Restart mysqld binar new		1. Stop mysqld 2. Make desired changes in hardware, operating system, or both 3. Start mysqld	1.Stop mysqld 2.Start mysqld	Restart mysqld			

In the previous diagram, the **Stop** and **Start** steps indicate that the process must be stopped completely using a shell command (such as kill on most Unix systems) or the management client STOP command, then started again from a system shell by invoking the ndbd or ndb\_mgmd executable as appropriate. On Windows (MySQL Cluster NDB 7.1.3 and later), you can also use the system NET START and NET STOP commands or the Windows Service Manager to start and stop nodes which have been installed as Windows services (see Section 4.2.4, "Installing MySQL Cluster Processes as Windows Services").

Restart indicates that the process may be restarted using the ndb\_mgm management client RESTART command (see Section 7.2, "Commands in the MySQL Cluster Management Client").

**Prior to MySQL Cluster NDB 6.3.29 and MySQL Cluster NDB 7.0.10.** When performing an upgrade or downgrade of the cluster software, you must upgrade or downgrade the management nodes first, then the data nodes, and finally the SQL nodes. Doing so in any other order may leave the cluster in an unusable state.

**MySQL Cluster NDB 6.3.29 and later; MySQL Cluster NDB 7.0.10 and later.** MySQL Cluster supports a more flexible order for upgrading the cluster nodes. When upgrading a cluster running MySQL Cluster NDB 6.3.29 or later, or a cluster that is running MySQL Cluster NDB 7.0.10 or later, you may upgrade API nodes (including SQL nodes) before upgrading the management nodes, data nodes, or both. In other words, you are permitted to upgrade the API and SQL nodes in any order. This is subject to the following provisions:

- This functionality is intended for use as part of an online upgrade only. A mix of node binaries from different MySQL Cluster releases is neither intended nor supported for constant, long-term use in a production setting.
- All management nodes must be upgraded before any data nodes are upgraded. This remains true regardless of the order in which you upgrade the cluster's API and SQL nodes.
- For MySQL Cluster NDB 6.3, the ability to upgrade API nodes in any order relative to upgrading
  management nodes and data nodes is supported only for MySQL Cluster NDB 6.3.29 and later; for
  MySQL Cluster NDB 7.0, it supported only for MySQL Cluster NDB 7.0.10 and later. This means that,
  if you are upgrading from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0 release, the
  "old" NDB engine version must be 6.3.29 or later, and the "new" NDB engine version must be 7.0.10 or
  later.
- When upgrading the cluster from a MySQL Cluster NDB 6.3 release to a MySQL Cluster NDB 7.0
  release: Once you have started upgrading the API nodes, you should not perform DDL operations until
  all management nodes and data nodes have been upgraded. DML operations should be unaffected, and
  can continue while the upgrade is in progress.

However, it is possible to perform DDL from an "old" (NDB 6.3 version) API node as long as the master data node is also running the "old" version of MySQL Cluster. You should keep in mind that a data node restart could result in the master node running a "new" (NDB 7.0 version) binary while one or more data nodes are still using the "old" (NDB 6.3) version; in this situation, no DDL can be performed from *any* API node, because the master data node is no longer using an NDB 6.3 binary, but the cluster still contains nodes which are not yet using NDB 7.0. For this reason, we recommend that you avoid performing DDL at any time while the upgrade is in progress.

• Features specific to the "new" version must not be used until all management nodes and data nodes have been upgraded.

This also applies to any MySQL Server version change that may apply, in addition to the NDB engine version change, so do not forget to take this into account when planning the upgrade. (This is true for online upgrades of MySQL Cluster in general.)

See also Bug #48528 and Bug #49163.

Rolling restarts with multiple management servers (MySQL Cluster NDB 7.0.8 and later). A change in MySQL Cluster NDB 7.0.8 in the way in which management nodes obtain configuration data makes it necessary to alter the procedure previously outlined, when performing a rolling restart of a MySQL Cluster with multiple management nodes. (Previously, a management node checked only its own configuration cache, but in MySQL Cluster NDB 7.0.8 and later, ndb\_mgmd also checks to see if any other

management node is running, and, if so, tries to use that node's configuration data.) To keep this from occurring, and to force ndb mgmd to reread its configuration file, perform the following steps:

- 1. Stop all MySQL Cluster ndb\_mgmd processes.
- 2. Update all config.ini files.
- Start a single ndb\_mgmd with --reload, --initial, or both options as desired.
- 4. If you started the first ndb\_mgmd with the --initial option, you must also start any remaining ndb\_mgmd processes using --initial.

Regardless of any other options used when starting the first ndb\_mgmd, you should not start any remaining ndb\_mgmd processes after the first one using --reload.

5. Complete the rolling restarts of the data nodes and API nodes as normal.

See also Bug #45495 and Bug #46488.

**MySQL Cluster NDB 7.0.24 and later; MySQL Cluster NDB 7.1.13 and later.** When performing a rolling restart to update the cluster's configuration, you can use the config\_generation column of the ndbinfo.nodes table to keep track of which data nodes have been successfully restarted with the new configuration. See Section 7.10.13, "The ndbinfo nodes Table".

## 7.6 Event Reports Generated in MySQL Cluster

In this section, we discuss the types of event logs provided by MySQL Cluster, and the types of events that are logged.

MySQL Cluster provides two types of event log:

• The *cluster log*, which includes events generated by all cluster nodes. The cluster log is the log recommended for most uses because it provides logging information for an entire cluster in a single location.

By default, the cluster log is saved to a file named ndb\_node\_id\_cluster.log, (where node\_id is the node ID of the management server) in the same directory where the ndb\_mgm binary resides.

Cluster logging information can also be sent to stdout or a syslog facility in addition to or instead of being saved to a file, as determined by the values set for the DataDir and LogDestination configuration parameters. See Section 5.2.5, "Defining a MySQL Cluster Management Server", for more information about these parameters.

· Node logs are local to each node.

Output generated by node event logging is written to the file ndb\_node\_id\_out.log (where node\_id is the node's node ID) in the node's DataDir. Node event logs are generated for both management nodes and data nodes.

Node logs are intended to be used only during application development, or for debugging application code.

Both types of event logs can be set to log different subsets of events.

Each reportable event can be distinguished according to three different criteria:

• Category: This can be any one of the following values: STARTUP, SHUTDOWN, STATISTICS, CHECKPOINT, NODERESTART, CONNECTION, ERROR, or INFO.

- *Priority*: This is represented by one of the numbers from 1 to 15 inclusive, where 1 indicates "most important" and 15 "least important."
- Severity Level: This can be any one of the following values: ALERT, CRITICAL, ERROR, WARNING, INFO, or DEBUG.

Both the cluster log and the node log can be filtered on these properties.

The format used in the cluster log is as shown here:

```
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 1: Data usage is 2%(60 32K pages of total 2560)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 1: Index usage is 1%(24 8K pages of total 2336)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 1: Resource 0 min: 0 max: 639 curr: 0
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 2: Data usage is 2%(76 32K pages of total 2560)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 2: Index usage is 1%(24 8K pages of total 2336)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 2: Resource 0 min: 0 max: 639 curr: 0
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 3: Data usage is 2%(58 32K pages of total 2560)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 3: Index usage is 1%(25 8K pages of total 2336)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 3: Resource 0 min: 0 max: 639 curr: 0
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 4: Data usage is 2%(74 32K pages of total 2560)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 4: Index usage is 1%(25 8K pages of total 2336)
2007-01-26 19:35:55 [MgmSrvr] INFO -- Node 4: Resource 0 min: 0 max: 639 curr: 0 2007-01-26 19:39:42 [MgmSrvr] INFO -- Node 4: Node 9 Connected
2007-01-26 19:39:42 [MgmSrvr] INFO
                                                        -- Node 1: Node 9 Connected
2007-01-26 19:39:42 [MgmSrvr] INFO
                                                        -- Node 1: Node 9: API 5.1.73-ndb-7.1.33
2007-01-26 19:39:42 [MgmSrvr] INFO -- Node 2: Node 9 Connected
2007-01-26 19:39:42 [MgmSrvr] INFO -- Node 2: Node 9: API 5.1.73-ndb-7.1.33 2007-01-26 19:39:42 [MgmSrvr] INFO -- Node 3: Node 9 Connected 2007-01-26 19:39:42 [MgmSrvr] INFO -- Node 3: Node 9: API 5.1.73-ndb-7.1.33
                                                        -- Node 3: Node 9: API 5.1.73-ndb-7.1.33
2007-01-26 19:39:42 [MgmSrvr] INFO
                                                        -- Node 4: Node 9: API 5.1.73-ndb-7.1.33
2007-01-26 19:59:22 [MgmSrvr] ALERT -- Node 2: Node 7 Disconnected
2007-01-26 19:59:22 [MgmSrvr] ALERT -- Node 2: Node 7 Disconnected
```

Each line in the cluster log contains the following information:

- A timestamp in YYYY-MM-DD HH:MM:SS format.
- The type of node which is performing the logging. In the cluster log, this is always [MgmSrvr].
- The severity of the event.
- The ID of the node reporting the event.
- A description of the event. The most common types of events to appear in the log are connections and disconnections between different nodes in the cluster, and when checkpoints occur. In some cases, the description may contain status information.

## 7.6.1 MySQL Cluster Logging Management Commands

ndb\_mgm supports a number of management commands related to the cluster log. In the listing that follows, node\_id denotes either a database node ID or the keyword ALL, which indicates that the command should be applied to all of the cluster's data nodes.

• CLUSTERLOG ON

Turns the cluster log on.

• CLUSTERLOG OFF

Turns the cluster log off.

• CLUSTERLOG INFO

Provides information about cluster log settings.

• node\_id CLUSTERLOG category=threshold

Logs category events with priority less than or equal to threshold in the cluster log.

• CLUSTERLOG FILTER severity\_level

Toggles cluster logging of events of the specified *severity\_level*.

The following table describes the default setting (for all data nodes) of the cluster log category threshold. If an event has a priority with a value lower than or equal to the priority threshold, it is reported in the cluster log.

Note that events are reported per data node, and that the threshold can be set to different values on different nodes.

Category	Default threshold (All data nodes)			
STARTUP	7			
SHUTDOWN	7			
STATISTICS	7			
CHECKPOINT	7			
NODERESTART	7			
CONNECTION	7			
ERROR	15			
INFO	7			

The STATISTICS category can provide a great deal of useful data. See Section 7.6.3, "Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client", for more information.

Thresholds are used to filter events within each category. For example, a STARTUP event with a priority of 3 is not logged unless the threshold for STARTUP is set to 3 or higher. Only events with priority 3 or lower are sent if the threshold is 3.

The following table shows the event severity levels.

#### Note

These correspond to Unix syslog levels, except for LOG\_EMERG and LOG NOTICE, which are not used or mapped.

Severity Level Value	Severity	Description
1	ALERT	A condition that should be corrected immediately, such as a corrupted system database
2	CRITICAL	Critical conditions, such as device errors or insufficient resources
3	ERROR	Conditions that should be corrected, such as configuration errors
4	WARNING	Conditions that are not errors, but that might require special handling

Severity Level Value	Severity	Description
5	INFO	Informational messages
6	DEBUG	Debugging messages used for NDBCLUSTER development

Event severity levels can be turned on or off (using CLUSTERLOG FILTER—see above). If a severity level is turned on, then all events with a priority less than or equal to the category thresholds are logged. If the severity level is turned off then no events belonging to that severity level are logged.

#### **Important**

Cluster log levels are set on a per ndb\_mgmd, per subscriber basis. This means that, in a MySQL Cluster with multiple management servers, using a CLUSTERLOG command in an instance of ndb\_mgm connected to one management server affects only logs generated by that management server but not by any of the others. This also means that, should one of the management servers be restarted, only logs generated by that management server are affected by the resetting of log levels caused by the restart.

## 7.6.2 MySQL Cluster Log Events

An event report reported in the event logs has the following format:

```
datetime [string] severity -- message
```

#### For example:

```
09:19:30 2005-07-24 [NDB] INFO -- Node 4 Start phase 4 completed
```

This section discusses all reportable events, ordered by category and severity level within each category.

In the event descriptions, GCP and LCP mean "Global Checkpoint" and "Local Checkpoint", respectively.

#### **CONNECTION Events**

These events are associated with connections between Cluster nodes.

Event	Priority	Severity Level	Description
Connected	8	INFO	Data nodes connected
Disconnected	8	ALERT	Data nodes disconnected
CommunicationClosed	8	INFO	SQL node or data node connection closed
CommunicationOpened	8	INFO	SQL node or data node connection open
ConnectedApiVersion	8	INFO	Connection using API version

#### **CHECKPOINT Events**

The logging messages shown here are associated with checkpoints.

Event	Priority	Severity Level	Description
GlobalCheckpointStarted	9	INFO	Start of GCP: REDO log is written to disk

Event	Priority	Severity Level	Description
GlobalCheckpointCompleted	10	INFO	GCP finished
LocalCheckpointStarted	7	INFO	Start of LCP: data written to disk
LocalCheckpointCompleted	7	INFO	LCP completed normally
LCPStoppedInCalcKeepGci	0	ALERT	LCP stopped
LCPFragmentCompleted	11	INFO	LCP on a fragment has been completed
UndoLogBlocked	7	INFO	UNDO logging blocked; buffer near overflow
RedoStatus	7	INFO	Redo status

### **STARTUP Events**

The following events are generated in response to the startup of a node or of the cluster and of its success or failure. They also provide information relating to the progress of the startup process, including information concerning logging activities.

Event	Priority	Severity Level	Description
NDBStartStarted	1	INFO	Data node start phases initiated (all nodes starting)
NDBStartCompleted	1	INFO	Start phases completed, all data nodes
STTORRYRecieved	15	INFO	Blocks received after completion of restart
StartPhaseCompleted	4	INFO	Data node start phase <i>x</i> completed
CM_REGCONF	3	INFO	Node has been successfully included into the cluster; shows the node, managing node, and dynamic ID
CM_REGREF	8	INFO	Node has been refused for inclusion in the cluster; cannot be included in cluster due to misconfiguration, inability to establish communication, or other problem
FIND_NEIGHBOURS	8	INFO	Shows neighboring data nodes
NDBStopStarted	1	INFO	Data node shutdown initiated
NDBStopCompleted	1	INFO	Data node shutdown complete
NDBStopForced	1	ALERT	Forced shutdown of data node
NDBStopAborted	1	INFO	Unable to shut down data node normally
StartREDOLog	4	INFO	New redo log started; GCI keep <i>x</i> , newest restorable GCI <i>y</i>
StartLog	10	INFO	New log started; log part $X$ , start MB $Y$ , stop MB $Z$
UNDORecordsExecuted	15	INFO	Undo records executed
StartReport	4	INFO	Report started
LogFileInitStatus	7	INFO	Log file initialization status
LogFileInitCompStatus	7	INFO	Log file completion status
StartReadLCP	10	INFO	Start read for local checkpoint

Event	Priority	Severity Level	Description
ReadLCPComplete	10	INFO	Read for local checkpoint completed
RunRedo	8	INFO	Running the redo log
RebuildIndex	10	INFO	Rebuilding indexes

#### **NODERESTART Events**

The following events are generated when restarting a node and relate to the success or failure of the node restart process.

Event	Priority	Severity Level	Description
NR_CopyDict	7	INFO	Completed copying of dictionary information
NR_CopyDistr	7	INFO	Completed copying distribution information
NR_CopyFragsStarted	7	INFO	Starting to copy fragments
NR_CopyFragDone	10	INFO	Completed copying a fragment
NR_CopyFragsCompleted	7	INFO	Completed copying all fragments
NodeFailCompleted	8	ALERT	Node failure phase completed
NODE_FAILREP	8	ALERT	Reports that a node has failed
ArbitState	6	INFO	Report whether an arbitrator is found or not; there are seven different possible outcomes when seeking an arbitrator, listed here:
			<ul> <li>Management server restarts arbitration thread [state=X]</li> </ul>
			Prepare arbitrator node X [ticket=Y]
			Receive arbitrator node X [ticket=Y]
			Started arbitrator node <i>X</i> [ticket= <i>Y</i> ]
			• Lost arbitrator node <i>X</i> - process failure [state= <i>Y</i> ]
			Lost arbitrator node <i>X</i> - process exit [state= <i>Y</i> ]
			• Lost arbitrator node <i>x</i> <error msg=""> [state=<i>y</i>]</error>
ArbitResult	2	ALERT	Report arbitrator results; there are eight different possible results for arbitration attempts, listed here:
			Arbitration check failed: less than 1/2 nodes left
			Arbitration check succeeded: node group majority
			Arbitration check failed: missing node group

Event	Priority	Severity Level	Description
			Network partitioning: arbitration required
			Arbitration succeeded: affirmative response from node <i>x</i>
			Arbitration failed: negative response from node <i>x</i>
			Network partitioning: no arbitrator available
			Network partitioning: no arbitrator configured
GCP_TakeoverStarted	7	INFO	GCP takeover started
GCP_TakeoverCompleted	7	INFO	GCP takeover complete
LCP_TakeoverStarted	7	INFO	LCP takeover started
LCP_TakeoverCompleted	7	INFO	LCP takeover complete (state = X)
ConnectCheckStarted	6	INFO	Connection check started
ConnectCheckCompleted	6	INFO	Connection check completed
NodeFailRejected	6	ALERT	Node failure phase failed

#### **STATISTICS Events**

The following events are of a statistical nature. They provide information such as numbers of transactions and other operations, amount of data sent or received by individual nodes, and memory usage.

Event	Priority	Severity Level	Description
TransReportCounters	8	INFO	Report transaction statistics, including numbers of transactions, commits, reads, simple reads, writes, concurrent operations, attribute information, and aborts
OperationReportCounters	8	INFO	Number of operations
TableCreated	7	INFO	Report number of tables created
JobStatistic	9	INFO	Mean internal job scheduling statistics
ThreadConfigLoop	9	INFO	Number of thread configuration loops
SendBytesStatistic	9	INFO	Mean number of bytes sent to node X
ReceiveBytesStatistic	9	INFO	Mean number of bytes received from node X
MemoryUsage	5	INFO	Data and index memory usage (80%, 90%, and 100%)
MTSignalStatistics	9	INFO	Multi-threaded signals

#### **SCHEMA Events**

These events relate to MySQL Cluster schema operations.

Event	Priority	Severity	Description
CreateSchemaObject	8	INFO	Schema objected created

Event	Priority	Severity	Description
AlterSchemaObject	8	INFO	Schema object updated
DropSchemaObject	8	INFO	Schema object dropped

#### **ERROR Events**

These events relate to Cluster errors and warnings. The presence of one or more of these generally indicates that a major malfunction or failure has occurred.

Event	Priority	Severity	Description
TransporterError	2	ERROR	Transporter error
TransporterWarning	8	WARNING	Transporter warning
MissedHeartbeat	8	WARNING	Node X missed heartbeat number Y
DeadDueToHeartbeat	8	ALERT	Node X declared "dead" due to missed heartbeat
WarningEvent	2	WARNING	General warning event
SubscriptionStatus	4	WARNING	Change in subscription status

#### **INFO** Events

These events provide general information about the state of the cluster and activities associated with Cluster maintenance, such as logging and heartbeat transmission.

Event	Priority	Severity	Description
SentHeartbeat	12	INFO	Sent heartbeat
CreateLogBytes	11	INFO	Create log: Log part, log file, size in MB
InfoEvent	2	INFO	General informational event
EventBufferStatus	7	INFO	Event buffer status

#### SINGLEUSER Events

These events are associated with entering and exiting single user mode.

Event	Priority	Severity	Description
SingleUser	7	INFO	Entering or exiting single user mode

#### **BACKUP Events**

These events provide information about backups being created or restored.

Event	Priority	Severity	Description
BackupStarted	7	INFO	Backup started
BackupStatus	7	INFO	Backup status
BackupCompleted	7	INFO	Backup completed
BackupFailedToStart	7	ALERT	Backup failed to start
BackupAborted	7	ALERT	Backup aborted by user
RestoreStarted	7	INFO	Started restoring from backup

Event	Priority	Severity	Description
RestoreMetaData	7	INFO	Restoring metadata
RestoreData	7	INFO	Restoring data
RestoreLog	7	INFO	Restoring log files
RestoreCompleted	7	INFO	Completed restoring from backup
SavedEvent	7	INFO	Event saved

## 7.6.3 Using CLUSTERLOG STATISTICS in the MySQL Cluster Management Client

The NDB management client's CLUSTERLOG STATISTICS command can provide a number of useful statistics in its output. Counters providing information about the state of the cluster are updated at 5-second reporting intervals by the transaction coordinator (TC) and the local query handler (LQH), and written to the cluster log.

**Transaction coordinator statistics.** Each transaction has one transaction coordinator, which is chosen by one of the following methods:

- In a round-robin fashion
- · By communication proximity
- (Beginning with MySQL Cluster NDB 6.3.4:) By supplying a data placement hint when the transaction is started

#### Note

You can determine which TC selection method is used for transactions started from a given SQL node using the ndb\_optimized\_node\_selection system variable.

All operations within the same transaction use the same transaction coordinator, which reports the following statistics:

• Trans count. This is the number transactions started in the last interval using this TC as the transaction coordinator. Any of these transactions may have committed, have been aborted, or remain uncommitted at the end of the reporting interval.

#### Note

Transactions do not migrate between TCs.

- Commit count. This is the number of transactions using this TC as the transaction coordinator that were committed in the last reporting interval. Because some transactions committed in this reporting interval may have started in a previous reporting interval, it is possible for Commit count to be greater than Trans count.
- Read count. This is the number of primary key read operations using this TC as the transaction coordinator that were started in the last reporting interval, including simple reads. This count also includes reads performed as part of unique index operations. A unique index read operation generates 2 primary key read operations—1 for the hidden unique index table, and 1 for the table on which the read takes place.
- **Simple read count.** This is the number of simple read operations using this TC as the transaction coordinator that were started in the last reporting interval. This is a subset of Read count. Because

the value of Simple read count is incremented at a different point in time from Read count, it can lag behind Read count slightly, so it is conceivable that Simple read count is not equal to Read count for a given reporting interval, even if all reads made during that time were in fact simple reads.

• Write count. This is the number of primary key write operations using this TC as the transaction coordinator that were started in the last reporting interval. This includes all inserts, updates, writes and deletes, as well as writes performed as part of unique index operations.

#### Note

A unique index update operation can generate multiple PK read and write operations on the index table and on the base table.

AttrInfoCount. This is the number of 32-bit data words received in the last reporting interval for
primary key operations using this TC as the transaction coordinator. For reads, this is proportional to the
number of columns requested. For inserts and updates, this is proportional to the number of columns
written, and the size of their data. For delete operations, this is usually zero.

Unique index operations generate multiple PK operations and so increase this count. However, data words sent to describe the PK operation itself, and the key information sent, are *not* counted here. Attribute information sent to describe columns to read for scans, or to describe ScanFilters, is also not counted in AttrInfoCount.

• Concurrent Operations. This is the number of primary key or scan operations using this TC as the transaction coordinator that were started during the last reporting interval but that were not completed. Operations increment this counter when they are started and decrement it when they are completed; this occurs after the transaction commits. Dirty reads and writes—as well as failed operations—decrement this counter.

The maximum value that Concurrent Operations can have is the maximum number of operations that a TC block can support; currently, this is (2 \* MaxNoOfConcurrentOperations) + 16 + MaxNoOfConcurrentTransactions. (For more information about these configuration parameters, see the *Transaction Parameters* section of Section 5.2.6, "Defining MySQL Cluster Data Nodes".)

- Abort count. This is the number of transactions using this TC as the transaction coordinator that were aborted during the last reporting interval. Because some transactions that were aborted in the last reporting interval may have started in a previous reporting interval, Abort count can sometimes be greater than Trans count.
- scans. This is the number of table scans using this TC as the transaction coordinator that were started during the last reporting interval. This does not include range scans (that is, ordered index scans).
- Range scans. This is the number of ordered index scans using this TC as the transaction coordinator that were started in the last reporting interval.

**Local query handler statistics (Operations).** There is 1 cluster event per local query handler block (that is, 1 per data node process). Operations are recorded in the LQH where the data they are operating on resides.

#### Note

A single transaction may operate on data stored in multiple LQH blocks.

The Operations statistic provides the number of local operations performed by this LQH block in the last reporting interval, and includes all types of read and write operations (insert, update, write, and delete

operations). This also includes operations used to replicate writes. For example, in a 2-replica cluster, the write to the primary replica is recorded in the primary LQH, and the write to the backup will be recorded in the backup LQH. Unique key operations may result in multiple local operations; however, this does not include local operations generated as a result of a table scan or ordered index scan, which are not counted.

**Process scheduler statistics.** In addition to the statistics reported by the transaction coordinator and local query handler, each ndbd process has a scheduler which also provides useful metrics relating to the performance of a MySQL Cluster. This scheduler runs in an infinite loop; during each loop the scheduler performs the following tasks:

- 1. Read any incoming messages from sockets into a job buffer.
- Check whether there are any timed messages to be executed; if so, put these into the job buffer as well.
- 3. Execute (in a loop) any messages in the job buffer.
- 4. Send any distributed messages that were generated by executing the messages in the job buffer.
- 5. Wait for any new incoming messages.

Process scheduler statistics include the following:

- Mean Loop Counter. This is the number of loops executed in the third step from the preceding list. This statistic increases in size as the utilization of the TCP/IP buffer improves. You can use this to monitor changes in performance as you add new data node processes.
- Mean send size and Mean receive size. These statistics enable you to gauge the efficiency
  of, respectively writes and reads between nodes. The values are given in bytes. Higher values mean a
  lower cost per byte sent or received; the maximum value is 64K.

To cause all cluster log statistics to be logged, you can use the following command in the NDB management client:

ndb\_mgm> ALL CLUSTERLOG STATISTICS=15

#### Note

Setting the threshold for STATISTICS to 15 causes the cluster log to become very verbose, and to grow quite rapidly in size, in direct proportion to the number of cluster nodes and the amount of activity in the MySQL Cluster.

For more information about MySQL Cluster management client commands relating to logging and reporting, see Section 7.6.1, "MySQL Cluster Logging Management Commands".

# 7.7 MySQL Cluster Log Messages

This section contains information about the messages written to the cluster log in response to different cluster log events. It provides additional, more specific information on NDB transporter errors.

# 7.7.1 MySQL Cluster: Messages in the Cluster Log

The following table lists the most common NDB cluster log messages. For information about the cluster log, log events, and event types, see Section 7.6, "Event Reports Generated in MySQL Cluster". These log

messages also correspond to log event types in the MGM API; see The  $\mathtt{Ndb\_logevent\_type}$  Type, for related information of interest to Cluster API developers.

Log Message. Node mgm_node_id: Node	
	Event Name. Connected
data_node_id Connected	Event Type. Connection
<b>Description.</b> The data node having node ID node_id has connected to the management server (node mgm_node_id).	Priority. 8
	Severity. INFO
Log Message. Node mgm_node_id: Node data_node_id Disconnected	Event Name. Disconnected
	Event Type. Connection
<b>Description.</b> The data node having node ID data_node_id has disconnected from the management server (node mgm_node_id).	Priority. 8
Server (node ligit_node_rd).	Severity. ALERT
<pre>Log Message. Node data_node_id: Communication to Node api_node_id closed</pre>	Event Name. CommunicationClosed
<b>Description.</b> The API node or SQL node having node ID	Event Type. Connection
api_node_id is no longer communicating with data node data_node_id.	Priority. 8
	Severity. INFO
Log Message. Node data_node_id: Communication	Event Name.
to Node api_node_id opened	CommunicationOpened
<b>Description.</b> The API node or SQL node having node	Event Type. Connection
ID and made did in now communicating with data and	
ID api_node_id is now communicating with data node data_node_id.	Priority. 8
<del>_</del>	Priority. 8 Severity. INFO
data_node_id.  Log Message. Node mgm_node_id: Node	Severity. INFO Event Name.
data_node_id.  Log Message. Node mgm_node_id: Node	Severity. INFO
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id	Severity. INFO Event Name.
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL	Severity. INFO  Event Name. ConnectedApiVersion
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name.
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint gci started  Description. A global checkpoint with the ID gci has been	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name. GlobalCheckpointStarted  Event Type. Checkpoint
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint gci started  Description. A global checkpoint with the ID gci has been started; node node_id is the master responsible for this global	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name. GlobalCheckpointStarted  Event Type. Checkpoint
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint gci started  Description. A global checkpoint with the ID gci has been started; node node_id is the master responsible for this global	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name. GlobalCheckpointStarted  Event Type. Checkpoint
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint gci started  Description. A global checkpoint with the ID gci has been started; node node_id is the master responsible for this global checkpoint.  Log Message. Node node_id: Global checkpoint	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name. GlobalCheckpointStarted  Event Type. Checkpoint  Priority. 9
Log Message. Node mgm_node_id: Node api_node_id: API version  Description. The API node having node ID api_node_id has connected to management node mgm_node_id using NDB API version version (generally the same as the MySQL version number).  Log Message. Node node_id: Global checkpoint gci started  Description. A global checkpoint with the ID gci has been started; node node_id is the master responsible for this global checkpoint.	Severity. INFO  Event Name. ConnectedApiVersion  Event Type. Connection  Priority. 8  Severity. INFO  Event Name. GlobalCheckpointStarted  Event Type. Checkpoint  Priority. 9  Severity. INFO  Event Name.

	Severity. INFO
Log Message. Node node_id: Local checkpoint lcp started. Keep GCI = current_gci oldest restorable GCI = old_gci	Event Name.  LocalCheckpointStarted
<b>Description.</b> The local checkpoint having sequence ID $1cp$ has been started on node $node\_id$ . The most recent GCI that can be used has the index $current\_gci$ , and the oldest GCI from which the cluster can be restored has the index $old\_gci$ .	Priority. 7 Severity. INFO
Log Message. Node node_id: Local checkpoint lcp completed	Event Name. LocalCheckpointCompleted
<b>Description.</b> The local checkpoint having sequence ID <i>lcp</i> on node <i>node_id</i> has been completed.	Event Type. Checkpoint  Priority. 8
	Severity. INFO
Log Message. Node node_id: Local Checkpoint stopped in CALCULATED_KEEP_GCI	Event Name. LCPStoppedInCalcKeepGci
<b>Description.</b> The node was unable to determine the most recent usable GCI.	Event Type. Checkpoint
Tecent usable GCI.	<b>Priority.</b> 0
	Severity. ALERT
Log Message. Node node_id: Table ID = table_id, fragment ID = fragment_id has completed LCP on Node node_id maxGciStarted: started_gci maxGciCompleted: completed_gci	Event Name.  LCPFragmentCompleted  Event Type. Checkpoint
<b>Description.</b> A table fragment has been checkpointed to disk on node <i>node_id</i> . The GCI in progress has the index <i>started_gci</i> , and the most recent GCI to have been completed has the index <i>completed_gci</i> .	Priority. 11 Severity. INFO
Log Message. Node node_id: ACC Blocked num_1 and TUP Blocked num_2 times last second	Event Name. UndoLogBlocked
<b>Description.</b> Undo logging is blocked because the log	Event Type. Checkpoint
buffer is close to overflowing.	Priority. 7
	Severity. INFO
Log Message. Node node_id: Start initiated version	Event Name. NDBStartStarted
<b>Description.</b> Data node <i>node_id</i> , running NDB version <i>version</i> , is beginning its startup process.	Event Type. StartUp  Priority. 1
	Severity. INFO
Log Message. Node node_id: Started version	Event Name. NDBStartCompleted
<b>Description.</b> Data node <u>node_id</u> , running NDB version	Event Type. StartUp
version, has started successfully.	Priority. 1

	Severity. INFO
Log Message. Node node_id: STTORRY received after restart finished	Event Name. STTORRYRecieved
<b>Description.</b> The node has received a signal indicating that a cluster restart has completed.	Event Type. StartUp  Priority. 15
·	Severity. INFO
Log Message. Node node_id: Start phase phase completed (type)	Event Name. StartPhaseCompleted
<b>Description.</b> The node has completed start phase <i>phase</i> of a <i>type</i> start. For a listing of start phases, see Section 7.1,	Event Type. StartUp
"Summary of MySQL Cluster Start Phases". (type is one of initial, system, node, initial node, or <unknown>.)</unknown>	Priority. 4
Log Message. Node node_id: CM_REGCONF	Severity. INFO  Event Name. CM REGCONF
<pre>president = president_id, own Node = own_id, our dynamic id = dynamic_id</pre>	Event Type. StartUp
<b>Description.</b> Node <a href="mailto:president_id">president_id</a> has been selected as "president". <a href="mailto:own_id">own_id</a> and <a href="mailto:dynamic_id">dynamic_id</a> should always be the	Priority. 3
same as the ID (node_id) of the reporting node.	Severity. INFO
<pre>Log Message. Node node_id: CM_REGREF from Node president_id to our Node node_id. Cause = cause</pre>	Event Name. CM_REGREF  Event Type. StartUp
<b>Description.</b> The reporting node (ID node_id) was unable	Priority. 8
to accept node <pre>president_id</pre> as president. The <pre>cause</pre> of the problem is given as one of <pre>Busy</pre> , <pre>Election</pre> with wait = false, <pre>Not</pre> president, <pre>Election</pre> without selecting new candidate, <pre>Or</pre> No such cause.	Severity. INFO
<b>Log Message.</b> Node node_id: We are Node own_id with dynamic ID dynamic_id, our left neighbor is Node id_1, our right is Node id_2	Event Name. FIND_NEIGHBOURS  Event Type. StartUp
<b>Description.</b> The node has discovered its neighboring	Priority. 8
nodes in the cluster (node <code>id_1</code> and node <code>id_2</code> ). <code>node_id</code> , <code>own_id</code> , and <code>dynamic_id</code> should always be the same; if they are not, this indicates a serious misconfiguration of the cluster nodes.	Severity. INFO
Log Message. Node node_id: type shutdown initiated	Event Name. NDBStopStarted
<b>Description.</b> The node has received a shutdown signal. The <i>type</i> of shutdown is either Cluster or Node.	Event Type. StartUp  Priority. 1
The type of Shutuowii is either Cluster of Node.	Severity. INFO
Log Message. Node node_id: Node shutdown	Event Name. NDBStopCompleted
<pre>completed [, action][Initiated by signal signal.]</pre>	Event Type. StartUp
	Priority. 1

<b>Description.</b> The node has been shut down. This report may include an <i>action</i> , which if present is one of restarting, no start, or initial. The report may also include a reference to an NDB Protocol <i>signal</i> ; for possible signals, refer to Operations and Signals.	Severity. INFO
Log Message. Node node_id: Forced node shutdown completed [, action]. [Occured during startphase start_phase.][ Initiated by signal.][Caused by error error_code: 'error_message(error_classification). error_status'.[(extra info extra_code)]]	Event Name. NDBStopForced  Event Type. StartUp  Priority. 1  Severity. ALERT
<b>Description.</b> The node has been forcibly shut down. The <i>action</i> (one of restarting, no start, or initial) subsequently being taken, if any, is also reported. If the shutdown occurred while the node was starting, the report includes the <i>start_phase</i> during which the node failed. If this was a result of a <i>signal</i> sent to the node, this information is also provided (see Operations and Signals, for more information). If the error causing the failure is known, this is also included; for more information about NDB error messages and classifications, see MySQL Cluster API Errors.	•
Log Message. Node node_id: Node shutdown aborted  Description. The node shutdown process was aborted by the user.	Event Name. NDBStopAborted  Event Type. StartUp  Priority. 1  Severity. INFO
Log Message. Node node_id: StartLog: [GCI Keep: keep_pos LastCompleted: last_pos NewestRestorable: restore_pos]	Event Name. StartREDOLog Event Type. StartUp
<b>Description.</b> This reports global checkpoints referenced during a node start. The redo log prior to <code>keep_pos</code> is dropped. <code>last_pos</code> is the last global checkpoint in which data node the participated; <code>restore_pos</code> is the global checkpoint which is actually used to restore all data nodes.	Priority. 4 Severity. INFO
Log Message. startup_message [Listed separately; see below.]	Event Name. StartReport Event Type. StartUp
<b>Description.</b> There are a number of possible startup messages that can be logged under different circumstances.	Priority. 4 Severity. INFO
Log Message. Node node_id: Node restart completed copy of dictionary information	Event Name. NR_CopyDict
<b>Description.</b> Copying of data dictionary information to the restarted node has been completed.	Event Type. NodeRestart  Priority. 8
	Severity. INFO

Log Message. Node node_id: Node restart completed copy of distribution information	Event Name. NR_CopyDistr
<b>Description.</b> Copying of data distribution information to the	Event Type. NodeRestart
restarted node has been completed.	Priority. 8
	Severity. INFO
Log Message. Node node_id: Node restart starting to copy the fragments to Node node_id	Event Name. NR_CopyFragsStarted
<b>Description.</b> Copy of fragments to starting data node node_id has begun	Event Type. NodeRestart
	Priority. 8
	Severity. INFO
<pre>Log Message. Node node_id: Table ID = table_id, fragment ID = fragment_id have been</pre>	Event Name. NR_CopyFragDone
copied to Node node_id	Event Type. NodeRestart
<b>Description.</b> Fragment fragment_id from table	Priority. 10
table_id has been copied to data node node_id	Severity. INFO
Log Message. Node node_id: Node restart	Event Name.
completed copying the fragments to Node node_id	NR_CopyFragsCompleted
	Event Type. NodeRestart
<b>Description.</b> Copying of all table fragments to restarting data node <i>node_id</i> has been completed	Priority. 8
	Severity. INFO
Log Message. Any of the following:	Event Name. NodeFailCompleted
1. Node node_id: Node node1_id completed failure of Node node2_id	Event Type. NodeRestart
2. All nodes completed failure of Node node_id	Priority. 8
3. Node failure of node_idblock completed	Severity. ALERT
<b>Description.</b> One of the following (each corresponding to the same-numbered message listed above):	
Data node node1_id has detected the failure of data node node2_id	
All (remaining) data nodes have detected the failure of data node node_id	
3. The failure of data node <pre>node_id</pre> has been detected in the <pre>blockNDB</pre> kernel block, where block is 1 of <pre>DBDICT</pre> , <pre>DBDIH</pre> , or <pre>DBLQH</pre> ; for more information, see <pre>NDB</pre> Kernel <pre>Blocks</pre>	
Log Message. Node mgm_node_id: Node data_node_id has failed. The Node state at	Event Name. NODE_FAILREP
failure was state_code	Event Type. NodeRestart

**Description.** A data node has failed. Its state at the time of failure is described by an arbitration state code <code>state\_code</code>: possible state code values can be found in the file <code>include/kernel/signaldata/ArbitSignalData.hpp</code>.

Priority. 8

Severity. ALERT

Log Message. President restarts arbitration thread [state=state\_code] Of Prepare arbitrator node node\_id [ticket=ticket\_id] Of Receive arbitrator node node\_id [ticket=ticket\_id] Of Started arbitrator node node\_id [ticket=ticket\_id] Of Lost arbitrator node node\_id - process failure [state=state\_code] Of Lost arbitrator node node\_id - process exit [state=state\_code] Of Lost arbitrator node node\_id - error\_message [state=state\_code]

Event Name. ArbitState

Event Type. NodeRestart

**Priority.** 6

Severity. INFO

**Description.** This is a report on the current state and progress of arbitration in the cluster.  $node\_id$  is the node ID of the management node or SQL node selected as the arbitrator.  $state\_code$  is an arbitration state code, as found in include/kernel/signaldata/ArbitSignalData.hpp. When an error has occurred, an  $error\_message$ , also defined in ArbitSignalData.hpp, is provided.  $ticket\_id$  is a unique identifier handed out by the arbitrator when it is selected to all the nodes that participated in its selection; this is used to ensure that each node requesting arbitration was one of the nodes that took part in the selection process.

Log Message. Arbitration check lost - less than 1/2 nodes left Or Arbitration check won - all node groups and more than 1/2 nodes left Or Arbitration check won - node group majority Or Arbitration check lost - missing node group Or Network partitioning - arbitration required Or Arbitration won - positive reply from node node\_id Or Arbitration lost - negative reply from node node\_id Or Network partitioning - no arbitrator available Or Network partitioning - no arbitrator configured Or Arbitration failure - error\_message [state=state\_code]

**Event Name.** ArbitResult

**Event Type.** NodeRestart

Priority. 2

Severity. ALERT

**Description.** This message reports on the result of arbitration. In the event of arbitration failure, an *error\_message* and an arbitration *state\_code* are provided; definitions for both of these are found in include/kernel/signaldata/ArbitSignalData.hpp.

Log Message. Node node\_id: GCP Take over
started

**Description.** This node is attempting to assume responsibility for the next global checkpoint (that is, it is becoming the master node)

**Event Name.** 

GCP\_TakeoverStarted

Event Type. NodeRestart

Priority. 7

Severity. INFO

Log Message. Node node_id: GCP Take over	Event Name.
completed	GCP_TakeoverCompleted
<b>Description.</b> This node has become the master, and has assumed responsibility for the next global checkpoint	Event Type. NodeRestart
	Priority. 7
	Severity. INFO
Log Message. Node node_id: LCP Take over	Event Name.
started	LCP_TakeoverStarted
<b>Description.</b> This node is attempting to assume responsibility for the next set of local checkpoints (that is, it is	Event Type. NodeRestart
becoming the master node)	Priority. 7
	Severity. INFO
Log Message. Node node_id: LCP Take over	Event Name.
completed	LCP_TakeoverCompleted
<b>Description.</b> This node has become the master, and has assumed responsibility for the next set of local checkpoints	Event Type. NodeRestart
	Priority. 7
	Severity. INFO
Log Message. Node node_id: Trans. Count	Event Name.
= transactions, Commit Count = commits, Read Count = reads, Simple Read Count	TransReportCounters
= simple_reads, Write Count = writes,	Event Type. Statistic
AttrInfo Count = AttrInfo_objects, Concurrent Operations = concurrent_operations, Abort	Priority. 8
Count = aborts, Scans = scans, Range scans = range_scans	Severity. INFO
<b>Description.</b> This report of transaction activity is given approximately once every 10 seconds	
Log Message. Node node_id:	Event Name.
Operations=operations	OperationReportCounters
<b>Description.</b> Number of operations performed by this node, provided approximately once every 10 seconds	Event Type. Statistic
provided approximately office every to seconds	Priority. 8
	Severity. INFO
Log Message. Node node_id: Table with ID = table_id created	Event Name. TableCreated
Description A table boying the table ID shows has been	Event Type. Statistic
<b>Description.</b> A table having the table ID shown has been created	Priority. 7
	Severity. INFO
Log Message. Node node_id: Mean loop Counter in doJob last 8192 times = count	Event Name. JobStatistic
	Event Type. Statistic

	Priority. 9
	Severity. INFO
Log Message. Mean send size to Node = node_id last 4096 sends = bytes bytes	Event Name. SendBytesStatistic
<b>Description.</b> This node is sending an average of <i>bytes</i> bytes per send to node <i>node_id</i>	Event Type. Statistic  Priority. 9
bytes per seria to node node_ra	Severity. INFO
Log Message. Mean receive size to Node =	Event Name.
<pre>node_id last 4096 sends = bytes bytes</pre>	ReceiveBytesStatistic
<b>Description.</b> This node is receiving an average of <i>bytes</i> of data each time it receives data from node <i>node_id</i>	
	Priority. 9
	Severity. INFO
Log Message. Node node_id: Data usage is	Event Name. MemoryUsage
<pre>data_memory_percentage% (data_pages_used 32K pages of total data_pages_total)/Node node_id: Index usage is index_memory_percentage%</pre>	Event Type. Statistic
(index_pages_used 8K pages of total	Priority. 5
<pre>index_pages_total)</pre>	Severity. INFO
<b>Description.</b> This report is generated when a DUMP 1000 command is issued in the cluster management client; for more information, see DUMP 1000, in MySQL Cluster Internals	
Log Message. Node node1_id: Transporter to node node2_id reported error error_code:	Event Name. TransporterError
error_message	Event Type. Error
<b>Description.</b> A transporter error occurred while	Priority. 2
communicating with node $node2\_id$ ; for a listing of transporter error codes and messages, see NDB Transporter Errors, in MySQL Cluster Internals	Severity. ERROR
Log Message. Node node1_id: Transporter to	Event Name. TransporterWarning
<pre>node node2_id reported error error_code: error_message</pre>	Event Type. Error
<b>Description.</b> A warning of a potential transporter problem	Priority. 8
while communicating with node <i>node2_id</i> ; for a listing of transporter error codes and messages, see NDB Transporter Errors, for more information	Severity. WARNING
Log Message. Node node1_id: Node node2_id	Event Name. MissedHeartbeat
missed heartbeat heartbeat_id	Event Type. Error
<b>Description.</b> This node missed a heartbeat from node node2_id	Priority. 8
	Severity. WARNING
Log Message. Node node1_id: Node node2_id	Event Name. DeadDueToHeartbeat
declared dead due to missed heartbeat	

user mode, Node node_id: Entered single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Event Type. Info  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Name. BackupCompleted  Event Name. BackupCompleted  Event Name. BackupCompleted	<b>Description.</b> This node has missed at least 3 heartbeats	Event Type. Error
Log Message. Node node _ id: Node Sent Heartbeat to node = node2_id  Description. This node has sent a heartbeat to node node2_id  Description. This node has sent a heartbeat to node node2_id  Log Message. Node node_id: Event	from node node2_1d, and so has declared that node "dead"	Priority. 8
Description. This node has sent a heartbeat to node node2_id  Description. This node has sent a heartbeat to node node2_id  Description. This node has sent a heartbeat to node node2_id  Description. This node has sent a heartbeat to node node2_id: Event buffer status: used=bytes_used (percent_used\$) alloc=bytes_allocated (percent_available\$) max=bytes_available apply_goi=latest_restorable_GCT latest_goi=latest_gcI  Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entered single user mode Node node_id: Entering single user mode Node node_id: Entering single user mode Node node_id: Entering single user mode node_id: Entering single user mode node_id: Entering single user mode node_id: Event Type. Info  Priority. 7  Severity. INFO  Event Name. SingleUser Event Type. Info Priority. 7  Severity. INFO  Priority. 7  Severity. INFO  Event Name. SingleUser Event Type. Info Priority. 7  Severity. INFO  Event Name. SingleUser Event Type. Info Priority. 7  Severity. INFO  Event Name. SangleUser Event Type. Info Priority. 7  Severity. INFO  Event Name. SangleUser Event Type. Info Priority. 7  Severity. INFO  Event Name. BackupStarted Event Type. Backup Priority. 7  Severity. INFO  Event Name. BackupStarted Event Type. Backup Priority. 7  Severity. INFO  Event Name. BackupStarted Event Type. Backup Priority. 7  Severity. INFO  Event Name. BackupStarted Event Type. Backup Priority. 7  Event Name. BackupCompleted Event Name. BackupCompleted Event Name. BackupCompleted Event Name. BackupCompleted Event Type. Backup Priority. 7  Event Name. BackupCompleted Event Name. Back		Severity. ALERT
Description. This node has sent a heartbeat to node node2_id   Log Message. Node node_id: Event buffer status! used=bytes_used (percent_used*) alloc=bytes_allocated (percent_used*) alloc=bytes_allocated (percent_available*) max=bytes_available apply_gci=latest_restorable_gCT latest_gci=latest_restorable_gCT latest_gci=latest_gci = latest_gci	_	Event Name. SentHeartbeat
Priority. 12   Severity. INFO	<b>Description</b> This node has sent a heartheat to node	Event Type. Info
Log Message. Node node_id: Event buffer status: used=bytes_used (percent_used*) alloc=bytes_allocated (percent_available*) max=bytes_available apply_gci=latest_restorable_GCT latest_gci=latest_restorable_GCT  Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode, Node node_id Entering single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode]; the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup'  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_cp #Records: records #LogRecords: log_records  Event Name. EventBufferStatus  Event Type. Info  Priority. 7  Severity. INFO  Event Name. EventBufferStatus  Event Name. EventBufferStatus  Event Name. EventBufferStatus  Event Name.  Event Name. EventBufferStatus  Event Name.  Event Name.  Event Name.  Event Name.  Event Name.  Event Type.  Info  Priority. 7  Severity. INFO  Event Name.  Eve	·	Priority. 12
buffer status: used=bytes_used (percent_used%) alloc=bytes_allocated (percent_used%) alloc=bytes_allocated (percent_used%) alloc=bytes_allocated apply_gci=latest_restorable_GCT latest_gci=latest_GCT  Pescription. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode, Node node_id: Entering single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Percent_used%) alloc=bytes_allocated  Event Type. Info  Priority. 7  Severity. INFO  Priority. 7  Severity. Info  Priority. 7  Severity. Info  Priority. 7  Severity. Info  Event Name. SingleUser Event Type. Info  Priority. 7  Severity. INFO  Event Name. Backup  Event Name. Backup  Event Name. Backup  Event Na		Severity. INFO
(percent_used\( ) alloc=bytes_allocated (percent_available\( ) anx=bytes_available apply_gci=latest_restorable_GCI latest_gci=latest_gCI  Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed.  Sevent Type. Backup Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Name. BackupStarted  Event Type. Backup  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Type. Backup  Priority. 7  Severity. INFO		<b>Event Name.</b> EventBufferStatus
apply_gci=latest_restorable_GCT latest_gci=latest_gci latest_gci=latest_gci  Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode, Node node_id: Entering single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode, API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed.  Sevent Name. BackupCompleted Event Type. Backup  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Type. Backup  Priority. 7  Severity. INFO  Event Name. BackupCompleted  Event Type. Backup  Priority. 7  Severity. INFO	(percent_used%) alloc=bytes_allocated	Event Type. Info
Description. This report is seen during heavy event buffer usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode, Node node_id base exclusive access, Node node_id base exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed.  StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Name. BackupCompleted  Event Type. Backup  Priority. 7  Severity. INFO	apply_gci=latest_restorable_GCI	Priority. 7
usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest and latest restorable global checkpoints  Log Message. Node node_id: Entering single user mode, Node node_id has exclusive access, Node node_id has exclusive access, Node node_id: Entering single user mode node node_id: Section 7.8, "MySQL Cluster log when entering and exiting single user mode; API_node_id is indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup."  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed.  Event Name. SingleUser  Event Type. Info  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Name. BackupCompleted  Event Type. Backup  Priority. 7  Severity. INFO  Event Type. Backup  Priority. 7  Event Name. BackupCompleted	latest_gci=latest_GCI	Severity. INFO
user mode, Node node_id: Entered single user mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Event Type. Info  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Name. BackupCompleted  Event Name. BackupCompleted  Event Name. BackupCompleted  Event Type. Backup  Backup  Event Name. BackupCompleted	usage, for example, when many updates are being applied in a relatively short period of time; the report shows the number of bytes and the percentage of event buffer memory used, the bytes allocated and percentage still available, and the latest	
mode Node API_node_id has exclusive access, Node node_id: Entering single user mode  Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records    Event Type. Info   Priority. 7		Event Name. SingleUser
Description. These reports are written to the cluster log when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority. 7  Severity. INFO  Event Name. BackupStarted  Event Type. Backup  Event Name. BackupCompleted  Event Name. BackupCompleted  Event Name. BackupCompleted	mode Node API_node_id has exclusive access,	Event Type. Info
when entering and exiting single user mode; API_node_id is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message Unknown single user report API_node_id indicates an error has taken place and should never be seen in normal operation  Log Message. Node node_id: Backup backup_id started from node mgm_node_id  Description. A backup has been started using the management node having mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed.  StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Bioxibi. INFO  Event Name. BackupStarted  Event Type. Backup  Beverity.  Event Name. Backup Priority. 7  Severity.  Priority. 7		Priority. 7
Description. A backup has been started using the management node having mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Event Type. Backup  Event Type. Backup  Priority. 7  Severity. INFO	when entering and exiting single user mode; <code>API_node_id</code> is the node ID of the API or SQL having exclusive access to the cluster (for more information, see Section 7.8, "MySQL Cluster Single User Mode"); the message <code>Unknown single user report API_node_id</code> indicates an error has taken place	-
Description. A backup has been started using the management node having mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records    Event Type. Backup   Priority. 7		Event Name. BackupStarted
management node having mgm_node_id; this message is also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority. 7  Severity. INFO  Event Name. BackupCompleted  Event Type. Backup	started from node mgm_node_id	Event Type. Backup
also displayed in the cluster management client when the START BACKUP command is issued; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority. 7		Priority. 7
Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"  Log Message. Node node_id: Backup backup_id started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority 7	also displayed in the cluster management client when the	Savarity TVT0
started from node mgm_node_id completed. StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority 7	Section 7.3.2, "Using The MySQL Cluster Management Client	Seventy. INFO
StartGCP: start_gcp StopGCP: stop_gcp #Records: records #LogRecords: log_records  Priority 7		Event Name. BackupCompleted
Drianity 7	StartGCP: start_gcp StopGCP: stop_gcp	Event Type. Backup
Data: data_bytes bytes Log: log_bytes bytes   '''''''''''''''''''''''''''''''''''		Priority. 7
Severity. INFO		Severity. INFO

<b>Description.</b> The backup having the ID backup_id has been completed; for more information, see Section 7.3.2, "Using The MySQL Cluster Management Client to Create a Backup"	
Log Message. Node node_id: Backup request from	Event Name.
<pre>mgm_node_id failed to start. Error: error_code</pre>	BackupFailedToStart
<b>Description.</b> The backup failed to start; for error codes, see MGM API Errors	Event Type. Backup
	Priority. 7
	Severity. ALERT
Log Message. Node node_id: Backup backup_id started from mgm node id has been aborted.	Event Name. BackupAborted
Error: error_code	Event Type. Backup
<b>Description.</b> The backup was terminated after starting, possibly due to user intervention	Priority. 7
possibly due to user intervention	Severity. ALERT

# 7.7.2 MySQL Cluster: NDB Transporter Errors

This section lists error codes, names, and messages that are written to the cluster log in the event of transporter errors.

Error Code	Error Name	Error Text
0x00	TE_NO_ERROR	No error
0x01	TE_ERROR_CLOSING_SOCKET	Error found during closing of socket
0x02	TE_ERROR_IN_SELECT_BEFORE_ACCEPT	Error found before accept. The transporter will retry
0x03	TE_INVALID_MESSAGE_LENGTH	Error found in message (invalid message length)
0x04	TE_INVALID_CHECKSUM	Error found in message (checksum)
0x05	TE_COULD_NOT_CREATE_SOCKET	Error found while creating socket(can't create socket)
0x06	TE_COULD_NOT_BIND_SOCKET	Error found while binding server socket
0x07	TE_LISTEN_FAILED	Error found while listening to server socket
0x08	TE_ACCEPT_RETURN_ERROR	Error found during accept(accept return error)

## MySQL Cluster: NDB Transporter Errors

Error Code	Error Name	Error Text
0x0b	TE_SHM_DISCONNECT	The remote node has disconnected
0x0c	TE_SHM_IPC_STAT	Unable to check shm segment
0x0d	TE_SHM_UNABLE_TO_CREATE_SEGMENT	Unable to create shm segment
0x0e	TE_SHM_UNABLE_TO_ATTACH_SEGMENT	Unable to attach shm segment
0x0f	TE_SHM_UNABLE_TO_REMOVE_SEGMENT	Unable to remove shm segment
0x10	TE_TOO_SMALL_SIGID	Sig ID too small
0x11	TE_TOO_LARGE_SIGID	Sig ID too large
0x12	TE_WAIT_STACK_FULL	Wait stack was full
0x13	TE_RECEIVE_BUFFER_FULL	Receive buffer was full
0x14	TE_SIGNAL_LOST_SEND_BUFFER_FULL	Send buffer was full, and trying to force send fails
0x15	TE_SIGNAL_LOST	Send failed for unknown reason(signal lost)
0x16	TE_SEND_BUFFER_FULL	The send buffer was full, but sleeping for a while solved
0x0017	TE_SCI_LINK_ERROR	There is no link from this node to the switch
0x18	TE_SCI_UNABLE_TO_START_SEQUENCE	Could not start a sequence, because system resources are exumed or no sequence has been created
0x19	TE_SCI_UNABLE_TO_REMOVE_SEQUENCE	Could not remove a sequence
0x1a	TE_SCI_UNABLE_TO_CREATE_SEQUENCE	Could not create a sequence, because system resources are exempted. Must reboot
0x1b	TE_SCI_UNRECOVERABLE_DATA_TFX_ERROR	Tried to send data on redundant link but failed
0x1c	TE_SCI_CANNOT_INIT_LOCALSEGMENT	Cannot initialize local segment

Error Code	Error Name	Error Text
0x1d	TE_SCI_CANNOT_MAP_REMOTESEGMENT	Cannot map remote segment
0x1e	TE_SCI_UNABLE_TO_UNMAP_SEGMENT	Cannot free the resources used by this segment (step 1)
0x1f	TE_SCI_UNABLE_TO_REMOVE_SEGMENT	Cannot free the resources used by this segment (step 2)
0x20	TE_SCI_UNABLE_TO_DISCONNECT_SEGMENT	Cannot disconnect from a remote segment
0x21	TE_SHM_IPC_PERMANENT	Shm ipc Permanent error
0x22	TE_SCI_UNABLE_TO_CLOSE_CHANNEL	Unable to close the sci channel and the resources allocated

# 7.8 MySQL Cluster Single User Mode

<u>Single user mode</u> enables the database administrator to restrict access to the database system to a single API node, such as a MySQL server (SQL node) or an instance of ndb\_restore. When entering single user mode, connections to all other API nodes are closed gracefully and all running transactions are aborted. No new transactions are permitted to start.

Once the cluster has entered single user mode, only the designated API node is granted access to the database.

You can use the ALL STATUS command in the ndb\_mgm client to see when the cluster has entered single user mode. Beginning with MySQL Cluster NDB 7.1.1, you can also check the status column of the ndbinfo.nodes table (see Section 7.10.13, "The ndbinfo nodes Table", for more information).

#### Example:

```
ndb_mgm> ENTER SINGLE USER MODE 5
```

After this command has executed and the cluster has entered single user mode, the API node whose node ID is 5 becomes the cluster's only permitted user.

The node specified in the preceding command must be an API node; attempting to specify any other type of node will be rejected.

#### Note

When the preceding command is invoked, all transactions running on the designated node are aborted, the connection is closed, and the server must be restarted.

The command EXIT SINGLE USER MODE changes the state of the cluster's data nodes from single user mode to normal mode. API nodes—such as MySQL Servers—waiting for a connection (that is, waiting for the cluster to become ready and available), are again permitted to connect. The API node denoted as the single-user node continues to run (if still connected) during and after the state change.

#### Example:

```
ndb_mgm> EXIT SINGLE USER MODE
```

There are two recommended ways to handle a node failure when running in single user mode:

- Method 1:
  - 1. Finish all single user mode transactions
  - 2. Issue the EXIT SINGLE USER MODE command
  - Restart the cluster's data nodes
- Method 2:

Restart database nodes prior to entering single user mode.

# 7.9 Quick Reference: MySQL Cluster SQL Statements

This section discusses several SQL statements that can prove useful in managing and monitoring a MySQL server that is connected to a MySQL Cluster, and in some cases provide information about the cluster itself.

• SHOW ENGINE NDB STATUS, SHOW ENGINE NDBCLUSTER STATUS

The output of this statement contains information about the server's connection to the cluster, creation and usage of MySQL Cluster objects, and binary logging for MySQL Cluster replication.

See **SHOW ENGINE** Syntax, for a usage example and more detailed information.

• SHOW ENGINES

This statement can be used to determine whether or not clustering support is enabled in the MySQL server, and if so, whether it is active.

See **SHOW ENGINES** Syntax, for more detailed information.

#### Note

In MySQL 5.1 and later, this statement does not support a LIKE clause. However, you can use LIKE to filter queries against the INFORMATION\_SCHEMA.ENGINES table, as discussed in the next item.

• SELECT \* FROM INFORMATION\_SCHEMA.ENGINES [WHERE ENGINE LIKE 'NDB%']

This is the equivalent of SHOW ENGINES, but uses the ENGINES table of the INFORMATION\_SCHEMA database (available beginning with MySQL 5.1.5). Unlike the case with the SHOW ENGINES statement, it is possible to filter the results using a LIKE clause, and to select specific columns to obtain information that may be of use in scripts. For example, the following query shows whether the server was built with NDB support and, if so, whether it is enabled:

```
mysql> SELECT SUPPORT FROM INFORMATION_SCHEMA.ENGINES
-> WHERE ENGINE LIKE 'NDB%';
+-----+
```

```
| support |
+-----+
| ENABLED |
+-----+
```

See The INFORMATION\_SCHEMA ENGINES Table, for more information.

• SHOW VARIABLES LIKE 'NDB%'

This statement provides a list of most server system variables relating to the NDB storage engine, and their values, as shown here:

See Server System Variables, for more information.

 SELECT \* FROM INFORMATION\_SCHEMA.GLOBAL\_VARIABLES WHERE VARIABLE\_NAME LIKE 'NDB%';

This statement is the equivalent of the SHOW command described in the previous item, and provides almost identical output, as shown here:

```
mysql> SELECT * FROM INFORMATION_SCHEMA.GLOBAL_VARIABLES
  -> WHERE VARIABLE_NAME LIKE 'NDB%';
----+
 NDB_AUTOINCREMENT_PREFETCH_SZ | 32
 NDB_CACHE_CHECK_TIME
 NDB_EXTRA_LOGGING
                                    0
 NDB_FORCE_SEND
 NDB_FORCE_SEND | ON NDB_INDEX_STAT_CACHE_ENTRIES | 32
                                   OFF
 NDB_INDEX_STAT_ENABLE
                          ) | OF1
 NDB_INDEX_STAT_UPDATE_FREQ
 NDB_REPORT_THRESH_BINLOG_EPOCH_SLIP | 3
 NDB_REPORT_THRESH_BINLOG_MEM_USAGE | 10
NDB_USE_COPYING_ALTER_TABLE | OFF
NDB_USE_EXACT_COUNT | ON
NDB_USE_TRANSACTIONS | ON
```

Unlike the case with the SHOW command, it is possible to select individual columns. For example:

```
mysql> SELECT VARIABLE_VALUE
-> FROM INFORMATION_SCHEMA.GLOBAL_VARIABLES
-> WHERE VARIABLE_NAME = 'ndb_force_send';
```

See The INFORMATION\_SCHEMA GLOBAL\_VARIABLES and SESSION\_VARIABLES Tables, and Server System Variables, for more information.

SHOW STATUS LIKE 'NDB%'

This statement shows at a glance whether or not the MySQL server is acting as a cluster SQL node, and if so, it provides the MySQL server's cluster node ID, the host name and port for the cluster management server to which it is connected, and the number of data nodes in the cluster, as shown here:

If the MySQL server was built with clustering support, but it is not connected to a cluster, all rows in the output of this statement contain a zero or an empty string:

See also SHOW STATUS Syntax.

SELECT \* FROM INFORMATION\_SCHEMA.GLOBAL\_STATUS WHERE VARIABLE\_NAME LIKE 'NDB %';

Beginning with MySQL 5.1.12, this statement provides similar output to the SHOW command discussed in the previous item. However, unlike the case with SHOW STATUS, it is possible using the SELECT to extract values in SQL for use in scripts for monitoring and automation purposes.

See The INFORMATION\_SCHEMA GLOBAL\_STATUS and SESSION\_STATUS Tables, for more information.

Beginning with MySQL Cluster NDB 7.1.1, you can also query the tables in the ndbinfo information database for real-time data about many MySQL Cluster operations. See Section 7.10, "The ndbinfo MySQL Cluster Information Database".

# 7.10 The ndbinfo MySQL Cluster Information Database

ndbinfo is a database storing containing information specific to MySQL Cluster, available beginning with MySQL Cluster NDB 7.1.1.

This database contains a number of tables, each providing a different sort of data about MySQL Cluster node status, resource usage, and operations. You can find more detailed information about each of these tables in the next several sections.

ndbinfo is included with MySQL Cluster support in the MySQL Server; no special compilation or configuration steps are required; the tables are created by the MySQL Server when it connects to the cluster. You can verify that ndbinfo support is active in a given MySQL Server instance using SHOW PLUGINS; if ndbinfo support is enabled, you should see a row containing ndbinfo in the Name column and ACTIVE in the Status column, as shown here (emphasized text):

Name	Status	Type	Library	License
binlog	ACTIVE	STORAGE ENGINE	NULL	GPL
partition	ACTIVE	STORAGE ENGINE	NULL	GPL
ARCHIVE	ACTIVE	STORAGE ENGINE	NULL	GPL
BLACKHOLE	ACTIVE	STORAGE ENGINE	NULL	GPL
CSV	ACTIVE	STORAGE ENGINE	NULL	GPL
FEDERATED	DISABLED	STORAGE ENGINE	NULL	GPL
MEMORY	ACTIVE	STORAGE ENGINE	NULL	GPL
InnoDB	ACTIVE	STORAGE ENGINE	NULL	GPL
MyISAM	ACTIVE	STORAGE ENGINE	NULL	GPL
MRG_MYISAM	ACTIVE	STORAGE ENGINE	NULL	GPL
ndbcluster	ACTIVE	STORAGE ENGINE	NULL	GPL
ndbinfo	ACTIVE	STORAGE ENGINE	/ NULL	GPL

You can also do this by checking the output of SHOW ENGINES for a row that has ndbinfo for Engine and YES for Support, as shown here (emphasized text):

```
mysql> SHOW ENGINES\G
     ****************** 1. row ****************
    Engine: ndbcluster
    Support: YES
    Comment: Clustered, fault-tolerant tables
Transactions: YES
       XA: NO
 Savepoints: NO
************************* 2. row ******************
    Engine: MRG_MYISAM
    Support: YES
   Comment: Collection of identical MyISAM tables
Transactions: NO
       XA: NO
 Savepoints: NO
Engine: ndbinfo
   Support: YES
   Comment: MySQL Cluster system information storage engine
Transactions: NO
        XA: NO
 Savepoints: NO
************************** 4. row *******************
    Engine: CSV
    Support: YES
   Comment: CSV storage engine
Transactions: NO
        XA: NO
 Savepoints: NO
 ******************* 5. row ****************
    Engine: MEMORY
```

```
Support: YES
   Comment: Hash based, stored in memory, useful for temporary tables
Transactions: NO
       XA: NO
 Savepoints: NO
*********************** 6. row *****************
    Engine: FEDERATED
   Support: NO
   Comment: Federated MySQL storage engine
Transactions: NULL
       XA: NULL
 Savepoints: NULL
Engine: ARCHIVE
    Support: YES
   Comment: Archive storage engine
Transactions: NO
       XA: NO
 Savepoints: NO
Engine: InnoDB
   Support: YES
   Comment: Supports transactions, row-level locking, and foreign keys
Transactions: YES
       XA: YES
 Savepoints: YES
            ******** 9. row ****************
    Engine: MyISAM
   Support: DEFAULT
   Comment: Default engine as of MySQL 3.23 with great performance
Transactions: NO
       XA: NO
 Savepoints: NO
*********************** 10. row ****************
    Engine: BLACKHOLE
   Support: YES
   Comment: /dev/null storage engine (anything you write to it disappears)
Transactions: NO
       XA: NO
 Savepoints: NO
10 rows in set (0.00 sec)
```

If ndbinfo support is enabled, then you can access ndbinfo using SQL statements in mysql or another MySQL client. For example, you can see ndbinfo listed in the output of SHOW DATABASES, as shown here:

If the mysqld process was not started with the --ndbcluster option, ndbinfo is not available and is not displayed by SHOW DATABASES. If mysqld was formerly connected to a MySQL Cluster but the cluster becomes unavailable (due to events such as cluster shutdown, loss of network connectivity, and so forth), ndbinfo and its tables remain visible, but an attempt to access any tables (other than blocks or config\_params) fails with Got error 157 'Connection to NDB failed' from NDBINFO.

With the exception of the blocks and config\_params tables, what we refer to as ndbinfo "tables" are actually views generated from internal NDB tables not normally visible to the MySQL Server.

All ndbinfo tables are read-only, and are generated on demand when queried. Because many of them are generated in parallel by the data nodes while other are specific to a given SQL node, they are not guaranteed to provide a consistent snapshot.

In addition, pushing down of joins is not supported on ndbinfo tables; so joining large ndbinfo tables can require transfer of a large amount of data to the requesting API node, even when the query makes use of a WHERE clause.

Beginning with MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11, ndbinfo tables are not included in the query cache. (Bug #59831)

You can select the ndbinfo database with a USE statement, and then issue a SHOW TABLES statement to obtain a list of tables, just as for any other database, like this:

```
mysql> USE ndbinfo;
Database changed
mysql> SHOW TABLES;
 Tables_in_ndbinfo
 blocks
 cluster_operations
 cluster transactions
 config_params
 counters
 diskpagebuffer
 logbuffers
 logspaces
 memoryusage
 nodes
 resources
 server_operations
 server_transactions
 threadblocks
 threadstat
 transporters
16 rows in set (0.04 sec)
```

The diskpagebuffer table was added in MySQL Cluster NDB 7.1.9.

The cluster\_operations, cluster\_transactions, server\_operations, server\_transactions, threadblocks, and threadstat tables were added in MySQL Cluster NDB 7.1.17.

In early versions of MySQL Cluster NDB 7.1, there was an additional pools table in the ndbinfo database; however, this table was removed in MySQL Cluster NDB 7.1.3.

You can execute SELECT statements against these tables, just as you would normally expect:

mysql> SELECT * FROM memoryusage;					
node_id   memory_type	used	used_pages	total	total_pages	
5   Data memory   5   Index memory	753664 163840	23   20	1073741824 1074003968	32768     131104	

5   Long message buffer	2304	9   67108864	262144	
6   Data memory	753664	23   1073741824	32768	
6   Index memory	163840	20   1074003968	131104	
6   Long message buffer	2304	9   67108864	262144	
++ 6 rows in set (0.02 sec)				

More complex queries, such as the two following SELECT statements using the memoryusage table, are possible:

ndbinfo table and column names are case sensitive (as is the name of the ndbinfo database itself). These identifiers are in lowercase. Trying to use the wrong lettercase results in an error, as shown in this example:

```
mysql> SELECT * FROM nodes;
+-----+
| node_id | uptime | status | start_phase |
+-----+
| 1 | 13602 | STARTED | 0 |
| 2 | 16 | STARTED | 0 |
+-----+
2 rows in set (0.04 sec)
mysql> SELECT * FROM Nodes;
ERROR 1146 (42S02): Table 'ndbinfo.Nodes' doesn't exist
```

Beginning with MySQL Cluster NDB 7.1.7, mysqldump ignores ndbinfo entirely, and excludes it from any output. This is true even when using the --databases or --all-databases option.

MySQL Cluster also maintains tables in the INFORMATION\_SCHEMA information database, including the FILES table which contains information about files used for MySQL Cluster Disk Data storage. For more information, see INFORMATION\_SCHEMA Tables for MySQL Cluster.

# 7.10.1 The ndbinfo arbitrator\_validity\_detail Table

The arbitrator\_validity\_detail table shows the view that each data node in the cluster of the arbitrator. It is a subset of the membership table.

The following table provides information about the columns in the arbitrator\_validity\_detail table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	This node's node ID
arbitrator	integer	Node ID of arbitrator
arb_ticket	string	Internal identifier used to track arbitration
arb_connected	Yes <b>or</b> No	Whether this node is connected to the arbitrator
arb_state	Enumeration (see text)	Arbitration state

The node ID is the same as that reported by ndb\_mgm -e "SHOW".

All nodes should show the same arbitrator and arb\_ticket values as well as the same arb\_state value. Possible arb\_state values are ARBIT\_NULL, ARBIT\_INIT, ARBIT\_FIND, ARBIT\_PREP1, ARBIT\_PREP2, ARBIT\_START, ARBIT\_RUN, ARBIT\_CHOOSE, ARBIT\_CRASH, and UNKNOWN.

arb\_connected shows whether the current node is connected to the arbitrator.

Like the membership and arbitrator\_validity\_summary tables, this table was added in MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26.

## 7.10.2 The ndbinfo arbitrator\_validity\_summary Table

The arbitrator\_validity\_summary table provides a composite view of the arbitrator with regard to the cluster's data nodes.

The following table provides information about the columns in the arbitrator\_validity\_summary table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
arbitrator	integer	Node ID of arbitrator
arb_ticket	string	Internal identifier used to track arbitration
arb_connected	Yes <b>or</b> No	Whether this arbitrator is connected to the cluster
consensus_count	integer	Number of data nodes that see this node as arbitrator

In normal operations, this table should have only 1 row for any appreciable length of time. If it has more than 1 row for longer than a few moments, then either not all nodes are connected to the arbitrator, or all nodes are connected, but do not agree on the same arbitrator.

The arbitrator column shows the arbitrator's node ID.

arb\_ticket is the internal identifier used by this arbitrator.

arb connected shows whether this node is connected to the cluster as an arbitrator.

Like the membership and arbitrator\_validity\_detail tables, this table was added in MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26.

#### 7.10.3 The ndbinfo blocks Table

The blocks table is a static table which simply contains the names and internal IDs of all NDB kernel blocks (see NDB Kernel Blocks). It is for use by the other ndbinfo tables (most of which are actually views) in mapping block numbers to block names for producing human-readable output.

The following table provides information about the columns in the blocks table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
block_number	integer	Block number
block_name	string	Block name

To obtain a list of all block names, simply execute SELECT block\_name FROM ndbinfo.blocks. Although this is a static table, its content can vary between different MySQL Cluster releases.

### 7.10.4 The ndbinfo cluster\_operations Table

The cluster\_operations table provides a per-operation (stateful primary key op) view of all activity in the MySQL Cluster from the point of view of the local data management (LQH) blocks (see The DBLQH Block).

The following table provides information about the columns in the cluster\_operations table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	Node ID of reporting LQH block
block_instance	integer	LQH block instance
transid	integer	Transaction ID
operation_type	string	Operation type (see text for possible values)
state	string	Operation state (see text for possible values)
tableid	integer	Table ID
fragmentid	integer	Fragment ID
client_node_id	integer	Client node ID
client_block_ref	integer	Client block reference
tc_node_id	integer	Transaction coordinator node ID
tc_block_no	integer	Transaction coordinator block number
tc_block_instance	integer	Transaction coordinator block instance

The transaction ID is a unique 64-bit number which can be obtained using the NDB API's getTransactionId() method. (Currently, the MySQL Server does not expose the NDB API transaction ID of an ongoing transaction.)

The operation\_type column can take any one of the values READ, READ-SH, READ-EX, INSERT, UPDATE, DELETE, WRITE, UNLOCK, REFRESH, SCAN, SCAN-SH, SCAN-EX, Or <unknown>.

The state column can have any one of the values ABORT\_QUEUED, ABORT\_STOPPED, COMMITTED, COMMIT\_QUEUED, COMMIT\_STOPPED, COPY\_CLOSE\_STOPPED,

COPY\_FIRST\_STOPPED, COPY\_STOPPED, COPY\_TUPKEY, IDLE, LOG\_ABORT\_QUEUED, LOG\_COMMIT\_QUEUED, LOG\_COMMIT\_QUEUED\_WAIT\_SIGNAL, LOG\_COMMIT\_WRITTEN, LOG\_COMMIT\_WRITTEN, LOG\_COMMIT\_WRITTEN\_WAIT\_SIGNAL, LOG\_QUEUED, PREPARED, PREPARED\_RECEIVED\_COMMIT, SCAN\_CHECK\_STOPPED, SCAN\_CLOSE\_STOPPED, SCAN\_FIRST\_STOPPED, SCAN\_RELEASE\_STOPPED, SCAN\_STATE\_USED, SCAN\_STOPPED, SCAN\_TUPKEY, STOPPED, TC\_NOT\_CONNECTED, WAIT\_ACC, WAIT\_ACC\_ABORT, WAIT\_AI\_AFTER\_ABORT, WAIT\_ATTR, WAIT\_SCAN\_AI, WAIT\_TUP, WAIT\_TUPKEYINFO, WAIT\_TUP\_COMMIT, or WAIT\_TUP\_TO\_ABORT. (If the MySQL Server is running with ndbinfo\_show\_hidden enabled, you can view this list of states by selecting from the ndb \$dblqh\_tcconnect\_state table, which is normally hidden.)

You can obtain the name of an NDB table from its table ID by checking the output of ndb\_show\_tables.

The fragid is the same as the partition number seen in the output of ndb\_desc --extra-partition-info (short form -p).

In client\_node\_id and client\_block\_ref, client refers to a MySQL Cluster API or SQL node (that is, an NDB API client or a MySQL Server attached to the cluster).

This table was added in MySQL Cluster NDB 7.1.17.

### 7.10.5 The ndbinfo cluster\_transactions Table

The cluster\_transactions table shows information about all ongoing transactions in a MySQL Cluster.

The following table provides information about the columns in the cluster\_transactions table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	Node ID of transaction coordinator
block_instance	integer	TC block instance
transid	integer	Transaction ID
state	string	Operation state (see text for possible values)
count_operations	integer	Number of stateful primary key operations in transaction (includes reads with locks, as well as DML operations)
outstanding_operations	integer	Operations still being executed in local data management blocks
inactive_seconds	integer	Time spent waiting for API
client_node_id	integer	Client node ID
client_block_ref	integer	Client block reference

The transaction ID is a unique 64-bit number which can be obtained using the NDB API's getTransactionId() method. (Currently, the MySQL Server does not expose the NDB API transaction ID of an ongoing transaction.)

The state column can have any one of the values CS\_ABORTING, CS\_COMMITTING, CS\_COMMIT\_SENT, CS\_COMPLETE\_SENT, CS\_COMPLETING, CS\_CONNECTED, CS\_DISCONNECTED, CS\_FAIL\_ABORTED, CS\_FAIL\_ABORTING, CS\_FAIL\_COMMITTED, CS\_FAIL\_COMMITTING, CS\_FAIL\_COMPLETED,

CS\_FAIL\_PREPARED, CS\_PREPARE\_TO\_COMMIT, CS\_RECEIVING, CS\_REC\_COMMITTING, CS\_RESTART, CS\_SEND\_FIRE\_TRIG\_REQ, CS\_STARTED, CS\_START\_COMMITTING, CS\_START\_SCAN, CS\_WAIT\_ABORT\_CONF, CS\_WAIT\_COMMIT\_CONF, CS\_WAIT\_COMPLETE\_CONF, CS\_WAIT\_FIRE\_TRIG\_REQ. (If the MySQL Server is running with ndbinfo\_show\_hidden enabled, you can view this list of states by selecting from the ndb\$dbtc\_apiconnect\_state table, which is normally hidden.)

In client\_node\_id and client\_block\_ref, client refers to a MySQL Cluster API or SQL node (that is, an NDB API client or a MySQL Server attached to the cluster).

This table was added in MySQL Cluster NDB 7.1.17.

## 7.10.6 The ndbinfo config\_params Table

The config\_params table is a static table which provides the names and internal ID numbers of all MySQL Cluster configuration parameters.

The following table provides information about the columns in the config\_params table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
param_number	integer	The parameter's internal ID number
param_name	string	The name of the parameter

Although this is a static table, its content can vary between MySQL Cluster installations, since supported parameters can vary due to differences between software releases, cluster hardware configurations, and other factors.

### 7.10.7 The ndbinfo counters Table

The counters table provides running totals of events such as reads and writes for specific kernel blocks and data nodes. Counts are kept from the most recent node start or restart; a node start or restart resets all counters on that node. Not all kernel blocks have all types of counters.

The following table provides information about the columns in the counters table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The data node ID
block_name	string	Name of the associated NDB kernel block (see NDB Kernel Blocks).
block_instance	integer	Block instance
counter_id	integer	The counter's internal ID number; normally an integer between 1 and 10, inclusive.
counter_name	string	The name of the counter. See text for names of individual counters and the NDB kernel block with which each counter is associated.

Column Name	Туре	Description
val	integer	The counter's value

Each counter is associated with a particular NDB kernel block. Prior to MySQL Cluster NDB 7.2.0, this was limited to either the DBLQH kernel block or the DBTC kernel block.

The OPERATIONS counter is associated with the DBLQH (local query handler) kernel block (see The DBLQH Block).

The ATTRINFO, TRANSACTIONS, COMMITS, READS, SIMPLE\_READS, WRITES, ABORTS, TABLE\_SCANS, and RANGE\_SCANS counters are associated with the DBTC (transaction co-ordinator) kernel block (see The DBTC Block).

MySQL Cluster NDB 7.2.0, as part of its implementation of distributed pushed-down joins, adds the Local\_table\_scans\_sent, reads\_received, pruned\_range\_scans\_received, range\_scans\_received, Local\_reads\_sent, const\_pruned\_range\_scans\_received, Local\_range\_scans\_sent, remote\_reads\_sent, remote\_range\_scans\_sent, reads\_not\_found, scan\_batches\_returned, table\_scans\_received, and scan\_rows\_returned counters. These counters are associated with the dbspj (select push-down join) kernel block (see The dbspj Block).

A number of counters increasing the visibility of transporter overload and send buffer sizing when troubleshooting such issues were added in MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26. (Bug #15935206) For each LQH instance, there is one instance of each counter in the following list:

- LQHKEY\_OVERLOAD: Number of primary key requests rejected at the LQH block instance due to transporter overload
- LQHKEY\_OVERLOAD\_TC: Count of instances of LQHKEY\_OVERLOAD where the TC node transporter was overloaded
- LQHKEY\_OVERLOAD\_READER: Count of instances of LQHKEY\_OVERLOAD where the API reader (reads only) node was overloaded.
- LQHKEY\_OVERLOAD\_NODE\_PEER: Count of instances of LQHKEY\_OVERLOAD where the next backup data node (writes only) was overloaded
- LQHKEY\_OVERLOAD\_SUBSCRIBER: Count of instances of LQHKEY\_OVERLOAD where a event subscriber (writes only) was overloaded.
- LQHSCAN\_SLOWDOWNS: Count of instances where a fragment scan batch size was reduced due to scanning API transporter overload.

# 7.10.8 The ndbinfo diskpagebuffer Table

The diskpagebuffer table provides statistics about disk page buffer usage by MySQL Cluster Disk Data tables.

The following table provides information about the columns in the diskpagebuffer table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The data node ID
block_instance	integer	Block instance

Column Name	Туре	Description
pages_written	integer	Number of pages written to disk.
pages_written_lcp	integer	Number of pages written by local checkpoints.
pages_read	integer	Number of pages read from disk
log_waits	integer	Number of page writes waiting for log to be written to disk
page_requests_direct_return	integer	Number of requests for pages that were available in buffer
page_requests_wait_queue	integer	Number of requests that had to wait for pages to become available in buffer
page_requests_wait_io	integer	Number of requests that had to be read from pages on disk (pages were unavailable in buffer)

You can use this table with MySQL Cluster Disk Data tables to determine whether DiskPageBufferMemory is sufficiently large to allow data to be read from the buffer rather from disk; minimizing disk seeks can help improve performance of such tables.

You can determine the proportion of reads from <code>DiskPageBufferMemory</code> to the total number of reads using a query such as this one, which obtains this ratio as a percentage:

```
SELECT
  node_id,
  100 * page_requests_direct_return /
     (page_requests_direct_return + page_requests_wait_io)
     AS hit_ratio
FROM ndbinfo.diskpagebuffer;
```

The result from this query should be similar to what is shown here, with one row for each data node in the cluster (in this example, the cluster has 4 data nodes):

```
+-----+
| node_id | hit_ratio |
+------+
| 5 | 97.6744 |
| 6 | 97.6879 |
| 7 | 98.1776 |
| 8 | 98.1343 |
+------+
4 rows in set (0.00 sec)
```

hit\_ratio values approaching 100% indicate that only a very small number of reads are being made from disk rather than from the buffer, which means that Disk Data read performance is approaching an optimum level. If any of these values are less than 95%, this is a strong indicator that the setting for <code>DiskPageBufferMemory</code> needs to be increased in the <code>config.ini</code> file.

#### Note

A change in DiskPageBufferMemory requires a rolling restart of all of the cluster's data nodes before it takes effect.

# 7.10.9 The ndbinfo logbuffers Table

The logbuffer table provides information on MySQL Cluster log buffer usage.

The following table provides information about the columns in the logbuffers table. For each column, the table shows the name, data type, and a brief description.

Column Name	Туре	Description
node_id	integer	The ID of this data node.
log_type	string	Type of log; one of: REDO or DD-UNDO.
log_id	integer	The log ID.
log_part	integer	The log part number.
total	integer	Total space available for this log.
used	integer	Space used by this log.

## 7.10.10 The ndbinfo logspaces Table

This table provides information about MySQL Cluster log space usage.

The following table provides information about the columns in the logspaces table. For each column, the table shows the name, data type, and a brief description.

Column Name	Туре	Description
node_id	integer	The ID of this data node.
log_type	string	Type of log; one of: REDO or DD-UNDO.
log_id	integer	The log ID.
log_part	integer	The log part number.
total	integer	Total space available for this log.
used	integer	Space used by this log.

# 7.10.11 The ndbinfo membership Table

The membership table describes the view that each data node has of all the others in the cluster, including node group membership, president node, arbitrator, arbitrator successor, arbitrator connection states, and other information.


The following table provides information about the columns in the membership table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	This node's node ID
group_id	integer	Node group to which this node belongs
left node	integer	Node ID of the previous node
right_node	integer	Node ID of the next node
president	integer	President's node ID

Column Name	Туре	Description
successor	integer	Node ID of successor to president
succession_order	integer	Order in which this node succeeds to presidency
Conf_HB_order	integer	-
arbitrator	integer	Node ID of arbitrator
arb_ticket	string	Internal identifier used to track arbitration
arb_state	Enumeration (see text)	Arbitration state
arb_connected	Yes or No	Whether this node is connected to the arbitrator
connected_rank1_arbs	List of node IDs	Connected arbitrators of rank 1
connected_rank2_arbs	List of node IDs	Connected arbitrators of rank 1

The node ID and node group ID are the same as reported by ndb\_mgm -e "SHOW".

left\_node and right\_node are defined in terms of a model that connects all data nodes in a circle, in order of their node IDs, similar to the ordering of the numbers on a clock dial, as shown here:



In this example, we have 8 data nodes, numbered 5, 6, 7, 8, 12, 13, 14, and 15, ordered clockwise in a circle. We determine "left" and "right" from the interior of the circle. The node to the left of node 5 is node 15, and the node to the right of node 5 is node 6. You can see all these relationships by running the following query and observing the output:

mys	-	ndbinfo.mer	left_node,righ
n	· ·		right_node
i	5	15	6
	6	5	7
	7	6	8
	8	7	12
	12	8	13
	13	12	14
Ì	14	13	15
Ì	15	14	5

```
**-----**
8 rows in set (0.00 sec)
```

The designations "left" and "right" are used in the event log in the same way.

The president node is the node viewed by the current node as responsible for setting an arbitrator (see MySQL Cluster Start Phases). If the president fails or becomes disconnected, the current node expects the node whose ID is shown in the successor column to become the new president. The succession\_order column shows the place in the succession queue that the current node views itself as having.

In a normal MySQL Cluster, all data nodes should see the same node as president, and the same node (other than the president) as its successor. In addition, the current president should see itself as 1 in the order of succession, the successor node should see itself as 2, and so on.

All nodes should show the same <code>arb\_ticket</code> values as well as the same <code>arb\_state</code> values. Possible <code>arb\_state</code> values are <code>ARBIT\_NULL</code>, <code>ARBIT\_INIT</code>, <code>ARBIT\_FIND</code>, <code>ARBIT\_PREP1</code>, <code>ARBIT\_PREP2</code>, <code>ARBIT\_START</code>, <code>ARBIT\_RUN</code>, <code>ARBIT\_CHOOSE</code>, <code>ARBIT\_CRASH</code>, and <code>UNKNOWN</code>.

arb\_connected shows whether this node is connected to the node shown as this node's arbitrator.

The connected\_rank1\_arbs and connected\_rank2\_arbs columns each display a list of 0 or more arbitrators having an ArbitrationRank equal to 1, or to 2, respectively.

#### Note

Both management nodes and API nodes are eligible to become arbitrators.

Like the arbitrator\_validity\_detail and arbitrator\_validity\_summary tables, this table was added in MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26.

## 7.10.12 The ndbinfo memoryusage Table

Querying this table provides information similar to that provided by the ALL REPORT MemoryUsage command in the ndb\_mgm client, or logged by ALL DUMP 1000.

The following table provides information about the columns in the memoryusage table in MySQL Cluster NDB 7.1.3 and later. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The node ID of this data node.
memory_type	string	One of Data memory, Index memory, Or (MySQL Cluster NDB 7.1.31 and later) Long message buffer.
used	integer	Number of bytes currently used for data memory or index memory by this data node.
used_pages	integer	Number of pages currently used for data memory or index memory by this data node; see text.
total	integer	Total number of bytes of data memory or index memory available for this data node; see text.

Column Name	Туре	Description
total_pages	integer	Total number of memory pages available for data memory or index memory on this data node; see text.

The total column represents the total amount of memory in bytes available for the given resource (data memory or index memory) on a particular data node. This number should be approximately equal to the setting of the corresponding configuration parameter in the config.ini file.

Suppose that the cluster has 2 data nodes having node IDs 5 and 6, and the config.ini file contains the following:

```
[ndbd default]
DataMemory = 1G
IndexMemory = 1G
```

Suppose also that the value of the LongMessageBuffer configuration parameter is allowed to assume its default (64 MB in MySQL Cluster NDB 7.1.31 and later).

The following query shows approximately the same values:

	CT node_id, memory_typendbinfo.memoryusage;	pe, total
- '	memory_type	+   total +
5	Data memory	1073741824
5	Index memory	1074003968
5	Long message buffer	67108864
6	Data memory	1073741824
6	Index memory	1074003968
6	Long message buffer	67108864

In this case, the total column values for index memory are slightly higher than the value set of IndexMemory due to internal rounding.

For the used\_pages and total\_pages columns, resources are measured in pages, which are 32K in size for DataMemory and 8K for IndexMemory. For long message buffer memory, the page size is 256 bytes.

Long message buffer information can be found in this table beginning with MySQL Cluster NDB 7.1.31; in earlier versions, only data memory and index memory were included.

**MySQL Cluster NDB 7.1.2 and earlier.** The remainder of this section provides information about the memoryusage table as implemented prior to MySQL Cluster NDB 7.1.3. (If you are using MySQL Cluster NDB 7.1.3 or later, refer to the beginning of this section.) For each column, the table shown here provides the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The node ID of this data node.
memory_type	string	One of Data memory or Index memory

Column Name	Туре	Description
used	integer	Number of memory pages used; see text.
max	integer	Total number of memory pages available; see text.

For the used and max columns, resources are measured in pages, which (in MySQL Cluster NDB 7.1.2 and earlier) are 16K in size for <code>DataMemory</code> and 8K for <code>IndexMemory</code>. This example shows how to use this information in obtaining totals for <code>DataMemory</code>, <code>IndexMemory</code>, or both, which you can do by summing across data nodes and table columns, like this:

```
mysql> USE ndbinfo;
Database changed
mysql> SET @IPAGE := 8 * 1024;
Query OK, 0 rows affected (0.03 sec)
mysql> SET @DPAGE := 2 * @IPAGE;
Query OK, 0 rows affected (0.00 sec)
mysal> SELECT
        @DPAGE * SUM(used) as 'Total DataMemory Used',
        @DPAGE * SUM(max) as 'Total DataMemory Available',
   -> @DPAGE * SUM(used) DIV COUNT(*) as 'Average DataMemory Used Per Node',
        @DPAGE * SUM(max) DIV COUNT(*) as 'Average DataMemory Available Per Node'
   ->
            FROM memoryusage WHERE memory_type = 'Data memory'\G
Total DataMemory Used: 106102784
         Total DataMemory Available: 209977344
    Average DataMemory Used Per Node: 53051392
Average DataMemory Available Per Node: 104988672
1 row in set (0.34 sec)
mysql> SELECT
   -> @IPAGE * SUM(used) as 'Total IndexMemory Used',
        @IPAGE * SUM(max) as 'Total IndexMemory Available',
   -> @IPAGE * SUM(used) DIV COUNT(*) as 'Average IndexMemory Used Per Node',
         @IPAGE * SUM(max) DIV COUNT(*) as 'Average IndexMemory Available Per Node'
   -> FROM memoryusage WHERE memory_type = 'INDEX_MEMORY'\G
Total IndexMemory Used: 376832
        Total IndexMemory Available: 210239488
    Average IndexMemory Used Per Node: 188416
Average IndexMemory Available Per Node: 105119744
1 row in set (0.33 sec)
```

(We use DIV rather than / in both gueries so that the results in all of the output columns are integers.)

Prior to MySQL Cluster NDB 7.1.2, the memory\_type column was named DATA\_MEMORY. (Bug #50926)

### 7.10.13 The ndbinfo nodes Table

This table contains information on the status of data nodes. For each data node that is running in the cluster, a corresponding row in this table provides the node's node ID, status, and uptime. For nodes that are starting, it also shows the current start phase.

The following table provides information about the columns in the nodes table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The data node's unique node ID in the cluster.

Column Name	Туре	Description
uptime	integer	Time since the node was last started, in seconds.
status	string	Current status of the data node; see text for possible values.
start_phase	integer	If the data node is starting, the current start phase.
config_generation	integer	The version of the cluster configuration file in use on this data node.

The uptime column shows the time in seconds that this node has been running since it was last started or restarted. This is a BIGINT value. This figure includes the time actually needed to start the node; in other words, this counter starts running the moment that ndbd or ndbmtd is first invoked; thus, even for a node that has not yet finished starting, uptime may show a non-zero value.

The status column shows the node's current status. This is one of: NOTHING, CMVMI, STARTING, STARTED, SINGLEUSER, STOPPING\_1, STOPPING\_2, STOPPING\_3, or STOPPING\_4. When the status is STARTING, you can see the current start phase in the start\_phase column (see later in this section). SINGLEUSER is displayed in the status column for all data nodes when the cluster is in single user mode (see Section 7.8, "MySQL Cluster Single User Mode"). Seeing one of the STOPPING states does not necessarily mean that the node is shutting down but can mean rather that it is entering a new state; for example, if you put the cluster in single user mode, you can sometimes see data nodes report their state briefly as STOPPING\_2 before the status changes to SINGLEUSER.

The start\_phase column uses the same range of values as those used in the output of the ndb\_mgm client node\_id STATUS command (see Section 7.2, "Commands in the MySQL Cluster Management Client"). If the node is not currently starting, then this column shows 0. For a listing of MySQL Cluster start phases with descriptions, see Section 7.1, "Summary of MySQL Cluster Start Phases".

The config\_generation column was added in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13. This column shows which version of the cluster configuration is in effect on each data node. This can be useful when performing a rolling restart of the cluster in order to make changes in configuration parameters. For example, from the output of the following SELECT statement, you can see that node 3 is not yet using the latest version of the cluster configuration (6) although nodes 1, 2, and 4 are doing so:

	atabase changed vsql> SELECT * FROM nodes;				
		nodes;	·	h	
node_id	uptime	status	start_phase	config_generation	
	+	+	+	<u>+</u>	
1	10462	STARTED	0	б	
2	10460	STARTED	0	6	
3	10457	STARTED	0	5	
4	10455	STARTED	0	6	

Therefore, for the case just shown, you should restart node 3 to complete the rolling restart of the cluster.

#### Note

When upgrading to MySQL Cluster NDB 7.0.24 or MySQL Cluster NDB 7.1.13 from a previous version of MySQL Cluster, you should run mysql\_upgrade on all MySQL Servers that should connect to the cluster, in order to enable support for the

new config\_generation column. Otherwise, when you attempt to access this table, you get the warning Table 'ndb\$nodes' is defined differently in NDB, there are more columns available...

Nodes that are stopped are not accounted for in this table. Suppose that you have a MySQL Cluster with 4 data nodes (node IDs 1, 2, 3 and 4), and all nodes are running normally, then this table contains 4 rows, 1 for each data node:

If you shut down one of the nodes, only the nodes that are still running are represented in the output of this SELECT statement, as shown here:

```
ndb_mgm> 2 STOP
Node 2: Node shutdown initiated
Node 2: Node shutdown completed.
Node 2 has shutdown.
```

	mysql> SELECT * FROM nodes;			
node_id	uptime	status	start_phase 	config_generation
1 3 4	11807   11802   11800	STARTED STARTED STARTED	0 0	6   6   6
3 rows in	rows in set (0.02 sec)			

### 7.10.14 The ndbinfo pools Table

### **Important**

This table was part of the original ndbinfo implementation, but was later removed (in MySQL Cluster NDB 7.1.3). The information in this section is now obsolete, and subject to removal in a future version of the documentation.

The pools table was originally intended to provide information about NDB memory pool usage, but was later removed.

For each column, this table shows the name, data type, and a brief description of each ndbinfo.pools column (as it appeared prior to MySQL Cluster NDB 7.1.3). Additional information can be found in the notes afterward.

Column Name	Туре	Description
node_id	integer	The data node's node ID.

Column Name	Туре	Description
block_name	string	Name of the NDB kernel block using this pool.
block_instance	integer	Kernel block instance ID.
pool_name	string	The name of the pool.
used	integer	Amount of the pool in use.
total	integer	Total size of the pool.
high	integer	The maximum used from this pool (since the node was last started).
entry_size	integer	The size of each object, in bytes.
param_name1	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name2	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name3	string	Name of a configuration parameter associated with this pool (or NULL); see text.
param_name4	string	Name of a configuration parameter associated with this pool (or NULL); see text.

The columns param\_name1, param\_name2, param\_name3, and param\_name4 contain names of configuration parameters that are associated with a given pool. If no parameters are associated with the pool, then all 4 of these columns are NULL. For pools that are associated with configuration parameters, these columns are filled with non-NULL values, but not in any particular order.

You can use a query such as the one shown here to generate a table showing the associations of pools, NDB kernel blocks, and (where applicable) configuration parameters:

You may also find the following stored procedure useful. It returns a list of pools associated with a given configuration parameter, along with the kernel blocks to which these pools belong. You can see here the statement used to create this stored procedure along with sample output for some typical parameters:

```
mysql> DELIMITER |
mysql> CREATE PROCEDURE get_pools (p VARCHAR(50))
    -> BEGIN
    -> SELECT
```

```
DISTINCT(pool_name) as Pool,
    -> block_name ___
-> FROM ndbinfo.pools
-> WHERE p
                block_name as Block
              IN (param_name1, param_name2, param_name3, param_name4)
    .> ORDER BY Pool;
    -> END
    -> |
Query OK, 0 rows affected (0.02 sec)
mysql> DELIMITER ;
mysql> CALL get_pools('MaxNoOfTables');
| pool_name | block_name |
 Table Record | DBDICT DictObject | DBDICT Index | DBTC Table | BACKUP Trigger | BACKUP Fragment | BACKUP SUbscriber | SUMA Table | SUMA SUMA
 Subscription | SUMA
Index | DBTUX
 Descriptor page | DBTUX
11 rows in set (0.30 sec)
Query OK, 0 rows affected (0.30 sec)
mysql> CALL get_pools('MaxNoOfOrderedIndexes');
| pool_name | block_name
 DictObject | DBDICT | DBTC
              BACKUP
BACKUP
BACKUP
  Table
  Trigger
  Fragment
 Index | DBTUX
Fragment | DBTUX
| Descriptor page | DBTUX
8 rows in set (0.29 sec)
```

### 7.10.15 The ndbinfo resources Table

This table provides information about data node resource availability and usage.

These resources are sometimes known as super-pools.

The following table provides information about the columns in the resources table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	The unique node ID of this data node.
resource_name	string	Name of the resource; see text.
reserved	integer	The amount reserved for this resource.
used	integer	The amount actually used by this resource.
max	integer	The maximum amount of this resource used, since the node was last started.

The resource\_name can be one of RESERVED, DISK\_OPERATIONS, DISK\_RECORDS, DATA\_MEMORY, JOBBUFFER, FILE BUFFERS, OF TRANSPORTER BUFFERS.

### 7.10.16 The ndbinfo server\_operations Table

The server\_operations table contains entries for all ongoing NDB operations that the current SQL node (MySQL Server) is currently involved in. It effectively is a subset of the cluster\_operations table, in which operations for other SQL and API nodes are not shown.

The following table provides information about the columns in the server\_operations table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
mysql_connection_id	integer	MySQL Server connection ID
node_id	integer	Node ID
block_instance	integer	Block instance
transid	integer	Transaction ID
operation_type	string	Operation type (see text for possible values)
state	string	Operation state (see text for possible values)
tableid	integer	Table ID
fragmentid	integer	Fragment ID
client_node_id	integer	Client node ID
client_block_ref	integer	Client block reference
tc_node_id	integer	Transaction coordinator node ID
tc_block_no	integer	Transaction coordinator block number
tc_block_instance	integer	Transaction coordinator block instance

The mysql\_connection\_id is the same as the connection or session ID shown in the output of SHOW PROCESSLIST. It is obtained from the INFORMATION\_SCHEMA table NDB TRANSID MYSQL CONNECTION MAP.

The transaction ID is a unique 64-bit number which can be obtained using the NDB API's getTransactionId() method. (Currently, the MySQL Server does not expose the NDB API transaction ID of an ongoing transaction.)

The operation\_type column can take any one of the values READ, READ-SH, READ-EX, INSERT, UPDATE, DELETE, WRITE, UNLOCK, REFRESH, SCAN, SCAN-SH, SCAN-EX, Or <unknown>.

The state column can have any one of the values ABORT\_QUEUED, ABORT\_STOPPED, COMMITTED, COMMIT\_QUEUED, COMMIT\_STOPPED, COPY\_CLOSE\_STOPPED, COPY\_FIRST\_STOPPED, COPY\_STOPPED, COPY\_TUPKEY, IDLE, LOG\_ABORT\_QUEUED, LOG\_COMMIT\_QUEUED, LOG\_COMMIT\_QUEUED\_WAIT\_SIGNAL, LOG\_COMMIT\_WRITTEN, LOG\_COMMIT\_WRITTEN, WAIT\_SIGNAL, LOG\_QUEUED, PREPARED, PREPARED\_RECEIVED\_COMMIT, SCAN\_CHECK\_STOPPED, SCAN\_CLOSE\_STOPPED, SCAN\_FIRST\_STOPPED, SCAN\_RELEASE\_STOPPED, SCAN\_STATE\_USED, SCAN\_STOPPED, SCAN\_TUPKEY, STOPPED, TC\_NOT\_CONNECTED, WAIT\_ACC, WAIT\_ACC\_ABORT, WAIT\_AI\_AFTER\_ABORT, WAIT\_ATTR, WAIT\_SCAN\_AI, WAIT\_TUP, WAIT\_TUPKEYINFO, WAIT\_TUP\_COMMIT, or WAIT\_TUP\_TO\_ABORT. (If the MySQL Server is running with ndbinfo\_show\_hidden enabled, you can view this list of states by selecting from the ndb \$dblqh\_tcconnect\_state table, which is normally hidden.)

You can obtain the name of an NDB table from its table ID by checking the output of ndb\_show\_tables.

The fragid is the same as the partition number seen in the output of ndb\_desc --extra-partition-info (short form -p).

In client\_node\_id and client\_block\_ref, client refers to a MySQL Cluster API or SQL node (that is, an NDB API client or a MySQL Server attached to the cluster).

This table was added in MySQL Cluster NDB 7.1.17.

## 7.10.17 The ndbinfo server\_transactions Table

The server\_transactions table is subset of the cluster\_transactions table, but includes only those transactions in which the current SQL node (MySQL Server) is a participant, while including the relevant connection IDs.

The following table provides information about the columns in the server\_transactions table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description	
mysql_connection_id	integer	MySQL Server connection ID	
node_id	integer	Transaction coordinator node ID	
block_instance	integer	Transaction coordinator block instance	
transid	integer	Transaction ID	
state	string	Operation state (see text for possible values)	
count_operations	integer	Number of stateful operations in the transaction	
outstanding_operations	integer	Operations still being executed by local data management layer (LQH blocks)	
inactive_seconds	integer	Time spent waiting for API	
client_node_id	integer	Client node ID	
client_block_ref	integer	Client block reference	

The mysql\_connection\_id is the same as the connection or session ID shown in the output of SHOW PROCESSLIST. It is obtained from the INFORMATION\_SCHEMA table NDB\_TRANSID\_MYSQL\_CONNECTION\_MAP.

The transaction ID is a unique 64-bit number which can be obtained using the NDB API's getTransactionId() method. (Currently, the MySQL Server does not expose the NDB API transaction ID of an ongoing transaction.)

The state column can have any one of the values CS\_ABORTING, CS\_COMMITTING, CS\_COMMIT\_SENT, CS\_COMPLETE\_SENT, CS\_COMPLETING, CS\_CONNECTED, CS\_DISCONNECTED, CS\_FAIL\_ABORTED, CS\_FAIL\_ABORTING, CS\_FAIL\_COMMITTED, CS\_FAIL\_COMMITTING, CS\_FAIL\_COMPLETED, CS\_FAIL\_PREPARED, CS\_PREPARE\_TO\_COMMIT, CS\_RECEIVING, CS\_REC\_COMMITTING, CS\_RESTART, CS\_SEND\_FIRE\_TRIG\_REQ, CS\_STARTED, CS\_START\_COMMITTING, CS\_START\_SCAN, CS\_WAIT\_ABORT\_CONF, CS\_WAIT\_COMMITTCONF, CS\_WAIT\_COMPLETE\_CONF, CS\_WAIT\_FIRE\_TRIG\_REQ. (If the MySQL Server is running with ndbinfo\_show\_hidden enabled, you can view this list of states by selecting from the ndb\$dbtc\_apiconnect\_state table, which is normally hidden.)

In client\_node\_id and client\_block\_ref, client refers to a MySQL Cluster API or SQL node (that is, an NDB API client or a MySQL Server attached to the cluster).

This table was added in MySQL Cluster NDB 7.1.17.

## 7.10.18 The ndbinfo threadblocks Table

The threadblocks table associates data nodes, threads, and instances of NDB kernel blocks.

The following table provides information about the columns in the threadblocks table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer Node ID	
thr_no	integer	Thread ID
block_name	string	Block name
block_instance	integer	Block instance number

The block\_name is one of the values found in the block\_name column when selecting from the ndbinfo.blocks table. Although the list of possible values is static for a given MySQL Cluster release, the list may vary between releases.

This table was added in MySQL Cluster NDB 7.1.17.

## 7.10.19 The ndbinfo threadstat Table

The threadstat table provides a rough snapshot of statistics for threads running in the NDB kernel.

The following table provides information about the columns in the threadstat table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description
node_id	integer	Node ID
thr_no	integer	Thread ID
thr_nm	string	Thread name
c_loop	string	Number of loops in main loop
c_exec	string	Number of signals executed
c_wait	string	Number of times waiting for additional input
c_l_sent_prioa	integer	Number of priority A signals sent to own node
c_l_sent_priob	integer	Number of priority B signals sent to own node
c_r_sent_prioa	integer	Number of priority A signals sent to remote node
c_r_sent_priob	integer	Number of priority B signals sent to remote node
os_tid	integer	OS thread ID

Column Name	Туре	Description	
os_now	integer	OS time (ms)	
os_ru_utime	integer	OS user CPU time (µs)	
os_ru_stime	integer	OS system CPU time (µs)	
os_ru_minflt	integer	OS page reclaims (soft page faults)	
os_ru_majflt	integer	OS page faults (hard page faults)	
os_ru_nvcsw	integer	OS voluntary context switches	
os_ru_nivcsw	integer	OS involuntary context switches	

os\_time uses the system gettimeofday() call.

The values of the os\_ru\_utime, os\_ru\_stime, os\_ru\_minflt, os\_ru\_majflt, os\_ru\_nvcsw, and os ru nivcsw columns are obtained using the system getrusage() call, or the equivalent.

Since this table contains counts taken at a given point in time, for best results it is necessary to query this table periodically and store the results in an intermediate table or tables. The MySQL Server's Event Scheduler can be employed to automate such monitoring. For more information, see Using the Event Scheduler.

This table was added in MySQL Cluster NDB 7.1.17.

# 7.10.20 The ndbinfo transporters Table

This table contains information about NDB transporters.

The following table provides information about the columns in the transporters table. For each column, the table shows the name, data type, and a brief description. Additional information can be found in the notes following the table.

Column Name	Туре	Description	
node_id	integer	This data node's unique node ID in the cluster.	
remote_node_id	integer	The remote data node's node ID.	
status	string	Status of the connection.	
remote_address	string	Name or IP address of the remote host	
bytes_sent	integer	Number of bytes sent using this connection	
bytes_received		Number of bytes received using this connection	
connect_count		Number of times connection established on this transporter	
overloaded		1 if this transporter is currently overloaded, otherwise 0	
overload_count		Number of times this transporter has entered overload state since connecting	
slowdown		1 if this transporter is in scan slowdown state, otherwise 0	
slowdown_count		Number of times this transporter has entered scan slowdown state since connecting	

For each running data node in the cluster, the transporters table displays a row showing the status of each of that node's connections with all nodes in the cluster, *including itself*. This information is shown in the table's *status* column, which can have any one of the following values: CONNECTING, CONNECTED, DISCONNECTING, or DISCONNECTED.

Connections to API and management nodes which are configured but not currently connected to the cluster are shown with status <code>DISCONNECTED</code>. Rows where the <code>node\_id</code> is that of a data nodes which is not currently connected are not shown in this table. (This is similar omission of disconnected nodes in the <code>ndbinfo.nodes</code> table.

The remote\_address, bytes\_sent, and bytes\_received columns were added in MySQL Cluster NDB 7.0.36 and MySQL Cluster NDB 7.1.25. The remote\_address is the host name or address for the node whose ID is shown in the remote\_node\_id column. The bytes\_sent from this node and bytes\_received by this node are the numbers, respectively, of bytes sent and received by the node using this connection since it was established; for nodes whose status is CONNECTING or DISCONNECTED, these columns always display 0.

The connect\_count, overloaded, overload\_count ,slowdown, and slowdown\_count columns were added in MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26. These counters are reset on connection, and retain their values after the remote node disconnects. Also beginning with MySQL Cluster NDB 7.0.37 and MySQL Cluster NDB 7.1.26, the bytes\_send and bytes\_received counters are reset on connection as well, and so retain their values following disconnection. (Previously, the values in these columns were reset on disconnection.) (Bug #15935206)

Assume you have a 5-node cluster consisting of 2 data nodes, 2 SQL nodes, and 1 management node, as shown in the output of the SHOW command in the ndb\_mgm client:

There are 10 rows in the transporters table—5 for the first data node, and 5 for the second—assuming that all data nodes are running, as shown here:

```
mysql> SELECT node_id, remote_node_id, status
   -> FROM ndbinfo.transporters;
| node_id | remote_node_id | status
                        1 | DISCONNECTED
       1 |
       1 |
                        2 | CONNECTED
                       10 | CONNECTED
       1 |
       1 |
                       20 | CONNECTED
       1 |
                       21 | CONNECTED
       2 |
                        1 | CONNECTED
       2 |
                        2 | DISCONNECTED
                       10 | CONNECTED
       2 |
                       20 | CONNECTED
       2 |
                       21 | CONNECTED
```

```
10 rows in set (0.04 sec)
```

If you shut down one of the data nodes in this cluster using the command 2 STOP in the ndb\_mgm client, then repeat the previous query (again using the mysql client), this table now shows only 5 rows—1 row for each connection from the remaining management node to another node, including both itself and the data node that is currently offline—and displays CONNECTING for the status of each remaining connection to the data node that is currently offline, as shown here:

# 7.11 MySQL Cluster Security Issues

This section discusses security considerations to take into account when setting up and running MySQL Cluster.

Topics covered in this section include the following:

- MySQL Cluster and network security issues
- Configuration issues relating to running MySQL Cluster securely
- MySQL Cluster and the MySQL privilege system
- MySQL standard security procedures as applicable to MySQL Cluster

# 7.11.1 MySQL Cluster Security and Networking Issues

In this section, we discuss basic network security issues as they relate to MySQL Cluster. It is extremely important to remember that MySQL Cluster "out of the box" is not secure; you or your network administrator must take the proper steps to ensure that your cluster cannot be compromised over the network.

Cluster communication protocols are inherently insecure, and no encryption or similar security measures are used in communications between nodes in the cluster. Because network speed and latency have a direct impact on the cluster's efficiency, it is also not advisable to employ SSL or other encryption to network connections between nodes, as such schemes will effectively slow communications.

It is also true that no authentication is used for controlling API node access to a MySQL Cluster. As with encryption, the overhead of imposing authentication requirements would have an adverse impact on Cluster performance.

In addition, there is no checking of the source IP address for either of the following when accessing the cluster:

SQL or API nodes using "free slots" created by empty [mysqld] or [api] sections in the config.ini
file

This means that, if there are any empty [mysqld] or [api] sections in the config.ini file, then any API nodes (including SQL nodes) that know the management server's host name (or IP address) and port can connect to the cluster and access its data without restriction. (See Section 7.11.2, "MySQL Cluster and MySQL Privileges", for more information about this and related issues.)

#### Note

You can exercise some control over SQL and API node access to the cluster by specifying a HostName parameter for all [mysqld] and [api] sections in the config.ini file. However, this also means that, should you wish to connect an API node to the cluster from a previously unused host, you need to add an [api] section containing its host name to the config.ini file.

More information is available elsewhere in this chapter about the HostName parameter. Also see Section 5.1, "Quick Test Setup of MySQL Cluster", for configuration examples using HostName with API nodes.

Any ndb\_mgm client

Data Node

Data Node

Data Node

Data Node

This means that any cluster management client that is given the management server's host name (or IP address) and port (if not the standard port) can connect to the cluster and execute any management client command. This includes commands such as ALL STOP and SHUTDOWN.

For these reasons, it is necessary to protect the cluster on the network level. The safest network configuration for Cluster is one which isolates connections between Cluster nodes from any other network communications. This can be accomplished by any of the following methods:

1. Keeping Cluster nodes on a network that is physically separate from any public networks. This option is the most dependable; however, it is the most expensive to implement.

MGM Node

MGM Node

SQL Node

Router

Firewall

We show an example of a MySQL Cluster setup using such a physically segregated network here:

This setup has two networks, one private (solid box) for the Cluster management servers and data nodes, and one public (dotted box) where the SQL nodes reside. (We show the management and data

nodes connected using a gigabit switch since this provides the best performance.) Both networks are protected from the outside by a hardware firewall, sometimes also known as a *network-based firewall*.

This network setup is safest because no packets can reach the cluster's management or data nodes from outside the network—and none of the cluster's internal communications can reach the outside —without going through the SQL nodes, as long as the SQL nodes do not permit any packets to be forwarded. This means, of course, that all SQL nodes must be secured against hacking attempts.


### **Important**

With regard to potential security vulnerabilities, an SQL node is no different from any other MySQL server. See Making MySQL Secure Against Attackers, for a description of techniques you can use to secure MySQL servers.

Using one or more software firewalls (also known as <u>host-based firewalls</u>) to control which packets
pass through to the cluster from portions of the network that do not require access to it. In this type
of setup, a software firewall must be installed on every host in the cluster which might otherwise be
accessible from outside the local network.

The host-based option is the least expensive to implement, but relies purely on software to provide protection and so is the most difficult to keep secure.

This type of network setup for MySQL Cluster is illustrated here:



Using this type of network setup means that there are two zones of MySQL Cluster hosts. Each cluster host must be able to communicate with all of the other machines in the cluster, but only those hosting

SQL nodes (dotted box) can be permitted to have any contact with the outside, while those in the zone containing the data nodes and management nodes (solid box) must be isolated from any machines that are not part of the cluster. Applications using the cluster and user of those applications must *not* be permitted to have direct access to the management and data node hosts.

To accomplish this, you must set up software firewalls that limit the traffic to the type or types shown in the following table, according to the type of node that is running on each cluster host computer:


Type of Node to be Accessed	Traffic to Permit	
SQL or API node	It originates from the IP address of a management or data node (using any TCP or UDP port).	
	<ul> <li>It originates from within the network in which the cluster resides and is on the port that your application is using.</li> </ul>	
Data node or Management node	It originates from the IP address of a management or data node (using any TCP or UDP port).	
	<ul> <li>It originates from the IP address of an SQL or API node.</li> </ul>	

Any traffic other than that shown in the table for a given node type should be denied.

The specifics of configuring a firewall vary from firewall application to firewall application, and are beyond the scope of this Manual. iptables is a very common and reliable firewall application, which is often used with APF as a front end to make configuration easier. You can (and should) consult the documentation for the software firewall that you employ, should you choose to implement a MySQL Cluster network setup of this type, or of a "mixed" type as discussed under the next item.

3. It is also possible to employ a combination of the first two methods, using both hardware and software to secure the cluster—that is, using both network-based and host-based firewalls. This is between the first two schemes in terms of both security level and cost. This type of network setup keeps the cluster behind the hardware firewall, but permits incoming packets to travel beyond the router connecting all cluster hosts to reach the SQL nodes.

One possible network deployment of a MySQL Cluster using hardware and software firewalls in combination is shown here:



In this case, you can set the rules in the hardware firewall to deny any external traffic except to SQL nodes and API nodes, and then permit traffic to them only on the ports required by your application.

Whatever network configuration you use, remember that your objective from the viewpoint of keeping the cluster secure remains the same—to prevent any unessential traffic from reaching the cluster while ensuring the most efficient communication between the nodes in the cluster.

Because MySQL Cluster requires large numbers of ports to be open for communications between nodes, the recommended option is to use a segregated network. This represents the simplest way to prevent unwanted traffic from reaching the cluster.

### Note

If you wish to administer a MySQL Cluster remotely (that is, from outside the local network), the recommended way to do this is to use ssh or another secure login shell to access an SQL node host. From this host, you can then run the management client to access the management server safely, from within the Cluster's own local network.

Even though it is possible to do so in theory, it is *not* recommended to use <a href="mailto:ndb\_mgm">ndb\_mgm</a>
to manage a Cluster directly from outside the local network on which the Cluster is running. Since neither authentication nor encryption takes place between the management client and the management server, this represents an extremely insecure means of managing the cluster, and is almost certain to be compromised sooner or later.

# 7.11.2 MySQL Cluster and MySQL Privileges

In this section, we discuss how the MySQL privilege system works in relation to MySQL Cluster and the implications of this for keeping a MySQL Cluster secure.

Standard MySQL privileges apply to MySQL Cluster tables. This includes all MySQL privilege types (SELECT privilege, UPDATE privilege, DELETE privilege, and so on) granted on the database, table, and column level. As with any other MySQL Server, user and privilege information is stored in the mysql system database. The SQL statements used to grant and revoke privileges on NDB tables, databases containing such tables, and columns within such tables are identical in all respects with the GRANT and REVOKE statements used in connection with database objects involving any (other) MySQL storage engine. The same thing is true with respect to the CREATE USER and DROP USER statements.

It is important to keep in mind that, by default, the MySQL grant tables use the MyISAM storage engine. Because of this, those tables are not duplicated or shared among MySQL servers acting as SQL nodes in a MySQL Cluster. By way of example, suppose that two SQL nodes **A** and **B** are connected to the same MySQL Cluster, which has an NDB table named mytable in a database named mydb, and that you execute an SQL statement on server **A** that creates a new user jon@localhost and grants this user the SELECT privilege on that table:

```
mysql> GRANT SELECT ON mydb.mytable
    -> TO jon@localhost IDENTIFIED BY 'mypass';
```

This user is *not* created on server **B**. For this to take place, the statement must also be run on server **B**. Similarly, statements run on server **A** and affecting the privileges of existing users on server **A** do not affect users on server **B** unless those statements are actually run on server **B** as well.

In other words, *changes in users and their privileges do not automatically propagate between SQL nodes by default.* Prior to MySQL Cluster NDB 7.2, any synchronization of privileges between SQL nodes must be done either manually or by scripting an application that periodically synchronizes the privilege tables on all SQL nodes in the cluster. In MySQL Cluster NDB 7.2 and later, you can enable automatic distribution of MySQL users and privileges across MySQL Cluster SQL nodes; see Section 7.14, "Distributed MySQL Privileges for MySQL Cluster", for details.

Conversely, because there is no way in MySQL to deny privileges (privileges can either be revoked or not granted in the first place, but not denied as such), there is no special protection for NDB tables on one SQL node from users that have privileges on another SQL node. (This is true even if you are not using the automatic distribution of user privileges available in MySQl Cluster NDB 7.2 and later.) The most farreaching example of this is the MySQL root account, which can perform any action on any database object. In combination with empty [mysqld] or [api] sections of the config.ini file, this account can be especially dangerous. To understand why, consider the following scenario:

- The config.ini file contains at least one empty [mysqld] or [api] section. This means that the MySQL Cluster management server performs no checking of the host from which a MySQL Server (or other API node) accesses the MySQL Cluster.
- There is no firewall, or the firewall fails to protect against access to the MySQL Cluster from hosts external to the network.
- The host name or IP address of the MySQL Cluster's management server is known or can be determined from outside the network.

If these conditions are true, then anyone, anywhere can start a MySQL Server with --ndbcluster --ndb-connectstring=management\_host and access this MySQL Cluster. Using the MySQL root account, this person can then perform the following actions:

- Execute a SHOW DATABASES statement to obtain a list of all NDB databases
- Execute a SHOW TABLES FROM some\_database statement to obtain a list of all NDB tables in a given database

- Run any legal MySQL statements on any of those tables, such as:
  - SELECT \* FROM some\_table to read all the data from any table
  - DELETE FROM some\_table to delete all the data from a table
  - DESCRIBE some\_table or SHOW CREATE TABLE some\_table to determine the table schema
  - UPDATE some\_table SET column1 = some\_value to fill a table column with "garbage" data; this could actually cause much greater damage than simply deleting all the data

More insidious variations might include statements like these:

```
UPDATE some_table SET an_int_column = an_int_column + 1

Or

UPDATE some_table SET a_varchar_column = REVERSE(a_varchar_column)
```

Such malicious statements are limited only by the imagination of the attacker.

The only tables that would be safe from this sort of mayhem would be those tables that were created using storage engines other than NDB, and so not visible to a "rogue" SQL node.

#### Note

A user who can log in as root can also access the INFORMATION\_SCHEMA database and its tables, and so obtain information about databases, tables, stored routines, scheduled events, and any other database objects for which metadata is stored in INFORMATION\_SCHEMA.

It is also a very good idea to use different passwords for the root accounts on different cluster SQL nodes (unless you are using distributed privileges as supported in MySQL Cluster NDB 7.2 and later).

In sum, you cannot have a safe MySQL Cluster if it is directly accessible from outside your local network.

## **Important**

Never leave the MySQL root account password empty. This is just as true when running MySQL as a MySQL Cluster SQL node as it is when running it as a standalone (non-Cluster) MySQL Server, and should be done as part of the MySQL installation process before configuring the MySQL Server as an SQL node in a MySQL Cluster.

Prior to MySQL Cluster NDB 7.2, you should never convert the system tables in the mysql database to use the NDB storage engine. There are a number of reasons why you should not do this, but the most important reason is this: Many of the SQL statements that affect mysql tables storing information about user privileges, stored routines, scheduled events, and other database objects cease to function if these tables are changed to use any storage engine other than MyISAM. This is a consequence of various MySQL Server internals. Beginning with MySQL Cluster NDB 7.2, you can use a stored procedure provided for this purpose (see Section 7.14, "Distributed MySQL Privileges for MySQL Cluster"), but you are strongly advised not to attempt convert the system tables manually.

Otherwise, if you need to synchronize mysql system tables between SQL nodes, you can use standard MySQL replication to do so, or employ a script to copy table entries between the MySQL servers.

**Summary.** The two most important points to remember regarding the MySQL privilege system with regard to MySQL Cluster are:

- 1. **Prior to MySQL Cluster NDB 7.2.** Users and privileges established on one SQL node do not automatically exist or take effect on other SQL nodes in the cluster. Conversely, removing a user or privilege on one SQL node in the cluster does not remove the user or privilege from any other SQL nodes.
  - **In MySQL Cluster NDB 7.2 and later.** You can distribute MySQL users and privileges among SQL nodes using the SQL script, and the stored procedures it contains, that are supplied for this purpose in the MySQL Cluster distribution.
- 2. Once a MySQL user is granted privileges on an NDB table from one SQL node in a MySQL Cluster, that user can "see" any data in that table regardless of the SQL node from which the data originated. (This is true even if you are not using the privilege distribution support available in MySQl Cluster NDB 7.2 or later.)

# 7.11.3 MySQL Cluster and MySQL Security Procedures

In this section, we discuss MySQL standard security procedures as they apply to running MySQL Cluster.

In general, any standard procedure for running MySQL securely also applies to running a MySQL Server as part of a MySQL Cluster. First and foremost, you should always run a MySQL Server as the <code>mysql</code> system user; this is no different from running MySQL in a standard (non-Cluster) environment. The <code>mysql</code> system account should be uniquely and clearly defined. Fortunately, this is the default behavior for a new MySQL installation. You can verify that the <code>mysqld</code> process is running as the system user <code>mysql</code> by using the system command such as the one shown here:

If the <code>mysqld</code> process is running as any other user than <code>mysql</code>, you should immediately shut it down and restart it as the <code>mysql</code> user. If this user does not exist on the system, the <code>mysql</code> user account should be created, and this user should be part of the <code>mysql</code> user group; in this case, you should also make sure that the MySQL data directory on this system (as set using the <code>--datadir</code> option for <code>mysqld</code>) is owned by the <code>mysql</code> user, and that the SQL node's <code>my.cnf</code> file includes <code>user=mysql</code> in the <code>[mysqld]</code> section. Alternatively, you can start the MySQL server process with <code>--user=mysql</code> on the command line, but it is preferable to use the <code>my.cnf</code> option, since you might forget to use the command-line option and so have <code>mysqld</code> running as another user unintentionally. The <code>mysqld\_safe</code> startup script forces MySQL to run as the <code>mysql</code> user.

## **Important**

Never run mysqld as the system root user. Doing so means that potentially any file on the system can be read by MySQL, and thus—should MySQL be compromised —by an attacker.

As mentioned in the previous section (see Section 7.11.2, "MySQL Cluster and MySQL Privileges"), you should always set a root password for the MySQL Server as soon as you have it running. You should also

delete the anonymous user account that is installed by default. You can accomplish these tasks using the following statements:

Be very careful when executing the DELETE statement not to omit the WHERE clause, or you risk deleting all MySQL users. Be sure to run the FLUSH PRIVILEGES statement as soon as you have modified the mysql.user table, so that the changes take immediate effect. Without FLUSH PRIVILEGES, the changes do not take effect until the next time that the server is restarted.

### Note

Many of the MySQL Cluster utilities such as ndb\_show\_tables, ndb\_desc, and ndb\_select\_all also work without authentication and can reveal table names, schemas, and data. By default these are installed on Unix-style systems with the permissions wxr-xr-x (755), which means they can be executed by any user that can access the mysql/bin directory.

See Chapter 6, MySQL Cluster Programs, for more information about these utilities.

# 7.12 MySQL Cluster Disk Data Tables

Beginning with MySQL 5.1.6, it is possible to store the nonindexed columns of NDB tables on disk, rather than in RAM as with previous versions of MySQL Cluster.

As part of implementing MySQL Cluster Disk Data work, a number of improvements were made in MySQL Cluster for the efficient handling of very large amounts (terabytes) of data during node recovery and restart. These include a "no-steal" algorithm for synchronizing a starting node with very large data sets. For more information, see the paper *Recovery Principles of MySQL Cluster 5.1*, by MySQL Cluster developers Mikael Ronström and Jonas Oreland.

MySQL Cluster Disk Data performance can be influenced by a number of configuration parameters. For information about these parameters and their effects, see *MySQL Cluster Disk Data configuration* parameters and *MySQL Cluster Disk Data storage and GCP Stop errors* 

The performance of a MySQL Cluster that uses Disk Data storage can also be greatly improved by separating data node file systems from undo log files and tablespace data files, which can be done using symbolic links. For more information, see Section 7.12.2, "Using Symbolic Links with Disk Data Objects".

# 7.12.1 MySQL Cluster Disk Data Objects

MySQL Cluster Disk Data storage is implemented using a number of <u>Disk Data objects</u>. These include the following:

- Tablespaces act as containers for other Disk Data objects.
- Undo log files undo information required for rolling back transactions.
- One or more undo log files are assigned to a log file group, which is then assigned to a tablespace.
- Data files store Disk Data table data. A data file is assigned directly to a tablespace.

Undo log files and data files are actual files in the file system of each data node; by default they are placed in ndb\_node\_id\_fs in the DataDir specified in the MySQL Cluster config.ini file, and where node\_id is the data node's node ID. It is possible to place these elsewhere by specifying either an absolute or relative path as part of the filename when creating the undo log or data file. Statements that create these files are shown later in this section.

MySQL Cluster tablespaces and log file groups are not implemented as files.

### **Important**

Although not all Disk Data objects are implemented as files, they all share the same namespace. This means that *each Disk Data object* must be uniquely named (and not merely each Disk Data object of a given type). For example, you cannot have a tablespace and a log file group both named dd1.

Assuming that you have already set up a MySQL Cluster with all nodes (including management and SQL nodes) running MySQL 5.1.6 or newer, the basic steps for creating a Cluster table on disk are as follows:

1. Create a log file group, and assign one or more undo log files to it (an undo log file is also sometimes referred to as an *undofile*).

#### Note

In MySQL 5.1 and later, undo log files are necessary only for Disk Data tables. They are no longer used for NDBCLUSTER tables that are stored only in memory.

- 2. Create a tablespace; assign the log file group, as well as one or more data files, to the tablespace.
- 3. Create a Disk Data table that uses this tablespace for data storage.

Each of these tasks can be accomplished using SQL statements in the mysql client or other MySQL client application, as shown in the example that follows.

1. We create a log file group named lg\_1 using CREATE LOGFILE GROUP. This log file group is to be made up of two undo log files, which we name undo\_1.log and undo\_2.log, whose initial sizes are 16 MB and 12 MB, respectively. (The default initial size for an undo log file is 128 MB.) Optionally, you can also specify a size for the log file group's undo buffer, or permit it to assume the default value of 8 MB. In this example, we set the UNDO buffer's size at 2 MB. A log file group must be created with an undo log file; so we add undo\_1.log to lg\_1 in this CREATE LOGFILE GROUP statement:

```
CREATE LOGFILE GROUP lg_1

ADD UNDOFILE 'undo_1.log'

INITIAL_SIZE 16M

UNDO_BUFFER_SIZE 2M

ENGINE NDBCLUSTER;
```

To add undo 2.log to the log file group, use the following ALTER LOGFILE GROUP statement:

```
ALTER LOGFILE GROUP lg_1

ADD UNDOFILE 'undo_2.log'

INITIAL_SIZE 12M

ENGINE NDBCLUSTER;
```

### Some items of note:

• The .log file extension used here is not required. We use it merely to make the log files easily recognizable.

• Every CREATE LOGFILE GROUP and ALTER LOGFILE GROUP statement must include an ENGINE clause. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the permitted values for this clause are NDBCLUSTER and NDB.

### **Important**

In MySQL 5.1.8 and later, there can exist only one log file group in the same MySQL Cluster at any given time.

- When you add an undo log file to a log file group using ADD UNDOFILE 'filename', a file with the name filename is created in the ndb\_node\_id\_fs directory within the DataDir of each data node in the cluster, where node\_id is the node ID of the data node. Each undo log file is of the size specified in the SQL statement. For example, if a MySQL Cluster has 4 data nodes, then the ALTER LOGFILE GROUP statement just shown creates 4 undo log files, 1 each on in the data directory of each of the 4 data nodes; each of these files is named undo\_2.log and each file is 12 MB in size.
- UNDO BUFFER SIZE is limited by the amount of system memory available.
- For more information about the CREATE LOGFILE GROUP statement, see CREATE LOGFILE GROUP Syntax. For more information about ALTER LOGFILE GROUP, see ALTER LOGFILE GROUP Syntax.
- 2. Now we can create a tablespace, which contains files to be used by MySQL Cluster Disk Data tables for storing their data. A tablespace is also associated with a particular log file group. When creating a new tablespace, you must specify the log file group which it is to use for undo logging; you must also specify a data file. You can add more data files to the tablespace after the tablespace is created; it is also possible to drop data files from a tablespace (an example of dropping data files is provided later in this section).

Assume that we wish to create a tablespace named ts\_1 which uses lg\_1 as its log file group. This tablespace is to contain two data files named data\_1.dat and data\_2.dat, whose initial sizes are 32 MB and 48 MB, respectively. (The default value for INITIAL\_SIZE is 128 MB.) We can do this using two SQL statements, as shown here:

```
CREATE TABLESPACE ts_1

ADD DATAFILE 'data_1.dat'

USE LOGFILE GROUP 1g_1

INITIAL_SIZE 32M

ENGINE NDBCLUSTER;

ALTER TABLESPACE ts_1

ADD DATAFILE 'data_2.dat'

INITIAL_SIZE 48M

ENGINE NDBCLUSTER;
```

The CREATE TABLESPACE statement creates a tablespace ts\_1 with the data file data\_1.dat, and associates ts\_1 with log file group lg\_1. The ALTER TABLESPACE adds the second data file (data\_2.dat).

### Some items of note:

- As is the case with the .log file extension used in this example for undo log files, there is no special significance for the .dat file extension; it is used merely for easy recognition of data files.
- When you add a data file to a tablespace using ADD DATAFILE 'filename', a file with the name filename is created in the ndb\_node\_id\_fs directory within the DataDir of each data node in the cluster, where node\_id is the node ID of the data node. Each data file is of the size

specified in the SQL statement. For example, if a MySQL Cluster has 4 data nodes, then the ALTER TABLESPACE statement just shown creates 4 data files, 1 each in the data directory of each of the 4 data nodes; each of these files is named data\_2.dat and each file is 48 MB in size.

- All CREATE TABLESPACE and ALTER TABLESPACE statements must contain an ENGINE clause; only tables using the same storage engine as the tablespace can be created in the tablespace. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), the only permitted values for this clause are NDBCLUSTER and NDB.
- For more information about the CREATE TABLESPACE and ALTER TABLESPACE statements, see CREATE TABLESPACE Syntax, and ALTER TABLESPACE Syntax.
- 3. Now it is possible to create a table whose nonindexed columns are stored on disk in the tablespace ts 1:

```
CREATE TABLE dt_1 (
    member_id INT UNSIGNED NOT NULL AUTO_INCREMENT PRIMARY KEY,
    last_name VARCHAR(50) NOT NULL,
    first_name VARCHAR(50) NOT NULL,
    dob DATE NOT NULL,
    joined DATE NOT NULL,
    INDEX(last_name, first_name)
    )
    TABLESPACE ts_1 STORAGE DISK
    ENGINE NDBCLUSTER;
```

The TABLESPACE ... STORAGE DISK option tells the NDBCLUSTER storage engine to use tablespace ts\_1 for disk data storage.

## Note

Beginning with MySQL Cluster NDB 6.2.5 and MySQL Cluster NDB 6.3.2, it is also possible to specify whether an individual column is stored on disk or in memory by using a STORAGE clause as part of the column's definition in a CREATE TABLE OF ALTER TABLE Statement. STORAGE DISK causes the column to be stored on disk, and STORAGE MEMORY causes in-memory storage to be used. See CREATE TABLE Syntax, for more information.

Once table ts\_1 has been created as shown, you can perform INSERT, SELECT, UPDATE, and DELETE statements on it just as you would with any other MySQL table.

For table dt\_1 as it has been defined here, only the dob and joined columns are stored on disk. This is because there are indexes on the id, last\_name, and first\_name columns, and so data belonging to these columns is stored in RAM. In MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1), only nonindexed columns can be held on disk; indexes and indexed column data continue to be stored in memory. This tradeoff between the use of indexes and conservation of RAM is something you must keep in mind as you design Disk Data tables.

**Performance note.** The performance of a cluster using Disk Data storage is greatly improved if Disk Data files are kept on a separate physical disk from the data node file system. This must be done for each data node in the cluster to derive any noticeable benefit.

You may use absolute and relative file system paths with ADD UNDOFILE and ADD DATAFILE. Relative paths are calculated relative to the data node's data directory. You may also use symbolic links; see Section 7.12.2, "Using Symbolic Links with Disk Data Objects", for more information and examples.

A log file group, a tablespace, and any Disk Data tables using these must be created in a particular order. The same is true for dropping any of these objects:

- · A log file group cannot be dropped as long as any tablespaces are using it.
- A tablespace cannot be dropped as long as it contains any data files.
- You cannot drop any data files from a tablespace as long as there remain any tables which are using the tablespace.
- Beginning with MySQL 5.1.12, it is no longer possible to drop files created in association with a different tablespace than the one with which the files were created. (Bug #20053)

For example, to drop all the objects created so far in this section, you would use the following statements:

```
mysql> DROP TABLE dt_1;
mysql> ALTER TABLESPACE ts_1
    -> DROP DATAFILE 'data_2.dat'
    -> ENGINE NDBCLUSTER;
mysql> ALTER TABLESPACE ts_1
    -> DROP DATAFILE 'data_1.dat'
    -> ENGINE NDBCLUSTER;
mysql> DROP TABLESPACE ts_1
    -> ENGINE NDBCLUSTER;
mysql> DROP LOGFILE GROUP lg_1
    -> ENGINE NDBCLUSTER;
```

These statements must be performed in the order shown, except that the two ALTER TABLESPACE ...

DROP DATAFILE statements may be executed in either order.

You can obtain information about data files used by Disk Data tables by querying the FILES table in the INFORMATION\_SCHEMA database. An extra "NULL row" was added to this table in MySQL 5.1.14 for providing additional information about undo log files. For more information and examples of use, see The INFORMATION\_SCHEMA FILES Table.

Beginning with MySQL Cluster NDB 6.3.27 and MySQL Cluster NDB 7.0.8, it is also possible to view information about allocated and free disk space for each Disk Data table or table partition using the ndb\_desc utility. For more information, see Section 6.10, "ndb\_desc — Describe NDB Tables".

# 7.12.2 Using Symbolic Links with Disk Data Objects

The performance of a MySQL Cluster that uses Disk Data storage can be greatly improved by separating data node file systems from undo log files and tablespace data files and placing these on different disks. Previous to MySQL Cluster NDB 6.2.17, MySQL Cluster NDB 6.3.22, and MySQL Cluster NDB 6.4.3, there was no direct support for this in MySQL Cluster, but it was possible to achieve this separation using symbolic links as described in this section.

Beginning with MySQL Cluster NDB 6.2.17, MySQL Cluster NDB 6.3.22, and MySQL Cluster NDB 6.4.3, the data node configuration parameters FileSystemPathDD, FileSystemPathDataFiles, and FileSystemPathUndoFiles make the use of symbolic links for this purpose unnecessary. For information about these parameters, see Disk Data file system parameters.

Each data node in the cluster creates a file system in the directory named ndb\_node\_id\_fs under the data node's DataDir as defined in the config.ini file. In this example, we assume that each data node host has 3 disks, aliased as /data0, /data1, and /data2, and that the cluster's config.ini includes the following:

```
[ndbd default]
DataDir= /data0
```

Our objective is to place all Disk Data log files in /data1, and all Disk Data data files in /data2, on each data node host.

### Note

In this example, we assume that the cluster's data node hosts are all using Linux operating systems. For other platforms, you may need to substitute you operating system's commands for those shown here.

To accomplish this, perform the following steps:

• Under the data node file system create symbolic links pointing to the other drives:

```
shell> cd /data0/ndb_2_fs
shell> ls
D1 D10 D11 D2 D8 D9 LCP
shell> ln -s /data0 dnlogs
shell> ln -s /data1 dndata
```

You should now have two symbolic links:

```
shell> 1s -1 --hide=D*
lrwxrwxrwx 1 user group  30 2007-03-19 13:58 dndata -> /data1
lrwxrwxrwx 1 user group  30 2007-03-19 13:59 dnlogs -> /data2
```

We show this only for the data node with node ID 2; however, you must do this for each data node.

• Now, in the mysql client, create a log file group and tablespace using the symbolic links, as shown here:

```
mysql> CREATE LOGFILE GROUP 1g1
   -> ADD UNDOFILE 'dnlogs/undo1.log'
   -> INITIAL_SIZE 150M
   -> UNDO_BUFFER_SIZE = 1M
   -> ENGINE=NDBCLUSTER;
mysql> CREATE TABLESPACE ts1
   -> ADD DATAFILE 'dndata/data1.log'
   -> USE LOGFILE GROUP 1g1
   -> INITIAL_SIZE 1G
   -> ENGINE=NDBCLUSTER;
```

Verify that the files were created and placed correctly as shown here:

```
shell> cd /data1
shell> ls -1
total 2099304
-rw-rw-r-- 1 user group 157286400 2007-03-19 14:02 undol.dat
shell> cd /data2
shell> ls -1
total 2099304
-rw-rw-r-- 1 user group 1073741824 2007-03-19 14:02 datal.dat
```

• If you are running multiple data nodes on one host, you must take care to avoid having them try to use the same space for Disk Data files. You can make this easier by creating a symbolic link in each data node file system. Suppose you are using /data0 for both data node file systems, but you wish to have the Disk Data files for both nodes on /data1. In this case, you can do something similar to what is shown here:

```
shell> cd /data0
```

```
shell> ln -s /data1/dn2 ndb_2_fs/dd
shell> ln -s /data1/dn3 ndb_3_fs/dd
shell> ls -l --hide=D* ndb_2_fs
lrwxrwxrwx 1 user group  30 2007-03-19 14:22 dd -> /data1/dn2
shell> ls -l --hide=D* ndb_3_fs
lrwxrwxrwx 1 user group  30 2007-03-19 14:22 dd -> /data1/dn3
```

Now you can create a logfile group and tablespace using the symbolic link, like this:

```
mysql> CREATE LOGFILE GROUP lg1
   -> ADD UNDOFILE 'dd/undol.log'
   -> INITIAL_SIZE 150M
   -> UNDO_BUFFER_SIZE = 1M
   -> ENGINE=NDBCLUSTER;
mysql> CREATE TABLESPACE ts1
   -> ADD DATAFILE 'dd/datal.log'
   -> USE LOGFILE GROUP lg1
   -> INITIAL_SIZE 1G
   -> ENGINE=NDBCLUSTER;
```

Verify that the files were created and placed correctly as shown here:

```
shell> cd /datal
shell> ls
dn2     dn3
shell> ls dn2
undol.log     datal.log
shell> ls dn3
undol.log     datal.log
```

# 7.12.3 MySQL Cluster Disk Data Storage Requirements

The following items apply to Disk Data storage requirements:

• Variable-length columns of Disk Data tables take up a fixed amount of space. For each row, this is equal to the space required to store the largest possible value for that column.

For general information about calculating these values, see Data Type Storage Requirements.

You can obtain an estimate the amount of space available in data files and undo log files by querying the INFORMATION\_SCHEMA.FILES table. For more information and examples, see The INFORMATION\_SCHEMA FILES Table.

### Note

The OPTIMIZE TABLE statement does not have any effect on Disk Data tables.

- In a Disk Data table, the first 256 bytes of a TEXT or BLOB column are stored in memory; only the remainder is stored on disk.
- Each row in a Disk Data table uses 8 bytes in memory to point to the data stored on disk. This means that, in some cases, converting an in-memory column to the disk-based format can actually result in greater memory usage. For example, converting a CHAR (4) column from memory-based to disk-based format increases the amount of DataMemory used per row from 4 to 8 bytes.

## **Important**

Starting the cluster with the --initial option does *not* remove Disk Data files. You must remove these manually prior to performing an initial restart of the cluster.

Performance of Disk Data tables can be improved by minimizing the number of disk seeks by making sure that <code>DiskPageBufferMemory</code> is of sufficient size. You can query the <code>diskpagebuffer</code> table to help determine whether the value for this parameter needs to be increased.

# 7.13 Adding MySQL Cluster Data Nodes Online

This section describes how to add MySQL Cluster data nodes "online"—that is, without needing to shut down the cluster completely and restart it as part of the process. This capability is available in MySQL Cluster NDB 7.0 (beginning with MySQL Cluster NDB 6.4.0) and later MySQL Cluster release series.

### **Important**

Currently, you must add new data nodes to a MySQL Cluster as part of a new node group. In addition, it is not possible to change the number of replicas (or the number of nodes per node group) online.

# 7.13.1 Adding MySQL Cluster Data Nodes Online: General Issues

This section provides general information about the behavior of and current limitations in adding MySQL Cluster nodes online.

Redistribution of Data. The ability to add new nodes online includes a means to reorganize NDBCLUSTER table data and indexes so that they are distributed across all data nodes, including the new ones, by means of the ALTER ONLINE TABLE ... REORGANIZE PARTITION statement. Table reorganization of both in-memory and Disk Data tables is supported. This redistribution does not currently include unique indexes (only ordered indexes are redistributed). Prior to MySQL Cluster NDB 7.0.40 and MySQL Cluster NDB 7.1.28, BLOB table data is also not redistributed using this method (Bug #13714148).

The redistribution for NDBCLUSTER tables already existing before the new data nodes were added is not automatic, but can be accomplished using simple SQL statements in mysql or another MySQL client application. However, all data and indexes added to tables created after a new node group has been added are distributed automatically among all cluster data nodes, including those added as part of the new node group.

**Partial starts.** It is possible to add a new node group without all of the new data nodes being started. It is also possible to add a new node group to a degraded cluster—that is, a cluster that is only partially started, or where one or more data nodes are not running. In the latter case, the cluster must have enough nodes running to be viable before the new node group can be added.

**Effects on ongoing operations.** Normal DML operations using MySQL Cluster data are not prevented by the creation or addition of a new node group, or by table reorganization. However, it is not possible to perform DDL concurrently with table reorganization—that is, no other DDL statements can be issued while an ALTER TABLE ... REORGANIZE PARTITION statement is executing. In addition, during the execution of ALTER TABLE ... REORGANIZE PARTITION (or the execution of any other DDL statement), it is not possible to restart cluster data nodes.

**Failure handling.** Failures of data nodes during node group creation and table reorganization are handled as shown in the following table:

Failure occurs during:	Failure occurs in:				
	"Old" data nodes "New" data nodes System				
Node group creation	If a node other than the master fails:     The creation of the	• If a node other than the master fails: The creation of the	If the execution of CREATE NODEGROUP has reached the		

Failure occurs during:	Failure occurs in:			
	"Old" data nodes	"New" data nodes	System	
	node group is always rolled forward.  • If the master fails:  • If the internal commit point has been reached:	node group is always rolled forward.  If the master fails:  If the internal commit point has been reached:	internal commit point: When restarted, the cluster includes the new node group. Otherwise it without.  • If the execution of	
	The creation of the node group is rolled forward.  • If the internal commit point has not yet been reached. The creation of the node	The creation of the node group is rolled forward.  • If the internal commit point has not yet been reached. The creation of the node	create nodegroup has not yet reached the internal commit point: When restarted, the cluster does not include the new node group.	
Table reorganization	<ul> <li>If a node other than the master fails: The table reorganization is always rolled forward.</li> <li>If the master fails: <ul> <li>If the internal commit point has been reached: The table reorganization is rolled forward.</li> <li>If the internal commit point has not yet been reached. The table reorganization is rolled back.</li> </ul> </li> </ul>	<ul> <li>If a node other than the master fails: The table reorganization is always rolled forward.</li> <li>If the master fails:         <ul> <li>If the internal commit point has been reached: The table reorganization is rolled forward.</li> </ul> </li> <li>If the internal commit point has not yet been reached. The table reorganization is rolled back.</li> </ul>	• If the execution of an ALTER ONLINE TABLE table REORGANIZE PARTITION statement has reached the internal commit point:  When the cluster is restarted, the data and indexes belonging to table are distributed using the "new" data nodes.  • If the execution of an ALTER ONLINE TABLE table REORGANIZE PARTITION statement has not yet reached the internal commit point:  When the cluster is restarted, the data and indexes belonging to table are distributed using only the "old" data nodes.	

**Dropping node groups.** The ndb\_mgm client supports a DROP NODEGROUP command, but it is possible to drop a node group only when no data nodes in the node group contain any data. Since there is currently no way to "empty" a specific data node or node group, this command works only the following two cases:

- 1. After issuing CREATE NODEGROUP in the ndb\_mgm client, but before issuing any ALTER ONLINE TABLE ... REORGANIZE PARTITION statements in the mysql client.
- 2. After dropping all NDBCLUSTER tables using DROP TABLE.

TRUNCATE TABLE does not work for this purpose because the data nodes continue to store the table definitions.

# 7.13.2 Adding MySQL Cluster Data Nodes Online: Basic procedure

In this section, we list the basic steps required to add new data nodes to a MySQL Cluster. For a detailed example, see Section 7.13.3, "Adding MySQL Cluster Data Nodes Online: Detailed Example".

#### Note

Beginning with MySQL Cluster NDB 7.0.4, this procedure applies whether you are using ndbd or ndbmtd binaries for the data node processes. Previously, this did not work with multi-threaded data nodes. (Bug #43108)

Assuming that you already have a running MySQL Cluster, adding data nodes online requires the following steps:

1. Edit the cluster configuration <code>config.ini</code> file, adding new <code>[ndbd]</code> sections corresponding to the nodes to be added. In the case where the cluster uses multiple management servers, these changes need to be made to all <code>config.ini</code> files used by the management servers.

You must be careful that node IDs for any new data nodes added in the config.ini file do not overlap node IDs used by existing nodes. In the event that you have API nodes using dynamically allocated node IDs and these IDs match node IDs that you want to use for new data nodes, it is possible to force any such API nodes to "migrate", as described later in this procedure.

2. Perform a rolling restart of all MySQL Cluster management servers.

#### **Important**

All management servers must be restarted with the --reload or --initial option to force the reading of the new configuration.

3. Perform a rolling restart of all existing MySQL Cluster data nodes. It is not necessary (or usually even desirable) to use --initial when restarting the existing data nodes.

If you are using API nodes with dynamically allocated IDs matching any node IDs that you wish to assign to new data nodes, you must restart all API nodes (including SQL nodes) before restarting any of the data nodes processes in this step. This causes any API nodes with node IDs that were previously not explicitly assigned to relinquish those node IDs and acquire new ones.

- 4. Perform a rolling restart of any SQL or API nodes connected to the MySQL Cluster.
- 5. Start the new data nodes.

The new data nodes may be started in any order. They can also be started concurrently, as long as they are started after the rolling restarts of all existing data nodes have been completed, and before proceeding to the next step.

6. Execute one or more CREATE NODEGROUP commands in the MySQL Cluster management client to create the new node group or node groups to which the new data nodes will belong.

7. Redistribute the cluster's data among all data nodes (including the new ones) by issuing an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client for each NDBCLUSTER table.

### Note

This needs to be done only for tables already existing at the time the new node group is added. Data in tables created after the new node group is added is distributed automatically; however, data added to any given table tbl that existed before the new nodes were added is not distributed using the new nodes until that table has been reorganized using ALTER ONLINE TABLE tbl REORGANIZE PARTITION.

8. Reclaim the space freed on the "old" nodes by issuing, for each NDBCLUSTER table, an OPTIMIZE TABLE statement in the mysql client.

You can add all the nodes desired, then issue several CREATE NODEGROUP commands in succession to add the new node groups to the cluster. Prior to MySQL Cluster NDB 7.0.16 and MySQL Cluster NDB 7.1.5, when adding multiple new node groups to a MySQL Cluster, it was necessary to add only the nodes to be assigned to a given new node group, create that node group using CREATE NODEGROUP, then repeat this process for each new node group to be added to the cluster. (Bug #54497)

# 7.13.3 Adding MySQL Cluster Data Nodes Online: Detailed Example

In this section we provide a detailed example illustrating how to add new MySQL Cluster data nodes online, starting with a MySQL Cluster having 2 data nodes in a single node group and concluding with a cluster having 4 data nodes in 2 node groups.

**Starting configuration.** For purposes of illustration, we assume a minimal configuration, and that the cluster uses a config.ini file containing only the following information:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NoOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
[ndbd]
Id = 1
HostName = 192.168.0.1
[ndbd]
Id = 2
HostName = 192.168.0.2
HostName = 192.168.0.10
Id = 10
[api]
Id=20
HostName = 192.168.0.20
Td=21
HostName = 192.168.0.21
```

#### Note

We have left a gap in the sequence between data node IDs and other nodes. This make it easier later to assign node IDs that are not already in use to data nodes which are newly added.

We also assume that you have already started the cluster using the appropriate command line or my.cnf options, and that running SHOW in the management client produces output similar to what is shown here:

Finally, we assume that the cluster contains a single NDBCLUSTER table created as shown here:

```
USE n;

CREATE TABLE ips (

id BIGINT NOT NULL AUTO_INCREMENT PRIMARY KEY,
country_code CHAR(2) NOT NULL,
type CHAR(4) NOT NULL,
ip_address varchar(15) NOT NULL,
addresses BIGINT UNSIGNED DEFAULT NULL,
date BIGINT UNSIGNED DEFAULT NULL
) ENGINE NDBCLUSTER;
```

The memory usage and related information shown later in this section was generated after inserting approximately 50000 rows into this table.

#### Note

In this example, we show the single-threaded ndbd being used for the data node processes. However—beginning with MySQL Cluster NDB 7.0.4—you can also apply this example, if you are using the multi-threaded ndbmtd by substituting ndbmtd for ndbd wherever it appears in the steps that follow. (Bug #43108)

**Step 1: Update configuration file.** Open the cluster global configuration file in a text editor and add <code>[ndbd]</code> sections corresponding to the 2 new data nodes. (We give these data nodes IDs 3 and 4, and assume that they are to be run on host machines at addresses 192.168.0.3 and 192.168.0.4, respectively.) After you have added the new sections, the contents of the <code>config.ini</code> file should look like what is shown here, where the additions to the file are shown in bold type:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NoOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
[ndbd]
Id = 1
HostName = 192.168.0.1
[ndbd]
Id = 2
HostName = 192.168.0.2
[ndbd]
Id = 3
HostName = 192.168.0.3
[ndbd]
```

```
Id = 4
HostName = 192.168.0.4
[mgm]
HostName = 192.168.0.10
Id = 10
[api]
Id=20
HostName = 192.168.0.20
[api]
Id=21
HostName = 192.168.0.21
```

Once you have made the necessary changes, save the file.

**Step 2: Restart the management server.** Restarting the cluster management server requires that you issue separate commands to stop the management server and then to start it again, as follows:

1. Stop the management server using the management client STOP command, as shown here:

```
ndb_mgm> 10 STOP
Node 10 has shut down.
Disconnecting to allow Management Server to shutdown
shell>
```

2. Because shutting down the management server causes the management client to terminate, you must start the management server from the system shell. For simplicity, we assume that config.ini is in the same directory as the management server binary, but in practice, you must supply the correct path to the configuration file. You must also supply the --reload or --initial option so that the management server reads the new configuration from the file rather than its configuration cache. If your shell's current directory is also the same as the directory where the management server binary is located, then you can invoke the management server as shown here:

```
shell> ndb_mgmd -f config.ini --reload
2008-12-08 17:29:23 [MgmSrvr] INFO -- NDB Cluster Management Server. 5.1.73-ndb-7.1.33
2008-12-08 17:29:23 [MgmSrvr] INFO -- Reading cluster configuration from 'config.ini'
```

If you check the output of SHOW in the management client after restarting the ndb\_mgm process, you should now see something like this:

**Step 3: Perform a rolling restart of the existing data nodes.** This step can be accomplished entirely within the cluster management client using the RESTART command, as shown here:

```
ndb_mgm> 1 RESTART
```

```
Node 1: Node shutdown initiated
Node 1: Node shutdown completed, restarting, no start.
Node 1 is being restarted
ndb_mgm> Node 1: Start initiated (version 7.1.33)
Node 1: Started (version 7.1.33)
ndb_mgm> 2 RESTART
Node 2: Node shutdown initiated
Node 2: Node shutdown completed, restarting, no start.
Node 2 is being restarted
ndb_mgm> Node 2: Start initiated (version 7.1.33)
ndb_mgm> Node 2: Started (version 7.1.33)
```

### **Important**

After issuing each *X* RESTART command, wait until the management client reports Node *X*: Started (version ...) before proceeding any further.

Beginning with MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, you can verify that all existing data nodes were restarted using the updated configuration by checking the ndbinfo.nodes table in the mysql client.

**Step 4: Perform a rolling restart of all cluster API nodes.** Shut down and restart each MySQL server acting as an SQL node in the cluster using mysqladmin shutdown followed by mysqld\_safe (or another startup script). This should be similar to what is shown here, where password is the MySQL root password for a given MySQL server instance:

```
shell> mysqladmin -uroot -ppassword shutdown
081208 20:19:56 mysqld_safe mysqld from pid file
/usr/local/mysql/var/tonfisk.pid ended
shell> mysqld_safe --ndbcluster --ndb-connectstring=192.168.0.10 &
081208 20:20:06 mysqld_safe Logging to '/usr/local/mysql/var/tonfisk.err'.
081208 20:20:06 mysqld_safe Starting mysqld daemon with databases
from /usr/local/mysql/var
```

Of course, the exact input and output depend on how and where MySQL is installed on the system, as well as which options you choose to start it (and whether or not some or all of these options are specified in a my.cnf file).

**Step 5: Perform an initial start of the new data nodes.** From a system shell on each of the hosts for the new data nodes, start the data nodes as shown here, using the --initial option:

```
shell> ndbd -c 192.168.0.10 --initial
```

### Note

Unlike the case with restarting the existing data nodes, you can start the new data nodes concurrently; you do not need to wait for one to finish starting before starting the other.

Wait until both of the new data nodes have started before proceeding with the next step. Once the new data nodes have started, you can see in the output of the management client SHOW command that they do not yet belong to any node group (as indicated with bold type here):

**Step 6: Create a new node group.** You can do this by issuing a CREATE NODEGROUP command in the cluster management client. This command takes as its argument a comma-separated list of the node IDs of the data nodes to be included in the new node group, as shown here:

```
ndb_mgm> CREATE NODEGROUP 3,4
Nodegroup 1 created
```

By issuing SHOW again, you can verify that data nodes 3 and 4 have joined the new node group (again indicated in bold type):

**Step 7: Redistribute cluster data.** When a node group is created, existing data and indexes are not automatically distributed to the new node group's data nodes, as you can see by issuing the appropriate REPORT command in the management client:

```
ndb_mgm> ALL REPORT MEMORY

Node 1: Data usage is 5%(177 32K pages of total 3200)

Node 1: Index usage is 0%(108 8K pages of total 12832)

Node 2: Data usage is 5%(177 32K pages of total 3200)

Node 2: Index usage is 0%(108 8K pages of total 12832)

Node 3: Data usage is 0%(0 32K pages of total 3200)

Node 3: Index usage is 0%(0 8K pages of total 12832)

Node 4: Data usage is 0%(0 32K pages of total 3200)

Node 4: Index usage is 0%(0 8K pages of total 3200)
```

By using  $ndb\_desc$  with the -p option, which causes the output to include partitioning information, you can see that the table still uses only 2 partitions (in the  $Per\ partition\ info\ section$  of the output, shown here in bold text):

```
shell> ndb_desc -c 192.168.0.10 -d n ips -p
-- ips --
Version: 1
Fragment type: 9
K Value: 6
```

```
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 6
Number of primary keys: 1
Length of frm data: 340
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 2
TableStatus: Retrieved
-- Attributes --
id Bigint PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
country_code Char(2;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
type Char(4;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
ip_address Varchar(15;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
addresses Bigunsigned NULL AT=FIXED ST=MEMORY
date Bigunsigned NULL AT=FIXED ST=MEMORY
-- Indexes -
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
-- Per partition info --
Partition Row count Commit count Frag fixed memory Frag varsized memory
    26086 26086 1572864
26329 26329 1605632
                                                         557056
                                                        557056
NDBT_ProgramExit: 0 - OK
```

You can cause the data to be redistributed among all of the data nodes by performing, for each NDBCLUSTER table, an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client. After issuing the statement ALTER ONLINE TABLE ips REORGANIZE PARTITION, you can see using ndb\_desc that the data for this table is now stored using 4 partitions, as shown here (with the relevant portions of the output in bold type):

```
shell> ndb_desc -c 192.168.0.10 -d n ips -p
-- ips --
Version: 16777217
Fragment type: 9
K Value: 6
Min load factor: 78
Max load factor: 80
Temporary table: no
Number of attributes: 6
Number of primary keys: 1
Length of frm data: 341
Row Checksum: 1
Row GCI: 1
SingleUserMode: 0
ForceVarPart: 1
FragmentCount: 4
TableStatus: Retrieved
-- Attributes --
id Bigint PRIMARY KEY DISTRIBUTION KEY AT=FIXED ST=MEMORY AUTO_INCR
country_code Char(2;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
type Char(4;latin1_swedish_ci) NOT NULL AT=FIXED ST=MEMORY
ip_address Varchar(15;latin1_swedish_ci) NOT NULL AT=SHORT_VAR ST=MEMORY
addresses Bigunsigned NULL AT=FIXED ST=MEMORY
date Bigunsigned NULL AT=FIXED ST=MEMORY
-- Indexes --
PRIMARY KEY(id) - UniqueHashIndex
PRIMARY(id) - OrderedIndex
-- Per partition info --
Partition Row count Commit count Frag fixed memory Frag varsized memory
           12981 52296 1572864
0
                                                         557056
1
           13236
                       52515
                                    1605632
                                                         557056
```

2	13105	13105	819200	294912	
3	13093	13093	819200	294912	
NDBT_ProgramExit: 0 - OK					

### Note

Normally, ALTER [ONLINE] TABLE table\_name REORGANIZE PARTITION is used with a list of partition identifiers and a set of partition definitions to create a new partitioning scheme for a table that has already been explicitly partitioned. Its use here to redistribute data onto a new MySQL Cluster node group is an exception in this regard; when used in this way, only the name of the table is used following the TABLE keyword, and no other keywords or identifiers follow REORGANIZE PARTITION.

Prior to MySQL Cluster NDB 6.4.3, ALTER ONLINE TABLE ... REORGANIZE PARTITION with no partition\_names INTO (partition\_definitions) option did not work correctly with Disk Data tables or with in-memory NDBCLUSTER tables having one or more disk-based columns. (Bug #42549)

For more information, see ALTER TABLE Syntax.

In addition, for each table, the ALTER ONLINE TABLE statement should be followed by an OPTIMIZE TABLE to reclaim wasted space. You can obtain a list of all NDBCLUSTER tables using the following query against the INFORMATION\_SCHEMA.TABLES table:

```
SELECT TABLE_SCHEMA, TABLE_NAME

FROM INFORMATION_SCHEMA.TABLES

WHERE ENGINE = 'NDBCLUSTER';
```

#### Note

The INFORMATION\_SCHEMA.TABLES.ENGINE value for a MySQL Cluster table is always NDBCLUSTER, regardless of whether the CREATE TABLE statement used to create the table (or ALTER TABLE statement used to convert an existing table from a different storage engine) used NDB or NDBCLUSTER in its ENGINE option.

You can see after performing these statements in the output of ALL REPORT MEMORY that the data and indexes are now redistributed between all cluster data nodes, as shown here:

```
ndb_mgm> ALL REPORT MEMORY

Node 1: Data usage is 5%(176 32K pages of total 3200)

Node 1: Index usage is 0%(76 8K pages of total 12832)

Node 2: Data usage is 5%(176 32K pages of total 3200)

Node 2: Index usage is 0%(76 8K pages of total 12832)

Node 3: Data usage is 2%(80 32K pages of total 3200)

Node 3: Index usage is 0%(51 8K pages of total 12832)

Node 4: Data usage is 2%(80 32K pages of total 3200)

Node 4: Index usage is 0%(50 8K pages of total 12832)
```

### Note

Since only one DDL operation on NDBCLUSTER tables can be executed at a time, you must wait for each ALTER ONLINE TABLE ... REORGANIZE PARTITION statement to finish before issuing the next one.

It is not necessary to issue ALTER ONLINE TABLE ... REORGANIZE PARTITION statements for NDBCLUSTER tables created *after* the new data nodes have been added; data added to such tables is

distributed among all data nodes automatically. However, in NDBCLUSTER tables that existed *prior to* the addition of the new nodes, neither existing nor new data is distributed using the new nodes until these tables have been reorganized using ALTER ONLINE TABLE ... REORGANIZE PARTITION.

**Alternative procedure, without rolling restart.** It is possible to avoid the need for a rolling restart by configuring the extra data nodes, but not starting them, when first starting the cluster. We assume, as before, that you wish to start with two data nodes—nodes 1 and 2—in one node group and later to expand the cluster to four data nodes, by adding a second node group consisting of nodes 3 and 4:

```
[ndbd default]
DataMemory = 100M
IndexMemory = 100M
NoOfReplicas = 2
DataDir = /usr/local/mysql/var/mysql-cluster
Id = 1
HostName = 192.168.0.1
[ndbd]
Td = 2
HostName = 192.168.0.2
[ndbd]
Id = 3
HostName = 192.168.0.3
Nodegroup = 65536  # MySQL Cluster NDB 7.0.24 and later;
                   # MySQL Cluster NDB 7.1.13 and later
[ndbd]
Id = 4
HostName = 192.168.0.4
Nodegroup = 65536 # MySQL Cluster NDB 7.0.24 and later;
                   # MySQL Cluster NDB 7.1.13 and later
HostName = 192.168.0.10
Id = 10
[api]
Id=20
HostName = 192.168.0.20
[api]
Td = 21
HostName = 192.168.0.21
```

Prior to MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, you must perform the initial start of the cluster using the --nowait-nodes option with ndbd (or ndbmtd in MySQL Cluster NDB 7.0.4 and later) for each of the data nodes that you wish to have online immediately, so that the cluster does not wait for the remaining nodes to start:

```
shell> ndbd -c 192.168.0.10 --initial --nowait-nodes=3,4
```

Beginning with MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13, the data nodes to be brought online at a later time (nodes 3 and 4) can be configured with NodeGroup = 65536, in which case it is not necessary to start the nodes to be started immediately (nodes 1 and 2) with the --nowait-nodes option, so nodes 1 and 2 can each be started as shown here:

```
shell> ndbd -c 192.168.0.10 --initial
```

The data nodes configured with NodeGroup = 65536 are treated by the management server as though you had started nodes 1 and 2 using --nowait-nodes=3, 4 after waiting for a period of time determined by the setting for the StartNoNodeGroupTimeout data node configuration parameter (also introduced in MySQL Cluster NDB 7.0.24 and MySQL Cluster NDB 7.1.13). By default, this is 15 seconds (15000 milliseconds).

#### Note

StartNoNodegroupTimeout must be the same for all data nodes in the cluster; for this reason, you should always set it in the <code>[ndbd default]</code> section of the <code>config.ini</code> file, rather than for individual data nodes.

When you are ready to add the second node group, you need only perform the following additional steps:

1. Start data nodes 3 and 4, invoking the data node process once for each new node:

```
shell> ndbd -c 192.168.0.10 --initial
```

2. Issue the appropriate CREATE NODEGROUP command in the management client:

```
ndb_mgm> CREATE NODEGROUP 3,4
```

3. In the mysql client, issue ALTER ONLINE TABLE ... REORGANIZE PARTITION and OPTIMIZE TABLE statements for each existing NDBCLUSTER table. (As noted elsewhere in this section, existing MySQL Cluster tables cannot use the new nodes for data distribution until this has been done.)

# 7.14 Distributed MySQL Privileges for MySQL Cluster

MySQL Cluster NDB 7.2 introduces support for distributing MySQL users and privileges across all SQL nodes in a MySQL Cluster. This support is not enabled by default; you should follow the procedure outlined in this section in order to do so.

Normally, each MySQL server's user privilege tables in the mysql database must use the MyISAM storage engine, which means that a user account and its associated privileges created on one SQL node are not available on the cluster's other SQL nodes. In MySQL Cluster NDB 7.2 and later, an SQL file ndb\_dist\_priv.sql is provided with the MySQL Cluster distribution. This file can be found in the share/mysql directory in the MySQL installation directory.

The first step in enabling distributed privileges is to load this script into a MySQL Server that functions as an SQL node (which we refer to after this as the *target* SQL node or MySQL Server). You can do this by executing the following command from the system shell on the target SQL node after changing to its MySQL installation directory (where *options* stands for any additional options needed to connect to this SQL node):

```
shell> mysql options -uroot < share/mysql/ndb_dist_priv.sql
```

Importing ndb\_dist\_priv.sql creates a number of stored routines (six stored procedures and one stored function) in the mysql database on the target SQL node. After connecting to the SQL node in the mysql client (as the MySQL root user), you can verify that these were created as shown here:

```
mysql> SELECT ROUTINE_NAME, ROUTINE_SCHEMA, ROUTINE_TYPE
   -> FROM INFORMATION_SCHEMA.ROUTINES
        WHERE ROUTINE_NAME LIKE 'mysql_cluster%'
   -> ORDER BY ROUTINE_TYPE;
 ROUTINE NAME
                                          ROUTINE_SCHEMA | ROUTINE_TYPE
                                          mysql
 mysgl cluster privileges are distributed
                                                          FUNCTION
 mysql_cluster_backup_privileges
                                           mysql
                                                          PROCEDURE
                                                          PROCEDURE
 mysql_cluster_move_grant_tables
                                           mysql
                                                          PROCEDURE
 mysql_cluster_move_privileges
                                            mvsal
 mysql_cluster_restore_local_privileges
                                          mysql
                                                           PROCEDURE
 mysql_cluster_restore_privileges
                                                           PROCEDURE
                                           mysql
```

The stored procedure named <code>mysql\_cluster\_move\_privileges</code> creates backup copies of the existing privilege tables, then converts them to <code>NDB</code>.

mysql\_cluster\_move\_privileges performs the backup and conversion in two steps. The first step is to call mysql cluster backup privileges, which creates two sets of copies in the mysql database:

- A set of local copies that use the MyISAM storage engine. Their names are generated by adding the suffix backup to the original privilege table names.
- A set of distributed copies that use the NDBCLUSTER storage engine. These tables are named by prefixing ndb\_ and appending \_backup to the names of the original tables.

After the copies are created, mysql\_cluster\_move\_privileges invokes
mysql\_cluster\_move\_grant\_tables, which contains the ALTER TABLE ... ENGINE = NDB
statements that convert the mysql system tables to NDB.

Normally, you should not invoke either mysql\_cluster\_backup\_privileges or mysql\_cluster\_move\_grant\_tables manually; these stored procedures are intended only for use by mysql\_cluster\_move\_privileges.

Although the original privilege tables are backed up automatically, it is always a good idea to create backups manually of the existing privilege tables on all affected SQL nodes before proceeding. You can do this using mysqldump in a manner similar to what is shown here:

```
shell> mysqldump options -uroot \
   mysql host user db tables_priv columns_priv procs_priv proxies_priv > backup_file
```

To perform the conversion, you must be connected to the target SQL node using the mysql client (again, as the MySQL root user). Invoke the stored procedure like this:

```
mysql> CALL mysql.mysql_cluster_move_privileges();
Query OK, 0 rows affected (22.32 sec)
```

Depending on the number of rows in the privilege tables, this procedure may take some time to execute. If some of the privilege tables are empty, you may see one or more No data - zero rows fetched, selected, or processed warnings when mysql\_cluster\_move\_privileges returns. In such cases, the warnings may be safely ignored. To verify that the conversion was successful, you can use the stored function mysql\_cluster\_privileges are distributed as shown here:

mysql\_cluster\_privileges\_are\_distributed checks for the existence of the distributed privilege tables and returns 1 if all of the privilege tables are distributed; otherwise, it returns 0.

You can verify that the backups have been created using a query such as this one:

```
mysql> SELECT TABLE_NAME, ENGINE FROM INFORMATION_SCHEMA.TABLES
    -> WHERE TABLE_SCHEMA = 'mysql' AND TABLE_NAME LIKE '%backup'
    ->
           ORDER BY ENGINE;
                              ENGINE
 TABLE_NAME
 host_backup | MyISAM db_backup | MyISAM columns_priv_backup | MyISAM user_backup | MyISAM
 tables_priv_backup | MyISAM proxies_priv_backup | MyISAM procs_priv_backup | MyISAM ndb_user_backup | ndbcluster
 ndb_tables_priv_backup | ndbcluster
 ndb_proxies_priv_backup | ndbcluster
 ndb_procs_priv_backup | ndbcluster
                       | ndbcluster
| ndbcluster
  ndb_host_backup
 ndb db backup
| ndb_columns_priv_backup | ndbcluster |
14 rows in set (0.00 sec)
```

Once the conversion to distributed privileges has been made, any time a MySQL user account is created, dropped, or has its privileges updated on any SQL node, the changes take effect immediately on all other MySQL servers attached to the cluster. Once privileges are distributed, any new MySQL Servers that connect to the cluster automatically participate in the distribution.

#### Note

For clients connected to SQL nodes at the time that mysql\_cluster\_move\_privileges is executed, you may need to execute FLUSH PRIVILEGES on those SQL nodes, or to disconnect and then reconnect the clients, in order for those clients to be able to see the changes in privileges.

All MySQL user privileges are distributed across all connected MySQL Servers. This includes any privileges associated with views and stored routines, even though distribution of views and stored routines themselves is not currently supported.

In the event that an SQL node becomes disconnected from the cluster while mysql\_cluster\_move\_privileges is running, you must drop its privilege tables after reconnecting to the cluster, using a statement such as DROP TABLE IF EXISTS mysql.user mysql.db 
mysql.tables\_priv mysql.columns\_priv mysql.procs\_priv. This causes the SQL node to use the shared privilege tables rather than its own local versions of them. This is not needed when connecting a new SQL node to the cluster for the first time.

In the event of an initial restart of the entire cluster (all data nodes shut down, then started again with <code>--initial</code>), the shared privilege tables are lost. If this happens, you can restore them using the original target SQL node either from the backups made by <code>mysql\_cluster\_move\_privileges</code> or from a dump file created with <code>mysqldump</code>. If you need to use a new MySQL Server to perform the restoration, you should start it with <code>--skip-grant-tables</code> when connecting to the cluster for the first time; after this, you can restore the privilege tables locally, then distribute them again using <code>mysql\_cluster\_move\_privileges</code>. After restoring and distributing the tables, you should restart this MySQL Server without the <code>--skip-grant-tables</code> option.

You can also restore the distributed tables using ndb\_restore --restore-privilege-tables [335] from a backup made using START BACKUP in the ndb\_mgm client. (The MyISAM tables created by mysql cluster move privileges are not backed up by the START BACKUP command.)

ndb\_restore does not restore the privilege tables by default; the --restore-privilege-tables [335] option causes it to do so.

You can restore the SQL node's local privileges using either of two procedures. mysql\_cluster\_restore\_privileges works as follows:

- 1. If copies of the mysql.ndb\_\*\_backup tables are available, attempt to restore the system tables from these.
- 2. Otherwise, attempt to restore the system tables from the local backups named \*\_backup (without the ndb\_ prefix).

The other procedure, named mysql\_cluster\_restore\_local\_privileges, restores the system tables from the local backups only, without checking the ndb\_\* backups.

The system tables re-created by mysql\_cluster\_restore\_privileges or mysql\_cluster\_restore\_local\_privileges use the MySQL server default storage engine; they are not shared or distributed in any way, and do not use MySQL Cluster's NDB storage engine.

The additional stored procedure <code>mysql\_cluster\_restore\_privileges\_from\_local</code> is intended for the use of <code>mysql\_cluster\_restore\_privileges</code> and <code>mysql\_cluster\_restore\_local privileges</code>. It should not be invoked directly.

## **Important**

Applications that access MySQL Cluster data directly, including NDB API and ClusterJ applications, are not subject to the MySQL privilege system. This means that, once you have distributed the grant tables, they can be freely accessed by such applications, just as they can any other NDB tables. In particular, you should keep in mind that NDB API and ClusterJ applications can read and write user names, host names, password hashes, and any other contents of the distributed grant tables without any restrictions.

# 7.15 NDB API Statistics Counters and Variables

Beginning with MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11, a number of types of statistical counters relating to actions performed by or affecting Ndb objects are added. Such actions include starting and closing (or aborting) transactions; primary key and unique key operations; table, range, and pruned scans; threads blocked while waiting for the completion of various operations; and data and events sent and received by NDBCLUSTER. The counters are incremented inside the NDB kernel whenever NDB API calls are made or data is sent to or received by the data nodes. mysqld exposes these counters as system status variables; their values can be read in the output of SHOW STATUS, or by querying the INFORMATION\_SCHEMA.SESSION\_STATUS or INFORMATION\_SCHEMA.GLOBAL\_STATUS table. By comparing the values before and after statements operating on NDB tables, you can observe the corresponding actions taken on the API level, and thus the cost of performing the statement.

You can list all of these status variables using the following SHOW STATUS statement:

```
Ndb_api_bytes_received_count_session
                                           0
 Ndb_api_trans_start_count_session
 Ndb_api_trans_commit_count_session
                                           0
 Ndb_api_trans_abort_count_session
                                           0
 Ndb_api_trans_close_count_session
                                           1 0
 Ndb_api_pk_op_count_session
 Ndb_api_uk_op_count_session
                                           0
 Ndb_api_table_scan_count_session
                                           0
 Ndb_api_range_scan_count_session
 Ndb_api_pruned_scan_count_session
                                           1 0
 Ndb_api_scan_batch_count_session
                                           1 0
 Ndb_api_read_row_count_session
 Ndb_api_trans_local_read_row_count_session | 0
 Ndb_api_event_data_count_injector
                                             0
 Ndb_api_event_nondata_count_injector
                                           0
 Ndb_api_event_bytes_count_injector
                                           0
 Ndb_api_wait_exec_complete_count_slave
 Ndb_api_wait_scan_result_count_slave
Ndb_api_wait_meta_request_count_slave
                                           0
                                           0
 Ndb_api_wait_nanos_count_slave
 Ndb_api_bytes_sent_count_slave
                                           0
 Ndb_api_bytes_received_count_slave
                                           0
 Ndb_api_trans_start_count_slave
                                           0
 Ndb_api_trans_commit_count_slave
 Ndb_api_trans_abort_count_slave
                                           0
 Ndb_api_trans_close_count_slave
                                           0
 Ndb_api_pk_op_count_slave
                                           0
 Ndb_api_uk_op_count_slave
 Ndb_api_table_scan_count_slave
                                           0
                                           0
 Ndb_api_range_scan_count_slave
 Ndb_api_pruned_scan_count_slave
 Ndb_api_scan_batch_count_slave
                                           1 0
 Ndb_api_read_row_count_slave
                                           1 0
 Ndb_api_trans_local_read_row_count_slave | 0
 Ndb_api_wait_exec_complete_count
                                           | 2
 Ndb_api_wait_scan_result_count
 Ndb_api_wait_meta_request_count
                                           27
                                           45612023
 Ndb_api_wait_nanos_count
 Ndb_api_bytes_sent_count
                                           992
 Ndb_api_bytes_received_count
                                           9640
 Ndb_api_trans_start_count
                                             2
 Ndb_api_trans_commit_count
 Ndb_api_trans_abort_count
                                            0
 Ndb_api_trans_close_count
                                             2
 Ndb_api_pk_op_count
                                           1 1
 Ndb_api_uk_op_count
                                            Ω
 Ndb_api_table_scan_count
                                             1
 Ndb_api_range_scan_count
                                           0
 Ndb_api_pruned_scan_count
                                           1 0
 Ndb_api_scan_batch_count
                                           1
 Ndb_api_read_row_count
 Ndb_api_trans_local_read_row_count
                                           1
 Ndb_api_event_data_count
                                             0
 Ndb_api_event_nondata_count
                                           1 0
 Ndb_api_event_bytes_count
                                           1 0
60 rows in set (0.02 sec)
```

These status variables are also available from the SESSION\_STATUS and GLOBAL\_STATUS tables of the INFORMATION SCHEMA database, as shown here:

```
NDB_API_WAIT_EXEC_COMPLETE_COUNT_SESSION
                                              0
  NDB_API_WAIT_SCAN_RESULT_COUNT_SESSION
  NDB_API_WAIT_META_REQUEST_COUNT_SESSION
                                              1
  NDB_API_WAIT_NANOS_COUNT_SESSION
                                              8144375
 NDB_API_BYTES_SENT_COUNT_SESSION
                                             68
 NDB_API_BYTES_RECEIVED_COUNT_SESSION
                                             84
 NDB_API_TRANS_START_COUNT_SESSION
                                              1
 NDB_API_TRANS_COMMIT_COUNT_SESSION
                                              1
  NDB_API_TRANS_ABORT_COUNT_SESSION
                                              0
 NDB_API_TRANS_CLOSE_COUNT_SESSION
                                              1
 NDB_API_PK_OP_COUNT_SESSION
                                              1
 NDB_API_UK_OP_COUNT_SESSION
                                              0
                                              0
 NDB_API_TABLE_SCAN_COUNT_SESSION
  NDB API RANGE SCAN COUNT SESSION
                                              0
  NDB_API_PRUNED_SCAN_COUNT_SESSION
                                              0
 NDB_API_SCAN_BATCH_COUNT_SESSION
                                              Ω
 NDB_API_READ_ROW_COUNT_SESSION
                                              1
 NDB_API_TRANS_LOCAL_READ_ROW_COUNT_SESSION |
 NDB_API_EVENT_DATA_COUNT_INJECTOR
                                              0
  NDB_API_EVENT_NONDATA_COUNT_INJECTOR
                                              0
 NDB_API_EVENT_BYTES_COUNT_INJECTOR
                                              0
 NDB API WAIT EXEC COMPLETE COUNT SLAVE
                                              0
 NDB_API_WAIT_SCAN_RESULT_COUNT_SLAVE
                                              0
 NDB_API_WAIT_META_REQUEST_COUNT_SLAVE
                                              0
 NDB_API_WAIT_NANOS_COUNT_SLAVE
                                              0
  NDB_API_BYTES_SENT_COUNT_SLAVE
                                              0
 NDB_API_BYTES_RECEIVED_COUNT_SLAVE
                                              0
 NDB_API_TRANS_START_COUNT_SLAVE
                                              0
 NDB_API_TRANS_COMMIT_COUNT_SLAVE
                                              0
                                              0
 NDB_API_TRANS_ABORT_COUNT_SLAVE
  NDB_API_TRANS_CLOSE_COUNT_SLAVE
                                              0
 NDB_API_PK_OP_COUNT_SLAVE
                                              0
 NDB_API_UK_OP_COUNT_SLAVE
                                              0
 NDB_API_TABLE_SCAN_COUNT_SLAVE
                                              0
 NDB_API_RANGE_SCAN_COUNT_SLAVE
  NDB_API_PRUNED_SCAN_COUNT_SLAVE
                                              0
  NDB_API_SCAN_BATCH_COUNT_SLAVE
                                              0
 NDB_API_READ_ROW_COUNT_SLAVE
                                              0
 NDB_API_TRANS_LOCAL_READ_ROW_COUNT_SLAVE
                                              0
 NDB_API_WAIT_EXEC_COMPLETE_COUNT
                                              4
 NDB_API_WAIT_SCAN_RESULT_COUNT
                                              3
  NDB_API_WAIT_META_REQUEST_COUNT
                                              28
 NDB_API_WAIT_NANOS_COUNT
                                              53756398
 NDB_API_BYTES_SENT_COUNT
                                              1060
 NDB_API_BYTES_RECEIVED_COUNT
                                              9724
 NDB_API_TRANS_START_COUNT
                                              3
  NDB_API_TRANS_COMMIT_COUNT
                                              2
  NDB_API_TRANS_ABORT_COUNT
                                              0
 NDB_API_TRANS_CLOSE_COUNT
                                              3
 NDB_API_PK_OP_COUNT
                                              2
 NDB_API_UK_OP_COUNT
                                              0
 NDB_API_TABLE_SCAN_COUNT
                                              1
  NDB_API_RANGE_SCAN_COUNT
                                              0
 NDB_API_PRUNED_SCAN_COUNT
                                              0
 NDB_API_SCAN_BATCH_COUNT
                                              0
 NDB_API_READ_ROW_COUNT
                                               2
 NDB_API_TRANS_LOCAL_READ_ROW_COUNT
                                              2
 NDB_API_EVENT_DATA_COUNT
                                              0
  NDB_API_EVENT_NONDATA_COUNT
                                              0
 NDB_API_EVENT_BYTES_COUNT
                                              0
60 rows in set (0.00 sec)
mysql> SELECT * FROM INFORMATION_SCHEMA.GLOBAL_STATUS
          WHERE VARIABLE_NAME LIKE 'ndb_api%';
  _______
 VARIABLE NAME
                                            | VARIABLE_VALUE |
```

NDB_API_WAIT_EXEC_COMPLETE_COUNT_SESSION	2
NDB_API_WAIT_SCAN_RESULT_COUNT_SESSION	0
NDB_API_WAIT_META_REQUEST_COUNT_SESSION	1
NDB_API_WAIT_NANOS_COUNT_SESSION	8144375
NDB_API_BYTES_SENT_COUNT_SESSION	68
NDB_API_BYTES_RECEIVED_COUNT_SESSION	84
NDB_API_TRANS_START_COUNT_SESSION	1
NDB_API_TRANS_COMMIT_COUNT_SESSION	1
NDB_API_TRANS_ABORT_COUNT_SESSION	0
NDB_API_TRANS_CLOSE_COUNT_SESSION	
NDB_API_PK_OP_COUNT_SESSION	1
NDB_API_UK_OP_COUNT_SESSION	
NDB_API_TABLE_SCAN_COUNT_SESSION	0
NDB_API_RANGE_SCAN_COUNT_SESSION	0
NDB_API_PRUNED_SCAN_COUNT_SESSION	0
NDB_API_SCAN_BATCH_COUNT_SESSION	0
NDB_API_READ_ROW_COUNT_SESSION	1
NDB_API_TRANS_LOCAL_READ_ROW_COUNT_SESSION	1
NDB_API_EVENT_DATA_COUNT_INJECTOR	0
NDB_API_EVENT_NONDATA_COUNT_INJECTOR	i o
NDB_API_EVENT_BYTES_COUNT_INJECTOR	0
NDB_API_WAIT_EXEC_COMPLETE_COUNT_SLAVE	0
NDB_API_WAIT_SCAN_RESULT_COUNT_SLAVE	0
	0
NDB_API_WAIT_META_REQUEST_COUNT_SLAVE	
NDB_API_WAIT_NANOS_COUNT_SLAVE	
NDB_API_BYTES_SENT_COUNT_SLAVE	0
NDB_API_BYTES_RECEIVED_COUNT_SLAVE	0
NDB_API_TRANS_START_COUNT_SLAVE	0
NDB_API_TRANS_COMMIT_COUNT_SLAVE	0
NDB_API_TRANS_ABORT_COUNT_SLAVE	0
NDB_API_TRANS_CLOSE_COUNT_SLAVE	0
NDB_API_PK_OP_COUNT_SLAVE	0
NDB_API_UK_OP_COUNT_SLAVE	
NDB_API_TABLE_SCAN_COUNT_SLAVE	j o
NDB_API_RANGE_SCAN_COUNT_SLAVE	0
NDB_API_PRUNED_SCAN_COUNT_SLAVE	0
NDB_API_SCAN_BATCH_COUNT_SLAVE	0
NDB_API_READ_ROW_COUNT_SLAVE	0
NDB_API_TRANS_LOCAL_READ_ROW_COUNT_SLAVE	
NDB_API_WAIT_EXEC_COMPLETE_COUNT	
NDB_API_WAIT_SCAN_RESULT_COUNT	3
NDB_API_WAIT_META_REQUEST_COUNT	28
NDB_API_WAIT_NANOS_COUNT	53756398
NDB_API_BYTES_SENT_COUNT	1060
NDB_API_BYTES_RECEIVED_COUNT	9724
NDB_API_TRANS_START_COUNT	3
NDB_API_TRANS_COMMIT_COUNT	j 2
NDB_API_TRANS_ABORT_COUNT	j o
NDB_API_TRANS_CLOSE_COUNT	3
NDB_API_PK_OP_COUNT	2
NDB_API_UK_OP_COUNT	2
NDB_API_TABLE_SCAN_COUNT	
NDB_API_RANGE_SCAN_COUNT	
NDB_API_PRUNED_SCAN_COUNT	
NDB_API_SCAN_BATCH_COUNT	0
NDB_API_READ_ROW_COUNT	2
NDB_API_TRANS_LOCAL_READ_ROW_COUNT	2
NDB_API_EVENT_DATA_COUNT	0
NDB_API_EVENT_NONDATA_COUNT	0
1122_11 1_2 12111_1011211111_000111	
NDB_API_EVENT_BYTES_COUNT	

Each Ndb object has its own counters. NDB API applications can read the values of the counters for use in optimization or monitoring. For multi-threaded clients which use more than one Ndb object

concurrently, it is also possible to obtain a summed view of counters from all Ndb objects belonging to a given Ndb cluster connection.

Four sets of these counters are exposed. One set applies to the current session only; the other 3 are global. This is in spite of the fact that their values can be obtained as either session or global status variables in the <code>mysql</code> client. This means that specifying the <code>SESSION</code> or <code>GLOBAL</code> keyword with <code>SHOW</code> STATUS has no effect on the values reported for NDB API statistics status variables, and the value for each of these variables is the same whether the value is obtained from the equivalent column of the <code>SESSION\_STATUS</code> or the <code>GLOBAL\_STATUS</code> table.

#### Session counters (session specific)

Session counters relate to the Ndb objects in use by (only) the current session. Use of such objects by other MySQL clients does not influence these counts.

In order to minimize confusion with standard MySQL session variables, we refer to the variables that correspond to these NDB API session counters as "\_session variables", with a leading underscore.

#### • Slave counters (global)

This set of counters relates to the Ndb objects used by the replication slave SQL thread, if any. If this mysqld does not act as a replication slave, or does not use NDB tables, then all of these counts are 0.

We refer to the related status variables as "\_slave variables" (with a leading underscore).

### • Injector counters (global)

Injector counters relate to the Ndb object used to listen to cluster events by the binlog injector thread. Even when not writing a binary log, mysqld processes attached to a MySQL Cluster continue to listen for some events, such as schema changes.

We refer to the status variables that correspond to NDB API injector counters as "\_injector variables" (with a leading underscore).

### • Server (Global) counters (global)

This set of counters relates to all Ndb objects currently used by this mysqld. This includes all MySQL client applications, the slave SQL thread (if any), the binlog injector, and the NDB utility thread.

We refer to the status variables that correspond to these counters as "global variables" or "mysqld-level variables".

You can obtain values for a particular set of variables by additionally filtering for the substring session, slave, or injector in the variable name (along with the common prefix Ndb\_api). For \_session variables, this can be done as shown here:

```
Ndb_api_trans_close_count_session
 Ndb_api_pk_op_count_session
                                        | 1
 Ndb_api_uk_op_count_session
                                        0
 Ndb_api_table_scan_count_session
                                        0
 Ndb_api_range_scan_count_session
                                        0
 Ndb_api_pruned_scan_count_session
 Ndb_api_scan_batch_count_session
                                        0
 Ndb_api_read_row_count_session
                                        1
 Ndb_api_trans_local_read_row_count_session | 1
18 rows in set (0.50 sec)
```

To obtain a listing of the NDB API mysqld-level status variables, filter for variable names beginning with ndb\_api and ending in \_count, like this:

```
mysql> SELECT * FROM INFORMATION_SCHEMA.SESSION_STATUS
   -> WHERE VARIABLE_NAME LIKE 'ndb_api%count';
NDB_API_WAIT_EXEC_COMPLETE_COUNT | 4
 NDB_API_WAIT_SCAN_RESULT_COUNT | 3
NDB_API_WAIT_META_REQUEST_COUNT | 28
 NDB_API_WAIT_NANOS_COUNT | 53756398

NDB_API_BYTES_SENT_COUNT | 1060

NDB_API_BYTES_RECEIVED_COUNT | 9724

NDB_API_TRANS_START_COUNT | 3
 NDB_API_TRANS_COMMIT_COUNT
                                        | 2
 NDB_API_TRANS_ABORT_COUNT
NDB_API_TRANS_CLOSE_COUNT
NDB_API_PK_OP_COUNT
                                         | 0
                                          2
                                          0
 NDB_API_UK_OP_COUNT
                                      | 1
 NDB_API_TABLE_SCAN_COUNT
 NDB_API_RANGE_SCAN_COUNT
                                           0
 NDB_API_PRUNED_SCAN_COUNT
                                         | 0
 NDB_API_SCAN_BATCH_COUNT
                                          | 0
 NDB API READ ROW COUNT
 NDB_API_TRANS_LOCAL_READ_ROW_COUNT | 2
 NDB_API_EVENT_DATA_COUNT | 0
 NDB_API_EVENT_NONDATA_COUNT | 0
NDB_API_EVENT_BYTES_COUNT | 0
21 rows in set (0.09 sec)
```

Not all counters are reflected in all 4 sets of status variables. For the event counters

DataEventsRecvdCount, NondataEventsRecvdCount, and EventBytesRecvdCount, only

\_injector and mysqld-level NDB API status variables are available:

\_injector status variables are not implemented for any other NDB API counters, as shown here:

The names of the status variables can easily be associated with the names of the corresponding counters. Each NDB API statistics counter is listed in the following table with a description as well as the names of any MySQL server status variables corresponding to this counter.

	Description
Counter Name	Status Variables (by statistic type):
	• Session
	• Slave
	Injector
	• Server
	Number of times thread has been blocked while waiting for execution of an operation to complete. Includes all <code>execute()</code> calls as well as implicit executes for blob operations and auto-increment not visible to clients.
   WaitExecCompleteCount	• Ndb_api_wait_exec_complete_count_session
_	• Ndb_api_wait_exec_complete_count_slave
	• [none]
	• Ndb_api_wait_exec_complete_count
	Number of times thread has been blocked while waiting for a scan- based signal, such waiting for additional results, or for a scan to close.
	• Ndb_api_wait_scan_result_count_session
WaitScanResultCount	• Ndb_api_wait_scan_result_count_slave
	• [none]
	• Ndb_api_wait_scan_result_count
WaitMetaRequestCount	Number of times thread has been blocked waiting for a metadata- based signal; this can occur when waiting for a DDL operation or for an epoch to be started (or ended).
	Ndb_api_wait_meta_request_count_session
	• Ndb_api_wait_meta_request_count_slave
	• [none]
	• Ndb_api_wait_meta_request_count

	Description
	Status Variables (by statistic type):
	• Session
Counter Name	• Slave
	• Injector
	• Server
	Total time (in nanoseconds) spent waiting for some type of signal from the data nodes.
	Ndb_api_wait_nanos_count_session
WaitNanosCount	• Ndb_api_wait_nanos_count_slave
	• [none]
	• Ndb_api_wait_nanos_count
	Amount of data (in bytes) sent to the data nodes
	Ndb_api_bytes_sent_count_session
BytesSentCount	• Ndb_api_bytes_sent_count_slave
	• [none]
	Ndb_api_bytes_sent_count
	Amount of data (in bytes) received from the data nodes
	Ndb_api_bytes_received_count_session
BytesRecvdCount	• Ndb_api_bytes_received_count_slave
	• [none]
	Ndb_api_bytes_received_count
	Number of transactions started.
	• Ndb_api_trans_start_count_session
TransStartCount	• Ndb_api_trans_start_count_slave
	• [none]
	• Ndb_api_trans_start_count
	Number of transactions committed.
	• Ndb_api_trans_commit_count_session
TransCommitCount	• Ndb_api_trans_commit_count_slave
	• [none]
	• Ndb_api_trans_commit_count
TransAbortCount	Number of transactions aborted.

	Description
	Status Variables (by statistic type):
	• Session
Counter Name	• Slave
	• Injector
	• Server
	• Ndb_api_trans_abort_count_session
	• Ndb_api_trans_abort_count_slave
	• [none]
	• Ndb_api_trans_abort_count
	Number of transactions aborted. (This value may be greater than the sum of TransCommitCount and TransAbortCount.)
	• Ndb_api_trans_close_count_session
TransCloseCount	• Ndb_api_trans_close_count_slave
	• [none]
	• Ndb_api_trans_close_count
	Number of operations based on or using primary keys. This count includes blob-part table operations, implicit unlocking operations, and auto-increment operations, as well as primary key operations normally visible to MySQL clients.
PkOpCount	• Ndb_api_pk_op_count_session
- Trop count	• Ndb_api_pk_op_count_slave
	• [none]
	• Ndb_api_pk_op_count
	Number of operations based on or using unique keys.
	• Ndb_api_uk_op_count_session
UkOpCount	• Ndb_api_uk_op_count_slave
	• [none]
	• Ndb_api_uk_op_count
	Number of table scans that have been started. This includes scans of internal tables.
TableScanCount	• Ndb_api_table_scan_count_session
	• Ndb_api_table_scan_count_slave
	• [none]

	Description
Counter Name	Status Variables (by statistic type):
	Session
	• Slave
	• Injector
	• Server
	• Ndb_api_table_scan_count
	Number of range scans that have been started.
	• Ndb_api_range_scan_count_session
RangeScanCount	• Ndb_api_range_scan_count_slave
	• [none]
	• Ndb_api_range_scan_count
	Number of scans that have been pruned to a single partition.
	Ndb_api_pruned_scan_count_session
PrunedScanCount	• Ndb_api_pruned_scan_count_slave
	• [none]
	Ndb_api_pruned_scan_count
	Number of batches of rows received. (A <u>batch</u> in this context is a set of scan results from a single fragment.)
	• Ndb_api_scan_batch_count_session
ScanBatchCount	• Ndb_api_scan_batch_count_slave
	• [none]
	Ndb_api_scan_batch_count
	Total number of rows that have been read. Includes rows read using primary key, unique key, and scan operations.
	• Ndb_api_read_row_count_session
ReadRowCount	• Ndb_api_read_row_count_slave
	• [none]
	• Ndb_api_read_row_count
	Number of rows read from the data same node on which the transaction was being run.
TransLocalReadRowCount	• Ndb_api_trans_local_read_row_count_session
	• Ndb_api_trans_local_read_row_count_slave
	• [none]

	Description
	Status Variables (by statistic type):
	Session
Counter Name	Clave
	Slave
	• Injector
	• Server
	• Ndb_api_trans_local_read_row_count
	Number of row change events received.
	• [none]
DataEventsRecvdCount	• [none]
	• Ndb_api_event_data_count_injector
	Ndb_api_event_data_count
	Number of events received, other than row change events.
	• [none]
NondataEventsRecvdCount	• [none]
	• Ndb_api_event_nondata_count_injector
	• Ndb_api_event_nondata_count
	Number of bytes of events received.
	• [none]
EventBytesRecvdCount	• [none]
	• Ndb_api_event_bytes_count_injector
	• Ndb_api_event_bytes_count

To see all counts of committed transactions—that is, all TransCommitCount counter status variables—you can filter the results of SHOW STATUS for the substring trans\_commit\_count, like this:

From this you can determine that 1 transaction has been committed in the current mysql client session, and 2 transactions have been committed on this mysqld since it was last restarted.

You can see how various NDB API counters are incremented by a given SQL statement by comparing the values of the corresponding \_session status variables immediately before and after performing the

statement. In this example, after getting the initial values from SHOW STATUS, we create in the test database an NDB table, named t, that has a single column:

```
mysql> SHOW STATUS LIKE 'ndb_api%session%';
 Variable name
                                  | Value
 Ndb_api_wait_exec_complete_count_session | 2
 Ndb_api_wait_scan_result_count_session
                                                   0
 Ndb_api_wait_meta_request_count_session | 3
 Ndb_api_wait_nanos_count_session | 820705
Ndb_api_bytes_sent_count_session | 132
Ndb_api_bytes_received_count_session | 372
Ndb_api_trans_start_count_session | 1
 Ndb_api_trans_start_count_session
                                                   1 1
 Ndb_api_trans_commit_count_session
 Ndb_api_trans_abort_count_session
                                                   0
 Ndb_api_trans_close_count_session
                                                   | 1
 Ndb_api_pk_op_count_session
 Ndb_api_uk_op_count_session
                                                   | 0
 Ndb_api_table_scan_count_session
Ndb_api_range_scan_count_session
Ndb_api_pruned_scan_count_session
                                                   1 0
                                                   0
                                                   0
 Ndb_api_scan_batch_count_session
 Ndb_api_read_row_count_session
                                                     1
 Ndb_api_trans_local_read_row_count_session | 1
18 rows in set (0.00 sec)
mysql> USE test;
Database changed
mysql> CREATE TABLE t (c INT) ENGINE NDBCLUSTER;
Query OK, 0 rows affected (0.85 sec)
```

Now you can execute a new SHOW STATUS statement and observe the changes, as shown here (with the changed rows highlighted in the output):

```
mysql> SHOW STATUS LIKE 'ndb_api%session%';
                                         | Value
 Variable name
 Ndb_api_wait_exec_complete_count_session | 8
 Ndb_api_wait_scan_result_count_session
 Ndb_api_wait_meta_request_count_session | 17
 Ndb_api_wait_nanos_count_session | 706871709
 Ndb_api_bytes_sent_count_session
 Ndb_api_bytes_received_count_session
                                               | 3844
 Ndb_api_trans_start_count_session
 Ndb_api_trans_commit_count_session
 Ndb_api_trans_abort_count_session
                                                0
 Ndb_api_trans_close_count_session
                                               | 4
 Ndb_api_pk_op_count_session
 Ndb_api_uk_op_count_session
 Ndb_api_table_scan_count_session
 Ndb_api_table_scan_count_session
Ndb_api_range_scan_count_session
Ndb_api_pruned_scan_count_session
Ndb_api_scan_batch_count_session
Ndb_api_read_row_count_session
                                                0
                                                0
 Ndb_api_read_row_count_session
 Ndb_api_trans_local_read_row_count_session | 1
18 rows in set (0.00 sec)
```

Similarly, you can see the changes in the NDB API statistics counters caused by inserting a row into t: Insert the row, then run the same SHOW STATUS statement used in the previous example, as shown here:

```
mysql> INSERT INTO t VALUES (100);
Query OK, 1 row affected (0.00 sec)
mysql> SHOW STATUS LIKE 'ndb_api%session%';
| Variable_name
                                                | Value
| Ndb_api_wait_exec_complete_count_session | 11
| Ndb_api_wait_neta_request_count_session | 20
| Ndb_api_wait_nanos_count_session | 707370418
| Ndb_api_bytes_sent_count_session | 2724
| Ndb_api_bytes_received_count_session |
                                               / 7
| Ndb_api_trans_start_count_session
 Ndb_api_trans_commit_count_session
                                               16
                                                0
 Ndb_api_trans_abort_count_session
| Ndb_api_trans_close_count_session
                                                / 7
| Ndb_api_pk_op_count_session
                                                0
 Ndb_api_uk_op_count_session
                                               / 1
 Ndb_api_table_scan_count_session
                                                 0
 Ndb_api_range_scan_count_session
| Ndb_api_pruned_scan_count_s
                                                1 0
                                                0
| Ndb_api_read_row_count_session
                                                / 3
| Ndb_api_trans_local_read_row_count_session | 2
18 rows in set (0.00 sec)
```

We can make a number of observations from these results:

- Although we created t with no explicit primary key, 5 primary key operations were performed in doing so (the difference in the "before" and "after" values of Ndb\_api\_pk\_op\_count\_session, or 6 minus 1). This reflects the creation of the hidden primary key that is a feature of all tables using the NDB storage engine.
- By comparing successive values for Ndb\_api\_wait\_nanos\_count\_session, we can see that the NDB API operations implementing the CREATE TABLE statement waited much longer (706871709 820705 = 706051004 nanoseconds, or approximately 0.7 second) for responses from the data nodes than those executed by the INSERT (707370418 706871709 = 498709 ns or roughly .0005 second). The execution times reported for these statements in the mysql client correlate roughly with these figures.

On platforms with without sufficient (nanosecond) time resolution, small changes in the value of the WaitNanosCount NDB API counter due to SQL statements that execute very quickly may not always be visible in the values of Ndb\_api\_wait\_nanos\_count\_session, Ndb api wait nanos count slave, or Ndb api wait nanos count.

• The INSERT statement incremented both the ReadRowCount and TransLocalReadRowCount NDB API statistics counters, as reflected by the increased values of Ndb\_api\_read\_row\_count\_session and Ndb\_api\_trans\_local\_read\_row\_count\_session.


# Chapter 8 MySQL Cluster Replication

### **Table of Contents**

8.1 MySQL Cluster Replication: Abbreviations and Symbols	472
8.2 General Requirements for MySQL Cluster Replication	473
8.3 Known Issues in MySQL Cluster Replication	474
8.4 MySQL Cluster Replication Schema and Tables	481
8.5 Preparing the MySQL Cluster for Replication	486
8.6 Starting MySQL Cluster Replication (Single Replication Channel)	488
8.7 Using Two Replication Channels for MySQL Cluster Replication	490
8.8 Implementing Failover with MySQL Cluster Replication	491
8.9 MySQL Cluster Backups With MySQL Cluster Replication	492
8.9.1 MySQL Cluster Replication: Automating Synchronization of the Replication Slave to the	
Master Binary Log	495
8.9.2 Point-In-Time Recovery Using MySQL Cluster Replication	497
8.10 MySQL Cluster Replication: Multi-Master and Circular Replication	
8.11 MySQL Cluster Replication Conflict Resolution	503

Previous to MySQL 5.1.6, <u>asynchronous replication</u>, more usually referred to simply as "replication", was not available when using MySQL Cluster. MySQL 5.1.6 introduces master-slave replication of this type for MySQL Cluster databases. This section explains how to set up and manage a configuration wherein one group of computers operating as a MySQL Cluster replicates to a second computer or group of computers. We assume some familiarity on the part of the reader with standard MySQL replication as discussed elsewhere in this Manual. (See Replication).

Normal (non-clustered) replication involves a "master" server and a "slave" server, the master being the source of the operations and data to be replicated and the slave being the recipient of these. In MySQL Cluster, replication is conceptually very similar but can be more complex in practice, as it may be extended to cover a number of different configurations including replicating between two complete clusters. Although a MySQL Cluster itself depends on the NDB storage engine for clustering functionality, it is not necessary to use NDB as the storage engine for the slave's copies of the replicated tables (see Replication from NDB to non-NDB tables). However, for maximum availability, it is possible (and preferable) to replicate from one MySQL Cluster to another, and it is this scenario that we discuss, as shown in the following figure:



In this scenario, the replication process is one in which successive states of a master cluster are logged and saved to a slave cluster. This process is accomplished by a special thread known as the NDB binlog injector thread, which runs on each MySQL server and produces a binary log (binlog). This thread ensures that all changes in the cluster producing the binary log—and not just those changes that are effected through the MySQL Server—are inserted into the binary log with the correct serialization order. We refer to the MySQL replication master and replication slave servers as replication servers or replication nodes, and the data flow or line of communication between them as a *replication channel*.

For information about performing point-in-time recovery with MySQL Cluster and MySQL Cluster Replication, see Section 8.9.2, "Point-In-Time Recovery Using MySQL Cluster Replication".

NDB API\_slave status variables. Beginning with MySQL Cluster NDB 7.0.22 and MySQL Cluster NDB 7.1.11, NDB API counters provide enhanced monitoring capabilities on MySQL Cluster replication slaves. These are implelemented as NDB statistics \_slave status variables, as seen in the output of SHOW STATUS, or in the results of queries against the SESSION\_STATUS or GLOBAL\_STATUS table in a mysql client session connected to a MySQL Server that is acting as a slave in MySQL Cluster Replication. By comparing the values of these status variables before and after the execution of statements affecting replicated NDB tables, you can observe the corresponding actions taken on the NDB API level by the slave, which can be useful when monitoring or troubleshooting MySQL Cluster Replication. Section 7.15, "NDB API Statistics Counters and Variables", provides additional information.

Replication from NDB to non-NDB tables. It is possible to replicate NDB tables from a MySQL Cluster acting as the master to tables using other MySQL storage engines such as InnoDB or MyISAM on a slave mysqld. However, because of differences between the version of mysqld provided with MySQL Cluster and that included with MySQL Server 5.1, the slave server must also use a mysqld binary from the MySQL Cluster distribution. See Section 8.2, "General Requirements for MySQL Cluster Replication".

# 8.1 MySQL Cluster Replication: Abbreviations and Symbols

Throughout this section, we use the following abbreviations or symbols for referring to the master and slave clusters, and to processes and commands run on the clusters or cluster nodes:

Symbol or Abbreviation	Description (Refers to)
М	The cluster serving as the (primary) replication master

Symbol or Abbreviation	Description (Refers to)
S	The cluster acting as the (primary) replication slave
shellM>	Shell command to be issued on the master cluster
mysqlM>	MySQL client command issued on a single MySQL server running as an SQL node on the master cluster
mysqlM*>	MySQL client command to be issued on all SQL nodes participating in the replication master cluster
shellS>	Shell command to be issued on the slave cluster
mysqlS>	MySQL client command issued on a single MySQL server running as an SQL node on the slave cluster
mysqlS*>	MySQL client command to be issued on all SQL nodes participating in the replication slave cluster
C	Primary replication channel
C'	Secondary replication channel
M'	Secondary replication master
S'	Secondary replication slave

# 8.2 General Requirements for MySQL Cluster Replication

A replication channel requires two MySQL servers acting as replication servers (one each for the master and slave). For example, this means that in the case of a replication setup with two replication channels (to provide an extra channel for redundancy), there will be a total of four replication nodes, two per cluster.

Replication of a MySQL Cluster as described in this section and those following is dependent on row-based replication. This means that the replication master MySQL server must be started with --binlog-format=ROW or --binlog-format=MIXED, as described in Section 8.6, "Starting MySQL Cluster Replication (Single Replication Channel)". For general information about row-based replication, see Replication Formats.

#### **Important**

If you attempt to use MySQL Cluster Replication with <code>--binlog-format=STATEMENT</code>, replication fails to work properly because the <code>ndb\_binlog\_index</code> table on the master and the <code>epoch</code> column of the <code>ndb\_apply\_status</code> table on the slave are not updated (see Section 8.4, "MySQL Cluster Replication Schema and Tables"). Instead, only updates on the MySQL server acting as the replication master propagate to the slave, and no updates from any other SQL nodes on the master cluster are replicated.

In all MySQL Cluster NDB 6.x and 7.x releases, the default value for the --binlog-format option is MIXED.

Each MySQL server used for replication in either cluster must be uniquely identified among all the MySQL replication servers participating in either cluster (you cannot have replication servers on both the master and slave clusters sharing the same ID). This can be done by starting each SQL node using the --server-id=id option, where id is a unique integer. Although it is not strictly necessary, we will assume for purposes of this discussion that all MySQL Cluster binaries are of the same release version.

It is generally true in MySQL Replication that both MySQL servers (mysqld processes) involved must be compatible with one another with respect to both the version of the replication protocol used and the SQL

feature sets which they support (see Replication Compatibility Between MySQL Versions). It is due to such differences between the binaries in the MySQL Cluster and MySQL Server 5.1 distributions that MySQL Cluster Replication has the additional requirement that both mysqld binaries come from a MySQL Cluster distribution. The simplest and easiest way to assure that the mysqld servers are compatible is to use the same MySQL Cluster distribution for all master and slave mysqld binaries.

We assume that the slave server or cluster is dedicated to replication of the master, and that no other data is being stored on it.

#### Note

It is possible to replicate a MySQL Cluster using statement-based replication. However, in this case, the following restrictions apply:

- All updates to data rows on the cluster acting as the master must be directed to a single MySQL server.
- It is not possible to replicate a cluster using multiple simultaneous MySQL replication processes.
- Only changes made at the SQL level are replicated.

These are in addition to the other limitations of statement-based replication as opposed to row-based replication; see Advantages and Disadvantages of Statement-Based and Row-Based Replication, for more specific information concerning the differences between the two replication formats.

# 8.3 Known Issues in MySQL Cluster Replication

This section discusses known problems or issues when using replication with MySQL Cluster in MySQL 5.1 (including MySQL Cluster NDB 6.X and 7.X through 7.1).

Loss of master-slave connection. A loss of connection can occur either between the replication master SQL node and the replication slave SQL node, or between the replication master SQL node and the data nodes in the master cluster. In the latter case, this can occur not only as a result of loss of physical connection (for example, a broken network cable), but due to the overflow of data node event buffers; if the SQL node is too slow to respond, it may be dropped by the cluster (this is controllable to some degree by adjusting the MaxBufferedEpochs and TimeBetweenEpochs configuration parameters). If this occurs, it is entirely possible for new data to be inserted into the master cluster without being recorded in the replication master's binary log. For this reason, to guarantee high availability, it is extremely important to maintain a backup replication channel, to monitor the primary channel, and to fail over to the secondary replication channel when necessary to keep the slave cluster synchronized with the master. MySQL Cluster is not designed to perform such monitoring on its own; for this, an external application is required.

Prior to MySQL 5.1.18, a MySQL Cluster replication slave mysqld had no way of detecting that the connection from the master had been interrupted. For this reason, it was possible for the slave to become inconsistent with the master.

Beginning with MySQL 5.1.18, the replication master issues a "gap" event when connecting or reconnecting to the master cluster. (A gap event is a type of "incident event," which indicates an incident that occurs that affects the contents of the database but that cannot easily be represented as a set of changes. Examples of incidents are server crashes, database resynchronization, (some) software updates, and (some) hardware changes.) When the slave encounters a gap in the replication log, it stops with an error message. This message is available in the output of SHOW SLAVE STATUS, and indicates that

the SQL thread has stopped due to an incident registered in the replication stream, and that manual intervention is required. See Section 8.8, "Implementing Failover with MySQL Cluster Replication", for more information about what to do in such circumstances.

### **Important**

Because MySQL Cluster is not designed on its own to monitor replication status or provide failover, if high availability is a requirement for the slave server or cluster, then you must set up multiple replication lines, monitor the master mysqld on the primary replication line, and be prepared fail over to a secondary line if and as necessary. This must be done manually, or possibly by means of a third-party application. For information about implementing this type of setup, see Section 8.7, "Using Two Replication Channels for MySQL Cluster Replication", and Section 8.8, "Implementing Failover with MySQL Cluster Replication".

However, if you are replicating from a standalone MySQL server to a MySQL Cluster, one channel is usually sufficient.

**Multibyte character sets.** Previously, there were several known issues with regard to the use of multibyte characters sets with MySQL Cluster Replication. These were resolved in MySQL 5.1.21, MySQL Cluster NDB 6.2.14, and MySQL Cluster NDB 6.3.11. (See Bug #27404 and Bug #29562.)


**Circular replication.** Prior to MySQL 5.1.18, circular replication was not supported with MySQL Cluster replication, due to the fact that all log events created in a particular MySQL Cluster were wrongly tagged with the server ID of the MySQL server used as master and not with the server ID of the originating server.

Beginning with MySQL 5.1.18, this limitation is lifted, as discussed in the next few paragraphs, in which we consider the example of a replication setup involving three MySQL Clusters numbered 1, 2, and 3, in which Cluster 1 acts as the replication master for Cluster 2, Cluster 2 acts as the master for Cluster 3, and Cluster 3 acts as the master for Cluster 1. Each cluster has two SQL nodes, with SQL nodes A and B belonging to Cluster 1, SQL nodes C and D belonging to Cluster 2, and SQL nodes E and F belonging to Cluster 3.

Circular replication using these clusters is supported as long as the following conditions are met:


- The SQL nodes on all masters and slaves are the same
- All SQL nodes acting as replication masters and slaves are started using the --log-slave-updates
  option

This type of circular replication setup is shown in the following diagram:



In this scenario, SQL node A in Cluster 1 replicates to SQL node C in Cluster 2; SQL node C replicates to SQL node E in Cluster 3; SQL node E replicates to SQL node A. In other words, the replication line (indicated by the red arrows in the diagram) directly connects all SQL nodes used as replication masters and slaves.

It should also be possible to set up circular replication in which not all master SQL nodes are also slaves, as shown here:



In this case, different SQL nodes in each cluster are used as replication masters and slaves. However, you must *not* start any of the SQL nodes using --log-slave-updates). This type of circular replication scheme for MySQL Cluster, in which the line of replication (again indicated by the red arrows in the diagram) is discontinuous, should be possible, but it should be noted that it has not yet been thoroughly tested and must therefore still be considered experimental.

#### Note

Beginning with MySQL 5.1.24, the NDB storage engine uses <u>idempotent execution</u> <u>mode</u>, which suppresses duplicate-key and other errors that otherwise break circular replication of MySQL Cluster. This is equivalent to setting the global slave\_exec\_mode system variable to IDEMPOTENT.

Idempotent mode is also required for multi-master replication when using MySQL Cluster (Bug #31609), but it is not necessary to set slave\_exec\_mode in MySQL Cluster replication since MySQL Cluster does this automatically, and ignores any attempts to set this variable explicitly.

**MySQL Cluster replication and primary keys.** In MySQL 5.1.6, only those NDB tables having explicit primary keys could be replicated. This limitation was lifted in MySQL 5.1.7. However, in the event of a node failure, errors in replication of NDB tables without primary keys can still occur, due to the possibility of duplicate rows being inserted in such cases. For this reason, it is highly recommended that all NDB tables being replicated have primary keys.

**MySQL Cluster Replication and Unique Keys.** Prior to MySQL Cluster NDB 7.0.25 and MySQL Cluster NDB 7.1.14, operations that updated values of unique key columns of NDB tables could result in duplicate-key errors when replicated. This was due to the ordering of row events in the binary log according to the partitioning of the base table, which meant that they could appear in a different order from that in which they were originally executed. (Bug #11756082)

In MySQL Cluster NDB 7.0.25, MySQL Cluster NDB 7.1.14, and later, this issue is solved for replication between NDB tables by deferring unique key checks until after all table row updates have been performed.

Deferring constraints in this way is currently supported only by NDB. Thus, updates of unique keys when replicating from NDB to a different storage engine such as MyISAM or InnoDB are still not supported.

The problem encountered when replicating without deferred checking of unique key updates can be illustrated using NDB table such as t, is created and populated on the master (and replicated to a slave that does not support deferred unique key updates) as shown here:

```
CREATE TABLE t (
p INT PRIMARY KEY,
c INT,
uNIQUE KEY u (c)
) ENGINE NDB;
INSERT INTO t
VALUES (1,1), (2,2), (3,3), (4,4), (5,5);
```

The following UPDATE statement on t succeeded on the master, since the rows affected are processed in the order determined by the ORDER BY option, performed over the entire table:

```
UPDATE t SET c = c - 1 ORDER BY p;
```

However, the same statement failed with a duplicate key error or other constraint violation on the slave, because the ordering of the row updates was done for one partition at a time, rather than for the table as a whole.

#### **Note**

In MySQL 5.1.6 and later, every NDB table is implicitly partitioned by key when it is created. This also applies to all MySQL Cluster NDB 6.x and MySQL Cluster NDB 7.x releases. See KEY Partitioning, for more information.

**Restarting with --initial.** Restarting the cluster with the --initial option causes the sequence of GCI and epoch numbers to start over from 0. (This is generally true of MySQL Cluster and not limited to replication scenarios involving Cluster.) The MySQL servers involved in replication should in this case be restarted. After this, you should use the RESET MASTER and RESET SLAVE statements to clear the invalid ndb\_binlog\_index and ndb\_apply\_status tables, respectively.

auto\_increment\_offset and auto\_increment\_increment variables. The use of the auto\_increment\_offset and auto\_increment\_increment server system variables is supported beginning with MySQL 5.1.20. Previously, these produced unpredictable results when used with NDB tables or MySQL Cluster replication.

**Replication from NDB to other storage engines.** It is possible to replicate an NDB table on the master to a table using a different storage engine on the slave, taking into account the restrictions listed here:

 Multi-master and circular replication are not supported (tables on both the master and the slave must use the NDB storage engine for this to work).

- Using a storage engine which does not perform binary logging for slave tables requires special handling.
- Use of a nontransactional storage engine for slave tables also requires special handling.

The next few paragraphs provide additional information about each of the issues just described.

**Multiple masters not supported when replicating NDB to other storage engines.** For replication from NDB to a different storage engine, the relationship between the two databases must be a simple master-slave one. This means that circular or master-master replication is not supported between MySQL Cluster and other storage engines.

In addition, it is not possible to configure more than one replication channel when replicating between NDB and a different storage engine. (However, a MySQL Cluster database *can* simultaneously replicate to multiple slave MySQL Cluster databases.) If the master uses NDB tables, it is still possible to have more than one MySQL Server maintain a binary log of all changes; however, for the slave to change masters (fail over), the new master-slave relationship must be explicitly defined on the slave.

Replicating NDB to a slave storage engine that does not perform binary logging. If you attempt to replicate from a MySQL Cluster to a slave that uses a storage engine that does not handle its own binary logging, the replication process aborts with the error Binary logging not possible ... Statement cannot be written atomically since more than one engine involved and at least one engine is self-logging (Error 1595). It is possible to work around this issue in one of the following ways:

- Turn off binary logging on the slave. This can be accomplished by setting  $sql_{log_bin} = 0$ .
- Change the storage engine used for the mysql.ndb\_apply\_status table. Causing this table to use an engine that does not handle its own binary logging can also eliminate the conflict. This can be done by issuing a statement such as ALTER TABLE mysql.ndb\_apply\_status ENGINE=MyISAM on the slave. It is safe to do this when using a non-NDB storage engine on the slave, since you do not then need to worry about keeping multiple slave SQL nodes synchronized.
- Filter out changes to the mysql.ndb\_apply\_status table on the slave. This can be done by starting the slave SQL node with --replicate-ignore-table=mysql.ndb\_apply\_status. If you need for other tables to be ignored by replication, you might wish to use an appropriate --replicate-wild-ignore-table option instead.

### **Important**

You should *not* disable replication or binary logging of mysql.ndb\_apply\_status or change the storage engine used for this table when replicating from one MySQL Cluster to another. See Replication and binary log filtering rules with replication between MySQL Clusters, for details.

Replication from NDB to a nontransactional storage engine. When replicating from NDB to a nontransactional storage engine such as MyISAM, you may encounter unnecessary duplicate key errors when replicating INSERT ... ON DUPLICATE KEY UPDATE statements. You can suppress these in MySQL Cluster NDB 6.2 and later MySQL Cluster releases by using --ndb-log-update-as-write=0 [505], which forces updates to be logged as writes (rather than as updates).

In addition, when replicating from NDB to a storage engine that does not implement transactions, if the slave fails to apply any row changes from a given transaction, it does not roll back the rest of the transaction. (This is true when replicating tables using any transactional storage engine—not only NDB—to a nontransactional storage engine.) Because of this, it cannot be guaranteed that transactional consistency will be maintained on the slave in such cases.

Replication and binary log filtering rules with replication between MySQL Clusters. If you are using any of the options --replicate-do-\*, --replicate-ignore-\*, --binlog-do-db, or --binlog-ignore-db to filter databases or tables being replicated, care must be taken not to block replication or binary logging of the mysql.ndb\_apply\_status, which is required for replication between MySQL Clusters to operate properly. In particular, you must keep in mind the following:

- 1. Using --replicate-do-db=db\_name (and no other --replicate-do-\* or --replicate-ignore-\* options) means that only tables in database db\_name are replicated. In this case, you should also use --replicate-do-db=mysql, --binlog-do-db=mysql, or --replicate-do-table=mysql.ndb\_apply\_status to ensure that mysql.ndb\_apply\_status is populated on slaves.
  - Using <code>--binlog-do-db=db\_name</code> (and no other <code>--binlog-do-db</code> options) means that changes <code>only</code> to tables in database <code>db\_name</code> are written to the binary log. In this case, you should also use <code>--replicate-do-db=mysql</code>, <code>--binlog-do-db=mysql</code>, <code>or --replicate-do-table=mysql</code>. <code>ndb\_apply\_status</code> to ensure that <code>mysql.ndb\_apply\_status</code> is populated on slaves.
- 2. Using --replicate-ignore-db=mysql means that no tables in the mysql database are replicated. In this case, you should also use --replicate-do-table=mysql.ndb\_apply\_status to ensure that mysql.ndb\_apply\_status is replicated.


Using --binlog-ignore-db=mysql means that no changes to tables in the mysql database are written to the binary log. In this case, you should also use --replicate-do-table=mysql.ndb\_apply\_status to ensure that mysql.ndb\_apply\_status is replicated.

You should also remember that each replication rule requires the following:

- 1. Its own --replicate-do-\* or --replicate-ignore-\* option, and that multiple rules cannot be expressed in a single replication filtering option. For information about these rules, see Replication and Binary Logging Options and Variables.
- 2. Its own --binlog-do-db or --binlog-ignore-db option, and that multiple rules cannot be expressed in a single binary log filtering option. For information about these rules, see The Binary Log.

If you are replicating a MySQL Cluster to a slave that uses a storage engine other than NDB, the considerations just given previously may not apply, as discussed elsewhere in this section.

**MySQL Cluster Replication and IPv6.** Currently, the NDB API and MGM API do not support IPv6. However, beginning with MySQL Cluster NDB 6.4.1, MySQL Servers—including those acting as SQL nodes in a MySQL Cluster—can use IPv6 to contact other MySQL Servers. This means that you can replicate between MySQL Clusters using IPv6 to connect the master and slave SQL nodes as shown by the dotted arrow in the following diagram:



However, all connections originating *within* the MySQL Cluster—represented in the preceding diagram by solid arrows—must use IPv4. In other words, all MySQL Cluster data nodes, management servers, and management clients must be accessible from one another using IPv4. In addition, SQL nodes must use IPv4 to communicate with the cluster.

Since there is currently no support in the NDB and MGM APIs for IPv6, any applications written using these APIs must also make all connections using IPv4.

Attribute promotion and demotion. Formerly, support in MySQL Cluster for type conversions between columns of similar but different types on the master and the slave was extremely limited. However, starting with MySQL Cluster NDB 6.3.33, 7.0.14, and 7.1.3, MySQL Cluster Replication includes support for attribute promotion and demotion. The implementation of the latter distinguishes between lossy and non-lossy type conversions, and their use on the slave can be controlled by setting the slave\_type\_conversions global server system variable.

For more information about attribute promotion and demotion in MySQL Cluster, see Attribute promotion and demotion (MySQL Cluster).

# 8.4 MySQL Cluster Replication Schema and Tables

Replication in MySQL Cluster makes use of a number of dedicated tables in the mysql database on each MySQL Server instance acting as an SQL node in both the cluster being replicated and the replication slave (whether the slave is a single server or a cluster). These tables are created during the MySQL installation process by the mysql\_install\_db script, and include a table for storing the binary log's indexing data. Since the ndb\_binlog\_index table is local to each MySQL server and does not participate in clustering, it uses the MyISAM storage engine. This means that it must be created separately on each mysqld participating in the master cluster. (However, the binary log itself contains updates from all MySQL servers in the cluster to be replicated.) This table is defined as follows:

```
CREATE TABLE `ndb_binlog_index` (
   `Position` BIGINT(20) UNSIGNED NOT NULL,
```

```
`File` VARCHAR(255) NOT NULL,
    `epoch` BIGINT(20) UNSIGNED NOT NULL,
    `inserts` BIGINT(20) UNSIGNED NOT NULL,
    `updates` BIGINT(20) UNSIGNED NOT NULL,
    `deletes` BIGINT(20) UNSIGNED NOT NULL,
    `schemaops` BIGINT(20) UNSIGNED NOT NULL,
    `next_position` bigint(20) unsigned NOT NULL,
    `next_file` varchar(255) NOT NULL,
    PRIMARY KEY (`epoch`)
) ENGINE=MYISAM DEFAULT CHARSET=latin1;
```

The size of this table is dependent on the number of epochs per binary log file and the number of binary log files. The number of epochs per binary log file normally depends on the amount of binary log generated per epoch and the size of the binary log file, with smaller epochs resulting in more epochs per file. It should be noted that empty epochs produce result in inserts to the ndb\_binlog\_index table, even when the --ndb-log-empty-epochs option is OFF, meaning that the number of entries per file depends on the length of time that the file is in use; that is,

```
[number of epochs per file] = [time spent per file] / TimeBetweenEpochs
```

A busy MySQL Cluster writes to the binary log regularly and presumably rotates binary log files more quickly than a quiet one. This means that a "quiet" MySQL Cluster with --ndb-log-empty-epochs=ON can actually have a much higher number of ndb\_binlog\_index rows per file than one with a great deal of activity.

When mysqld is started with the --ndb-log-orig option, the orig\_server\_id and orig\_epoch columns store, respectively, the ID of the server on which the event originated and the epoch in which the event took place on the originating server, which is useful in MySQL Cluster replication setups employing multiple masters. The SELECT statement used to find the closest binlog position to the highest applied epoch on the slave in a multi-master setup (see Section 8.10, "MySQL Cluster Replication: Multi-Master and Circular Replication") employs these two columns, which are not indexed. This can lead to performance issues when trying to fail over, since the query must perform a table scan, especially when the master has been running with --ndb-log-empty-epochs=ON. You can improve multi-master failover times by adding an index to these columns, as shown here:

```
ALTER TABLE mysql.ndb_binlog_index
ADD INDEX orig_lookup USING BTREE (orig_server_id, orig_epoch);
```

Adding this index provides no benefit when replicating from a single master to a single slave, since the query used to get the binary log position in such cases makes no use of orig\_server\_id or orig\_epoch.

The next\_position and next\_file columns were added in MySQL Cluster NDB 7.2.6; see Section 8.8, "Implementing Failover with MySQL Cluster Replication", for more information about using these columns.

### **Important**

Prior to MySQL 5.1.14, the ndb\_binlog\_index table was known as binlog\_index, and was kept in a separate cluster database, which in MySQL 5.1.7 and earlier was known as the cluster\_replication database. Similarly, the ndb\_apply\_status and ndb\_schema tables were known as apply\_status and schema, and were also found in the cluster (earlier cluster\_replication) database. However, beginning with MySQL 5.1.14, all MySQL Cluster replication tables reside in the mysql system database.

Information about how this change affects upgrades from MySQL Cluster 5.1.13 and earlier to 5.1.14 and later versions can be found in <a href="http://dev.mysql.com/doc/relnotes/mysql/5.1/en/news-5-1-14.html">http://dev.mysql.com/doc/relnotes/mysql/5.1/en/news-5-1-14.html</a>.

Beginning with MySQL Cluster NDB 6.3.2, this table has been changed to facilitate 3-way replication recovery. Two columns orig\_server\_id and orig\_epoch have been added to this table; when mysqld is started with the --ndb-log-orig option, these columns store, respectively, the ID of the server on which the event originated and the epoch in which the event took place on the originating server. In addition, the table's primary key now includes these two columns. The modified table definition is shown here:

```
CREATE TABLE `ndb_binlog_index` (
    `Position` BIGINT(20) UNSIGNED NOT NULL,
    `File` VARCHAR(255) NOT NULL,
    `epoch` BIGINT(20) UNSIGNED NOT NULL,
    `inserts` INT(10) UNSIGNED NOT NULL,
    `updates` INT(10) UNSIGNED NOT NULL,
    `deletes` INT(10) UNSIGNED NOT NULL,
    `schemaops` INT(10) UNSIGNED NOT NULL,
    `orig_server_id` INT(10) UNSIGNED NOT NULL,
    `orig_epoch` BIGINT(20) UNSIGNED NOT NULL,
    `gci` INT(10) UNSIGNED NOT NULL,
    `next_position` bigint(20) unsigned NOT NULL,
    `next_file` varchar(255) NOT NULL,
    PRIMARY KEY (`epoch`, `orig_server_id`, `orig_epoch`)
) ENGINE=MyISAM DEFAULT CHARSET=latin1;
```

The gci column was added in MySQL Cluster NDB 6.2.6 and MySQL Cluster NDB 6.3.2.

The next\_position and next\_file columns were added in MySQL Cluster NDB 7.0.33 and MySQL Cluster NDB 7.1.22; see Section 8.8, "Implementing Failover with MySQL Cluster Replication", for more information about using these columns.

The following figure shows the relationship of the MySQL Cluster replication master server, its binlog injector thread, and the mysql.ndb\_binlog\_index table.

### MySQL Server connection thread (mysqld) ndb\_binloq\_index Table NdbCluster table handler injector thread receiver/thread mutex mutex receive binlog send events (MyISAM) Data node (ndbd) Data node(ndbd) Data node(ndbd) Data node (ndbd)

### MySQL Replication Between Clusters, Injecting into Binlog

An additional table, named ndb\_apply\_status, is used to keep a record of the operations that have been replicated from the master to the slave. Unlike the case with ndb\_binlog\_index, the data in this table is not specific to any one SQL node in the (slave) cluster, and so ndb\_apply\_status can use the NDBCLUSTER storage engine, as shown here:

```
CREATE TABLE `ndb_apply_status` (
   `server_id` INT(10) UNSIGNED NOT NULL,
   `epoch` BIGINT(20) UNSIGNED NOT NULL,
   `log_name` VARCHAR(255) CHARACTER SET latin1 COLLATE latin1_bin NOT NULL,
   `start_pos` BIGINT(20) UNSIGNED NOT NULL,
   `end_pos` BIGINT(20) UNSIGNED NOT NULL,
   PRIMARY KEY (`server_id`) USING HASH
) ENGINE=NDBCLUSTER DEFAULT CHARSET=latin1;
```

The ndb\_apply\_status table is populated only on slaves, which means that, on the master, this table never contains any rows; thus, there is no need to allow for DataMemory or IndexMemory to be allotted to ndb apply status there.

Because this table is populated from data originating on the master, it should be allowed to replicate; any replication filtering or binary log filtering rules that inadvertently prevent the slave from updating ndb\_apply\_status or the master from writing into the binary log may prevent replication between clusters from operating properly. For more information about potential problems arising from such filtering rules, see Replication and binary log filtering rules with replication between MySQL Clusters.

The log\_name, start\_pos, and end\_pos columns were added in MySQL 5.1.18.

#### **Important**

If you are using MySQL Cluster replication, see Section 4.7.3, "Upgrade and downgrade compatibility: MySQL 5.1" before upgrading to MySQL 5.1.18 or later from an earlier version.

The ndb\_binlog\_index and ndb\_apply\_status tables are created in the mysql database because they should not be explicitly replicated by the user. User intervention is normally not required to create or maintain either of these tables, since both ndb\_binlog\_index and the ndb\_apply\_status are maintained by the NDB binary log (binlog) injector thread. This keeps the master mysqld process updated to changes performed by the NDB storage engine. The NDB binlog injector thread receives events directly from the NDB storage engine. The NDB injector is responsible for capturing all the data events within the cluster, and ensures that all events which change, insert, or delete data are recorded in the ndb\_binlog\_index table. The slave I/O thread transfers the events from the master's binary log to the slave's relay log.

However, it is advisable to check for the existence and integrity of these tables as an initial step in preparing a MySQL Cluster for replication. It is possible to view event data recorded in the binary log by querying the mysql.ndb\_binlog\_index table directly on the master. This can be also be accomplished using the SHOW BINLOG EVENTS statement on either the replication master or slave MySQL servers. (See SHOW BINLOG EVENTS Syntax.)

You can also obtain useful information from the output of SHOW ENGINE NDB STATUS.

The ndb\_schema table is used to track schema changes made to NDB tables. It is defined as shown here:

```
CREATE TABLE ndb_schema (
    `db` VARBINARY(63) NOT NULL,
    `name` VARBINARY(63) NOT NULL,
    `slock` BINARY(32) NOT NULL,
    `query` BLOB NOT NULL,
    `node_id` INT UNSIGNED NOT NULL,
    `epoch` BIGINT UNSIGNED NOT NULL,
    `id` INT UNSIGNED NOT NULL,
    `version` INT UNSIGNED NOT NULL,
    `type` INT UNSIGNED NOT NULL,
    PRIMARY KEY USING HASH (db,name)
) ENGINE=NDB    DEFAULT CHARSET=latin1;
```

Unlike the two tables previously mentioned in this section, the ndb\_schema table is not visible either to MySQL SHOW statements, or in any INFORMATION\_SCHEMA tables; however, it can be seen in the output of ndb\_show\_tables, as shown here:

```
shell> ndb_show_tables -t 2
           state logging database schema name
able Online Yes mysql def ndb_apply_status
id type
     UserTable
5
     UserTable
                        Online Yes ndbworld def
                                                               City
     UserTable
                                                      def Country
def NDB$BLOB_2_3
def CountryLangua
6
                         Online Yes ndbworld
     UserTable
UserTable
                         Online Yes mysql
Online Yes ndbworld
                                          ndbworld
                                                                CountryLanguage
                         Online Yes
                                                       def
     UserTable
                                          mysql
                                                                ndb schema
NDBT_ProgramExit: 0 - OK
```

It is also possible to SELECT from this table in mysql and other MySQL client applications, as shown here:

```
slock:
  query: alter table City engine=ndb
node_id: 4
  epoch: 0
    id: 0
version: 0
   type: 7
1 row in set (0.00 sec)
```

This can sometimes be useful when debugging applications.

#### Note

When performing schema changes on NDB tables, applications should wait until the ALTER TABLE statement has returned in the MySQL client connection that issued the statement before attempting to use the updated definition of the table.

The ndb\_schema table was added in MySQL 5.1.8.

Beginning with MySQL 5.1.14, if the ndb\_apply\_status table or the ndb\_schema table does not exist on the slave, ndb\_restore re-creates the missing table or tables (Bug #14612).

Conflict resolution for MySQL Cluster Replication requires the presence of an additional mysql.ndb\_replication table. Currently, this table must be created manually. For information about how to do this, see Section 8.11, "MySQL Cluster Replication Conflict Resolution".

# 8.5 Preparing the MySQL Cluster for Replication

Preparing the MySQL Cluster for replication consists of the following steps:

- Check all MySQL servers for version compatibility (see Section 8.2, "General Requirements for MySQL Cluster Replication").
- 2. Create a slave account on the master Cluster with the appropriate privileges:

```
mysqlM> GRANT REPLICATION SLAVE
    -> ON *.* TO 'slave_user'@'slave_host'
    -> IDENTIFIED BY 'slave_password';
```

In the previous statement, <code>slave\_user</code> is the slave account user name, <code>slave\_host</code> is the host name or IP address of the replication slave, and <code>slave\_password</code> is the password to assign to this account.

For example, to create a slave user account with the name "myslave," logging in from the host named "rep-slave," and using the password "53cr37," use the following GRANT statement:

```
mysqlM> GRANT REPLICATION SLAVE
-> ON *.* TO 'myslave'@'rep-slave'
-> IDENTIFIED BY '53cr37';
```

For security reasons, it is preferable to use a unique user account—not employed for any other purpose —for the replication slave account.

3. Configure the slave to use the master. Using the MySQL Monitor, this can be accomplished with the CHANGE MASTER TO statement:

```
mysqlS> CHANGE MASTER TO
-> MASTER_HOST='master_host',
```

```
-> MASTER_PORT=master_port,
-> MASTER_USER='slave_user',
-> MASTER_PASSWORD='slave_password';
```

In the previous statement, <code>master\_host</code> is the host name or IP address of the replication master, <code>master\_port</code> is the port for the slave to use for connecting to the master, <code>slave\_user</code> is the user name set up for the slave on the master, and <code>slave\_password</code> is the password set for that user account in the previous step.

For example, to tell the slave to replicate from the MySQL server whose host name is "rep-master," using the replication slave account created in the previous step, use the following statement:

```
mysqlS> CHANGE MASTER TO
   -> MASTER_HOST='rep-master',
   -> MASTER_PORT=3306,
   -> MASTER_USER='myslave',
   -> MASTER_PASSWORD='53cr37';
```

For a complete list of options that can be used with this statement, see CHANGE MASTER TO Syntax.

To provide replication backup capability, you also need to add an --ndb-connectstring option to the slave's my.cnf file prior to starting the replication process. See Section 8.9, "MySQL Cluster Backups With MySQL Cluster Replication", for details.

For additional options that can be set in my. cnf for replication slaves, see Replication and Binary Logging Options and Variables.

4. If the master cluster is already in use, you can create a backup of the master and load this onto the slave to cut down on the amount of time required for the slave to synchronize itself with the master. If the slave is also running MySQL Cluster, this can be accomplished using the backup and restore procedure described in Section 8.9, "MySQL Cluster Backups With MySQL Cluster Replication".

```
ndb-connectstring=management_host[:port]
```

In the event that you are *not* using MySQL Cluster on the replication slave, you can create a backup with this command on the replication master:

```
shellM> mysqldump --master-data=1
```

Then import the resulting data dump onto the slave by copying the dump file over to the slave. After this, you can use the mysql client to import the data from the dumpfile into the slave database as shown here, where  $dump\_file$  is the name of the file that was generated using mysqldump on the master, and  $db\_name$  is the name of the database to be replicated:

```
shellS> mysql -u root -p db_name < dump_file
```

For a complete list of options to use with <code>mysqldump</code>, see <code>mysqldump</code> — A Database Backup Program.

#### Note

If you copy the data to the slave in this fashion, you should make sure that the slave is started with the --skip-slave-start option on the command line, or else include skip-slave-start in the slave's my.cnf file to keep it from trying to connect to the master to begin replicating before all the data has

been loaded. Once the data loading has completed, follow the additional steps outlined in the next two sections.

5. Ensure that each MySQL server acting as a replication master is configured with a unique server ID, and with binary logging enabled, using the row format. (See Replication Formats.) These options can be set either in the master server's my.cnf file, or on the command line when starting the master mysqld process. See Section 8.6, "Starting MySQL Cluster Replication (Single Replication Channel)", for information regarding the latter option.

# 8.6 Starting MySQL Cluster Replication (Single Replication Channel)

This section outlines the procedure for starting MySQL Cluster replication using a single replication channel.

1. Start the MySQL replication master server by issuing this command:

```
shellM> mysqld --ndbcluster --server-id=id \
--log-bin --binlog-format=ROW &
```

In the previous statement, *id* is this server's unique ID (see Section 8.2, "General Requirements for MySQL Cluster Replication"). This starts the server's mysqld process with binary logging enabled using the proper logging format.

#### Note

You can also start the master with <code>--binlog-format=MIXED</code>, in which case row-based replication is used automatically when replicating between clusters. <code>STATEMENT</code> based binary logging is not supported for MySQL Cluster Replication (see Section 8.2, "General Requirements for MySQL Cluster Replication").

2. Start the MySQL replication slave server as shown here:

```
shellS> mysqld --ndbcluster --server-id=id &
```

In the command just shown, *id* is the slave server's unique ID. It is not necessary to enable logging on the replication slave.

#### Note

You should use the <code>--skip-slave-start</code> option with this command or else you should include <code>skip-slave-start</code> in the slave server's <code>my.cnf</code> file, unless you want replication to begin immediately. With the use of this option, the start of replication is delayed until the appropriate <code>START SLAVE</code> statement has been issued, as explained in Step 4 below.

3. It is necessary to synchronize the slave server with the master server's replication binary log. If binary logging has not previously been running on the master, run the following statement on the slave:

```
mysqlS> CHANGE MASTER TO
   -> MASTER_LOG_FILE='',
   -> MASTER_LOG_POS=4;
```

This instructs the slave to begin reading the master's binary log from the log's starting point. Otherwise—that is, if you are loading data from the master using a backup—see Section 8.8, "Implementing

Failover with MySQL Cluster Replication", for information on how to obtain the correct values to use for MASTER LOG FILE and MASTER LOG POS in such cases.

4. Finally, you must instruct the slave to begin applying replication by issuing this command from the mysql client on the replication slave:

```
mysqlS> START SLAVE;
```

This also initiates the transmission of replication data from the master to the slave.

It is also possible to use two replication channels, in a manner similar to the procedure described in the next section; the differences between this and using a single replication channel are covered in Section 8.7, "Using Two Replication Channels for MySQL Cluster Replication".

Beginning with MySQL Cluster NDB 6.2.3, it is possible to improve cluster replication performance by enabling *batched updates*. This can be accomplished by setting the slave\_allow\_batching system variable on the slave mysqld processes. Normally, updates are applied as soon as they are received. However, the use of batching causes updates to be applied in 32 KB batches, which can result in higher throughput and less CPU usage, particularly where individual updates are relatively small.

#### Note

Slave batching works on a per-epoch basis; updates belonging to more than one transaction can be sent as part of the same batch.

All outstanding updates are applied when the end of an epoch is reached, even if the updates total less than 32 KB.

Batching can be turned on and off at runtime. To activate it at runtime, you can use either of these two statements:

```
SET GLOBAL slave_allow_batching = 1;
SET GLOBAL slave_allow_batching = ON;
```

If a particular batch causes problems (such as a statement whose effects do not appear to be replicated correctly), slave batching can be deactivated using either of the following statements:

```
SET GLOBAL slave_allow_batching = 0;
SET GLOBAL slave_allow_batching = OFF;
```

You can check whether slave batching is currently being used by means of an appropriate SHOW VARIABLES statement, like this one:

# 8.7 Using Two Replication Channels for MySQL Cluster Replication

In a more complete example scenario, we envision two replication channels to provide redundancy and thereby guard against possible failure of a single replication channel. This requires a total of four replication servers, two masters for the master cluster and two slave servers for the slave cluster. For purposes of the discussion that follows, we assume that unique identifiers are assigned as shown here:

Server ID	Description
1	Master - primary replication channel (M)
2	Master - secondary replication channel (M')
3	Slave - primary replication channel (S)
4	Slave - secondary replication channel (S')

Setting up replication with two channels is not radically different from setting up a single replication channel. First, the mysqld processes for the primary and secondary replication masters must be started, followed by those for the primary and secondary slaves. Then the replication processes may be initiated by issuing the START SLAVE statement on each of the slaves. The commands and the order in which they need to be issued are shown here:

1. Start the primary replication master:

2. Start the secondary replication master:

3. Start the primary replication slave server:

4. Start the secondary replication slave:

5. Finally, initiate replication on the primary channel by executing the START SLAVE statement on the primary slave as shown here:

```
mysqlS> START SLAVE;
```

### Warning

Only the primary channel is to be started at this point. The secondary replication channel is to be started only in the event that the primary replication channel fails, as described in Section 8.8, "Implementing Failover with MySQL Cluster Replication". Running multiple replication channels simultaneously can result in unwanted duplicate records being created on the replication slaves.

As mentioned previously, it is not necessary to enable binary logging on replication slaves.

# 8.8 Implementing Failover with MySQL Cluster Replication

In the event that the primary Cluster replication process fails, it is possible to switch over to the secondary replication channel. The following procedure describes the steps required to accomplish this.

1. Obtain the time of the most recent global checkpoint (GCP). That is, you need to determine the most recent epoch from the ndb\_apply\_status table on the slave cluster, which can be found using the following query:

2. Using the information obtained from the query shown in Step 1, obtain the corresponding records from the ndb binlog index table on the master cluster.

Prior to MySQL Cluster NDB 7.0.33 and MySQL Cluster 7.1.22, you should use the following query to accomplish this task:

Beginning with MySQL Cluster NDB 7.0.33 and MySQL Cluster NDB 7.1.22, you can take advantage of the improved binary logging of DDL statements implemented in those and later versions by using the following query to obtain the needed records from the master's ndb\_binlog\_index table:

```
mysqlM'> SELECT
-> @file:=SUBSTRING_INDEX(next_file, '/', -1),
-> @pos:=next_position
-> FROM mysql.ndb_binlog_index
-> WHERE epoch = @latest
-> ORDER BY epoch ASC LIMIT 1;
```

In either case, these are the records saved on the master since the failure of the primary replication channel. We have employed a user variable @latest here to represent the value obtained in Step 1. Of course, it is not possible for one mysqld instance to access user variables set on another server instance directly. These values must be "plugged in" to the second query manually or in application code.

#### **Important**

If (and only if) you use the second of the two queries just shown against ndb\_binlog\_index (that is, the query that employs the next\_position and next\_file columns), you must ensure that the slave mysqld is started with --slave-skip-errors=ddl\_exist\_errors before executing START SLAVE. Otherwise, replication may stop with duplicate DDL errors.

3. Now it is possible to synchronize the secondary channel by running the following query on the secondary slave server:

Again we have employed user variables (in this case @file and @pos) to represent the values obtained in Step 2 and applied in Step 3; in practice these values must be inserted manually or using application code that can access both of the servers involved.

#### Note

@file is a string value such as '/var/log/mysql/replication-master-bin.00001', and so must be quoted when used in SQL or application code. However, the value represented by @pos must *not* be quoted. Although MySQL normally attempts to convert strings to numbers, this case is an exception.

4. You can now initiate replication on the secondary channel by issuing the appropriate command on the secondary slave mysqld:

```
mysqlS' > START SLAVE;
```

Once the secondary replication channel is active, you can investigate the failure of the primary and effect repairs. The precise actions required to do this will depend upon the reasons for which the primary channel failed.

#### Warning

The secondary replication channel is to be started only if and when the primary replication channel has failed. Running multiple replication channels simultaneously can result in unwanted duplicate records being created on the replication slaves.

If the failure is limited to a single server, it should (in theory) be possible to replicate from M to S', or from M' to S; however, this has not yet been tested.

# 8.9 MySQL Cluster Backups With MySQL Cluster Replication

This section discusses making backups and restoring from them using MySQL Cluster replication. We assume that the replication servers have already been configured as covered previously (see Section 8.5, "Preparing the MySQL Cluster for Replication", and the sections immediately following). This having been done, the procedure for making a backup and then restoring from it is as follows:

- 1. There are two different methods by which the backup may be started.
  - **Method A.** This method requires that the cluster backup process was previously enabled on the master server, prior to starting the replication process. This can be done by including the following line in a [mysql\_cluster] section in the my.cnf file, where management\_host is the IP address or host name of the NDB management server for the master cluster, and port is the management server's port number:

ndb-connectstring=management\_host[:port]

#### Note

The port number needs to be specified only if the default port (1186) is not being used. See Section 4.3, "Initial Configuration of MySQL Cluster", for more information about ports and port allocation in MySQL Cluster.

In this case, the backup can be started by executing this statement on the replication master:

```
shellM> ndb_mgm -e "START BACKUP"
```

• **Method B.** If the my.cnf file does not specify where to find the management host, you can start the backup process by passing this information to the NDB management client as part of the START BACKUP command. This can be done as shown here, where management\_host and port are the host name and port number of the management server:

```
shellM> ndb_mgm management_host:port -e "START BACKUP"
```

In our scenario as outlined earlier (see Section 8.5, "Preparing the MySQL Cluster for Replication"), this would be executed as follows:

```
shellM> ndb_mgm rep-master:1186 -e "START BACKUP"
```

2. Copy the cluster backup files to the slave that is being brought on line. Each system running an ndbd process for the master cluster will have cluster backup files located on it, and all of these files must be copied to the slave to ensure a successful restore. The backup files can be copied into any directory on the computer where the slave management host resides, so long as the MySQL and NDB binaries have read permissions in that directory. In this case, we will assume that these files have been copied into the directory /var/BACKUPS/BACKUP-1.

It is not necessary that the slave cluster have the same number of ndbd processes (data nodes) as the master; however, it is highly recommended this number be the same. It is necessary that the slave be started with the --skip-slave-start option, to prevent premature startup of the replication process.

3. Create any databases on the slave cluster that are present on the master cluster that are to be replicated to the slave.

### **Important**

A CREATE DATABASE (or CREATE SCHEMA) statement corresponding to each database to be replicated must be executed on each SQL node in the slave cluster.

4. Reset the slave cluster using this statement in the MySQL Monitor:

```
mysqlS> RESET SLAVE;
```

It is important to make sure that the slave's ndb\_apply\_status table does not contain any records prior to running the restore process. You can accomplish this by running this SQL statement on the slave:

```
mysqlS> DELETE FROM mysql.ndb_apply_status;
```

5. You can now start the cluster restoration process on the replication slave using the ndb\_restore command for each backup file in turn. For the first of these, it is necessary to include the -m option to restore the cluster metadata:

```
shellS> ndb_restore -c slave_host:port -n node-id \
    -b backup-id -m -r dir
```

dir is the path to the directory where the backup files have been placed on the replication slave. For the ndb\_restore commands corresponding to the remaining backup files, the -m option should not be used.

For restoring from a master cluster with four data nodes (as shown in the figure in Chapter 8, MySQL Cluster Replication) where the backup files have been copied to the directory /var/BACKUPS/BACKUP-1, the proper sequence of commands to be executed on the slave might look like this:

#### **Important**

The -e (or --restore\_epoch [334]) option in the final invocation of ndb\_restore in this example is required in order that the epoch is written to the slave mysql.ndb\_apply\_status. Without this information, the slave will not be able to synchronize properly with the master. (See Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup".)

6. Now you need to obtain the most recent epoch from the ndb\_apply\_status table on the slave (as discussed in Section 8.8, "Implementing Failover with MySQL Cluster Replication"):

```
mysqlS> SELECT @latest:=MAX(epoch)
   FROM mysql.ndb_apply_status;
```

7. Using @latest as the epoch value obtained in the previous step, you can obtain the correct starting position @pos in the correct binary log file @file from the master's mysql.ndb\_binlog\_index table using the query shown here:

In the event that there is currently no replication traffic, you can get this information by running SHOW MASTER STATUS on the master and using the value in the Position column for the file whose name has the suffix with the greatest value for all files shown in the File column. However, in this case, you must determine this and supply it in the next step manually or by parsing the output with a script.

8. Using the values obtained in the previous step, you can now issue the appropriate CHANGE MASTER TO statement in the slave's mysgl client:

9. Now that the slave "knows" from what point in which binlog file to start reading data from the master, you can cause the slave to begin replicating with this standard MySQL statement:

```
mysqls> start slave;
```

To perform a backup and restore on a second replication channel, it is necessary only to repeat these steps, substituting the host names and IDs of the secondary master and slave for those of the primary master and slave replication servers where appropriate, and running the preceding statements on them.

For additional information on performing Cluster backups and restoring Cluster from backups, see Section 7.3, "Online Backup of MySQL Cluster".

# 8.9.1 MySQL Cluster Replication: Automating Synchronization of the Replication Slave to the Master Binary Log

It is possible to automate much of the process described in the previous section (see Section 8.9, "MySQL Cluster Backups With MySQL Cluster Replication"). The following Perl script reset-slave.pl serves as an example of how you can do this.

```
#!/user/bin/perl -w
# file: reset-slave.pl
 Copyright ©2005 MySOL AB
 This program is free software; you can redistribute it and/or modify
 it under the terms of the GNU General Public License as published by
  the Free Software Foundation; either version 2 of the License, or
  (at your option) any later version.
  This program is distributed in the hope that it will be useful,
 but WITHOUT ANY WARRANTY; without even the implied warranty of
 MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
  GNU General Public License for more details.
  You should have received a copy of the GNU General Public License
  along with this program; if not, write to:
  Free Software Foundation, Inc.
 59 Temple Place, Suite 330
 Boston, MA 02111-1307 USA
  Version 1.1
my $m_host='';
my $m_port='';
my
   $m_user='';
my $m_pass='';
my $s_host='';
my $s_port='';
my $s_user='';
my $s_pass='';
my $dbhM='';
my $dbhS='';
sub CollectCommandPromptInfo;
sub ConnectToDatabases;
sub DisconnectFromDatabases;
sub GetSlaveEpoch;
sub GetMasterInfo;
sub UpdateSlave;
CollectCommandPromptInfo;
ConnectToDatabases;
GetSlaveEpoch;
GetMasterInfo;
UpdateSlave;
DisconnectFromDatabases;
sub CollectCommandPromptInfo
 ### Check that user has supplied correct number of command line args
```

```
die "Usage:\n
      reset-slave >master MySQL host< >master MySQL port< \n
                 >master user< >master pass< >slave MySQL host< \n
                 >slave MySQL port< >slave user< >slave pass< \n
      All 8 arguments must be passed. Use BLANK for NULL passwords\n"
      unless @ARGV == 8;
 m_host = ARGV[0];
 $m_port = $ARGV[1];
 $m_user = $ARGV[2];
$m_pass = $ARGV[3];
 $s_host = $ARGV[4];
 s_port = ARGV[5];
 $s_user = $ARGV[6];
 s_pass = ARGV[7];
 if ($m_pass eq "BLANK") { $m_pass = '';}
 if ($s_pass eq "BLANK") { $s_pass = '';}
############ Make connections to both databases ###############
sub ConnectToDatabases
 ### Connect to both master and slave cluster databases
 ### Connect to master
 $dbhM
   = DBI->connect(
   "dbi:mysql:database=mysql;host=$m_host;port=$m_port",
   "$m_user", "$m_pass")
     or die "Can't connect to Master Cluster MySQL process!
            Error: $DBI::errstr\n";
  ### Connect to slave
 $dbhS
   = DBI->connect(
         "dbi:mysql:database=mysql;host=$s_host",
         "$s_user", "$s_pass")
   or die "Can't connect to Slave Cluster MySQL process!
          Error: $DBI::errstr\n";
sub DisconnectFromDatabases
 ### Disconnect from master
 $dbhM->disconnect
 or warn " Disconnection failed: $DBI::errstr\n";
 ### Disconnect from slave
 $dbhS->disconnect
 or warn " Disconnection failed: $DBI::errstr\n";
sub GetSlaveEpoch
 $sth = $dbhS->prepare("SELECT MAX(epoch)
                       FROM mysql.ndb_apply_status;")
     or die "Error while preparing to select epoch from slave: ",
            $dbhS->errstr;
 $sth->execute
     or die "Selecting epoch from slave error: ", $sth->errstr;
 $sth->bind_col (1, \$epoch);
 $sth->fetch;
 print "\tSlave Epoch = $epoch\n";
 $sth->finish;
###### Find the position of the last GCI in the binary log ########
sub GetMasterInfo
 $sth = $dbhM->prepare("SELECT
                         SUBSTRING_INDEX(File, '/', -1), Position
                       FROM mysql.ndb_binlog_index
                       WHERE epoch > $epoch
```

```
ORDER BY epoch ASC LIMIT 1;")
     or die "Prepare to select from master error: ", $dbhM->errstr;
 $sth->execute
     or die "Selecting from master error: ", $sth->errstr;
 $sth->bind_col (1, \$binlog);
 $sth->bind_col (2, \$binpos);
 $sth->fetch;
 print "\tMaster binary log = $binlog\n";
 print "\tMaster binary log position = $binpos\n";
 $sth->finish;
######## Set the slave to process from that location ########
sub UpdateSlave
 $sth = $dbhS->prepare("CHANGE MASTER TO
                     MASTER_LOG_FILE='$binlog',
                       MASTER_LOG_POS=$binpos;")
     or die "Prepare to CHANGE MASTER error: ", $dbhS->errstr;
 $sth->execute
      or die "CHANGE MASTER on slave error: ", $sth->errstr;
 $sth->finish;
 print "\tSlave has been updated. You may now start the slave.\n";
 end reset-slave.pl
```

### 8.9.2 Point-In-Time Recovery Using MySQL Cluster Replication

<u>Point-in-time</u> recovery—that is, recovery of data changes made since a given point in time—is performed after restoring a full backup that returns the server to its state when the backup was made. Performing point-in-time recovery of MySQL Cluster tables with MySQL Cluster and MySQL Cluster Replication can be accomplished using a native NDB data backup (taken by issuing CREATE BACKUP in the ndb\_mgm client) and restoring the ndb\_binlog\_index table (from a dump made using mysqldump).

To perform point-in-time recovery of MySQL Cluster, it is necessary to follow the steps shown here:

- 1. Back up all NDB databases in the cluster, using the START BACKUP command in the ndb\_mgm client (see Section 7.3, "Online Backup of MySQL Cluster").
- 2. At some later point, prior to restoring the cluster, make a backup of the mysql.ndb\_binlog\_index table. It is probably simplest to use mysqldump for this task. Also back up the binary log files at this time.

This backup should be updated regularly—perhaps even hourly—depending on your needs.

- 3. (Catastrophic failure or error occurs.)
- 4. Locate the last known good backup.
- 5. Clear the data node file systems (using ndbd --initial or, in MySQL Cluster NDB 7.0 and later, ndbmtd --initial).

### Note

MySQL Cluster Disk Data tablespace and log files are not removed by --initial. You must delete these manually.

- 6. Use DROP TABLE or TRUNCATE TABLE with the mysgl.ndb\_binlog\_index table.
- 7. Execute ndb\_restore, restoring all data. You must include the --restore\_epoch [334] option when you run ndb\_restore, so that the ndb\_apply\_status table is populated correctly. (See Section 6.19, "ndb\_restore Restore a MySQL Cluster Backup", for more information.)

- 8. Restore the ndb\_binlog\_index table from the output of mysqldump and restore the binary log files from backup, if necessary.
- 9. Find the epoch applied most recently—that is, the maximum epoch column value in the ndb\_apply\_status table—as the user variable @LATEST\_EPOCH (emphasized):

```
SELECT @LATEST_EPOCH:=MAX(epoch)
FROM mysql.ndb_apply_status;
```

10. Find the latest binary log file (@FIRST\_FILE) and position (Position column value) within this file that correspond to @LATEST\_EPOCH in the ndb\_binlog\_index table:

```
SELECT Position, @FIRST_FILE:=File
FROM mysql.ndb_binlog_index
WHERE epoch > @LATEST_EPOCH ORDER BY epoch ASC LIMIT 1;
```

11. Using mysqlbinlog, replay the binary log events from the given file and position up to the point of the failure. (See mysqlbinlog — Utility for Processing Binary Log Files.)

See also Point-in-Time (Incremental) Recovery Using the Binary Log, for more information about the binary log, replication, and incremental recovery.

# 8.10 MySQL Cluster Replication: Multi-Master and Circular Replication

Beginning with MySQL 5.1.18, it is possible to use MySQL Cluster in multi-master replication, including circular replication between a number of MySQL Clusters.

### Note


Prior to MySQL 5.1.18, multi-master replication including circular replication was not supported with MySQL Cluster replication. This was because log events created in a particular MySQL Cluster were wrongly tagged with the server ID of the master rather than the server ID of the originating server.

**Circular replication example.** In the next few paragraphs we consider the example of a replication setup involving three MySQL Clusters numbered 1, 2, and 3, in which Cluster 1 acts as the replication master for Cluster 2, Cluster 2 acts as the master for Cluster 3, and Cluster 3 acts as the master for Cluster 1. Each cluster has two SQL nodes, with SQL nodes A and B belonging to Cluster 1, SQL nodes C and D belonging to Cluster 2, and SQL nodes E and F belonging to Cluster 3.

Circular replication using these clusters is supported as long as the following conditions are met:


- The SQL nodes on all masters and slaves are the same
- All SQL nodes acting as replication masters and slaves are started using the --log-slave-updates option

This type of circular replication setup is shown in the following diagram:



In this scenario, SQL node A in Cluster 1 replicates to SQL node C in Cluster 2; SQL node C replicates to SQL node E in Cluster 3; SQL node E replicates to SQL node A. In other words, the replication line (indicated by the red arrows in the diagram) directly connects all SQL nodes used as replication masters and slaves.

It is also possible to set up circular replication in such a way that not all master SQL nodes are also slaves, as shown here:




In this case, different SQL nodes in each cluster are used as replication masters and slaves. However, you must *not* start any of the SQL nodes using <code>--log-slave-updates</code>. This type of circular replication scheme for MySQL Cluster, in which the line of replication (again indicated by the red arrows in the diagram) is discontinuous, should be possible, but it should be noted that it has not yet been thoroughly tested and must therefore still be considered experimental.

Using NDB-native backup and restore to initialize a slave MySQL Cluster. When setting up circular replication, it is possible to initialize the slave cluster by using the management client BACKUP command on one MySQL Cluster to create a backup and then applying this backup on another MySQL Cluster using ndb\_restore. However, this does not automatically create binary logs on the second MySQL Cluster's SQL node acting as the replication slave. In order to cause the binary logs to be created, you must issue a SHOW TABLES statement on that SQL node; this should be done prior to running START SLAVE.


This is a known issue which we intend to address in a future release.

**Multi-master failover example.** In this section, we discuss failover in a multi-master MySQL Cluster replication setup with three MySQL Clusters having server IDs 1, 2, and 3. In this scenario, Cluster 1 replicates to Clusters 2 and 3; Cluster 2 also replicates to Cluster 3. This relationship is shown here:



In other words, data replicates from Cluster 1 to Cluster 3 through 2 different routes: directly, and by way of Cluster 2.

Not all MySQL servers taking part in multi-master replication must act as both master and slave, and a given MySQL Cluster might use different SQL nodes for different replication channels. Such a case is shown here:



MySQL servers acting as replication slaves must be run with the --log-slave-updates option. Which mysqld processes require this option is also shown in the preceding diagram.

### Note

Using the --log-slave-updates option has no effect on servers not being run as replication slaves.

The need for failover arises when one of the replicating clusters goes down. In this example, we consider the case where Cluster 1 is lost to service, and so Cluster 3 loses 2 sources of updates from Cluster 1. Because replication between MySQL Clusters is asynchronous, there is no guarantee that Cluster 3's updates originating directly from Cluster 1 are more recent than those received through Cluster 2. You can handle this by ensuring that Cluster 3 catches up to Cluster 2 with regard to updates from Cluster 1. In terms of MySQL servers, this means that you need to replicate any outstanding updates from MySQL server C to server F.

On server C, perform the following queries:

```
mysqlC> SELECT @latest:=MAX(epoch)
    ->     FROM mysql.ndb_apply_status
    ->     WHERE server_id=1;
mysqlC> SELECT
    ->     @file:=SUBSTRING_INDEX(File, '/', -1),
    ->     @pos:=Position
    ->     FROM mysql.ndb_binlog_index
    ->     WHERE orig_epoch >= @latest
    ->     AND orig_server_id = 1
    ->     ORDER BY epoch ASC LIMIT 1;
```

### **Note**

You can improve the performance of this query, and thus likely speed up failover times significantly, by adding the appropriate index to the <a href="mailto:ndex">ndb\_binlog\_index</a> table. See Section 8.4, "MySQL Cluster Replication Schema and Tables", for more information.

Copy over the values for <code>@file</code> and <code>@pos</code> manually from server C to server F (or have your application perform the equivalent). Then, on server F, execute the following <code>CHANGE MASTER TO</code> statement:

```
mysqlF> CHANGE MASTER TO
    ->     MASTER_HOST = 'serverC'
    ->     MASTER_LOG_FILE='@file',
    ->     MASTER_LOG_POS=@pos;
```

Once this has been done, you can issue a START SLAVE statement on MySQL server F, and any missing updates originating from server B will be replicated to server F.

Beginning with MySQL Cluster MySQL Cluster NDB 6.1.29, MySQL Cluster NDB 6.3.31, MySQL Cluster NDB 7.0.11, and MySQL Cluster NDB 7.1.0, the CHANGE MASTER TO statement also supports an IGNORE\_SERVER\_IDS option which takes a comma-separated list of server IDs and causes events originating from the corresponding servers to be ignored. For more information, see CHANGE MASTER TO Syntax, and SHOW SLAVE STATUS Syntax.

## 8.11 MySQL Cluster Replication Conflict Resolution

When using a replication setup involving multiple masters (including circular replication), it is possible that different masters may try to update the same row on the slave with different data. Conflict resolution in MySQL Cluster Replication provides a means of resolving such conflicts by permitting a user-defined resolution column to be used to determine whether or not an update on a given master should be applied on the slave.

Some types of conflict resolution supported by MySQL Cluster (NDB\$OLD(), NDB\$MAX(), NDB \$MAX\_DELETE\_WIN()) implement this user-defined column as a "timestamp" column (although its type cannot be TIMESTAMP, as explained later in this section). These types of conflict resolution are always applied a row-by-row basis rather than a transactional basis. The epoch-based conflict resolution functions introduced in MySQL Cluster NDB 7.1.16 (NDB\$EPOCH() and NDB\$EPOCH\_TRANS()) compare the order in which epochs are replicated (and thus these functions are transactional). Different methods can be used to compare resolution column values on the slave when conflicts occur, as explained later in this section; the method used can be set on a per-table basis.

You should also keep in mind that it is the application's responsibility to ensure that the resolution column is correctly populated with relevant values, so that the resolution function can make the appropriate choice when determining whether to apply an update.

**Requirements.** Preparations for conflict resolution must be made on both the master and the slave. These tasks are described in the following list:

• On the master writing the binary logs, you must determine which columns are sent (all columns or only those that have been updated). This is done for the MySQL Server as a whole by applying the mysqld startup option --ndb-log-updated-only [504] (described later in this section) or on a per-table basis by entries in the mysql.ndb\_replication table (see The ndb\_replication system table).

### Note

If you are replicating tables with very large columns (such as TEXT or BLOB columns), --ndb-log-updated-only [504] can also be useful for reducing the size of the master and slave binary logs and avoiding possible replication failures due to exceeding max\_allowed\_packet.

See Replication and max\_allowed\_packet, for more information about this issue.

- On the slave, you must determine which type of conflict resolution to apply ("latest timestamp wins", "same timestamp wins", or none). This is done using the mysql.ndb\_replication system table, on a per-table basis (see The ndb\_replication system table).
- Prior to MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, conflict detection and resolution did not always work properly unless set up for NDB tables created on the same server only (Bug #13578660).

When using the functions NDB\$OLD(), NDB\$MAX(), and NDB\$MAX\_DELETE\_WIN() for timestamp-based conflict resolution, we often refer to the column used for determining updates as a "timestamp" column, but the data type of this column is never TIMESTAMP; rather, its data type should be INT (INTEGER) or BIGINT. The "timestamp" column should also be UNSIGNED and NOT NULL.

**Master column control.** We can see update operations in terms of "before" and "after" images—that is, the states of the table before and after the update is applied. Normally, when updating a table with a primary key, the "before" image is not of great interest; however, when we need to determine on a perupdate basis whether or not to use the updated values on a replication slave, we need to make sure that both images are written to the master's binary log. This is done with the --ndb-log-update-as-write [505] option for mysqld, as described later in this section.

### **Important**

Whether logging of complete rows or of updated columns only is done is decided when the MySQL server is started, and cannot be changed online; you must either restart mysqld, or start a new mysqld instance with different logging options.

### Logging Full or Partial Rows (--ndb-log-updated-only Option)

Introduced	5.1.19-ndb-6.3.0		
Command-Line Format	ndb-log-updated-only		
Option-File Format	ndb_log_updated_only		
System Variable Name	ndb_log	g_updated_only	
Variable Scope	Global		
Dynamic Variable	Yes Permitted Values		
	Туре	boolean	
	Default	ON	

For purposes of conflict resolution, there are two basic methods of logging rows, as determined by the setting of the --ndb-log-updated-only [504] option for mysqld:

- · Log complete rows
- Log only column data that has been updated—that is, column data whose value has been set, regardless of whether or not this value was actually changed. This is the default behavior.

It is usually sufficient—and more efficient—to log updated columns only; however, if you need to log full rows, you can do so by setting --ndb-log-updated-only [504] to 0 or OFF.

# --ndb-log-update-as-write [505] Option: Logging Changed Data as Updates

Introduced 5.1.19-ndb-6.3.0, 5.1.22-ndb-6.2.5
---

Command-Line Format	ndb-log-update-as-write		
Option-File Format	ndb-log-update-as-write		
System Variable Name	ndb_log_update_as_write		
Variable Scope	Global		
Dynamic Variable	Yes		
	Permitted Values		
	Туре	boolean	
	Default	ON	

The setting of the MySQL Server's --ndb-log-update-as-write [505] option determines whether logging is performed with or without the "before" image. Because conflict resolution is done in the MySQL Server's update handler, it is necessary to control logging on the master such that updates are updates and not writes; that is, such that updates are treated as changes in existing rows rather than the writing of new rows (even though these replace existing rows). This option is turned on by default; in other words, updates are treated as writes. (That is, updates are by default written as write\_row events in the binary log, rather than as update\_row events.) To turn off the option, start the master mysqld with --ndb-log-update-as-write=0[505] or --ndb-log-update-as-write=OFF.

**Conflict resolution control.** Conflict resolution is usually enabled on the server where conflicts can occur. Like logging method selection, it is enabled by entries in the mysql.ndb\_replication table.

The ndb\_replication system table. To enable conflict resolution, it is necessary to create an ndb\_replication table in the mysql system database on the master, the slave, or both, depending on the conflict resolution type and method to be employed. This table is used to control logging and conflict resolution functions on a per-table basis, and has one row per table involved in replication. ndb\_replication is created and filled with control information on the server where the conflict is to be resolved. In a simple master-slave setup where data can also be changed locally on the slave this will typically be the slave. In a more complex master-master (2-way) replication schema this will usually be all of the masters involved. Each row in mysql.ndb\_replication corresponds to a table being replicated, and specifies how to log and resolve conflicts (that is, which conflict resolution function, if any, to use) for that table. The definition of the mysql.ndb\_replication table is shown here:

```
CREATE TABLE mysql.ndb_replication (
    db VARBINARY(63),
    table_name VARBINARY(63),
    server_id INT UNSIGNED,
    binlog_type INT UNSIGNED,
    conflict_fn VARBINARY(128),
    PRIMARY KEY USING HASH (db, table_name, server_id)
) ENGINE=NDB
PARTITION BY KEY(db,table_name);
```

The columns in this table are described in the next few paragraphs.

**db.** The name of the database containing the table to be replicated.

Beginning with MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, you may employ either or both of the wildcards \_ and % as part of the database name. Matching is similar to what is implemented for the LIKE operator.

table\_name. The name of the table to be replicated.

Beginning with MySQL Cluster NDB 7.0.31 and MySQL Cluster NDB 7.1.20, the table name may include either or both of the wildcards and %. Matching is similar to what is implemented for the LIKE operator.

server\_id. The unique server ID of the MySQL instance (SQL node) where the table resides.

**binlog\_type.** The type of binary logging to be employed. This is determined as shown in the following table:

Value	Internal Value	Description
0	NBT_DEFAULT	Use server default
1	NBT_NO_LOGGING	Do not log this table in the binary log
2	NBT_UPDATED_ONLY	Only updated attributes are logged
3	NBT_FULL	Log full row, even if not updated (MySQL server default behavior)
4	NBT_USE_UPDATE	(For generating NBT_UPDATED_ONLY_USE_UPDATE and NBT_FULL_USE_UPDATE values only—not intended for separate use)
5	[Not used]	
6	NBT_UPDATED_ONLY_USE_UPDATE (equal to NBT_UPDATED_ONLY   NBT_USE_UPDATE)	Use updated attributes, even if values are unchanged
7	NBT_FULL_USE_UPDATE (equal to NBT_FULL   NBT_USE_UPDATE)	Use full row, even if values are unchanged

**conflict\_fn.** The conflict resolution function to be applied. This function must be specified as one of those shown in the following list:

- NDB\$OLD(column\_name)
- NDB\$MAX(column name)
- NDB\$MAX\_DELETE\_WIN(column\_name)
- NDB\$EPOCH() and NDB\$EPOCH\_TRANS() (MySQL Cluster NDB 7.1.16 and later)
- NDB\$EPOCH\_TRANS() (MySQL Cluster NDB 7.1.16 and later)
- NULL

These functions are described in the next few paragraphs.

NDB\$OLD(column\_name). If the value of column\_name is the same on both the master and the slave, then the update is applied; otherwise, the update is not applied on the slave and an exception is written to the log. This is illustrated by the following pseudocode:

```
if (master_old_column_value == slave_current_column_value)
  apply_update();
else
  log_exception();
```

This function can be used for "same value wins" conflict resolution. This type of conflict resolution ensures that updates are not applied on the slave from the wrong master.

### **Important**

The column value from the master's "before" image is used by this function.

NDB\$MAX(column\_name). If the "timestamp" column value for a given row coming from the master is higher than that on the slave, it is applied; otherwise it is not applied on the slave. This is illustrated by the following pseudocode:

```
if (master_new_column_value > slave_current_column_value)
   apply_update();
```

This function can be used for "greatest timestamp wins" conflict resolution. This type of conflict resolution ensures that, in the event of a conflict, the version of the row that was most recently updated is the version that persists.

### **Important**

The column value from the master's "after" image is used by this function.

NDB\$MAX\_DELETE\_WIN(column\_name). This is a variation on NDB\$MAX(). Due to the fact that no timestamp is available for a delete operation, a delete using NDB\$MAX() is in fact processed as NDB \$OLD. However, for some use cases, this is not optimal. For NDB\$MAX\_DELETE\_WIN(), if the "timestamp" column value for a given row adding or updating an existing row coming from the master is higher than that on the slave, it is applied. However, delete operations are treated as always having the higher value. This is illustrated in the following pseudocode:

This function can be used for "greatest timestamp, delete wins" conflict resolution. This type of conflict resolution ensures that, in the event of a conflict, the version of the row that was deleted or (otherwise) most recently updated is the version that persists.

#### Note

As with NDB\$MAX ( ), the column value from the master's "after" image is the value used by this function.

NDB\$EPOCH() and NDB\$EPOCH\_TRANS(). The NDB\$EPOCH() function, available beginning with MySQL Cluster NDB 7.1.16, tracks the order in which replicated epochs are applied on a slave MySQL Cluster relative to changes originating on the slave. This relative ordering is used to determine whether changes originating on the slave are concurrent with any changes that originate locally, and are therefore potentially in conflict.

Most of what follows in the description of NDB\$EPOCH() also applies to NDB\$EPOCH\_TRANS(). Any exceptions are noted in the text.

NDB\$EPOCH() is asymmetric, operating on one MySQL Cluster in a two-cluster circular replication configuration (sometimes referred to as "active-active" replication). We refer here to cluster on which it operates as the primary, and the other as the secondary. The slave on the primary is responsible for detecting and handling conflicts, while the slave on the secondary is not involved in any conflict detection or handling.

When the slave on the primary detects conflicts, it injects events into its own binary log to compensate for these; this ensures that the secondary MySQL Cluster eventually realigns itself with the primary and so keeps the primary and secondary from diverging. This compensation and realignment mechanism requires that the primary MySQL Cluster always wins any conflicts with the secondary—that is, that the primary's

changes are always used rather than those from the secondary in event of a conflict. This "primary always wins" rule has the following implications:

- Operations that change data, once committed on the primary, are fully persistent and will not be undone or rolled back by conflict detection and resolution.
- Data read from the primary is fully consistent. Any changes committed on the Primary (locally or from the slave) will not be reverted later.
- Operations that change data on the secondary may later be reverted if the primary determines that they
  are in conflict.
- Individual rows read on the secondary are self-consistent at all times, each row always reflecting either a state committed by the secondary, or one committed by the primary.
- Sets of rows read on the secondary may not necessarily be consistent at a given single point in time. For NDB\$EPOCH\_TRANS(), this is a transient state; for NDB\$EPOCH(), it can be a persistent state.
- Assuming a period of sufficient length without any conflicts, all data on the secondary MySQL Cluster (eventually) becomes consistent with the primary's data.

NDB\$EPOCH() and NDB\$EPOCH\_TRANS() do not require any user schema modifications, or application changes to provide conflict detection. However, careful thought must be given to the schema used, and the access patterns used, to verify that the complete system behaves within specified limits.

Each of the NDB\$EPOCH() and NDB\$EPOCH\_TRANS() functions can take an optional parameter; this is the number of bits to use to represent the lower 32 bits of the epoch, and should be set to no less than

```
CEIL( LOG2( TimeBetweenGlobalCheckpoints / TimeBetweenEpochs ), 1)
```

For the default values of these configuration parameters (2000 and 100 milliseconds, respectively), this gives a value of 5 bits, so the default value (6) should be sufficient, unless other values are used for <code>TimeBetweenGlobalCheckpoints</code>, <code>TimeBetweenEpochs</code>, or both. A value that is too small can result in false positives, while one that is too large could lead to excessive wasted space in the database.

Both NDB\$EFOCH() and NDB\$EFOCH\_TRANS() insert entries for conflicting rows into the relevant exceptions tables, provided that these tables have been defined according to the same exception table schema rules as described elsewhere in this section (see NDB\$OLD(column\_name)). Note that you need to create any exception table before creating the table with which it is to be used.

As with the other conflict detection functions discussed in this section, NDB\$EPOCH() and NDB
\$EPOCH\_TRANS() are activated by including relevant entries in the mysql.ndb\_replication table (see
The ndb\_replication system table). The roles of the primary and secondary MySQL Clusters in this
scenario are fully determined by mysql.ndb replication table entries.

Because the conflict detection algorithms employed by NDB\$EPOCH() and NDB\$EPOCH\_TRANS() are asymmetric, you must use different values for the primary slave's and secondary slave's server\_id entries.

Prior to MySQL Cluster NDB 7.1.32, conflict between DELETE operations were handled like those for UPDATE operations, and within the same epoch were considered in conflict. In MySQL Cluster NDB 7.1.32 and later, a conflict between DELETE operations alone is not sufficient to trigger a conflict using NDB \$EPOCH() or NDB\$EPOCH\_TRANS(), and the relative placement within epochs does not matter. (Bug "18454499)

NDB\$EPOCH() and NDB\$EPOCH\_TRANS() status variables. MySQL Cluster NDB 7.1.16 introduces several status variables that can be used to monitor NDB\$EPOCH() and NDB\$EPOCH TRANS() conflict

detection. You can see how many rows have been found in conflict by NDB\$EPOCH() since this slave was last restarted from the current value of the Ndb conflict fn epoch system status variable.

Ndb\_conflict\_fn\_epoch\_trans provides the number of rows that have been found directly in conflict by NDB\$EPOCH\_TRANS(); the number of rows actually realigned, including those affected due to their membership in or dependency on the same transactions as other conflicting rows, is given by Ndb\_conflict\_trans\_row\_reject\_count.

For more information, see Section 5.4.4, "MySQL Cluster Status Variables".

**Limitations on NDB\$EPOCH().** The following limitations currently apply when using NDB\$EPOCH() to perform conflict detection:

- Conflicts are detected using MySQL Cluster epoch boundaries, with granularity proportional to <code>TimeBetweenEpochs</code> (default: 100 milliseconds). The minimum conflict window is the minimum time during which concurrent updates to the same data on both clusters always report a conflict. This is always a nonzero length of time, and is roughly proportional to <code>2 \* (latency + queueing + TimeBetweenEpochs)</code>. This implies that—assuming the default for <code>TimeBetweenEpochs</code> and ignoring any latency between clusters (as well as any queuing delays)—the minimum conflict window size is approximately 200 milliseconds. This minimum window should be considered when looking at expected application "race" patterns.
- Additional storage is required for tables using the NDB\$EPOCH() and NDB\$EPOCH\_TRANS() functions; from 1 to 32 bits extra space per row is required, depending on the value passed to the function.
- Conflicts between delete operations may result in divergence between the primary and secondary. When
  a row is deleted on both clusters concurrently, the conflict can be detected, but is not recorded, since the
  row is deleted. This means that further conflicts during the propagation of any subsequent realignment
  operations will not be detected, which can lead to divergence.
  - Deletes should be externally serialized, or routed to one cluster only. Alternatively, a separate row should be updated transactionally with such deletes and any inserts that follow them, so that conflicts can be tracked across row deletes. This may require changes in applications.
- Only two MySQL Clusters in a circular "active-active" configuration are currently supported when using NDB\$EPOCH() or NDB\$EPOCH\_TRANS() for conflict detection.
- Tables having BLOB or TEXT columns are not currently supported with NDB\$EPOCH() or NDB \$EPOCH\_TRANS().

NDB\$EPOCH\_TRANS(). NDB\$EPOCH\_TRANS() extends the NDB\$EPOCH() function, and, like NDB \$EPOCH(), is available beginning with MySQL Cluster NDB 7.1.16. Conflicts are detected and handled in the same way using the "primary wins all" rule (see NDB\$EPOCH() and NDB\$EPOCH\_TRANS()) but with the extra condition that any other rows updated in the same transaction in which the conflict occurred are also regarded as being in conflict. In other words, where NDB\$EPOCH() realigns individual conflicting rows on the secondary, NDB\$EPOCH\_TRANS() realigns conflicting transactions.

In addition, any transactions which are detectably dependent on a conflicting transaction are also regarded as being in conflict, these dependencies being determined by the contents of the secondary cluster's binary log. Since the binary log contains only data modification operations (inserts, updates, and deletes), only overlapping data modifications are used to determine dependencies between transactions.

NDB\$EPOCH\_TRANS() is subject to the same conditions and limitations as NDB\$EPOCH(), and in addition requires that Version 2 binary log row events are used (--log-bin-use-vl-row-events equal to 0), which adds a storage overhead of 2 bytes per event in the binary log. In addition, all transaction IDs must be recorded in the secondary's binary log (--ndb-log-transaction-id option), which adds a further variable overhead (up to 13 bytes per row).

See NDB\$EPOCH() and NDB\$EPOCH\_TRANS().

**NULL.** Indicates that conflict resolution is not to be used for the corresponding table.

**Status information.** Beginning with MySQL Cluster NDB 6.3.3, a server status variable Ndb\_conflict\_fn\_max provides a count of the number of times that a row was not applied on the current SQL node due to "greatest timestamp wins" conflict resolution since the last time that mysqld was started.

Beginning with MySQL Cluster NDB 6.3.4, the number of times that a row was not applied as the result of "same timestamp wins" conflict resolution on a given mysqld since the last time it was restarted is given by the global status variable Ndb\_conflict\_fn\_old. In addition to incrementing Ndb\_conflict\_fn\_old, the primary key of the row that was not used is inserted into an exceptions table, as explained later in this section.

**Exceptions table.** To use the NDB\$OLD() conflict resolution function, it is also necessary to create an exceptions table corresponding to each NDB table for which this type of conflict resolution is to be employed. This is also true when using NDB\$EPOCH() or NDB\$EPOCH\_TRANS() in MySQL Cluster NDB 7.1.16 and later. The name of this table is that of the table for which conflict resolution is to be applied, with the string \$EX appended. (For example, if the name of the original table is mytable, the name of the corresponding exception table name should be mytable\$EX.) This table is created as follows:

```
CREATE TABLE original_table$EX (
    server_id INT UNSIGNED,
    master_server_id INT UNSIGNED,
    master_epoch BIGINT UNSIGNED,
    count INT UNSIGNED,
    original_table_pk_columns,
    [additional_columns,]
    PRIMARY KEY(server_id, master_server_id, master_epoch, count)
) ENGINE=NDB;
```

The first four columns are required. Following these columns, the columns making up the original table's primary key should be copied in the order in which they are used to define the primary key of the original table.

### **Note**

The names of the first four columns and the columns matching the original table's primary key columns are not critical; however, we suggest for reasons of clarity and consistency, that you use the names shown here for the server\_id, master\_server\_id, master\_epoch, and count columns, and that you use the same names as in the original table for the columns matching those in the original table's primary key.

The data types for the columns duplicating the primary key columns of the original table should be the same as for (or larger than) the original columns.

Additional columns may optionally be defined following these columns, but not before any of them; any such extra columns cannot be NOT NULL. The exception table's primary key must be defined as shown. The exception table must use the NDB storage engine. An example that uses NDB\$OLD() with an exceptions table is shown later in this section.

### **Important**

The mysql.ndb\_replication table is read when a data table is set up for replication, so the row corresponding to a table to be replicated must be inserted into mysql.ndb\_replication *before* the table to be replicated is created.

**Examples.** The following examples assume that you have already a working MySQL Cluster replication setup, as described in Section 8.5, "Preparing the MySQL Cluster for Replication", and Section 8.6, "Starting MySQL Cluster Replication (Single Replication Channel)".

- NDB\$MAX() example. Suppose you wish to enable "greatest timestamp wins" conflict resolution on table test.t1, using column mycol as the "timestamp". This can be done using the following steps:
  - 1. Make sure that you have started the master mysqld with --ndb-log-update-as-write=OFF [505].
  - 2. On the master, perform this INSERT statement:

```
INSERT INTO mysql.ndb_replication
   VALUES ('test', 't1', 0, NULL, 'NDB$MAX(mycol)');
```

Inserting a 0 into the server\_id indicates that all SQL nodes accessing this table should use conflict resolution. If you want to use conflict resolution on a specific mysqld only, use the actual server ID.

Inserting NULL into the binlog\_type column has the same effect as inserting 0 (NBT\_DEFAULT); the server default is used.

3. Create the test.t1 table:

```
CREATE TABLE test.t1 (
    columns
    mycol INT UNSIGNED,
    columns
) ENGINE=NDB;
```

Now, when updates are done on this table, conflict resolution is applied, and the version of the row having the greatest value for mycol is written to the slave.

### Note

Other binlog\_type options—such as NBT\_UPDATED\_ONLY\_USE\_UPDATE should be used to control logging on the master using the ndb\_replication table rather than by using command-line options.

• NDB\$OLD() example. Suppose an NDB table such as the one defined here is being replicated, and you wish to enable "same timestamp wins" conflict resolution for updates to this table:

```
CREATE TABLE test.t2 (
   a INT UNSIGNED NOT NULL,
   b CHAR(25) NOT NULL,
   columns,
   mycol INT UNSIGNED NOT NULL,
   columns,
   PRIMARY KEY pk (a, b)
) ENGINE=NDB;
```

The following steps are required, in the order shown:

1. First—and *prior* to creating test.t2—you must insert a row into the mysql.ndb\_replication table, as shown here:

```
INSERT INTO mysql.ndb_replication
```

```
VALUES ('test', 't2', 0, NULL, 'NDB$OLD(mycol)');
```

Possible values for the binlog\_type column are shown earlier in this section. The value 'NDB \$OLD(mycol)' should be inserted into the conflict\_fn column.

2. Create an appropriate exceptions table for test.t2. The table creation statement shown here includes all required columns; any additional columns must be declared following these columns, and before the definition of the table's primary key.

```
CREATE TABLE test.t2$EX (
    server_id SMALLINT UNSIGNED,
    master_server_id INT UNSIGNED,
    master_epoch BIGINT UNSIGNED,
    count BIGINT UNSIGNED,
    a INT UNSIGNED NOT NULL,
    b CHAR(25) NOT NULL,
    [additional_columns,]
    PRIMARY KEY(server_id, master_server_id, master_epoch, count)
) ENGINE=NDB;
```

3. Create the table test.t2 as shown previously.

These steps must be followed for every table for which you wish to perform conflict resolution using NDB \$OLD(). For each such table, there must be a corresponding row in mysql.ndb\_replication, and there must be an exceptions table in the same database as the table being replicated.

# Appendix A Licenses for Third-Party Components

### **Table of Contents**

A.1 ANTER 3 License	515
A.2 dtoa.c License	516
A.3 Editline Library (libedit) License	516
A.4 FindGTest.cmake License	519
A.5 Fred Fish's Dbug Library License	519
A.6 getarg License	520
A.7 GLib License (for MySQL Proxy)	
A.8 GNU General Public License Version 2.0, June 1991	522
A.9 GNU Lesser General Public License Version 2.1, February 1999	527
A.10 GNU Libtool License	535
A.11 GNU Readline License	536
A.12 Google Controlling Master Thread I/O Rate Patch License	536
A.13 Google Perftools (TCMalloc utility) License	537
A.14 Google SMP Patch License	537
A.15 lib_sql.cc License	538
A.16 libevent License	538
A.17 Libiconv License	540
A.18 libintl License	540
A.19 Linux-PAM License	541
A.20 LPeg Library License	542
A.21 Lua (liblua) License	542
A.22 LuaFileSystem Library License	
A.23 md5 (Message-Digest Algorithm 5) License	543
A.24 memcached License	544
A.25 nt_servc (Windows NT Service class library) License	544
A.26 OpenPAM License	544
A.27 Paramiko License	545
A.28 PCRE License	545
A.29 Percona Multiple I/O Threads Patch License	546
A.30 RegEX-Spencer Library License	547
A.31 RFC 3174 - US Secure Hash Algorithm 1 (SHA1) License	547
A.32 Richard A. O'Keefe String Library License	548
A.33 SHA-1 in C License	
A.34 zlib License	549

The following is a list of the libraries we have included with the MySQL Server source and components used to test MySQL. We are thankful to all individuals that have created these. Some of the components require that their licensing terms be included in the documentation of products that include them. Cross references to these licensing terms are given with the applicable items in the list.

### • Bjorn Benson

For his safe\_malloc (memory checker) package which is used in when you build MySQL using one of the BUILD/compile-\*-debug scripts or by manually setting the -DSAFEMALLOC flag.

· GroupLens Research Project

The MySQL Quality Assurance team would like to acknowledge the use of the MovieLens Data Sets (10 million ratings and 100,000 tags for 10681 movies by 71567 users) to help test MySQL products and to thank the GroupLens Research Project at the University of Minnesota for making the data sets available.

### MySQL 5.1

- · Section A.2, "dtoa.c License"
- · Section A.3, "Editline Library (libedit) License"
- Section A.4, "FindGTest.cmake License"
- Section A.5, "Fred Fish's Dbug Library License"
- Section A.6, "getarg License"
- Section A.8, "GNU General Public License Version 2.0, June 1991"
- Section A.10, "GNU Libtool License"
- Section A.11, "GNU Readline License"
- Section A.12, "Google Controlling Master Thread I/O Rate Patch License"
- Section A.14, "Google SMP Patch License"
- Section A.15, "lib\_sql.cc License"
- Section A.23, "md5 (Message-Digest Algorithm 5) License"
- Section A.25, "nt servc (Windows NT Service class library) License"
- Section A.29, "Percona Multiple I/O Threads Patch License"
- Section A.30, "RegEX-Spencer Library License"
- Section A.31, "RFC 3174 US Secure Hash Algorithm 1 (SHA1) License"
- Section A.32, "Richard A. O'Keefe String Library License"
- Section A.34, "zlib License"

### MySQL Cluster 7.1

- Section A.1, "ANTLR 3 License"
- Section A.2, "dtoa.c License"
- Section A.3, "Editline Library (libedit) License"
- · Section A.4, "FindGTest.cmake License"
- Section A.5, "Fred Fish's Dbug Library License"
- Section A.6, "getarg License"
- Section A.8, "GNU General Public License Version 2.0, June 1991"
- Section A.9, "GNU Lesser General Public License Version 2.1, February 1999"

- Section A.10, "GNU Libtool License"
- Section A.11, "GNU Readline License"
- Section A.12, "Google Controlling Master Thread I/O Rate Patch License"
- Section A.13, "Google Perftools (TCMalloc utility) License"
- Section A.14, "Google SMP Patch License"
- Section A.15, "lib\_sql.cc License"
- Section A.16, "libevent License"
- · Section A.19, "Linux-PAM License"
- Section A.23, "md5 (Message-Digest Algorithm 5) License"
- Section A.24, "memcached License"
- Section A.25, "nt\_servc (Windows NT Service class library) License"
- Section A.26, "OpenPAM License"
- · Section A.27, "Paramiko License"
- Section A.29, "Percona Multiple I/O Threads Patch License"
- Section A.30, "RegEX-Spencer Library License"
- Section A.32, "Richard A. O'Keefe String Library License"
- Section A.33, "SHA-1 in C License"
- Section A.34, "zlib License"

## **MySQL Proxy**

- Section A.7, "GLib License (for MySQL Proxy)"
- Section A.9, "GNU Lesser General Public License Version 2.1, February 1999"
- Section A.16, "libevent License"
- Section A.17, "Libiconv License"
- Section A.18, "libintl License"
- Section A.20, "LPeg Library License"
- Section A.21, "Lua (liblua) License"
- Section A.22, "LuaFileSystem Library License"
- Section A.28, "PCRE License"

### A.1 ANTLR 3 License

The following software may be included in this product:

ANTLR 3

ANTLR 3 License [The BSD License] Copyright (c) 2003-2007, Terence Parr All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

### A.2 dtoa.c License

The following software may be included in this product:

#### dtoa.c

The author of this software is David M. Gay.

Copyright (c) 1991, 2000, 2001 by Lucent Technologies.

Permission to use, copy, modify, and distribute this software for any purpose without fee is hereby granted, provided that this entire notice is included in all copies of any software which is or includes a copy or modification of this software and in all copies of the supporting documentation for such software.

THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.

# A.3 Editline Library (libedit) License

The following software may be included in this product:

Editline Library (libedit)

#### Some files are:

Copyright (c) 1992, 1993
The Regents of the University of California. All rights reserved.

This code is derived from software contributed to Berkeley by Christos Zoulas of Cornell University.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the University nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING,
BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO
EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY
DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING
IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED
OF THE POSSIBILITY OF SUCH DAMAGE.

### Some files are:

Copyright (c) 2001 The NetBSD Foundation, Inc. All rights reserved.

This code is derived from software contributed to The NetBSD Foundation

by Anthony Mallet.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE NETBSD FOUNDATION, INC. AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE FOUNDATION OR CONTRIBUTORS BE LIABLE FOR ANY

DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

#### Some files are:

Copyright (c) 1997 The NetBSD Foundation, Inc. All rights reserved.

This code is derived from software contributed to The NetBSD Foundation

by Jaromir Dolecek.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce
  the above copyright notice, this list of conditions
  and the following disclaimer in the documentation
  and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE NETBSD FOUNDATION, INC. AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE FOUNDATION OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH

#### Some files are:

Copyright (c) 1998 Todd C. Miller <Todd.Miller@courtesan.com>

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED "AS IS" AND TODD C. MILLER DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL TODD C. MILLER BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR

PERFORMANCE OF THIS SOFTWARE.

### A.4 FindGTest.cmake License

The following software may be included in this product:

```
FindGTest.cmake helper script (part of CMake)
Copyright 2009 Kitware, Inc.
Copyright 2009 Philip Lowman
Copyright 2009 Daniel Blezek
Distributed under the OSI-approved BSD License (the "License");
see accompanying file Copyright.txt for details.
This software is distributed WITHOUT ANY WARRANTY; without even the
implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.
See the License for more information.
_____
(To distributed this file outside of CMake, substitute the full
 License text for the above reference.)
Thanks to Daniel Blezek for the GTEST_ADD_TESTS code
Text of Copyright.txt mentioned above:
CMake - Cross Platform Makefile Generator
Copyright 2000-2009 Kitware, Inc., Insight Software Consortium
All rights reserved.
Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
* Redistributions of source code must retain the above copyright
 notice, this list of conditions and the following disclaimer.
* Redistributions in binary form must reproduce the above copyright
 notice, this list of conditions and the following disclaimer in the
 documentation and/or other materials provided with the distribution.
* Neither the names of Kitware, Inc., the Insight Software Consortium,
 nor the names of their contributors may be used to endorse or promote
 products derived from this software without specific prior written
 permission.
THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

# A.5 Fred Fish's Dbug Library License

The following software may be included in this product:

Fred Fish's Dbug Library

#### NOTICE

Copyright Abandoned, 1987, Fred Fish

This previously copyrighted work has been placed into the public domain by the author and may be freely used for any purpose, private or commercial.

Because of the number of inquiries I was receiving about the use of this product in commercially developed works I have decided to simply make it public domain to further its unrestricted use. I specifically would be most happy to see this material become a part of the standard Unix distributions by AT&T and the Berkeley Computer Science Research Group, and a standard part of the GNU system from the Free Software Foundation.

I would appreciate it, as a courtesy, if this notice is left in all copies and derivative works. Thank you.

The author makes no warranty of any kind with respect to this product and explicitly disclaims any implied warranties of merchantability or fitness for any particular purpose.

The dbug\_analyze.c file is subject to the following notice:

Copyright June 1987, Binayak Banerjee All rights reserved.

This program may be freely distributed under the same terms and conditions as Fred Fish's Dbug package.

### A.6 getarg License

The following software may be included in this product:

getarg Function (getarg.h, getarg.c files)

Copyright (c) 1997 - 2000 Kungliga Tekniska Högskolan (Royal Institute of Technology, Stockholm, Sweden). All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the

following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the Institute nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE INSTITUTE AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING,
BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO
EVENT SHALL THE INSTITUTE OR CONTRIBUTORS BE LIABLE FOR ANY
DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE
GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS
INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY,
WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH
DAMAGE.

# A.7 GLib License (for MySQL Proxy)

The following software may be included in this product:

```
GLib
You are receiving a copy of the GLib library in both source
and object code in the following [proxy install dir]/lib/ and
[proxy install dir]/licenses/lgpl folders. The terms of the
Oracle license do NOT apply to the GLib library; it is licensed
under the following license, separately from the Oracle programs
you receive. If you do not wish to install this library, you may
create an "exclude" file and run tar with the X option, as in
the following example, but the Oracle program might not operate
properly or at all without the library:
  tar -xvfX <package-tar-file> <exclude-file>
where the exclude-file contains, e.g.:
  <package-name>/lib/libglib-2.0.so.0.1600.6
 <package-name>/lib/libglib-2.0.so.0
Example:
tar -xvfX mysql-proxy-0.8.1-solaris10-x86-64bit.tar.gz Exclude
Exclude File:
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libglib-2.0.so
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libglib-2.0.so.0
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libglib-2.0.so.0.1600.6
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgmodule-2.0.so
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgmodule-2.0.so.0
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgmodule-2.0.so.0.1600.6
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgthread-2.0.so
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgthread-2.0.so.0
mysql-proxy-0.8.1-solaris10-x86-64bit/lib/libgthread-2.0.so.0.1600.6
mysql-proxy-0.8.1-solaris10-x86-64bit/licenses/lgpl/glib-2.16.6.tar.gz
```

This component is licensed under Section A.9, "GNU Lesser General Public License Version 2.1, February 1999".

### A.8 GNU General Public License Version 2.0, June 1991

The following applies to all products licensed under the GNU General Public License, Version 2.0: You may not use the identified files except in compliance with the GNU General Public License, Version 2.0 (the "License.") You may obtain a copy of the License at http://www.gnu.org/licenses/gpl-2.0.txt. A copy of the license is also reproduced below. Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

GNU GENERAL PUBLIC LICENSE Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software—to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Lesser General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and  $\mbox{modification follow}.$ 

GNU GENERAL PUBLIC LICENSE
TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

O. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

- 2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
  - a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
  - b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
  - c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program,

and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

- 3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:
  - a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
  - b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
  - c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

- 4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
- 5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or

distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.

- 6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.
- 7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

#### NO WARRANTY

- 11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.
- 12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

#### END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

<one line to give the program's name and a brief idea of what it
does.>

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA.

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this

when it starts in an interactive mode:

Gnomovision version 69, Copyright (C) year name of author Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type 'show w'. This is free software, and you are welcome to redistribute it under certain conditions; type 'show c' for details.

The hypothetical commands 'show w' and 'show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than 'show w' and 'show c'; they could even be mouse-clicks or menu items--whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the program 'Gnomovision' (which makes passes at compilers) written by James Hacker.

<signature of Ty Coon>, 1 April 1989
Ty Coon, President of Vice

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License.

### A.9 GNU Lesser General Public License Version 2.1, February 1999

The following applies to all products licensed under the GNU Lesser General Public License, Version 2.1: You may not use the identified files except in compliance with the GNU Lesser General Public License, Version 2.1 (the "License"). You may obtain a copy of the License at http://www.gnu.org/licenses/lgpl-2.1.html. A copy of the license is also reproduced below. Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

GNU LESSER GENERAL PUBLIC LICENSE Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software—to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain

special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

GNU LESSER GENERAL PUBLIC LICENSE
TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

- O. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".
- A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact

all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

- 2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
  - a) The modified work must itself be a software library.
  - b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.
  - c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.
  - d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for

that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

- 4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.
- If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.
- 5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever

changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)

- b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.
- c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.
- d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.
- e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

- It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.
- 7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:
  - a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.
  - b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.
- 8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses

terminated so long as such parties remain in full compliance.

- 9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.
- 10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.
- 11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and

conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

#### NO WARRANTY

15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

#### END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Libraries

If you develop a new library, and you want it to be of the greatest possible use to the public, we recommend making it free software that everyone can redistribute and change. You can do so by permitting redistribution under these terms (or, alternatively, under the terms of the ordinary General Public License).

To apply these terms, attach the following notices to the library. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

<one line to give the library's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 2.1 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Lesser General Public License for more details.

You should have received a copy of the GNU Lesser General Public

```
License along with this library; if not, write to the Free Software
Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA
02110-1301 USA

Also add information on how to contact you by electronic and paper mail.

You should also get your employer (if you work as a programmer) or your
school, if any, to sign a "copyright disclaimer" for the library, if
necessary. Here is a sample; alter the names:

Yoyodyne, Inc., hereby disclaims all copyright interest in the
library `Frob' (a library for tweaking knobs) written by James
Random Hacker.

<signature of Ty Coon>, 1 April 1990
Ty Coon, President of Vice

That's all there is to it!
```

#### A.10 GNU Libtool License

The following software may be included in this product:

GNU Libtool (The GNU Portable Library Tool)

```
If you are receiving a copy of the Oracle software in
source code, you are also receiving a copy of two files
(ltmain.sh and ltdl.h) generated by the GNU Libtool in
source code. If you received the Oracle software under
a license other than a commercial (non-GPL) license,
then the terms of the Oracle license do NOT apply to
these files from GNU Libtool; they are licensed under
the following licenses, separately from the Oracle
programs you receive.
Oracle elects to use GNU General Public License version
2 (GPL) for any software where a choice of GPL or GNU
Lesser/Library General Public License (LGPL) license
versions are made available with the language indicating
that GPL/LGPL or any later version may be used, or where
a choice of which version of the GPL/LGPL is applied is
unspecified.
From GNU Libtool:
ltmain.sh - Provide generalized library-building support
services.
NOTE: Changing this file will not affect anything until
you rerun configure.
Copyright (C) 1996, 1997, 1998, 1999, 2000, 2001, 2003, 2004,
2005, 2006, 2007 Free Software Foundation, Inc.
Originally by Gordon Matzigkeit, 1996
This program is free software; you can redistribute it
and/or modify it under the terms of the GNU General
Public License as published by the Free Software Foundation;
either version 2 of the License, or (at your option) any
later version.
This program is distributed in the hope that it will be
useful, but WITHOUT ANY WARRANTY; without even the implied
warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
PURPOSE. See the GNU General Public License for more
details. You should have received a copy of the GNU General
Public License along with this program; if not, write to
```

the Free Software Foundation, Inc., 51 Franklin Street,
Fifth Floor, Boston, MA 02110-1301, USA.

As a special exception to the GNU General Public License,
if you distribute this file as part of a program that
contains a configuration script generated by Autoconf,
you may include it under the same distribution terms that
you use for the rest of that program.

This component is licensed under Section A.8, "GNU General Public License Version 2.0, June 1991"

#### A.11 GNU Readline License

The following software may be included in this product:

**GNU Readline Library** 

GNU Readline Library
With respect to MySQL Server/Cluster software licensed
under GNU General Public License, you are receiving a
copy of the GNU Readline Library in source code. The
terms of any Oracle license that might accompany the
Oracle programs do NOT apply to the GNU Readline Library;
it is licensed under the following license, separately
from the Oracle programs you receive. Oracle elects to
use GNU General Public License version 2 (GPL) for any
software where a choice of GPL license versions are
made available with the language indicating that GPLv2
or any later version may be used, or where a choice of
which version of the GPL is applied is unspecified.

This component is licensed under Section A.8, "GNU General Public License Version 2.0, June 1991"

## A.12 Google Controlling Master Thread I/O Rate Patch License

The following software may be included in this product:

Google Controlling master thread I/O rate patch

Copyright (c) 2009, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER

CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## A.13 Google Perftools (TCMalloc utility) License

The following software may be included in this product:

Google Perftools (TCMalloc utility)

Copyright (c) 1998-2006, Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## A.14 Google SMP Patch License

The following software may be included in this product:

#### Google SMP Patch

Google SMP patch

Copyright (c) 2008, Google Inc.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the Google Inc. nor the names of its contributors

may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING,
BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER
CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN
ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE
POSSIBILITY OF SUCH DAMAGE.

## A.15 lib\_sql.cc License

The following software may be included in this product:

lib\_sql.cc

Copyright (c) 2000 SWsoft company

This material is provided "as is", with absolutely no warranty expressed or implied. Any use is at your own risk.

Permission to use or copy this software for any purpose is hereby granted without fee, provided the above notices are retained on all copies. Permission to modify the code and to distribute modified code is granted, provided the above notices are retained, and a notice that the code was modified is included with the above copyright notice.

This code was modified by the MySQL team.

#### A.16 libevent License

The following software may be included in this product:

libevent

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,

DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE

==

Parts developed by Adam Langley

==

==

log.c

Based on err.c, which was adapted from OpenBSD libc \*err\*warncode.

Copyright (c) 2005 Nick Mathewson

Copyright (c) 2000 Dug Song

Copyright (c) 1993 The Regents of the University of California. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the University nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

==

==

min\_heap.h

Copyright (c) 2006 Maxim Yegorushkin All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE

ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

==

==

win32.c

Copyright 2000-2002 Niels Provos Copyright 2003 Michael A. Davis All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## A.17 Libiconv License

The following software may be included in this product:

Libiconv

You are receiving a copy of the GNU LIBICONV Library. The terms of the Oracle license do NOT apply to the GNU LIBICONV Library; it is licensed under the following license, separately from the Oracle programs you receive. If you do not wish to install this program, you may delete [agent install dir]/lib/libiconv.\* and [agent install dir]/licenses/lgpl/iconv files.

This component is licensed under Section A.9, "GNU Lesser General Public License Version 2.1, February 1999".

### A.18 libintl License

The following software may be included in this product:

libintl

```
Copyright (C) 1994 X Consortium

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.
```

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE X CONSORTIUM BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of the X Consortium shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from the X Consortium.

FSF changes to this file are in the public domain.

. Copyright 1996-2007 Free Software Foundation, Inc. Taken from GNU libtool, 2001

Originally by Gordon Matzigkeit <gord@gnu.ai.mit.edu>, 1996

This file is free software; the Free Software Foundation gives unlimited permission to copy and/or distribute it, with or without modifications, as long as this notice is preserved.

You are receiving a copy of the libintl library. The terms of the Oracle license do NOT apply to the libintl library; it is licensed under the following license, separately from the Oracle programs you receive. If you do not wish to install this program, you may create an "exclude" file and run tar with the X option.

This component is licensed under Section A.9, "GNU Lesser General Public License Version 2.1, February 199

### A.19 Linux-PAM License

The following software may be included in this product:

```
Linux-PAM (pam-devel, Pluggable authentication modules for Linux)

Copyright Theodore Ts'o, 1996. All rights reserved.

(For the avoidance of doubt, Oracle uses and distributes this component under the terms below and elects not to do so under
```

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

the GPL even though the GPL is referenced as an option below.)

- Redistributions of source code must retain the above copyright notice, and the entire permission notice in its entirety, including the disclaimer of warranties.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The name of the author may not be used to endorse or promote

products derived from this software without specific prior written permission.

ALTERNATIVELY, this product may be distributed under the terms of the GNU Public License, in which case the provisions of the GPL are required INSTEAD OF the above restrictions. (This clause is necessary due to a potential bad interaction between the GPL and the restrictions contained in a BSD-style copyright.)

THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## A.20 LPeg Library License

The following software may be included in this product:

LPeg

Use of any of this software is governed by the terms of the license below:

Copyright © 2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## A.21 Lua (liblua) License

The following software may be included in this product:

Lua (liblua)

Copyright © 1994-2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject

to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## A.22 LuaFileSystem Library License

The following software may be included in this product:

LuaFileSystem

Copyright © 2003 Kepler Project.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## A.23 md5 (Message-Digest Algorithm 5) License

The following software may be included in this product:

md5 (Message-Digest Algorithm 5)

This code implements the MD5 message-digest algorithm. The algorithm is due to Ron Rivest. This code was written by Colin Plumb in 1993, no copyright is claimed. This code is in the public domain; do with it what you wish.

Equivalent code is available from RSA Data Security, Inc. This code has been tested against that, and is equivalent, except that you don't need to include two pages of legalese with every copy.

The code has been modified by Mikael Ronstroem to handle calculating a hash value of a key that is always a multiple of 4 bytes long. Word 0 of the calculated 4-word hash value is returned as the hash value.

## A.24 memcached License

The following software may be included in this product:

#### memcached

Copyright (c) 2003, Danga Interactive, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of the Danga Interactive nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## A.25 nt\_servc (Windows NT Service class library) License

The following software may be included in this product:

nt servc (Windows NT Service class library)

```
Windows NT Service class library
Copyright Abandoned 1998 Irena Pancirov - Irnet Snc
This file is public domain and comes with NO WARRANTY of any kind
```

## A.26 OpenPAM License

The following software may be included in this product:

#### OpenPAM

```
Copyright (c) 2002-2003 Networks Associates Technology, Inc. Copyright (c) 2004-2007 Dag-Erling Smørgrav All rights reserved.
```

This software was developed for the FreeBSD Project by ThinkSec AS and Network Associates Laboratories, the Security Research Division of Network Associates, Inc. under DARPA/SPAWAR contract N66001-01-C-8035 ("CBOSS"), as part of the DARPA CHATS research program.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING,
BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY
AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN
NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR
CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)
ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN
IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

### A.27 Paramiko License

The following software may be included in this product:

Paramiko

You are receiving a copy of Paramiko in both source and object code. The terms of the Oracle license do NOT apply to the Paramiko program; it is licensed under the following license, separately from the Oracle programs you receive. If you do not wish to install this program, you may delete the Paramiko folder and all its contents.

This component is licensed under Section A.9, "GNU Lesser General Public License Version 2.1, February 1999".

#### A.28 PCRE License

The following software may be included in this product:

PCRE (Perl Compatible Regular Expressions) Library

PCRE LICENCE

PCRE is a library of functions to support regular expressions whose syntax and semantics are as close as possible to those of the Perl 5 language.

Release 7 of PCRE is distributed under the terms of the "BSD" licence, as specified below. The documentation for PCRE, supplied in the "doc" directory, is distributed under the same

```
terms as the software itself.
The basic library functions are written in C and are
freestanding. Also included in the distribution is a set
of C++ wrapper functions.
THE BASIC LIBRARY FUNCTIONS
Written by: Philip Hazel
Email local part: ph10
Email domain:
                 cam.ac.uk
University of Cambridge Computing Service,
Cambridge, England. Phone: +44 1223 334714.
Copyright (c) 1997-2006 University of Cambridge
All rights reserved.
THE C++ WRAPPER FUNCTIONS
Contributed by: Google Inc.
Copyright (c) 2006, Google Inc.
All rights reserved.
THE "BSD" LICENCE
Redistribution and use in source and binary forms,
with or without modification, are permitted provided
that the following conditions are met:
* Redistributions of source code must retain the above
 copyright notice, this list of conditions and the
 following disclaimer.
 Redistributions in binary form must reproduce the
  above copyright notice, this list of conditions and
  the following disclaimer in the documentation and/or
 other materials provided with the distribution.
 Neither the name of the University of Cambridge nor
  the name of Google Inc. nor the names of their contributors
  may be used to endorse or promote products derived from
  this software without specific prior written permission.
THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND
CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES,
INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF
MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE
DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS
BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY,
OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT
OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS;
OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

## A.29 Percona Multiple I/O Threads Patch License

The following software may be included in this product:

Percona Multiple I/O threads patch

Copyright (c) 2008, 2009 Percona Inc All rights reserved.

Redistribution and use of this software in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- \* Neither the name of Percona Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission of Percona Inc.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS
FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE
COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING,
BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER
CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT
LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN
ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE
POSSIBILITY OF SUCH DAMAGE.

## A.30 RegEX-Spencer Library License

The following software may be included in this product: Henry Spencer's Regular-Expression Library (RegEX-Spencer)

Copyright 1992, 1993, 1994 Henry Spencer. All rights reserved. This software is not subject to any license of the American Telephone and Telegraph Company or of the Regents of the University of California.

Permission is granted to anyone to use this software for any purpose on any computer system, and to alter it and redistribute it, subject to the following restrictions:

- 1. The author is not responsible for the consequences of use of this software, no matter how awful, even if they arise from flaws in it.
- The origin of this software must not be misrepresented, either by explicit claim or by omission. Since few users ever read sources, credits must appear in the documentation.
- 3. Altered versions must be plainly marked as such, and must not be misrepresented as being the original software. Since few users ever read sources, credits must appear in the documentation.
- 4. This notice may not be removed or altered.

## A.31 RFC 3174 - US Secure Hash Algorithm 1 (SHA1) License

The following software may be included in this product:

RFC 3174 - US Secure Hash Algorithm 1 (SHA1)

RFC 3174 - US Secure Hash Algorithm 1 (SHA1)

Copyright (C) The Internet Society (2001). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.

## A.32 Richard A. O'Keefe String Library License

The following software may be included in this product:

Richard A. O'Keefe String Library

The Richard O'Keefe String Library is subject to the following notice:

These files are in the public domain. This includes getopt.c, which is the work of Henry Spencer, University of Toronto Zoology, who says of it "None of this software is derived from Bell software. I had no access to the source for Bell's versions at the time I wrote it. This software is hereby explicitly placed in the public domain. It may be used for any purpose on any machine by anyone." I would greatly prefer it if \*my\* material received no military use.

The t\_ctype.h file is subject to the following notice:

Copyright (C) 1998, 1999 by Pruet Boonma, all rights reserved. Copyright (C) 1998 by Theppitak Karoonboonyanan, all rights reserved.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies.

Smaphan Raruenrom and Pruet Boonma makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

### A.33 SHA-1 in C License

The following software may be included in this product:

#### SHA-1 in C

```
SHA-1 in C
By Steve Reid <steve@edmweb.com>
100% Public Domain
```

### A.34 zlib License

The following software may be included in this product:

zlib

Oracle gratefully acknowledges the contributions of Jean-loup Gailly and Mark Adler in creating the zlib general purpose compression library which is used in this product.

```
zlib.h -- interface of the 'zlib' general purpose compression library
Copyright (C) 1995-2004 Jean-loup Gailly and Mark Adler
zlib.h -- interface of the 'zlib' general purpose compression library
version 1.2.3, July 18th, 2005
Copyright (C) 1995-2005 Jean-loup Gailly and Mark Adler
zlib.h -- interface of the 'zlib' general purpose compression library
version 1.2.5, April 19th, 2010
Copyright (C) 1995-2010 Jean-loup Gailly and Mark Adler
This software is provided 'as-is', without any express or implied warranty.
In no event will the authors be held liable for any damages arising from the
use of this software. Permission is granted to anyone to use this software
for any purpose, including commercial applications, and to alter it and
redistribute it freely, subject to the following restrictions:
1. The origin of this software must not be misrepresented; you must not
   claim that you wrote the original software. If you use this software
   in a product, an acknowledgment in the product documentation would
   be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not
  be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.
Jean-loup Gailly jloup@gzip.org
Mark Adler madler@alumni.caltech.edu
```

550

## Appendix B MySQL 5.1 FAQ: MySQL Cluster

In the following section, we answer questions that are frequently asked about MySQL Cluster and the NDBCLUSTER storage engine.

#### Questions

- B.1: [552] Which versions of the MySQL software support Cluster? Do I have to compile from source?
- B.2: [553] What happened to MySQL Cluster NDB 6.4?
- B.3: [553] What do "NDB" and "NDBCLUSTER" mean?
- B.4: [553] What is the difference between using MySQL Cluster vs using MySQL Replication?
- B.5: [554] Do I need any special networking to run MySQL Cluster? How do computers in a cluster communicate?
- B.6: [554] How many computers do I need to run a MySQL Cluster, and why?
- B.7: [554] What do the different computers do in a MySQL Cluster?
- B.8: [555] When I run the SHOW command in the MySQL Cluster management client, I see a line of output that looks like this:

```
id=2 @10.100.10.32 (Version: 5.6.20-ndb-7.3.7 Nodegroup: 0, *)
```

What does the \* mean? How is this node different from the others?

- B.9: [555] With which operating systems can I use MySQL Cluster?
- B.10: [555] What are the hardware requirements for running MySQL Cluster?
- B.11: [556] How much RAM do I need to use MySQL Cluster? Is it possible to use disk memory at all?
- B.12: [557] What file systems can I use with MySQL Cluster? What about network file systems or network shares?
- B.13: [557] Can I run MySQL Cluster nodes inside virtual machines (such as those created by VMWare, Parallels, or Xen)?
- B.14: [557] I am trying to populate a MySQL Cluster database. The loading process terminates prematurely and I get an error message like this one: ERROR 1114: The table 'my\_cluster\_table' is full Why is this happening?
- B.15: [557] MySQL Cluster uses TCP/IP. Does this mean that I can run it over the Internet, with one or more nodes in remote locations?
- B.16: [558] Do I have to learn a new programming or query language to use MySQL Cluster?
- B.17: [558] What programming languages and APIs are supported by MySQL Cluster?
- B.18: [558] Does MySQL Cluster include any management tools?
- B.19: [559] How do I find out what an error or warning message means when using MySQL Cluster?
- B.20: [559] Is MySQL Cluster transaction-safe? What isolation levels are supported?

- B.21: [559] What storage engines are supported by MySQL Cluster?
- B.22: [559] In the event of a catastrophic failure—say, for instance, the whole city loses power *and* my UPS fails—would I lose all my data?
- B.23: [559] Is it possible to use FULLTEXT indexes with MySQL Cluster?
- B.24: [559] Can I run multiple nodes on a single computer?
- B.25: [560] Can I add data nodes to a MySQL Cluster without restarting it?
- B.26: [560] Are there any limitations that I should be aware of when using MySQL Cluster?
- B.27: [561] Does MySQL Cluster support foreign keys?
- B.28: [561] How do I import an existing MySQL database into a MySQL Cluster?
- B.29: [561] How do MySQL Cluster nodes communicate with one another?
- B.30: [561] What is an arbitrator?
- B.31: [561] What data types are supported by MySQL Cluster?
- B.32: [562] How do I start and stop MySQL Cluster?
- B.33: [562] What happens to MySQL Cluster data when the MySQL Cluster is shut down?
- B.34: [563] Is it a good idea to have more than one management node for a MySQL Cluster?
- B.35: [563] Can I mix different kinds of hardware and operating systems in one MySQL Cluster?
- B.36: [563] Can I run two data nodes on a single host? Two SQL nodes?
- B.37: [563] Can I use host names with MySQL Cluster?
- B.38: [563] Does MySQL Cluster support IPv6?
- B.39: [563] How do I handle MySQL users in a MySQL Cluster having multiple MySQL servers?
- B.40: [564] How do I continue to send queries in the event that one of the SQL nodes fails?
- B.41: [564] How do I back up and restore a MySQL Cluster?
- B.42: [564] What is an "angel process"?

#### **Questions and Answers**

#### B.1: Which versions of the MySQL software support Cluster? Do I have to compile from source?

MySQL Cluster is not supported in standard MySQL Server 5.1 releases. Instead, MySQL Cluster is provided as a separate product. Currently, the following MySQL Cluster release series are available for production use:

- MySQL Cluster NDB 6.3. This series is still maintained and available for use but is not recommended
  for new deployments. The most recent MySQL Cluster NDB 6.3 release can be obtained from <a href="http://dev.mysql.com/downloads/cluster/">http://dev.mysql.com/downloads/cluster/</a>.
- MySQL Cluster NDB 7.0. This series is still available for use in production, although MySQL Cluster NDB 7.2 is recommended for new deployments. The most recent MySQL Cluster NDB 7.0 release can be obtained from http://dev.mysql.com/downloads/cluster/.

- MySQL Cluster NDB 7.1. This series is a previous General Availability (GA) version of MySQL
  Cluster, still available for production, although we recommend that new deployments use MySQL Cluster
  NDB 7.3. The most recent MySQL Cluster NDB 7.1 release can be obtained from http://dev.mysql.com/
  downloads/cluster/.
- MySQL Cluster NDB 7.2. This series is a General Availability (GA) version of MySQL Cluster, still available for production, although we recommend that new deployments use the latest MySQL Cluster NDB 7.3 release. The most recent MySQL Cluster NDB 7.2 release can be obtained from http://dev.mysql.com/downloads/cluster/.
- MySQL Cluster NDB 7.3. This series is the latest Generally Available (GA) version of MySQL Cluster, based on version 7.3 of the NDB storage engine and MySQL Server 5.6. New deployments should use the latest release in this series. The most recent MySQL Cluster NDB 7.3 release can be obtained from http://dev.mysql.com/downloads/cluster/.

You should use MySQL Cluster NDB 7.2 or MySQL Cluster NDB 7.3 for any new deployments; if you are using an older version of MySQL Cluster, you should upgrade to one of these soon as possible. For an overview of improvements made in MySQL Cluster NDB 7.2, see MySQL Cluster Development in MySQL Cluster NDB 7.2; for information about improvements made in MySQL Cluster NDB 7.3, see MySQL Cluster Development in MySQL Cluster NDB 7.3.

You can determine whether your MySQL Server has NDB support using one of the statements SHOW VARIABLES LIKE 'have\_%', SHOW ENGINES, or SHOW PLUGINS.

#### **B.2: What happened to MySQL Cluster NDB 6.4?**

Because of the number and impact of new features introduced into MySQL Cluster following the General Availability of MySQL Cluster NDB 6.3, it was decided that the following release series represented a "major" new release series rather than a "minor" one, and should be known as MySQL Cluster 7.0.

The earliest development versions of MySQL Cluster NDB 7.0 were originally designated "MySQL Cluster 6.4", and the first four releases in this series were identified as MySQL Cluster NDB 6.4.0 through NDB 6.4.3. MySQL Cluster NDB 7.0.4 was the fifth MySQL Cluster NDB 7.0 release; it was the successor to MySQL Cluster NDB 6.4.3.

For more information about MySQL Cluster NDB 7.0, see Section 3.4.3, "MySQL Cluster Development in MySQL Cluster NDB 7.0", and http://dev.mysql.com/doc/relnotes/mysql-cluster/7.1/en/mysql-cluster-news-7-0.html.

#### B.3: What do "NDB" and "NDBCLUSTER" mean?

"NDB" stands for "Network Database". NDB and NDBCLUSTER are both names for the storage engine that enables clustering support in MySQL. While our developers prefer NDB, either name is correct; both names appear in our documentation, and either name can be used in the ENGINE option of a CREATE TABLE statement for creating a MySQL Cluster table.

#### B.4: What is the difference between using MySQL Cluster vs using MySQL Replication?

In traditional MySQL replication, a master MySQL server updates one or more slaves. Transactions are committed sequentially, and a slow transaction can cause the slave to lag behind the master. This means that if the master fails, it is possible that the slave might not have recorded the last few transactions. If a transaction-safe engine such as InnoDB is being used, a transaction will either be complete on the slave or not applied at all, but replication does not guarantee that all data on the master and the slave will be consistent at all times. In MySQL Cluster, all data nodes are kept in synchrony, and a transaction committed by any one data node is committed for all data nodes. In the event of a data node failure, all remaining data nodes remain in a consistent state.

In short, whereas standard MySQL replication is asynchronous, MySQL Cluster is synchronous.

Asynchronous replication for MySQL Cluster is available in MySQL 5.1 and later. <u>MySQL Cluster Replication</u> (also sometimes known as "geo-replication") includes the capability to replicate both between two MySQL Clusters, and from a MySQL Cluster to a non-Cluster MySQL server. See Chapter 8, <u>MySQL Cluster Replication</u>.

## B.5: Do I need any special networking to run MySQL Cluster? How do computers in a cluster communicate?

MySQL Cluster is intended to be used in a high-bandwidth environment, with computers connecting using TCP/IP. Its performance depends directly upon the connection speed between the cluster's computers. The minimum connectivity requirements for MySQL Cluster include a typical 100-megabit Ethernet network or the equivalent. We recommend you use gigabit Ethernet whenever available.

The faster SCI protocol is also supported, but requires special hardware. See Section 5.5, "Using High-Speed Interconnects with MySQL Cluster", for more information about SCI.

#### B.6: How many computers do I need to run a MySQL Cluster, and why?

A minimum of three computers is required to run a viable cluster. However, the minimum *recommended* number of computers in a MySQL Cluster is four: one each to run the management and SQL nodes, and two computers to serve as data nodes. The purpose of the two data nodes is to provide redundancy; the management node must run on a separate machine to guarantee continued arbitration services in the event that one of the data nodes fails.

To provide increased throughput and high availability, you should use multiple SQL nodes (MySQL Servers connected to the cluster). It is also possible (although not strictly necessary) to run multiple management servers.

#### B.7: What do the different computers do in a MySQL Cluster?

A MySQL Cluster has both a physical and logical organization, with computers being the physical elements. The logical or functional elements of a cluster are referred to as <u>nodes</u>, and a computer housing a cluster node is sometimes referred to as a <u>cluster host</u>. There are three types of nodes, each corresponding to a specific role within the cluster. These are:

- Management node. This node provides management services for the cluster as a whole, including startup, shutdown, backups, and configuration data for the other nodes. The management node server is implemented as the application <a href="mailto:ndb\_mgmd">ndb\_mgmd</a>; the management client used to control MySQL Cluster is <a href="mailto:ndb\_mgm">ndb\_mgm</a>. See Section 6.4, "ndb\_mgmd The MySQL Cluster Management Server Daemon", and Section 6.5, "ndb\_mgm The MySQL Cluster Management Client", for information about these programs.
- **Data node.** This type of node stores and replicates data. Data node functionality is handled by instances of the NDB data node process ndbd. For more information, see Section 6.1, "ndbd The MySQL Cluster Data Node Daemon".
- SQL node. This is simply an instance of MySQL Server (mysqld) that is built with support for the NDBCLUSTER storage engine and started with the --ndb-cluster option to enable the engine and the --ndb-connectstring option to enable it to connect to a MySQL Cluster management server. For more about these options, see Section 5.4.2, "MySQL Server Options for MySQL Cluster".

#### Note

An <u>API node</u> is any application that makes direct use of Cluster data nodes for data storage and retrieval. An SQL node can thus be considered a type of API

node that uses a MySQL Server to provide an SQL interface to the Cluster. You can write such applications (that do not depend on a MySQL Server) using the NDB API, which supplies a direct, object-oriented transaction and scanning interface to MySQL Cluster data; see MySQL Cluster API Overview: The NDB API, for more information.

## B.8: When I run the SHOW command in the MySQL Cluster management client, I see a line of output that looks like this:

```
id=2 @10.100.10.32 (Version: 5.6.20-ndb-7.3.7 Nodegroup: 0, *)
```

#### What does the \* mean? How is this node different from the others?

The simplest answer is, "It's not something you can control, and it's nothing that you need to worry about in any case, unless you're a software engineer writing or analyzing the MySQL Cluster source code".

If you don't find that answer satisfactory, here's a longer and more technical version:

A number of mechanisms in MySQL Cluster require distributed coordination among the data nodes. These distributed algorithms and protocols include global checkpointing, DDL (schema) changes, and node restart handling. To make this coordination simpler, the data nodes "elect" one of their number to act as leader. (This node was once referred to as a "master", but this terminology was dropped to avoid confusion with master server in MySQL Replication.) There is no user-facing mechanism for influencing this selection, which is completely automatic; the fact that it *is* automatic is a key part of MySQL Cluster's internal architecture.

When a node acts as the "leader" for any of these mechanisms, it is usually the point of coordination for the activity, and the other nodes act as "followers", carrying out their parts of the activity as directed by the leader. If the node acting as leader fails, then the remaining nodes elect a new leader. Tasks in progress that were being coordinated by the old leader may either fail or be continued by the new leader, depending on the actual mechanism involved.

It is possible for some of these different mechanisms and protocols to have different leader nodes, but in general the same leader is chosen for all of them. The node indicated as the leader in the output of SHOW in the management client is known internally as the DICT manager (see The DBDICT Block, in the MySQL Cluster API Developer Guide, for more information), responsible for coordinating DDL and metadata activity.

MySQL Cluster is designed in such a way that the choice of leader has no discernable effect outside the cluster itself. For example, the current leader does not have significantly higher CPU or resource usage than the other data nodes, and failure of the leader should not have a significantly different impact on the cluster than the failure of any other data node.

#### B.9: With which operating systems can I use MySQL Cluster?

MySQL Cluster is supported on most Unix-like operating systems. Beginning with MySQL Cluster NDB 7.1.3, MySQL Cluster is also supported in production on Microsoft Windows operating systems.

For more detailed information concerning the level of support which is offered for MySQL Cluster on various operating system versions, operating system distributions, and hardware platforms, please refer to http://www.mysql.com/support/supportedplatforms/cluster.html.

#### B.10: What are the hardware requirements for running MySQL Cluster?

MySQL Cluster should run on any platform for which NDB-enabled binaries are available. For data nodes and API nodes, faster CPUs and more memory are likely to improve performance, and 64-bit CPUs are likely to be more effective than 32-bit processors. There must be sufficient memory on machines used

for data nodes to hold each node's share of the database (see *How much RAM do I Need?* for more information). For a computer which is used only for running the MySQL Cluster management server, the requirements are minimal; a common desktop PC (or the equivalent) is generally sufficient for this task. Nodes can communicate through the standard TCP/IP network and hardware. They can also use the high-speed SCI protocol; however, special networking hardware and software are required to use SCI (see Section 5.5, "Using High-Speed Interconnects with MySQL Cluster").

#### B.11: How much RAM do I need to use MySQL Cluster? Is it possible to use disk memory at all?

Formerly MySQL Cluster was in-memory only. MySQL 5.1 and later also provide the ability to store MySQL Cluster on disk. (Note that we have no plans to backport this capability to previous releases.) See Section 7.12, "MySQL Cluster Disk Data Tables", for more information.

For in-memory NDB tables, you can use the following formula for obtaining a rough estimate of how much RAM is needed for each data node in the cluster:

```
(SizeofDatabase × NumberOfReplicas × 1.1 ) / NumberOfDataNodes
```

To calculate the memory requirements more exactly requires determining, for each table in the cluster database, the storage space required per row (see Data Type Storage Requirements, for details), and multiplying this by the number of rows. You must also remember to account for any column indexes as follows:

- Each primary key or hash index created for an NDBCLUSTER table requires 21–25 bytes per record. These indexes use IndexMemory.
- Each ordered index requires 10 bytes storage per record, using DataMemory.
- Creating a primary key or unique index also creates an ordered index, unless this index is created with USING HASH. In other words:
  - A primary key or unique index on a Cluster table normally takes up 31 to 35 bytes per record.
  - However, if the primary key or unique index is created with USING HASH, then it requires only 21 to 25 bytes per record.

Note that creating MySQL Cluster tables with USING HASH for all primary keys and unique indexes will generally cause table updates to run more quickly—in some cases by a much as 20 to 30 percent faster than updates on tables where USING HASH was not used in creating primary and unique keys. This is due to the fact that less memory is required (because no ordered indexes are created), and that less CPU must be utilized (because fewer indexes must be read and possibly updated). However, it also means that queries that could otherwise use range scans must be satisfied by other means, which can result in slower selects.

When calculating Cluster memory requirements, you may find useful the ndb\_size.pl utility which is available in recent MySQL 5.1 releases. This Perl script connects to a current (non-Cluster) MySQL database and creates a report on how much space that database would require if it used the NDBCLUSTER storage engine. For more information, see Section 6.23, "ndb\_size.pl — NDBCLUSTER Size Requirement Estimator".

It is especially important to keep in mind that *every MySQL Cluster table must have a primary key*. The NDB storage engine creates a primary key automatically if none is defined; this primary key is created without USING HASH.

You can determine how much memory is being used for storage of MySQL Cluster data and indexes at any given time using the REPORT MEMORYUSAGE command in the ndb mgm client; see Section 7.2.

"Commands in the MySQL Cluster Management Client", for more information. In addition, warnings are written to the cluster log when 80% of available DataMemory or IndexMemory is in use, and again when usage reaches 85%, 90%, and so on.

## B.12: What file systems can I use with MySQL Cluster? What about network file systems or network shares?

Generally, any file system that is native to the host operating system should work well with MySQL Cluster. If you find that a given file system works particularly well (or not so especially well) with MySQL Cluster, we invite you to discuss your findings in the MySQL Cluster Forums.

For Windows, we recommend that you use NTFS file systems for MySQL Cluster, just as we do for standard MySQL. We do not test MySQL Cluster with FAT or VFAT file systems. Because of this, we do not recommend their use with MySQL or MySQL Cluster.

MySQL Cluster is implemented as a shared-nothing solution; the idea behind this is that the failure of a single piece of hardware should not cause the failure of multiple cluster nodes, or possibly even the failure of the cluster as a whole. For this reason, the use of network shares or network file systems is not supported for MySQL Cluster. This also applies to shared storage devices such as SANs.

## B.13: Can I run MySQL Cluster nodes inside virtual machines (such as those created by VMWare, Parallels, or Xen)?

This is possible but not recommended for a production environment with MySQL Cluster versions prior to MySQL Cluster NDB 7.2.

For deployment in virtualized environments, you should use MySQL Cluster NDB 7.2 or later.

# B.14: I am trying to populate a MySQL Cluster database. The loading process terminates prematurely and I get an error message like this one: ERROR 1114: The table 'my\_cluster\_table' is full Why is this happening?

The cause is very likely to be that your setup does not provide sufficient RAM for all table data and all indexes, including the primary key required by the NDB storage engine and automatically created in the event that the table definition does not include the definition of a primary key.

It is also worth noting that all data nodes should have the same amount of RAM, since no data node in a cluster can use more memory than the least amount available to any individual data node. For example, if there are four computers hosting Cluster data nodes, and three of these have 3GB of RAM available to store Cluster data while the remaining data node has only 1GB RAM, then each data node can devote at most 1GB to MySQL Cluster data and indexes.

In some cases it is possible to get Table is full errors in MySQL client applications even when ndb\_mgm -e "ALL REPORT MEMORYUSAGE" shows significant free DataMemory. You can force NDB to create extra partitions for MySQL Cluster tables and thus have more memory available for hash indexes by using the MAX\_ROWS option for CREATE TABLE. In general, setting MAX\_ROWS to twice the number of rows that you expect to store in the table should be sufficient.

For similar reasons, you can also sometimes encounter problems with data node restarts on nodes that are heavily loaded with data. In MySQL Cluster NDB 7.1 and later, the addition of the MinFreePct [122] parameter helps with this issue by reserving a portion (5% by default) of DataMemory and IndexMemory for use in restarts. This reserved memory is not available for storing NDB tables or data.

## B.15: MySQL Cluster uses TCP/IP. Does this mean that I can run it over the Internet, with one or more nodes in remote locations?

It is *very* unlikely that a cluster would perform reliably under such conditions, as MySQL Cluster was designed and implemented with the assumption that it would be run under conditions guaranteeing dedicated high-speed connectivity such as that found in a LAN setting using 100 Mbps or gigabit Ethernet —preferably the latter. We neither test nor warrant its performance using anything slower than this.

Also, it is extremely important to keep in mind that communications between the nodes in a MySQL Cluster are not secure; they are neither encrypted nor safeguarded by any other protective mechanism. The most secure configuration for a cluster is in a private network behind a firewall, with no direct access to any Cluster data or management nodes from outside. (For SQL nodes, you should take the same precautions as you would with any other instance of the MySQL server.) For more information, see Section 7.11, "MySQL Cluster Security Issues".

#### B.16: Do I have to learn a new programming or query language to use MySQL Cluster?

No. Although some specialized commands are used to manage and configure the cluster itself, only standard (My)SQL statements are required for the following operations:

- · Creating, altering, and dropping tables
- · Inserting, updating, and deleting table data
- · Creating, changing, and dropping primary and unique indexes

Some specialized configuration parameters and files are required to set up a MySQL Cluster—see Section 5.2, "MySQL Cluster Configuration Files", for information about these.

A few simple commands are used in the MySQL Cluster management client (ndb\_mgm) for tasks such as starting and stopping cluster nodes. See Section 7.2, "Commands in the MySQL Cluster Management Client".

#### B.17: What programming languages and APIs are supported by MySQL Cluster?

MySQL Cluster 5.1 and later support the same programming APIs and languages as the standard MySQL Server, including ODBC, .Net, the MySQL C API, and numerous drivers for popular scripting languages such as PHP, Perl, and Python. MySQL Cluster applications written using these APIs behave similarly to other MySQL applications; they transmit SQL statements to a MySQL Server (in the case of MySQL Cluster, an SQL node), and receive responses containing rows of data. For more information about these APIs, see Connectors and APIs.

MySQL Cluster 5.1 and later also support application programming using the NDB API, which provides a low-level C++ interface to MySQL Cluster data without needing to go through a MySQL Server. See The NDB API. In addition, many NDBCLUSTER management functions are exposed by the C-language MGM API; see The MGM API, for more information.

MySQL Cluster NDB 7.1 and later also support Java application programming using ClusterJ, which supports a domain object model of data using sessions and transactions. See Java and MySQL Cluster, for more information.

#### **B.18: Does MySQL Cluster include any management tools?**

MySQL Cluster includes a command line client for performing basic management functions. See Section 6.5, "ndb\_mgm — The MySQL Cluster Management Client", and Section 7.2, "Commands in the MySQL Cluster Management Client".

MySQL Cluster NDB 7.0 and later is also supported by MySQL Cluster Manager, a separate product providing an advanced command line interface that can automate many MySQL Cluster management

tasks such as rolling restarts and configuration changes. For more information about MySQL Cluster Manager, see MySQL™ Cluster Manager 1.3.2 User Manual.

#### B.19: How do I find out what an error or warning message means when using MySQL Cluster?

There are two ways in which this can be done:

- From within the <code>mysql</code> client, use <code>SHOW ERRORS</code> or <code>SHOW WARNINGS</code> immediately upon being notified of the error or warning condition.
- From a system shell prompt, use perror --ndb error\_code.

#### B.20: Is MySQL Cluster transaction-safe? What isolation levels are supported?

Yes. For tables created with the NDB storage engine, transactions are supported. Currently, MySQL Cluster supports only the READ COMMITTED transaction isolation level.

#### B.21: What storage engines are supported by MySQL Cluster?

Clustering with MySQL is supported only by the NDB storage engine. That is, in order for a table to be shared between nodes in a MySQL Cluster, the table must be created using ENGINE=NDB (or the equivalent option ENGINE=NDBCLUSTER).

It is possible to create tables using other storage engines (such as InnoDB or MyISAM) on a MySQL server being used with a MySQL Cluster, but since these tables do not use NDB, they do not participate in clustering; each such table is strictly local to the individual MySQL server instance on which it is created.

## B.22: In the event of a catastrophic failure—say, for instance, the whole city loses power and my UPS fails—would I lose all my data?

All committed transactions are logged. Therefore, although it is possible that some data could be lost in the event of a catastrophe, this should be quite limited. Data loss can be further reduced by minimizing the number of operations per transaction. (It is not a good idea to perform large numbers of operations per transaction in any case.)

#### **B.23:** Is it possible to use **FULLTEXT** indexes with MySQL Cluster?

FULLTEXT indexing is currently supported only by the MyISAM storage engine. See Full-Text Search Functions, for more information.

#### B.24: Can I run multiple nodes on a single computer?

It is possible but not always advisable. One of the chief reasons to run a cluster is to provide redundancy. To obtain the full benefits of this redundancy, each node should reside on a separate machine. If you place multiple nodes on a single machine and that machine fails, you lose all of those nodes. For this reason, if you do run multiple data nodes on a single machine, it is *extremely* important that they be set up in such a way that the failure of this machine does not cause the loss of all the data nodes in a given node group.

Given that MySQL Cluster can be run on commodity hardware loaded with a low-cost (or even no-cost) operating system, the expense of an extra machine or two is well worth it to safeguard mission-critical data. It also worth noting that the requirements for a cluster host running a management node are minimal. This task can be accomplished with a 300 MHz Pentium or equivalent CPU and sufficient RAM for the operating system, plus a small amount of overhead for the ndb mgmd and ndb mgm processes.

It is acceptable to run multiple cluster data nodes on a single host that has multiple CPUs, cores, or both. MySQL Cluster NDB 7.0 and later also provide a multi-threaded version of the data node binary intended for use on such systems. For more information, see Section 6.3, "ndbmtd — The MySQL Cluster Data Node Daemon (Multi-Threaded)".

It is also possible in some cases to run data nodes and SQL nodes concurrently on the same machine; how well such an arrangement performs is dependent on a number of factors such as number of cores and CPUs as well as the amount of disk and memory available to the data node and SQL node processes, and you must take these factors into account when planning such a configuration.

#### B.25: Can I add data nodes to a MySQL Cluster without restarting it?

In MySQL Cluster NDB 7.0 and later, it is possible to add new data nodes to a running MySQL Cluster without taking it offline. For more information, see Section 7.13, "Adding MySQL Cluster Data Nodes Online".

For other types of MySQL Cluster nodes, a rolling restart is all that is required (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").

(In MySQL Cluster NDB 6.3 and earlier releases, it was not possible to add new data nodes without shutting down and restarting the MySQL Cluster.)

#### B.26: Are there any limitations that I should be aware of when using MySQL Cluster?

Limitations on NDB tables in MySQL NDB 6.3, MySQL Cluster NDB 7.0, and MySQL Cluster NDB 7.1 include the following:

- Temporary tables are not supported; a CREATE TEMPORARY TABLE statement using ENGINE=NDB or ENGINE=NDBCLUSTER fails with an error.
- The only types of user-defined partitioning supported for NDBCLUSTER tables are KEY and LINEAR KEY. Trying to create an NDB table using any other partitioning type fails with an error.
- FULLTEXT indexes are not supported.
- Index prefixes are not supported. Only complete columns may be indexed.
- Spatial indexes are not supported (although spatial columns can be used). See Extensions for Spatial Data.
- Prior to MySQL Cluster NDB 6.3.19, the NDBCLUSTER storage engine did not support partial transactions or partial rollbacks of transactions. Beginning with MySQL Cluster NDB 6.3.19, this limitation has been removed, and the behavior of NDBCLUSTER is now in line with that of other transactional storage engines (such as InnoDB) that can roll back individual statements.
- Prior to MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, the maximum number of attributes allowed per table was 128; beginning with MySQL Cluster NDB 7.0.15 and MySQL Cluster NDB 7.1.4, this limit is increased to 512. Attribute names cannot be any longer than 31 characters. For each table, the maximum combined length of the table and database names is 122 characters.
- Previous to MySL Cluster NDB 7.0, the maximum size for a table row was 8 kilobytes, not counting BLOB values. MySQL Cluster NDB 7.0 and later support a maximum row length of 14 KB (also not including BLOB values).

There is no set limit for the number of rows per NDB table. Limits on table size depend on a number of factors, in particular on the amount of RAM available to each data node.

• The NDBCLUSTER engine does not support foreign key constraints. As with MyISAM tables, if these are specified in a CREATE TABLE or ALTER TABLE statement, they are ignored.

For a complete listing of limitations in MySQL Cluster, see Section 3.6, "Known Limitations of MySQL Cluster". See also Section 3.6.11, "Previous MySQL Cluster Issues Resolved in MySQL 5.1, MySQL Cluster NDB 6.x, and MySQL Cluster NDB 7.x".

#### **B.27: Does MySQL Cluster support foreign keys?**

MySQL Cluster NDB 7.1 and earlier MySQL Cluster releases do not support foreign key contraints, and ignore foreign keys in CREATE TABLE statements (similarly to how MyISAM treats foreign key syntax).

Foreign key support comparable to that found in the InnoDB storage engine is provided by NDB beginning with MySQL Cluster NDB 7.3. Applications requiring foreign support key should use MySQL Cluster NDB 7.3 or later.

#### B.28: How do I import an existing MySQL database into a MySQL Cluster?

You can import databases into MySQL Cluster much as you would with any other version of MySQL. Other than the limitations mentioned elsewhere in this FAQ, the only other special requirement is that any tables to be included in the cluster must use the NDB storage engine. This means that the tables must be created with ENGINE=NDB or ENGINE=NDBCLUSTER.

It is also possible to convert existing tables that use other storage engines to NDBCLUSTER using one or more ALTER TABLE statement. However, the definition of the table must be compatible with the NDBCLUSTER storage engine prior to making the conversion. In MySQL 5.1, an additional workaround is also required; see Section 3.6, "Known Limitations of MySQL Cluster", for details.

#### B.29: How do MySQL Cluster nodes communicate with one another?

Cluster nodes can communicate through any of three different transport mechanisms: TCP/IP, SHM (shared memory), and SCI (Scalable Coherent Interface). Where available, SHM is used by default between nodes residing on the same cluster host; however, this is considered experimental. SCI is a high-speed (1 gigabit per second and higher), high-availability protocol used in building scalable multi-processor systems; it requires special hardware and drivers. See Section 5.5, "Using High-Speed Interconnects with MySQL Cluster", for more about using SCI as a transport mechanism for MySQL Cluster.

#### B.30: What is an arbitrator?

If one or more data nodes in a cluster fail, it is possible that not all cluster data nodes will be able to "see" one another. In fact, it is possible that two sets of data nodes might become isolated from one another in a network partitioning, also known as a "split-brain" scenario. This type of situation is undesirable because each set of data nodes tries to behave as though it is the entire cluster. An arbitrator is required to decide between the competing sets of data nodes.

When all data nodes in at least one node group are alive, network partitioning is not an issue, because no single subset of the cluster can form a functional cluster on its own. The real problem arises when no single node group has all its nodes alive, in which case network partitioning (the "split-brain" scenario) becomes possible. Then an arbitrator is required. All cluster nodes recognize the same node as the arbitrator, which is normally the management server; however, it is possible to configure any of the MySQL Servers in the cluster to act as the arbitrator instead. The arbitrator accepts the first set of cluster nodes to contact it, and tells the remaining set to shut down. Arbitrator selection is controlled by the ArbitrationRank configuration parameter for MySQL Server and management server nodes. In MySQL Cluster NDB 7.0.7 and later, you can also use the ArbitrationRank configuration parameter to control the arbitrator selection process. For more information about these parameters, see Section 5.2.5, "Defining a MySQL Cluster Management Server".

The role of arbitrator does not in and of itself impose any heavy demands upon the host so designated, and thus the arbitrator host does not need to be particularly fast or to have extra memory especially for this purpose.

#### **B.31: What data types are supported by MySQL Cluster?**

MySQL Cluster supports all of the usual MySQL data types, including those associated with MySQL's spatial extensions; however, the NDB storage engine does not support spatial indexes. (Spatial indexes are supported only by MyISAM; see Extensions for Spatial Data, for more information.) In addition, there are some differences with regard to indexes when used with NDB tables.

#### Note

MySQL Cluster Disk Data tables (that is, tables created with TABLESPACE ... STORAGE DISK ENGINE=NDB or TABLESPACE ... STORAGE DISK ENGINE=NDBCLUSTER) have only fixed-width rows. This means that (for example) each Disk Data table record containing a VARCHAR (255) column requires space for 255 characters (as required for the character set and collation being used for the table), regardless of the actual number of characters stored therein.

See Section 3.6, "Known Limitations of MySQL Cluster", for more information about these issues.

#### B.32: How do I start and stop MySQL Cluster?

It is necessary to start each node in the cluster separately, in the following order:

1. Start the management node, using the ndb\_mgmd command.

You must include the -f or --config-file option to tell the management node where its configuration file can be found.

2. Start each data node with the ndbd command.

Each data node must be started with the -c or --ndb-connectstring option so that the data node knows how to connect to the management server.

3. Start each MySQL Server (SQL node) using your preferred startup script, such as mysqld\_safe.

Each MySQL Server must be started with the --ndbcluster and --ndb-connectstring options. These options cause mysqld to enable NDBCLUSTER storage engine support and how to connect to the management server.

Each of these commands must be run from a system shell on the machine housing the affected node. (You do not have to be physically present at the machine—a remote login shell can be used for this purpose.) You can verify that the cluster is running by starting the NDB management client ndb\_mgm on the machine housing the management node and issuing the SHOW or ALL STATUS command.

To shut down a running cluster, issue the command SHUTDOWN in the management client. Alternatively, you may enter the following command in a system shell:

```
shell> ndb_mgm -e "SHUTDOWN"
```

(The quotation marks in this example are optional, since there are no spaces in the command string following the -e option; in addition, the SHUTDOWN command, like other management client commands, is not case-sensitive.)

Either of these commands causes the ndb\_mgm, ndb\_mgm, and any ndbd processes to terminate gracefully. MySQL servers running as SQL nodes can be stopped using mysqladmin shutdown.

For more information, see Section 7.2, "Commands in the MySQL Cluster Management Client", and Section 4.6, "Safe Shutdown and Restart of MySQL Cluster".

B.33: What happens to MySQL Cluster data when the MySQL Cluster is shut down?

The data that was held in memory by the cluster's data nodes is written to disk, and is reloaded into memory the next time that the cluster is started.

#### B.34: Is it a good idea to have more than one management node for a MySQL Cluster?

It can be helpful as a fail-safe. Only one management node controls the cluster at any given time, but it is possible to configure one management node as primary, and one or more additional management nodes to take over in the event that the primary management node fails.

See Section 5.2, "MySQL Cluster Configuration Files", for information on how to configure MySQL Cluster management nodes.

#### B.35: Can I mix different kinds of hardware and operating systems in one MySQL Cluster?

Yes, as long as all machines and operating systems have the same "endianness" (all big-endian or all little-endian).

It is also possible to use software from different MySQL Cluster releases on different nodes. However, we support this only as part of a rolling upgrade procedure (see Section 7.5, "Performing a Rolling Restart of a MySQL Cluster").

#### B.36: Can I run two data nodes on a single host? Two SQL nodes?

Yes, it is possible to do this. In the case of multiple data nodes, it is advisable (but not required) for each node to use a different data directory. If you want to run multiple SQL nodes on one machine, each instance of mysqld must use a different TCP/IP port. However, in MySQL 5.1, running more than one cluster node of a given type per machine is generally not encouraged or supported for production use.

We also advise against running data nodes and SQL nodes together on the same host, since the ndbd and mysqld processes may compete for memory.

#### B.37: Can I use host names with MySQL Cluster?

Yes, it is possible to use DNS and DHCP for cluster hosts. However, if your application requires "five nines" availability, you should use fixed (numeric) IP addresses, since making communication between Cluster hosts dependent on services such as DNS and DHCP introduces additional potential points of failure.

#### **B.38: Does MySQL Cluster support IPv6?**

MySQL Cluster NDB 7.0 and later support IPv6 for connections between SQL nodes (MySQL servers). However, connections between all other types of nodes must use IPv4.

In practical terms, this means that you can use IPv6 for replication between MySQL Clusters, but connections between nodes in the same MySQL Cluster must use IPv4. For more information, see Section 8.3, "Known Issues in MySQL Cluster Replication".

#### B.39: How do I handle MySQL users in a MySQL Cluster having multiple MySQL servers?

MySQL user accounts and privileges are *not* automatically propagated between different MySQL servers accessing the same MySQL Cluster. Therefore, you must make sure that these are copied between the SQL nodes yourself. You can do this manually, or automate the task with scripts.

#### Warning

Do not attempt to work around this issue by converting the MySQL system tables to use the NDBCLUSTER storage engine. Only the MyISAM storage engine is supported for these tables.

#### B.40: How do I continue to send queries in the event that one of the SQL nodes fails?

MySQL Cluster does not provide any sort of automatic failover between SQL nodes. Your application must be prepared to handlethe loss of SQL nodes and to fail over between them.

#### B.41: How do I back up and restore a MySQL Cluster?

You can use the NDB native backup and restore functionality in the MySQL Cluster management client and the ndb\_restore program. See Section 7.3, "Online Backup of MySQL Cluster", and Section 6.19, "ndb\_restore — Restore a MySQL Cluster Backup".

You can also use the traditional functionality provided for this purpose in mysqldump and the MySQL server. See mysqldump — A Database Backup Program, for more information.

#### B.42: What is an "angel process"?

This process monitors and, if necessary, attempts to restart the data node process. If you check the list of active processes on your system after starting ndbd, you can see that there are actually 2 processes running by that name, as shown here (we omit the output from ndb\_mgmd and ndbd for brevity):

```
shell> ./ndb_mgmd
shell> ps aux | grep ndb
     23002 0.0 0.0 122948 3104 ? Ssl 14:14 0:00 ./ndb_mgmd
me
      23025 0.0 0.0 5284 820 pts/2 S+ 14:14 0:00 grep ndb
me
shell> ./ndbd -c 127.0.0.1 --initial
shell> ps aux | grep ndb
      23002 0.0 0.0 123080 3356 ?
                                       Ssl 14:14 0:00 ./ndb_mgmd
me
                                         Ss 14:14
Sl 14:14
       23096 0.0 0.0 35876 2036 ?
                                                    0:00 ./ndbd -c 127.0.0.1 --initial
me
                                                   0:00 ./ndbd -c 127.0.0.1 --initial
       23097 1.0 2.4 524116 91096 ?
       23168 0.0 0.0 5284 812 pts/2 R+ 14:15 0:00 grep ndb
```

The ndbd process showing 0 memory and CPU usage is the angel process. It actually does use a very small amount of each, of course. It simply checks to see if the main ndbd process (the primary data node process that actually handles the data) is running. If permitted to do so (for example, if the StopOnError configuration parameter is set to false—see Section 5.3.1, "MySQL Cluster Data Node Configuration Parameters"), the angel process tries to restart the primary data node process.