# **Boost.Synchro 0.3.3**

# Vicente J. Botet Escriba

Copyright © 2008 Vicente J. Botet Escriba

Distributed under the Boost Software License, Version 1.0. (See accompanying file LICENSE\_1\_0.txt or copy at http://www.boost.org/LICENSE\_1\_0.txt)

# **Table of Contents**

Overview	1
Introduction	3
Users'Guide	13
Getting Started	14
Tutorial	14
References	47
Glossary	47
Reference	48
Lockables	48
Generic Free Functions on Lockable	56
Generic Free Functions on Multiple Lockables	74
Condition Lockables	74
Lockers	75
Single-threaded	89
Multi-threaded	91
Multi-process	102
Polymorphic Locks	104
Other	106
High Level	107
Examples	108
Appendices	108
Appendix A: History	108
Appendix B: Rationale	109
Appendix C: Implementation Notes	109
Appendix D: Acknowledgements	110
Appendix E: Tests	110
Appendix F: Tickets	111
Appendix E: Future plans	111



# Warning

Synchro is not a part of the Boost libraries.

# **Overview**

# **Description**

To date, C++ multi threaded programs that need to be efficient use the same mutexes, semaphores, and events that Dijkstra described 40 years ago. This unfortunate state of affairs makes multi threaded programs difficult to design, debug, ensure correct, optimize, maintain, and analyze formally. Consequently, building tools that automate detection of race conditions and deadlocks is highly desirable.



I believe that most of the synchronization mechanisms applied to multi-threaded programs works as well for multi-process programs. This can not be done if the basic facilities mutexes and condition variables are not based on common concepts and take a different form depending of the library provider. We need to states these bases through concepts.

The main sources of inspiration of this library were

- the papers of Kevlin Henney about asynchronous C++ More C++ Threading From Procedural to Generic, by Example and its C++0x proposal [N1833 Preliminary Threading Library Proposal for TR2].
- the papers of Andrei Alexandrescu on multi-threading programming volatile Multithreaded Programmer's Best Friend
- the ACE framework of Douglas C. Schmidt An OO Encapsulation of Lightweight OS Concurrency Mechanisms in the ACE Toolkit.

This library is a compilation of what I have found in the literature not yet present in Boost. My main concen has been to boostify all these ideas in a coherent way.

#### Boost.Synchro provides:

- A uniform usage of Boost. Thread and Boost. Interprocess synchronization mechanisms based on lockables (mutexes) concepts and locker (guards) concepts.
  - · lockables traits and lock generators,
  - generic free functions on lockables as: lock, try\_lock, ...
  - · locker adapters of the Boost.Thread and Boost.Interprocess lockers models,
  - complete them with the corresponding models for single-threaded programms: null\_mutex and null\_condition classes,
  - · locking families,
  - ullet semaphore and binary\_semaphore,
  - condition\_lockable lock which put toghether a lock and its associated conditions.
- A coherent way exception based timed lock approach for functions and constructors,
- A rich palete of lockers as
  - strict\_locker, nested\_strict\_locker,
  - condition\_locker,
  - reverse\_locker, nested\_reverse\_locker,
  - locking\_ptr, on\_derreference\_locking\_ptr,
  - externally\_locked,
- array\_unique\_locker on multiple lockables.
- Generic free functions on multiple lockables lock, try\_lock, lock\_until, lock\_for, try\_lock\_until, try\_lock\_for, unlock \* lock adapters of the Boost.Thread and Boost.Interprocess lockable models,
  - lock\_until, lock\_for, try\_lock\_until, try\_lock\_for
- · A polymorphic lockable hierarchy.
- · High-level abstractions for handling more complicated synchronization problems, including
  - monitor for guaranteeing exclusive access to an object.



· Language-like Synchronized Block Macros

# **How to Use This Documentation**

This documentation makes use of the following naming and formatting conventions.

- · Code is in fixed width font and is syntax-highlighted.
- Replaceable text that you will need to supply is in *italics*.
- If a name refers to a free function, it is specified like this: free\_function(); that is, it is in code font and its name is followed by () to indicate that it is a free function.
- If a name refers to a class template, it is specified like this: class\_template<>; that is, it is in code font and its name is followed by <> to indicate that it is a class template.
- If a name refers to a function-like macro, it is specified like this: MACRO(); that is, it is uppercase in code font and its name is followed by () to indicate that it is a function-like macro. Object-like macros appear without the trailing ().
- Names that refer to *concepts* in the generic programming sense are specified in CamelCase.



#### **Note**

In addition, notes such as this one specify non-essential information that provides additional background or rationale.

Finally, you can mentally add the following to any code fragments in this document:

```
// Include all of Synchro files
#include <boost/synchro/synchro.hpp>

// Create a namespace aliases
namespace bsynchro = boost::synchro;
```

# Introduction

# Using Thread, Interprocess and Null synchronization mechanisms uniformly

One of the problems when doing multi threaded application with Boost.Thread and Boost.Interprocess is that the synchronization mechanism of these two libraries even if they are very close since the release 1.35, there are some minor differences that make quite difficult to design a class that can work independently with synchronization mechanisms of both libraries.

This library proposes some classes that allows to write code that can be used indistinguishably with thread or interprocess synchronization mechanisms. This section is inspired on the work from C++ Threading - A Generic-Programming Approach - Kevlin Henney.

#### Lock substitutability

The Boost (C++0x) mutexes have associated a category which form a sub-typing hierarchy:

```
ExclusiveLockable <- SharedLockable <- UpgradeLockable
```

```
struct exclusive_lock_tag {};
struct sharable_lock_tag : exclusive_lock_tag {};
struct upgradable_lock_tag : sharable_lock_tag {};
```

Locking behavior can be further categorized as:



· Re-entrancy: recursive or not

```
non_recursive <- recursive
```

· Scope: whether the lock is usable with a mono-threaded, multi-threaded or multi-process context

```
mono_threaded <- multi_threaded <- multi_process</pre>
```

• Lifetime: The lifetime of a lock could be associated to the process, the kernel or the file-system

```
process_lifetime <- kernel_lifetime <- filesystem_lifetime</pre>
```

• Timed interface: has or not a timed interfaces

```
hasnt_timed_interface <- has_timed_interface
```

Substitutability applies both to the degree of syntactic support and to the locking semantics

- A recursive mutex and binary semaphore are substitutable in code written against a exclusive mutex
- · A null mutex is substitutable for all others in a single-threaded environment

We can see these axes of variation expressed against some Boost synchronization mechanisms (from now bip stands for boost::interprocess):

- · boost::mutex: ExclusiveLock, non-recursive, has-not-timed-interface, multi-threaded
- boost::shared\_mutex: UpgradableLock, non-recursive, has-timed-interface, multi-threaded
- bip::synchro::null\_mutex: UpgradableLock, recursive, has-timed-interface, mono-threaded
- bip::synchro::interprocess\_recursive\_mutex ExclusiveLock, recursive, has-timed-interface, multi\_process.

#### Lock traits

The Boost.Synchro library contains a set of very specific traits classes, some of them encapsulate a single trait for a Lockable type; for example, is a lock recursive (is\_recursive), is useful in a multi threaded context (is\_multi\_threaded).

The Boost.Synchro lock-traits classes share a unified design that mimic the one of Boost.TypeTraits: each class inherits from a the type true\_type if the type has the specified property and inherits from false\_type otherwise.

Boost.Synchro also contains a set of classes that perform a specific transformation on a type; for example, they can remove a top-level const or volatile qualifier from a type. Each class that performs a transformation defines a single typedef-member type that is the result of the transformation.

#### Finding the best lock

Inverse traits can match a lockable type based on specific traits, for a given family of lock types.

It is also possible to specify characteristics to perform a reverse lookup to find a primitive lock type, either by exact match or by substitutable match.

#### Synchronization family

A class that will do internal locking can be parameterized by the type of synchronization family needed to achieve the desired level of concurrency control. This depends of the usage scope of this class, and this can be mono\_threaded, multi\_threaded, multi\_process.



For example the thread\_synchronization\_family can be used to instantiate a message\_queue class in a multi\_threaded environment, all public methods will be thread-safe, with the corresponding overhead that implies. In contrast, if a null\_synchronization\_policy class is used to instantiate message\_queue, all public methods will not be thread-safe, and there will be no additional overhead.

#### Syntactic lock traits

The Boost.Synchro library also contains classes that try to remove the syntactic differences between the synchronization mechanisms of the Boost.Thread and Boost::Interprocess libraries. The differences identified up to now are:

- The scoped locks live in a different namespace and some have different names with the same semantic. IMO these should be shared.
- The exception thrown lives in a different name space and different names with the same semantic.
- · This exception should be common.
- The move semantics (&&) are expressed with a class named differently. This class could be a good candidate of Boost library by itself.
- The scoped locks can be initialized with static const variables in order to overload the constructor for lock adoption, lock deferral or try to lock. Even if the name of these variables is the same, these variables live in different namespace. It would be nice if these both libraries use the same type and the same variables

I hope that these two Boost libraries will merge their synchronization mechanisms in a near future. Waiting for this merge this could serve as a temporary solution.

# Mapping the current mutexes (Boost.Thread and Boost/Interprocess) to the common concepts

The mapping from the current mutexes and scoped guards (Boost.Thread and Boost/Interprocess) to the common concepts has been done adding a indirection level. Instead of requiring a given member function, the lockable concepts reside in fre functions. Neither the Boost.Thread nor Boost/Interprocess mutexes and locks are based on functions, but can see them as models of the common lockable and loker concepts by specializing these generic free functions. In order to make easier the mapping these functions call by default to a member function with the equivalent signature.

For example thread\_timed\_mutex is viwed as a lockable by specializing the folloxing functions:



```
namespace partial_specialization_workaround {
          template <class Clock, class Duration >
          struct lock_until<boost::timed_mutex,Clock, Duration>
                    static void
                   apply( boost::timed_mutex& lockable, const chrono::time_point<Clock, Dura,
tion>& abs_time ) {
                             if(!lockable.timed_lock(boost::con-
vert_to<posix_time::ptime>(abs_time))) throw timeout_exception();
          };
          template <class Rep, class Period >
          struct lock_for<boost::timed_mutex,Rep, Period> {
                    static void
                    apply( boost::timed_mutex& lockable, const chrono::duration<Rep, Period>& rel_time ) {
                              if(!lockable.timed_lock(boost::convert_to<posix_time::time_dura↓</pre>
tion>(rel_time))) throw timeout_exception();
          };
          template <class Clock, class Duration >
          struct try_lock_until<boost::timed_mutex,Clock, Duration> {
                    static typename result_of::template try_lock_until<boost::timed_mutex,Clock, Dura-J
tion>::type
                    \verb"apply" (boost::timed_mutex@lockable, const chrono::timed_point<Clock, Dura$\cite{Clock} (const chrono::timed_point<Clock) (const chrono::timed_mutex@lockable) (const chrono::timed_point<Clock) (const chrono::timed_mutex@lockable) (const chrono::timed_point<Clock) (const chr
tion>& abs_time ) {
                             return lockable.timed_lock(boost::convert_to<posix_time::ptime>(abs_time));
          };
          template <class Rep, class Period >
          struct try_lock_for<boost::timed_mutex,Rep, Period> {
                   static typename result_of::template try_lock_for<boost::timed_mutex,Rep, Period>::type
                    apply( boost::timed_mutex& lockable, const chrono::duration<Rep, Period>& rel_time ) {
                            return lockable.timed_lock(boost::convert_to<posix_time::time_duration>(rel_time));
          };
```

Note that only the functions for which the equivalent signature differ are defined. For the others the default works as expected.

## **Condition lockable**

Based on the idead of Kevlin Henney, the library provides condition lockable, which allows a condition variable to be associated with a Lockable.

Treating condition locking as a property of Lockable rather than viceversa has the benefit of making clear how something is locked and accessed, as it were emphasising it in the first person.



Requiring the user of a condition variable to implement a while loop to verify a condition's predicate is potentially error prone. It can be better encapsulated by passing the predicate as a function object to the locking function.

```
class product_queue {
public:
    ...
    product *pull() {
        mtx.lock_when(not_empty, has_products(queue));
        product *pulled = queue.front();
        queue.pop();
        mtx.unlock();
        return pulled;
    }
    ...
};
```

# **Exception-based Timed Locks**

Based on the idead of Kevlin Henney, the library supports timeout exception for all the locking functions having a time or duration parameter.

- A lock with a timeout parameter, i.e. a time or a duration, throws a timeout\_exception on expiry
- A try\_lock with a timeout simply returns false on expiry
- Any of the conditional locks throw a timeout\_exception on expiry
- · all the locker constructors with the first parameter a timeout.

Use of timeouts can create more robust programs, by not blocking forever, but at the same time one needs to avoid annoyingly arbitrary limits.

#### Lockers

Typically, object-oriented programs use object-level locking by associating a synchronization object (mutex) with each object that is susceptible to be shared between threads. Then, code that manipulates the state of the object can synchronize by locking that object. Inside a synchronized section, the mutex associated with the object is locked, and consequently that object's fields can be accessed safely.

In C++, this fundamental idiom is typically implemented with a helper Locker object or lock guard.

A locker is any object or function responsible for coordinating the use of lockable objects.

- Lockers depend on lockable objects which need not be locking primitives and not vice-versa. This avoids cycles in the dependency graph.
- Lockers are applications of lockable objects and, as such, form a potentially unbounded family. Most common role of lockers is for exception safety and programming convenience
- · Lockers execute-around the lock-unlock pairing.

A locker defines an execution strategy for locking and unlocking that is automated by construction and destruction. It simplifies common use of locking, and does so in an exception-safe fashion. As such, lockers depend on the interface of lockables -e.g. lock and unlock - but lockables do not depend on lockers. The relationship is strictly layered, open and extensible: lockable types may be whole, externally locked objects against which existing lockers can be used; new lockers can be defined that work against existing lockable types.

Substitutability between lockables and lockers does not make sense, so the constructor is always explicit. Implicit copyability is also disabled.



Boost.Thread and Boost.Interprocess defines already a good starting point with these lockers:

- boost::lock\_guard,
- boost::unique\_lock, boost::interprocess::unique\_lock and boost::interprocess::scoped\_lock
- boost::share\_lock and boost::interprocess::sharable\_lock
- boost::upgrade\_lock and boost::interprocess::upgradable\_lock.

The problem is that even if these locker models the same model, there is no a single syntax.

The library defines some locker adapters which take care of naming differences and that can be used like

```
bsynchro::unique_locker<boost::mutex> scoped(guard);
```

or

```
bsynchro::unique_locker<boost::interprocess::interprocess_mutex> scoped(guard);
```

#### Strict lockers

Strict lockers were first introduced by Andrei Alexandrescu. A strict locker is a scoped lock guard ensuring the mutex is locked on the scope of the lock, by locking the mutex on construction and unlocking it on destruction.

boost::lock\_guard could be seen as a strict\_locker if the following constructor didn't exists

```
lock_guard(Lockable & m, boost::adopt_lock_t)
```

We can say that lock\_guard is a strict locker "sur parolle".

There is a const function that is very useful when working with strict lockers and external locking which check is the strict locker is locking an instace of a lockable.

```
bool is_locking(lockable_type* 1) const;
```

The library provides three strict lockers

- strict\_locker: is the basic strict locker, special use when doing external locking.
- neested\_strict\_locker: is a strict\_locker of another locker as a unique\_lock.
- conditional\_unique\_locker and conditional\_shared\_locker : are strict lockers with the condition\_lockable interface. These are the synchronizer of the monitor class.

```
class product_queue {
public:
    ...
    product *pull() {
        conditional_unique_locker<> _(mtx, not_empty, has_products(queue));
        product *pulled = queue.front();
        queue.pop();
        mtx.unlock();
        return pulled;
    }
    ...
};
```



and a meta function is\_strict\_locker which states if a locker is a strict locker.

So as strict lockers do not provide lock/unlock functions they are not models of Lockable.

#### Try lockers

A Try Locker is a Locker that initialize it in a such way that instead of locking on the constructor with <code>lock()</code> they can try to lock with <code>try\_lock()</code>. Most of the lockers defined in Boost.Thread and Boost.Interprocess could be cosidered as <code>TryLockers</code>, i.e. them initialize in this way when <code>boost::try\_to\_lock</code> is given as parameter.

The following code shows one way to use the TryLocker:

```
product *product_queue::try_pull() {
    product *pulled = 0;
    boost::unique_lock<boost::mutex> locker(mtx, boost::try_to_lock);
    if(locker && !queue.empty()) {
        pulled = queue.front();
        queue.pop();
    }
    return pulled;
}
```

All of them use a safe strategy for a boolean conversion which use a member pointer rather than a bool, which is typically too permissive:

```
typedef bool try_locker::*is_locked;
operator is_locked() const {
   return locked ? &try_locker::locked : 0;
}
```

If we use interprocess mutexes we need to replace the following line

```
boost::unique_lock<boost::mutex> scoped(guard, boost::try_to_lock);
```

by

```
boost::interprocess::scoped_lock<boost::interprocess::interprocess_mutex> scoped(guard, boost::ind-terprocess::try_to_lock);
```

There are other TryLockers in Boost. Thread defined as a member typedef scoped\_try\_lock. The semantics of each constructor and member function are identical to those of boost::unique\_lock<Lockable> for the same Lockable, except that the constructor that takes a single reference to a mutex will call m.try\_lock() rather than m.lock().

```
boost::mutex::scoped_try_lock locker(mtx);
```

The library defines in a generic way a try\_unique\_locker adapter which takes care of naming differences and that can be used like

```
bsynchro::unique_try_locker<Lockable> locker(mtx);
```

for any model of Lockable.

#### **Exception-based Timed Lockers**

In addition to supporting timeout exception for Lock, the library supports them also for ExceptionBaseTimedLockers. The semantics of each constructor and member function are identical to those of boost::unique\_locker<Lockable> for the same Lockable, except that the constructor that takes a time or a duration as first parameter in a addition to the reference to a mutex will call m.lock\_un-



til(t) or  $m.lock_for(d)$  rather than  $m.try_lock_until(t)$  or  $m.try_lock_for(d)$  and so a timeout\_exception is possible on the constructor.

Let me start with an example of an application needing to lock several locks at the same time. Once all the locks are locked something must be done. Otherwise the application do something else and reiterate the lock requests. The natural and exception safe way to do that is

```
while (polling) {
    t=now()+100;
    boost::unique_lock<boost::mutex> l1(m1, t);
    boost::unique_lock<boost::mutex> l2(m2, t);
    boost::unique_lock<boost::mutex> l3(m3, t);
    if (l1.has_lock() && l2.has_lock() && l3.has_lock() {
        foo();
        polling = false;
    } else execute_on_failed();
}
```

The problem with this code is that it locks m2 even if 11 do not owns the lock m1. The advertised reader could argument that if the lock m1 has not been locked by a timeout, as all share the same time constraint the failing lock of m2 will not be expensive. Well the problem is that the locking of m1 can fail because m1 is already locked. When we try to optimize this

we found that this starts to be unmaintenable. What is event wrost is that as the preceding one is subject to deadlock if another thread acquire the locks in a different order.

#### try\_lock\_until and try\_lock\_for free functions

To avoid this we can request the acquisition of all the locks toghether (letting the function to try several orders), as it does the function try\_lock of Boost. Threads, but adding this time a expiration period parameter

```
while (polling) {
    if (bsynchro::try_lock_for(100, m1, m2, m3)) {
        foo();
        polling = false;
    } else execute_on_failed();
}
```

While this solve the deadlock problem, this code is not exception safe. With exception based lockers we can do the following (note that the time is given as first aregument to the locker constructor)



```
while (polling)
    try {
        t = now() + 100;
        bsynchro::unique_locker < boost::mutex > 11(t, m1);
        bsynchro::unique_locker < boost::mutex > 12(t, m2);
        bsynchro::unique_locker < boost::mutex > 13(t, m3);
        foo();
        polling = false;
    } catch (bsynchro::timeout_exception& ex) {execute_on_failed(); }
```

#### locker\_tuples or locker\_array of Locker containers

While this code is exception safe and do not locks m2 if m1 is not acquired, it is subject to deadlock. We can go a step ahead and mix the advantage of taking all the locks at once and making the acquisition block scoped. In order to do that we need either a array\_locker or a tuple\_locker depending on whether the locks are homogeneus or not. The library provides both of them. These locker containers follows the same rules as the element wise lockers. If the time comes after the locks no exception is thrown on timeout and if given as the first parameter a exception will be thown when the time will expire.

So the preceding code becomes without timeout exceptions

```
while (polling) {
   bsynchro::array_unique_locker<boost::mutex, 3> lk(m1, m2, m3, 100);
   if (lk.owns_lock()) {
      foo();
      polling = false;
   } else execute_on_failed();
}
```

which is exception safe or with exception based timed locks (Note that the time is given before the locks)

```
while (polling)
try { bsynchro::array_locker<boost::mutex, 3> lk(100, m1, m2, m3);
    foo();
    polling = false;
} catch (bsynchro::timeout_exception& ex) { execute_on_failed(); }
```

When the Locks locked by an array\_unique\_locker are not homogeneus we need some kind of tuple.

```
while (polling)
try { bsynchro::tuple_unique_locker<T1, T2, T1> lk(100, m1, m2, m3);
    foo();
    polling = false;
} catch (bsynchro::timed_exception& ex) { execute_on_failed(); }
```

#### lock\_until and lock\_for free functions

For completion the exception based timed multi lock functions unlock, lock\_until and lock\_for are also provided.

```
while (polling)
   try {
      bsynchro::lock_for(100, m1, m2, m3);
      foo();
      polling = false;
   } catch (bsynchro::timeout_exception& ex) {execute_on_failed(); }
```

#### **External lockers**



An alternative or complementary approach to internal locking is to support external locking for an object - Multiple calls may be grouped within the same externally defined critical region.

External locking has some associated risks for high-level objects. Incorrect usage can be too easy: a forgotten call to lock or unlock is more likely than with synchronisation primitives because the focus of using the object is on the rest of its non-Lockable interface, so it becomes easy to forget that to use the interface correctly also requires participation in a locking scheme.

To some extent lockers can help, but such a co-operative scheme should only be employed when internal locking is too restricted for a given use, e.g. multiple operations must be performed together. Ideally, if such operations are common they should be defined internally locked and defined in the interface of the object as Combined Methods.

Assuming that locks are re-entrant, external locking can be provided to complement the more encapsulated internal locking, i.e. by default if you want to call a single function you just call it and it automatically locks, but if you want to call multiple functions together you first apply an external lock.

The library provides a externally\_locked class that allows to access a externally locked class in a thread safe mode through strict lockers.

Where only external locking is used, a safe approach is needed for calling single functions easily. The library provides two classes

- locking\_ptr and
- on\_dereference\_locking\_ptr
- externally\_locked

# Polymorphic lockable

The locks classes introduced previously are a non-polymorphic classes. Clearly, many of the synchronisation primitives support common operations, and hence interfaces. In some cases a more general interface is useful.

The synchronised interface class may be used explicitly as a base class for a class supporting synchronisation.

```
struct exclusive_lock {
    virtual ~exclusive_lock()=0;
    virtual void lock()=0;
    virtual void unlock()=0;
    virtual bool try_lock()=0;
};
```

More usefully for primitives, which are best left as non-polymorphic, an adaptor class is used to provide the interface -- run-time polymorphism -- on behalf of anything supporting the correctly named functions - compile time polymorphism. It easier to take a nonpolymorphic class and adapt it to be polymorphic, than it is do it the other way around: the overhead and semantics of polymorphism can only be introduced to a class, not removed.

```
template <typename Lockable>
class exclusive_lock_adapter : public virtual exclusive_lock
{
    exclusive_lock_adapter(): lock_() {}
    virtual ~exclusive_lock_adapter() {}

    virtual void lock() {lock_.lock();}
    virtual void unlock() {lock_.unlock();}

    virtual bool try_lock() { return lock_.try_lock();}

protected:
    Lockable lock_;
};
```



# Language-like Synchronized Block

Nest follows an example of mutual exclusion with automatic objects.

```
{
    scoped_guard<boost_mutex> lock(l);
    foo();
    return bar(); // lock released
}
```

With language-like mutual exclusion this results in:

```
synchronize(1)
{
   foo();
   return bar();
} // lock released
```

This is achieved through macros. If the user wants to use synchronized this way he needs to include a specific file which defines

```
#define synchronized(MUTEX) BOOST_SYNCHRONIZED(MUTEX)
```

The library do not provides this directly because this can broke some user code. The library provideds other safer macros, using the BOOST prefix.

```
#define BOOST_SYNCHRONIZED_VAR(VARS_DECLARATION) \
    if (bool stop_ = false) {} else \
    for (VARS_DECLARATION; !stop_; stop_ = true)

#define BOOST_SYNCHRONIZED(MUTEX) \
    BOOST_SYNCHRONIZED_VAR(boost::scoped_guard<boost::mutex> __lock(MUTEX))
```

## **Monitors**

Concurrent components may interact in different ways: they may access the same objects by, for example, executing functions of these objects; or they may communicate directly by executing functions of each other.

Concurrent execution of objects requires a mechanism for synchronizing the access to shared objects, just as direct communication between objects may require synchronization. The basic mechanism for synchronization in Boost.Threads and Boost.Interprocess are the well known mutex and condition\_variables. Mutexes and condition variables are, however, only useful for very simple synchronization problems. The Synchro Library therefore introduce high-level abstractions for handling more complicated synchronization problems, including monitor for guaranteeing exclusive access to an object.

Į/

# **Users'Guide**

Ţ/



# **Getting Started**

# **Installing Synchro**

## **Getting Boost.Synchro**

You can get the last stable release of Boost. Synchro by downloading synchro. zip from the Boost Vault

You can also access the latest (unstable?) state from the Boost Sandbox.

#### **Building Boost.Synchro**

There is no need to compile **Boost.Synchro**, since it's a header only library. Just include your Boost header directory in your compiler include path.

#### Requirements

**Boost.Synchro** depends on Boost. You must use either Boost version 1.38.x or the version in SVN trunk (even if Boost version 1.35.x should works also). In particular, **Boost.Synchro** depends on:

**Boost.Interprocess** interprocess synchronization primitives

**Boost.MPL** for all the meta programing task

**Boost.Thread** thread synchronization primitives

#### **Exceptions safety**

All functions in the library are exception-neutral and provide strong guarantee of exception safety as long as the underlying parameters provide it.

#### **Thread safety**

All functions in the library are thread-unsafe except when noted explicitly.

#### **Tested compilers**

Currently, **Boost.Synchro** has been tested in the following compilers/platforms:

- GCC 3.4.4 Cygwin
- GCC 3.4.6 Linux
- GCC 4.1.2 Linux



#### **Note**

Please send any questions, comments and bug reports to boost <at> lists <dot> boost <dot> org.

## **Hello World!**

# **Tutorial**

[info The contents of this tutorial is an adaptation of the papers of Andrei Alexandrescu, Kevlin Henney and the concurrent part of the BETA Programming Language.]

Concurrent components may interact in different ways: they may access the same shared objects by, for example, executing functions of these objects; or they may communicate directly by executing functions of each other.



Concurrent execution of objects requires a mechanism for synchronizing the access to shared objects, just as direct communication between objects may require synchronization. The basic mechanism for synchronization in Boost.Threads and Boost.Interprocess are the well known mutex and condition\_variables. Mutexes and condition variables are, however, only useful for very simple synchronization problems. The Synchro Library therefore introduce high-level abstractions for handling more complicated synchronization problems, including monitor for guaranteeing exclusive access to an object, controlling external locking and last a so-called rendezvous mechanism for handling direct communication between objects. All the concurrency abstractions being introduced are defined by means of mutexes an conditions.

## **Lockables**



#### Note

The following is an adaptation of the article "C++ Threading - A Generic-Programming Approach" by Kevin Henney.

#### Lock substitutability

The Boost (C++0x) mutexes have associated a category which form a sub-typing hierarchy: ExclusiveLock <- SharableLock <- UpgradableLock

```
exclusive_lock <- sharable_lock <- upgradable_lock
```

```
struct exclusive_lock_tag {};
struct sharable_lock_tag : exclusive_lock_tag {};
struct upgradable_lock_tag : sharable_lock_tag {};
```

Locking behavior can be further categorized as:

· Re-entrancy: recursive or not

```
non_recursive <- recursive
```

```
struct non_recursive_tag {};
struct recursive_tag : non_recursive_tag {};
```

· Scope: whether the lock is usable with a mono-threaded, multi-threaded or multi-process context

```
mono_threaded <- multi_threaded <- multi_process</pre>
```

```
struct mono_threaded_tag {};
struct multi_threaded_tag : mono_threaded_tag {};
struct multi_process_tag : multi_threaded_tag {};
```

Lifetime: The lifetime of a lock could be associated to the process, the kernel or the file-system

```
process_lifetime <- kernel_lifetime <- filesystem_lifetime</pre>
```

```
struct process_lifetime_tag {};
struct kernel_lifetime_tag : process_lifetime_tag {};
struct filesystem_lifetime_tag : kernel_lifetime_tag {};
```

• Timed interface: has or not a timed interfaces



```
hasnt_timed_interface <- has_timed_interface</pre>
```

```
struct hasnt_timed_interface_tag {};
struct has_timed_interface_tag : hasnt_timed_interface_tag {};
```

Substitutability applies both to the degree of syntactic support and to the locking semantics

- A recursive mutex and binary semaphore are substitutable in code written against a exclusive mutex
- A null mutex is substitutable for all others in a single-threaded environment

We can see these axes of variation expressed against some Boost synchronization mechanisms (from now bip stands for boost::interprocess):

- boost::mutex: ExclusiveLock, non-recursive, has-not-timed-interface, multi-threaded
- boost::shared\_mutex: UpgradableLock, non-recursive, has-timed-interface, multi-threaded
- bip::sync::null\_mutex: UpgradableLock, recursive, has-timed-interface, mono-threaded
- bip::sync::interprocess\_recursive\_mutex ExclusiveLock, recursive, has-timed-interface, multi\_process.

#### Lock traits

Generic programming (writing code which works with any data type meeting a set of requirements) has become the method of choice for providing reusable code.

However, there are times in generic programming when "generic" just isn't good enough - sometimes the differences between types are too large for an efficient generic implementation. This is when the traits technique becomes important - by encapsulating those properties that need to be considered on a type by type basis inside a traits class, we can minimize the amount of code that has to differ from one type to another, and maximize the amount of generic code.

Consider an example:

Boost.Synchro follow the design of Boost.TypeTraits, and contains a set of very specific traits classes, each of which encapsulate a single trait from the Lockable or Locker concepts; for example, is the lock recursive? Or does the lock have a timed interface?

The Boost.Synchro traits classes share a unified design: each class inherits from a the type true\_type if the type has the specified property and inherits from false\_type otherwise. As we will show, these classes can be used in generic programming to determine the properties of a given lock type and introduce optimizations that are appropriate for that case.

The type-traits library also contains a set of classes that perform a specific transformation on a type; for example, they can remove a top-level const or volatile qualifier from a type. Each class that performs a transformation defines a single typedef-member type that is the result of the transformation. All of the type-traits classes are defined inside namespace boost; for brevity, namespace-qualification is omitted in most of the code samples given.

#### **Implementation**

Most of the implementation is fairly repetitive anyway, so here we will just give you a flavor for how some of the classes are implemented. See the reference section for the full details.

A lockable implementer must specialize the scope\_tag template class. By default the scope\_tag forward to a nested type scope.

```
template <typename Lockable>
struct scope_tag {
   typedef typename Lockable::scope type;
};
```

So the implementer can either have a nested type scope or inherit from the helper lock\_traits\_base.



```
template<
    typename Scope,
    typename Category,
    typename Reentrancy,
    typename TimedInterface,
    typename Lifetime,
    typename Naming,
    typename Base
struct lock_traits_base : Base {
    // TODO add constraints on typenames
    typedef Scope scope;
    typedef Category category;
    typedef Reentrancy reentrancy;
    typedef TimedInterface timed_interface;
    typedef Lifetime lifetime;
    typedef Naming naming;
};
```

which defines the correct types. The lock\_traits\_base has a lot of parameters, and the defaults are the ones from boost::mutex. So Boost.Thread could use it as follows

```
class mutex : public lock_traits_base<> {
    // ...
};
```

Waiting for that Boost.Synchro specialize the scope\_tag in the synchro/thread/mutex.hpp file.

```
template<>
struct scope_tag<boost::mutex> {
   typedef multi_threaded_tag type;
};
```

So the user must include this file to make boost::mutex a model of Lockable for Boost.Synchro.

For example the trait is\_multi\_threaded is defined as: If Lockable has a scope\_tag that inherits from multi\_threaded\_tag then inherits from true\_type, otherwise inherits from false\_type.

```
template <typename Lockable>
struct is_multi_threaded
   : is_same_or_is_base_and_derived<
        multi_threaded_tag,
        typename scope_tag<Lockable>::type
   >
{};
```

#### Finding the best lock

Inverse traits can match a lockable type based on specific traits, for a given family of lock types.

It is also possible to specify characteristics to perform a reverse lookup to find a primitive lock type, either by exact match or by substitutable match.

```
find_best_lock<>>::type == boost::mutex
find_best_lock<mono_threaded_tag>::type == bsync::null_mutex
find_best_lock<multi_threaded_tag>::type == bsync::thread_mutex
find_best_lock<multi_process_tag>::type == bsync::interprocess_mutex
```



The user can also find a lock using mpl constraints as follows

```
typedef find_best_lock_between<Lockables,
    mpl::and<is_multi_threaded<_>, is_recursive<_> > >::type best;
```

#### Synchronization family

A class that will do internal locking can be parameterized by the type of synchronization familly needed to achieve the desired level of concurrency control. This could depend of the usage scope of this class, and this can be mono\_threaded, multi\_threaded, multi\_process.

For example the thread\_synchronization\_family can be used to instantiate a message\_queue class in a multi\_threaded environment, all public methods will be thread-safe, with the corresponding overhead that implies. In contrast, if a null\_synchronization\_policy class is used to instantiate message\_queue, all public methods will not be thread-safe, and there will be no additional overhead. A synchronization family must define typedef as for example

```
template <>
struct synchronization_family<multi_threaded_tag> {
   typedef thread_mutex
                                            mutex_type;
   typedef thread_recursive_mutex
                                            recursive mutex type;
   typedef thread_timed_mutex
                                            timed_mutex_type;
   typedef thread_recursive_timed_mutex
                                           recursive_timed_mutex_type;
   typedef thread_shared_mutex
                                            shared_mutex_type;
   typedef boost::condition_variable
                                            condition_type;
   typedef boost::condition_variable_any
                                            condition_type_any;
```

#### Lockable concept

For the main category clasification, the library provides concept classes that can be used with Boost.ConceptCheck. For example LockableConcept object supports the basic features required to delimit a critical region. Supports the basic lock, unlock and try\_lock functions and defines the lock traits.

```
template <typename Lockable>
struct LockableConcept {
   typedef typename category_tag<Lockable>::type category;
   typedef typename timed_interface_tag<Lockable>::type timed_interface;
   typedef typename reentrancy_tag<Lockable>::type reentrancy;
   typedef typename scope_tag<Lockable>::type scope;
   typedef typename lifetime_tag<Lockable>::type lifetime;
   typedef typename naming_tag<Lockable>::type naming;

BOOST_CONCEPT_USAGE(LockableConcept) {
    lockable::lock(l);
    lockable::unlock(l);
    lockable::try_lock(l);
  }
  Lockable& l;
};
```

The user can now check staticaly that the template parameter is a model of Locable as follows

```
#include "boost/synchro/lockable_concepts.hpp"
template <typename Lockable>
class my_class {
   BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
   // ...
};
```



The same can be done for TimedLockableConcept, ShareLockableConcept and UpgradeLockableConcept (See the reference section for more details).

#### Syntactic lock traits

The locks on Boost. Thread and Boost::Interprocess do not follow the same interface. Most of the differences can be handled through traits, but other are better handled by adapting the interface.

The \* The scoped locks live in a different namespace and some have different names with the same semantic.

```
template <typename Lockable>
struct scoped_lock_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::scoped_lock type;
};
template <typename Lockable>
struct unique_lock_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::unique_lock type;
};
template <typename Lockable>
struct shared_lock_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::shared_lock type;
};
template <typename Lockable>
struct upgrade_lock_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::upgrade_lock type;
};
template <typename Lockable>
struct upgrade_to_unique_locker_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::upgrade_to_unique_locker type;
};
```

So instead of using directly the locker of the respective libraries, use these traits.

```
bsync::shared_lock_type<Lockable>::type lock(mutex_);
```

• The exception thrown lives in a different name space and different names with the same semantic.

```
template <typename Lockable>
struct lock_error_type {
   typedef typename lockable_scope_traits<
        typename scope_tag<Lockable>::type, Lockable
   >::lock_error type;
};
```

So instead of using directly the exception type of the respective libraries, use these traits.



```
try {
    // ...
} catch (bsync::lock_error_type<Lockable>::type& ex) {
    // ...
}
```

• The move semantics (&&) are expressed with a class named differently.

• The scoped locks can be initialized with static const variables in order to overload the constructor for lock adoption, lock deferral or try to lock. Even if the name of these variables is the same, these variables live in different namespace.

```
template <typename Lockable>
struct defer_lock_type {
    typedef typename lockable_scope_traits<
               typename scope_tag<Lockable>::type, Lockable>::defer_lock_t type;
    static const type& value() {return lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::defer_lock();}
};
template <typename Lockable>
struct adopt_lock_type {
    typedef typename lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::adopt_lock_t type;
    static const type& value(){return lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::adopt_lock();}
};
template <typename Lockable>
struct try_to_lock_type {
    typedef typename lockable_scope_traits<
               typename scope_tag<Lockable>::type, Lockable>::try_to_lock_t type;
    static const type& value(){return lockable_scope_traits<
                typename scope_tag<Lockable>::type, Lockable>::try_to_lock();}
};
```

So instead of using directly the variables of the respective libraries, use these traits.

```
bsync::shared_lock_type<Lockable>::type lock(mutex_, bsync::try_to_lock_type::value());
```

# **Internal Locking--Monitors**



#### Note

This tutorial is an adaptation of chapter Concurrency of the Object-Oriented Programming in the BETA Programming Language and of the paper of Andrei Alexandrescu "Multithreading and the C++ Type System" to the Boost library.



## **Concurrent threads of execution**

Consider, for example, modeling a bank account class that supports simultaneous deposits and withdrawals from multiple locations (arguably the "Hello, World" of multithreaded programming).

From here a component is a model of the Callable concept.

On C++0X (Boost) concurrent execution of a component is obtained by means of the std::thread(boost::thread):

```
boost::thread thread1(S);
```

where S is a model of Callable. The meaning of this expression is that execution of S() will take place concurrently with the current thread of execution executing the expression.

The following example includes a bank account of a person (Joe) and two components, one corresponding to a bank agent depositing money in Joe's account, and one representing Joe. Joe will only be withdrawing money from the account:

```
class BankAccount;
BankAccount JoesAccount;
void bankAgent()
    for (int i =10; i>0; --i) {
        JoesAccount.Deposit(500);
        //...
void Joe() {
    for (int i =10; i>0; --i) {
        int myPocket = JoesAccount.Withdraw(100);
        std::cout << myPocket << std::endl;</pre>
        //...
}
int main() {
    //...
    boost::thread thread1(bankAgent); // start concurrent execution of bankAgent
    boost::thread thread2(Joe); // start concurrent execution of Joe
    thread1.join();
    thread2.join();
    return 0;
```

From time to time, the bankAgent will deposit \$500 in JoesAccount. Joe will similarly withdraw \$100 from his account. These sentences describe that the bankAgent and Joe are executed concurrently.

The above example works well as long as the bankAgent and Joe do not access JoesAccount at the same time. There is, however, no guarantee that this will not happen. We may use a mutex to guarantee exclusive access to each bank.



```
class BankAccount {
    boost::mutex mtx_;
    int balance_;
public:
    void Deposit(int amount) {
        mtx_.lock();
        balance_ += amount;
        mtx_.unlock();
    void Withdraw(int amount) {
        mtx_.lock();
        balance_ -= amount;
        mtx_.unlock();
    int GetBalance() {
        mtx_.lock();
        int b = balance_;
        mtx_.unlock();
        return balance_;
};
```

Execution of the Deposit and Withdraw operations will no longer be able to make simultaneous access to balance.

Mutex is a simple and basic mechanism for obtaining synchronization. In the above example it is relatively easy to be convinced that the synchronization works correctly (in the absence of exception). In a system with several concurrent objects and several shared objects, it may be difficult to describe synchronization by means of mutexes. Programs that make heavy use of mutexes may be difficult to read and write. Instead, we shall introduce a number of generic classes for handling more complicated forms of synchronization and communication.

With the RAII idiom we can simplify a lot this using the scoped locks. In the code below, guard's constructor locks the passed-in object this, and guard's destructor unlocks this.

#### • explicit mutex declaration

The object-level locking idiom doesn't cover the entire richness of a threading model. For example, the model above is quite deadlock-prone when you try to coordinate multi-object transactions. Nonetheless, object-level locking is useful in many cases, and in combination with other mechanisms can provide a satisfactory solution to many threaded access problems in object-oriented programs.

The BankAccount class above uses internal locking. Basically, a class that uses internal locking guarantees that any concurrent calls to its public member functions don't corrupt an instance of that class. This is typically ensured by having each public member function



acquire a lock on the object upon entry. This way, for any given object of that class, there can be only one member function call active at any moment, so the operations are nicely serialized.

This approach is reasonably easy to implement and has an attractive simplicity. Unfortunately, "simple" might sometimes morph into "simplistic."

Internal locking is insufficient for many real-world synchronization tasks. Imagine that you want to implement an ATM withdrawal transaction with the BankAccount class. The requirements are simple. The ATM transaction consists of two withdrawals-one for the actual money and one for the \$2 commission. The two withdrawals must appear in strict sequence; that is, no other transaction can exist between them.

The obvious implementation is erratic:

```
void ATMWithdrawal(BankAccount& acct, int sum) {
    acct.Withdraw(sum);
    acct.Withdraw(2);
}
```

#### • preemption possible

The problem is that between the two calls above, another thread can perform another operation on the account, thus breaking the second design requirement.

In an attempt to solve this problem, let's lock the account from the outside during the two operations:

#### • mtx\_ field is private

Notice that the code above do not compiles, the mtx\_field is private. We have two possibilities:

- make mtx\_ public which seams odd
- make the BankAccount lockable by adding the lock/unlock functions

We can add these functions explicitly



```
class BankAccount {
   boost::mutex mtx_;
   int balance_;
public:
   void Deposit(int amount) {
      boost::lock_guard<boost::mutex> guard(mtx_);
      balance_ += amount;
   }
   void Withdraw(int amount) {
      boost::lock_guard<boost::mutex> guard(mtx_);
      balance_ -= amount;
   }
   void lock() {
      mtx_.lock();
   }
   void unlock() {
      mtx_.unlock();
   }
}
```

or inheriting from a class which add these lockable functions.

The exclusive\_lockable\_adapter class

```
template <typename Lockable>
class exclusive_lockable_adapter
public:
    typedef Lockable lockable_type;
    typedef typename scope_tag<Lockable>::type scope;
    typedef typename category_tag<Lockable>::type category;
    typedef typename reentrancy_tag<Lockable>::type reentrancy;
    typedef typename timed_interface_tag<Lockable>::type timed_interface;
    typedef typename lifetime_tag<Lockable>::type lifetime;
    typedef typename naming_tag<Lockable>::type naming;
    BOOST_COPY_CONSTRUCTOR_DELETE(exclusive_lockable_adapter)  
    BOOST_COPY_ASSIGNEMENT_DELETE(exclusive_lockable_adapter) 2
    exclusive_lockable_adapter() {}
    void lock() {lock_.lock();}
    void unlock() {lock_.unlock();}
   bool try_lock() { return lock_.try_lock();}
protected:
   lockable_type* mutex() const { return &lock_; }
   mutable Lockable lock_;
};
```

- disable copy construction
- disable copy asignement

The BankAccount class result now in



```
class BankAccount
 public exclusive_lockable_adapter<thread_mutex>
    int balance_;
public:
    void Deposit(int amount) {
        boost::lock_guard<BankAccount> guard(*this);
//
          boost::lock_guard<boost::mutex> guard(*this->mutex());
        balance_ += amount;
    void Withdraw(int amount) {
        boost::lock_guard<BankAccount> guard(*this);
//
          boost::lock_guard<boost::mutex> guard(*this->mutex());
        balance_ -= amount;
    int GetBalance() {
        boost::lock_guard<BankAccount> guard(*this);
          boost::lock_guard<boost::mutex> guard(*this->mutex());
11
        return balance_;
};
```

and the code that do not comiles becomes

```
void ATMWithdrawal(BankAccount& acct, int sum) {
// boost::lock_guard<boost::mutex> guard(*acct.mutex());
  boost::lock_guard<BankAccount> guard(acct);
  acct.Withdraw(sum);
  acct.Withdraw(2);
}
```

Notice that now acct is being locked by Withdraw after it has already been locked by guard. When running such code, one of two things happens.

- Your mutex implementation might support the so-called recursive mutex semantics. This means that the same thread can lock the
  same mutex several times successfully. In this case, the implementation works but has a performance overhead due to unnecessary
  locking. (The locking/unlocking sequence in the two Withdraw calls is not needed but performed anyway-and that costs time.)
- Your mutex implementation might not support recursive locking, which means that as soon as you try to acquire it the second time, it blocks-so the ATMWithdrawal function enters the dreaded deadlock.

As boost::mutex is not recursive, we need to use its recursive version boost::recursive\_mutex.

```
class BankAccount
: public exclusive_lockable_adapter<thread_recursive_mutex>
{
    // ...
};
```

#### **Monitors**

The use of mutex and lockers, as in BankAccount, is a common way of defining objects shared by two or more concurrent components. The exclusive\_lockable\_adapter class was a first step. We shall therefore introduce an abstraction that makes it easier to define such objects. The following class describes a so-called monitor pattern.



- behaves like an ExclusiveLockable for the derived classes
- 2 is an strict lock guard

A monitor object behaves like a ExclusiveLockable object but only for the inheriting classes. Protected inheritance from exclusive\_lockable\_adapter provide to all the derived classes all ExclusiveLockable operations. In addition has a protected nested class, synchronizer, used when defining the monitor operations to synchronize the access critical regions. The BankAccount may be described using Monitor in the following way:

```
class BankAccount : protected exclusive_monitor<>
protected:
    int balance_;
public:
    BankAccount() : balance_(0) {}
    BankAccount(const BankAccount &rhs) {
        synchronizer _(*rhs.mutex());
        balance_=rhs.balance_;
    BankAccount & operator = (BankAccount &rhs)
        if(&rhs == this) return *this;
        int balance=0;
            synchronizer _(*rhs.mutex());
            balance=rhs.balance_;
        synchronizer _(*this->mutex());
        balance_=balance;
        return *this;
#if 0
    BankAccount & operator = (BankAccount &rhs)
        if(&rhs == this) return *this;
        int balance=0;
        synchronize (*rhs.mutex()) balance=rhs.balance_;
        synchronize (*this->mutex()) balance_=balance;
        return *this;
#endif
    void Deposit(int amount) {
        synchronizer _(*this->mutex());
        balance_ += amount;
    int Withdraw(int amount) {
        synchronizer _(*this->mutex());
        balance_ -= amount;
        return amount;
```



```
int GetBalance() {
    synchronizer _(*this->mutex());
    return balance_;
}
```

In the following, a monitor means some sub-class of monitor. A synchroronized operation means an operation using the synchronizer guard defined within some monitor. Monitor is one example of a high-level concurrency abstraction that can be defined by means of mutexes.

#### **Monitor Conditions**

It may happen that a component executing an entry operation of a monitor is unable to continue execution due to some condition not being fulfilled. Consider, for instance, a bounded buffer of characters. Such a buffer may be implemented as a monitor with two operations Push and Pull: the Puss operation cannot be executed if the buffer is full, and the Pull operation cannot be executed if the buffer is empty. A sketch of such a buffer monitor may look as follows:

#### • explicit mutex declaration

The meaning of a wait is that the calling component is delayed until the condition becomes true. We can do that using Boost. Thread condition variables like:



```
template <typename T, unsigned size>
class sync_buffer
    typedef boost::mutex mutex_type;
    typedef boost::condition_variable condition_type;
    typedef boost::unique_lock<mutex_type> unique_lock_type;
   mutex_type mtx_;
    condition_type not_full_;
    condition_type not_empty_;
   T data_[size+1];
   unsigned in_, out_;
public:
   sync_buffer():in_(0), out_(0) {}
   bool full() { return out_==(in_+1)%(size+1); }
   bool empty() { return out_==in_; }
   unsigned get_in() {return in_;}
   unsigned get_out() {return out_;}
   void push(T v) {
       while (full()) { 2
           not_full_.wait(guard);
       data_[in_]=v;
       in_ = (in_+1)% (size+1);
       not_empty_.notify_one(); 3
   T pull() {
       unique_lock_type guard(mtx_); 4
       while (empty()) { 6
           not_empty_.wait(guard);
       unsigned idx = out_;
       out_ = (out_+1)% (size+1);
       not_full_.notify_one(); 6
       return data_[idx];
};
```

- ensure the mutex is locked!!!
- 2 loop until not full!!!
- **3** notifies a not\_empty condition
- ensure the mutex is locked!!!
- loop until not full!!!
- onotifies a not\_full condition

The Monitor class replace the nested synchronizer unique\_lock with the class condition\_locker for this purpose:



```
template <
    typename Lockable,
    class Condition=condition_safe<typename best_condition<Lockable>::type >
    , typename ScopeTag=typename scope_tag<Lockable>::type
class condition_unique_locker
    : protected unique_locker<Lockable,ScopeTag>
    BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
    typedef unique_locker<Lockable, ScopeTag> super_type;
public:
    typedef Lockable lockable_type;
    typedef Condition condition;
    explicit condition_unique_locker(lockable_type& obj);  
    condition_unique_locker(lockable_type& obj, condition &cond); @
    template <typename Predicate>
    condition_unique_locker(lockable_type& obj, condition &cond, Predicate pred); 3
    ~condition_unique_locker() 4
    typedef bool (condition_unique_locker::*bool_type)() const; 6
    operator bool_type() const; 6
    bool operator!() const { return false; } 0
    bool owns_lock() const { return true; } 3
   bool is_locking(lockable_type* 1) const 9
    void relock_on(condition & cond);
    template<typename Clock, typename Duration>
    void relock_until(condition & cond, chrono::time_point<Clock, Duration> const& abs_time);
    template<typename duration_type>
    void relock_on_for(condition & cond, duration_type const& rel_time);
    template<typename Predicate>
    void relock_when(condition &cond, Predicate pred);
    template<typename Predicate>
    template<typename Clock, typename Duration>
    void relock_when_until(condition &cond, Predicate pred,
            \verb|chrono::time_point<Clock|, | Duration>| const& | abs_time|||;
    template<typename Predicate, typename duration_type>
    void relock_when_for(condition &cond, Predicate pred,
            duration_type const& rel_time);
    0
};
```

- locks on construction
- 2 relock on condition
- relock condition when predicate satisfaied
- 4 unlocks on destruction
- **6** safe bool idiom
- always owned
- always owned
- always owned
- 9 strict lockers specific function
- no possibility to unlock without blocking on wait...

We may now give the complete version of the buffer class. The content of the buffer is:  $data_[out_+1]$ ,  $data_[out_+2]$ , ...  $data_R[in_-1]$  where all the indexes are modulo size. The buffer is full if  $in_=out_$  and it is empty if  $in_=(out_+1)$ \*size.



```
template <typename T, unsigned size>
class sync_buffer : protected exclusive_monitor<>
   condition not_full_;
   condition not_empty_;
   T data_[size+1];
   unsigned in_, out_;
   struct not_full {
       bool operator()() const { return !that_.full(); }
       sync_buffer &that_;
   };
   struct not_empty {
       bool operator()() const { return !that_.empty(); }
       sync_buffer &that_;
public:
   BOOST_COPY_CONSTRUCTOR_DELETE(sync_buffer)  
   BOOST_COPY_ASSIGNEMENT_DELETE(sync_buffer) 2
   sync_buffer():in_(0), out_(0) {}
   bool full() { return out_==(in_+1)%(size+1); }
   bool empty() { return out_==in_; }
   unsigned get_in() {return in_;}
   unsigned get_out() {return out_;}
   void push(T v) {
       synchronizer _(*this->mutex(), not_full_, not_full(*this));
       data_[in_]=v;
       in_ = (in_+1)% (size+1);
       not_empty_.notify_one(); 4
   T pull() {
       synchronizer _(*this->mutex(), not_empty_, not_empty(*this));
       unsigned idx = out_;
       out_ = (out_+1)% (size+1);
       not_full_.notify_one(); 6
       return data_[idx];
};
```

- disable copy construction
- **2** disable copy asignement
- waits until the condition not\_full is satisfyed
- notifies a not\_empty condition
- waits until the condition not\_empty is satisfyed
- 6 notifies a not\_full condition

Monitors and conditions are useful for describing simple cases of shared objects (by simple we mean a limited use of conditions). If the conditions for delaying a calling component become complicated, the monitor may similarly become difficult to program and read.



## volatile and locking\_ptr



#### Note

This tutorial is an adaptation of the article of Andrei Alexandrescu "volatile - Multithreaded Programmer's Best Friend" to the Boost library.

## Just a Little Keyword

Although both C and C++ Standards are conspicuously silent when it comes to threads, they do make a little concession to multi-threading, in the form of the volatile keyword.

Just like its better-known counterpart const, volatile is a type modifier. It's intended to be used in conjunction with variables that are accessed and modified in different threads. Basically, without volatile, either writing multi-threaded programs becomes impossible, or the compiler wastes vast optimization opportunities. An explanation is in order.

Consider the following code:

```
class Gadget
{
  public:
     void Wait()
     {
           while (!flag_)
           {
                sleep(1000); // sleeps for 1000 milliseconds
           }
     }
  void Wakeup()
     {
           flag_ = true;
     }
     ...
private:
     bool flag_;
};
```

The purpose of Gadget::Wait above is to check the flag\_ member variable every second and return when that variable has been set to true by another thread. At least that's what its programmer intended, but, alas, Wait is incorrect. Suppose the compiler figures out that sleep(1000) is a call into an external library that cannot possibly modify the member variable flag\_. Then the compiler concludes that it can cache flag\_ in a register and use that register instead of accessing the slower on-board memory. This is an excellent optimization for single-threaded code, but in this case, it harms correctness: after you call Wait for some Gadget object, although another thread calls Wakeup, Wait will loop forever. This is because the change of flag\_ will not be reflected in the register that caches flag\_. The optimization is too ... optimistic. Caching variables in registers is a very valuable optimization that applies most of the time, so it would be a pity to waste it. C and C++ give you the chance to explicitly disable such caching. If you use the volatile modifier on a variable, the compiler won't cache that variable in registers -- each access will hit the actual memory location of that variable. So all you have to do to make Gadget's Wait/Wakeup combo work is to qualify flag\_appropriately:

```
class Gadget
{
public:
    ... as above ...
private:
    volatile bool flag_;
};
```

Most explanations of the rationale and usage of volatile stop here and advise you to volatile-qualify the primitive types that you use in multiple threads. However, there is much more you can do with volatile, because it is part of C++'s wonderful type system.



## Using volatile with User-Defined Types

You can volatile-qualify not only primitive types, but also user-defined types. In that case, volatile modifies the type in a way similar to const. (You can also apply const and volatile to the same type simultaneously.) Unlike const, volatile discriminates between primitive types and user-defined types. Namely, unlike classes, primitive types still support all of their operations (addition, multiplication, assignment, etc.) when volatile-qualified. For example, you can assign a non-volatile int to a volatile int, but you cannot assign a non-volatile object to a volatile object. Let's illustrate how volatile works on user-defined types on an example.

```
class Gadget
{
public:
    void Foo() volatile;
    void Bar();
    ...
private:
    std::tring name_;
    int state_;
};
...
Gadget regularGadget;
volatile Gadget volatileGadget;
```

If you think volatile is not that useful with objects, prepare for some surprise.

The conversion from a non-qualified type to its volatile counterpart is trivial. However, just as with const, you cannot make the trip back from volatile to non-qualified. You must use a cast:

```
Gadget& ref = const_cast<Gadget&>(volatileGadget);
ref.Bar(); // ok
```

A volatile-qualified class gives access only to a subset of its interface, a subset that is under the control of the class implementer. Users can gain full access to that type's interface only by using a const\_cast. In addition, just like constness, volatileness propagates from the class to its members (for example, volatileGadget.name\_ and volatileGadget.state\_ are volatile variables).

#### volatile, Critical Sections, and Race Conditions

The simplest and the most often-used synchronization device in multi-threaded programs is the mutex.

Mutexes are used to protect data against race conditions. By definition, a race condition occurs when the effect of more threads on data depends on how threads are scheduled. Race conditions appear when two or more threads compete for using the same data. Because threads can interrupt each other at arbitrary moments in time, data can be corrupted or misinterpreted. Consequently, changes and sometimes accesses to data must be carefully protected with critical sections. In object-oriented programming, this usually means that you store a mutex in a class as a member variable and use it whenever you access that class' state. Experienced multi-threaded programmers might have yawned reading the two paragraphs above, but their purpose is to provide an intellectual workout, because now we will link with the volatile connection. We do this by drawing a parallel between the C++ types' world and the threading semantics world.



- Outside a critical section, any thread might interrupt any other at any time; there is no control, so consequently variables accessible
  from multiple threads are volatile. This is in keeping with the original intent of volatile -- that of preventing the compiler
  from unwittingly caching values used by multiple threads at once.
- Inside a critical section defined by a mutex, only one thread has access. Consequently, inside a critical section, the executing code has single-threaded semantics. The controlled variable is not volatile anymore -- you can remove the volatile qualifier.

In short, data shared between threads is conceptually volatile outside a critical section, and non-volatile inside a critical section. You enter a critical section by locking a mutex. You remove the volatile qualifier from a type by applying a const\_cast. If we manage to put these two operations together, we create a connection between C++'s type system and an application's threading semantics. We can make the compiler check race conditions for us.

#### locking\_ptr

We need a tool that collects a mutex acquisition and a const\_cast. Let's develop a locking\_ptr class template that you initialize with a volatile object obj and a mutex mtx. During its lifetime, a locking\_ptr keeps mtx acquired. Also, locking\_ptr offers access to the volatile-stripped obj. The access is offered in a smart pointer fashion, through operator-> and operator\*. The const\_cast is performed inside locking\_ptr. The cast is semantically valid because locking\_ptr keeps the mutex acquired for its lifetime. First, let's define the skeleton of a class mutex with which locking\_ptr will work:

```
class mutex
{
public:
    void lock();
    void unlock();
    ...
};
```

locking\_ptr is templated with the type of the controlled variable and the exclusive lockable type. For example, if you want to control a Widget, you use a locking\_ptr<Widget> that you initialize with a variable of type volatile Widget. locking\_ptr is very simple. locking\_ptr implements an unsophisticated smart pointer. It focuses solely on collecting a const\_cast and a critical section.

```
template <typename T>
class locking_ptr {
public:
    // Constructors/destructors
    locking_ptr(volatile T& obj, mutex& mtx)
        : obj_(*const_cast<T*>(&obj)),
           mtx_(mtx)
        mtx_.lock();
    ~locking_ptr()
        mtx_->unlock();
    // Pointer behavior
    T& operator*()
        return obj_;
    T* operator->()
    {
       return &obj_;
private:
    T& obj_;
    mutex& mtx_;
    locking_ptr(const locking_ptr&);
    locking_ptr& operator=(const locking_ptr&);
};
```

In spite of its simplicity, <code>locking\_ptr</code> is a very useful aid in writing correct multi-threaded code. You should define objects that are shared between threads as volatile and never use <code>const\_cast</code> with them -- always use <code>locking\_ptr</code> automatic objects. Let's illustrate this with an example. Say you have two threads that share a vector<char> object:



```
class SynchroBuf {
public:
    void Thread1();
    void Thread2();
private:
    typedef vector<char> BufT;
    volatile BufT buffer_;
    mutex mtx_; // controls access to buffer_
};
```

Inside a thread function, you simply use a locking\_ptr<BufT> to get controlled access to the buffer\_ member variable:

```
void SynchroBuf::Thread1() {
    locking_ptr<BufT> lpBuf(buffer_, mtx_);
    BufT::iterator i = lpBuf->begin();
    for (; i != lpBuf->end(); ++i) {
            ... use *i ...
    }
}
```

The code is very easy to write and understand -- whenever you need to use buffer\_, you must create a locking\_ptr<Buff> pointing to it. Once you do that, you have access to vector's entire interface. The nice part is that if you make a mistake, the compiler will point it out:

```
void SynchroBuf::Thread2() {
    // Error! Cannot access 'begin' for a volatile object
    BufT::iterator i = buffer_.begin();
    // Error! Cannot access 'end' for a volatile object
    for (; i != lpBuf->end(); ++i) {
            ... use *i ...
    }
}
```

You cannot access any function of buffer\_ until you either apply a const\_cast or use locking\_ptr. The difference is that locking\_ptr offers an ordered way of applying const\_cast to volatile variables. locking\_ptr is remarkably expressive. If you only need to call one function, you can create an unnamed temporary locking\_ptr object and use it directly:

```
unsigned int SynchroBuf::Size() {
    return locking_ptr<BufT>(buffer_, mtx_)->size();
}
```

# **Back to Primitive Types**

We saw how nicely volatile protects objects against uncontrolled access and how locking\_ptr provides a simple and effective way of writing thread-safe code. Let's now return to primitive types, which are treated differently by volatile. Let's consider an example where multiple threads share a variable of type int.

```
class Counter
{
public:
    ...
    void Increment() { ++ctr_; }
    void Decrement() { --ctr_; }

private:
    int ctr_;
};
```



If Increment and Decrement are to be called from different threads, the fragment above is buggy. First, ctr\_must be volatile. Second, even a seemingly atomic operation such as ++ctr\_ is actually a three-stage operation. Memory itself has no arithmetic capabilities. When incrementing a variable, the processor:

- Reads that variable in a register
- · Increments the value in the register
- Writes the result back to memory

This three-step operation is called RMW (Read-Modify-Write). During the Modify part of an RMW operation, most processors free the memory bus in order to give other processors access to the memory. If at that time another processor performs a RMW operation on the same variable, we have a race condition: the second write overwrites the effect of the first. To avoid that, you can rely, again, on locking\_ptr:

```
class Counter
{
public:
    ...
    void Increment() { ++*locking_ptr<int, boost::mutex>(ctr_, mtx_); }
    void Decrement() { --*locking_ptr<int, boost::mutex>(ctr_, mtx_); }

private:
    volatile int ctr_;
    boost::mutex mtx_;
};
```

Now the code is correct, but its quality is inferior when compared to SynchroBuf's code. Why? Because with Counter, the compiler will not warn you if you mistakenly access ctr\_ directly (without locking it). The compiler compiles ++ctr\_ if ctr\_ is volatile, although the generated code is simply incorrect. The compiler is not your ally anymore, and only your attention can help you avoid race conditions. What should you do then? Simply encapsulate the primitive data that you use in higher-level structures and use volatile with those structures. Paradoxically, it's worse to use volatile directly with built-ins, in spite of the fact that initially this was the usage intent of volatile!

### volatile Member Functions

So far, we've had classes that aggregate volatile data members; now let's think of designing classes that in turn will be part of larger objects and shared between threads. Here is where volatile member functions can be of great help. When designing your class, you volatile-qualify only those member functions that are thread safe. You must assume that code from the outside will call the volatile functions from any code at any time. Don't forget: volatile equals free multi-threaded code and no critical section; non-volatile equals single-threaded scenario or inside a critical section. For example, you define a class Widget that implements an operation in two variants -- a thread-safe one and a fast, unprotected one.

```
class Widget
{
public:
    void Operation() volatile;
    void Operation();
    ...
private:
    boost::mutex mtx_;
};
```

Notice the use of overloading. Now Widget's user can invoke Operation using a uniform syntax either for volatile objects and get thread safety, or for regular objects and get speed. The user must be careful about defining the shared Widget objects as volatile. When implementing a volatile member function, the first operation is usually to lock this with a locking\_ptr. Then the work is done by using the non-volatile sibling:



```
void Widget::Operation() volatile
{
    locking_ptr<Widget,boost::mutex> lpThis(*this, mtx_);
    lpThis->Operation(); // invokes the non-volatile function
}
```

#### Generic locking\_ptr

The locking\_ptr works with a mutex class. How to use it with other mutexes? We can make a more generic locking\_ptr adding a Lockable template parameter.

```
template <typename T, typename Lockable=boost::mutex>
class locking_ptr
public:
   typedef T value_type;
   typedef Lockable lockable_type;
   locking_ptr(volatile value_type& obj, lockable_type& mtx) •
       , mtx_(mtx)
                       mtx_.lock();
   ~locking_ptr()
       mtx_.unlock();
   value_type& operator*()
       return *ptr_;
   value_type* operator->()
   { return ptr_; }
   BOOST_DEFAULT_CONSTRUCTOR_DELETE(locking_ptr) 6
   BOOST_COPY_CONSTRUCTOR_DELETE(locking_ptr) •
   BOOST_COPY_ASSIGNEMENT_DELETE(locking_ptr) 3
private:
   value_type* ptr_;
   lockable_type& mtx_;
};
```

- volatile
- const\_cast
- 3 locks on construction
- 4 unlocks on destruction
- **5** smart pointer related operations
- 6 disable default construction
- disable copy construction
- disable copy asignement

Every model of the ExclusiveLockable concept can be used as parameter.

## Specific locking\_ptr for lockable value types

When the value type is itself lockable we can simplify the locking\_ptr as follows:



```
template <typename Lockable>
class locking_ptr_1 {
public:
    typedef Lockable value_type;
    typedef Lockable mutex_type;
    locking_ptr_1(volatile value_type& obj)
      : ptr_(const_cast<value_type*>(&obj))
        ptr_->lock();
    ~locking_ptr_1()
        ptr_->unlock();
                           }
    value_type& operator*()
       return *ptr_;
    value_type* operator->()
      return ptr_;
                      }
    BOOST_DEFAULT_CONSTRUCTOR_DELETE(locking_ptr_1)  
    BOOST_COPY_CONSTRUCTOR_DELETE(locking_ptr_1) 2
    BOOST_COPY_ASSIGNEMENT_DELETE(locking_ptr_1) 3
private:
    value_type* ptr_; 4
};
```

- disable default construction
- **2** disable copy construction
- 3 disable copy asignement
- only one pointer needed

# External Locking -- strict\_locker and externally\_locked classes



#### **Note**

This tutorial is an adaptation of the paper of Andrei Alexandrescu "Multithreading and the C++ Type System" to the Boost library.

#### **Locks as Permits**

So what to do? Ideally, the BankAccount class should do the following:

- Support both locking models (internal and external).
- Be efficient; that is, use no unnecessary locking.
- Be safe; that is, BankAccount objects cannot be manipulated without appropriate locking.

Let's make a worthwhile observation: Whenever you lock a BankAccount, you do so by using a lock\_guard<BankAccount> object. Turning this statement around, wherever there's a lock\_guard<BankAccount>, there's also a locked BankAccount somewhere. Thus, you can think of-and use-a lock\_guard<BankAccount> object as a permit. Owning a lock\_guard<BankAccount> gives you rights to do certain things. The lock\_guard<BankAccount> object should not be copied or aliased (it's not a transmissible permit).

- 1. As long as a permit is still alive, the BankAccount object stays locked.
- 2. When the lock\_guard<BankAccount> is destroyed, the BankAccount's mutex is released.

The net effect is that at any point in your code, having access to a lock\_guard<BankAccount> object guarantees that a BankAccount is locked. (You don't know exactly which BankAccount is locked, however-an issue that we'll address soon.)



For now, let's make a couple of enhancements to the <code>lock\_guard</code> class template defined in Boost.Thread. We'll call the enhanced version <code>strict\_locker</code>. Essentially, a <code>strict\_locker</code>'s role is only to live on the stack as an automatic variable. <code>strict\_locker</code> must adhere to a non-copy and non-alias policy. <code>strict\_locker</code> disables copying by making the copy constructor and the assignment operator private. While we're at it, let's disable operator new and operator delete; <code>strict\_locker</code> are not intended to be allocated on the heap. <code>strict\_locker</code> avoids aliasing by using a slightly less orthodox and less well-known technique: disable address taking.

```
template <typename Lockable>
class strict_locker
     BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
public:
   typedef Lockable lockable_type;
   explicit strict_locker(lockable_type& obj)
       : obj_(obj) { obj.lock(); } ①
   ~strict_locker() { obj_.unlock(); } 2
   typedef bool (strict_locker::*bool_type)() const; 3
   operator bool_type() const { return &strict_locker::owns_lock;
   bool operator!() const { return false; } @
   bool owns_lock() const { return true; }
   const lockable_type* mutex() const { return &obj_; }
   bool is_locking(lockable_type* 1) const { return l==mutex(); } 6
   BOOST_ADRESS_OF_DELETE(strict_locker) 6
   BOOST HEAP ALLOCATEION DELETE(strict locker) •
   BOOST_COPY_CONSTRUCTOR_DELETE(strict_locker) 9
   BOOST_COPY_ASSIGNEMENT_DELETE(strict_locker) •
   Ф
private:
   lockable_type& obj_;
```

- locks on construction
- 2 unlocks on destruction
- safe bool idiom
- always owned
- **5** strict lockers specific function
- **6** disable aliasing
- disable heap allocation
- disable default construction
- **9** disable copy construction
- disable copy asignement
- no possibility to unlock

Silence can be sometimes louder than words-what's forbidden to do with a strict\_locker is as important as what you can do. Let's see what you can and what you cannot do with a strict\_locker instantiation:

 You can create a strict\_locker<T> only starting from a valid T object. Notice that there is no other way you can create a strict\_locker<T>.



```
BankAccount myAccount("John Doe", "123-45-6789");
strict_locerk<BankAccount> myLock(myAccount); // ok
```

 You cannot copy strict\_lockers to one another. In particular, you cannot pass strict\_lockers by value to functions or have them returned by functions:

```
extern strict_locker<BankAccount> Foo(); // compile-time error
extern void Bar(strict_locker<BankAccount>); // compile-time error
```

However, you still can pass strict\_lockers by reference to and from functions:

```
// ok, Foo returns a reference to strict_locker<BankAccount>
extern strict_locker<BankAccount>& Foo();
// ok, Bar takes a reference to strict_locker<BankAccount>
extern void Bar(strict_locker<BankAccount>&);
```

• You cannot allocate a strict\_locker on the heap. However, you still can put strict\_lockers on the heap if they're members of a class.

```
strict_locker<BankAccount>* pL =
   new strict_locker<BankAccount>(myAcount); //error!
   // operator new is not accessible
class Wrapper {
   strict_locker memberLock_;
   ...
};
Wrapper* pW = new Wrapper; // ok
```

(Making strict\_locker a member variable of a class is not recommended. Fortunately, disabling copying and default construction makes strict\_locker quite an unfriendly member variable.)

• You cannot take the address of a strict\_locker object. This interesting feature, implemented by disabling unary operator&, makes it very unlikely to alias a strict\_locker object. Aliasing is still possible by taking references to a strict\_locker:

```
strict_locker<BankAccount> myLock(myAccount); // ok
strict_locker<BankAccount>* pAlias = &myLock; // error!
    // strict_locker<BankAccount>::operator& is not accessible
strict_locker<BankAccount>& rAlias = myLock; // ok
```

Fortunately, references don't engender as bad aliasing as pointers because they're much less versatile (references cannot be copied or reseated).

You can even make strict\_locker final; that is, impossible to derive from. This task is left in the form of an exercise to the reader

All these rules were put in place with one purpose-enforcing that owning a strict\_locker<T> is a reasonably strong guarantee that

- 1. you locked a T object, and
- 2. that object will be unlocked at a later point.

Now that we have such a strict strict\_locker, how do we harness its power in defining a safe, flexible interface for BankAccount? The idea is as follows:

• Each of BankAccount's interface functions (in our case, Deposit and Withdraw) comes in two overloaded variants.



- One version keeps the same signature as before, and the other takes an additional argument of type strict\_locker<BankAccount>. The first version is internally locked; the second one requires external locking. External locking is enforced at compile time by requiring client code to create a strict\_locker<BankAccount> object.
- BankAccount avoids code bloating by having the internal locked functions forward to the external locked functions, which do the
  actual job.

A little code is worth 1,000 words, a (hacked into) saying goes, so here's the new BankAccount class:

```
class BankAccount
 public exclusive_lockable_adapter<boost:recursive_mutex>
    int balance ;
public:
    void Deposit(int amount, strict_locker<BankAccount>&) {
        // Externally locked
       balance_ += amount;
    void Deposit(int amount) {
        strict_locker<boost:mutex> quard(*this); // Internally locked
        Deposit(amount, guard);
    void Withdraw(int amount, strict_locker<BankAccount>&) {
        // Externally locked
        balance_ -= amount;
    void Withdraw(int amount) {
        strict_locker<boost:mutex> guard(*this); // Internally locked
        Withdraw(amount, guard);
};
```

Now, if you want the benefit of internal locking, you simply call Deposit(int) and Withdraw(int). If you want to use external locking, you lock the object by constructing a strict\_locker<BankAccount> and then you call Deposit(int, strict\_locker<BankAccount>&). For example, here's the ATMWithdrawal function implemented correctly:

```
void ATMWithdrawal(BankAccount& acct, int sum) {
   strict_locker<BankAccount> guard(acct);
   acct.Withdraw(sum, guard);
   acct.Withdraw(2, guard);
}
```

This function has the best of both worlds-it's reasonably safe and efficient at the same time.

It's worth noting that strict\_locker being a template gives extra safety compared to a straight polymorphic approach. In such a design, BankAccount would derive from a Lockable interface. strict\_locker would manipulate Lockable references so there's no need for templates. This approach is sound; however, it provides fewer compile-time guarantees. Having a strict\_locker object would only tell that some object derived from Lockable is currently locked. In the templated approach, having a strict\_locker<BankAccount> gives a stronger guarantee-it's a BankAccount that stays locked.

There's a weasel word in there-I mentioned that ATMWithdrawal is reasonably safe. It's not really safe because there's no enforcement that the strict\_locker<BankAccount> object locks the appropriate BankAccount object. The type system only ensures that some BankAccount object is locked. For example, consider the following phony implementation of ATMWithdrawal:



```
void ATMWithdrawal(BankAccount& acct, int sum) {
    BankAccount fakeAcct("John Doe", "123-45-6789");
    strict_locker<BankAccount> guard(fakeAcct);
    acct.Withdraw(sum, guard);
    acct.Withdraw(2, guard);
}
```

This code compiles warning-free but obviously doesn't do the right thing-it locks one account and uses another.

It's important to understand what can be enforced within the realm of the C++ type system and what needs to be enforced at runtime. The mechanism we've put in place so far ensures that some BankAccount object is locked during the call to BankAccount::Withdraw(int, strict\_locker<BankAccount>&). We must enforce at runtime exactly what object is locked.

If our scheme still needs runtime checks, how is it useful? An unwary or malicious programmer can easily lock the wrong object and manipulate any BankAccount without actually locking it.

First, let's get the malice issue out of the way. C is a language that requires a lot of attention and discipline from the programmer. C++ made some progress by asking a little less of those, while still fundamentally trusting the programmer. These languages are not concerned with malice (as Java is, for example). After all, you can break any C/C++ design simply by using casts "appropriately" (if appropriately is an, er, appropriate word in this context).

The scheme is useful because the likelihood of a programmer forgetting about any locking whatsoever is much greater than the likelihood of a programmer who does remember about locking, but locks the wrong object.

Using strict\_locker permits compile-time checking of the most common source of errors, and runtime checking of the less frequent problem.

Let's see how to enforce that the appropriate BankAccount object is locked. First, we need to add a member function to the strict\_locker class template. The strict\_locker<T>::get\_lockable function returns a reference to the locked object.

```
template <class T> class strict_locker {
    ... as before ...
public:
    T* get_lockable() const { return &obj_; }
};
```

Second, BankAccount needs to compare the locked object against this:

```
class BankAccount {
    public exclusive_lockable_adapter<boost::recursive_mutex>
        int balance_;
public:
    void Deposit(int amount, strict_locker<BankAccount>& guard) {
        // Externally locked
        if (!guard.is_locking(*this))
            throw "Locking Error: Wrong Object Locked";
        balance_ += amount;
    }
};
```

The overhead incurred by the test above is much lower than locking a recursive mutex for the second time.

#### **Improving External Locking**

Now let's assume that BankAccount doesn't use its own locking at all, and has only a thread-neutral implementation:



```
class BankAccount {
    int balance_;
public:
    void Deposit(int amount) {
        balance_ += amount;
    }
    void Withdraw(int amount) {
        balance_ -= amount;
    }
};
```

Now you can use BankAccount in single-threaded and multi-threaded applications alike, but you need to provide your own synchronization in the latter case.

Say we have an AccountManager class that holds and manipulates a BankAccount object:

```
class AccountManager
: public exclusive_lockable_adapter<boost::mutex>
{
    BankAccount checkingAcct_;
    BankAccount savingsAcct_;
    ...
};
```

Let's also assume that, by design, AccountManager must stay locked while accessing its BankAccount members. The question is, how can we express this design constraint using the C++ type system? How can we state "You have access to this BankAccount object only after locking its parent AccountManager object"?

The solution is to use a little bridge template externally\_locked that controls access to a BankAccount.



```
template <typename T, typename Lockable>
class externally_locked {
    BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
    typedef typename syntactic_lock_traits<Lockable>::lock_error lock_error;
public:
    externally_locked(T& obj, Lockable& lockable)
        : obj_(obj)
        , lockable_(lockable)
    {}
    externally_locked(Lockable& lockable)
        : obj ()
        , lockable_(lockable)
    {}
    T& get(strict_locker<Lockable>& locker) {
#ifndef BOOST_SYNCHRO_EXTERNALLY_LOCKED_DONT_CHECK_SAME 2
        if (!locker.is_locking(&lockable_)) throw lock_error(); 3
#endif
        return obj_;
    void set(const T& obj, Lockable& lockable) {
        obj_ = obj_i
        lockable_=lockable;
private:
   T obj_;
   Lockable& lockable_;
};
```

- needed until Boost Thread and Interprocess unify the exceptions
- define BOOST\_SYNCHRO\_EXTERNALLY\_LOCKED\_DONT\_CHECK\_SAME if you don't want to check locker check the same lockable
- **3** run time check throw if not locks the same

externally\_locked cloaks an object of type T, and actually provides full access to that object through the get and set member functions, provided you pass a reference to a strict\_locker<Owner> object.

Instead of making checkingAcct\_ and savingsAcct\_ of type BankAccount, AccountManager holds objects of type externally\_locked<BankAccount, AccountManager>:



The pattern is the same as before-to access the BankAccount object cloaked by checkingAcct\_, you need to call get. To call get, you need to pass it a strict\_locker<AccountManager>. The one thing you have to take care of is to not hold pointers or references you obtained by calling get. If you do that, make sure that you don't use them after the strict\_locker has been destroyed. That is, if you alias the cloaked objects, you're back from "the compiler takes care of that" mode to "you must pay attention" mode.

Typically, you use externally\_locked as shown below. Suppose you want to execute an atomic transfer from your checking account to your savings account:

```
void AccountManager::Checking2Savings(int amount) {
   strict_locker<AccountManager> guard(*this);
   checkingAcct_.get(guard).Withdraw(amount);
   savingsAcct_.get(guard).Deposit(amount);
}
```

We achieved two important goals. First, the declaration of checkingAcct\_ and savingsAcct\_ makes it clear to the code reader that that variable is protected by a lock on an AccountManager. Second, the design makes it impossible to manipulate the two accounts without actually locking a BankAccount. externally\_locked is what could be called active documentation.

#### Allowing other strict lockers

Now imagine that the AccountManager function needs to take a unique\_lock in order to reduce the critical regions. And at some time it needs to access to the checkingAcct\_. As unique\_lock is not a strict lock the following code do not compiles:

```
void AccountManager::AMoreComplicatedChecking2Savings(int amount) {
    unique_lock<AccountManager> guard(*this);
    if (some_condition()) {
        guard.lock();
    }
    checkingAcct_.get(guard).Withdraw(amount);
    savingsAcct_.get(guard).Deposit(amount);
    guard1.unlock();
}
```

We need a way to transfer the ownership from the unique\_lock to a strict\_locker the time we are working with savingsAcct\_and then restore the ownership on unique\_lock.

```
void AccountManager::AMoreComplicatedChecking2Savings(int amount) {
    unique_lock<AccountManager> guard1(*this);
    if (some_condition()) {
        guard1.lock();
    }
    {
        strict_locker<AccountManager> guard(guard1);
        checkingAcct_.get(guard).Withdraw(amount);
        savingsAcct_.get(guard).Deposit(amount);
    }
    guard1.unlock();
}
```

In order to make this code compilable we need to store either a Lockable or a unique\_lock<Lockable> reference depending on the constructor. Store which kind of reference we have stored, and in the destructor call either to the Lockable unlock or restore the ownership.

This seams too complicated to me. Another possibility is to define a nested strict locker class. The drawback is that instead of having only one strict locker we have two and we need either to duplicate every function taking a strictlock or make these function templates functions. The problem with template functions is that we don't profit anymore of the C++ type system. We must add some static metafunction that check that the Locker parameter is a strict locker. The problem is that we can not really check this or can we? The is\_strict\_locker metafunction must be specialized by the strict locker developer. We need to belive it "sur parolle". The advantage is that now we can manage with more than two strict lockers without changing our code. This is really nice.



Now we need to state that both classes are strict\_lockers.

```
template <typename Locker>
struct is_strict_locker : mpl::false_ {};

template <typename Lockable>
struct is_strict_locker<strict_locker<Lockable> > : mpl::true_ {}

template <typename Locker>
struct is_strict_locker<nested_strict_locker<Locker> > : mpl::true_ {}
```

Well let me show how this nested\_strict\_locker class looks like and the impacts on the externally\_locked class and the AccountManager::AMoreComplicatedFunction function.

First nested\_strict\_locker class will store on a temporary lock the Locker, and transfer the lock ownership on the constructor. On destruction he will restore the ownership. Note also that the Locker needs to have already a reference to the mutex otherwise an exception is thrown and the use of the locker\_traits.

```
template <typename Locker >
class nested_strict_locker
     BOOST_CONCEPT_ASSERT((MovableLockerConcept<Locker>));
public:
    typedef typename lockable_type<Locker>::type lockable_type;
    typedef typename syntactic_lock_traits<lockable_type>::lock_error lock_error;
    nested_strict_locker(Locker& locker)
       : locker_(locker) 2
        , tmp_locker_(locker.move()) 3
       #ifndef BOOST_SYNCHRO_STRCIT_LOCKER_DONT_CHECK_OWNERSHIP 4
       if (tmp_locker_.mutex()==0) {
           locker_=tmp_locker_.move(); 6
           throw lock_error();
       #endif
       if (!tmp_locker_) tmp_locker_.lock(); 6
    ~nested_strict_locker() {
       locker_=tmp_locker_.move();
    typedef bool (nested_strict_locker::*bool_type)() const;
    operator bool_type() const { return &nested_strict_locker::owns_lock; }
    bool operator!() const { return false; }
    bool owns_lock() const { return true; }
    const lockable_type* mutex() const { return tmp_locker_.mutex(); }
    bool is_locking(lockable_type* 1) const { return l==mutex(); }
   BOOST_ADRESS_OF_DELETE(nested_strict_locker)
    BOOST_HEAP_ALLOCATEION_DELETE(nested_strict_locker)
    BOOST_COPY_CONSTRUCTOR_DELETE(nested_strict_locker) 9
    BOOST_COPY_ASSIGNEMENT_DELETE(nested_strict_locker)  
private:
    Locker& locker_;
    Locker tmp_locker_;
};
```

Name the lockable type locked by Locker



- 2 Store reference to locker
- **3** Move ownership to temporaty locker
- Define BOOST\_SYNCHRO\_EXTERNALLY\_LOCKED\_DONT\_CHECK\_OWNERSHIP if you don't want to check locker ownership
- 6 Rollback for coherency purposes
- 6 ensures it is locked
- Move ownership to nesting locker
- 3 disable default construction
- **9** disable copy construction
- disable copy asignement

The externally\_locked get function is now a template function taking a Locker as parameters instead of a strict\_locker. We can add test in debug mode that ensure that the Lockable object is locked.

```
template <typename T, typename Lockable>
class externally_locked_any {
public:
   // ... as before
   template <class Locker>
   T& get(Locker& locker) {
       BOOST_CONCEPT_ASSERT((StrictLockerConcept<Locker>));
       BOOST_STATIC_ASSERT((is_same<Lockable,
              typename lockable_type<Locker>::type>::value)); 2
#ifndef BOOST_SYNCHRO_EXTERNALLY_LOCKED_DONT_CHECK_OWNERSHIP  
       if (! locker ) throw lock_error(); 4
#endif
#ifndef BOOST_SYNCHRO_EXTERNALLY_LOCKED_DONT_CHECK_SAME
       if (!locker.is_locking(&lockable_)) throw lock_error();
#endif
       return obj_;
};
```

- locker is a strict locker "sur parolle"
- **2** that locks the same type
- define BOOST\_SYNCHRO\_EXTERNALLY\_LOCKED\_NO\_CHECK\_OWNERSHIP if you don't want to check locker ownership
- 4 run time check throw if no locked

The AccountManager::AMoreComplicatedFunction function needs only to replace the strict\_locker by a nested\_strict\_locker.



```
void AccountManager::AMoreComplicatedChecking2Savings(int amount) {
    unique_lock<AccountManager> guard1(*this);
    if (some_condition()) {
        guard1.lock();
    }
    {
        nested_strict_locker<unique_lock<AccountManager> > guard(guard1);
        checkingAcct_.get(guard).Withdraw(amount);
        savingsAcct_.get(guard).Deposit(amount);
    }
    guard1.unlock();
}
```

### References

Toward Simplified Parallel Support in C++

Justin E. Gottschlich & Paul J. Rogers, 2009 - Not yet published

N1833 - Preliminary Threading Library Proposal for TR2 Kevlin Henney, 2005

More C++ Threading - From Procedural to Generic, by Example

Kevlin Henney

C++ Threading - A Generic-Programming Approach

Kevlin Henney, April 16, 2004

Multithreading and the C++ Type

Andrei Alexandrescu, Febraury 8, 2002

**System** 

volatile - Multithreaded Program-

Andrei Alexandrescu, Febraury 1, 2001

mer's Best Friend

Asynchronous C++

Kevlin Henney, September 9, 1996.

An OO Encapsulation of Lightweight OS Concurrency Mechanisms in the ACE Toolkit

Douglas C. Schmidt

ACE

Douglas C. Schmidt

# **Glossary**

lockable .

reentrancy .

lock .

locker .

lifetime

scope .



# Reference

### **Lockables**

Header <boost/synchro/lockable\_traits.hpp>

```
namespace boost { namespace synchro {
    struct mono_threaded_tag;
    struct multi_threaded_tag;
    struct multi_process_tag;
    template <typename Lockable> struct scope_tag;
    template <typename Lockable> struct is_mono_threaded;
    template <typename Lockable> struct is_multi_threaded;
    template <typename Lockable> struct is_multi_process;
    struct process_lifetime_tag;
    struct kernel_lifetime_tag;
    struct filesystem_lifetime_tag;
    template <typename Lockable> struct lifetime_tag;
    struct anonymous_tag;
    struct named_tag;
    template <typename Lockable> struct naming_tag;
    struct exclusive_lock_tag;
    struct sharable lock tag;
    struct upgradable_lock_tag;
    template <typename Lockable> struct category_tag;
    template <typename Lockable> struct is_exclusive_lock;
    template <typename Lockable> struct is_sharable_lock;
    template <typename Lockable> struct is_upgradable_lock;
    struct non_recursive_tag;
    struct recursive_tag;
    template <typename Lockable> struct reentrancy_tag;
    template <typename Lockable> struct is_recursive_lock;
    struct hasnt_timed_interface_tag;
    struct has_timed_interface_tag;
    template <typename Lockable> struct timed_interface_tag;
    template <typename Lockable> struct has_timed_interface;
    template <typename Locker> struct lockable_type;
    template <typename Lockable> struct best_condition;
    template <typename Lockable> struct best_condition_any;
    template <typename Lockable> struct scoped_lock_type;
    template <typename Lockable> struct unique_lock_type;
    template <typename Lockable> struct shared_lock_type;
    template <typename Lockable> struct upgrade_lock_type;
    template <typename Lockable> struct lock_error_type;
```



```
template <typename Lockable> struct move_object_type;

template <typename Lockable> struct defer_lock_type;
template <typename Lockable> struct adopt_lock_type;
template <typename Lockable> struct try_to_lock_type;

template
template
template
template<
typename Scope=multi_threaded_tag,
typename Cathegory=exclusive_lock_tag,
typename Reentrancy=non_recursive_tag,
typename TimedInterface=has_timed_interface_tag,
typename Lifetime=typename default_lifetime<Scope>,
typename Naming=anonymous_tag,
typename Base=void
> struct lock_traits_base;

}}
```

#### Template Class has\_timed\_interface

#### **Synopsis Description**

Class is\_exclusive

**Synopsis Description** 

Class is\_shared

**Synopsis Description** 

Class is\_recursive

**Synopsis Description** 

Class is\_mono\_threaded

**Synopsis Description** 

Class is\_multi\_threaded

**Synopsis Description** 

Class is\_multi\_process

**Synopsis Description** 

Class mutex\_type

**Synopsis Description** 



```
Class scoped_lock
```

**Synopsis Description** 

Class unique\_lock

**Synopsis Description** 

Class shared\_lock

**Synopsis Description** 

Class upgrade\_lock

**Synopsis Description** 

Class lock\_error

**Synopsis Description** 

Class moved\_object

**Synopsis Description** 

Class lock\_error2

**Synopsis Description** 

Class lock\_error3

**Synopsis Description** 

Class lock\_error4

**Synopsis Description** 

Class lock\_traits

**Synopsis** 

```
template<typename Lockable>
struct lock_traits;
   typedef Lockable
                               mutex_type;
                               scoped_lock;
   typedef unspecified
   typedef unspecified
                                  unique_lock;
   typedef unspecified
                                  shared_lock;
   typedef unspecified
                                  upgrade_lock;
   typedef unspecified
                                     lock_error;
   typedef unspecified
                             moved_object;
   static const unspecified
                              defer_lock();
   static const unspecified
                              adopt_lock();
   static const unspecified
                                try_to_lock();
};
```

**Description** Lock Traits characterise lockable types.

 ${\tt nested\_strict\_locker}\ public\ member\ types$ 

1. ;



# Header <boost/synchro/lockable\_concepts.hpp>

Lockable concepts.

```
template <typename Lockable> struct LockableConcept;
template <typename Lockable> struct TimedLockableConcept;
template <typename Lockable> struct ShareLockableConcept;
template <typename Lockable> struct UpgradeLockableConcept;
```

#### Template Class LockableConcept<>

The boost::mutex and boost:interprocess mutex family classes are a non-polymorphic classes that encapsulates a system primitive and portion of C API. Clearly, many of the synchronisation primitives support common operations, and hence a Concept. The ExclusiveLockable class can be used with the Boost.ConceptCheck in templates that work with a exclusive synchronisation.

LockableConcept object supports the basic features required to delimit a critical region. Supports the basic lock, unlock and try\_lock functions and defines the lock traits

```
template <typename Lockable>
struct LockableConcept {
   typedef typename category_tag<Lockable>::type category;
   typedef typename timed_interface_tag<Lockable>::type timed_interface;
   typedef typename reentrancy_tag<Lockable>::type reentrancy;
   typedef typename scope_tag<Lockable>::type scope;
   typedef typename lifetime_tag<Lockable>::type lifetime;
   typedef typename naming_tag<Lockable>::type naming;

BOOST_CONCEPT_USAGE(LockableConcept) {
    lockable::lock(1);
    lockable::unlock(1);
    lockable::try_lock(1);
   }
   Lockable& 1;
};
```

#### Template Class TimedLockableConcept<>

TimedLockableConcept object extends ExclusiveLockConcept with the timed\_lock function

```
template <typename Lockable>
struct TimedLockableConcept {
   BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));

BOOST_CONCEPT_USAGE(TimedLockableConcept) {
    lockable::lock_until(1, t);
    lockable::lock_for(1, boost::chrono::seconds(1));
    lockable::try_lock_until(1, t);
    lockable::try_lock_for(1, boost::chrono::seconds(1));
  }
  Lockable& 1;
  boost::chrono::system_clock::time_point t;
};
```

#### Template Class ShareLockableConcept<>

ShareLockableConcept object extends ExclusiveTimedLockConcept with the lock\_shared, timed\_lock\_shared, try\_lock\_shared and unlock\_shared functions



```
template <typename Lockable>
struct ShareLockableConcept {
    BOOST_CONCEPT_ASSERT((TimedLockableConcept<Lockable>));

BOOST_CONCEPT_USAGE(ShareLockableConcept) {
    lockable::lock_shared(l);
    lockable::lock_shared_until(l, t);
    lockable::lock_shared_for(l, boost::chrono::seconds(1));
    lockable::try_lock_shared(l);
    lockable::try_lock_shared_until(l, t);
    lockable::try_lock_shared_for(l, boost::chrono::seconds(1));
    lockable::unlock_shared(l);
    lockable::unlock_shared(l);
}
Lockable& l;
boost::chrono::system_clock::time_point t;
};
```

#### Template Class UpgradeLockableConcept<>

UpgradeLockableConcept object extends SharableLockableConcept with the lock\_upgrade, timed\_lock\_upgrade, unlock\_upgrade\_and\_lock, unlock\_and\_lock\_shared and unlock\_upgrade\_and\_lock\_shared functions.

```
template <typename Lockable>
struct UpgradeLockableConcept {
    BOOST_CONCEPT_ASSERT((ShareLockableConcept<Lockable>));
    BOOST_CONCEPT_USAGE(UpgradeLockableConcept) {
        lockable::lock_upgrade(1);
        //lockable::lock_upgrade_until(1, t);
        //lockable::lock_upgrade_for(1, boost::chrono::seconds(1));
        lockable::try_lock_upgrade(1);
        //lockable::try_lock_upgrade_until(1, t);
        //lockable::try_lock_upgrade_for(1,boost::chrono::seconds(1));
        lockable::unlock_upgrade_and_lock(1);
        lockable::unlock_and_lock_upgrade(1);
        lockable::unlock_and_lock_shared(1);
        lockable::unlock_upgrade_and_lock_shared(1);
   Lockable& 1;
   boost::chrono::system_clock::time_point t;
};
```



# Header <boost/synchro/lock\_generator.hpp>

```
namespace boost { namespace synchro {
    template<typename Scope>
    struct default_lifetime {
        typedef see_below type;
    }
    template<
        typename Scope=multi_threaded_tag,
        typename Category=exclusive_lock_tag,
        typename Reentrancy=non_recursive_tag,
        typename TimedInterface=has_timed_interface_tag,
        typename Lifetime=typename default_lifetime<Scope>,
        typename Naming=anonymous_tag
>
    struct find_best_lock{
        typedef see_below type;
    }
}
```

#### Metafunction default\_lifetime<>

Metafunction that returns the default lifetime depending on the Scope.

```
template<typename Scope> struct default_lifetime;
template<> struct default_lifetime<multi_threaded_tag> {
    typedef process_lifetime_tag type;
};
template<> struct default_lifetime<multi_process_tag> {
    typedef kernel_lifetime_tag type;
};
```

Expression: default\_lifetime<Scope>::type

Return type: A lifetime tag.

Complexity: constant.

#### Table 1. default\_lifetime relationship

Scope	default_lifetime <scope>::type</scope>		
multi_threaded_tag	process_lifetime_tag		
multi_process_tag	kernel_lifetime_tag		



#### Metafunction find\_best\_lock<>

```
template<
    typename Scope=multi_threaded_tag,
    typename Category=exclusive_lock_tag,
    typename Reentrancy=non_recursive_tag,
    typename TimedInterface=has_timed_interface_tag,
    typename Lifetime=typename default_lifetime<Scope>,
    typename Naming=anonymous_tag
>
struct find_best_lock{
    typedef see_below type;
}
```

Expression: find\_best\_lock<...>::type

Return type: A model of Lockable.

Complexity: constant.

The library defines already the following matchings:

#### Table 2. find\_best\_lock relationship

Scope	Category	Reen- trancy	TimedInter- face	Lifetime	Naming	find_best_lock<>::type
multi_threaded_tag	exclus- ive_lock_tag	non_re- curs- ive_tag	h a s - nt_timed_in- terface_tag	pro- cess_life- time_tag	anonym- ous_tag	boost::synchro::thread_mu- tex
multi_threaded_tag	exclus- ive_lock_tag	recurs- ive_tag	h a s - nt_timed_in- terface_tag	pro- cess_life- time_tag	anonym- ous_tag	boost::synchro::thread_recursive_mutex
multi_threaded_tag	exclus- ive_lock_tag	non_re- curs- ive_tag	has_timed_in- terface_tag	pro- cess_life- time_tag	anonym- ous_tag	b o o s t : : s y n - chro::thread_timed_mutex
multi_threaded_tag	*	non_re- curs- ive_tag	*	pro- cess_life- time_tag	anonym- ous_tag	b o o s t : : s y n - chro::thread_shared_mutex
multi_process_tag	exclus- ive_lock_tag	non_re- curs- ive_tag	*	k e r - nel_life-time_tag	anonym- ous_tag	boost::synchro::interpro- cess_mutex
multi_process_tag	exclus- ive_lock_tag	recurs- ive_tag	*	k e r - nel_life-time_tag	anonym- ous_tag	boost::synchro::interpro- cess_recursive_mutex
multi_process_tag	*	non_re- curs- ive_tag	*	pro- cess_life- time_tag	anonym- ous_tag	boost::synchro::interpro- cess_upgradable_mutex



# Header <boost/synchro/lockable\_adapter.hpp>

```
namespace boost { namespace synchro {
    template <typename Lockable> class exclusive_lockable_adapter;
    template <typename TimedLock> class timed_lockable_adapter;
    template <typename SharableLock> class shared_lockable_adapter;
    template <typename UpgradableLock> class upgrade_lockable_adapter;
    template <
        typename Lockable,
        typename category,
        typename timed_interface
    > struct lockable_adapter;
}
```

#### Template Class exclusive\_lockable\_adapter<>

```
template <typename Lockable>
class exclusive_lockable_adapter {
public:
    BOOST_COPY_CONSTRUCTOR_DELETE(exclusive_lockable_adapter)
    BOOST_COPY_ASSIGNEMENT_DELETE(exclusive_lockable_adapter)
    typedef Lockable lockable_type;
    typedef typename scope_tag<Lockable>::type scope;
    typedef typename category_tag<Lockable>::type category;
    typedef typename reentrancy_tag<Lockable>::type reentrancy;
    typedef typename timed_interface_tag<Lockable>::type timed_interface;
    typedef typename lifetime_tag<Lockable>::type lifetime;
    typedef typename naming_tag<Lockable>::type naming;
    exclusive_lockable_adapter() {}
    void lock();
    void unlock();
   bool try_lock();
};
```

#### Template Class timed\_lockable\_adapter<>

```
template <typename TimedLock>
class timed_lockable_adapter : public exclusive_lockable_adapter<TimedLock> {
public:
    timed_lockable_adapter() {}

    bool try_lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    bool try_lock_for(TimeDuration const & relative_time);

    void lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const & relative_time);
};
```



#### Template Class shared\_lockable\_adapter<>

```
template <typename SharableLock>
class shared_lockable_adapter : public timed_lockable_adapter<SharableLock> {
public:
    shared_lockable_adapter() {}
    void lock_shared();
    bool try_lock_shared();
    void unlock_shared();

    bool try_lock_shared_until(system_time const& t);
    template<typename TimeDuration>
    bool try_lock_shared_for(TimeDuration const& t);

    template<typename TimeDuration>
    void lock_shared_for(TimeDuration const& t);
    void lock_shared_until(system_time const& t);
};
```

#### Template Class upgrade\_lockable\_adapter<>

```
template <typename UpgradableLock>
class upgrade_lockable_adapter : public shared_lockable_adapter<UpgradableLock>{
public:
    upgrade_lockable_adapter();
    void lock_upgrade();
   bool try_lock_upgrade();
    void unlock_upgrade();
    void unlock_upgrade_and_lock();
    void unlock_and_lock_upgrade();
    void unlock_and_lock_shared();
    void unlock_upgrade_and_lock_shared();
    bool try_lock_upgrade_until(system_time const&t);
    template<typename TimeDuration>
    bool try_lock_upgrade_for(TimeDuration const&t);
    void lock_upgrade_until(system_time const&t);
    template<typename TimeDuration>
    void lock_upgrade_for(TimeDuration const&t);
};
```

# **Generic Free Functions on Lockable**

# Header <boost/sychro/lockable/lock.hpp>

Defines a free function lock which locks the Lockable passed as parameter. The default implementation applies the lock member function to the Lockable. A user adapting another Lockable could need to specialize the lock free function if the Lockable do not provides a lock member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the lock member function, lock calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct lock {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template<typename Lockable> struct lock {
            static typename result_of::template lock<Lockable>::type apply( Lockable& lockable );
        };
    }

    template <typename Lockable>
    typename result_of::template lock<Lockable>::type lock(Lockable& lockable);
}}
```

### Header <boost/sychro/lockable/unlock.hpp>

Defines a free function unlock which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock member function to the Lockable. A user adapting another Lockable could need to specialize the unlock free function if the Lockable do not provides a unlock member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock member function, unlock calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct unlock {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
        struct unlock {
            static typename result_of::template unlock<Lockable>::type apply( Lockable& lockable );
        };
    }

    template <typename Lockable>
        typename result_of::template unlock<Lockable>::type unlock(Lockable& lockable);
}}
```

### Header <boost/sychro/lockable/try\_lock.hpp>

Defines a free function try\_lock which try to lock the Lockable passed as parameter and return false if unsucessful. The default implementation applies the try\_lock member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock free function if the Lockable do not provides a try\_lock member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock member function, try\_lock calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationwork\_around\_. So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct try_lock {
            typedef bool type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct try_lock {
            static typename result_of::template try_lock<Lockable>::type apply( Lockable& lock_Jable );
    };
    }

    template <typename Lockable>
    typename result_of::template try_lock<Lockable>::type
    try_lock(Lockable& lockable);
}}
```

# Header <boost/sychro/lockable/try\_lock\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace unlock\_upgrade\_and\_lock\_until. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
   namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct try_lock_until {
            typedef bool type;
        };
    namespace partial_specialization_workaround {
        template <typename Lockable, class Clock, class Duration >
        struct try_lock_until
            static typename result_of::template try_lock_until<Lockable,Clock,Duration>::type
            apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
        };
    template <typename Lockable, class Clock, class Duration >
    typename result_of::template try_lock_until<Lockable,Clock,Duration>::type
    try_lock_until(Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time);
} } }
```

### Header <boost/sychro/lockable/try\_lock\_for.hpp>

Defines a free function try\_lock\_for which tries to locks the Lockable passed as parameter until a given time is elapsed. The default implementation applies the try\_lock\_for member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock\_for free function if the Lockable do not provides a try\_lock\_for member function with the same prototype.



As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock\_for member function, try\_lock\_for calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround . So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Rep, class Period >
        struct try_lock_for {
            typedef bool type;
        };
    namespace partial_specialization_workaround {
        template <typename Lockable, class Rep, class Period >
        struct try_lock_for {
            static typename result_of::template try_lock_for<Lockable,Rep,Period>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    }
    template <typename Lockable, class Rep, class Period >
    typename result_of::template try_lock_for<Lockable,Rep,Period>::type
    try_lock_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
} } }
```

### Header <boost/sychro/lockable/lock\_until.hpp>

Defines a free function lock\_until which lock the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_until free function if the \_\_lockuntilable\_ do not provides a lock\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_until</code> member function, <code>lock\_until</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specializationwork\_around\_</code>. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct lock_until {
            typedef void type;
        };
    namespace partial_specialization_workaround {
        template <typename Lockable, class Clock, class Duration >
        struct lock_until {
            static typename result_of::template lock_until<Lockable,Clock,Duration>::type
            apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
        };
    template <typename Lockable, class Clock, class Duration >
    typename result_of::template lock_until<Lockable,Clock,Duration>::type
    lock_until(Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time);
} } }
```



# Header <boost/sychro/lockable/lock\_for.hpp>

Defines a free function lock\_for which lock the Lockable passed as parameter until a given time is elapsed. The default implementation applies the lock\_for member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_for free function if the Lockable do not provides a lock\_for member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_for</code> member function, <code>lock\_for</code> calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationwork\_around\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct lock_for {
            typedef void type;
        };
    }

namespace partial_specialization_workaround {
    template <typename Lockable, class Rep, class Period >
        struct lock_for {
            static typename result_of::template lock_for<Lockable>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    }

template <typename Lockable, class Rep, class Period >
        typename result_of::template lock_for<Lockable>::type
        lock_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
}}
```

# Header <boost/sychro/lockable/lock\_shared.hpp>

Defines a free function lock\_shared which lock shared the Lockable passed as parameter. The default implementation applies the lock\_shared member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared free function if the Lockable do not provides a lock\_shared member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared</code> member function, <code>lock\_shared</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround</code>. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct lock_shared {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
        struct lock_shared {
            static typename result_of::template lock_shared<Lockable>::type apply( Lockable& lock_dable );
        };
    }

    template <typename Lockable>
    typename result_of::template lock_shared<Lockable>::type lock_shared(Lockable& lockable);
}}
```



# Header <boost/sychro/lockable/unlock\_shared.hpp>

Defines a free function unlock\_shared which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_shared member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_shared free function if the Lockable do not provides a unlock\_shared member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_shared member function, unlock\_shared calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround . So the user can specialize partially this class.

# Header <boost/sychro/lockable/try\_lock\_shared.hpp>

Defines a free function try\_lock\_shared which try to lock the Lockable passed as parameter and return false if unsucessful. The default implementation applies the try\_lock\_shared member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock\_shared free function if the Lockable do not provides a try\_lock\_shared member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock\_shared member function, try\_lock\_shared calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround . So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct try_lock_shared_shared {
            typedef bool type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct try_lock_shared {
                  static typename result_of::template try_lock_shared<Lockable>::type apply( Lock_Jable& lockable );
        };
    }

    template <typename Lockable>
        typename result_of::template try_lock_shared<Lockable>::type
    try_lock_shared(Lockable& lockable);
}}
```



# Header <boost/sychro/lockable/try\_lock\_shared\_for.hpp>

Defines a free function try\_lock\_shared\_for which tries to locks the Lockable passed as parameter until a given time is elapsed. The default implementation applies the try\_lock\_shared\_for member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock\_shared\_for free function if the Lockable do not provides a try\_lock\_shared\_for member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock\_shared\_for member function, try\_lock\_shared\_for calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Rep, class Period >
        struct try_lock_shared_for {
            typedef bool type;
        };
    }

    namespace partial_specialization_workaround {
        template <typename Lockable, class Rep, class Period >
        struct try_lock_shared_for {
            static typename result_of::template try_lock_shared_for<Lockable,Rep,Period>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    }

    template <typename Lockable, class Rep, class Period >
        typename result_of::template try_lock_shared_for<Lockable,Rep,Period>::type
        try_lock_shared_for(Lockable& lockable, const chrono::duration<Rep, Period>::type
        try_lock_shared_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
}}}
```

### Header <boost/sychro/lockable/lock\_shared\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround\_.</code> So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct lock_shared_until {
            typedef void type;
    }
    namespace partial_specialization_workaround {
        template <typename Lockable, class Clock, class Duration >
        struct lock_shared_until {
          static typename result_of::template lock_shared_until<Lockable,Clock,Duration>::type
            apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
        };
    }
    template <typename Lockable, class Clock, class Duration >
    typename result_of::template lock_shared_until<Lockable,Clock,Duration>::type
    lock_shared_until(Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time);
} } }
```

### Header <boost/sychro/lockable/lock\_shared\_for.hpp>

Defines a free function <code>lock\_shared\_for</code> which locks shared the <code>Lockable</code> passed as parameter until a given time is elepsed. The default implementation applies the <code>lock\_shared\_for</code> member function to the <code>Lockable</code>. A user adapting another <code>Lockable</code> could need to specialize the <code>lock\_shared\_for</code> free function if the <code>Lockable</code> do not provides a <code>lock\_shared\_for</code> member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_for</code> member function, <code>lock\_shared\_for</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround</code>. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Rep, class Period >
        struct lock_shared_for {
            typedef void type;
    }
    namespace partial_specialization_workaround {
        template <typename Lockable, class Rep, class Period >
        struct lock_shared_for {
            static typename result_of::template lock_shared_for<Lockable,Rep,Period>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    template <typename Lockable, class Rep, class Period >
    typename result_of::template lock_shared_for<Lockable,Rep,Period>::type
    lock_shared_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
} } }
```

# Header <boost/sychro/lockable/lock\_upgrade.hpp>

Defines a free function <code>lock\_upgrade</code> which lock upgrade the <code>Lockable</code> passed as parameter. The default implementation applies the <code>lock\_upgrade</code> member function to the <code>Lockable</code>. A user adapting another <code>Lockable</code> could need to specialize the <code>lock\_upgrade</code> free function if the <code>Lockable</code> do not provides a <code>lock\_upgrade</code> member function with the same prototype.



As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_upgrade</code> member function, <code>lock\_upgrade</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround</code>. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct lock_upgrade {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct lock_upgrade {
                 static typename result_of::template lock_upgrade<Lockable>::type apply( Lockable& lock_J
able );
    };
    }

    template <typename Lockable>
    typename result_of::template lock_upgrade<Lockable>::type
    lock_upgrade(Lockable& lockable);
}}
```

### Header <boost/sychro/lockable/unlock\_upgrade.hpp>

Defines a free function unlock\_upgrade which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_upgrade member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_upgrade free function if the Lockable do not provides a unlock\_upgrade member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_upgrade member function, unlock\_upgrade calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

# Header <boost/sychro/lockable/try\_lock\_upgrade.hpp>

Defines a free function try\_lock\_upgrade which try to lock the Lockable passed as parameter and return false if unsucessful. The default implementation applies the try\_lock\_upgrade member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock\_upgrade free function if the Lockable do not provides a try\_lock\_upgrade member function with the same prototype.



As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock\_upgrade member function, try\_lock\_upgrade calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct try_lock_upgrade_shared {
            typedef bool type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct try_lock_upgrade {
                  static typename result_of::template try_lock_upgrade<Lockable>::type apply( Lock_J able& lockable );
        };
    }

    template <typename Lockable>
        typename result_of::template try_lock_upgrade<Lockable>::type
        try_lock_upgrade(Lockable& lockable);
}
}}
```

# Header <boost/sychro/lockable/try\_lock\_upgrade\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace unlock\_upgrade\_and\_lock\_until. So the user can specialize partially this class.

```
{\tt namespace\ boost\ \{\ namespace\ synchro\ \{\ namespace\ lockable\ namespace\ lockable\ \{\ namespace\ lockable\ \{\ namespace\ lockable\ namespace\ lockable\ namespace\ lockable\ namespace\ 
              namespace result_of {
                              template <typename Lockable, class Clock, class Duration >
                               struct try_lock_upgrade_until {
                                             typedef bool type;
                               };
               }
               namespace partial_specialization_workaround {
                               template <typename Lockable, class Clock, class Duration >
                              struct try_lock_upgrade_until {
                                              static typename result_of::template try_lock_upgrade_until<Lockable,Clock,Dura-
tion>::type
                                              apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
                               };
               template <typename Lockable, class Clock, class Duration >
               typename result_of::template try_lock_upgrade_until<Lockable,Clock,Duration>::type
               try_lock_upgrade_until(Lockable& lockable, const chrono::time_point<Clock, DuraJ
tion>& abs_time);
} } }
```



### Header <boost/sychro/lockable/lock\_upgrade\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround</code>. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct lock_upgrade_until {
            typedef void type;
        };
    }

namespace partial_specialization_workaround {
    template <typename Lockable, class Clock, class Duration >
        struct lock_upgrade_until {
        static typename result_of::template lock_upgrade_until<Lockable,Clock,Duration>::type
        apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
    };
}

template <typename Lockable, class Clock, class Duration >
    typename result_of::template lock_upgrade_until<Lockable,Clock,Duration>::type
    lock_upgrade_until(Lockable& lockable, const chrono::time_point<Clock,Duration>& abs_time);
}}}
```

### Header <boost/sychro/lockable/lock\_upgrade\_for.hpp>

Defines a free function <code>lock\_upgrade\_for</code> which locks shared the <code>Lockable</code> passed as parameter until a given time is elepsed. The default implementation applies the <code>lock\_upgrade\_for</code> member function to the <code>Lockable</code>. A user adapting another <code>Lockable</code> could need to specialize the <code>lock\_upgrade\_for</code> free function if the <code>Lockable</code> do not provides a <code>lock\_upgrade\_for</code> member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_upgrade\_for</code> member function, <code>lock\_upgrade\_for</code> calls to the static operation apply on a class with the same name in the namespace <code>\_\_partial\_specialization\_workaround\_.</code> So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Rep, class Period >
        struct lock_upgrade_for {
            typedef void type;
    }
    namespace partial_specialization_workaround {
        template <typename Lockable, class Rep, class Period >
        struct lock_upgrade_for {
            static typename result_of::template lock_upgrade_for<Lockable,Rep,Period>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    }
    template <typename Lockable, class Rep, class Period >
    typename result_of::template lock_upgrade_for<Lockable,Rep,Period>::type
    lock_upgrade_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
} } }
```

# Header <boost/sychro/lockable/unlock\_and\_lock\_upgrade.hpp>

Defines a free function unlock\_and\_lock\_upgrade which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_and\_lock\_upgrade member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_and\_lock\_upgrade free function if the Lockable do not provides a unlock\_and\_lock\_upgrade member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_and\_lock\_upgrade member function, unlock\_and\_lock\_upgrade calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct unlock_and_lock_upgrade {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct unlock_and_lock_upgrade {
                static typename result_of::template unlock_and_lock_upgrade<Lockable>::type apply( Lock_Jable& lockable );
        };
    }

    template <typename Lockable>
    typename result_of::template unlock_upgrade<Lockable>::type unlock_and_lock_upgrade(Lockable& lockable);
}}
```

### **Header** <boost/sychro/lockable/unlock\_and\_lock\_shared.hpp>

Defines a free function unlock\_and\_lock\_shared which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_and\_lock\_shared member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_and\_lock\_shared free function if the Lockable do not provides a unlock\_and\_lock\_shared member function with the same prototype.



As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_and\_lock\_shared member function, unlock\_and\_lock\_shared calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct unlock_and_lock_shared {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct unlock_and_lock_shared {
                static typename result_of::template unlock_and_lock_shared<Lockable>::type apply( Lock_J able& lockable );
        };
    }

    template <typename Lockable>
    typename result_of::template unlock_and_lock_shared<Lockable>::type unlock_and_lock_shared(Lockable& lockable);
}}
}
```

### **Header** <boost/sychro/lockable/unlock\_upgrade\_and\_lock\_shared.hpp>

Defines a free function unlock\_upgrade\_and\_lock\_shared which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_upgrade\_and\_lock\_shared member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_upgrade\_and\_lock\_shared free function if the Lockable do not provides a unlock\_upgrade\_and\_lock\_shared member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_upgrade\_and\_lock\_shared member function, unlock\_upgrade\_and\_lock\_shared calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
{\tt namespace\ boost\ \{\ namespace\ synchro\ \{\ namespace\ lockable\ namespace\ lockable\ \{\ namespace\ lockable\ \{\ namespace\ lockable\ namespace\ lockable\ namespace\ lockable\ namespace\ 
                  namespace result of {
                                      template <typename Lockable> struct unlock_upgrade_and_lock_shared {
                                                         typedef void type;
                                      };
                   }
                   namespace partial_specialization_workaround {
                                      template< typename Lockable >
                                      struct unlock_upgrade_and_lock_shared {
                                                 static typename result_of::template unlock_upgrade_and_lock_shared<Lockable>::type ap |
ply( Lockable & lockable );
                                      };
                   template <typename Lockable>
                   typename result_of::template unlock_upgrade_and_lock_shared<Lockable>::type
                   unlock_upgrade_and_lock_shared(Lockable& lockable);
} } }
```

### Header <boost/sychro/lockable/unlock\_upgrade\_and\_lock.hpp>

Defines a free function unlock\_upgrade\_and\_lock which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_upgrade\_and\_lock member function to the Lockable. A user adapting another Lockable could



need to specialize the unlock\_upgrade\_and\_lock free function if the Lockable do not provides a unlock\_upgrade\_and\_lock member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_up-grade\_and\_lock member function, unlock\_upgrade\_and\_lock calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround . So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct unlock_upgrade_and_lock {
            typedef void type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct unlock_upgrade_and_lock {
                static typename result_of::template unlock_upgrade_and_lock<Lockable>::type apply( Lock_J able& lockable );
        };
    }

    template <typename Lockable>
    typename result_of::template unlock_upgrade_and_lock<Lockable>::type unlock_upgrade_and_lock(Lockable& lockable);
}}
```

### Header <boost/sychro/lockable/unlock\_upgrade\_and\_lock\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace unlock\_upgrade\_and\_lock\_until. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct lock_upgrade_until {
            typedef void type;
        };
    }
    namespace partial_specialization_workaround {
        template <typename Lockable, class Clock, class Duration >
        struct lock_upgrade_until
          static typename result_of::template lock_upgrade_until<Lockable,Clock,Duration>::type
            apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
        };
    template <typename Lockable, class Clock, class Duration >
    typename result_of::template lock_upgrade_until<Lockable,Clock,Duration>::type
   lock_upgrade_until(Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time);
} } }
```



# Header <boost/sychro/lockable/unlock\_upgrade\_and\_lock\_for.hpp>

Defines a free function unlock\_upgrade\_and\_lock\_for which locks shared the Lockable passed as parameter until a given time is elepsed. The default implementation applies the unlock\_upgrade\_and\_lock\_for member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_upgrade\_and\_lock\_for free function if the Lockable do not provides a unlock\_upgrade\_and\_lock\_for member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_upgrade\_and\_lock\_for member function, unlock\_upgrade\_and\_lock\_for calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
{\tt namespace\ boost\ \{\ namespace\ synchro\ \{\ namespace\ lockable\ namespace\ lockable\ \{\ namespace\ lockable\ \{\ namespace\ lockable\ namespace\ lockable\ namespace\ lockable\ namespace\ 
               namespace result_of {
                               template <typename Lockable, class Rep, class Period >
                               struct unlock_upgrade_and_lock_for {
                                              typedef void type;
                }
                namespace partial_specialization_workaround {
                               template <typename Lockable, class Rep, class Period >
                               struct unlock_upgrade_and_lock_for {
                                              static typename result_of::template unlock_upgrade_and_lock_for<Lockable,Rep,PeriJ
od>::type
                                              apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
                               };
                template <typename Lockable, class Rep, class Period >
                typename result_of::template unlock_upgrade_and_lock_for<Lockable,Rep,Period>::type
             unlock_upgrade_and_lock_for(Lockable& lockable, const chrono::duration<Rep, Period>& abs_time);
} } }
```

# Header <boost/sychro/lockable/try\_unlock\_upgrade\_and\_lock\_until.hpp>

Defines a free function lock\_shared\_until which locks shared the Lockable passed as parameter until a given time is reached. The default implementation applies the lock\_shared\_until member function to the Lockable. A user adapting another Lockable could need to specialize the lock\_shared\_until free function if the \_\_lock\_shared\_untilable\_ do not provides a lock\_shared\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the <code>lock\_shared\_until</code> member function, <code>lock\_shared\_until</code> calls to the static operation apply on a class with the same name in the namespace unlock\_upgrade\_and\_lock\_until. So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Clock, class Duration >
        struct try_unlock_upgrade_and_lock_until {
            typedef bool type;
        };
    }
    namespace partial_specialization_workaround {
        template <typename Lockable, class Clock, class Duration >
        struct try_unlock_upgrade_and_lock_until {
            static typename result_of::template try_unlock_upgrade_and_lock_until<Lock \lambda
able,Clock,Duration>::type
            apply( Lockable& lockable, const chrono::time_point<Clock, Duration>& abs_time );
    }
    template <typename Lockable, class Clock, class Duration >
   typename result_of::template try_unlock_upgrade_and_lock_until<Lockable,Clock,Duration>::type
   try_unlock_upgrade_and_lock_until(Lockable& lockable, const chrono::time_point<Clock, DuraJ
tion>& abs_time);
} } }
```

### **Header** <boost/sychro/lockable/try\_unlock\_upgrade\_and\_lock\_for.hpp>

Defines a free function try\_unlock\_upgrade\_and\_lock\_until which tries to locks the Lockable passed as parameter until a given time is elapsed. The default implementation applies the try\_unlock\_upgrade\_and\_lock\_until member function to the Lockable. A user adapting another Lockable could need to specialize the try\_unlock\_upgrade\_and\_lock\_until free function if the Lockable do not provides a try\_unlock\_upgrade\_and\_lock\_until member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_unlock\_upgrade\_and\_lock\_until member function, try\_unlock\_upgrade\_and\_lock\_until calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable, class Rep, class Period >
        struct try_unlock_upgrade_and_lock_until {
            typedef bool type;
        };
    namespace partial_specialization_workaround {
        template <typename Lockable, class Rep, class Period >
        struct try_unlock_upgrade_and_lock_until {
          static typename result_of::template try_unlock_upgrade_and_lock_until<Lockable,Rep,PeriJ
od>::type
            apply( Lockable& lockable, const chrono::duration<Rep, Period>& rel_time );
        };
    template <typename Lockable, class Rep, class Period >
    typename result_of::template try_unlock_upgrade_and_lock_until<Lockable,Rep,Period>::type
    try_unlock_upgrade_and_lock_until(Lockable& lockable, const chrono::duration<Rep, Peri-
od>& abs_time);
} } }
```



# Header <boost/sychro/lockable/unlock\_shared\_and\_lock.hpp>

Defines a free function unlock\_shared\_and\_lock which lock upgrade the Lockable passed as parameter. The default implementation applies the unlock\_shared\_and\_lock member function to the Lockable. A user adapting another Lockable could need to specialize the unlock\_shared\_and\_lock free function if the Lockable do not provides a unlock\_shared\_and\_lock member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the unlock\_shared\_and\_lock member function, unlock\_shared\_and\_lock calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.

```
{\tt namespace boost} \ \{ \ {\tt namespace synchro} \ \{ \ {\tt namespace lockable} \ \} \ \}
           namespace result_of {
                       template <typename Lockable> struct unlock_shared_and_lock {
                                  typedef void type;
                       };
           }
           namespace partial_specialization_workaround {
                       template< typename Lockable >
                       struct unlock_shared_and_lock {
                             static typename result_of::template unlock_shared_and_lock<Lockable>::type apply( Lock_l
able& lockable );
                       };
           template <typename Lockable>
           typename result_of::template unlock_shared_and_lock<Lockable>::type
           unlock_shared_and_lock(Lockable& lockable);
} } }
```

### **Header** <boost/sychro/lockable/try\_unlock\_shared\_and\_lock\_hpp.hpp>

Defines a free function try\_lock\_upgrade which try to lock the Lockable passed as parameter and return false if unsucessful. The default implementation applies the try\_lock\_upgrade member function to the Lockable. A user adapting another Lockable could need to specialize the try\_lock\_upgrade free function if the Lockable do not provides a try\_lock\_upgrade member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_lock\_upgrade member function, try\_lock\_upgrade calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround . So the user can specialize partially this class.



```
namespace boost { namespace synchro { namespace lockable {
    namespace result_of {
        template <typename Lockable> struct try_unlock_shared_and_lock {
            typedef bool type;
        };
    }

    namespace partial_specialization_workaround {
        template< typename Lockable >
            struct try_lock_upgrade {
                  static typename result_of::template try_lock_upgrade<Lockable>::type apply( Lock_J able& lockable );
        };
    }

    template <typename Lockable>
    typename result_of::template try_lock_upgrade<Lockable>::type
    try_lock_upgrade(Lockable& lockable);
}}
```

### **Header** <boost/sychro/lockable/try\_unlock\_shared\_and\_lock\_upgrade.hpp>

Defines a free function try\_unlock\_shared\_and\_lock\_upgrade which try to lock the Lockable passed as parameter and return false if unsucessful. The default implementation applies the try\_unlock\_shared\_and\_lock\_upgrade member function to the Lockable. A user adapting another Lockable could need to specialize the try\_unlock\_shared\_and\_lock\_upgrade free function if the Lockable do not provides a try\_unlock\_shared\_and\_lock\_upgrade member function with the same prototype.

As for the moment we can not partially specialize a function a trick is used: instead of calling directly to the try\_unlock\_shared\_and\_lock\_upgrade member function, try\_unlock\_shared\_and\_lock\_upgrade calls to the static operation apply on a class with the same name in the namespace \_\_partial\_specializationworkaround\_. So the user can specialize partially this class.



### **Generic Free Functions on Multiple Lockables**

### **Condition Lockables**

Header <boost/synchro/locker/condition\_safe.hpp>

Wraps a condition variable in order make public only the safe functions, and let the others accesible via a backdoor.

```
template <typename Condition> class condition_safe;
```

#### Template Class condition\_safe

```
template <class Condition>
class condition_safe {
public:
  typedef Condition condition;
  typedef condition_backdoor<Condition> backdoor;
    void notify_one();
    void notify_all();
};
```

### Header <boost/synchro/condition\_backdoor.hpp>

```
template <typename Condition> struct condition_backdoor;
```

### Template Class condition\_backdoor

Condition Backdoor template. Used by safe lockers as condition\_locker.

```
template <class Condition>
struct condition_backdoor {
 condition_backdoor(condition_safe<Condition>&cnd);
    template <typename Locker>
    void wait(Locker& lock);
    template <typename Locker>
    bool\ wait\_until(\texttt{Locker}\&\ lock,\ boost{::system\_time}\ const\&\ abs\_time);\\
    template<typename Locker, typename duration_type>
    bool wait_for(Locker& lock, duration_type const& rel_time);
    template <typename Locker, typename Predicate>
    void wait_when(Locker& lock, Predicate pred);
    template<typename Locker, typename predicate_type>
   bool\ wait\_when\_until(Locker\&\ lock,\ predicate\_type\ pred,\ boost::system\_time\ const\&\ abs\_time);\\
    template<typename Locker, typename predicate_type, typename duration_type>
    bool wait_when_for(Locker& lock, predicate_type pred, duration_type const& rel_time);
    template <typename Locker>
    void notify_one(Locker& lock);
    template <typename Locker>
    void notify_all(Locker& lock);
```



### Header <boost/synchro/condition\_lockable.hpp>

```
namespace boost { namespace synchro {
    template <typename Lockable, typename Condition>
    class condition_lockable
    typedef condition_lockable<thread_mutex> thread_condition_mutex;
    typedef condition_lockable<interprocess_mutex> interprocess_condition_mutex;
}}
```

#### Template Class condition\_lockable

Allows a condition variable to be associated with a Lockable. Treating condition locking as a property of Lockable rather than viceversa has the benefit of making clear how something is locked and accessed, as it were emphasising it in the first person.

Requiring the user of a condition variable to implement a while loop to verify a condition's predicate is potentially error prone. It can be better encapsulated by passing the predicate as a function object to the locking function.

```
template <
    typename Lockable=thread_mutex,
    class Condition=condition_safe<typename best_condition<Lockable>::type >
class condition_lockable {
    : public Lockable {
    BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
public:
    typedef Lockable lockable_type;
    typedef Condition condition;
    condition_lockable();
    ~condition_lockable();
    void relock_on(condition & cond);
    void relock_on_until(condition & cond, boost::system_time const& abs_time);
    template<typename duration_type>
    void relock_on_for(condition & cond, duration_type const& rel_time);
    template<typename Predicate>
    void relock_when(condition &cond, Predicate pred);
    template<typename Predicate>
    void relock_when_until(condition &cond, Predicate pred,
            boost::system_time const& abs_time);
    template<typename Predicate, typename duration_type>
    void relock_when_for(condition &cond, Predicate pred,
            duration_type const& rel_time);
private:
    friend class boost::condition_variable;
    friend class boost::condition_variable_any;
    friend class boost::interprocess::condition;
};
```

### **Lockers**

Header <boost/synchro/locker\_concepts.hpp>

Locker concepts.



```
namespace boost { namespace synchro {
    template <typename Locker> struct BasicLockerConcept;
    template <typename Locker> struct LockerConcept;
    template <typename Locker> struct TimedLockerConcept;
    template <typename Locker> struct UniqueLockerConcept;
    template <typename Locker> struct SharedLockerConcept;
    template <typename Locker> struct UpgradeLockerConcept;
    template <typename Locker> struct WovableLockerConcept;
}
```

### Template Class BasicLockerConcept<>

```
template <typename Locker>
struct BasicLockerConcept {
   typedef typename lockable_type<Locker>::type lockable_type;

BOOST_CONCEPT_USAGE(BasicLockerConcept) {
      const Locker l1(mtx_);
      if (l1.is_locking(mtx_)) return;
      if (l1.owns_lock()) return;
      if (l1) return;
      if (!11) return;
    }
   lockable_type mtx_;
   system_time t;
};
```

### Template Class LockerConcept<>

```
template <typename Locker>
struct LockerConcept {
    BOOST_CONCEPT_ASSERT((BasicLockerConcept<Locker>));
    typedef typename lockable_type<Locker>::type lockable_type;

BOOST_CONCEPT_USAGE(LockerConcept) {
        Locker 12(mtx_, defer_lock);
        Locker 13(mtx_, adopt_lock);
        Locker 14(mtx_, try_to_lock);
        locker 14(mtx_, try_to_lock);
        if (12.try_lock()) return;
        12.unlock();
        12.release();
    }
    lockable_type mtx_;
    system_time t;
};
```



### Template Class TimedLockerConcept<>

```
template <typename Locker>
struct TimedLockerConcept {
    BOOST_CONCEPT_ASSERT((LockerConcept<Locker>));
    typedef typename lockable_type<Locker>::type lockable_type;
    BOOST_CONCEPT_USAGE(TimedLockerConcept) {
        const Locker l1(mtx_);
       Locker 15(mtx_, t);
       Locker 16(mtx_, boost::posix_time::seconds(1));
        Locker 17(t, mtx_);
        Locker 18(boost::posix_time::seconds(1), mtx_);
        15.lock_until(t);
        15.lock\_for(boost::posix\_time::seconds(1));\\
        if (15.try_lock_until(t)) return;
        if (15.try_lock_for(boost::posix_time::seconds(1))) return;
    lockable_type mtx_;
    system_time t;
};
```

### Template Class UniqueLockerConcept<>

```
template <typename Locker>
struct UniqueLockerConcept {
    BOOST_CONCEPT_ASSERT((TimedLockerConcept<Locker>));

BOOST_CONCEPT_USAGE(UniqueLockerConcept) {
    }
};
```

#### Template Class SharedLockerConcept<>

```
template <typename Locker>
struct SharedLockerConcept {
   BOOST_CONCEPT_ASSERT((TimedLockerConcept<Locker>));

   BOOST_CONCEPT_USAGE(SharedLockerConcept) {
   }
};
```

### Template Class UpgradeLockerConcept<>

```
template <typename Locker>
struct UpgradeLockerConcept {
    BOOST_CONCEPT_ASSERT((TimedLockerConcept<Locker>));

    BOOST_CONCEPT_USAGE(UpgradeLockerConcept) {
    }
};
```



### Template Class MovableLockerConcept<>

```
template <typename Locker>
struct MovableLockerConcept {
    typedef typename lockable_type<Locker>::type lockable_type;
    BOOST_CONCEPT_ASSERT((LockerConcept<lockable_type>));

BOOST_CONCEPT_USAGE(MovableLockerConcept) {
        Locker l1(mtx_);
        Locker& 12(l1);
        Locker& 13(l1.move());
        BOOST_ASSERT((l2.mutex()!=&mtx_));
        l3.lock();
        l2 = 13.move();
    }
    lockable_type mtx_;
};
```

# Header <boost/synchro/locker/is\_strict\_locker.hpp>

### Metafunction is\_strict\_locker

```
template <typename Locker>
struct is_strict_locker {
   typedef unspecified value;
};
```

### Header <boost/synchro/locker/strict\_locker.hpp>

### Class strict\_locker

### **Synopsis**

namespace boost { namespace synchro {



```
template <typename Locker>
struct StrictLockerConcept {
    typedef typename lockable_type<Locker>::type lockable_type;
    BOOST_STATIC_ASSERT((is_strict_locker<Locker>::value));
    void f(Locker& l ) {
        BOOST_ASSERT((l.is_locking(lock)));
    BOOST_CONCEPT_USAGE(StrictLockerConcept) {
//
              Locker 1(lock);
//
              BOOST_ASSERT((1));
    lockable_type lock;
};
template <typename Lockable>
class strict_locker {
public:
    typedef Lockable lockable_type;
    typedef unspecified bool_type;
    explicit strict_locker(lockable_type& obj);
    ~strict_locker();
    operator bool_type() const;
    bool operator!() const;
    bool owns_lock() const;
    lockable_type* mutex() const;
    BOOST_ADRESS_OF_DELETE(strict_locker)
    BOOST_HEAP_ALLOCATION_DELETE()
    BOOST_DEFAULT_CONSTRUCTOR_DELETE(strict_locker) /*< disable default construction >*/
    BOOST_COPY_CONSTRUCTOR_DELETE(strict_locker) /*< disable copy construction >*/
    BOOST_COPY_ASSIGNEMENT_DELETE(strict_locker) /*< disable copy asignement >*/
};
template <typename Lockable>
struct is_strict_locker<strict_locker<Lockable> > : mpl::true_ {};
template <typename Locker > class nested_strict_locker {
      BOOST_CONCEPT_ASSERT((MovableLockerConcept<Locker>));
public:
    typedef typename lockable_type<Locker>::type lockable_type;
    typedef typename syntactic_lock_traits<lockable_type>::lock_error lock_error;
    nested_strict_locker(Locker& locker);
    ~nested_strict_locker();
    typedef bool (nested_strict_locker::*bool_type)() const;
    operator bool_type() const;
    bool operator!() const;
   bool owns_lock() const;
    const lockable_type* mutex() const;
   bool is_locking(lockable_type* 1) const;
    BOOST_ADRESS_OF_DELETE(nested_strict_locker)
    BOOST_HEAP_ALLOCATEION_DELETE(nested_strict_locker)
    BOOST_DEFAULT_CONSTRUCTOR_DELETE(strict_locker) /*< disable default construction >*/
```



```
BOOST_COPY_CONSTRUCTOR_DELETE(strict_locker) /*< disable copy construction >*/
BOOST_COPY_ASSIGNEMENT_DELETE(strict_locker) /*< disable copy asignement >*/
};

template <typename Locker>
struct is_strict_locker<nested_strict_locker<Locker> > : mpl::true_ {} ;

}}
```

#### **Description**

[Note strict\_locker is not a model of Lockable concept.]

#### strict\_locker template parameters

• Lockable: The exclusive lockable type used to synchronize exclusive access

#### strict\_locker public types

- lockable\_type: The exclusive lockable type used to synchronize exclusive access
- lock\_error: The exception type throw incase of errors
- bool\_type: The bool\_type of the safe\_bool idiom

#### nested\_strict\_locker public member functions

```
explicit strict_locker(lockable_type& obj);
```

```
~strict_locker();
```

- operator bool\_type() const;
- bool operator!() const;
- operator bool\_type() const;
- lockable\_type\* mutex() const;
- lockable\_type\* get\_lockable() const;

#### nested\_strict\_locker private and not defined member functions

```
strict_locker()
```

- strict\_locker(strict\_locker&);
- operator=(strict\_locker&);
- operator&();
- void\* operator new(std::size\_t)
- void\* operator new[](std::size\_t)
- void operator delete(void\*)
- void operator delete[](void\*)

### Class nested\_strict\_locker



```
template <typename Locker>
class nested_strict_locker : private boost::noncopyable {
public:
    typedef typename locker_traits<Locker>::bad_lock bad_lock;
   nested_strict_locker(Locker& lock);
    ~nested_strict_locker();
    typedef unspecified bool_type;
    operator bool_type() const;
   bool operator!() const
   bool owns_lock() const
   Mutex* mutex() const
private:
   strict_locker();
   BOOST_NON_ALIAS(strict_locker);
    BOOST_NON_HEAP_ALLOCATED();
};
```

#### **Description**

### Template Class nested\_strict\_locker

A reverse (or anti) locker.

#### **Synopsis**

#### **Description**

### Header <boost/synchro/locker/reverse\_locker.hpp>

```
template <typename Lockable>
class reverse_locker;
```

### Class reverse\_lock

This is an interesting adapter class that changes a Lockable into a reverse lockable, i.e.,lock on this class calls unlock on the lockable, and unlock on this class calls lock on the lock. One motivation for this class is when we temporarily want to unlock a lock (which we have already locked) but then re-lock it soon after.

#### **Synopsis**

```
template <typename Lockable>
class reverse_locker
{
    reverse_locker(Lockable& mtx);
    ~reverse_locker();

protected:
    Lockable& mtx_;
};
```

### Header <boost/synchro/locker/nested\_reverse\_locker.hpp>

```
template <typename Locker>
class nested_reverse_locker;
```



### Class nested\_reverse\_locker

This is an interesting adapter class that changes a locker into a reverse locker, i.e., unlock on construction and lock on destruction. One motivation for this class is when we temporarily want to unlock a lock (locked by another locker) but then re-lock it soon after.

#### **Synopsis**

template <typename Locker> class nested\_reverse\_locker: boost::noncopyable { BOOST\_CONCEPT\_ASSERT((MovableLocker-Concept<Locker>)); public: explicit nested\_reverse\_locker(Locker& locker); ~nested\_reverse\_locker(); };

### Header <boost/synchro/locker/condition\_locker.hpp>

```
template <typename Condition> struct condition_backdoor;
template <typename Condition> class condition_safe;
template <typename Lockable, typename Condition>
class condition_unique_locker
template <typename Lockable, typename Condition>
class condition_shared_locker

template <typename Lockable, typename Condition>
class condition_unique_lockable
template <typename Lockable, typename Condition>
class condition_unique_lockable
```

#### Template Class condition\_backdoor

```
template <class Condition>
struct condition_backdoor {
condition_backdoor(condition_safe<Condition>&cnd);
    template <typename Locker>
    void wait(Locker& lock);
    template <typename Locker>
    bool wait_until(Locker& lock, boost::system_time const& abs_time);
    template<typename Locker, typename duration_type>
   bool wait_for(Locker& lock, duration_type const& rel_time);
    template <typename Locker, typename Predicate>
    void wait_when(Locker& lock, Predicate pred);
    template<typename Locker, typename predicate_type>
   bool wait_when_until(Locker& lock, predicate_type pred, boost::system_time const& abs_time);
    template<typename Locker, typename predicate_type, typename duration_type>
    bool wait_when_for(Locker& lock, predicate_type pred, duration_type const& rel_time);
    template <typename Locker>
    void notify_one(Locker& lock);
    template <typename Locker>
    void notify_all(Locker& lock);
};
```

#### Template Class condition\_safe

```
template <class Condition>
class condition_safe {
public:
  typedef Condition condition;
  typedef condition_backdoor<Condition> backdoor;
    void notify_one();
    void notify_all();
};
```



### Template Class condition\_unique\_locker

template < typename Lockable, class Condition=condition\_safe<typename best\_condition<Lockable>::type > > class condition\_unique\_locker : protected unique\_lock<Lockable> { BOOST\_CONCEPT\_ASSERT((LockableConcept<Lockable>)); public: typedef Lockable lockable\_type; typedef Condition condition;

```
explicit condition_unique_locker(lockable_type& obj);
condition_unique_locker(lockable_type& obj, condition &cond);
template <typename Predicate>
condition_unique_locker(lockable_type& obj, condition &cond, Predicate pred);
~condition_unique_locker();
typedef bool (condition_unique_locker::*bool_type)() const;
operator bool_type() const;
bool operator!() const;
bool owns_lock() const;
bool is_locking(lockable_type* 1) const;
void relock_on(condition & cond);
void relock_until(condition & cond, boost::system_time const& abs_time);
template<typename duration_type>
void relock_on_for(condition & cond, duration_type const& rel_time);
template<typename Predicate>
void relock_when(condition &cond, Predicate pred);
template<typename Predicate>
void relock_when_until(condition &cond, Predicate pred,
 boost::system_time const& abs_time);
template<typename Predicate, typename duration_type>
void relock_when_for(condition &cond, Predicate pred,
  duration_type const& rel_time);
/*< no possibility to unlock without blocking on wait... >*/
```

**}**;

### Header <boost/synchro/locker/externally\_locked.hpp>

### Template Class externally\_locked

#### **Synopsis**

```
template <class T, class Lockable>
class externally_locked {
public:
    externally_locked(Lockable& owner);
    externally_locked(const T& obj, Lockable& own);

    template <typename Locker>
    T& get(Locker& locker);
    void set(const T& obj, Lockable& owner);
};
```

**Description** externally\_locked cloaks an object of type T, and actually provides full access to that object through the get and set member functions, provided you pass a reference to a strict\_locker<Lockable> object.

#### externally\_locked template parameters

• T: the type locked externally



• Lockable: The lockable type used to synchronize the access to a T instance

#### externally\_locked public member functions

• template <typename Locker> T& get(Locker& locker);

**Requires:** mpl:and\_<is\_strict\_locker<Locker>, is\_same<lockable\_type\_trait<Locker>, Lockable>.

**Returns:** a reference to the type locked externally.

**Throws:** lock\_error when the locker do not owns the lockable instance

• void set(const T& obj, Lockable& owner);

**Effect:** reinit the type and lockable references with the given values.

Example: See

Header <boost/synchro/locker/locking\_ptr.hpp>

### Class locking\_ptr

#### **Synopsis**

```
template <typename T, typename Lockable>
class locking_ptr : private boost::noncopyable {
public:
    typedef T value_type;
    typedef Lockable mutex_type;

    locking_ptr(volatile value_type& obj, mutex_type& mtx);
    ~locking_ptr();

    value_type& operator*();
    const value_type& operator*() const;
    value_type* operator->();
    const value_type* operator->() const;
};
```

#### Description

The locking\_ptr overloads operator-> to return a temporary object that will perform the locking. This too provides an operator->. Calls to operator-> are automatically chained by the compiler until a raw pointer type is returned. In pointer's operator-> the lock is applied and in its destructor, called at the end of a full expression, it is released.



### Warning

Programmers should be careful about attempting to access the same object twice in a statement using <code>locking\_ptr</code>: this will cause deadlock if the synchronisation strategy is not re-entrant.

#### **Example Code**

locking\_ptr constructors:destructors # locking\_ptr(volatile value\_type& obj, mutex\_type& mtx); # ~locking\_ptr();

#### locking\_ptr public member functions

```
1. value_type& operator*();
```

2. const value\_type& operator\*() const;



```
    value_type* operator->();
    const value_type* operator->() const;
```

#### Class sharable\_locking\_ptr

#### **Synopsis**

```
template <typename T, typename SharableLockable>
class sharable_locking_ptr
   : private boost::noncopyable {
public:
    typedef T value_type;
    typedef SharableLockable mutex_type;
    sharable_locking_ptr(volatile value_type& obj, mutex_type& mtx);
    ~sharable_locking_ptr();
    value_type& operator*();
    const value_type& operator*() const;
    value_type* operator->();
    const value_type* operator->() const;
};
template <typename T, typename SharableLockable>
class sharable_locking_ptr<const T, SharableLockable>
    : private boost::noncopyable {
public:
    typedef T value_type;
    typedef SharableLockable mutex_type;
    sharable_locking_ptr(
        volatile const value_type& obj,
        mutex_type& mtx);
    ~sharable_locking_ptr();
   value_type& operator*();
    const value_type& operator*() const;
    value_type* operator->();
    const value_type* operator->() const;
};
```

#### **Description**

 ${\tt nested\_strict\_locker}\ public\ member\ functions$ 

1.;

**Header** <boost/synchro/locker/on\_derreference\_locking\_ptr.hpp>

```
namespace boost { namespace synchro {
    template<typename T, typename Lockable>
    class on_derreference_locking_ptr;
}}
```

#### Class on\_derreference\_locking\_ptr



```
template<typename T, typename Lockable>
class on_derreference_locking_ptr {
public:
    class pointer {
    public:
        explicit pointer(T* target, Lockable* mutex);
        ~pointer();
        T *operator->();
    };

    explicit on_derreference_locking_ptr(T &target, Lockable& mutex);
    pointer operator->() const;
};
```

### **Description**

### Header <boost/synchro/locker/array\_unique\_locker.hpp>

```
namespace boost { namespace synchro {
   template <typename Lockable, unsigned N>
   class unique_array_locker;
   template <typename Lockable, unsigned N>
   class try_unique_array_locker;
}
```

### Template Class unique\_array\_locker<>



```
template <typename Lockable, unsigned N>
class unique_array_locker {
public:
        typedef Lockable lockable_type;
       BOOST_NON_CONST_COPY_CONSTRUCTOR_DELETE(unique_array_locker) /*< disable copy construction >*/
      BOOST_NON_CONST_COPY_ASSIGNEMENT_DELETE(unique_array_locker) /*< disable copy asignement >*/
        unique_array_locker(Lockable& m0, ..., Lockable& m_n);
        unique\_array\_locker(Lockable\& \ m0\ , \ \dots, \ Lockable\& \ m_n\ , \ adopt\_lock\_t)\ ;
        unique\_array\_locker(\texttt{Lockable}\&\ \texttt{m0}\,,\ \dots,\ \texttt{Lockable}\&\ \texttt{m\_n}\,,\ \texttt{defer\_lock})\,\textit{;}
        unique\_array\_locker(Lockable\& \ m0\,, \ \dots, \ Lockable\& \ m_n, \ try\_to\_lock\_t)\,;\\
        // try_lock_until constructor
        template < class Clock, class Duration >
        unique_array_locker(Lockable& m0, ..., Lockable& m_n, chrono::time_point<Clock, DuraJ
tion> const& target_time);
       template<class Rep, class Period >
      unique_array_locker(Lockable& m0, ..., Lockable& m_n, chrono::duration<Rep, Period> const& tar-
get_time)
        template < class Clock, class Duration >
        unique\_array\_locker(Lockable \& \ m0, \ \dots, \ Lockable \& \ m_n, \ chrono::time\_point < Clock, \ Dura \rightarrow Lockable \& \ m_n, \ chrono::time\_point < Clock, \ Dura \rightarrow Lockable \& \ mn + Lockable \& \ m
tion> const& target_time, throw_timeout_t);
       template<class Rep, class Period >
       unique_array_locker(Lockable& m0, ..., Lockable& m_n, chrono∷duration<Rep, Period> const& tar→
get_time, throw_timeout_t)
        template < class Clock, class Duration >
        unique_array_locker(chrono::time_point<Clock, Duration> const& target_time, Lock↓
able& m0, ..., Lockable& m_n);
        template<class Rep, class Period >
       unique_array_locker(chrono::duration<Rep, Period> const& target_time, Lockable& m0, ..., Lockal
able\&\ m\_n\,,\ )
        template<class Clock, class Duration >
        unique_array_locker(nothrow_timeout_t, chrono::time_point<Clock, Duration> const& tar-
\texttt{get\_time}\,,\,\, \texttt{Lockable}\&\,\, \texttt{m0}\,,\,\, \ldots\,,\,\, \texttt{Lockable}\&\,\, \texttt{m\_n})\,;
       template<class Rep, class Period >
       unique_array_locker(nothrow_timeout_t, chrono::duration<Rep, Period> const& target_time, Lock |
able& m0, ..., Lockable& m2)
        ~unique_array_locker();
       bool is_locking(lockable_type* 1) const;
        bool owns_lock() const;
        typedef unspecified-type bool_type)() const; /*< safe bool idiom >*/
        operator bool_type() const;
       bool operator!() const;
        void lock();
        template<class Clock, class Duration >
        void lock_until(chrono::time_point<Clock, Duration> const& absolute_time);
        template<class Rep, class Period >
        void lock_for(chrono::duration<Rep, Period> const& relative_time);
       void unlock();
       bool try_lock();
```



```
template<class Clock, class Duration >
bool try_lock_until(chrono::time_point<Clock, Duration> const& absolute_time);
template<class Rep, class Period >
bool try_lock_for(chrono::duration<Rep, Period> const& relative_time);
};
```

#### **Description**

#### unique\_array\_locker template parameters

- Lockable : The exclusive lockable type used to synchronize exclusive access
- N: The number of lockables in the array

#### unique\_array\_locker public types

- lockable\_type: The exclusive lockable type used to synchronize exclusive access
- lock\_error: The exception type throw in case of errors
- bool\_type: The bool\_type of the safe\_bool idiom

#### unique\_array\_locker private and not defined member functions

```
unique_array_locker()unique_array_locker(unique_array_locker&);operator=(unique_array_locker&);
```

### Template Class try\_unique\_array\_locker<>



# Single-threaded

### Header <boost/synchro/null\_mutex.hpp>

```
namespace boost { namespace synchro {
    class null_condition;
    class null_mutex : public lock_traits_base<</pre>
        mono_threaded_tag,
        upgradable_lock_tag,
        recursive_tag,
        has_timed_interface_tag,
        kernel_lifetime_tag,
        anonymous_tag,
        void
       null_mutex(const null_mutex&);
       null_mutex &operator= (const null_mutex&);
    public:
        typedef null_condition condition_type;
        typedef null_condition condition_any_type;
       null_mutex();
       ~null_mutex();
       void lock();
       bool try_lock();
       bool try_lock_until(const boost::posix_time::ptime &);
       template<typename TimeDuration>
       bool try_lock_for(TimeDuration const & relative_time);
       void unlock();
       void lock_shared(){};
       bool try_lock_shared();
       bool try_lock_shared_until(const boost::posix_time::ptime &);
       template<typename DurationType>
       bool try_lock_shared_for(DurationType const& rel_time)
       void unlock_shared();
       void lock_upgrade();
       bool try_lock_upgrade();
       bool timed_lock_upgrade(boost::posix_time::ptime const &);
        void unlock_upgrade();
       void unlock_and_lock_upgrade();
       void unlock_and_lock_shared();
       void unlock_upgrade_and_lock_shared();
       void unlock_upgrade_and_lock();
       bool try_unlock_upgrade_and_lock();
       bool timed_unlock_upgrade_and_lock(const boost::posix_time::ptime &);
```



```
bool try_unlock_share_and_lock();

bool try_unlock_share_and_lock_upgrade();
};

}}
```

### Header <boost/synchro/null\_condition.hpp>

```
namespace boost { namespace synchro {
    class null_condition {
    private:
      null_condition(const null_condition &);
      null_condition &operator=(const null_condition &);
   public:
      null_condition();
       ~null_condition();
       void notify_one();
       void notify_all();
       template <typename L>
       void wait(L& lock);
       template <typename L, typename Pr>
       void wait(L& lock, Pr pred);
       template <typename L>
      bool timed_wait(L& lock, const boost::posix_time::ptime &abs_time);
       template <typename L, typename Pr>
      bool timed_wait(L& lock, const boost::posix_time::ptime &abs_time, Pr pred);
    };
    template <>
    struct best_condition<null_mutex> {
        typedef null_condition type;
    };
}}
```

### Header <boost/synchro/null\_synchronization\_family.hpp>

```
namespace boost { namespace synchro {
    struct null_synchronization_family;
}}
```

#### Class null\_synchronization\_policy



### **Multi-threaded**

Header <boost/synchro/thread/lockable\_scope\_traits.hpp>

```
namespace boost { namespace synchro {
    template<> struct scope_traits<multi_threaded_tag>;
    template<typename Lockable>
    struct lockable_scope_traits<multi_threaded_tag, Lockable>;
}}
```

### Template Class Specialization scope\_traits<multi\_threaded\_tag>

#### **Synopsis**

```
template<> struct scope_traits<multi_threaded_tag> {
   typedef boost::lock_error lock_error;

template <typename T>
   struct moved_object : boost::detail::thread_move_t<T> {
        moved_object(T& t_): boost::detail::thread_move_t<T>(t_) {}
};

typedef boost::defer_lock_t defer_lock_t;
typedef boost::adopt_lock_t adopt_lock_t;
typedef boost::try_to_lock_t try_to_lock_t;

static const defer_lock_t& defer_lock() {return boost::defer_lock;}
   static const adopt_lock_t& adopt_lock() {return boost::adopt_lock;}
   static const try_to_lock_t& try_to_lock() {return boost::try_to_lock;}
};
```

### Template Class Specialization lockable\_scope\_traits<multi\_threaded\_tag, Lockable>



### Header <boost/synchro/thread/mutex.hpp>

```
namespace boost { namespace synchro {
    class thread_mutex;
    template <> struct unique_lock_type<thread_mutex>;
    template <> struct shared_lock_type<thread_mutex>;
    template <> struct upgrade_lock_type<thread_mutex>;
    template <> struct upgrade_to_unique_locker_type<thread_mutex>;
    template <> struct upgrade_to_unique_locker_type<thread_mutex>;
    template <> struct lock_error_type<boost::mutex>;
    class thread_timed_mutex;
}
```

#### Class thread mutex



```
class thread_mutex : public lock_traits_base<</pre>
       multi_threaded_tag,
        exclusive_lock_tag,
       non_recursive_tag,
       hasnt_timed_interface_tag,
        process_lifetime_tag,
        anonymous_tag,
       mutex
   > {
public:
    // public types
    typedef boost::condition_variable best_condition_type;
    typedef boost::condition_variable_any best_condition_any_type;
    //Non-copyable
    BOOST_COPY_CONSTRUCTOR_DELETE(thread_mutex) /*< disable copy construction >*/
    BOOST_COPY_ASSIGNEMENT_DELETE(thread_mutex) /*< disable copy asignement >*/
    thread_mutex() {}
};
template <>
struct unique_lock_type<thread_mutex> {
    typedef boost::unique_lock<boost::mutex> type;
template <>
struct shared_lock_type<thread_mutex> {
    typedef boost::shared_lock<boost::mutex> type;
};
template <>
struct upgrade_lock_type<thread_mutex> {
    typedef boost::upgrade_lock<boost::mutex> type;
};
template <>
struct upgrade_to_unique_locker_type<thread_mutex> {
    typedef boost::upgrade_to_unique_lock<boost::mutex> type;
template <>
struct lock_error_type<boost::mutex> {
   typedef boost::lock_error type;
```



### Class thread\_timed\_mutex

```
class thread_timed_mutex : public lock_traits_base<</pre>
        multi_threaded_tag,
        exclusive_lock_tag,
        non_recursive_tag,
        {\tt has\_timed\_interface\_tag}\,,
        process_lifetime_tag,
        anonymous_tag,
        timed_mutex
    > {
public:
    typedef boost::condition_variable_any best_condition_type;
    typedef boost::condition_variable_any best_condition_any_type;
    //Non-copyable
    BOOST_COPY_CONSTRUCTOR_DELETE(thread_timed_mutex) /*< disable copy construction >*/
    BOOST_COPY_ASSIGNEMENT_DELETE(thread_timed_mutex) /*< disable copy asignement >*/
    thread_timed_mutex ();
    bool try_lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    bool try_lock_for(TimeDuration const & relative_time);
    void lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const & relative_time);
};
```

### Header <boost/synchro/thread\_recursive\_mutex.hpp>

```
namespace boost { namespace synchro {
   class thread_recursive_mutex;

   class thread_timed_mutex;
}}
```

#### Class thread\_recursive\_mutex

```
class thread_recursive_mutex : public lock_traits_base<</pre>
        multi_threaded_tag,
        exclusive_lock_tag,
        recursive_tag,
        hasnt_timed_interface_tag,
        process_lifetime_tag,
        anonymous_tag,
        recursive_mutex
public:
    typedef boost::condition_variable_any best_condition_type;
    typedef boost::condition_variable_any best_condition_any_type;
    //Non-copyable
    BOOST_COPY_CONSTRUCTOR_DELETE(thread_recursive_mutex) /*< disable copy construction >*/
    BOOST_COPY_ASSIGNEMENT_DELETE(thread_recursive_mutex) /*< disable copy asignement >*/
    thread_recursive_mutex() {}
};
```



### Class thread\_recursive\_timed\_mutex

```
class thread_recursive_timed_mutex : public lock_traits_base
        multi_threaded_tag,
        exclusive_lock_tag,
        recursive_tag,
       has_timed_interface_tag,
        process_lifetime_tag,
        anonymous_tag,
       recursive_timed_mutex
    > {
public:
    typedef boost::condition_variable_any best_condition_type;
    typedef boost::condition_variable_any best_condition_any_type;
    //Non-copyable
   BOOST_COPY_CONSTRUCTOR_DELETE(thread_recursive_timed_mutex) /*< disable copy construction >*/
   BOOST_COPY_ASSIGNEMENT_DELETE(thread_recursive_timed_mutex) /*< disable copy asignement >*/
    thread_recursive_timed_mutex();
   bool try_lock_until(system_time const & abs_time);
    template<typename TimeDuration>
   bool try_lock_for(TimeDuration const & relative_time);
    void lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const & relative_time);
};
```

### Header <boost/synchro/thread/shared\_mutex.hpp>

```
namespace boost { namespace synchro {
    class thread_recursive_mutex;

    class thread_timed_mutex;
}}
```

#### Class thread\_shared\_mutex



```
class thread_shared_mutex : public lock_traits_base<</pre>
        multi_threaded_tag,
        upgradable_lock_tag,
        non_recursive_tag,
        has_timed_interface_tag,
        process_lifetime_tag,
        anonymous_tag,
        shared_mutex
public:
    typedef boost::condition_variable_any best_condition_type;
    typedef boost::condition_variable_any best_condition_any_type;
    //Non-copyable
    BOOST_COPY_CONSTRUCTOR_DELETE(thread_shared_mutex) /*< disable copy construction >*/
    BOOST_COPY_ASSIGNEMENT_DELETE(thread_shared_mutex) /*< disable copy asignement >*/
    thread_shared_mutex();
   bool try_lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    bool try_lock_for(TimeDuration const & relative_time);
    void lock_until(system_time const & abs_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const & relative_time);
    bool try_lock_shared_until(system_time const& abs_time);
    template<typename TimeDuration>
    bool try_lock_shared_for(TimeDuration const& rel_time);
    void lock_shared_until(system_time const& abs_time);
    template<typename TimeDuration>
    void lock_shared_for(TimeDuration const& abs_time);
};
```

### Header <boost/synchro/thread/locks.hpp>

```
namespace boost { namespace synchro {
   class thread_recursive_mutex;

   class thread_timed_mutex;
}
```



### Template Class unique\_locker<>

```
template <typename T>
struct lockable_type<boost::unique_lock<T> > {
    typedef T type;
};
template <typename T>
struct lockable_type<boost::shared_lock<T> > {
    typedef T type;
template <typename T>
struct lockable_type<boost::upgrade_lock<T> > {
   typedef T type;
};
template <typename T>
struct lockable_type<boost::upgrade_to_unique_lock<T> > {
    typedef T type;
template<typename Mutex>
class unique_locker<Mutex,multi_threaded_tag>: public unique_lock_type<Mutex>::type {
    //typename scope_tag<Mutex>::type == multi_threaded_tag
private:
    typedef Mutex lockable_type;
    typedef multi_threaded_tag scope_tag_type;
    typedef typename unique_lock_type<Mutex>::type base_type;
public:
    BOOST_NON_CONST_COPY_CONSTRUCTOR_DELETE(unique_locker) /*< disable copy construction >*/
    BOOST_NON_CONST_COPY_ASSIGNEMENT_DELETE(unique_locker) /*< disable copy asignement >*/
    unique_locker();
    explicit unique_locker(Mutex& m_);
    unique_locker(Mutex& m_,adopt_lock_t);
    unique_locker(Mutex& m_,defer_lock_t);
    unique_locker(Mutex& m_,try_to_lock_t);
    template<typename TimeDuration>
    unique_locker(Mutex& m_,TimeDuration const& target_time);
    unique_locker(Mutex& m_,system_time const& target_time);
    template<typename TimeDuration>
    unique_locker(Mutex& m_,TimeDuration const& target_time, throw_lock_t);
    unique_locker(Mutex& m_,system_time const& target_time, throw_lock_t);
    template<typename TimeDuration>
    unique_locker(TimeDuration const& target_time, Mutex& m_);
    unique_locker(system_time const& target_time, Mutex& m_);
#ifdef BOOST_HAS_RVALUE_REFS
    unique_locker(unique_locker&& other);
    explicit unique_locker(upgrade_locker<Mutex,scope_tag_type>&& other);
    unique_locker<Mutex, scope_tag_type>&& move();
    unique_locker& operator=(unique_locker<Mutex, scope_tag_type>&& other);
    unique_locker& operator=(upgrade_locker<Mutex, multi_threaded_tag>&& other);
    void swap(unique_locker&& other);
#else
    unique_locker(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
   unique_locker(detail::thread_move_t<upgrade_locker<Mutex,scope_tag_type> > other);
    operator detail::thread_move_t<unique_locker<Mutex, scope_tag_type> >();
```



```
detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > move();
   unique_locker& operator=(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
   unique_locker& operator=(detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > other);
   void swap(unique_locker& other);
   void swap(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
#endif
    ~unique_locker() {}
   Mutex* mutex() const;
   bool is_locking(lockable_type* 1) const;
    template<typename TimeDuration>
   bool try_lock_for(TimeDuration const& relative_time);
   bool try_lock_until(::boost::system_time const& absolute_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const& relative_time);
    void lock_until(::boost::system_time const& absolute_time);
};
```



### Template Class try\_unique\_locker<>

```
template<typename Mutex>
class try_unique_locker<Mutex,multi_threaded_tag>: public unique_locker<Mud-</pre>
tex,multi_threaded_tag> {
    //typename scope_tag<Mutex>::type == multi_threaded_tag
private:
    typedef Mutex lockable type;
    typedef multi_threaded_tag scope_tag_type;
    typedef unique_locker<Mutex,multi_threaded_tag> base_type;
public:
   try_unique_locker();
    explicit try_unique_locker(Mutex& m_);
    try_unique_locker(Mutex& m_,force_lock_t);
    try_unique_locker(Mutex& m_,adopt_lock_t);
    try_unique_locker(Mutex& m_,defer_lock_t);
    try_unique_locker(Mutex& m_,try_to_lock_t);
    template<typename TimeDuration>
    try_unique_locker(Mutex& m_,TimeDuration const& target_time);
    try_unique_locker(Mutex& m_,system_time const& target_time);
    template<typename TimeDuration>
    try_unique_locker(Mutex& m_,TimeDuration const& target_time, throw_lock_t);
    try_unique_locker(Mutex& m_,system_time const& target_time, throw_lock_t);
    template<typename TimeDuration>
    try_unique_locker(TimeDuration const& target_time, Mutex& m_);
    try_unique_locker(system_time const& target_time, Mutex& m_);
#ifdef BOOST_HAS_RVALUE_REFS
    try_unique_locker(try_unique_locker&& other);
    explicit try_unique_locker(upgrade_locker<Mutex,scope_tag_type>&& other);
    try_unique_locker<Mutex, scope_tag_type>&& move();
    try_unique_locker& operator=(try_unique_locker<Mutex, scope_tag_type>&& other);
    try_unique_locker& operator=(upgrade_locker<Mutex, multi_threaded_tag>&& other);
    void swap(try_unique_locker&& other);
#else
    try_unique_locker(detail::thread_move_t<try_unique_locker<Mutex, scope_tag_type> > other);
    try_unique_locker(detail::thread_move_t<upgrade_locker<Mutex,scope_tag_type> > other);
    operator detail::thread_move_t<try_unique_locker<Mutex, scope_tag_type> >();
    detail::thread_move_t<try_unique_locker<Mutex, scope_tag_type> > move();
   try_unique_locker& operator=(detail::thread_move_t<try_unique_locker<Mu,J
tex, scope_tag_type> > other);
   try_unique_locker& operator=(detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > oth I
er);
    void swap(try_unique_locker& other);
    void swap(detail::thread_move_t<try_unique_locker<Mutex, scope_tag_type> > other);
#endif
    ~try_unique_locker() {}
};
```



### Template Class shared\_locker<>

```
template<typename Mutex>
class shared_locker<Mutex,multi_threaded_tag>: public shared_lock_type<Mutex>::type {
    //typename scope_tag<Mutex>::type == multi_threaded_tag
public:
    typedef Mutex lockable_type;
    typedef multi_threaded_tag scope_tag_type;
    typedef typename shared_lock_type<Mutex>::type base_type;
    shared_locker();
    BOOST_NON_CONST_COPY_CONSTRUCTOR_DELETE(shared_locker) /*< disable copy construction >*/
    BOOST_NON_CONST_COPY_ASSIGNEMENT_DELETE(shared_locker) /*< disable copy asignement >*/
    explicit shared_locker(Mutex& m_)
    shared_locker(Mutex& m_,adopt_lock_t);
    shared_locker(Mutex& m_,defer_lock_t);
    shared_locker(Mutex& m_,try_to_lock_t);
    shared_locker(Mutex& m_,system_time const& target_time);
    template<typename TimeDuration>
    shared_locker(Mutex& m_,TimeDuration const& target_time);
    shared_locker(Mutex& m_,system_time const& target_time,throw_lock_t);
    template<typename TimeDuration>
    shared_locker(Mutex& m_,TimeDuration const& target_time,throw_lock_t);
    shared_locker(Mutex& m_,system_time const& target_time,throw_lock_t);
    template<typename TimeDuration>
    shared_locker(TimeDuration const& target_time, Mutex& m_);
    shared_locker(system_time const& target_time, Mutex& m_);
    shared_locker(detail::thread_move_t<shared_locker<Mutex, scope_tag_type> > other);
    shared_locker(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
    shared_locker(detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > other);
    operator detail::thread_move_t<shared_locker<Mutex.scope_tag_type> >();
   detail::thread_move_t<shared_locker<Mutex, scope_tag_type> > move();
   shared_locker& operator=(detail::thread_move_t<shared_locker<Mutex, scope_tag_type> > other);
   shared_locker& operator=(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
   shared_locker& operator=(detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > other);
#ifdef BOOST_HAS_RVALUE_REFS
   void swap(shared_locker&& other);
    void swap(shared_locker& other);
    void swap(boost::detail::thread_move_t<shared_locker<Mutex, scope_tag_type> > other);
#endif
   Mutex* mutex() const;
   bool is_locking(lockable_type* 1) const;
   bool try_lock_until(boost::system_time const& absolute_time);
    template<typename Duration>
    bool try_lock_for(Duration const& relative_time);
    template<typename TimeDuration>
    void lock_for(TimeDuration const& relative_time);
    void lock_until(::boost::system_time const& absolute_time);
};
```



### Template Class upgrade\_locker<>

```
template<typename Mutex>
class upgrade_locker<Mutex,multi_threaded_tag>: public upgrade_lock_type<Mutex>::type {
    //typename scope_tag<Mutex>::type == multi_threaded_tag
public:
    typedef Mutex lockable_type;
    typedef multi_threaded_tag scope_tag_type;
    typedef typename upgrade_lock_type<Mutex>::type base_type;
    upgrade_locker();
    BOOST_NON_CONST_COPY_CONSTRUCTOR_DELETE(upgrade_locker) /*< disable copy construction >*/
    BOOST_NON_CONST_COPY_ASSIGNEMENT_DELETE(upgrade_locker) /*< disable copy asignement >*/
    explicit upgrade_locker(Mutex& m_);
    upgrade_locker(Mutex& m_,adopt_lock_t);
    upgrade_locker(Mutex& m_,defer_lock_t);
    upgrade_locker(Mutex& m_,try_to_lock_t);
    \verb"upgrade_locker(detail::thread_move_t < \verb"upgrade_locker < Mutex", \verb"scope_tag_type"> > other);
    upgrade_locker(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
    operator detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> >();
    detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > move();
   upgrade_locker& operator=(detail::thread_move_t<upgrade_locker<Mutex, scope_tag_type> > other);
   upgrade_locker& operator=(detail::thread_move_t<unique_locker<Mutex, scope_tag_type> > other);
    void swap(upgrade_locker& other);
    ~upgrade_locker();
    Mutex* mutex() const;
    bool is_locking(lockable_type* 1) const;
};
```



### Template Class upgrade\_to\_unique\_locker<>

```
template<typename Mutex>
class upgrade_to_unique_locker<Mutex,multi_threaded_tag>: public upgrade_to_unique_locker_type<MuJ
tex>::type {
    //typename scope_tag<Mutex>::type == multi_threaded_tag
public:
    typedef Mutex lockable_type;
    typedef multi_threaded_tag scope_tag_type;
    typedef typename upgrade_to_unique_locker_type<Mutex>::type base_type;
public:
   BOOST_NON_CONST_COPY_CONSTRUCTOR_DELETE(upgrade_locker) /*< disable copy construction >*/
    BOOST_NON_CONST_COPY_ASSIGNEMENT_DELETE(upgrade_locker) /*< disable copy asignement >*/
    explicit upgrade_to_unique_locker(upgrade_locker<Mutex,multi_threaded_tag>& m_);
    ~upgrade_to_unique_locker();
   upgrade_to_unique_locker(detail::thread_move_t<upgrade_to_unique_locker<Mu↓
tex, scope_tag_type> > other);
   upgrade_to_unique_locker& operator=(detail::thread_move_t<upgrade_to_unique_locker<Mu,J
tex, scope_tag_type> > other);
   void swap(upgrade_to_unique_locker& other);
   Mutex* mutex() const;
   bool is_locking(lockable_type* 1) const;
};
```

### Header <boost/synchro/thread\_synchronization\_family.hpp>

### **Class** thread\_synchronization\_family

#### **Synopsis**

```
struct thread_synchronization_family
    typedef thread_mutex
                                             mutex_type;
    typedef thread_recursive_mutex
                                             recursive_mutex_type;
    typedef thread_timed_mutex
                                             timed_mutex_type;
    typedef thread_recursive_timed_mutex
                                             recursive_timed_mutex_type;
    typedef thread_shared_mutex
                                             shared_mutex_type;
    typedef boost::condition_variable
                                             condition_type;
    typedef boost::condition_variable_any
                                             condition_type_any;
};
```

### **Multi-process**

Header <boost/synchro/thread/lockable\_scope\_traits.hpp>

```
namespace boost { namespace synchro {
   template<> struct scope_traits<multi_process_tag>
   template<typename Lockable>
   struct lockable_scope_traits<multi_process_tag, Lockable>;
}}
```



### Template Class Specialization scope\_traits<multi\_process\_tag>

```
template<>
struct scope_traits<multi_process_tag> {
    typedef boost::interprocess::lock_exception lock_error;

    template <typename T>
    struct moved_object: boost::interprocess::detail::moved_object<T> {
        moved_object(T& t_): boost::interprocess::detail::moved_object<T>(t_) {}
};

    typedef boost::interprocess::defer_lock_type defer_lock_t;
    typedef boost::interprocess::accept_ownership_type adopt_lock_t;
    typedef boost::interprocess::try_to_lock_type try_to_lock_t;

    static const defer_lock_t& defer_lock() { return boost::interprocess::defer_lock; }
    static const adopt_lock_t& adopt_lock() { return boost::interprocess::accept_ownership; }
    static const try_to_lock_t& try_to_lock() { return boost::interprocess::accept_ownership; }
};
```

### Template Class Specialization lockable\_scope\_traits<multi\_process\_tag, Lockable>

### Header <boost/synchro/process\_synchronization\_family.hpp>

```
namespace boost { namespace synchro {
    struct process_synchronization_family;
}}
```

#### Class process\_synchronization\_family

```
struct process_synchronization_family {
  typedef boost::synchro::interprocess_mutex
                                                            mutex_type;
  typedef boost::synchro::interprocess_recursive_mutex
                                                            recursive_mutex_type;
  typedef boost::synchro::interprocess_mutex
                                                            timed_mutex_type;
  typedef boost::synchro::interprocess_recursive_mutex
                                                            recursive_timed_mutex_type;
  typedef boost::synchro::interprocess_upgradable_mutex
                                                            shared_mutex_type;
  typedef boost::interprocess::interprocess_condition
                                                            condition_type;
  typedef boost::interprocess::interprocess_condition
                                                            condition_any_type;
};
```



### **Polymorphic Locks**

# Header <boost/synchro/poly/lock.hpp>

```
namespace boost { namespace synchro {
    namespace poly {
        struct exclusive_lock;
        struct timed_lock;
        struct sharable_lock;
        struct upgradable_lock;
}
```

### Abstract Class exclusive\_lock

Polymorphic exclusive lock interface.

```
struct exclusive_lock {
    virtual ~exclusive_lock()=0;
    virtual void lock()=0;
    virtual void unlock()=0;
    virtual bool try_lock()=0;
};
```

### Abstract Class timed\_lock

Polymorphic timed lock interface.

```
struct timed_lock : exclusive_lock {
    virtual ~timed_lock()=0;
    bool try_lock_until(boost::system_time const& abs_time)=0;
    template<typename DurationType>
    bool try_lock_for(DurationType const& rel_time)
    {
        return try_lock_until(get_system_time()+abs_time);
    }
};
```

### Abstract Class sharable\_lock

Polymorphic sharable lock interface.

```
struct sharable_lock : timed_lock {
    virtual ~sharable_lock();
    virtual void lock_shared()=0;
    virtual bool try_lock_shared_until(boost::system_time const& abs_time)=0;
    virtual void unlock_shared()=0;
    template<typename DurationType>
    bool try_lock_shared_for(DurationType const& rel_time)
    {
        return try_lock_shared_until(get_system_time()+abs_time);
    }
};
```

#### Abstract Class upgradable\_lock

Polymorphic upgradable lock interface.



```
struct upgradable_lock : sharable_lock {
    virtual ~upgradable_lock();
    virtual void lock_upgrade()=0;
    virtual void unlock_upgrade()=0;
    virtual void unlock_upgrade_and_lock()=0;
    virtual void unlock_and_lock_upgrade()=0;
    virtual void unlock_and_lock_shared()=0;
    virtual void unlock_upgrade_and_lock_shared()=0;
};
```

### Header <boost/synchro/poly/lock\_adpater.hpp>

namespace boost { namespace synchro { namespace poly { template <typename Lockable> class exclusive\_lock\_adapter; template <typename TimeLockable> class timed\_lock\_adapter; template <typename UpgradaLockable> class upgradable\_lock\_adapter; } }}

#### Template Class exclusive\_lock\_adapter

### Template Class timed\_lock\_adapter

### Template Class sharable\_lock\_adapter



### Template Class upgradable\_lock

### **Other**

### Header <boost/synchro/semaphore.hpp>

```
namespace boost { namespace synchro {
    template <typename Sync=thread_synchronization_family>
    class basic_semaphore {
        basic_semaphore(const basic_semaphore &);
        this_type& operator=(const basic_semaphore &);
    public:
        basic_semaphore(int initialCount);
        ~basic_semaphore();
        void post();
        void wait();
        bool try_wait();
        bool wait_until(const system_time &abs_time);
        template<typename TimeDuration>
        bool wait_for(const TimeDuration &rel_time);
    };
    typedef basic_semaphore<> semaphore;
} }
```



### **High Level**

### Header <boost/synchro/monitor.hpp>

```
namespace boost { namespace synchro {
    template <
          typename Lockable=thread_mutex
        , class Condition=condition_safe<typename best_condition<Lockable>::type >
        , typename ScopeTag=typename scope_tag<Lockable>::type
    class exclusive_monitor;
    template <
         typename Lockable=thread_shared_mutex,
        , class Condition=condition_safe<typename best_condition_any<Lockable>::type >
        , typename ScopeTag=typename scope_tag<Lockable>::type
    class shared_monitor;
    template <
          typename Lockable=thread_mutex
        , typename lock_tag=typename category_tag<Lockable>::type
        , typename ScopeTag=typename scope_tag<Lockable>::type
    struct monitor;
} }
```

### Template Class exclusive\_monitor<>

```
template <
    typename Lockable=thread_mutex
, class Condition=condition_safe<typename best_condition<Lockable>::type >
, typename ScopeTag=typename scope_tag<Lockable>::type
>
class exclusive_monitor : protected lockable_adapter<Lockable> {
    BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
protected:
    typedef Condition condition;
    typedef condition_unique_locker<Lockable, Condition, ScopeTag> synchronizer;
};
```

### Template Class shared\_monitor<>

```
template <
    typename Lockable=thread_shared_mutex,
    class Condition=condition_safe<typename best_condition_any<Lockable>::type >
    typename ScopeTag=typename scope_tag<Lockable>::type
>
class shared_monitor : protected lockable_adapter<Lockable> {
    BOOST_CONCEPT_ASSERT((LockableConcept<Lockable>));
protected:
    typedef Condition condition;
    typedef condition_unique_locker<Lockable, Condition, ScopeTag> synchronizer;
    typedef condition_shared_locker<Lockable, Condition, ScopeTag> shared_synchronizer;
};
```



### Template Class monitor<>

```
template <
     typename Lockable=thread_mutex
     , typename lock_tag=typename category_tag<Lockable>::type
     , typename ScopeTag=typename scope_tag<Lockable>::type
> struct monitor;

template <typename Lockable, typename ScopeTag>
struct monitor<Lockable, exclusive_lock_tag, ScopeTag>
     : protected exclusive_monitor<Lockable, ScopeTag>
{};

template <typename Lockable, typename ScopeTag>
struct monitor<Lockable, sharable_lock_tag, ScopeTag>
     : protected shared_monitor<Lockable, ScopeTag>
{};

template <typename Lockable, typename ScopeTag>
struct monitor<Lockable, typename ScopeTag>
struct monitor<Lockable, typename ScopeTag>
     : protected shared_monitor<Lockable, ScopeTag>
     : protected shared_monitor<Lockable, ScopeTag>
}
```

# **Examples**

This section includes complete examples using the library.

Į/

# **Appendices**

### **Appendix A: History**

Version 0.3.3, May 24, 2009 Extraction of Boost.Rendez-Vous

Version 0.3.2, May 08, 2009 Adaptation Boost 1.39 + Extraction of Boost.Conversion

Version 0.3.1, Mars 29, 2009 Language-like Synchronized Block Macros

#### **New Features:**

• Language-like Synchronized Block Macros.

# Version 0.3.0, Mars 19, 2009 Generic free operations on multiple lockables + Usage of Boost.Chrono

### **New Features:**

- Generic free functions on lockables: lock, try\_lock
- Complete the generic free functions on multiple lockables in Boost.Thread lock, try\_lock with:
  - lock\_until, lock\_for, try\_lock\_until, try\_lock\_for, unlock



### Version 0.2.0, Mars 1, 2009 binary\_semaphore + array\_locker

#### **New Features:**

- binary\_semaphore emulation with mutex
- array\_locker locker containers.

### Version 0.1.0, Febraury 16, 2009 Announcement of Synchro

#### **Features:**

- A uniform usage of Boost.Thread and Boost.Interprocess synchronization mechanisms based on lockables(mutexes) concepts and locker(guards) concepts.
  - · lockables traits and lock generators,
  - · lock adapters of the Boost.Thread and Boost.Interprocess lockable models,
  - · locker adapters of the Boost.Thread and Boost.Interprocess lockers models,
  - complete them with the corresponding models for single-threaded programms: null\_mutex and null\_condition classes,
  - · locking families,
  - · semaphore,
  - condition\_lockable lock put toghether a lock and its associated conditions.
- · Exception based timed lockables and lockers,
- · A rich palete of lockers as
  - strict\_locker, nested\_strict\_locker,
  - condition\_locker,
  - reverse\_locker, nested\_reverse\_locker,
  - locking\_ptr, on\_derreference\_locking\_ptr,
  - externally\_locked,
- · A polymorphic lockable hierarchy.
- · High-level abstractions for handling more complicated synchronization problems, including
  - monitor for guaranteeing exclusive access to an object, and

### **Appendix B: Rationale**

**TBC** 

### **Appendix C: Implementation Notes**

TBC



# **Appendix D: Acknowledgements**

TBC

# **Appendix E: Tests**

# Lockables

Name	kind	Description	Result	Ticket
lockable_traits	compile	static assertion on lockables traits	Pass	#
lockable_concepts	compile	static assertion on lockables concepts	Pass	#

### **Lockers**

Name	kind	Description	Result	Ticket
locker_concepts	compile	static assertion on lockers concepts	Pass	#
nested_reverse_locker	run	nested_reverse_locker tests	Pass	#

### **Others**

Name	kind	Description	Result	Ticket
sync_buffer_family	run	synchronous buffer with synchronization family tests	Pass	#
sync_buffer_monitor	run	monitor synchronous buffer tests	Fail	v0.2#1

# **Examples**

Name	Kind	Description	Result	Ticket
BankAccount	run	tests	Pass	#
IL_BancAccount	run	tests	Pass	#
IL_Lockable_BancAccount	run-fail	tests	Pass	#
IL_Rec_Lockable_BancAccount	run	tests	Pass	#
IEL_Rec_Lockable_BancAccount	run	tests	Pass	#
EL_BancAccount	run	tests	Pass	#



# **Appendix F: Tickets**

Kind	Identifier	Description	Resolution	State	Tests	Version
feature	v0.1#1	array_locker	See section	Open	See array_locker_tests	v0.2
bug	v0.2#1	sync_buffer_monitor_test fails		Open	sync_buffer_monitor_test	v0.2

# **Appendix E: Future plans**

### Tasks to do before review

• tuple\_locker locker containers.

### For later releases

