

ANSI escape code

ANSI escape sequences are a standard for in-band signaling to control cursor location, color, font styling, and other options on video text terminals and terminal emulators. Certain sequences of bytes, most starting with an ASCII escape character and a bracket character, are embedded into text. The terminal interprets these sequences as commands, rather than text to display verbatim.

ANSI sequences were introduced in the 1970s to replace vendor-specific sequences and became widespread in the computer equipment market by the early 1980s. They are used in development, scientific, commercial text-based applications as well as bulletin board systems to offer standardized functionality.

Although hardware text terminals have become increasingly rare in the 21st century, the relevance of the ANSI standard persists because a great majority of terminal emulators and command consoles interpret at least a portion of the ANSI standard.

History

Almost all manufacturers of video terminals added vendor-specific escape sequences to perform operations such as placing the cursor at arbitrary positions on the screen. One example is the VT52 terminal, which allowed the cursor to be placed at an x,y location on the screen by sending the ESC character, a Y character, and then two characters representing numerical values equal to the x,y location plus 32 (thus starting at the ASCII space character and avoiding the control characters). The Hazeltine 1500 had a similar feature, invoked using ~, DC1 and then the X and Y positions separated with a comma. While the two terminals had identical functionality in this regard, different control sequences had to be used to invoke them.

As these sequences were different for different terminals, elaborate libraries such as termcap ("terminal capabilities") and utilities such as tput had to be


created so programs could use the same API to work with any terminal. In addition, many of these terminals required sending numbers (such as row and column) as the binary values of the characters; for some programming languages, and for systems that did not use ASCII internally, it was often difficult to turn a number into the correct character.

The ANSI standard attempted to address these problems by making a command set that all terminals would use and requiring all numeric information to be transmitted as ASCII numbers. The first standard in the series was ECMA-48, adopted in 1976.[1] It was a continuation of a series of character coding standards, the first one being ECMA-6 from 1965, a 7-bit standard from which ISO 646 originates. The name "ANSI escape sequence" dates from 1979 when ANSI adopted ANSI X3.64. The ANSI X3L2 committee collaborated with the ECMA committee TC 1 to produce nearly identical standards. These two standards were merged into an international standard, ISO 6429.[1] In 1994, ANSI withdrew its standard in favor of the international standard.

The first popular video terminal to support these sequences was the Digital VT100, introduced in 1978. [2] This model was very successful in the market, which sparked a variety of VT100 clones, among the earliest and most popular of which was the much more affordable Zenith Z-19 in 1979. [3] Others included the Qume QVT-108, Televideo TVI-970, Wyse WY-99GT as well as optional "VT100" or "VT103" or "ANSI" modes with varying degrees of compatibility on many other brands. The popularity of these gradually led to more and more software (especially bulletin board systems and other online services) assuming the escape sequences worked, leading to almost all new terminals and emulator programs supporting them.

In 1981, ANSI X3.64 was adopted for use in the US government by FIPS publication 86. Later, the US government stopped duplicating industry standards, so FIPS pub. 86 was withdrawn. [4]

ANSI X3.64 (ISO/IEC 6429)



Other related

encoding(s)

Other control

31626, ETS 300 706

ECMA-48 has been updated several times and is currently at its 5th edition, from 1991. It is also adopted by \underline{ISO} and \underline{IEC} as standard $\underline{ISO/IEC}$ 6429. A version is adopted as a Japanese Industrial Standard, as JIS X 0211.

Related standards include <u>ITU T.61</u>, the <u>Teletex</u> standard, and the **ISO/IEC 8613**, the <u>Open Document Architecture</u> standard (mainly ISO/IEC 8613-6 or ITU T.416). The two systems share many escape codes with the ANSI system, with extensions that are not necessarily meaningful to computer terminals. Both systems quickly fell into disuse, but ECMA-48 does mark the extensions used in them as reserved.

Platform support

T.T. T. Washington, and the state of the sta

The DEC VT100 video display terminal.

Unix-like systems

On these systems the terminal (or emulator) self-identifies using the \$TERM environment variable. A database library such as <u>termcap</u> or <u>terminfo</u> would perform a lookup to derive the capabilities of the terminal and specific escape sequences to use the capabilities, which may deviate from ANSI in early days.

Although such libraries were primarily developed on and for Unix, by the mid-1980s programs running on <u>Unix-like</u> operating systems could almost always assume they were using a terminal or emulator that supported ANSI sequences; this led to widespread use of ANSI by programs running on those platforms. For instance, many games and shell scripts, and utilities such as color directory listings, directly



The Xterm terminal emulator.

write the ANSI sequences and thus cannot be used on a terminal that does not interpret them. Many programs, including $\underline{\text{text editors}}$ such as $\underline{\text{vi}}$ and $\underline{\text{GNU Emacs}}$, use termcap or terminfo, or use libraries such as $\underline{\text{curses}}$ that use termcap or terminfo, and thus in theory support non-ANSI terminals, but this is so rarely tested nowadays that they are $\underline{\text{unlikely to}}$ work with those terminals.

<u>Terminal emulators</u> for communicating with local programs as well as remote machines and the text <u>system console</u> almost always support ANSI escape codes. This includes terminal emulators such as <u>xterm</u>, <u>rxvt</u>, <u>GNOME Terminal</u>, and <u>Konsole</u> on systems with $\underline{X11}$ -based or $\underline{Wayland}$ -based window systems, and $\underline{Terminal.app}$ and third-party terminal emulators such as iTerm2 on macOS.

CP/M

<u>CP/M</u> machines varied and several competing terminals existed, like for printers, each with their own control sequences. Some early systems were <u>headless</u> (needing an external terminal) and personal computers with a native screen typically emulated a terminal. Application developers had to support various popular terminals and to provide an installation program to configure them. Despite the CP/M hardware abstraction layer (<u>BIOS</u>), even for the same microprocessor, vendors provided platform-specific versions due to the competing disk formats, that would also be preconfigured for the native terminal (for example, various machine-specific WordStar adaptations were released).

The headless <u>Altair 8800</u> was typically connected to a <u>teletype</u> such as the <u>Model 33 ASR</u> or to an external terminal like the <u>TeleVideo 920C</u>, needing to output their respective sequences. [6] The <u>Osborne 1</u> and <u>Kaypro II</u> computers natively emulated a subset of the TeleVideo 920C and <u>ADM-3A</u> control codes, respectively. [7][8] The



A 1980s Kaypro II, a CP/M-80 PC. It natively emulated ADM-3A and also supported a terminal mode (being demonstrated).

TRS-80 Model 4 and the Xerox 820 also emulated the Lear Siegler ADM-3A. The Zenith Z-89, Heathkit H8 and Amstrad PCW CP/M-80 computers implemented the Zenith Z19 (Heathkit H19) terminal codes, mostly compatible with VT52, the Z-89 manual also describes it as supporting ANSI. [11][12]

The Microsoft Z-80 SoftCard for the Apple II emulated a limited subset of the Videx Videoterm, corresponding to the Datamedia 1520 sequences that the UCSD-based Apple Pascal supported. Its CP/M had the CONFIGIO command to adapt external terminals or run local applications that issued other control codes. Supported external terminals were the Soroc IQ 120/140 and Hazeltine 1500/1510. [13][14]

DOS, OS/2, and Windows

MS-DOS 1.x did not support the ANSI or any other escape sequences. Only a few <u>control characters</u> (<u>BEL</u>, <u>CR</u>, <u>LF</u>, <u>BS</u>) were interpreted by the underlying BIOS, making it almost $[\underline{a}]$ impossible to do any kind of full-screen application. Any display effects had to be done with BIOS calls, which were notoriously slow, or by directly manipulating the IBM PC hardware.

DOS 2.0 introduced the ability to add a <u>device driver</u> for the ANSI escape sequences – the <u>de facto</u> standard being <u>ANSI.SYS</u>, but others like ANSI.COM, NANSI.SYS and ANSIPLUS.EXE are used as well (these are considerably faster as they bypass the BIOS). Slowness and the fact that it was not installed by default made software rarely take advantage of it; instead, applications continued to directly manipulate the hardware to get the text display needed. ANSI.SYS and similar drivers continued to work in <u>Windows 9x</u> up to <u>Windows Me</u>, and in NT-derived systems for 16-bit legacy programs executing under the NTVDM.

Many clones of DOS were able to interpret the sequences and do not require a separate ANSI driver to be loaded. <u>PTS-DOS^{[17][18]}</u> as well as <u>Concurrent DOS</u>, <u>Multiuser DOS^[19]</u> and <u>REAL/32</u> have built-in support (plus a number of extensions). OS/2 had an ANSI command that enabled the sequences.

The Windows Console did not support ANSI escape sequences, nor did Microsoft provide any method to enable them. Some replacements or additions for the console window such as JP Software's TCC (formerly 4NT), Michael J. Mefford's ANSI.COM, Jason Hood's ANSICON[20] and Maximus5's ConEmu interpreted ANSI escape sequences printed by programs. A Python package named colorama [21] internally interpretes ANSI escape sequences in text being printed, translating them to win32 calls to modify the state of the terminal, to make it easier to port Python code using ANSI to Windows. Cygwin performs similar translation to all output written to the console using Cygwin file descriptors, the filtering is done by the output functions of cygwin1.dll, to allow porting of POSIX C code to Windows.

In 2016, Microsoft released the Windows 10 version 1511 update which unexpectedly implemented support for ANSI escape sequences, over two decades after the debut of Windows NT. This was done alongside Windows Subsystem for Linux, allowing Unix-like terminal-based software to use the sequences in Windows Console. This defaults to off, but Windows PowerShell 5.1 enabled it. PowerShell 6 made it possible to embed the necessary ESC character into a string with `e.[23]

<u>Windows Terminal</u>, introduced in 2019, supports the sequences by default, and Microsoft intends to replace the Windows Console with Windows Terminal. [24]

Atari ST/TT/Falcon series

 $\underline{\text{Atari TOS}}$ used the command system adapted from the $\underline{\text{VT52}}$ with some expansions for color support, $\underline{^{[25]}}$ rather than supporting ANSI escape codes.

AmigaOS

<u>AmigaOS</u> not only interprets ANSI code sequences for text output to the screen, the AmigaOS <u>printer</u> driver also interprets them (with extensions proprietary to AmigaOS) and translates them into the codes required for the particular printer that is actually attached. [26]

Amiga CLI (shell) window style control sequences

	Effect
ESC [nu	Sets maximum length of lines in window to n.
ESC [nt	Sets maximum number of lines in window to n.
ESC [nx	Starts text n pixels from left edge of window.
ESC [ny	Starts text n pixels from top edge of window.

VMS / OpenVMS

 $\underline{\text{VMS}}$ was designed to be controlled using Digital's text-based video terminals such as the aforementioned $\underline{\text{VT100}}$; thus software tends to write the ANSI escape sequences directly (and will not work on non-ANSI terminals). [27]

Description

C0 control codes

Almost all users assume some functions of some single-byte characters. Initially defined as part of ASCII, the default C0 control code set is now defined in ISO 6429 (ECMA-48), making it part of the same standard as the C1 set invoked by the ANSI escape sequences (although \underline{ISO} 2022 allows the ISO 6429 C0 set to be used without the ISO 6429 C1 set, and *vice versa*, provided that 0x1B is always \underline{ISO} . This is used to shorten the amount of data transmitted, or to perform some functions that are unavailable from escape sequences:

Popular C0 control codes (not an exhaustive list)

^	CO	Abbr	Name	Effect	
^G	0x07	BEL	Bell	Makes an audible noise.	
^Н	0x08	BS	Backspace	Moves the cursor left (but may "backwards wrap" if cursor is at start of line).	
^I	0x09	HT	Tab	Moves the cursor right to next multiple of 8.	
٨٦	0x0A	LF	Line Feed	Moves to next line, scrolls the display up if at bottom of the screen. Usually does not move horizontally, though programs should not rely on this.	
^L	0x0C	FF	Form Feed	Move a printer to top of next page. Usually does not move horizontally, though programs should not rely on this. Effect on video terminals varies.	
^M	0x0D	CR	Carriage Return	Moves the cursor to column zero.	
^[0x1B	ESC	Escape	Starts all the escape sequences	

Escape sequences vary in length. The general format for an ANSI-compliant escape sequence is defined by $\underline{\text{ANSI X3.41}}$ (equivalent to ECMA-35 or ISO/IEC 2022). [28]:13.1 The escape sequences consist only of bytes in the range 0x20-0x7F (all the non-control ASCII characters), and can be parsed without looking ahead. The behavior when a control character, a byte with the high bit set, or a byte that is not part of any valid sequence, is encountered before the end is undefined.

Fe Escape sequences

If the ESC is followed by a byte in the range 0x40 to 0x5F, the escape sequence is of type Fe. Its interpretation is delegated to the applicable C1 control code standard. Accordingly, all escape sequences corresponding to C1 control codes from ANSI X3.64 / ECMA-48 follow this format. 5:5.3.a

The standard says that, in 8-bit environments, the control functions corresponding to type Fe escape sequences (those from the set of C1 control codes) can be represented as single bytes in the 0x80–0x9F range. This is possible in character encodings conforming to the provisions for an 8-bit code made in ISO 2022, such as the ISO 8859 series. However, in

character encodings used on modern devices such as $\underline{\text{UTF-8}}$ or $\underline{\text{CP-1252}}$, those codes are often used for other purposes, so only the 2-byte sequence is typically used. In the case of $\underline{\text{UTF-8}}$, representing a C1 control code via the $\underline{\text{C1 Controls and}}$ Latin-1 Supplement block results in a different two-byte code (e.g. 0xC2,0x8E for U+008E), but no space is saved this way.

Some type Fe (C1 set element) ANSI escape sequences (not an exhaustive list)

Code	C1	Abbr	Name	Effect	
ESC N	0x8E	SS2	Single Shift Two	Select a single character from one of the <u>alternative character sets</u> . SS2 selects the G2 character set, and SS3 selects the G3 character set. [29] In a 7-bit environment, this is followed by one or more GL	
ESC 0	0x8F	SS3	Single Shift Three	bytes (0x20–0x7F) specifying a character from that set. [28]:9.4 In an 8-bit environment, these may instead be GR bytes (0xA0–0xFF). [28]:8.4	
ESC P	0x90	DCS	Device Control String	Terminated by ST. ^{[5]:5.6} Xterm's uses of this sequence include defining User-Defined Keys, and requesting or setting Termcap/Terminfo data. ^[29]	
ESC [0x9B	CSI	Control Sequence Introducer	Starts most of the useful sequences, terminated by a byte in the range 0x40 through 0x7E. [5]:5.4	
ESC \	0x9C	ST	String Terminator	Terminates strings in other controls. [5]:8.3.143	
ESC]	0x9D	0SC	Operating System Command	Starts a control string for the operating system to use, terminated by ST. [5]:8.3.89	
ESC X	0x98	SOS	Start of String	Takes an argument of a string of text, terminated by ST. 5.6 The uses for these string control sequences are defined by the application 5.8.3.2,8.3.128 or privacy discipline. 5.8.3.94 These	
ESC ^	0x9E	PM	Privacy Message	functions are rarely implemented and the arguments are ignored by xterm. [29] Some Kermit clients allow the server to automatically	
ESC _	0x9F	APC	Application Program Command	execute Kermit commands on the client by embedding them in APC sequences; this is a potential security risk if the server is untrusted. [30]	

CSI (Control Sequence Introducer) sequences

For Control Sequence Introducer, or CSI, commands, the ESC [(written as $\e [$ or $\o 33[$ in several programming and scripting languages) is followed by any number (including none) of "parameter bytes" in the range 0x30-0x3F (ASCII 0-9:;<=>?), then by any number of "intermediate bytes" in the range 0x20-0x2F (ASCII space and !"#\$%&'()*+,-./), then finally by a single "final byte" in the range 0x40-0x7E (ASCII $0A-Z[\]^ `a-z[\]^ `$

All common sequences just use the parameters as a series of semicolon-separated numbers such as 1;2;3. Missing numbers are treated as 0 (1;;3 acts like the middle number is 0, and no parameters at all in ESC[m acts like a 0 reset code). Some sequences (such as CUU) treat 0 as 1 in order to make missing parameters useful. [5]: F.4.2

A subset of arrangements was declared "private" so that terminal manufacturers could insert their own sequences without conflicting with the standard. Sequences containing the parameter bytes \iff ? or the final bytes 0x70-0x7E ($p-z\{|\}$) are private.

The behavior of the terminal is undefined in the case where a CSI sequence contains any character outside of the range 0x20-0x7E. These illegal characters are either C0 control characters (the range 0-0x1F), DEL (0x7F), or bytes with the high bit set. Possible responses are to ignore the byte, to process it immediately, and furthermore whether to continue with the CSI sequence, to abort it immediately, or to ignore the rest of it.

Some ANSI control sequences (not an exhaustive list)

Code	Abbr	Name	Effect
CSI n A	CUU	Cursor Up	
CSI n B	I n B CUD Cursor Down		Moves the cursor n (default 1) cells in the given direction. If the cursor is
CSI n C	CUF	Cursor Forward	already at the edge of the screen, this has no effect.
CSI n D	CUB	Cursor Back	
CSI n E	CNL	Cursor Next Line	Moves cursor to beginning of the line <i>n</i> (default 1) lines down. (not <u>ANSI.SYS</u>)
CSI n F	CPL	Cursor Previous Line	Moves cursor to beginning of the line <i>n</i> (default 1) lines up. (not ANSI.SYS)
CSI n G	СНА	Cursor Horizontal Absolute	Moves the cursor to column n (default 1). (not ANSI.SYS)
CSI n ; m H	CUP	Cursor Position	Moves the cursor to row n , column m . The values are 1-based, and default to 1 (top left corner) if omitted. A sequence such as CSI $_{15\text{H}}$ is a synonym for CSI $_{15\text{H}}$ as well as CSI $_{17;\text{H}}$ is the same as CSI $_{17;\text{H}}$ and CSI $_{17;\text{H}}$
CSI n J	ED	Erase in Display	Clears part of the screen. If n is 0 (or missing), clear from cursor to end of screen. If n is 1, clear from cursor to beginning of the screen. If n is 2, clear entire screen (and moves cursor to upper left on DOS ANSI.SYS). If n is 3, clear entire screen and delete all lines saved in the scrollback buffer (this feature was added for x term and is supported by other terminal applications).
CSI n K	EL	Erase in Line	Erases part of the line. If <i>n</i> is 0 (or missing), clear from cursor to the end of the line. If <i>n</i> is 1, clear from cursor to beginning of the line. If <i>n</i> is 2, clear entire line. Cursor position does not change.
CSI n S	SU	Scroll Up	Scroll whole page up by n (default 1) lines. New lines are added at the bottom. (not ANSI.SYS)
CSI n T	SD	Scroll Down	Scroll whole page down by n (default 1) lines. New lines are added at the top. (not $\underline{ANSI.SYS}$)
CSI n; mf	HVP	Horizontal Vertical Position	Same as CUP, but counts as a format effector function (like <u>CR</u> or <u>LF</u>) rather than an editor function (like CUD or CNL). This can lead to different handling in certain terminal modes. [5]: Annex A
CSI n m	SGR	Select Graphic Rendition	Sets colors and style of the characters following this code
CSI 5i		AUX Port On	Enable aux serial port usually for local serial printer
CSI 4i		AUX Port Off	Disable aux serial port usually for local serial printer
CSI 6n	DSR	Device Status Report	Reports the cursor position (CPR) by transmitting $ESC[n;mR, where n]$ is the row and m is the column.

Some popular private sequences

Code	Abbr	Name	Effect
CSI s	SCP, SCOSC	Save Current Cursor Position	Saves the cursor position/state in SCO console mode. [31] In vertical split screen mode, instead used to set (as CSI n ; n s) or reset left and right margins. [32]
CSI u	RCP, SCORC	Restore Saved Cursor Position	Restores the cursor position/state in SCO console mode. [33]
CSI ? 25 h	DECTCEM		Shows the cursor, from the <u>VT220</u> .
CSI ? 25 l	DECTCEM		Hides the cursor.
CSI ? 1004 h			Enable reporting focus. Reports whenever terminal emulator enters or exits focus as ESC [I and ESC [0, respectively.
CSI ? 1004 l			Disable reporting focus.
CSI ? 1049 h			Enable alternative screen buffer, from xterm
CSI ? 1049 l			Disable alternative screen buffer, from xterm
CSI ? 2004 h			Turn on bracketed paste mode. [34] In bracketed paste mode, text pasted into the terminal will be surrounded by ESC [200~ and ESC [201~; programs running in the terminal should not treat characters bracketed by those sequences as commands (Vim, for example, does not treat them as commands). [35] From xterm [36]
CSI ? 2004 l			Turn off bracketed paste mode.

SGR (Select Graphic Rendition) parameters

The control sequence CSI n m, named Select Graphic Rendition (SGR), sets display attributes. Several attributes can be set in the same sequence, separated by semicolons. Each display attribute remains in effect until a following occurrence of SGR resets it. If no codes are given, CSI m is treated as CSI 0 m (reset / normal).

n	Name	Note
0	Reset <i>or</i> normal	All attributes become turned off
1	Bold or increased intensity	As with faint, the color change is a PC (SCO / CGA) invention. [38]
2	Faint, decreased intensity, <i>or</i> dim	May be implemented as a light font weight like bold. ^[39]
3	Italic	Not widely supported. Sometimes treated as inverse or blink. ^[38]
4	Underline	Style extensions exist for Kitty, VTE, mintty and iTerm2. [40][41]
5	Slow blink	Sets blinking to less than 150 times per minute
6	Rapid blink	MS-DOS ANSI.SYS, 150+ per minute; not widely supported
7	Reverse video <i>or</i> invert	Swap foreground and background colors; inconsistent emulation [42]
8	Conceal <i>or</i> hide	Not widely supported.
9	Crossed-out, <i>or</i> strike	Characters legible but marked as if for deletion. Not supported in Terminal.app
10	Primary (default) font	
11–19	Alternative font	Select alternative font $n-10$
20	Fraktur (Gothic)	Rarely supported
21	Doubly underlined; or: not bold	Double-underline per ECMA-48, [5]:8.3.117 but instead disables bold intensity on several terminals, including in the Linux kernel's console before version 4.17. [43]
22	Normal intensity	Neither bold nor faint; color changes where intensity is implemented as such.
23	Neither italic, nor blackletter	
24	Not underlined	Neither singly nor doubly underlined
25	Not blinking	Turn blinking off
26	Proportional spacing	ITU T.61 and T.416, not known to be used on terminals
27	Not reversed	
28	Reveal	Not concealed
29	Not crossed out	
30–37	Set foreground color	
38	Set foreground color	Next arguments are 5;n or 2;r;g;b
39	Default foreground color	Implementation defined (according to standard)
40-47	Set background color	
48	Set background color	Next arguments are 5;n or 2;r;g;b
49	Default background color	Implementation defined (according to standard)
50	Disable proportional spacing	T.61 and T.416
51	Framed	Lead on the deal lane ii ve vieti
52	Encircled	Implemented as "emoji variation selector" in mintty. [44]
53	Overlined	Not supported in Terminal.app
54	Neither framed nor encircled	
55	Not overlined	
58	Set underline <u>color</u>	Not in standard; implemented in Kitty, VTE, mintty, and iTerm2. $\frac{[40][41]}{Next}$ arguments are 5;n or 2;r;g;b.

59	Default underline color	Not in standard; implemented in Kitty, VTE, mintty, and iTerm2. [40][41]	
60	Ideogram underline or right side line		
61	Ideogram double underline, <i>or</i> double line on the right side		
62	Ideogram overline or left side line	Rarely supported	
63	Ideogram double overline, <i>or</i> double line on the left side		
64	Ideogram stress marking		
65	No ideogram attributes	Reset the effects of all of 60–64	
73	Superscript		
74	Subscript	Implemented only in mintty ^[44]	
75	Neither superscript nor subscript		
90–97	Set bright foreground color	Not in standard; originally implemented by aixterm ^[29]	
100-107	Set bright background color		

Colors

3-bit and 4-bit

The original specification only had 8 colors, and just gave them names. The SGR parameters 30–37 selected the foreground color, while 40–47 selected the background. Quite a few terminals implemented "bold" (SGR code 1) as a brighter color rather than a different font, thus providing 8 additional foreground colors. Usually you could not get these as background colors, though sometimes inverse video (SGR code 7) would allow that. Examples: to get black letters on white background use ESC[30;47m, to get red use ESC[31m, to get bright red use ESC[1;31m. To reset colors to their defaults, use ESC[39;49m (not supported on some terminals), or reset all attributes with ESC[0m. Later terminals added the ability to directly specify the "bright" colors with 90–97 and 100–107.

When hardware started using 8-bit <u>digital-to-analog converters</u> (DACs) several pieces of software assigned 24-bit color numbers to these names. The chart below shows the default values sent to the DAC for some common hardware and software; in most cases they are configurable.

FG	BG	Name	$\begin{array}{c c} \textbf{VGA}^{[b]} & & \frac{\textbf{Windows XP}}{\textbf{Console}^{[c]}} \end{array}$		Windows PowerShell 6 ^[d]	Visual Studio Code ^[e]	Windows 10 Console [f]	Terminal.ap
30	40	Black	0,0,0				12,12,12	0,0,0
31	41	Red	170,0,0	128,0,0		205, 49, 49	197,15,31	194,54,33
32	42	Green	0,170,0	0,128,0		13, 188, 121	19,161,14	37,188,36
33	43	Yellow	170,85,0 ^[h]	128,128,0	238,237,240	229, 229, 16	193,156,0	173,173,39
34	44	Blue	0,0,170	0,0,128		36, 114, 200	0,55,218	73,46,225
35	45	Magenta	170,0,170	128,0,128	1,36,86	188, 63, 188	136,23,152	211,56,211
36	46	Cyan	0,170,170	0,128,128		17, 168, 205	58,150,221	51,187,200
37	47	White	170,170,170	192,192,192		229, 229, 229	204,204,204	203,204,205
90	100	Bright Black (Gray)	85,85,85	128,128,128		102, 102, 102	118,118,118	129,131,131
91	101	Bright Red	255,85,85	255,0,0		241, 76, 76	231,72,86	252,57,31
92	102	Bright Green	85,255,85	0,255,0		35, 209, 139	22,198,12	49,231,34
93	103	Bright Yellow	255,255,85	255,255,0		245, 245, 67	249,241,165	234,236,35
94	104	Bright Blue	85,85,255	0,0,255	0,0,255		59,120,255	88,51,255
95	105	Bright Magenta	255,85,255	255,0,255		214, 112, 214	180,0,158	249,53,248
96	106	Bright Cyan	85,255,255	0,255,255		41, 184, 219	97,214,214	20,240,240
97	107	Bright White	255,255,255			229, 229, 229	242,242,242	233,235,235

8-bit

As $\underline{256\text{-color}}$ lookup tables became common on graphic cards, escape sequences were added to select from a pre-defined set \underline{of} 256 \underline{colors} :

```
ESC[38;5;(n)m Select foreground color where n is a number from the table below
ESC[48;5;(n)m Select background color
0- 7: standard colors (as in ESC [ 30-37 m)
8- 15: high intensity colors (as in ESC [ 90-97 m)
16-231: 6 × 6 × 6 cube (216 colors): 16 + 36 × r + 6 × g + b (0 ≤ r, g, b ≤ 5)
232-255: grayscale from dark to light in 24 steps
```

The <u>ITU</u>'s T.416 Information technology - Open Document Architecture (ODA) and interchange format: Character content architectures [48] uses ":" as separator characters instead:

```
ESC[38:5:(n)m Select foreground color where n is a number from the table below
ESC[48:5:(n)m Select background color
```

```
| Color | Colo
```

```
232 233 234 235 236 237 238 239 240 241 242 243 244 245 246 247 248 249 250 251 252 253 254 255
```

There has also been a similar but incompatible 88-color encoding using the same escape sequence, seen in rxvt and xterm-88color. Not much is known about the scheme besides the color codes. It uses a 4×4×4 color cube.

24-bit

As "true color" graphic cards with 16 to 24 bits of color became common, applications began to support 24-bit colors. Terminal emulators supporting setting 24-bit foreground and background colors with escape sequences include Xterm, [29] KDE's Konsole, [49][50] and iTerm, as well as all libvte based terminals, [51] including GNOME Terminal.

```
ESC[38;2;(r);(g);(b) m Select RGB foreground color
ESC[48;2;(r);(g);(b) m Select RGB background color
```

The syntax is likely based on the <u>ITU</u>'s T.416 <u>Open Document Architecture</u> (ODA) and interchange format: Character content architectures, which was adopted as ISO/IEC 8613-6 but ended up as a commercial failure. The ODA version is more elaborate and thus incompatible:

- The parameters after the '2' (r, g, and b) are optional and can be left empty.
- Semicolons are replaced by colons, as above.
- There is a leading "colorspace ID". [29] The definition of the colorspace ID is not included in that document so it may be blank to represent the unspecified default.
- In addition to the '2' value after 48 to specify a Red-Green-Blue format (and the '5' above for a 0-255 indexed color), there are alternatives of '0' for implementation-defined and '1' for transparent neither of which have any further parameters; '3' specifies colors using a Cyan-Magenta-Yellow scheme, and '4' for a Cyan-Magenta-Yellow-Black one, the latter using the position marked as "unused" for the Black component: [48]

```
ESC[38:2:(Color-Space-ID):(r):(g):(b):(unused):(CS tolerance):(Color-Space associated with tolerance: 0 for "CIELUV"; 1 for "CIELAB") m Select RGB foreground color
ESC[48:2:(Color-Space-ID):(r):(g):(b):(unused):(CS tolerance):(Color-Space associated with tolerance: 0 for "CIELUV"; 1 for "CIELAB") m Select RGB background color
```

The ITU-RGB variation is supported by xterm, with the colorspace ID and tolerance parameters ignored. The simpler scheme using semicolons is initially found in Konsole. [29]: Can I set a color by its number?

Unix environment variables relating to color support

Before termcap and terminfo could indicate support for colors, the S-Lang library used \$COLORTERM to indicate whether a terminal emulator could use colors at all (later reinterpreted as 256-colors)^[52] and whether it supports 24-bit color. This system, although poorly documented, became widespread enough for Fedora and RHEL to consider using it as a simpler and more universal detection mechanism compared to querying the now-updated libraries. However, gnometerminal 3.14 dropped this variable as its authors considered it incorrect and no longer necessary.

Some terminal emulators (urxvt, konsole) set COLORFGBG to report the color scheme of the terminal (mainly light vs. dark background). This behavior originated in S-Lang and is used by vim. Again, gnome-terminal refuses to add this behavior, as the more "proper" xterm OSC 4/10/11 sequences already exist. [56]

OSC (Operating System Command) sequences

Most Operating System Command sequences were defined by Xterm, but many are also supported by other terminal emulators. For historical reasons, Xterm can end the command with BEL as well as the standard ST. [29] For example, Xterm allows the window title to be set by ESC]0; this is the window title BEL.

A non-xterm extension is the hyperlink, ESC [8;; link ST from 2017, used by VTE, [57] iTerm2, [57] and mintty.

The Linux console uses ESC] P n rr gg bb to change the palette, which, if hard-coded into an application, may hang other terminals. [59] However, appending ST will be ignored by Linux and form a proper, ignorable sequence for other terminals.

Fs Escape sequences

If the ESC is followed by a byte in the range 0x60-0x7E, the escape sequence is of type Fs. This type is used for control functions individually registered with the <u>ISO-IR</u> registry [60] and, consequently, available even in contexts where a different C1 control code set is used. Specifically, they correspond to single control functions approved by <u>ISO/IEC JTC 1/SC 2</u> and standardized by ISO or an ISO-recognised body. [28]:6.5.1 Some of these are specified in ECMA-35 (ISO 2022 / ANSI X3.41), others in ECMA-48 (ISO 6429 / ANSI X3.64). [28]:6.5.4 ECMA-48 refers to these as "independent control functions". [5]:5.5

Some type Fs (independent function) ANSI escape sequences recognised by terminals (not an exhaustive list)

	Abbr	Name	Effect
ESC c	RIS	Reset to Initial State	Triggers a full reset of the terminal to its original state. This may include (if applicable): reset graphic rendition, clear tabulation stops, reset to default font, and more. $[61]$

Fp Escape sequences

If the ESC is followed by a byte in the range 0x30-0x3F, the escape sequence is of type Fp, which is set apart for up to sixteen private-use control functions. [28]:6.5.3

Some type Fp (private-use) escape sequences recognised by the VT100, its successors, and/or terminal emulators such as xterm

	Abbr	Name	Effect
ESC 7	DECSC	DEC Save Cursor	Saves the cursor position, encoding shift state and formatting attributes. [62][29]
ESC 8	DECRC	DEC Restore Cursor	Restores the cursor position, encoding shift state and formatting attributes from the previous DECSC if any, otherwise resets these all to their defaults. [62][29]

nF Escape sequences

If the ESC is followed by a byte in the range 0x20-0x2F, the escape sequence is of type nF. Said byte is followed by any number of additional bytes in this range, and then a byte in the range 0x30-0x7E. These escape sequences are further subcategorised by the low four bits of the first byte, e.g. "type 2F" for sequences where the first byte is 0x22; and by whether the final byte is in the range 0x30-0x3F indicating private use (e.g. "type 2Fp") or not (e.g. "type 2Ft"). [28]: 13.2.1

Escape sequences of this type are mostly used for ANSI/ISO code-switching mechanisms such as those used by ISO-2022-JP, except for type 3F sequences (those where the first intermediate byte is 0x23), which are used for individual control functions. Type 3Ft sequences are reserved for additional ISO-IR registered individual control functions, [28]:6.5.2 while type 3Fp sequences are available for private-use control functions. Unlike type Fs sequences, no type 3Ft sequences are presently registered. [60]

Some type 0Ft (announcement) ANSI escape sequences recognised by terminals

	Abbr	Name	Effect
ESC SP F	ACS6 S7C1T	Announce Code Structure 6 Send 7-bit C1 Control Character to the Host	Defined in ECMA-35 (ANSI X3.41 / ISO 2022). [28]:15.2 Makes the function keys send ESC + letter instead of 8-bit C1 codes. [29]
ESC SP G	ACS7 S8C1T	Announce Code Structure 7 Send 8-bit C1 Control Character to the Host	Defined in ECMA-35. [28]:15.2 Makes the function keys send 8-bit C1 codes. [29]

Some type 3Fp (private-use) escape sequences recognised by the VT100, its successors, and/or terminal emulators such as xterm

	Abbr	Name	Effect
ESC # 3	DECDHL	DEC Double-Height Letters, Top Half	Makes the current line use characters twice as tall. This code is for the top half. $\overline{^{[63]}}$
ESC # 4	DECDHL	DEC Double-Height Letters, Bottom Half	Makes the current line use characters twice as tall. This code is for the bottom half. $^{[63]}$
ESC # 5	DECSWL	DEC Single-Width Line	Makes the current line use single-width characters, per the default behaviour. ^{[64][29]}
ESC # 6	DECDWL	DEC Double-Width Line	Makes the current line use double-width characters, discarding any characters in the second half of the line. [65][29]

Examples

- CSI 2 J This clears the screen and, on some devices, locates the cursor to the y,x position 1,1 (upper left corner).
- CSI 32 m This makes text green. The green may be a dark, dull green, so you may wish to enable Bold with the sequence CSI 1 m which would make it bright green, or combined as CSI 32; 1 m. Some implementations use the Bold state to make the character Bright.
- CSI 0; 6 8; "DIR"; 13 p— This reassigns the key F10 to send to the keyboard buffer the string "DIR" and ENTER, which in the DOS command line would display the contents of the current directory. (MS-DOS ANSI.SYS only) This was sometimes used for ANSI bombs. This is a private-use code (as indicated by the letter p), using a non-standard extension to include a string-valued parameter. Following the letter of the standard would consider the sequence to end at the letter D.
- CSI s This saves the cursor position. Using the sequence CSI u will restore it to the position. Say the current cursor position is 7(y) and 10(x). The sequence CSI s will save those two numbers. Now you can move to a different cursor position, such as 20(y) and 3(x), using the sequence CSI 20; 3 H or CSI 20; 3 f. Now if you use the sequence CSI u the cursor position will return to 7(y) and 10(x). Some terminals require the DEC sequences ESC 7 / ESC 8 instead which is more widely supported.

In shell scripting

ANSI escape codes are often used in <u>UNIX</u> and <u>UNIX-like terminals</u> to provide <u>syntax highlighting</u>. For example, on compatible terminals, the following *list* command color-codes file and directory names by type.

```
ls --color
```

Users can employ escape codes in their scripts by including them as part of <u>standard output</u> or <u>standard error</u>. For example, the following GNU <u>sed</u> command embellishes the output of the <u>make</u> command by displaying lines containing words starting with "WARN" in <u>reverse video</u> and words starting with "ERR" in bright yellow on a dark red background (<u>letter</u> case is ignored). The representations of the codes are highlighted.

```
make 2>&1 | sed -e 's/.*\bWARN.*/\x1b[7m]&\x1b[0m/i' -e 's/.*\bERR.*/\x1b[93;41m]&\x1b[0m/i'
```

The following Bash function flashes the terminal (by alternately sending reverse and normal video mode codes) until the user presses a $\overline{\text{key.}}$ [67]

```
flasher () { while true; do printf (\e[?5h]; sleep 0.1; printf (\e[?5l]; read -s -n1 -t1 && break; done; }
```

This can be used to alert a programmer when a lengthy command terminates, such as with make ; flasher. [68]

```
printf \\033c
```

This will reset the console, similar to the command reset on modern Linux systems; however it should work even on older Linux systems and on other (non-Linux) UNIX variants.

In C

```
#include <stdio.h>
     int main(void)
 5
          int i, j, n;
         for (i = 0; i < 11; i++) {
              for (j = 0; j < 10; j++) {
    n = 10 * i + j;
 8
 9
10
                  if (n > 108) break;
                  printf("\033[%dm %3d\033[m", n, n);
11
12
              printf("\n");
13
14
15
          return 0;
16
```

```
12
10
     11
               13
                     14
                          15
                                16
                                          18
                                                19
20
          22
                23
                     24
                          25
                                26
                                          28
                                                29
                                          38
                                               39
                                          48
                                                49
               53
                     54
                          55
50
                                          58
                                                59
60
     61
          62
               63
                     64
                          65
                                66
                                     67
                                          68
                                                69
70
     71
          72
               73
                     74
                          75
                                76
                                     77
                                          78
                                                79
     81
          82
               83
                     84
                          85
                               86
                                     87
                                          88
                                               89
                     94
                          95
                                          98
                                               99
                                         108
```

Terminal input sequences

Pressing special keys on the keyboard, as well as outputting many xterm CSI, DCS, or OSC sequences, often produces a CSI, DCS, or OSC sequence, sent from the terminal to the computer as though the user typed it.

When typing input on a terminal keypresses outside the normal main alphanumeric keyboard area can be sent to the host as ANSI sequences. For keys that have an equivalent output function, such as the cursor keys, these often mirror the output sequences. However, for most keypresses there isn't an equivalent output sequence to use.

There are several encoding schemes, and unfortunately most terminals mix sequences from different schemes, so host software has to be able to deal with input sequences using any scheme. To complicate the matter, the VT terminals themselves have two schemes of input, *normal mode* and *application mode* that can be switched by the application.

(draft section)

If the terminating character is '~', the first number must be present and is a keycode number, the second number is an optional modifier value. If the terminating character is a letter, the letter is the keycode value, and the optional number is the modifier value.

The modifier value defaults to 1, and after subtracting 1 is a bitmap of modifier keys being pressed: $\underline{\text{Meta}} + \underline{\text{Ctrl}} + \underline{\text{Alt}} + \underline{\text{tr}} + \underline{\text{Shift}}$. So, for example, $\langle \text{esc} \rangle [4;2^{\sim} \text{ is } \underline{\text{tr}} + \underline{\text{End}}]$, $\langle \text{esc} \rangle [20^{\sim} \text{ is function key } \underline{\text{F9}}]$, $\langle \text{esc} \rangle [5C \text{ is } \underline{\text{Ctrl}} + \underline{\text{T}} - \underline{\text{T}}]$.

In other words, the modifier is the sum of the following numbers:

Key pressed	Number	Comment
	1	always added, the rest are optional
Shift	1	
(Left) Alt	2	
Control	4	
Meta	8	

```
vt sequences:
                                                        <esc>[31~
                                                                     - F17
             - Home
                            <esc>[16~
<esc>[1~
                                         - F6
<esc>[2~
             - Insert
                            <esc>[17~
                                                        <esc>[32~
                                                                     - F18
<esc>[3~
             - Delete
                            <esc>[18~
                                         - F7
                                                        <esc>[33~
                                                                     - F19
             - End
                            <esc>[19~
                                         - F8
                                                        <esc>[34~
                                                                     - F20
<esc>[4~
<esc>[5~
             - PgUp
                            <esc>[20~
                                                        <esc>[35~
<esc>[6~
                            <esc>[21~
                                         - F10
             - PgDn
<esc>[7~
             - Home
                            <esc>[22~
<esc>[8~
                                         - F11
             - End
                            <esc>[23~
<esc>[9~
                            <esc>[24~
                                         - F12
             - F0
<esc>[10~
                            <esc>[25~
                                         - F13
<esc>[11~
             - F1
                            <esc>[26~
                                         - F14
<esc>[12~
             - F2
                            <esc>[27~
<esc>[13~
             - F3
                            <esc>[28~
                                         - F15
             - F4
                            <esc>[29~
                                         - F16
<esc>[14~
                            <esc>[30~
<esc>[15~
xterm sequences:
                            <esc>[K
                                                        <esc>[U
<esc>[A
<esc>[B
                            <esc>[L
<esc>[C
             - Right
                            <esc>[M
                                                         <esc>[W
<esc>[D
             - Left
                            <esc>[N
                                                        <esc>[X
<esc>[E
                            <esc>[0
                                                        <esc>[Y
             - End
<esc>[F
                            <esc>[1P
                                                         <esc>[Z
<esc>[G
             - Keypad 5
                            <esc>[10]
                                         - F2
<esc>[H
             - Home
                            <esc>[1R
                                         - F3
                            <esc>[1S
<esc>[I
<esc>[J
                            <esc>[T
```

<esc>[A to <esc>[D are the same as the ANSI output sequences. The <modifier> is normally omitted if no modifier keys
are pressed, but most implementations always emit the <modifier> for F1—F4]. (draft section)

Xterm has a comprehensive documentation page on the various function-key and mouse input sequence schemes from DEC's VT terminals and various other terminals it emulates. Thomas Dickey has added a lot of support to it over time; he also maintains a list of default keys used by other terminal emulators for comparison.

- On the Linux console, certain function keys generate sequences of the form CSI [*char*. The CSI sequence should terminate on the [.
- Old versions of <u>Terminator</u> generate SS3 1; *modifiers char* when F1 F4 are pressed with modifiers. The faulty behavior was copied from GNOME Terminal.
- xterm replies CSI row; column R if asked for cursor position and CSI 1; modifiers R if the F3 key is pressed with modifiers, which collide in the case of row == 1. This can be avoided by using the ? private modifier as CSI ? 6 n, which will be reflected in the response as CSI ? row; column R.
- many terminals prepend ESC to any character that is typed with the alt key down. This creates ambiguity for uppercase letters and symbols @[\]^_, which would form C1 codes.
- Konsole generates SS3 *modifiers char* when F1 F4 are pressed with modifiers.

See also

- ANSI art
- Control character
- Advanced Video Attribute Terminal Assembler and Recreator (AVATAR)
- ISO/IEC JTC 1/SC 2

■ C0 and C1 control codes

Notes

- a. The screen display could be replaced by drawing the entire new screen's contents at the bottom, scrolling the previous screen up sufficiently to erase all the old text. The user would see the scrolling, and the hardware <u>cursor</u> would be left at the very bottom. Some early <u>batch files</u> achieved rudimentary "full screen" displays in this way.
- b. Typical colors that are used when booting PCs and leaving them in text mode, which used a 16-entry color table. The colors are different in the EGA/VGA graphic modes.
- c. Seen in Windows XP through Windows 8.1
- d. A buglet only exposed in PowerShell 6 which enabled ANSI escapes. PowerShell's default shortcut .lnk, unchanged for over a decade, remapped yellow and magenta to give PowerShell distinctive foreground/background colors compared to the command prompt. [45] PowerShell 7 comes with a new shortcut and doesn't suffer from this issue.
- e. Debug console, "Dark+" theme
- f. Campbell theme, used as of Windows 10 version 1709.
- g. For virtual terminals, from /etc/vtrgb.
- h. On terminals based on CGA compatible hardware, such as ANSI.SYS running on DOS, this normal intensity foreground color is rendered as Orange. CGA RGBI monitors contained hardware to modify the dark yellow color to an orange/brown color by reducing the green component. See this ansi art (http://sixteencolors.net/pack/ciapak26/DH-JNS11.CIA) Archived (https://web.archive.org/web/2011072501440 1/http://sixteencolors.net/pack/ciapak26/DH-JNS11.CIA) 25 July 2011 at the Wayback Machine as an example.

References

- 1. "Standard ECMA-48: Control Functions for Character-Imaging I/O Devices" (https://www.ecma-international.org/wp-content/uploads/ECMA-48_2nd_edition_august_1979.pdf) (PDF) (Second ed.). Ecma International. August 1979. Brief History.
- 2. Williams, Paul (2006). "Digital's Video Terminals" (https://vt100.net/dec/vt_history). VT100.net. Retrieved 17 August 2011.
- 3. Heathkit Company (1979). "Heathkit Catalog 1979" (https://web.archive.org/web/20120113230301/http://www.pestingers.net/Computer_history/Computers_79.htm). Heathkit Company. Archived from the original (http://www.pestingers.net/Computer_history/Computers_79.htm) on 13 January 2012. Retrieved 4 November 2011.
- 4. "Withdrawn FIPS Listed by Number" (https://www.nist.gov/system/files/documents/2016/12/15/withdrawn_fips_by_numerical_order_index.pdf) (PDF). *National Institute of Standards and Technology*. 15 December 2016. Retrieved 2 January 2022.
- 5. "Standard ECMA-48: Control Functions for Coded Character Sets" (https://www.ecma-international.org/wp-content/uploads/ECMA-48_5th_edition_june_1991.pdf) (PDF) (Fifth ed.). Ecma International. June 1991.
- 6. MITS (August 1975). "World's Most Inexpensive BASIC language system" (https://archive.org/details/197 508PopularElectronics). *Popular Electronics*. Vol. 8, no. 2. Ziff Davis. p. 1.
- 7. Hogan, Thom; Iannamico, Mike (1981). *Osborne 1 User's Guide* (https://archive.org/details/bitsavers_osborneosbeferenceGuide1981_27272857). Osborne Computer Corporation. p. 350.
- 8. *The Kaypro user's guide* (https://archive.org/details/manualzilla-id-5678221). Kaypro Corporation. 1984. p. 56.
- 9. System programmer's guide for the TRS-80 Model 4/4P using Montezuma Micro CP/M 2.2 (http://oldcomputers-ddns.org/public/pub/manuals/montezuma_system_programmers_guide_trs80m4.pdf) (PDF). Montezuma Micro. 1985. p. 11.
- 10. "CP/M 2.2 Manual". *Xerox 820 Information Processor* (https://archive.org/details/bitsavers_xerox8209RP rocessorCPM2.2ManualAug81 14944730). Xerox. 1981. p. 7.
- 11. Gilmour, Jean (1985). *The PCW8256 and PCW8512 User Guide* (https://archive.org/details/pcw-8256-851 2-user-manual-engacme). AMSOFT. pp. 56, 139.
- 12. "Appendix—ANSI escape sequences". *Z-89 Computer System Operation Manuals* (https://archive.org/details/z-89-full-main-manual). Zenith Data Systems. 1981. p. 112.

- 13. SoftCard (https://archive.org/details/Microsoft_SoftCard_Volume_1). Vol. 1. Microsoft. 1980. pp. 18, 31, 32, 42.
- 14. *Softcard—Software and hardware details* (http://www.applelogic.org/files/MSZ8MANUAL.pdf) (PDF). Microsoft. 1980. p. 15.
- 15. Mefford, Michael (7 February 1989). "ANSI.com: Download It Here" (https://web.archive.org/web/20101 014020602/https://www.pcmag.com/article2/0,2817,5343,00.asp). *PC Magazine*. Archived from the original (https://www.pcmag.com/article2/0,2817,5343,00.asp) on 14 October 2010. Retrieved 10 August 2011.
- 16. Kegel, Dan; Auer, Eric (28 February 1999). "Nansi and NNansi ANSI Drivers for MS-DOS" (http://www.kegel.com/nansi/). Dan Kegel's Web Hostel. Retrieved 10 August 2011.
- 17. "PTS-DOS 2000 Pro User Manual" (http://download.paragon-software.com/doc/manual_dos_eng.pdf) (PDF). Buggingen, Germany: Paragon Technology GmbH. 1999. Archived (https://web.archive.org/web/20180512094512/http://download.paragon-software.com/doc/manual_dos_eng.pdf) (PDF) from the original on 12 May 2018. Retrieved 12 May 2018.
- 18. Günther, Jens; Ernst, Tobias (25 April 2004) [1996]. Ellsässer, Wolfgang (ed.). "Inoffizielle deutschsprachige PTS-DOS-FAQ (PTS/FAQD)" (https://almnet.de/ptsdos/ptsfaqd.html#absIV1) [Inofficial German PTS-DOS FAQ] (in German). Retrieved 2 October 2018.
- 19. CCI Multiuser DOS 7.22 GOLD Online Documentation. Concurrent Controls, Inc. (CCI). 10 February 1997. HELP.HLP.
- 20. Hood, Jason (2005). "Process ANSI escape sequences for Windows console programs" (https://github.c om/adoxa/ansicon). Jason Hood's Home page. Retrieved 9 May 2013.
- 21. "colorama · PyPI" (https://pypi.python.org/pypi/colorama). *Python Package Index*. Retrieved 27 February 2022.
- 22. bitcrazed. "Console Virtual Terminal Sequences Windows Console" (https://docs.microsoft.com/en-us/windows/console/console-virtual-terminal-sequences). docs.microsoft.com. Retrieved 30 May 2018.
- 23. "PowerShell Help: About Special Characters" (https://docs.microsoft.com/en-us/powershell/module/microsoft.powershell.core/about/about_special_characters?view=powershell-6). 12 January 2023.
- 24. "Windows Console and Terminal Ecosystem Roadmap" (https://docs.microsoft.com/en-us/windows/console/ecosystem-roadmap#roadmap-for-the-future). Microsoft. 2018. Retrieved 13 March 2021. "this includes retiring the classic console host user interface from its default position in favor of Windows Terminal, ConPTY, and virtual terminal sequences."
- 25. "Printer and terminal escape codes" (http://www.bighole.nl/pub/mirror/homepage.ntlworld.com/kryte n_droid/Atari/ST/spg/st_prog_guide_c.htm). *Concise Atari ST 68000 Programming Guide*. Archived (htt ps://web.archive.org/web/20160920103258/http://www.bighole.nl/pub/mirror/homepage.ntlworld.com/kryten_droid/Atari/ST/spg/st_prog_guide_c.htm) from the original on 20 September 2016. Retrieved 22 June 2020.
- 26. "Amiga Printer Command Definitions" (http://wiki.amigaos.net/wiki/Printer_Device#Printer_Command _Definitions). Commodore. Retrieved 10 July 2013.
- 27. "Escape Sequence OpenVMS Wiki" (https://wiki.vmssoftware.com/Escape Sequence).
- 28. "Standard ECMA-35: Character Code Structure and Extension Techniques" (https://www.ecma-international.org/wp-content/uploads/ECMA-35_6th_edition_december_1994.pdf) (PDF) (Sixth ed.). Ecma International. 1994.
- 29. Moy, Edward; Gildea, Stephen; Dickey, Thomas (2019). "XTerm Control Sequences (ctlseqs)" (https://invisible-island.net/xterm/ctlseqs/ctlseqs.html). *Invisible Island*.
- 30. Frank da Cruz; Christine Gianone (1997). *Using C-Kermit* (https://books.google.com/books?id=QuYQPc-c67MC&pg=PA278). Digital Press. p. 278. ISBN 978-1-55558-164-0.
- 31. "SCOSC—Save Current Cursor Position" (https://vt100.net/docs/vt510-rm/SCOSC.html). VT510 Video Terminal Programmer Information. DEC.
- 32. "DECSLRM—Set Left and Right Margins" (https://vt100.net/docs/vt510-rm/DECSLRM.html). VT510 Video Terminal Programmer Information. DEC.
- 33. "SCORC—Restore Saved Cursor Position" (https://vt100.net/docs/vt510-rm/SCORC.html). VT510 Video Terminal Programmer Information. DEC.
- 34. Moy, Edward; Gildea, Stephen; Dickey, Thomas. "XTerm Control Sequences" (https://invisible-island.ne t/xterm/ctlseqs/ctlseqs.html#h3-Functions-using-CSI-_-ordered-by-the-final-character_s_). Functions using CSI, ordered by the final character(s). Retrieved 4 February 2022.
- 35. Conrad Irwin (April 2013). "bracketed paste mode" (https://cirw.in/blog/bracketed-paste). cirw.in.

- 36. Moy, Edward; Gildea, Stephen; Dickey, Thomas. "XTerm Control Sequences" (https://invisible-island.ne t/xterm/ctlseqs/ctlseqs.html#h2-Bracketed-Paste-Mode). Bracketed Paste Mode. Retrieved 4 February 2022.
- 37. "console_codes(4) Linux manual page" (http://man7.org/linux/man-pages/man4/console_codes.4.ht ml). *man7.org*. Retrieved 23 March 2018.
- 38. "screen(HW)" (http://osr507doc.sco.com/man/html.HW/screen.HW.html). SCO OpenServer Release 5.0.7 Manual. 11 February 2003.
- 39. "Bug 791596 Thoughts about faint (SGR 2)" (https://bugzilla.gnome.org/show_bug.cgi?id=791596). bugzilla.gnome.org.
- 40. "Curly and colored underlines (#6382) · Issues · George Nachman / iterm2" (https://gitlab.com/gnachman/iterm2/-/issues/6382). *GitLab*. 11 December 2017.
- 41. "Extensions to the xterm protocol" (https://sw.kovidgoyal.net/kitty/protocol-extensions.html#colored-a nd-styled-underlines). *kitty documentation*. Retrieved 1 July 2020.
- 42. "console-termio-realizer" (http://jdebp.uk/Softwares/nosh/guide/commands/console-termio-realizer.x ml). *jdebp.uk*.
- 43. "console_codes(4)" (https://man7.org/linux/man-pages/man4/console_codes.4.html). *Linux Programmer's Manual*. 5.10. Linux man-pages project.
- 44. "mintty/mintty: Text attributes and rendering" (https://github.com/mintty/mintty/wiki/Tips#text-attributes-and-rendering). *GitHub*.
- 45. "default shortcut on Windows remaps ANSI colors 35,36 · Issue #4266 · PowerShell/PowerShell" (https://github.com/PowerShell/PowerShell/issues/4266). *GitHub*. Retrieved 21 December 2022.
- 46. Changed from 0, 0, 205 in July 2004 "Patch #192 2004/7/12 XFree86 4.4.99.9" (http://invisible-island.net/xterm/xterm.log.html#xterm_192).
- 47. Changed from 0, 0, 255 in July 2004 "Patch #192 2004/7/12 XFree86 4.4.99.9" (http://invisible-island.net/xterm/xterm.log.html#xterm_192).
- 48. "T.416 Information technology Open Document Architecture (ODA) and interchange format: Character content architectures" (https://www.itu.int/rec/dologin_pub.asp?lang=e&id=T-REC-T.416-199303-I!!PDF-E&type=items).
- 49. "color-spaces.pl (a copy of 256colors2.pl from xterm dated 1999-07-11)" (https://quickgit.kde.org/?p=konsole.git&a=blob&f=tests%2Fcolor-spaces.pl). KDE. 6 December 2006.
- 50. "README.moreColors" (https://invent.kde.org/personalizedrefrigerator/konsole/-/blob/master/doc/user/README.moreColors). KDE. 22 April 2010.
- 51. "libvte's bug report and patches: Support for 16 million colors" (https://bugzilla.gnome.org/show_bug. cgi?id=704449). GNOME Bugzilla. 4 April 2014. Retrieved 5 June 2016.
- 52. "Bug #1429584" gnome-terminal doesn't set \$COLORTERM from 3.14 on...": Bugs: gnome-terminal package: Ubuntu" (https://bugs.launchpad.net/ubuntu/+source/gnome-terminal/+bug/1429584).

 Launchpad. "\$COLORTERM should not be necessary ever. [...] COLORTERM's semantics have nothing to do with 256 color support per se, it was a mere coincidence that all terminals that set this variable also supported 256 colors."
- 53. "Midnight Commander: lib/tty/color-slang.c" (https://fossies.org/linux/mc/lib/tty/color-slang.c). Fossies.
- 54. Dickey, Thomas E. (2017). "NCURSES comments on S-Lang" (https://invisible-island.net/ncurses/ncurses-slang.html). invisible-island.net.
- 55. "Features/256 Color Terminals Fedora Project Wiki" (https://fedoraproject.org/wiki/Features/256_Color_Terminals#Scope). Fedora Project. Archived (https://web.archive.org/web/20121004184942/https://fedoraproject.org/wiki/Features/256_Color_Terminals#Scope) from the original on 4 October 2012.
- 56. "Bug 733423 Please set COLORFGBG environment variable for automatic color detection" (https://bug zilla.gnome.org/show_bug.cgi?id=733423). bugzilla.gnome.org.
- 57. Koblinger, Egmont. "Hyperlinks (a.k.a. HTML-like anchors) in terminal emulators" (https://gist.github.com/egmontkob/eb114294efbcd5adb1944c9f3cb5feda). *GitHub Gists*.
- 58. "mintty/mintty: Control Sequences" (https://github.com/mintty/mintty/wiki/CtrlSeqs#hyperlinks). *GitHub*.
- 59. "console_codes Linux console escape and control sequences" (https://man7.org/linux/man-pages/man4/console_codes.4.html). Linux Programmer's Manual.
- 60. *ISO-IR: ISO/IEC International Register of Coded Character Sets To Be Used With Escape Sequences* (https://itscj.ipsj.or.jp/english/vbcqpr00000004qn-att/ISO-IR.pdf) (PDF). ITSCJ/IPSJ. Retrieved 12 May 2023.
- 61. ISO/TC 97/SC 2 (30 December 1976). *Reset to Initial State (RIS)* (https://itscj.ipsj.or.jp/ir/035.pdf) (PDF). ITSCJ/IPSJ. ISO-IR-35.

- 62. <u>Digital.</u> "DECSC—Save Cursor" (https://vt100.net/docs/vt510-rm/DECSC.html). *VT510 Video Terminal Programmer Information*.
- 63. ANSI Escape sequences VT100 / VT52 (https://web.archive.org/web/20090227051140/http://ascii-table.com/ansi-escape-sequences-vt-100.php), archived from the original (http://ascii-table.com/ansi-escape-sequences-vt-100.php) on 27 February 2009, retrieved 21 August 2020
- 64. Digital. "DECSWL—Single-Width, Single-Height Line" (https://vt100.net/docs/vt510-rm/DECSWL.html). VT510 Video Terminal Programmer Information.
- 65. Digital. "DECDWL—Double-Width, Single-Height Line" (https://vt100.net/docs/vt510-rm/DECDWL.html). VT510 Video Terminal Programmer Information.
- 66. "Chapter 9. System tips" (http://www.debian.org/doc/manuals/debian-reference/ch09.en.html#_colorized_shell_echo). debian.org.
- 67. "VT100.net: Digital VT100 User Guide" (http://vt100.net/docs/vt100-ug/chapter3.html). Retrieved 19 January 2015.
- 68. "bash How to get a notification when my commands are done Ask Different" (http://apple.stackexch ange.com/questions/9412/how-to-get-a-notification-when-my-commands-are-done). Retrieved 19 January 2015.
- 69. Dickey, Thomas. "XTerm FAQ: Comparing versions, by counting controls" (https://invisible-island.net/xterm/xterm.faq.html#compare_versions). *Invisible Island*. Retrieved 25 January 2020.
- 70. Dickey, Thomas (2016). "Table of function-keys for XTerm and other Terminal Emulators" (https://invisible-island.net/xterm/xterm-function-keys.html). *Invisible Island*. Retrieved 25 January 2020.

External links

- Standard ECMA-48, Control Functions For Coded Character Sets (https://www.ecma-international.org/publications-and-standards/standards/ecma-48/). (5th edition, June 1991), European Computer Manufacturers Association, Geneva 1991 (also published by ISO and IEC as standard ISO/IEC 6429)
- vt100.net DEC Documents (http://vt100.net/docs/)
- "ANSI.SYS -- ansi terminal emulation escape sequences" (https://web.archive.org/web/2006020602222
 9/http://enterprise.aacc.cc.md.us/~rhs/ansi.html). Archived from the original (http://enterprise.aacc.cc. md.us/~rhs/ansi.html) on 6 February 2006. Retrieved 22 February 2007.
- Xterm / Escape Sequences (http://invisible-island.net/xterm/ctlseqs/ctlseqs.html)
- AIXterm / Escape Sequences (https://www.ibm.com/support/knowledgecenter/en/ssw_aix_72/a_com mands/aixterm.html)
- A collection of escape sequences for terminals that are vaguely compliant with ECMA-48 and friends. (ht tp://bjh21.me.uk/all-escapes/all-escapes.txt)
- "ANSI Escape Sequences" (https://web.archive.org/web/20110525032501/http://ascii-table.com/ansi-escape-sequences.php). Archived from the original (http://ascii-table.com/ansi-escape-sequences.php) on 25 May 2011.
- ITU-T Rec. T.416 (03/93) Information technology Open Document Architecture (ODA) and interchange format: Character content architectures (https://www.itu.int/rec/dologin_pub.asp?lang=e&id=T-REC-T.4 16-199303-I!!PDF-E&type=items)

Retrieved from "https://en.wikipedia.org/w/index.php?title=ANSI_escape_code&oldid=1163568738"