EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · FRONT · SIDE 1 OF 2

Running the EOC (Emergency Operations Center) Message Center

Share this card

STARTING UP

1. **Double-click the EOC Server icon** on the Windows host laptop
   Window shows: `http://10.x.x.x:8080` — note this IP (Internet Protocol) address
2. **Share the URL (web address)** with the EOC operators on the Wi-Fi: any device, any browser. A green banner = networked.

RECEIVING MESSAGES

3. Open Winlink Express → check for new mail
   During an activation, set Telnet to check every 5 minutes.
4. **Watch the blue "AUTO-INGEST ACTIVE" bar** in the EOC
   Church forms appear on every screen within 10 seconds.
5. Once: **choose the Winlink callsign** that feeds the EOC
   Click the blue bar and type it (it lists the ones found). Auto-ingest off? Drag the .mime from C:\RMS Express\<callsign>\Messages onto the page.
6. **SITREP (situation report):** Disaster Reports tab → **Generate SITREP** (toolbar above the table) → **Copy** → send it up
   Satellite → Stake Center EOC. Stake → council line (Area Seventy) and welfare line: Welfare and Self-Reliance Manager (WSRM), then Area Welfare and Self-Reliance Manager (AWSRM).
7. **Stake EOC: forward the forms up the welfare line**
   Winlink Express: open the form message → Forward → the welfare line's Winlink address → Send. Every Disaster Report and Supply Order.

Every work item (Work Items tab): give it an owner now (HIGH items at once), move it (In work, Up, Done), and write the decision in.

Reports without Winlink. Phones: volunteers on the EOC Wi-Fi tap **Send to EOC** (the wall code). Other reports arrive as `.txt` files: save them into the **EOC Drop Folder** on the Desktop.

Paper by runner (Emergency): type it in at `http://<server-ip>:8080/forms/dr` (so, `wcl`) and tap **Send**.

Before the event: Python 3 from `python.org/downloads` (not the Microsoft Store placeholder) and Winlink Express · USB (Universal Serial Bus) thumb drives, one USB-C/Lightning for iPhones · **Comms Sheet** typed on the Setup tab; **Export sheet JSON** (JavaScript Object Notation file) to every EOC · blank paper forms (form address + `?blank=1`, **Print**).

Turn over → Card 3, side 2: Tabs, Status, Shift Handoff, Roll-up & SITREP

EOC OPERATOR — SATELLITE, STAKE CENTER OR COUNCIL / AREA EOC

CARD 3 · BACK · SIDE 2 OF 2

Tabs, Status, Shift Handoff, Roll-up & SITREP

TABS — WHAT GOES WHERE

Disaster Reports — per-address damage records
Supply Orders — requests + the welfare line's approval status
Work Crew Logs — crews, hours, homes completed
Roster — wards (stakes at a Council / Area EOC) and who has reported
Work Items — what the reports ask you to do or decide: owner, status, next action, decision
Messages — every record, **Via** = the EOC it came through · **Notes** — shift log

Status badges (click one to move it on; every screen updates): NEW just arrived, nobody has read it · ACK acknowledged: someone read it · ASSGN assigned: someone is acting on it · DONE handled.

Shift Handoff: Export Handoff JSON → USB drive → the incoming operator clicks Import Handoff JSON (it *replaces* the event's records: shift change only). **New emergency?** Setup tab → **Open a New Event** (the old event keeps its reports).

Roll-up to the EOC above you (Satellite → Stake → Council / Area EOC, if open): Setup tab: level, name and parent once → **Export Roll-up JSON** ("only new" ticked) with every SITREP, by the PACE (Primary, Alternate, Contingency, Emergency) level: **P/A** email to the parent's drop email · **C** Winlink attachment · **E** USB drive with the printed SITREP. The parent merges it by itself; nothing counts twice. **No Council / Area EOC open?** Items set Up go up only in the SITREP; phone or email the welfare line for anything urgent.

SITREP: first as soon as possible, then regular status reports on the interval leadership sets (Setup tab), to the Stake President, the council line (Area Seventy) and the welfare line (WSRM, AWSRM). Header: the **PACE level in force**; log each change with the time. Send by email at P/A, Winlink radio (VARA FM or VARA HF, the radio modem) at C, county EOC liaison or courier at E.

Wall display (TV): open `http://<server-ip>:8080/wall`, press **F**. **Drill:** press **I am ready** on the drill bar; new to drills: card 9. Your level: cards 6–8.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.

travislhilton.github.io/church-emcomm-wnlk-forms/forms/