CARD 6 · FRONT · SIDE 1 OF 2

Satellite EOC — Closer to the Damage, Reporting to the Stake Center

Share this card

WHEN AND WHERE

The stake specialist (Welfare and Self-Reliance Specialist, emergency communications) recommends, the **Stake President decides**: open one when a group of wards cannot reach the Stake Center in reasonable time (roads cut, the river between, the Stake Center damaged or dark). A ward building with power, a HAM (amateur radio) station and Wi-Fi.

It covers the wards or the part of the community the Stake President assigns to it. One stake can have several.

SETUP TAB, ONCE

Level **Satellite** · this EOC's name · the wards it covers · parent = the **Stake Center EOC** (name, drop email, Winlink address) · the SITREP (situation report) interval leadership set.

Comms sheet: your Winlink address and net frequency, so the stake sheet sends your wards to *you*.

WHAT COMES IN

Disaster Reports, Supply Orders and Work Crew Logs from your wards: phones on your Wi-Fi (the wall QR (Quick Response) code), Winlink auto-ingest, the Drop Folder (email, text, USB (Universal Serial Bus) drive).

Roster tab: which of your wards have reported, which are overdue, missionaries not accounted for.

WHAT GOES UP, WITH EVERY SITREP

The **SITREP** text to the Stake Center EOC (and anything the Stake President asked for by voice on the net).

Export Roll-up JSON (JavaScript Object Notation, a data file) to the Stake Center EOC by the path the PACE (Primary, Alternate, Contingency, Emergency) level allows (back of this card). The stake merges it; your wards then count in the stake's SITREP without re-keying.

Supply Orders are not approved here: they ride up in the roll-up and the welfare line answers through the Stake Center.

WORK ITEMS

Own what the satellite can do (a shelter check, a crew, a headcount). Anything for the Stake President or the welfare line: set it **Up**; it rides in the roll-up and arrives open at the Stake Center.

> **Card 3** is how to run the Message Center (start-up, auto-ingest, tabs, status, handoff). This card is what your level does and what it owes the level above.

Turn over → Card 6, side 2: The Chain, the Roll-up Path, Phones and Drills

SATELLITE EOC (EMERGENCY OPERATIONS CENTER) — CARD 6 OF THE EOC SET

CARD 6 · BACK · SIDE 2 OF 2

The Chain, the Roll-up Path, Phones and Drills

THE CHAIN AT A GLANCE

EOC	Reports from	SITREP to	Roll-up JSON to
Satellite ◀ you	its wards	Stake Center EOC	Stake Center EOC
Stake Center	wards + satellites	Stake President, council line, welfare line	Council / Area EOC, if open
Council / Area	stakes	Area Presidency / Church headquarters, as directed	—

SITREP = situation report. The council line is the Area Seventy; the welfare line is the Welfare and Self-Reliance Manager (WSRM), then the Area Welfare and Self-Reliance Manager (AWSRM). A Council / Area EOC exists only when the council or the welfare region opens one.

ROLL-UP: HOW THE FILE TRAVELS

Setup tab → **Export Roll-up JSON** ("only new since last roll-up" ticked) → send it with every SITREP.

P / A (cellular, any internet): attach it to an email to the parent EOC's drop email. **C** (radio): attach it to a Winlink message to the parent's Winlink address. First Winlink peer-to-peer (P2P) over VARA FM straight to a nearby parent station, then VARA FM through a gateway, then VARA HF (VARA: the sound-card radio modem Winlink uses). **E** (runner): on a USB drive with the printed SITREP.

At the parent nothing is clicked: the Drop Folder and Winlink watchers merge it within 10 seconds and log "Roll-up received from …". From USB: drop it in the Drop Folder. Nothing is counted twice.

> **Any device in the room, no app needed:** scan the wall QR code (or open `http://<server-ip>:8080/m`): new reports, **Send to EOC**, the **Work items** list (tap an item: **Take it**, In work, Up, Done; your name goes in its log). **Paper by runner (Emergency):** type it in at `/forms/dr`, `/forms/so` or `/forms/wcl` and tap **Send**; keep blank paper forms on hand (add `?blank=1`, **Print**).

> **In a drill:** one simulator per EOC. The purple **drill bar** on every screen says what this EOC plays, the clock or the start time, and who is ready: press **I am ready**. Every simulated report says SIMULATED; real reports still go through. New to drills? Read **card 9**.

Church of Jesus Christ EMCOMM (emergency communications) is an independent volunteer project created by Travis Hilton (W9TLH), not an official product of The Church of Jesus Christ of Latter-day Saints.